
MATLAB® 7

Function Reference: Volume 2 (F-O)





How to Contact The MathWorks



www.mathworks.com

comp.soft-sys.matlab

www.mathworks.com/contact TS.html Technical Support

Web

Newsgroup



suggest@mathworks.com bugs@mathworks.com

doc@mathworks.com

service@mathworks.com info@mathworks.com

Product enhancement suggestions

Bug reports

Documentation error reports

Order status, license renewals, passcodes Sales, pricing, and general information



508-647-7000 (Phone)



508-647-7001 (Fax)



The MathWorks, Inc. 3 Apple Hill Drive Natick, MA 01760-2098

For contact information about worldwide offices, see the MathWorks Web site.

MATLAB Function Reference

© COPYRIGHT 1984–2010 by The MathWorks, Inc.

The software described in this document is furnished under a license agreement. The software may be used or copied only under the terms of the license agreement. No part of this manual may be photocopied or reproduced in any form without prior written consent from The MathWorks, Inc.

FEDERAL ACQUISITION: This provision applies to all acquisitions of the Program and Documentation by, for, or through the federal government of the United States. By accepting delivery of the Program or Documentation, the government hereby agrees that this software or documentation qualifies as commercial computer software or commercial computer software documentation as such terms are used or defined in FAR 12.212, DFARS Part 227.72, and DFARS 252.227-7014. Accordingly, the terms and conditions of this Agreement and only those rights specified in this Agreement, shall pertain to and govern the use, modification, reproduction, release, performance, display, and disclosure of the Program and Documentation by the federal government (or other entity acquiring for or through the federal government) and shall supersede any conflicting contractual terms or conditions. If this License fails to meet the government's needs or is inconsistent in any respect with federal procurement law, the government agrees to return the Program and Documentation, unused, to The MathWorks, Inc.

Trademarks

MATLAB and Simulink are registered trademarks of The MathWorks, Inc. See www.mathworks.com/trademarks for a list of additional trademarks. Other product or brand names may be trademarks or registered trademarks of their respective holders.

Patents

The MathWorks products are protected by one or more U.S. patents. Please see www.mathworks.com/patents for more information.

Revision History

December 1996	First printing	For MATLAB 5.0 (Release 8)
June 1997	Online only	Revised for MATLAB 5.1 (Release 9)
October 1997	Online only	Revised for MATLAB 5.2 (Release 10)
January 1999	Online only	Revised for MATLAB 5.3 (Release 11)
June 1999	Second printing	For MATLAB 5.3 (Release 11)
June 2001	Online only	Revised for MATLAB 6.1 (Release 12.1)
July 2002	Online only	Revised for 6.5 (Release 13)
June 2004	Online only	Revised for 7.0 (Release 14)
September 2006	Online only	Revised for 7.3 (Release 2006b)
March 2007	Online only	Revised for 7.4 (Release 2007a)
September 2007	Online only	Revised for Version 7.5 (Release 2007b)
March 2008	Online only	Revised for Version 7.6 (Release 2008a)
October 2008	Online only	Revised for Version 7.7 (Release 2008b)
March 2009	Online only	Revised for Version 7.8 (Release 2009a)
September 2009	Online only	Revised for Version 7.9 (Release 2009b)
March 2010	Online only	Revised for Version 7.10 (Release 2010a)

Function Reference

•	ı
	ı

Desktop Tools and Development Environment
Startup and Shutdown
Command Window and History
Help for Using MATLAB
Workspace
Managing Files
Programming Tools
System
Sy 2002
Data Import and Export
File Name Construction
File Opening, Loading, and Saving
Memory Mapping
Low-Level File I/O
Text Files
XML Documents
Spreadsheets
Scientific Data
Audio and Video
8
Internet Exchange
Mathematics
Arrays and Matrices
Linear Algebra
Elementary Math
Polynomials
Interpolation and Computational Geometry
Cartesian Coordinate System Conversion
Nonlinear Numerical Methods
Specialized Math
Sparse Matrices
Math Constants
Data Analysis
Dala Analysis

Basic Operations	1-57
Descriptive Statistics	1-57
Filtering and Convolution	1-58
Interpolation and Regression	1-58
Fourier Transforms	1-59
Derivatives and Integrals	1-59
Time Series Objects	1-60
Time Series Collections	1-63
Time beries concentions	1-00
December 1 December 1	1.05
Programming and Data Types	1-65
Data Types	1-65
Data Type Conversion	1-74
Operators and Special Characters	1-76
Strings	1-78
Bit-Wise Operations	1-81
Logical Operations	1-82
Relational Operations	1-82
Set Operations	1-83
Date and Time Operations	1-83
Programming in MATLAB	1-84
rrogramming in MATLAD	1-04
01: +0: +10: +10	1.00
Object-Oriented Programming	1-92
Classes and Objects	1-92
Handle Classes	1-93
Events and Listeners	1-94
Meta-Classes	1-94
Graphics	1-96
Basic Plots and Graphs	1-96
Plotting Tools	1-97
Annotating Plots	1-97
Specialized Plotting	1-98
Bit-Mapped Images	1-101
••	
Printing	1-102
Handle Graphics	1-102
a D.W. L. P.	1 105
	1-107
Surface and Mesh Plots	1-107
View Control	1-109
Lighting	1-111
Transparency	1-111
Volume Visualization	1-111

GUI Development	1-1	13
Predefined Dialog Boxes	1-1	13
User Interface Deployment	1-1	14
User Interface Development	1-1	14
User Interface Objects	1-1	15
Objects from Callbacks	1-1	16
GUI Utilities	1-1	16
Program Execution	1-1	17
External Interfaces	1-1	18
External Interfaces		
	1-1	18
Shared Libraries	1-1 1-1	18 19
Shared Libraries	1-1 1-1 1-1	18 19 20
Shared Libraries Java .NET	1-1 1-1 1-1	18 19 20 21
Shared Libraries Java .NET .Component Object Model and ActiveX	1-1 1-1 1-1 1-1 1-1	18 19 20 21 23

Alphabetical List

2

Index

Function Reference

Desktop Tools and Development

Environment (p. 1-3)

Startup, Command Window, help, editing and debugging, tuning, other

general functions

Data Import and Export (p. 1-12)

General and low-level file I/O, plus specific file formats, like audio, spreadsheet, HDF, images

Mathematics (p. 1-28)

Arrays and matrices, linear algebra,

other areas of mathematics

Data Analysis (p. 1-57)

Basic data operations, descriptive statistics, covariance and correlation, filtering and convolution, numerical derivatives and integrals, Fourier transforms, time series analysis

Programming and Data Types (p. 1-65)

Function/expression evaluation, program control, function handles, object oriented programming, error handling, operators, data types,

dates and times, timers

Object-Oriented Programming

(p. 1-92)

Functions for working with classes

and objects

Graphics (p. 1-96)

Line plots, annotating graphs, specialized plots, images, printing,

Handle Graphics

3-D Visualization (p. 1-107)

Surface and mesh plots, view control, lighting and transparency, volume

visualization

GUI Development (p. 1-113) GUIDE, programming graphical

user interfaces

services, and serial port devices, and C and Fortran routines

Desktop Tools and Development Environment

Startup and Shutdown (p. 1-3) Startup and shutdown options,

preferences

Command Window and History Control Command Window and History, enter statements and run

functions

Help for Using MATLAB (p. 1-5) Command line help, online

documentation in the Help browser,

demos

Workspace (p. 1-6) Manage variables

Managing Files (p. 1-6) Work with files, MATLAB search

path, manage variables

Programming Tools (p. 1-8) Edit and debug MATLAB code,

improve performance, source control,

publish results

System (p. 1-10) Identify current computer, license,

product version, and more

Startup and Shutdown

exit Terminate MATLAB® program

(same as quit)

finish Termination M-file for MATLAB

program

matlab (UNIX) Start MATLAB program (UNIX®

platforms)

matlab (Windows) Start MATLAB program (Windows®

platforms)

matlabrc Startup M-file for MATLAB program

prefdir Folder containing preferences,

history, and layout files

preferences Open Preferences dialog box

quit Terminate MATLAB program

startup Startup file for user-defined options

userpath View or change user portion of

search path

Command Window and History

cle Clear Command Window

commandhistory Open Command History window, or

select it if already open

commandwindow Open Command Window, or select

it if already open

diary Save session to file

dos Execute DOS command and return

result

format Set display format for output

home Send the cursor home

matlabcolon (matlab:)

Run specified function via hyperlink

more Control paged output for Command

Window

perl Call Perl script using appropriate

operating system executable

system Execute operating system command

and return result

unix Execute UNIX command and return

result

Help for Using MATLAB

builddocsearchdb Build searchable documentation

database

demo Access product demos via Help

browser

doc Reference page in Help browser

docsearch Help browser search

echodemo Run scripted demo step-by-step in

Command Window

help Help for functions in Command

Window

helpbrowser Open Help browser to access online

documentation and demos

helpwin Provide access to help comments for

all functions

info Information about contacting The

MathWorks

lookfor Search for keyword in all help

entries

playshow Run M-file demo (deprecated; use

echodemo instead)

support Open MathWorks Technical Support

Web page

web Open Web site or file in Web or Help

browser

whatsnew Release Notes for MathWorksTM

products

Workspace

clear Remove items from workspace,

freeing up system memory

delete Remove files or graphics objects

openvar Open workspace variable in Variable

Editor or other graphical editing tool

pack Consolidate workspace memory

which Locate functions and files who, whos List variables in workspace

workspace Open Workspace browser to manage

workspace

Managing Files

Search Path (p. 1-6) View and change MATLAB search

path

File Operations (p. 1-7) View and change files and directories

Search Path

addpath Add folders to search path

genpath Generate path string

path View or change search path
path2rc Save current search path to

pathdef.m file

pathsep Search path separator for current

platform

pathtool Open Set Path dialog box to view

and change search path

restoredefaultpath Restore default search path

Remove folders from search path rmpath

Save current search path savepath

userpath View or change user portion of

search path

which Locate functions and files

File Operations

See also "Data Import and Export" on page 1-12 functions.

cdChange current folder

copyfile Copy file or folder

delete Remove files or graphics objects

dir Folder listing

fileattrib Set or get attributes of file or folder

filebrowser Open Current Folder browser, or

select it if already open

isdir Determine whether input is folder lookfor

Search for keyword in all help

entries

lsFolder contents

matlabroot Root folder

mkdir Make new folder movefile Move file or folder

Identify current folder pwd

recycle Set option to move deleted files to

recycle folder

rmdir Remove folder

tempdir Name of system's temporary folder toolboxdir Root folder for specified toolbox

type Display contents of file

visdiff Compare two text files, MAT-Files,

binary files, or folders

Programming Tools

Editing Files (p. 1-8) Edit files

Debugging Programs (p. 1-8) Debug MATLAB program files

MATLAB Program Performance Improve performance and find potential problems in MATLAB code

O O I I (1 O) T I C MARTINATO 11

Source Control (p. 1-9) Interface MATLAB with source

control system

Publishing (p. 1-9) Publish MATLAB code and results

Editing Files

edit Edit or create file

Debugging Programs

dbclear Clear breakpoints
dbcont Resume execution

dbdown Reverse workspace shift performed

by dbup, while in debug mode

dbquitQuit debug modedbstackFunction call stackdbstatusList all breakpoints

dbstep Execute one or more lines from

current breakpoint

dbstop Set breakpoints

dbtype List text file with line numbers

dbup Shift current workspace to

workspace of caller, while in

debug mode

MATLAB Program Performance

rehash Refresh function and file system

path caches

Source Control

checkin Check files into source control

system (UNIX platforms)

checkout Check files out of source control

system (UNIX platforms)

cmopts Name of source control system

customverctrl Allow custom source control system

(UNIX platforms)

undocheckout Undo previous checkout from source

control system (UNIX platforms)

verctrl Source control actions (Windows

platforms)

Publishing

grabcode MATLAB code from files published

to HTML

notebook Open M-book in Microsoft® Word

software (on Microsoft Windows

platforms)

publish Publish MATLAB file with code cells,

saving output to specified file type

snapnow Force snapshot of image for inclusion

in published document

System

Operating System Interface (p. 1-10) Exchange operating system

information and commands with

MATLAB

MATLAB Version and License

(p. 1-11)

Information about MATLAB version

and license

Operating System Interface

clipboard Copy and paste strings to and from

system clipboard

computer Information about computer on

which MATLAB software is running

dos Execute DOS command and return

result

getenv Environment variable

hostid Server host identification number

perl Call Perl script using appropriate

operating system executable

setenv Set environment variable

system Execute operating system command

and return result

unix Execute UNIX command and return

result

winqueryreg Item from Windows registry

MATLAB Version and License

ismac Determine if version is for Mac OS®

X platform

ispc Determine if version is for Windows

(PC) platform

isstudent Determine if version is Student

Version

isunix Determine if version is for UNIX

platform

javachk Generate error message based on

SunTM JavaTM feature support

license Return license number or perform

licensing task

prefdir Folder containing preferences,

history, and layout files

usejava Determine whether Sun Java feature

is supported in MATLAB software

ver Version information for MathWorks

products

verLessThan Compare toolbox version to specified

version string

version Version number for MATLAB and

libraries

Data Import and Export

File Name Construction (p. 1-12) Get path, directory, filename information; construct filenames File Opening, Loading, and Saving Open files; transfer data between (p. 1-13) files and MATLAB workspace Memory Mapping (p. 1-13) Access file data via memory map using MATLAB array indexing Low-Level File I/O (p. 1-14) Low-level operations that use a file identifier Text Files (p. 1-14) Delimited or formatted I/O to text Documents written in Extensible XML Documents (p. 1-15) Markup Language Excel and Lotus 1-2-3 files Spreadsheets (p. 1-15) CDF, FITS, HDF formats Scientific Data (p. 1-16) Read and write audio and video, Audio and Video (p. 1-24) record and play audio Images (p. 1-26) Graphics files Internet Exchange (p. 1-26) URL, FTP, zip, tar, and e-mail

To see a listing of file formats that are readable from MATLAB, go to file formats.

File Name Construction

filemarker	Character to separate file name and internal function name
fileparts	Parts of file name and path
filesep	File separator for current platform
fullfile	Build full file name from parts

tempdir Name of system's temporary folder tempname Unique name for temporary file

File Opening, Loading, and Saving

Read Data Acquisition ToolboxTM dagread

(.dag) file

importdata Load data from file

load Load data from MAT-file into

workspace

Open file in appropriate application open save Save workspace variables to file

uigetdir Open standard dialog box for

selecting directory

uigetfile Open standard dialog box for

retrieving files

uiimport Open Import Wizard to import data uiputfile

Open standard dialog box for saving

files

uisave Open standard dialog box for saving

workspace variables

Open file in appropriate application winopen

(Windows)

Memory Mapping

disp (memmapfile) Information about memmapfile

object

get (memmapfile) Memmapfile object properties memmapfile Construct memmapfile object

Low-Level File I/O

fclose Close one or all open files

feof Test for end-of-file

ferror Information about file I/O errors fgetl Read line from file, removing

newline characters

fgets Read line from file, keeping newline

characters

fopen Open file, or obtain information

about open files

fprintf Write data to text file

fread Read data from binary file

frewind Move file position indicator to

beginning of open file

fscanf Read data from a text file

fseek Move to specified position in file

ftell Position in open file

fwrite Write data to binary file

Text Files

csvread Read comma-separated value file
csvwrite Write comma-separated value file

dlmread Read ASCII-delimited file of numeric

data into matrix

dlmwrite Write matrix to ASCII-delimited file

fileread Read contents of file into string textread Read data from text file; write to

multiple outputs

textscan Read formatted data from text file

or string

type Display contents of file

XML Documents

xmlread Parse XML document and return

Document Object Model node

xmlwrite Serialize XML Document Object

Model node

xslt Transform XML document using

XSLT engine

Spreadsheets

Microsoft Excel (p. 1-15) Read and write Microsoft Excel

spreadsheet

Lotus 1-2-3 (p. 1-16) Read and write Lotus WK1

spreadsheet

Microsoft Excel

xlsfinfo Determine whether file contains a

Microsoft® Excel® spreadsheet

xlsread Read Microsoft Excel spreadsheet

file

xlswrite Write Microsoft Excel spreadsheet

file

Lotus 1-2-3

wk1finfo Determine whether file contains

1-2-3 WK1 worksheet

wk1read Read Lotus 1-2-3 WK1 spreadsheet

file into matrix

wk1write Write matrix to Lotus 1-2-3 WK1

spreadsheet file

Scientific Data

Common Data Format (p. 1-16) Work with CDF files

Network Common Data Form Work with netCDF files

(p. 1-22)

Flexible Image Transport System Work with FITS files

(p. 1-23)

Hierarchical Data Format (p. 1-24) Work with HDF files

Band-Interleaved Data (p. 1-24) Work with band-interleaved files

Common Data Format

High-level I/O Functions

cdfepoch Convert MATLAB formatted dates

to CDF formatted dates

cdfinfo Information about Common Data

Format (CDF) file

cdfread Read data from Common Data

Format (CDF) file

cdfwrite Write data to Common Data Format

(CDF) file

todatenum Convert CDF epoch object to

MATLAB datenum

Library Information

cdflib Summary of Common Data Format

(CDF) capabilities

cdflib.getConstantNames Names of Common Data Format

(CDF) library constants

cdflib.getConstantValue Numeric value corresponding to

Common Data Format (CDF) library

constant

cdflib.getLibraryCopyright Copyright notice of Common Data

Format (CDF) library

cdflib.getLibraryVersion Library version and release

information

cdflib.getValidate Library validation mode

cdflib.setValidate Specify library validation mode

File Operations

cdflib.close Common Data Format (CDF)

file

cdflib.create Create Common Data Format (CDF)

file

cdflib.delete Delete existing Common Data

Format (CDF) file

cdflib.getCacheSize Number of cache buffers used

cdflib.getChecksum Checksum mode

cdflib.getCompression Compression settings

cdflib.getCompressionCacheSize Number of compression cache buffers

cdflib.getCopyright Copyright notice in Common Data

Format (CDF) file

cdflib.getFormat Format of Common Data Format

(CDF) file

cdflib.getMajority Majority of variables

cdflib.getName Name of Common Data Format

(CDF) file

cdflib.getReadOnlyMode Read-only mode

cdflib.getStageCacheSize Number of cache buffers for staging

cdflib.getVersion Common Data Format (CDF) library

version and release information

cdflib.inquire Basic characteristics of Common

Data Format (CDF) file

cdflib.open Open existing Common Data Format

(CDF) file

cdflib.setCacheSize Specify number of dotCDF cache

buffers

cdflib.setChecksum Specify checksum mode

cdflib.setCompression Specify compression settings

cdflib.setCompressionCacheSize Specify number of compression cache

buffers

cdflib.setFormat Specify format of Common Data

Format (CDF) file

cdflib.setMajority Specify majority of variables

cdflib.setReadOnlyMode Specify read-only mode

cdflib.setStageCacheSize Specify number of staging cache

buffers for Common Data Format

(CDF) file

Variables

cdflib.closeVar Close specified variable from

multifile format Common Data

Format (CDF) file

cdflib.createVar Create new variable

cdflib.deleteVar Delete variable

cdflib.deleteVarRecords Delete range of records from variable

cdflib.getVarAllocRecords Number of records allocated for

variable

cdflib.getVarBlockingFactor Blocking factor for variable

cdflib.getVarCacheSize Number of multifile cache buffers

cdflib.getVarCompression Information about compression used

by variable

cdflib.getVarData Single value from record in variable

cdflib.getVarMaxAllocRecNum Maximum allocated record number

for variable

cdflib.getVarMaxWrittenRecNum Maximum written record number for

variable

cdflib.getVarName Variable name, given variable

number

cdflib.getVarNum Variable number, given variable

name

cdflib.getVarNumRecsWritten Number of records written to

variable

cdflib.getVarPadValue Pad value for variable

cdflib.getVarRecordData Entire record for variable

cdflib.getVarReservePercent Compression reserve percentage for

variable

 ${\tt cdflib.getVarSparseRecords} \qquad \qquad {\tt Information \ about \ how \ variable}$

handles sparse records

cdflib.hyperGetVarData Read hyperslab of data from variable cdflib.hyperPutVarData Write hyperslab of data to variable

cdflib.inquireVar Information about variable
cdflib.putVarData Write single value to variable
cdflib.putVarRecordData Write entire record to variable

cdflib.renameVar Rename existing variable

cdflib.setVarAllocBlockRecords Specify range of records to be

allocated for variable

cdflib.setVarBlockingFactor Specify blocking factor for variable

cdflib.setVarCacheSize Specify number of multi-file cache

buffers for variable

cdflib.setVarCompression Specify compression settings used

with variable

cdflib.setVarInitialRecs Specify initial number of records

written to variable

cdflib.setVarPadValue Specify pad value used with variable

cdflib.SetVarReservePercent Specify reserve percentage for

variable

cdflib.setVarsCacheSize Specify number of cache buffers used

for all variables

cdflib.setVarSparseRecords Specify how variable handles sparse

records

Attributes and Entries

 $\begin{array}{ll} {\it cdflib.createAttr} & {\it Create\ attribute} \\ {\it cdflib.deleteAttr} & {\it Delete\ attribute} \end{array}$

cdflib.deleteAttrEntry Delete attribute entry

cdflib.deleteAttrgEntry Delete entry in global attribute cdflib.getAttrEntry Value of entry in attribute with

variable scope

cdflib.getAttrgEntry Value of entry in global attribute cdflib.getAttrMaxEntry Number of last entry for variable

attribute

cdflib.getAttrMaxgEntry Number of last entry for global

attribute

cdflib.getAttrName Name of attribute, given attribute

number

cdflib.getAttrNum Attribute number, given attribute

name

cdflib.getAttrScope Scope of attribute

cdflib.getNumAttrEntries Number of entries for attribute with

variable scope

cdflib.getNumAttrgEntries Number of entries for attribute with

global scope

cdflib.getNumAttributes Number of attributes with variable

scope

scope

cdflib.inquireAttr Information about attribute

cdflib.inquireAttrEntry Information about entry in attribute

with variable scope

cdflib.inquireAttrgEntry Information about entry in attribute

with global scope

cdflib.putAttrEntry Write value to entry in attribute

with variable scope

cdflib.putAttrgEntry Write value to entry in attribute

with global scope

cdflib.renameAttr Rename existing attribute

Utilities

cdflib.computeEpoch Convert time value to CDF EPOCH

value

cdflib.computeEpoch16 Convert time value to CDF EPOCH16

value

cdflib.epoch16Breakdown Convert CDF EPOCH16 value to time

value

cdflib.epochBreakdown Convert CDF_EPOCH value into time

value

Network Common Data Form

File Operations

netcdf Summary of MATLAB Network

Common Data Form (netCDF)

capabilities

netcdf.abort Revert recent netCDF file definitions

netcdf.close Close netCDF file

netcdf.create Create new netCDF dataset
netcdf.endDef End netCDF file define mode

netcdf.getConstant Return numeric value of named

constant

netcdf.getConstantNames Return list of constants known to

netCDF library

netcdf.inq Return information about netCDF

file

netcdf.ingLibVers Return netCDF library version

information

netcdf.open Open netCDF file

netcdf.reDef Put open netCDF file into define

mode

netcdf.setDefaultFormat Change default netCDF file format

netcdf.setFill Set netCDF fill mode

netcdf.sync Synchronize netCDF file to disk

Dimensions

netcdf.defDim Create netCDF dimension

netcdf.ingDim Return netCDF dimension name and

length

netcdf.ingDimID Return dimension ID

netcdf.renameDim Change name of netCDF dimension

Variables

netcdf.defVar Create netCDF variable

netcdf.getVar Return data from netCDF variable
netcdf.inqVar Return information about variable
netcdf.inqVarID Return ID associated with variable

name

netcdf.putVar Write data to netCDF variable
netcdf.renameVar Change name of netCDF variable

Attributes

netcdf.copyAtt Copy attribute to new location

 $\begin{array}{ll} {\rm netcdf.delAtt} & {\rm Delete\;netCDF\;attribute} \\ {\rm netcdf.getAtt} & {\rm Return\;netCDF\;attribute} \end{array}$

netcdf.inqAtt Return information about netCDF

attribute

netcdf.inqAttID Return ID of netCDF attribute netcdf.inqAttName Return name of netCDF attribute

netcdf.putAtt Write netCDF attribute netcdf.renameAtt Change name of attribute

Flexible Image Transport System

fitsinfo Information about FITS file fitsread Read data from FITS file

Hierarchical Data Format

hdf Summary of MATLAB HDF4

capabilities

hdf5 Summary of MATLAB HDF5

capabilities

hdf5info Information about HDF5 file

hdf5read Read HDF5 file

hdf5write Write data to file in HDF5 format

hdfinfo Information about HDF4 or

HDF-EOS file

hdfread Read data from HDF4 or HDF-EOS

file

hdftool Browse and import data from HDF4

or HDF-EOS files

Band-Interleaved Data

multibandread Read band-interleaved data from

binary file

multibandwrite Write band-interleaved data to file

Audio and Video

Reading and Writing Files (p. 1-25) Input/output data to audio and video

file formats

Recording and Playback (p. 1-25) Record and listen to audio

Utilities (p. 1-26) Convert audio signal

Reading and Writing Files

aufinfo Information about NeXT/SUN (.au)

sound file

auread Read NeXT/SUN (.au) sound file
auwrite Write NeXT/SUN (.au) sound file
avifile Create new Audio/Video Interleaved

(AVI) file

aviinfo Information about Audio/Video

Interleaved (AVI) file

aviread Read Audio/Video Interleaved (AVI)

file

mmfileinfo Information about multimedia file
mmreader Create multimedia reader object for

reading video files

movie2avi Create Audio/Video Interleaved

(AVI) file from MATLAB movie

wavfinfo Information about WAVE (.wav)

sound file

wavread Read WAVE (.wav) sound file wavwrite Write WAVE (.wav) sound file

Recording and Playback

audiodevinfo Information about audio device
audioplayer Create object for playing audio
audiorecorder Create object for recording audio
sound Convert matrix of signal data to

sound

soundsc Scale data and play as sound

wavplay Play recorded sound on PC-based

audio output device

wavrecord Record sound using PC-based audio

input device

Utilities

beep Produce beep sound

lin2mu Convert linear audio signal to

mu-law

mu2lin Convert mu-law audio signal to

linear

Images

exifread Read EXIF information from JPEG

and TIFF image files

im2java Convert image to Java image
imfinfo Information about graphics file
imread Read image from graphics file
imwrite Write image to graphics file

Tiff MATLAB Gateway to LibTIFF

library routines

Internet Exchange

URL, Zip, Tar, E-Mail (p. 1-27) Send e-mail, read from given URL,

extract from tar or zip file, compress

and decompress files

FTP (p. 1-27) Connect to FTP server, download

from server, manage FTP files, close

server connection

URL, Zip, Tar, E-Mail

gunzip Uncompress GNU zip files

gzip Compress files into GNU zip files sendmail Send e-mail message to address list

tar Compress files into tar file untar Extract contents of tar file unzip Extract contents of zip file urlread

Download content at URL into

MATLAB string

urlwrite Download content at URL and save

to file

zip Compress files into zip file

FTP

ascii Set FTP transfer type to ASCII Set FTP transfer type to binary binary cd (ftp) Change current directory on FTP

server

Close connection to FTP server close (ftp) Remove file on FTP server delete (ftp)

dir (ftp) Directory contents on FTP server ftp

Connect to FTP server, creating FTP

object

mget Download file from FTP server

mkdir (ftp) Create new directory on FTP server mput Upload file or directory to FTP server

Rename file on FTP server rename

Remove directory on FTP server rmdir (ftp)

Mathematics

Arrays and Matrices (p. 1-29)	Basic array operators and operations, creation of elementary and specialized arrays and matrices
Linear Algebra (p. 1-34)	Matrix analysis, linear equations, eigenvalues, singular values, logarithms, exponentials, factorization
Elementary Math (p. 1-38)	Trigonometry, exponentials and logarithms, complex values, rounding, remainders, discrete math
Polynomials (p. 1-43)	Multiplication, division, evaluation, roots, derivatives, integration, eigenvalue problem, curve fitting, partial fraction expansion
Interpolation and Computational Geometry (p. 1-43)	Interpolation, Delaunay triangulation and tessellation, convex hulls, Voronoi diagrams, domain generation
Cartesian Coordinate System Conversion (p. 1-47)	Conversions between Cartesian and polar or spherical coordinates
Nonlinear Numerical Methods (p. 1-47)	Differential equations, optimization, integration
Specialized Math (p. 1-51)	Airy, Bessel, Jacobi, Legendre, beta, elliptic, error, exponential integral, gamma functions
Sparse Matrices (p. 1-52)	Elementary sparse matrices, operations, reordering algorithms, linear algebra, iterative methods, tree operations
Math Constants (p. 1-55)	Pi, imaginary unit, infinity, Not-a-Number, largest and smallest positive floating point numbers, floating point relative accuracy

Arrays and Matrices

Basic Information (p. 1-29) Display array contents, get array

information, determine array type

Operators (p. 1-30) Arithmetic operators

Elementary Matrices and Arrays Create elementary arrays of different (p. 1-31)

types, generate arrays for plotting,

array indexing, etc.

Array Operations (p. 1-32) Operate on array content, apply

function to each array element, find

cumulative product or sum, etc.

Array Manipulation (p. 1-33) Create, sort, rotate, permute,

reshape, and shift array contents

Specialized Matrices (p. 1-34) Create Hadamard, Companion,

Hankel, Vandermonde, Pascal

matrices, etc.

Basic Information

disp Display text or array

display Display text or array (overloaded

method)

Determine whether array is empty isempty

isequal Test arrays for equality

Test arrays for equality, treating isequalwithequalnans

NaNs as equal

isfinite Array elements that are finite

isfloat Determine whether input is

floating-point array

isinf Array elements that are infinite

Determine whether input is integer isinteger

array

. 1 . 1	Th. 1.1 1 .	1
islogical	Determine whether input is logic	വ
151021041	Determine whether input is logic	α

array

isnan Array elements that are NaN

isnumeric Determine whether input is numeric

array

isscalar Determine whether input is scalar issparse Determine whether input is sparse isvector Determine whether input is vector length Length of vector or largest array

dimension

max Largest elements in array
min Smallest elements in array
ndims Number of array dimensions
numel Number of elements in array or

subscripted array expression

size Array dimensions

Operators

- + Addition
- + Unary plus
- Subtraction
- Unary minus
- * Matrix multiplication
- ^ Matrix power
- \ Backslash or left matrix divide
- / Slash or right matrix divide
- ' Transpose
- .' Nonconjugated transpose

- .* Array multiplication (element-wise)
- .^ Array power (element-wise)
- .\ Left array divide (element-wise)
- ./ Right array divide (element-wise)

Elementary Matrices and Arrays

blkdiag Construct block diagonal matrix

from input arguments

diag Diagonal matrices and diagonals of

matrix

eye Identity matrix

freqspace Frequency spacing for frequency

response

ind2sub Subscripts from linear index

linspace Generate linearly spaced vectors logspace Generate logarithmically spaced

vectors

meshgrid Generate X and Y arrays for 3-D plots

ndgrid Generate arrays for N-D functions

and interpolation

ones Create array of all ones rand Uniformly distributed

pseudorandom numbers

randi Uniformly distributed

pseudorandom integers

randn Normally distributed pseudorandom

numbers

RandStream Random number stream

sub2ind Convert subscripts to linear indices

zeros Create array of all zeros

Array Operations

See "Linear Algebra" on page 1-34 and "Elementary Math" on page 1-38 for other array operations.

accumarray Construct array with accumulation

arrayfun Apply function to each element of

array

bsxfun Apply element-by-element binary

operation to two arrays with singleton expansion enabled

cast Variable to different data type

cross Vector cross product
cumprod Cumulative product
cumsum Cumulative sum

dot Vector dot product

idivide Integer division with rounding

option

kron Kronecker tensor product
prod Product of array elements
sum Sum of array elements

tril Lower triangular part of matrix triu Upper triangular part of matrix

Array Manipulation

blkdiag Construct block diagonal matrix

from input arguments

cat Concatenate arrays along specified

dimension

circshift Shift array circularly

diag Diagonal matrices and diagonals of

matrix

end Terminate block of code, or indicate

last array index

flipdim Flip array along specified dimension

fliplr Flip matrix left to right flipud Flip matrix up to down

horzcat Concatenate arrays horizontally

inline Construct inline object

ipermute Inverse permute dimensions of N-D

array

permute Rearrange dimensions of N-D array

repmat Replicate and tile array

reshape Reshape array

rot90 Rotate matrix 90 degrees

shiftdim Shift dimensions

sort Sort array elements in ascending or

descending order

sortrows Sort rows in ascending order squeeze Remove singleton dimensions

vectorize Vectorize expression

vertcat Concatenate arrays vertically

Specialized Matrices

compan Companion matrix

gallery Test matrices

hadamard Hadamard matrix
hankel Hankel matrix
hilb Hilbert matrix

invhilb Inverse of Hilbert matrix

magic Magic square pascal Pascal matrix

rosser Classic symmetric eigenvalue test

problem

toeplitz Toeplitz matrix

vander Vandermonde matrix

wilkinson's eigenvalue test matrix

Linear Algebra

Matrix Analysis (p. 1-35) Compute norm, rank, determinant,

condition number, etc.

Linear Equations (p. 1-35) Solve linear systems, least

squares, LU factorization, Cholesky

factorization, etc.

Eigenvalues and Singular Values

(p. 1-36)

Eigenvalues, eigenvectors, Schur decomposition, Hessenburg

matrices, etc.

Matrix Logarithms and Exponentials

(p. 1-37)

Matrix logarithms, exponentials,

square root

Factorization (p. 1-37) Cholesky, LU, and QR factorizations,

diagonal forms, singular value

decomposition

Matrix Analysis

cond Condition number with respect to

inversion

condeig Condition number with respect to

eigenvalues

det Matrix determinant

norm Vector and matrix norms

normest 2-norm estimate

null Null space

orth Range space of matrix

rank Rank of matrix

rcond Matrix reciprocal condition number

estimate

rref Reduced row echelon form subspace Angle between two subspaces

trace Sum of diagonal elements

Linear Equations

chol Cholesky factorization

cholinc Sparse incomplete Cholesky and

Cholesky-Infinity factorizations

cond Condition number with respect to

inversion

condest 1-norm condition number estimate

funm Evaluate general matrix function

funm Evaluate general matrix function ilu Sparse incomplete LU factorization

inv Matrix inverse

ldl Block LDL' factorization for

Hermitian indefinite matrices

linsolve Solve linear system of equations

lscov Least-squares solution in presence

of known covariance

lsqnonneg Solve nonnegative least-squares

constraints problem

lu LU matrix factorization

luinc Sparse incomplete LU factorization

pinv Moore-Penrose pseudoinverse of

matrix

qr Orthogonal-triangular

decomposition

rcond Matrix reciprocal condition number

estimate

Eigenvalues and Singular Values

balance Diagonal scaling to improve

eigenvalue accuracy

cdf2rdf Convert complex diagonal form to

real block diagonal form

condeig Condition number with respect to

eigenvalues

eig Eigenvalues and eigenvectors

eigs Largest eigenvalues and

eigenvectors of matrix

gsvd Generalized singular value

decomposition

hess Hessenberg form of matrix

ordeig Eigenvalues of quasitriangular

matrices

ordqz Reorder eigenvalues in QZ

factorization

ordschur Reorder eigenvalues in Schur

factorization

poly Polynomial with specified roots polyeig Polynomial eigenvalue problem

rsf2csf Convert real Schur form to complex

Schur form

schur Schur decomposition sqrtm Matrix square root

ss2tf Convert state-space filter

parameters to transfer function

form

svd Singular value decomposition svds Find singular values and vectors

Matrix Logarithms and Exponentials

expm Matrix exponential logm Matrix logarithm sqrtm Matrix square root

Factorization

balance Diagonal scaling to improve

eigenvalue accuracy

cdf2rdf Convert complex diagonal form to

real block diagonal form

chol Cholesky factorization

cholinc Sparse incomplete Cholesky and

Cholesky-Infinity factorizations

cholupdate Rank 1 update to Cholesky

factorization

gsvd Generalized singular value

decomposition

ilu Sparse incomplete LU factorization

ldl Block LDL' factorization for

Hermitian indefinite matrices

lu LU matrix factorization

luinc Sparse incomplete LU factorization

planerot Givens plane rotation
qr Orthogonal-triangular

decomposition

qrdelete Remove column or row from QR

factorization

qrinsert Insert column or row into QR

factorization

qrupdate

qz QZ factorization for generalized

eigenvalues

rsf2csf Convert real Schur form to complex

Schur form

svd Singular value decomposition

Elementary Math

Trigonometric (p. 1-39) Trigonometric functions with results

in radians or degrees

Exponential (p. 1-40) Exponential, logarithm, power, and

root functions

Complex (p. 1-41) Numbers with real and imaginary

components, phase angles

Rounding and Remainder (p. 1-42)

Discrete Math (p. 1-42)

Rounding, modulus, and remainder

Prime factors, factorials,

permutations, rational fractions, least common multiple, greatest

common divisor

Trigonometric

acos Inverse cosine; result in radians

acosd Inverse cosine; result in degrees

acosh Inverse hyperbolic cosine

acot Inverse cotangent; result in radians acotd Inverse cotangent; result in degrees

acoth Inverse hyperbolic cotangent

acsc Inverse cosecant; result in radians acscd Inverse cosecant; result in degrees

acsch Inverse hyperbolic cosecant

asec Inverse secant; result in radians asecd Inverse secant; result in degrees

asech Inverse hyperbolic secant

asin Inverse sine; result in radians asind Inverse sine; result in degrees

asinh Inverse hyperbolic sine

atan Inverse tangent; result in radians atan2 Four-quadrant inverse tangent atand Inverse tangent; result in degrees

atanh Inverse hyperbolic tangent
cos Cosine of argument in radians
cosd Cosine of argument in degrees

Hyperbolic cosine cosh

cot Cotangent of argument in radians cotd Cotangent of argument in degrees

coth Hyperbolic cotangent

Cosecant of argument in radians csc cscd Cosecant of argument in degrees

Hyperbolic cosecant csch

hypot Square root of sum of squares sec Secant of argument in radians secd Secant of argument in degrees

sech Hyperbolic secant

sin Sine of argument in radians sind Sine of argument in degrees sinh

Hyperbolic sine of argument in

radians

tan Tangent of argument in radians tand Tangent of argument in degrees

tanh Hyperbolic tangent

Exponential

exp Exponential

expm1 Compute exp(x)-1 accurately for

small values of x

Natural logarithm log

log10 Common (base 10) logarithm

Compute log(1+x) accurately for log1p

small values of x

log2 Base 2 logarithm and dissect

floating-point numbers into exponent and mantissa

nextpow2 Next higher power of 2

nthroot Real nth root of real numbers

pow2 Base 2 power and scale floating-point

numbers

reallog Natural logarithm for nonnegative

real arrays

realpow Array power for real-only output

realsqrt Square root for nonnegative real

arrays

sqrt Square root

Complex

abs Absolute value and complex

magnitude

angle Phase angle

complex Construct complex data from real

and imaginary components

conj Complex conjugate

cplxpair Sort complex numbers into complex

conjugate pairs

i Imaginary unit

imag Imaginary part of complex number

isreal Check if input is real array

j Imaginary unit

real Real part of complex number

sign Signum function

unwrap Correct phase angles to produce

smoother phase plots

Rounding and Remainder

ceil Round toward positive infinity

fix Round toward zero

floor Round toward negative infinity idivide Integer division with rounding

option

mod Modulus after division
rem Remainder after division
round Round to nearest integer

Discrete Math

factor Prime factors

factorial Factorial function

gcd Greatest common divisor

isprime Array elements that are prime

numbers

lcm Least common multiple

nchoosek Binomial coefficient or all

combinations

perms All possible permutations

primes Generate list of prime numbers rat, rats Rational fraction approximation

Polynomials

conv Convolution and polynomial

multiplication

deconv Deconvolution and polynomial

division

poly Polynomial with specified roots

polyder Polynomial derivative

polyeig Polynomial eigenvalue problem

polyfit Polynomial curve fitting

polyint Integrate polynomial analytically

polyval Polynomial evaluation

polyvalm Matrix polynomial evaluation

residue Convert between partial fraction

expansion and polynomial

coefficients

roots Polynomial roots

Interpolation and Computational Geometry

Interpolation (p. 1-44) Data interpolation, data gridding,

polynomial evaluation, nearest point

search

Delaunay Triangulation and Delaunay triangulation and

Tessellation (p. 1-45) tessellation, triangular surface and

mesh plots

Convex Hull (p. 1-46) Plot convex hull, plotting functions

Voronoi Diagrams (p. 1-46) Plot Voronoi diagram, patch graphics

object, plotting functions

Domain Generation (p. 1-47) Generate arrays for 3-D plots, or for

N-D functions and interpolation

Interpolation

dsearch Search Delaunay triangulation for

nearest point

dsearchn N-D nearest point search

griddata Data gridding

griddata3 Data gridding and hypersurface

fitting for 3-D data

griddatan Data gridding and hypersurface

fitting (dimension ≥ 2)

interp1 1-D data interpolation (table lookup)

interp1q Quick 1-D linear interpolation

interp2 2-D data interpolation (table lookup)
interp3 3-D data interpolation (table lookup)
interpft 1-D interpolation using FFT method
interpn N-D data interpolation (table lookup)
meshgrid Generate X and Y arrays for 3-D plots

mkpp Make piecewise polynomial

ndgrid Generate arrays for N-D functions

and interpolation

padecoef Padé approximation of time delays

pchip Piecewise Cubic Hermite

Interpolating Polynomial (PCHIP)

ppval Evaluate piecewise polynomial spline Cubic spline data interpolation

TriScatteredInterp Interpolate scattered data
TriScatteredInterp Interpolate scattered data

tsearch Search for enclosing Delaunay

triangle

tsearchn N-D closest simplex search unmkpp Piecewise polynomial details

Delaunay Triangulation and Tessellation

baryToCart (TriRep) Converts point coordinates from

barycentric to Cartesian

cartToBary (TriRep) Convert point coordinates from

cartesian to barycentric

circumcenters (TriRep) Circumcenters of specified simplices

delaunay Delaunay triangulation
delaunay3 3-D Delaunay tessellation
delaunayn N-D Delaunay tessellation

DelaunayTri Contruct Delaunay triangulation
DelaunayTri Delaunay triangulation in 2-D and

3-D

edgeAttachments (TriRep) Simplices attached to specified edges

edges (TriRep) Triangulation edges

faceNormals (TriRep)

Unit normals to specified triangles
featureEdges (TriRep)

Sharp edges of surface triangulation

freeBoundary (TriRep) Facets referenced by only one

simplex

incenters (TriRep) Incenters of specified simplices

inOutStatus (DelaunayTri)

Status of triangles in 2-D constrained

Delaunay triangulation

isEdge (TriRep) Test if vertices are joined by edge nearestNeighbor (DelaunayTri) Point closest to specified location

neighbors (TriRep) Simplex neighbor information

pointLocation (DelaunayTri) Simplex containing specified location

size (TriRep) Size of triangulation matrix

tetramesh Tetrahedron mesh plot
trimesh Triangular mesh plot
triplot 2-D triangular plot

TriRep Triangulation representation
TriRep Triangulation representation

trisurf Triangular surface plot

vertexAttachments (TriRep) Return simplices attached to

specified vertices

Convex Hull

convexHull (DelaunayTri)

convhull

Convex hull

Convex hull

N-D convex hull

patch Create one or more filled polygons

trisurf Triangular surface plot

Voronoi Diagrams

patch Create one or more filled polygons

voronoi Voronoi diagram voronoiDiagram (DelaunayTri) Voronoi diagram

voronoin N-D Voronoi diagram

Domain Generation

meshgrid Generate X and Y arrays for 3-D plots ndgrid Generate arrays for N-D functions

and interpolation

Cartesian Coordinate System Conversion

cart2pol Transform Cartesian coordinates to

polar or cylindrical

cart2sph Transform Cartesian coordinates to

spherical

pol2cart Transform polar or cylindrical

coordinates to Cartesian

sph2cart Transform spherical coordinates to

Cartesian

Nonlinear Numerical Methods

Ordinary Differential Equations Solve stiff and nonstiff differential equations, define the problem, set

solver options, evaluate solution

Delay Differential Equations (p. 1-49)

Solve delay differential equations with constant and general delays, set solver options, evaluate solution

Boundary Value Problems (p. 1-49)

Solve boundary value problems for ordinary differential equations, set solver options, evaluate solution

Partial Differential Equations

(p. 1-50)

Solve initial-boundary value problems for parabolic-elliptic PDEs,

evaluate solution

Optimization (p. 1-50) Find minimum of single and

multivariable functions, solve

nonnegative least-squares constraint

problem

Numerical Integration (Quadrature)

(p. 1-50)

Evaluate Simpson, Lobatto, and vectorized quadratures, evaluate

double and triple integrals

Ordinary Differential Equations

decic Compute consistent initial conditions

for ode15i

deval Evaluate solution of differential

equation problem

ode15i Solve fully implicit differential

equations, variable order method

ode23, ode45, ode113, ode15s,

ode23s, ode23t, ode23tb

Solve initial value problems for ordinary differential equations

odefile Define differential equation problem

for ordinary differential equation

solvers

odeget Ordinary differential equation

options parameters

odeset Create or alter options structure

for ordinary differential equation

solvers

odextend Extend solution of initial value

problem for ordinary differential

equation

Delay Differential Equations

dde23 Solve delay differential equations

(DDEs) with constant delays

ddeget Extract properties from delay

differential equations options

structure

ddesd Solve delay differential equations

(DDEs) with general delays

ddeset Create or alter delay differential

equations options structure

deval Evaluate solution of differential

equation problem

Boundary Value Problems

bvp4c Solve boundary value problems for

ordinary differential equations

bvp5c Solve boundary value problems for

ordinary differential equations

bypget Extract properties from options

structure created with bypset

bypinit Form initial guess for byp4c

bypset Create or alter options structure of

boundary value problem

bypxtend Form guess structure for extending

boundary value solutions

deval Evaluate solution of differential

equation problem

Partial Differential Equations

pdepe Solve initial-boundary value

problems for parabolic-elliptic PDEs

in 1-D

pdeval Evaluate numerical solution of PDE

using output of pdepe

Optimization

fminbnd Find minimum of single-variable

function on fixed interval

fminsearch Find minimum of unconstrained

multivariable function using

derivative-free method

fzero Find root of continuous function of

one variable

lsqnonneg Solve nonnegative least-squares

constraints problem

optimget Optimization options values

optimset Create or edit optimization options

structure

Numerical Integration (Quadrature)

dblquad Numerically evaluate double

integral over rectangle

quad Numerically evaluate integral,

adaptive Simpson quadrature

guad2d Numerically evaluate double

integral over planar region

quadgk Numerically evaluate integral,

adaptive Gauss-Kronrod quadrature

quadl Numerically evaluate integral,

adaptive Lobatto quadrature

quadv Vectorized quadrature

triplequad Numerically evaluate triple integral

Specialized Math

airy Airy functions

besselh Bessel function of third kind (Hankel

function)

besseli Modified Bessel function of first kind

besselj Bessel function of first kind

besselk Modified Bessel function of second

kind

bessely Bessel function of second kind

beta Beta function

betainc Incomplete beta function

betainciny Beta inverse cumulative distribution

function

betaln Logarithm of beta function ellipj Jacobi elliptic functions

ellipke Complete elliptic integrals of first

and second kind

erf, erfc, erfcx, erfinv, erfcinv Error functions

expint Exponential integral

gamma, gammainc, gammaln Gamma functions

gammaincinv Inverse incomplete gamma function

legendre Associated Legendre functions

psi Psi (polygamma) function

Sparse Matrices

Elementary Sparse Matrices Create random and nonrandom

(p. 1-52) sparse matrices

Full to Sparse Conversion (p. 1-53) Convert full matrix to sparse, sparse

matrix to full

Sparse Matrix Manipulation (p. 1-53) Test matrix for sparseness, get

information on sparse matrix, allocate sparse matrix, apply function to nonzero elements, visualize sparsity pattern

Reordering Algorithms (p. 1-53) Random, column, minimum degree,

Dulmage-Mendelsohn, and reverse

Cuthill-McKee permutations

Linear Algebra (p. 1-54) Compute norms, eigenvalues,

factorizations, least squares,

structural rank

Linear Equations (Iterative

Methods) (p. 1-54)

Methods for conjugate and biconjugate gradients, residuals,

lower quartile

Tree Operations (p. 1-55) Elimination trees, tree plotting,

factorization analysis

Elementary Sparse Matrices

spdiags Extract and create sparse band and

diagonal matrices

speye Sparse identity matrix

sprand Sparse uniformly distributed

random matrix

sprandn Sparse normally distributed random

matrix

sprandsym Sparse symmetric random matrix

Full to Sparse Conversion

find Find indices and values of nonzero

elements

full Convert sparse matrix to full matrix

sparse Create sparse matrix

spconvert Import matrix from sparse matrix

external format

Sparse Matrix Manipulation

issparse Determine whether input is sparse

nnz Number of nonzero matrix elements

nonzeros Nonzero matrix elements

nzmax Amount of storage allocated for

nonzero matrix elements

spalloc Allocate space for sparse matrix

spfun Apply function to nonzero sparse

matrix elements

spones Replace nonzero sparse matrix

elements with ones

spparms Set parameters for sparse matrix

routines

spy Visualize sparsity pattern

Reordering Algorithms

amd Approximate minimum degree

permutation

colamd Column approximate minimum

degree permutation

colperm Sparse column permutation based

on nonzero count

dmperm Dulmage-Mendelsohn decomposition

ldl Block LDL' factorization for

Hermitian indefinite matrices

randperm Random permutation

symamd Symmetric approximate minimum

degree permutation

symrcm Sparse reverse Cuthill-McKee

ordering

Linear Algebra

cholinc Sparse incomplete Cholesky and

Cholesky-Infinity factorizations

condest 1-norm condition number estimate

eigs Largest eigenvalues and

eigenvectors of matrix

ilu Sparse incomplete LU factorization

luinc Sparse incomplete LU factorization

normest 2-norm estimate

spaugment Form least squares augmented

system

sprank Structural rank

svds Find singular values and vectors

Linear Equations (Iterative Methods)

bicg Biconjugate gradients method

bicgstab Biconjugate gradients stabilized

method

bicgstabl Biconjugate gradients stabilized (l)

method

cgs Conjugate gradients squared method

gmres Generalized minimum residual

method (with restarts)

lsqr LSQR method

minres Minimum residual method

pcg Preconditioned conjugate gradients

method

qmr Quasi-minimal residual method

symmlq Symmetric LQ method

tfqmr Transpose-free quasi-minimal

residual method

Tree Operations

etree Elimination tree

etreeplot Plot elimination tree

gplot Plot nodes and links representing

adjacency matrix

symbolic factorization analysis

treelayout Lay out tree or forest treeplot Plot picture of tree

unmesh Convert edge matrix to coordinate

and Laplacian matrices

Math Constants

eps Floating-point relative accuracy

i Imaginary unit

Inf Infinity

intmax Largest value of specified integer

type

intmin Smallest value of specified integer

type

j Imaginary unit

NaN Not-a-Number

pi Ratio of circle's circumference to its

diameter

realmax Largest positive floating-point

number

realmin Smallest positive normalized

floating-point number

Data Analysis

Basic Operations (p. 1-57) Sums, products, sorting

Descriptive Statistics (p. 1-57) Statistical summaries of data

Filtering and Convolution (p. 1-58) Data preprocessing

Interpolation and Regression Data fitting

(p. 1-58)

Fourier Transforms (p. 1-59) Frequency content of data

Derivatives and Integrals (p. 1-59) Data rates and accumulations

Time Series Objects (p. 1-60) Methods for timeseries objects

Time Series Collections (p. 1-63)

Basic Operations

brush Interactively mark, delete, modify,

and save observations in graphs

Methods for tscollection objects

cumprod Cumulative product

cumsum Cumulative sum

linkdata Automatically update graphs when

variables change

prod Product of array elements

sort Sort array elements in ascending or

descending order

sortrows Sort rows in ascending order

sum Sum of array elements

Descriptive Statistics

corrcoef Correlation coefficients

cov Covariance matrix

max Largest elements in array

mean Average or mean value of array

median Median value of array

min Smallest elements in array mode Most frequent values in array

std Standard deviation

var Variance

Filtering and Convolution

conv Convolution and polynomial

multiplication

conv2 2-D convolution convn N-D convolution

deconv Deconvolution and polynomial

division

detrend Remove linear trends

filter 1-D digital filter filter2 2-D digital filter

Interpolation and Regression

interp1 1-D data interpolation (table lookup)
interp2 2-D data interpolation (table lookup)

interp3 3-D data interpolation (table lookup)

interpn N-D data interpolation (table lookup)

mldivide \, mrdivide /

polyfit

Polynomial curve fitting

polyval

Polynomial evaluation

Fourier Transforms

abs Absolute value and complex

magnitude

angle Phase angle

cplxpair Sort complex numbers into complex

conjugate pairs

fft Discrete Fourier transform

fft2 2-D discrete Fourier transform
fftn N-D discrete Fourier transform

fftshift Shift zero-frequency component to

center of spectrum

fftw Interface to FFTW library run-time

algorithm tuning control

ifft Inverse discrete Fourier transform

ifft2 2-D inverse discrete Fourier

transform

ifftn N-D inverse discrete Fourier

transform

ifftshift Inverse FFT shift

nextpow2 Next higher power of 2

unwrap Correct phase angles to produce

smoother phase plots

Derivatives and Integrals

cumtrapz Cumulative trapezoidal numerical

integration

del2 Discrete Laplacian

diff Differences and approximate

derivatives

gradient Numerical gradient polyder Polynomial derivative

polyint Integrate polynomial analytically trapz Trapezoidal numerical integration

Time Series Objects

Utilities (p. 1-60) Combine timeseries objects,

query and set timeseries object properties, plot timeseries objects

Data Manipulation (p. 1-61) Add or delete data, manipulate

timeseries objects

Event Data (p. 1-62) Add or delete events, create new

timeseries objects based on event

data

Descriptive Statistics (p. 1-62) Descriptive statistics for timeseries

objects

Utilities

get (timeseries) Query timeseries object property

values

getdatasamplesize Size of data sample in timeseries

object

getqualitydesc Data quality descriptions

isempty (timeseries) Determine whether timeseries

object is empty

length (timeseries)

Length of time vector

plot (timeseries) Plot time series

set (timeseries) Set properties of timeseries object

size (timeseries) Size of timeseries object

timeseries Create timeseries object

tsdata.event Construct event object for

timeseries object

tsprops Help on timeseries object

properties

tstool Open Time Series Tools GUI

Data Manipulation

addsample Add data sample to timeseries

object

ctranspose (timeseries) Transpose timeseries object

delsample Remove sample from timeseries

object

detrend (timeseries) Subtract mean or best-fit line and all

NaNs from time series

filter (timeseries) Shape frequency content of time

series

getabstime (timeseries) Extract date-string time vector into

cell array

getinterpmethod Interpolation method for timeseries

object

getsampleusingtime (timeseries) Extract data samples into new

timeseries object

idealfilter (timeseries) Apply ideal (noncausal) filter to

timeseries object

resample (timeseries) Select or interpolate timeseries

data using new time vector

setabstime (timeseries) Set times of timeseries object as

date strings

setinterpmethod Set default interpolation method for

timeseries object

synchronize Synchronize and resample two

timeseries objects using common

time vector

transpose (timeseries) Transpose timeseries object

vertcat (timeseries) Vertical concatenation of

timeseries objects

Event Data

addevent Add event to timeseries object

delevent Remove tsdata.event objects from

timeseries object

gettsafteratevent New timeseries object with samples

occurring at or after event

gettsafterevent New timeseries object with samples

occurring after event

gettsatevent New timeseries object with samples

occurring at event

gettsbeforeatevent New timeseries object with samples

occurring before or at event

gettsbeforeevent New timeseries object with samples

occurring before event

gettsbetweenevents New timeseries object with samples

occurring between events

Descriptive Statistics

iqr (timeseries) Interquartile range of timeseries

data

max (timeseries) Maximum value of timeseries data

mean (timeseries)

Mean value of timeseries data

median (timeseries)

Median value of timeseries data

min (timeseries) Minimum value of timeseries data

std (timeseries) Standard deviation of timeseries

data

sum (timeseries) Sum of timeseries data

var (timeseries) Variance of timeseries data

Time Series Collections

Utilities (p. 1-63) Query and set tscollection object

properties, plot tscollection

objects

Data Manipulation (p. 1-64) Add or delete data, manipulate

tscollection objects

Utilities

get (tscollection) Query tscollection object property

values

isempty (tscollection) Determine whether tscollection

object is empty

length (tscollection)

Length of time vector

plot (timeseries) Plot time series

set (tscollection) Set properties of tscollection

object

size (tscollection)
Size of tscollection object
tscollection
Create tscollection object
tstool
Open Time Series Tools GUI

Data Manipulation

addsampletocollection Add sample to tscollection object

addts Add timeseries object to

tscollection object

delsamplefromcollection Remove sample from tscollection

object

getabstime (tscollection) Extract date-string time vector into

cell array

getsampleusingtime (tscollection) Extract data samples into new

tscollection object

gettimeseriesnames Cell array of names of timeseries

objects in tscollection object

horzcat (tscollection) Horizontal concatenation for

tscollection objects

removets Remove timeseries objects from

tscollection object

resample (tscollection) Select or interpolate data in

tscollection using new time vector

setabstime (tscollection) Set times of tscollection object as

date strings

settimeseriesnames Change name of timeseries object

in tscollection

vertcat (tscollection) Vertical concatenation for

tscollection objects

Programming and Data Types

Data Types (p. 1-65) Numeric, character, structures, cell arrays, and data type conversion Data Type Conversion (p. 1-74) Convert one numeric type to another, numeric to string, string to numeric, structure to cell array, etc. Operators and Special Characters Arithmetic, relational, and logical (p. 1-76) operators, and special characters Strings (p. 1-78) Create, identify, manipulate, parse, evaluate, and compare strings Bit-Wise Operations (p. 1-81) Perform set, shift, and, or, compare, etc. on specific bit fields Evaluate conditions, testing for true Logical Operations (p. 1-82) or false Relational Operations (p. 1-82) Compare values for equality, greater than, less than, etc. Set Operations (p. 1-83) Find set members, unions, intersections, etc. Date and Time Operations (p. 1-83) Obtain information about dates and times Programming in MATLAB (p. 1-84) Function/expression evaluation, timed execution, memory, program control, error handling, MEX programming

Data Types

Numeric Types (p. 1-66)

Characters and Strings (p. 1-67)

Structures (p. 1-68)

Data of varying types and sizes stored in fields of a structure

Cell Arrays (p. 1-69) Data of varying types and sizes

stored in cells of array

Map Container Objects (p. 1-70) Select elements of Map container

using indices of various data types

Function Handles (p. 1-71) Invoke a function indirectly via

handle

Java Classes and Objects (p. 1-71) Access Java classes through

MATLAB interface

Data Type Identification (p. 1-72) Determine data type of a variable

Numeric Types

arrayfun Apply function to each element of

array

cast Cast variable to different data type

cat Concatenate arrays along specified

dimension

class Determine class name of object

find Find indices and values of nonzero

elements

intmax Largest value of specified integer

type

intmin Smallest value of specified integer

type

intwarning Control state of integer warnings

ipermute Inverse permute dimensions of N-D

array

isa Determine whether input is object

of given class

isequal Test arrays for equality

isequalwithequalnans Test arrays for equality, treating

NaNs as equal

isfinite Array elements that are finite isinf Array elements that are infinite isnan Array elements that are NaN

isnumeric Determine whether input is numeric

array

isreal Check if input is real array

isscalar Determine whether input is scalar isvector Determine whether input is vector permute Rearrange dimensions of N-D array

realmax Largest positive floating-point

number

realmin Smallest positive normalized

floating-point number

reshape Reshape array

squeeze Remove singleton dimensions

zeros Create array of all zeros

Characters and Strings

See "Strings" on page 1-78 for all string-related functions.

cellstr Create cell array of strings from

character array

char Convert to character array (string)
eval Execute string containing MATLAB

expression

findstr Find string within another, longer

string

isstr Determine whether input is

character array

regexp, regexpi Match regular expression sprintf Format data into string

sscanf Read formatted data from string streat Concatenate strings horizontally

strcmp, strcmpi Compare strings

strfind Find one string within another

strings String handling

strjust Justify character array

strmatch Find possible matches for string strread Read formatted data from string

strrep Find and replace substring

strtrim Remove leading and trailing white

space from string

strvcat Concatenate strings vertically

Structures

arrayfun Apply function to each element of

array

cell2struct Convert cell array to structure array

class Determine class name of object deal Distribute inputs to outputs

fieldnames Field names of structure, or public

fields of object

getfield Field of structure array

isa Determine whether input is object

of given class

isequal Test arrays for equality

isfield Determine whether input is

structure array field

isscalar Determine whether input is scalar

isstruct Determine whether input is

structure array

isvector Determine whether input is vector

orderfields Order fields of structure array rmfield Remove fields from structure

setfield Assign values to structure array field

struct Create structure array

struct2cell Convert structure to cell array

structfun Apply function to each field of scalar

structure

Cell Arrays

cell Construct cell array

cell2mat Convert cell array of matrices to

single matrix

cell2struct Convert cell array to structure array

celldisp Cell array contents

cellfun Apply function to each cell in cell

array

cellplot Graphically display structure of cell

array

cellstr Create cell array of strings from

character array

class Determine class name of object

deal Distribute inputs to outputs

isa Determine whether input is object

of given class

iscell Determine whether input is cell

array

iscellstr Determine whether input is cell

array of strings

isegual Test arrays for equality

isscalar Determine whether input is scalar isvector Determine whether input is vector mat2cell Divide matrix into cell array of

matrices

num2cell Convert numeric array to cell array

struct2cell Convert structure to cell array

Map Container Objects

containers.Map Construct containers.Map object isKey (Map) Check if containers.Map contains

key

keys (Map) Return all keys of containers.Map

object

length (Map) Length of containers.Map object

remove (Map) Remove key-value pairs from

containers.Map

size (Map) size of containers. Map object

values (Map) Return values of containers.Map

object

Function Handles

class Determine class name of object

feval Evaluate function

func2str Construct function name string from

function handle

functions Information about function handle function handle (@) Handle used in calling functions

indirectly

isa Determine whether input is object

of given class

isequal Test arrays for equality

str2func Construct function handle from

function name string

Java Classes and Objects

cell Construct cell array

class Determine class name of object clear Remove items from workspace,

freeing up system memory

depfun List dependencies of function or

P-file

exist Check existence of variable, function,

folder, or class

fieldnames Field names of structure, or public

fields of object

im2java Convert image to Java image

import Add package or class to current

import list

inmem Names of functions, MEX-files, Sun

Java classes in memory

isa Determine whether input is object

of given class

isjava Determine whether input is Sun

Java object

javaaddpath Add entries to dynamic Sun Java

class path

javaArray Construct Sun Java array

javachk Generate error message based on

Sun Java feature support

javaclasspath Get and set Sun Java class path

javaMethod Invoke Sun Java method

javaMethodEDT Invoke Sun Java method from Event

Dispatch Thread (EDT)

javaObject Invoke Sun Java constructor, letting

MATLAB choose the thread

javaObjectEDT Invoke Sun Java object constructor

on Event Dispatch Thread (EDT)

javarmpath Remove entries from dynamic Sun

Java class path

methods Class method names
methodsview View class methods

usejava Determine whether Sun Java feature

is supported in MATLAB software

which Locate functions and files

Data Type Identification

is* Detect state

isa Determine whether input is object

of given class

iscell Determine whether input is cell

array

iscellstr Determine whether input is cell

array of strings

ischar Determine whether item is character

array

isfield Determine whether input is

structure array field

isfloat Determine whether input is

floating-point array

ishghandle True for Handle Graphics® object

handles

isinteger Determine whether input is integer

array

isjava Determine whether input is Sun

Java object

islogical Determine whether input is logical

array

isnumeric Determine whether input is numeric

array

isobject Is input MATLAB object isreal Check if input is real array

isstr Determine whether input is

character array

isstruct Determine whether input is

structure array

validateattributes Check validity of array

who, whos List variables in workspace

Data Type Conversion

Numeric (p. 1-74) Convert data of one numeric type to

another numeric type

String to Numeric (p. 1-74) Convert characters to numeric

equivalent

Numeric to String (p. 1-75) Convert numeric to character

equivalent

Other Conversions (p. 1-75) Convert to structure, cell array,

function handle, etc.

Numeric

single

cast Variable to different data type

double Convert to double precision int8, int16, int32, int64 Convert to signed integer

typecast Convert data types without changing

underlying data

Convert to single precision

uint8, uint16, uint32, uint64 Convert to unsigned integer

String to Numeric

base2dec Convert base N number string to

decimal number

bin2dec Convert binary number string to

decimal number

cast Cast variable to different data type

hex2dec Convert hexadecimal number string

to decimal number

hex2num Convert hexadecimal number string

to double-precision number

str2double Convert string to double-precision

value

str2num Convert string to number

unicode2native Convert Unicode® characters to

numeric bytes

Numeric to String

cast Variable to different data type

char Convert to character array (string)

dec2base Convert decimal to base N number

in string

dec2bin Convert decimal to binary number

in string

dec2hex Convert decimal to hexadecimal

number in string

int2str Convert integer to string mat2str Convert matrix to string

native2unicode Convert numeric bytes to Unicode

characters

num2str Convert number to string

Other Conversions

cell2mat Convert cell array of matrices to

single matrix

cell2struct Convert cell array to structure array

datestr Convert date and time to string

format

func2str Construct function name string from

function handle

logical Convert numeric values to logical

mat2cell Divide matrix into cell array of

matrices

num2cell Convert numeric array to cell array

num2hex Convert singles and doubles to

IEEE® hexadecimal strings

str2func Construct function handle from

function name string

str2mat Form blank-padded character matrix

from strings

struct2cell Convert structure to cell array

Operators and Special Characters

Arithmetic Operators (p. 1-76) Plus, minus, power, left and right

divide, transpose, etc.

Relational Operators (p. 1-77) Equal to, greater than, less than or

equal to, etc.

Logical Operators (p. 1-77) Element-wise and short circuit and,

or, not

Special Characters (p. 1-78) Array constructors, line

 $continuation, \, comments, \, etc. \,$

Arithmetic Operators

+ Plus

- Minus

. Decimal point

= Assignment

* Matrix multiplication

/ Matrix right division

Matrix left division

Matrix power

Matrix transpose

Array multiplication (element-wise)

Array right division (element-wise)

Array left division (element-wise)

Array power (element-wise)

Array transpose

Relational Operators

<	Less than
<=	Less than or equal to
>	Greater than
>=	Greater than or equal to
==	Equal to
~=	Not equal to

Logical Operators

See also "Logical Operations" on page 1-82 for functions like ${\tt xor}$, all, any, etc.

&&	Logical AND
11	Logical OR
&	Logical AND for arrays
1	Logical OR for arrays
~	Logical NOT

Special Characters

:	Create vectors, subscript arrays, specify for-loop iterations
()	Pass function arguments, prioritize operators
[]	Construct array, concatenate elements, specify multiple outputs from function
{}	Construct cell array, index into cell array
	Insert decimal point, define structure field, reference methods of object
.()	Reference dynamic field of structure
	Reference parent directory
	Continue statement to next line
,	Separate rows of array, separate function input/output arguments, separate commands
;	Separate columns of array, suppress output from current command
%	Insert comment line into code
044040	
% { % }	Insert block of comments into code
!	Issue command to operating system
, ,	Construct character array
@	Construct function handle, reference class directory

Strings

Description of Strings in MATLAB (p. 1-79)	Basics of string handling in MATLAB
String Creation (p. 1-79)	Create strings, cell arrays of strings, concatenate strings together
String Identification (p. 1-79)	Identify characteristics of strings

String Manipulation (p. 1-80) Convert case, strip blanks, replace

characters

String Parsing (p. 1-80) Formatted read, regular expressions,

locate substrings

String Evaluation (p. 1-81) Evaluate stated expression in string

String Comparison (p. 1-81) Compare contents of strings

Description of Strings in MATLAB

strings String handling

String Creation

blanks Create string of blank characters

cellstr Create cell array of strings from

character array

char Convert to character array (string)

sprintf Format data into string

streat Concatenate strings horizontally struct Concatenate strings vertically

String Identification

isa Determine whether input is object

of given class

iscellstr Determine whether input is cell

array of strings

ischar Determine whether item is character

o rro w

isletter Array elements that are alphabetic

letters

isscalar Determine whether input is scalar

isspace Array elements that are space

characters

isstrprop Determine whether string is of

specified category

isvector Determine whether input is vector

validatestring Check validity of text string

String Manipulation

deblank Strip trailing blanks from end of

string

lower Convert string to lowercase

strjust Justify character array

strrep Find and replace substring

strtrim Remove leading and trailing white

space from string

upper Convert string to uppercase

String Parsing

findstr Find string within another, longer

string

regexp, regexpi Match regular expression

regexprep Replace string using regular

expression

regexptranslate Translate string into regular

expression

sscanf Read formatted data from string

strfind Find one string within another

strread Read formatted data from string

strtok Selected parts of string

String Evaluation

eval Execute string containing MATLAB

expression

evalc Evaluate MATLAB expression with

capture

evalin Execute MATLAB expression in

specified workspace

String Comparison

strcmp, strcmpi Compare strings

strmatch Find possible matches for string

strncmp, strncmpi Compare first n characters of strings

Bit-Wise Operations

bitand Bitwise AND

bitcmp Bitwise complement

bitget Bit at specified position

bitmax Maximum double-precision

floating-point integer

bitor Bitwise OR

bitset Set bit at specified position

bitshift Shift bits specified number of places

bitxor Bitwise XOR

swapbytes Swap byte ordering

Logical Operations

all Determine whether all array

elements are nonzero or true

and Find logical AND of array or scalar

inputs

any Determine whether any array

elements are nonzero

false Logical 0 (false)

find Find indices and values of nonzero

elements

isa Determine whether input is object

of given class

iskeyword Determine whether input is

MATLAB keyword

isvarname Determine whether input is valid

variable name

logical Convert numeric values to logical

not Find logical NOT of array or scalar

input

or Find logical OR of array or scalar

inputs

true Logical 1 (true)

xor Logical exclusive-OR

See "Operators and Special Characters" on page 1-76 for logical operators.

Relational Operations

eq Test for equality

ge Test for greater than or equal to

gt Test for greater than

le Test for less than or equal to

lt Test for less than
ne Test for inequality

See "Operators and Special Characters" on page 1-76 for relational operators.

Set Operations

calendar

intersect Find set intersection of two vectors

ismember Array elements that are members

of set

issorted Determine whether set elements are

in sorted order

Calendar for specified month

setdiff Find set difference of two vectors

setxor Find set exclusive OR of two vectors

union Find set union of two vectors

unique Find unique elements of vector

Date and Time Operations

addtodate Modify date number by field

clock Current time as date vector

cputime Elapsed CPU time date Current date string

datenum Convert date and time to serial date

number

datestr Convert date and time to string

format

datevec Convert date and time to vector of

components

eomday Last day of month

etime Time elapsed between date vectors

now Current date and time

weekday Day of week

Programming in MATLAB

Functions and Scripts (p. 1-85) Write and execute program code,

interact with caller, check input and

output values, dependencies

Evaluation (p. 1-86) Evaluate expression in string, apply

function to array, run script file, etc.

Timer (p. 1-87) Schedule execution of MATLAB

commands

Variables and Functions in Memory

(p. 1-88)

List, lock, or clear functions in memory, construct variable names,

consolidate workspaces, refresh

caches

Control Flow (p. 1-89) Conditional control, loop control,

error control, program termination

Error Handling (p. 1-90) Generate warnings and errors, test

for and catch errors, capture data on

cause of error, warning control

MEX Programming (p. 1-91) Compile MEX function from C or

Fortran code, list MEX-files in

memory, debug MEX-files

Functions and Scripts

addOptional (inputParser) Add optional argument to Input

Parser scheme

addParamValue (inputParser) Add parameter name/value

argument to Input Parser scheme

addRequired (inputParser) Add required argument to Input

Parser scheme

createCopy (inputParser) Create copy of inputParser object

depdir List dependent folders for function

or P-file

depfun List dependencies of function or

P-file

echo Display statements during function

execution

end Terminate block of code, or indicate

last array index

function Declare function

input Request user input

inputname Variable name of function input inputParser Construct input parser object

mfilename File name of currently running

function

namelengthmax Maximum identifier length

nargchk Validate number of input arguments

nargin, nargout Number of function arguments

nargoutchk Validate number of output

arguments

parse (inputParser) Parse and validate named inputs

pcode Create protected function file

script Sequence of MATLAB statements in

file

syntax Two ways to call MATLAB functions
varargin Variable length input argument list
varargout Variable length output argument list

Evaluation

ans Most recent answer

arrayfun Apply function to each element of

array

assert Generate error when condition is

violated

builtin Execute built-in function from

overloaded method

cellfun Apply function to each cell in cell

array

echo Display statements during function

execution

eval Execute string containing MATLAB

expression

evalc Evaluate MATLAB expression with

capture

evalin Execute MATLAB expression in

specified workspace

feval Evaluate function

iskeyword Determine whether input is

MATLAB keyword

isvarname Determine whether input is valid

variable name

pause Halt execution temporarily

run Run script that is not on current

path

script Sequence of MATLAB statements in

file

structfun Apply function to each field of scalar

structure

symvar Determine symbolic variables in

expression

tic, toc Measure performance using

stopwatch timer

Timer

delete (timer) Remove timer object from memory

disp (timer) Information about timer object

get (timer) Timer object properties

isvalid (timer) Determine whether timer object is

valid

set (timer) Configure or display timer object

properties

start Start timer(s) running

startat Start timer(s) running at specified

time

stop Stop timer(s)

timer Construct timer object

timerfind Find timer objects

timerfindall Find timer objects, including

invisible objects

wait Wait until timer stops running

Variables and Functions in Memory

ans Most recent answer

assignin Assign value to variable in specified

workspace

datatipinfo Produce short description of input

variable

genvarname Construct valid variable name from

string

global Declare global variables

inmem Names of functions, MEX-files, Sun

Java classes in memory

isglobal Determine whether input is global

variable

memory Display memory information

mislocked Determine if function is locked in

memory

mlock Prevent clearing function from

memory

munlock Allow clearing functions from

memory

namelengthmax Maximum identifier length

pack Consolidate workspace memory

persistent Define persistent variable

rehash Refresh function and file system

path caches

Control Flow

break Terminate execution of for or while

loop

case Execute block of code if condition is

true

catch Handle error detected in try-catch

statement

continue Pass control to next iteration of for

or while loop

else Execute statements if condition is

false

elseif Execute statements if additional

condition is true

end Terminate block of code, or indicate

last array index

error Display message and abort function

for Execute statements specified

number of times

if Execute statements if condition is

true

otherwise Default part of switch statement

parfor Parallel for-loop

return Return to invoking function

switch Switch among several cases, based

on expression

try Execute statements and catch

resulting errors

while Repeatedly execute statements while

condition is true

Error Handling

addCause (MException) Record additional causes of exception

assert Generate error when condition is

violated

catch Handle error detected in try-catch

statement

disp (MException) Display MException object

eq (MException) Compare MException objects for

equality

error Display message and abort function

ferror Information about file I/O errors

getReport (MException) Get error message for exception

intwarning Control state of integer warnings

isequal (MException) Compare MException objects for

equality

last (MException) Last uncaught exception

lastwarn Last warning message

MException Capture error information

ne (MException) Compare MException objects for

inequality

rethrow (MException) Reissue existing exception

function

try Execute statements and catch

resulting errors

warning Warning message

MEX Programming

dbmex Enable MEX-file debugging (on

UNIX platforms)

inmem Names of functions, MEX-files, Sun

Java classes in memory

mex Compile MEX-function from C/C++

or Fortran source code

mex.getCompilerConfigurations Get compiler configuration

information for building MEX-files

mexext Binary MEX-file name extension

Object-Oriented Programming

Classes and Objects (p. 1-92) Get information about classes and

objects

Handle Classes (p. 1-93) Define and use handle classes

Events and Listeners (p. 1-94) Define and use events and listeners

Meta-Classes (p. 1-94) Access information about classes without requiring instances

Classes and Objects

class Determine class name of object

classdef Class definition keywords

exist Check existence of variable, function,

folder, or class

inferior of Specify inferior class relationship

isobject Is input MATLAB object

loadobj Modify load process for object

methods Class method names

methodsview View class methods

properties Class property names

subsasgn Subscripted assignment

subsindex Subscript indexing with object

subsref Redefine subscripted reference for

objects

superiorto Establish superior class relationship

Handle Classes

getdisp (hgsetget)

addlistener (handle) Create event listener addprop (dynamicprops) Add dynamic property

delete (handle) Handle object destructor function dynamicprops Abstract class used to derive handle

class with dynamic properties

findobj (handle) Find handle objects matching

specified conditions

findprop (handle) Find meta.property object associated with property name

Query property values of handle

get (hgsetget) objects derived from hgsetget class

Override to change command

window display

handle Abstract class for deriving handle

classes

Abstract class used to derive handle hgsetget

class with set and get methods

isvalid (handle) Is object valid handle class object

notify (handle) Notify listeners that event is

occurring

relational operators (handle) Equality and sorting of handle

objects

set (hgsetget) Assign property values to handle

objects derived from hgsetget class

Override to change command setdisp (hgsetget)

window display

Events and Listeners

addlistener (handle) Create event listener

event.EventData Base class for all data objects passed

to event listeners

event.listener Class defining listener objects event.PropertyEvent Listener for property events

event.proplistener Define listener object for property

events

events Event names

notify (handle) Notify listeners that event is

occurring

Meta-Classes

meta.class class describes

MATLAB classes

meta.class.fromName Return meta.class object associated

with named class

meta.DynamicProperty meta.DynamicProperty class

describes dynamic property of

MATLAB object

meta.event describes meta.event class describes

MATLAB class events

meta.method class describes

MATLAB class methods

meta.package meta.package class describes

MATLAB packages

meta.package.fromName Return meta.package object for

specified package

meta.package.getAllPackages Get all top-level packages

meta.property meta.property class describes

MATLAB class properties

metaclass Obtain meta.class object

Graphics

Basic Plots and Graphs (p. 1-96) Linear line plots, log and semilog Plotting Tools (p. 1-97) GUIs for interacting with plots Annotating Plots (p. 1-97) Functions for and properties of titles, axes labels, legends, mathematical symbols Specialized Plotting (p. 1-98) Bar graphs, histograms, pie charts, contour plots, function plotters Bit-Mapped Images (p. 1-101) Display image object, read and write graphics file, convert to movie frames Printing (p. 1-102) Printing and exporting figures to standard formats Handle Graphics (p. 1-102) Creating graphics objects, setting properties, finding handles

Basic Plots and Graphs

polar

box Axes border errorbar Plot error bars along curve hold Retain current graph in figure line Create line object LineSpec (Line Specification) Line specification string syntax Log-log scale plot loglog plot 2-D line plot 3-D line plot plot3 plotyy 2-D line plots with y-axes on both left and right side

Polar coordinate plot

semilogx, semilogy Semilogarithmic plots

subplot Create axes in tiled positions

Plotting Tools

figure palette Show or hide figure palette

pan Pan view of graph interactively

plotbrowser Show or hide figure plot browser

plotedit Interactively edit and annotate plots

plottools Show or hide plot tools

propertyeditor Show or hide property editor rotate3d Rotate 3-D view using mouse

showplottool Show or hide figure plot tool

zoom Turn zooming on or off or magnify

by factor

Annotating Plots

annotation Create annotation objects

clabel Contour plot elevation labels

datacursormode Enable, disable, and manage

interactive data cursor mode

datetick Date formatted tick labels

gtext Mouse placement of text in 2-D view

legend Graph legend for lines and patches

rectangle Create 2-D rectangle object

texlabel Produce TeX format from character

string

title Add title to current axes xlabel, ylabel, zlabel Label x-, y-, and z-axis

Specialized Plotting

Area, Bar, and Pie Plots (p. 1-98) 1-D, 2-D, and 3-D graphs and charts Unfilled and filled contours in 2-D Contour Plots (p. 1-99) and 3-D Direction and Velocity Plots (p. 1-99) Comet, compass, feather and quiver plots Discrete Data Plots (p. 1-99) Stair, step, and stem plots Function Plots (p. 1-99) Easy-to-use plotting utilities for graphing functions Plots for showing distributions of Histograms (p. 1-100) data Polygons and Surfaces (p. 1-100) Functions to generate and plot surface patches in two or more dimensions Plots of point distributions Scatter/Bubble Plots (p. 1-101)

of plots

Functions to create and play movies

Area, Bar, and Pie Plots

Animation (p. 1-101)

area	Filled area 2-D plot
bar, barh	Plot bar graph (vertical and horizontal)
bar3, bar3h	Plot 3-D bar chart
pareto	Pareto chart
pie	Pie chart
pie3	3-D pie chart

Contour Plots

contour Contour plot of matrix

contour3 3-D contour plot

contourc Low-level contour plot computation

contourf Filled 2-D contour plot

ezcontour Easy-to-use contour plotter

ezcontourf Easy-to-use filled contour plotter

Direction and Velocity Plots

comet 2-D comet plot comet3 3-D comet plot

compass Plot arrows emanating from origin

feather Plot velocity vectors
quiver Quiver or velocity plot

quiver3 3-D quiver or velocity plot

Discrete Data Plots

stairs Stairstep graph

stem Plot discrete sequence data

Plot 3-D discrete sequence data

Function Plots

stem3

ezcontour Easy-to-use contour plotter

ezcontourf Easy-to-use filled contour plotter

ezmesh Easy-to-use 3-D mesh plotter

ezmeshc Easy-to-use combination

mesh/contour plotter

ezplot Easy-to-use function plotter

ezplot3 Easy-to-use 3-D parametric curve

plotter

ezpolar Easy-to-use polar coordinate plotter

ezsurf Easy-to-use 3-D colored surface

plotter

ezsurfc Easy-to-use combination

surface/contour plotter

fplot Plot function between specified

limits

Histograms

hist Histogram plot
histc Histogram count
rose Angle histogram plot

Polygons and Surfaces

cylinder Generate cylinder

delaunay Delaunay triangulation
delaunay3 3-D Delaunay tessellation
delaunayn N-D Delaunay tessellation

dsearch Search Delaunay triangulation for

nearest point

ellipsoid Generate ellipsoid
fill Filled 2-D polygons
fill3 Filled 3-D polygons

inpolygon Points inside polygonal region pcolor Pseudocolor (checkerboard) plot

polyarea Area of polygon

rectint Rectangle intersection area

ribbon Ribbon plot

slice Volumetric slice plot sphere Generate sphere waterfall Waterfall plot

Scatter/Bubble Plots

plotmatrix Scatter plot matrix

scatter Scatter plot

scatter3 3-D scatter plot

Animation

frame2im Return image data associated with

movie frame

getframe Capture movie frame

im2frame Convert image to movie frame
movie Play recorded movie frames

noanimate Change EraseMode of all objects to

normal

Bit-Mapped Images

frame2im Return image data associated with

movie frame

im2frame Convert image to movie frame

im2java Convert image to Java image

image Display image object

imagesc Scale data and display image object imfinfo Information about graphics file imformats Manage image file format registry imread Read image from graphics file imwrite Write image to graphics file ind2rgb Convert indexed image to RGB

image

Printing

hgexport Export figure

orient Hardcopy paper orientation

print, printopt Print figure or save to file and

configure printer defaults

printdlg Print dialog box

printpreview Preview figure to print

saveas Save figure or Simulink block diagram using specified format

Handle Graphics

Graphics Object Identification Find and manipulate graphics (p. 1-103) Find and manipulate graphics objects via their handles

Object Creation (p. 1-104) Constructors for core graphics

objects

Annotation Objects (p. 1-104) Property descriptions for annotation

objects

Plot Objects (p. 1-105) Property descriptions for plot objects

Figure Windows (p. 1-105) Control and save figures
Axes Operations (p. 1-106) Operate on axes objects

Object Property Operations (p. 1-106) Query, set, and link object properties

Graphics Object Identification

allchild Find all children of specified objects

ancestor Ancestor of graphics object

copyobj Copy graphics objects and their

descendants

delete Remove files or graphics objects

findall Find all graphics objects

findfigs Find visible offscreen figures

findobj Locate graphics objects with specific

properties

gca Current axes handle

gcbf Handle of figure containing object

whose callback is executing

gcbo Handle of object whose callback is

executing

gco Handle of current object

get Query Handle Graphics object

properties

ishandle Determine whether input is valid

Handle Graphics handle

propedit Open Property Editor

set Set Handle Graphics object

properties

Object Creation

axes Create axes graphics object figure Create figure graphics object

hggroup Create hggroup object

hgtransform Create hgtransform graphics object

image Display image object light Create light object Create line object

patch Create one or more filled polygons

rectangle Create 2-D rectangle object

root object Root

surface Create surface object

text Create text object in current axes

uicontextmenu Create context menu

Annotation Objects

Annotation Arrow Properties Define annotation arrow properties

Annotation Doublearrow Properties Define annotation doublearrow

properties

Annotation Ellipse Properties Define annotation ellipse properties

Annotation Line Properties Define annotation line properties

Annotation Rectangle Properties Define annotation rectangle

properties

Annotation Textarrow Properties Define annotation textarrow

properties

Annotation Textbox Properties Define annotation textbox properties

Plot Objects

Areaseries Properties Define areaseries properties Barseries Properties Define barseries properties Contourgroup Properties Define contourgroup properties **Errorbarseries Properties** Define errorbarseries properties Image Properties Define image properties Lineseries Properties Define lineseries properties Quivergroup Properties Define quivergroup properties Scattergroup Properties Define scattergroup properties Stairseries Properties Define stairseries properties Stemseries Properties Define stemseries properties Surfaceplot Properties Define surfaceplot properties

Figure Windows

clf Clear current figure window close Remove specified figure

closereq Default figure close request function drawnow Flush event queue and update figure

window

gcf Current figure handle

hgload Load Handle Graphics object

hierarchy from file

hgsave Save Handle Graphics object

hierarchy to file

newplot Determine where to draw graphics

objects

opengl Control OpenGL® rendering

refresh Redraw current figure

saveas Save figure or Simulink block

diagram using specified format

Axes Operations

axis Axis scaling and appearance

box Axes border

cla Clear current axes
gca Current axes handle

grid Grid lines for 2-D and 3-D plots

ishold Current hold state

makehgtform Create 4-by-4 transform matrix

Object Property Operations

get Query Handle Graphics object

properties

linkaxes Synchronize limits of specified 2-D

axes

linkprop Keep same value for corresponding

properties

refreshdata Refresh data in graph when data

source is specified

set Set Handle Graphics object

properties

3-D Visualization

Surface and Mesh Plots (p. 1-107) Plot matrices, visualize functions of

two variables, specify colormap

View Control (p. 1-109) Control the camera viewpoint,

zooming, rotation, aspect ratio, set

axis limits

Lighting (p. 1-111) Add and control scene lighting

Transparency (p. 1-111) Specify and control object

transparency

Volume Visualization (p. 1-111) Visualize gridded volume data

Surface and Mesh Plots

Surface and Mesh Creation (p. 1-107) Visualizing gridded and triangulated

data as lines and surfaces

Domain Generation (p. 1-108) Gridding data and creating arrays

Color Operations (p. 1-108) Specifying, converting, and

manipulating color spaces, colormaps, colorbars, and

backgrounds

Surface and Mesh Creation

hidden Remove hidden lines from mesh plot

mesh, meshc, meshz Mesh plots

peaks Example function of two variables

surf, surfc 3-D shaded surface plot surface Create surface object

surfl Surface plot with colormap-based

lighting

tetramesh Tetrahedron mesh plot

trimesh Triangular mesh plot
triplot 2-D triangular plot
trisurf Triangular surface plot

Domain Generation

meshgrid Generate X and Y arrays for 3-D plots

Color Operations

brighten Brighten or darken colormap

caxis Color axis scaling

colorbar showing color scale

colordef Set default property values to

display different color schemes

colormap Set and get current colormap

colormapeditor Start colormap editor
ColorSpec (Color Specification) Color specification

contrast Grayscale colormap for contrast

enhancement

graymon Set default figure properties for

grayscale monitors

hsv2rgb Convert HSV colormap to RGB

colormap

rgb2hsv Convert RGB colormap to HSV

colormap

rgbplot Plot colormap

shading Set color shading properties

spinmap Spin colormap

surfnorm Compute and display 3-D surface

normals

whitebg Change axes background color

View Control

Camera Viewpoint (p. 1-109) Orbiting, dollying, pointing, rotating

camera positions and setting fields

of view

Specifying what portions of axes to Aspect Ratio and Axis Limits

(p. 1-110)

view and how to scale them

Panning, rotating, and zooming

views

Region of Interest (p. 1-110) Interactively identifying rectangular

regions

Camera Viewpoint

Object Manipulation (p. 1-110)

camdolly Move camera position and target

cameratoolbar Control camera toolbar

programmatically

camlookat Position camera to view object or

group of objects

camorbit Rotate camera position around

camera target

campan Rotate camera target around camera

position

campos Set or query camera position camproj Set or query projection type Rotate camera about view axis camroll

camtarget Set or query location of camera

target

camup Set or query camera up vector

camva Set or query camera view angle

camzoom Zoom in and out on scene

makehgtform Create 4-by-4 transform matrix

view Viewpoint specification

viewmtx View transformation matrices

Aspect Ratio and Axis Limits

daspect Set or query axes data aspect ratio

pbaspect Set or query plot box aspect ratio

xlim, ylim, zlim Set or query axis limits

Object Manipulation

pan Pan view of graph interactively

reset Reset graphics object properties to

their defaults

rotate Rotate object in specified direction

rotate3d Rotate 3-D view using mouse

selectmoveresize Select, move, resize, or copy axes

and uicontrol graphics objects

zoom Turn zooming on or off or magnify

by factor

Region of Interest

dragrect Drag rectangles with mouse

rbbox Create rubberband box for area

selection

Lighting

camlight Create or move light object in camera

coordinates

diffuse Calculate diffuse reflectance

light Create light object

lightangle Create or position light object in

spherical coordinates

lighting Specify lighting algorithm

material Control reflectance properties of

surfaces and patches

specular Calculate specular reflectance

Transparency

alim Set or query axes alpha limits

alpha Set transparency properties for

objects in current axes

alphamap Specify figure alphamap

(transparency)

Volume Visualization

coneplot Plot velocity vectors as cones in 3-D

vector field

contourslice Draw contours in volume slice planes

curl Compute curl and angular velocity

of vector field

divergence Compute divergence of vector field

flow Simple function of three variables

interpstreamspeed Interpolate stream-line vertices from

flow speed

isocaps Compute isosurface end-cap

geometry

isocolors Calculate isosurface and patch colors

isonormals Compute normals of isosurface

vertices

isosurface Extract isosurface data from volume

data

reducepatch Reduce number of patch faces
reducevolume Reduce number of elements in

volume data set

shrinkfaces Reduce size of patch faces

slice Volumetric slice plot

smooth3 Smooth 3-D data

stream2 Compute 2-D streamline data stream3 Compute 3-D streamline data

streamline Plot streamlines from 2-D or 3-D

vector data

streamparticles Plot stream particles

streamribbon 3-D stream ribbon plot from vector

volume data

streamslice Plot streamlines in slice planes

streamtube Create 3-D stream tube plot

subvolume Extract subset of volume data set surf2patch Convert surface data to patch data

volumebounds Coordinate and color limits for

volume data

GUI Development

Predefined Dialog Boxes (p. 1-113) Dialog boxes for error, user input, waiting, etc. User Interface Deployment (p. 1-114) Open GUIs, create the handles structure User Interface Development Start GUIDE, manage application (p. 1-114) data, get user input User Interface Objects (p. 1-115) Create GUI components Objects from Callbacks (p. 1-116) Find object handles from within callbacks functions Move objects, wrap text GUI Utilities (p. 1-116) Wait and resume based on user Program Execution (p. 1-117) input

Predefined Dialog Boxes

dialog Create and display empty dialog box errordlg Create and open error dialog box export2wsdlg Export variables to workspace helpdlg Create and open help dialog box Create and open input dialog box inputdlg listdlg Create and open list-selection dialog box msgbox Create and open message box printdlg Print dialog box printpreview Preview figure to print questdlg Create and open question dialog box uigetdir Open standard dialog box for

selecting directory

uigetfile Open standard dialog box for

retrieving files

uigetpref Open dialog box for retrieving

preferences

uiopen Open file selection dialog box with

appropriate file filters

uiputfile Open standard dialog box for saving

files

uisave Open standard dialog box for saving

workspace variables

uisetcolor Open standard dialog box for setting

object's ColorSpec

uisetfont Open standard dialog box for setting

object's font characteristics

waitbar Open or update a wait bar dialog box

warndlg Open warning dialog box

User Interface Deployment

guidata Store or retrieve GUI data guihandles Create structure of handles

movegui Move GUI figure to specified location

on screen

openfig Open new copy or raise existing copy

of saved figure

User Interface Development

addpref Add preference

getappdata Value of application-defined data

getpref Preference

ginput Graphical input from mouse or

cursor

guidata Store or retrieve GUI data guide Open GUI Layout Editor inspect Open Property Inspector

isappdata True if application-defined data

exists

ispref Test for existence of preference rmappdata Remove application-defined data

rmpref Remove preference

setappdata Specify application-defined data

setpref Set preference

uigetpref Open dialog box for retrieving

preferences

uisetpref Manage preferences used in

uigetpref

waitfor Wait for condition before resuming

execution

waitforbuttonpress Wait for key press or mouse-button

click

User Interface Objects

menu Generate menu of choices for user

input

uibuttongroup Create container object to exclusively

manage radio buttons and toggle

buttons

uicontextmenu Create context menu

uicontrol Create user interface control object

uimenu Create menus on figure windows

uipanelCreate panel container objectuipushtoolCreate push button on toolbaruitableCreate 2-D graphic table GUI

component

uitoggletool Create toggle button on toolbar

uitoolbar Create toolbar on figure

Objects from Callbacks

findall Find all graphics objects

findfigs Find visible offscreen figures

findobj Locate graphics objects with specific

properties

gcbf Handle of figure containing object

whose callback is executing

gcbo Handle of object whose callback is

executing

GUI Utilities

align Align user interface controls

(uicontrols) and axes

getpixelposition Get component position in pixels

listfonts List available system fonts

selectmoveresize Select, move, resize, or copy axes

and uicontrol graphics objects

setpixelposition Set component position in pixels

textwrap Wrapped string matrix for given

uicontrol

uistack Reorder visual stacking order of

objects

Program Execution

uiresume Resume execution of blocked M-file

uiwait Block execution and wait for resume

External Interfaces

Shared Libraries (p. 1-118) Access functions stored in external

shared library files

Java (p. 1-119) Work with objects constructed from

Java API and third-party class

packages

.NET (p. 1-120) Work with objects constructed from

.NET assemblies

Component Object Model and

ActiveX (p. 1-121)

Integrate COM components into

your application

Web Services (p. 1-123) Communicate between applications

over a network using SOAP and

WSDL

Serial Port Devices (p. 1-124) Read and write to devices connected

to your computer's serial port

See also *MATLAB C/C++* and *Fortran API Reference* for functions you can use in external routines that interact with MATLAB programs and the data in MATLAB workspaces.

Shared Libraries

calllib Call function in shared library

libfunctions Return information on functions in

shared library

libfunctionsview View functions in shared library

libisloaded Determine if shared library is loaded

libpointer Create pointer object for use with

shared libraries

libstruct Create structure pointer for use with

shared libraries

loadlibrary Load shared library into MATLAB

software

unloadlibrary Unload shared library from memory

Java

class Determine class name of object

fieldnames Field names of structure, or public

fields of object

import Add package or class to current

import list

inspect Open Property Inspector

isa Determine whether input is object

of given class

isjava Determine whether input is Sun

Java object

javaaddpath Add entries to dynamic Sun Java

class path

javaArray Construct Sun Java array

javachk Generate error message based on

Sun Java feature support

javaclasspath Get and set Sun Java class path

javaMethod Invoke Sun Java method

javaMethodEDT Invoke Sun Java method from Event

Dispatch Thread (EDT)

javaObject Invoke Sun Java constructor, letting

MATLAB choose the thread

javaObjectEDT Invoke Sun Java object constructor

on Event Dispatch Thread (EDT)

javarmpath Remove entries from dynamic Sun

Java class path

methods Class method names
methodsview View class methods

usejava Determine whether Sun Java feature

is supported in MATLAB software

.NET

enableNETfromNetworkDrive Enable access to .NET commands

from network drive

NET.addAssembly Make .NET assembly visible to

MATLAB

NET.Assembly Members of .NET assembly

NET.convertArray Convert numeric MATLAB array to

.NET array

NET.createArray Create single or multidimensional

.NET array

NET.createGeneric Create instance of specialized .NET

generic type

NET.GenericClass Represent parameterized generic

type definitions

NET.GenericClass Constructor for NET.GenericClass

class

NET.invokeGenericMethod Invoke generic method of object

NET.NetException .NET exception

NET.setStaticProperty Static property or field name

Component Object Model and ActiveX

actxcontrol Create Microsoft® ActiveX® control

in figure window

actxcontrollist List currently installed Microsoft

ActiveX controls

actxcontrolselect Create Microsoft ActiveX control

from GUI

actxGetRunningServer Handle to running instance of

Automation server

actxserver Create COM server

addproperty Add custom property to COM object

delete (COM) Remove COM control or server

deleteproperty Remove custom property from COM

object

enableservice Enable, disable, or report status of

MATLAB Automation server

eventlisteners List event handler functions

associated with COM object events

events (COM) List of events COM object can trigger

Execute MATLAB command in

Automation server

Feval (COM) Evaluate MATLAB function in

Automation server

fieldnames Field names of structure, or public

fields of object

get (COM) Get property value from interface, or

display properties

GetCharArray Character array from Automation

erver

GetFullMatrix Matrix from Automation server

workspace

GetVariable Data from variable in Automation

server workspace

GetWorkspaceData Data from Automation server

workspace

inspect Open Property Inspector

interfaces List custom interfaces exposed by

COM server object

invoke Invoke method on COM object or

interface, or display methods

isa Determine whether input is object

of given class

iscom Determine whether input is COM or

ActiveX object

isevent Determine whether input is COM

object event

isinterface Determine whether input is COM

interface

ismethod Determine whether input is COM

object method

isprop Determine whether input is COM

object property

load (COM) Initialize control object from file

MaximizeCommandWindow Open Automation server window

methods Class method names

methodsview View class methods

Minimize CommandWindow Minimize size of Automation server

window

move Move or resize control in parent

window

propedit (COM) Open built-in property page for

control

PutCharArray Store character array in Automation

server

PutFullMatrix Matrix in Automation server

workspace

PutWorkspaceData Data in Automation server

workspace

Quit (COM) Terminate MATLAB Automation

server

registerevent Associate event handler for COM

object event at run time

release COM interface

save (COM) Serialize control object to file

set (COM) Set object or interface property to

specified value

unregisterallevents Unregister all event handlers

associated with COM object events

at run time

unregisterevent Unregister event handler associated

with COM object event at run time

Web Services

callSoapService Send SOAP message to endpoint

createClassFromWsdl Create MATLAB class based on

WSDL document

createSoapMessage Create SOAP message to send to

server

parseSoapResponse Convert response string from SOAP

server into MATLAB types

Serial Port Devices

clear (serial) Remove serial port object from

MATLAB workspace

delete (serial) Remove serial port object from

memory

fgetl (serial) Read line of text from device and

discard terminator

fgets (serial) Read line of text from device and

include terminator

fopen (serial) Connect serial port object to device

fprintf (serial) Write text to device

fread (serial) Read binary data from device

fscanf (serial) Read data from device, and format

as text

fwrite (serial) Write binary data to device get (serial) Serial port object properties

instrcallback Event information when event

occurs

instrfind Read serial port objects from memory

to MATLAB workspace

instrfindall Find visible and hidden serial port

objects

isvalid (serial) Determine whether serial port

objects are valid

length (serial) Length of serial port object array

load (serial) Load serial port objects and variables

into MATLAB workspace

readasync Read data asynchronously from

device

record Record data and event information

to file

save (serial) Save serial port objects and variables

to file

serial Create serial port object

serialbreak Send break to device connected to

serial port

set (serial) Configure or display serial port

object properties

size (serial) Size of serial port object array

stopasync Stop asynchronous read and write

operations

Alphabetical List

```
Arithmetic Operators + - * / \setminus ^{\prime}
Relational Operators <> <= >= == ~=
Logical Operators: Elementwise & | ~
Logical Operators: Short-circuit && | |
Special Characters []() {} = '...., ;: %!@
colon (:)
abs
accumarray
acos
acosd
acosh
acot
acotd
acoth
acsc
acscd
acsch
actxcontrol
actxcontrollist
actx control select
actxGetRunningServer
actxserver
addCause (MException)
addevent
addframe (avifile)
addlistener (handle)
addOptional (inputParser)
addParamValue (inputParser)
```

```
addpath
addpref
addprop (dynamicprops)
addproperty
addRequired (inputParser)
addsample
addsampletocollection
addtodate
addts
airy
align
alim
all
allchild
alpha
alphamap
amd
ancestor
and
angle
annotation
Annotation Arrow Properties
Annotation Doublearrow Properties
Annotation Ellipse Properties
Annotation Line Properties
Annotation Rectangle Properties
Annotation Textarrow Properties
Annotation Textbox Properties
ans
any
area
Areaseries Properties
arrayfun
ascii
asec
asecd
asech
```

asin

asind

asinh

assert

assignin

atan

atan2

atand

atanh

audiodevinfo

audioplayer

audiorecorder

aufinfo

auread

auwrite

avifile

aviinfo

aviread

axes

Axes Properties

axis

balance

bar, barh

bar3, bar3h

Barseries Properties

baryToCart

base2dec

beep

осср

bench

besselh

besseli

besselj

besselk

bessely

beta

betainc

betaincinv

betaln

bicg

bicgstab

bicgstabl

bin2dec

binary

bitand

bitcmp

bitget

bitmax

bitor

bitset

bitshift

bitxor

blanks

blkdiag

box

break

brighten

brush

bsxfun

builddocsearchdb

builtin

bvp4c

bvp5c

bvpget

bvpinit

bvpset

bvpxtend

calendar

calllib

callSoapService

camdolly

camerato olbar

camlight

camlookat

camorbit

campan

campos

camproj

camroll

camtarget

camup

camva

camzoom

cartToBary

cart2pol

cart2sph

case

cast

cat

catch

caxis

cd

convexHull

cd (ftp)

cdf2rdf

cdfepoch

cdfinfo

cdflib

cdflib.close

cdflib.closeVar

cdflib.compute Epoch

cdflib.compute Epoch 16

cdflib.create

cdflib.createAttr

cdflib.createVar

cdflib.delete

cdflib.deleteAttr

cdflib.deleteAttrEntry

cdflib. delete Attrg Entry

cdflib.deleteVar

cdflib.deleteVarRecords

cdflib.epoch16Breakdown

cdflib.epochBreakdown cdflib.getAttrEntry cdflib.getAttrgEntry cdflib.getAttrMaxEntry cdflib.getAttrMaxgEntry cdflib.getAttrName cdflib.getAttrNum cdflib.getAttrScope cdflib.getCacheSize cdflib.getChecksum cdflib.getCompression cdflib.getCompressionCacheSize cdflib.getConstantNames cdflib.getConstantValue cdflib.getCopyright cdflib.getFormat cdflib.getLibraryCopyright cdflib.getLibraryVersion cdflib.getMajority cdflib.getName cdflib.getNumAttrEntries cdflib.getNumAttrgEntries cdflib.getNumAttributes cdflib.getNumgAttributes cdflib.getReadOnlyMode cdflib.getStageCacheSize cdflib.getValidate cdflib.getVarAllocRecords cdflib.getVarBlockingFactor cdflib.getVarCacheSize cdflib.getVarCompression cdflib.getVarData cdflib.getVarMaxAllocRecNum cdflib.getVarMaxWrittenRecNum cdflib.getVarName cdflib.getVarNum cdflib.getVarNumRecsWritten

cdflib.getVarPadValue cdflib.getVarRecordData cdflib.getVarReservePercentcdflib.getVarSparseRecords cdflib.getVersion cdflib.hyperGetVarData cdflib.hyperPutVarData cdflib.inquire cdflib.inquireAttr cdflib.inquireAttrEntry cdflib.inquireAttrgEntry cdflib.inquireVar cdflib.open cdflib.putAttrEntry cdflib.putAttrgEntry cdflib.putVarData cdflib.putVarRecordData cdflib.renameAttr cdflib.renameVar cdflib.setCacheSize cdflib.setChecksum cdflib.setCompression cdflib.setCompressionCacheSize cdflib.setFormat cdflib.setMajority cdflib.setReadOnlyMode cdflib.setStageCacheSize cdflib.setValidate cdflib.setVarAllocBlockRecords cdflib.setVarBlockingFactor cdflib.setVarCacheSize cdflib.setVarCompression cdflib.setVarInitialRecs cdflib.setVarPadValue cdflib.SetVarReservePercent cdflib.setVarsCacheSize cdflib.setVarSparseRecords

cdfread cdfwrite ceil cell cell2mat cell2struct celldisp cellfun cellplot cellstrcgs char checkin checkout chol cholinc cholupdate circshift circumcenters cla clabel class classdef clc clear clearvars clear (serial) clf clipboard clock closeclose close (avifile) close (ftp) closereq cmopts

cmpermute

cmunique colamd colorbar colordef colormap color map editorColorSpec (Color Specification) colperm comet comet3 commandhistory commandwindow compan compass complex computeStrip computeTilecomputer cond condeig condest coneplot conj continue contour contour3 contourc contourf Contourgroup Properties contourslice contrastconv conv2 convhull convhulln convn

copyfile

```
copyobj
corrcoef
cos
cosd
cosh
cot
cotd
coth
cov
cplxpair
cputime
create (RandStream)
create Class From Wsdl\\
createCopy (inputParser)
createSoapMessage
cross
csc
cscd
csch
csvread
csvwrite
ctranspose (timeseries)
cumprod
cumsum
cumtrapz
curl
currentDirectory
customverctrl
cylinder
dagread
daspect
datacursormode
datatipinfo
date
datenum
datestr
datetick
```

datevec

dbclear

dbcont

dbdown

dblquad

dbmex

dbquit

dbstack

dbstatus

dbstep

dbstop

dbtype

dbup

dde23

ddeget

ddesd

ddeset

deal

deblank

dec2base

dec2bin

dec2hex

decic

deconv

del2

DelaunayTri

DelaunayTri

delaunay

delaunay3

delaunayn

delete

delete (COM)

delete (ftp)

delete (handle)

delete (serial)

delete (timer)

deleteproperty

```
delevent
delsample
delsamplefromcollection
demo
depdir
depfun
det
detrend
detrend (timeseries)
deval
diag
dialog
diary
diff
diffuse
dir
dir (ftp)
disp
disp (memmapfile)
disp (MException)
disp (serial)
disp (timer)
display
dither
divergence
dlmread
dlmwrite
dmperm
doc
docsearch
dos
dot
double
dragrect
drawnow
dsearch
dsearchn
```

```
dynamicprops
echo
echodemo
edgeAttachments
edges
edit
eig
eigs
ellipj
ellipke
ellipsoid
else
elseif
enableNETfromNetworkDrive
enableservice
end
eomday
eps
eq
eq (MException)
erf, erfc, erfcx, erfinv, erfcinv
error
errorbar
Errorbarseries Properties
errordlg
etime
etree
etreeplot
eval
evalc
evalin
event.EventData
event.listener
event.PropertyEvent
event.proplistener
eventlisteners
events
```

events (COM)

Execute

exifread

exist

exit

exp

expint

expm

expm1

export2wsdlg

eye

ezcontour

ezcontourf

ezmesh

ezmeshc

ezplot

ezplot3

ezpolar

ezsurf

ezsurfc

faceNormals

factor

factorial

false

fclose

fclose (serial)

feather

featureEdges

feof

ferror

feval

Feval (COM)

fft

fft2

fftn

fftshift

fftw

fgetl

fgetl (serial)

fgets

fgets (serial)

fieldnames

figure

Figure Properties

figurepalette

fileattrib

filebrowser

File Formats

filemarker

fileparts

fileread

filesep

fill

fill3

filter

filter (timeseries)

filter2

find

findall

findfigs

findobj

findobj (handle)

findprop (handle)

findstr

finish

fitsinfo

fitsread

fix

flipdim

fliplr

flipud

floor

flow

fminbnd

```
fminsearch
fopen
fopen (serial)
for
format
fplot
fprintf
fprintf (serial)
frame2im
fread
fread (serial)
freeBoundary
freqspace
frewind
fscanf
fscanf (serial)
fseek
ftell
ftp
full
fullfile
func2str
function
function_handle (@)
functions
funm
fwrite
fwrite (serial)
fzero
gallery
gamma, gammainc, gammaln
gammaincinv
gca
gcbf
gcbo
gcd
gcf
```

```
gco
ge
genpath
genvarname
get
get
get
get (COM)
get (hgsetget)
get (memmapfile)
get
get (RandStream)
get (serial)
get (timer)
get (timeseries)
get (tscollection)
getabstime (timeseries)
getabstime (tscollection)
getappdata
getaudiodata
GetCharArray
getdatasamplesize
getDefaultStream (RandStream)
getdisp (hgsetget)
getenv
getfield
getFileFormats
getframe
GetFullMatrix
getinterpmethod
getpixelposition
getpref
getqualitydesc
getReport (MException)
getsampleusingtime (timeseries)
getsampleusingtime (tscollection)
getTag
```

getTagNames gettimeseriesnames gettsafteratevent gettsafterevent gettsatevent gettsbeforeatevent gettsbeforeevent gettsbetweenevents GetVariable getVersion GetWorkspaceData ginput global gmres gplot grabcode gradient graymon grid griddata griddata3 griddatan gsvd gt gtext guidata guide guihandles gunzip gzip hadamard handle hankel hdf hdf5 hdf5info

hdf5read

hdf5write hdfinfo hdfread hdftool help helpbrowserhelpdesk helpdlg helpwin hess hex2dec hex2num hgexport hggroup **Hggroup Properties** hgload hgsave hgsetget hgtransform **Hgtransform Properties** hidden hilb hist histc hold home horzcat horzcat (tscollection) hostid hsv2rgb hypot idealfilter (timeseries) idivide if ifft ifft2

ifftn

ifftshift

ilu

im2frame

im2java

imag

image

Image Properties

imagesc

imapprox

imfinfo

imformats

import

importdata

imread

imwrite

incenters

inOutStatus

ind2rgb

ind2sub

Inf

inferiorto

info

inline

inmem

inpolygon

input

inputdlg

inputname

inputParser

inspect

instrcallback

instrfind

instrfindall

int2str

int8, int16, int32, int64

interfaces

interp1

interp1q

interp2

interp3

interpft

interpn

interpstreamspeed

intersect

intmax

intmin

intwarning

inv

invhilb

invoke

ipermute

iqr (timeseries)

is*

isa

isappdata

iscell

iscellstr

ischar

iscom

isdir

isEdge

isempty

isempty (timeseries)

isempty (tscollection)

isequal

isequal (MException)

isequalwithequalnans

isevent

isfield

isfinite

isfloat

isglobal

ishandle

ishghandle

ishold

isinf

isinteger

isinterface

isjava

isKey (Map)

iskeyword

isletter

islogical

ismac

ismember

ismethod

isnan

isnumeric

isobject

isocaps

isocolors

isonormals

isosurface

ispc

is Platform Supported

ispref

isprime

isprop

isreal

isscalar

issorted

isspace

issparse

isstr

isstrprop

isstruct

isstudent

isTiled

isunix

isvalid (handle)

isvalid (serial) isvalid (timer) isvarname isvector javaaddpath javaArray javachk javaclasspath javaMethod javaMethodEDT javaObject javaObjectEDT javarmpath keyboard keys (Map) kron last (MException) lastDirectory lasterr lasterror lastwarn lcm ldl ldivide, rdivide le legend legendre length length (Map) length (serial) length (timeseries) length (tscollection) libfunctions libfunctionsview libisloaded

libpointer

libstruct

license

light

Light Properties

lightangle

lighting

lin2mu

line

Line Properties

Lineseries Properties

LineSpec (Line Specification)

linkaxes

linkdata

linkprop

linsolve

linspace

list (RandStream)

listdlg

listfonts

load

load (COM)

load (serial)

loadlibrary

loadobj

log

log10

log1p

log2

logical

loglog

logm

logspace

lookfor

lower

ls

lscov

lsqnonneg

lsqr lt lu luinc magic makehgtform containers.Map mat2cell mat2str material matlabcolon (matlab:) matlabrc matlabroot matlab (UNIX) matlab (Windows) max max (timeseries) Maximize Command WindowmaxNumCompThreads mean mean (timeseries) median median (timeseries) memmapfile memory menu mesh, meshc, meshz meshgrid meta.class meta.class.fromName meta.DynamicProperty

meta.event meta.method meta.package

meta.property

 $meta.package.from Name\\ meta.package.get All Packages$

```
metaclass
methods
methodsview
mex.getCompilerConfigurations
MException
mexext
mfilename
mget
min
min (timeseries)
MinimizeCommandWindow
minres
mislocked
mkdir
mkdir (ftp)
mkpp
mldivide \, mrdivide /
mlint
mlintrpt
mlock
mmfileinfo
mmreader
mod
mode
more
move
movefile
movegui
movie
movie2avi
mput
msgbox
mtimes
mu2lin
multibandread
multibandwrite
```

munlock

namelengthmax

NaN

nargchk

nargin, nargout

nargoutchk

native2unicode

nchoosek

ndgrid

ndims

ne

nearest Neighbor

ne (MException)

neighbors

NET

NET.addAssembly

NET.Assembly

NET.convertArray

NET.createArray

NET.createGeneric

NET.GenericClass

NET.GenericClass

NET.invokeGenericMethod

NET.NetException

NET.setStaticProperty

netcdf

netcdf.abort

netcdf.close

netcdf.copyAtt

netcdf.create

netcdf.defDim

netcdf.defVar

netcdf.delAtt

netcdf.endDef

netcdf.getAtt

netcdf.getConstant

netcdf.getConstantNames

netcdf.getVarnetcdf.inq netcdf.inqAtt netcdf.inqAttID netcdf.inqAttName netcdf.inqDim netcdf.inqDimID netcdf.inqLibVers netcdf.inqVar netcdf.inqVarID netcdf.open netcdf.putAtt netcdf.putVar netcdf.reDef netcdf.renameAtt netcdf.renameDim netcdf.renameVar netcdf.setDefaultFormatnetcdf.setFillnetcdf.sync newplot nextDirectory nextpow2 nnz noanimate nonzeros norm normest not notebook notify (handle) now nthroot null num2cell num2hex

num2str

```
numberOfStrips
numberOfTiles
numel
nzmax
ode15i
ode23, ode45, ode113, ode15s, ode23s, ode23t, ode23tb
odefile
odeget
odeset
odextend
onCleanup
ones
open
openfig
opengl
openvar
optimget
optimset
or
ordeig
orderfields
ordqz
ordschur
orient
orth
otherwise
pack
padecoef
pagesetupdlg
pan
pareto
parfor
parse (inputParser)
parseSoapResponse
pascal
patch
Patch Properties
```

path path2rc pathsep pathtool pause pbaspect pcg pchip pcode pcolor pdepe pdeval peaks perl perms permute persistent pi pie pie3 pinv planerot play play playblocking playshow plot plot (timeseries) plot3 plotbrowser plotedit plotmatrix plottools plotyy pointLocation pol2cart polar

poly polyarea polyder polyeig polyfit polyint polyval polyvalm pow2 power ppval prefdir preferences primes print, printopt printdlg printpreview prod profile profsave propedit propedit (COM) properties propertyeditor psi publish PutCharArray PutFullMatrixPutWork space Datapwd qmr qr qrdelete grinsert qrupdate quad

quad2d

```
quadgk
quadl
quadv
questdlg
quit
Quit (COM)
quiver
quiver3
Quivergroup Properties
qz
rand
rand (RandStream)
randi
randi (RandStream)
randn
randn (RandStream)
randperm
randperm (RandStream)
RandStream
RandStream (RandStream)
rank
rat, rats
rbbox
rcond
read
read
readasync
read Encoded Strip\\
readEncodedTile
real
reallog
realmax
realmin
realpow
realsqrt
record
record
```

recordblocking

rectangle

Rectangle Properties

rectint

recycle

reducepatch

reducevolume

refresh

refreshdata

regexp, regexpi

regexprep

regexptranslate

registerevent

rehash

release

relational operators (handle)

rem

remove (Map)

removets

rename

repmat

resample (timeseries)

resample (tscollection)

reset

reset (RandStream)

reshape

residue

restored efault path

rethrow

rethrow (MException)

return

rewriteDirectory

rgb2hsv

rgb2ind

rgbplot

ribbon

rmappdata

```
rmdir
rmdir (ftp)
rmfield
rmpath
rmpref
root object
Root Properties
roots
rose
rosser
rot90
rotate
rotate3d
round
rref
rsf2csf
run
save
save (COM)
save (serial)
saveas
saveobj
savepath
scatter
scatter3
Scattergroup Properties
schur
script
sec
secd
\operatorname{sech}
selectmoveresize
semilogx, semilogy
sendmail
serial
serialbreak
set
```

```
set
set
set (COM)
set (hgsetget)
set (RandStream)
set (serial)
set (timer)
set (timeseries)
set (tscollection)
setabstime (timeseries)
setabstime (tscollection)
setappdata
setDefaultStream (RandStream)
setdiff
\operatorname{setDirectory}
setdisp (hgsetget)
setenv
setfield
setinterpmethod
setpixelposition
setpref
setstr
setSubDirectory
setTag
settimeseriesnames
setxor
shading
shg
shiftdim
showplottool
shrinkfaces
sign
\sin
sind
single
sinh
```

```
size
size (Map)
size (serial)
size (timeseries)
size
size (tscollection)
slice
smooth3
snapnow
sort
sortrows
sound
soundsc
spalloc
sparse
spaugment
spconvert\\
spdiags
specular
speye
spfun
sph2cart
sphere
spinmap
spline
spones
spparms
sprand
sprandn
sprandsym
sprank
sprintf
spy
sqrt
sqrtm
squeeze
ss2tf
```

sscanf stairs Stairseries Properties start startat startup std std (timeseries) stem stem3 Stemseries Properties stop stopasync str2double str2func str2mat str2num strcat stremp, strempi stream2 stream3 streamline streamparticles streamribbon streamslice streamtube strfind strings strjust strmatch strncmp, strncmpi strread strrep strtok

strtrim struct struct2cell

structfun strvcat sub2ind subplot subsasgn subsindex subspace subsref substruct subvolume sum sum (timeseries) superclasses superiorto support surf, surfc surf2patch surface Surface Properties Surfaceplot Properties surfl surfnorm svd svds swapbytes switch symamd symbfact symmlqsymrcm symvar synchronize syntax system tan tand

tanh

tar

tempdir

tempname

tetramesh

texlabel

text

Text Properties

textread

textscan

textwrap

tfqmr

throw (MException)

throwAsCaller (MException)

tic, toc

Tiff

timer

timerfind

timerfindall

timeseries

title

todatenum

toeplitz

toolboxdir

trace

transpose (timeseries)

trapz

treelayout

treeplot

tril

trimesh

triplequad

triplot

TriRep

TriRep

TriScatteredInterp

TriScatteredInterp

trisurf

triu

true

try

tscollection

tsdata.event

tsearch

tsearchn

tsprops

tstool

type

typecast

uibuttongroup

Uibuttongroup Properties

uicontextmenu

Uicontextmenu Properties

uicontrol

Uicontrol Properties

uigetdir

uigetfile

uigetpref

uiimport

uimenu

Uimenu Properties

uint8, uint16, uint32, uint64

uiopen

uipanel

Uipanel Properties

uipushtool

Uipushtool Properties

uiputfile

uiresume

uisave

uisetcolor

uisetfont

uisetpref

uistack

uitable

Uitable Properties

uitoggletool

Uitoggletool Properties

uitoolbar

Uitoolbar Properties

uiwait

undocheckout

unicode2native

union

unique

unix

unloadlibrary

unmesh

unmkpp

unregisterallevents

unregisterevent

untar

unwrap

unzip

upper

urlread

urlwrite

usejava

userpath

validateattributes

validatestring

values (Map)

vander

var

var (timeseries)

varargin

varargout

vectorize

ver

verctrl

verLessThan

version

vertcat

vertcat (timeseries)

vertcat (tscollection)

vertexAttachments

view

viewmtx

visdiff

volumebounds

voronoi

voronoiDiagram

voronoin

wait

waitbar

waitfor

waitforbuttonpress

warndlg

warning

waterfall

wavfinfo

wavplay

wavread

wavrecord

wavwrite

web

weekday

what

whatsnew

which

while

whitebg

who, whos

wilkinson

winopen

winqueryreg

wk1finfo

wk1read

wk1write

workspace write write Directorywrite Encoded Stripwrite Encoded Tilexlabel, ylabel, zlabel xlim, ylim, zlim xlsfinfo xlsread xlswrite xmlread xmlwrite xor xslt zeros zip

zoom

Purpose

Unit normals to specified triangles

Syntax

FN = faceNormals(TR, TI)

Description

FN = faceNormals(TR, TI) returns the unit normal vector to each of the specified triangles TI.

Note This query is only applicable to triangular surface meshes.

Input Arguments

TR Triangulation representation.

TI Column vector of indices that index into the

triangulation matrix TR.Triangulation.

Output Arguments

FN

m-by-3 matrix. m = length(TI), the number of
triangles to be queried. Each row FN(i,:) represents

the unit normal vector to triangle TI(i).

If TI is not specified the unit normal information for the entire triangulation is returned, where the normal

associated with triangle i is the i'th row of FN.


Examples

Triangulate a sample of random points on the surface of a sphere and use the TriRep to compute the normal to each triangle:

```
numpts = 100;
thetha = rand(numpts,1)*2*pi;
phi = rand(numpts,1)*pi;
x = cos(thetha).*sin(phi);
y = sin(thetha).*sin(phi);
z = cos(phi);
dt = DelaunayTri(x,y,z);
```

TriRep.faceNormals

TriRep.faceNormals



See Also

TriRep.freeBoundary DelaunayTri

factor

Purpose Prime factors

Syntax f = factor(n)

Description f = factor(n) returns a row vector containing the prime factors of n.

Examples f = factor(123)

f =

3 41

See Also isprime, primes

factorial

Purpose Factorial function

Syntax factorial(N)

Description factorial(N), for scalar N, is the product of all the integers from 1 to

N, i.e. prod(1:n). When N is an N-dimensional array, factorial(N) is

the factorial for each element of N.

Since double precision numbers only have about 15 digits, the answer is only accurate for $n \le 21$. For larger n, the answer will have the right

magnitude, and is accurate for the first 15 digits.

See Also prod

Purpose Logical 0 (false)

Syntax false

false(n)
false(m, n)
false(m, n, p, ...)
false(size(A))

Description

false is shorthand for logical(0).

false(n) is an n-by-n matrix of logical zeros.

false(m, n) or false([m, n]) is an m-by-n matrix of logical zeros.

false(m, n, p, ...) or false([m n p ...]) is an m-by-n-by-p-by-... array of logical zeros.

Note The size inputs m, n, p, ... should be nonnegative integers. Negative integers are treated as 0.

false(size(A)) is an array of logical zeros that is the same size as array A.

Remarks

false(n) is much faster and more memory efficient than

logical(zeros(n)).

See Also

true, logical

Purpose Close one or all open files

Syntax fclose(fileID)

fclose('all')

status = fclose(...)

Description fclose(fileID) closes an open file. fileID is an integer file identifier

obtained from fopen.

fclose('all') closes all open files.

status = fclose(...) returns a status of 0 when the close operation

is successful. Otherwise, it returns -1.

See Also ferror | fopen

Disconnect serial port object from device

Syntax

fclose(obj)

Description

fclose(obj) disconnects obj from the device, where obj is a serial port object or an array of serial port objects.

Remarks

If obj was successfully disconnected, then the Status property is configured to closed and the RecordStatus property is configured to off. You can reconnect obj to the device using the fopen function.

An error is returned if you issue fclose while data is being written asynchronously. In this case, you should abort the write operation with the stopasync function, or wait for the write operation to complete.

If you use the help command to display help for fclose, then you need to supply the pathname shown below.

help serial/fclose

Example

This example creates the serial port object s on a Windows platform, connects s to the device, writes and reads text data, and then disconnects s from the device using fclose.

```
s = serial('COM1');
fopen(s)
fprintf(s, '*IDN?')
idn = fscanf(s);
fclose(s)
```

At this point, the device is available to be connected to a serial port object. If you no longer need s, you should remove from memory with the delete function, and remove it from the workspace with the clear command.

See Also

Functions

clear, delete, fopen, stopasync

fclose (serial)

Properties

RecordStatus, Status

Plot velocity vectors



GUI Alternatives

Use the Plot Selector to graph selected variables in the Workspace Browser and the Plot Catalog, accessed from the Figure Palette. Directly manipulate graphs in *plot edit* mode, and modify them using the Property Editor. For details, see "Working in Plot Edit Mode", and "The Figure Palette" in the MATLAB Graphics documentation, and also Creating Graphics from the Workspace Browser in the MATLAB Desktop documentation.

Syntax

```
feather(U,V)
feather(Z)
feather(...,LineSpec)
feather(axes_handle,...)
h = feather(...)
```

Description

A feather plot displays vectors emanating from equally spaced points along a horizontal axis. You express the vector components relative to the origin of the respective vector.

feather (U,V) displays the vectors specified by U and V, where U contains the x components as relative coordinates, and V contains the y components as relative coordinates.

feather(Z) displays the vectors specified by the complex numbers in Z.
This is equivalent to feather(real(Z),imag(Z)).

feather(...,LineSpec) draws a feather plot using the line type, marker symbol, and color specified by LineSpec.


feather(axes_handle,...) plots into the axes with the handle axes_handle instead of into the current axes (gca).

h = feather(...) returns the handles to line objects in h.

Examples

Create a feather plot showing the direction of theta.

```
theta = (-90:10:90)*pi/180;
r = 2*ones(size(theta));
[u,v] = pol2cart(theta,r);
feather(u,v);
```



See Also

compass, LineSpec, rose

TriRep.featureEdges

Purpose

Sharp edges of surface triangulation

Syntax

FE = featureEdges(TR, filterangle)

Description

FE = featureEdges(TR, filterangle) returns an edge matrix FE. This method is typically used to extract the sharp edges in the surface mesh for the purpose of display. Edges that are shared by only one triangle and edges that are shared by more than two triangles are considered to be feature edges by default.

Note This query is only applicable to triangular surface meshes.

Input Arguments

TR

Triangulation representation.

filterangle

The threshold angle in radians. Must be in the range $(0,\pi)$. featureEdges will return adjacent triangles that have a dihedral angle that deviates from π by an angle greater than filterangle.

Output Arguments

FΕ

Edges of the triangulation. FE is of size m-by-2 where m is the number of computed feature edges in the mesh. The vertices of the edges index into the array of points representing the vertex coordinates, TR.X.

Examples

Create a surface triangulation:


```
x = [0 0 0 0 0 3 3 3 3 3 3 3 6 6 6 6 6 9 9 9 9 9 9 9]';
y = [0 2 4 6 8 0 1 3 5 7 8 0 2 4 6 8 0 1 3 5 7 8]';
dt = DelaunayTri(x,y);
tri = dt(:,:);
```

Elevate the 2-D mesh to create a surface:

Compute the feature edges using a filter angle of pi/6:

Add the feature edges to the plot:

```
hold on;
plot3(x(fe), y(fe), z(fe), 'k', 'LineWidth',1.5);
hold off;
% TRISURF display of surface mesh
% suppressing mesh edges
% and showing feature edges
```



See Also

edges DelaunayTri

Test for end-of-file

Syntax

status = feof(fileID)

Description

status = feof(fileID) returns 1 if a previous operation set the
end-of-file indicator for the specified file. Otherwise, feof returns 0.
fileID is an integer file identifier obtained from fopen.

Opening an empty file does *not* set the end-of-file indicator. Read operations, and the fseek and frewind functions, move the file position indicator.

Examples

Read bench.dat, which contains MATLAB benchmark data, one character at a time:

```
fid = fopen('bench.dat');
k = 0;
while ~feof(fid)
    curr = fscanf(fid,'%c',1);
    if ~isempty(curr)
        k = k+1;
        benchstr(k) = curr;
    end
end
fclose(fid);
```

See Also

fclose | ferror | fopen | frewind | fseek | ftell

How To

• "Testing for End of File (EOF)"

Information about file I/O errors

Syntax

```
message = ferror(fileID)
[message, errnum] = ferror(fileID)
[...] = ferror(fileID, 'clear')
```

Description

message = ferror(fileID) returns the error message for the most recent file I/O operation on the specified file. If the operation was successful, message is an empty string. fileID is an integer file identifier obtained from fopen, or an identifier reserved for standard input (0), standard output (1), or standard error (2).

[message, errnum] = ferror(fileID) returns the error number. If the most recent file I/O operation was successful, errnum is 0. Negative error numbers correspond to MATLAB error messages. Positive error numbers correspond to C library error messages for your system.

[...] = ferror(fileID, 'clear') clears the error indicator for the specified file.

See Also

fclose | fopen

Evaluate function

Syntax

```
[y1, y2, ...] = feval(fhandle, x1, ..., xn)

[y1, y2, ...] = feval(fname, x1, ..., xn)
```

Description

[y1, y2, ...] = feval(fhandle, x1, ..., xn) evaluates the function handle, fhandle, using arguments x1 through xn. If the function handle is bound to more than one built-in or .m function, (that is, it represents a set of overloaded functions), then the data type of the arguments x1 through xn determines which function is dispatched to.

Note It is not necessary to use feval to call a function by means of a function handle. This is explained in in the MATLAB Programming Fundamentals documentation.

[y1, y2, ...] = feval(fname, x1, ..., xn). If fname is a quoted string containing the name of a function (usually defined within file having a .m file extension), then feval(fname, x1, ..., xn) evaluates that function at the given arguments. The fname parameter must be a simple function name; it cannot contain path information.

Remarks

The following two statements are equivalent.

```
[V,D] = eig(A)

[V,D] = feval(@eig, A)
```

Nested functions are not accessible to feval. To call a nested function, you must either call it directly by name, or construct a function handle for it using the @ operator.

Examples

The following example passes a function handle, fhandle, in a call to fminbnd. The fhandle argument is a handle to the humps function.

```
fhandle = @humps;
x = fminbnd(fhandle, 0.3, 1);
```

The fminbnd function uses feval to evaluate the function handle that was passed in.

See Also

assignin, function handle, functions, builtin, eval, evalin

Evaluate MATLAB function in Automation server

Syntax

MATLAB Client

```
result = h.Feval('functionname', numout, arg1, arg2, ...)
result = Feval(h, 'functionname', numout, arg1, arg2, ...)
result = invoke(h, 'Feval', 'functionname', numout, ...
arg1, arg2, ...)
```

IDL Method Signature

HRESULT Feval([in] BSTR functionname, [in] long nargout, [out] VARIANT* result, [in, optional] VARIANT arg1, arg2, ...)

Microsoft Visual Basic Client

Feval(String functionname, long numout, arg1, arg2, ...) As Object

Description

Feval executes the MATLAB function specified by the string functionname in the Automation server attached to handle h.

Indicate the number of outputs to be returned by the function in a 1-by-1 double array, numout. The server returns output from the function in the cell array, result.

You can specify as many as 32 input arguments to be passed to the function. These arguments follow numout in the Feval argument list. The following table shows ways to pass an argument.

Passing Mechanism	Description
Pass the value itself	To pass any numeric or string value, specify the value in the Feval argument list:
	a = h.Feval('sin', 1, -pi:0.01:pi);
Pass a client variable	To pass an argument assigned to a variable in the client, specify the variable name alone: x = -pi:0.01:pi; a = h.Feval('sin', 1, x);

Passing Mechanism	Description
Reference a server variable	To reference a variable defined in the server, specify the variable name followed by an equals (=) sign:
	<pre>h.PutWorkspaceData('x', 'base', -pi:0.01:pi); a = h.Feval('sin', 1, 'x=');</pre>
	MATLAB does not reassign the server variable.

Remarks

To display the output from Feval in the client window, assign a return value.

Server function names, like Feval, are case sensitive when using the first two syntaxes shown in the Syntax section.

COM functions are available on Microsoft Windows systems only.

Examples

Passing Arguments — MATLAB Client

This section contains a number of examples showing how to use Feval to execute MATLAB commands on a MATLAB Automation server.

• Concatenate two strings in the server by passing the input strings in a call to strcat through Feval (strcat deletes trailing spaces; use leading spaces):

```
h = actxserver('matlab.application');
a = h.Feval('strcat', 1, 'hello', ' world')

MATLAB displays:
a =
    'hello world'
```

• Perform the same concatenation, passing a string and a local variable clistr that contains the second string:

```
clistr = ' world';
```

```
a = h.Feval('strcat', 1, 'hello', clistr)
MATLAB displays:
    a =
        'hello world'
```

 In this example, the variable srvstr is defined in the server, not the client. Putting an equals sign after a variable name (for example, srvstr=) indicates it is a server variable, and the variable is not defined in the client:

```
% Define the variable srvstr on the server.
h.PutCharArray('srvstr', 'base', 'world')

% Pass the name of the server variable using 'name=' syntax
a = h.Feval('strcat', 1, 'hello', 'srvstr=')

MATLAB displays:
a =
    'hello world'
```

Visual Basic .NET Client

Here are the same examples shown above, but written for a Visual Basic .NET client. These examples return the same strings as shown above.

• Pass the two strings to the MATLAB function streat on the server:

```
Dim Matlab As Object
Dim out As Object
out = Nothing
Matlab = CreateObject("matlab.application")
Matlab.Feval("strcat", 1, out, "hello", " world")
```

• Define clistr locally and pass this variable:

```
Dim clistr As String
```

```
clistr = " world"
Matlab.Feval("strcat", 1, out, "hello", clistr)
```

• Pass the name of a variable defined on the server:

```
Matlab.PutCharArray("srvstr", "base", " world")
Matlab.Feval("strcat", 1, out, "hello", "srvstr=")
```

Feval Return Values — MATLAB Client. Feval returns data from the evaluated function in a cell array. The cell array has one row for every return value. You control the number of return values using the numout argument.

The numout argument in the following example specifies that Feval return three outputs from the fileparts function.

```
a = h.Feval('fileparts', 3, 'd:\work\ConsoleApp.cpp')
MATLAB displays:
a =
    'd:\work'
    'ConsoleApp'
    '.cpp'
```

Convert the returned values from the cell array \boldsymbol{a} to char arrays:

```
a{:}
MATLAB displays:
ans =
d:\work
ans =
ConsoleApp
```

ans =
.cpp

Feval Return Values - Visual Basic .NET Client

Here is the same example, but coded in Visual Basic. Define the argument returned by Feval as an Object.

```
Dim Matlab As Object
Dim out As Object
Matlab = CreateObject("matlab.application")
Matlab.Feval("fileparts", 3, out, "d:\work\ConsoleApp.cpp")
```

See Also

Execute, PutFullMatrix, GetFullMatrix, PutCharArray, GetCharArray

Discrete Fourier transform

Syntax

Definition

The functions Y=fft(x) and y=ifft(X) implement the transform and inverse transform pair given for vectors of length N by:

$$X(k) = \sum_{j=1}^{N} x(j) \omega_N^{(j-1)(k-1)}$$

$$x(j) = (1/N) \sum_{k=1}^{N} X(k) \omega_N^{-(j-1)(k-1)}$$

where

$$\omega_N \,=\, e^{\,(-2\pi i\,)/N}$$

is an Nth root of unity.

Description

Y = fft(X) returns the discrete Fourier transform (DFT) of vector X, computed with a fast Fourier transform (FFT) algorithm.

If X is a matrix, fft returns the Fourier transform of each column of the matrix.


If X is a multidimensional array, fft operates on the first nonsingleton dimension.

Y = fft(X,n) returns the n-point DFT. If the length of X is less than n, X is padded with trailing zeros to length n. If the length of X is greater than n, the sequence X is truncated. When X is a matrix, the length of the columns are adjusted in the same manner.

Y = fft(X,[],dim) and Y = fft(X,n,dim) applies the FFT operation across the dimension dim.


Examples

A common use of Fourier transforms is to find the frequency components of a signal buried in a noisy time domain signal. Consider data sampled at 1000 Hz. Form a signal containing a 50 Hz sinusoid of amplitude 0.7 and 120 Hz sinusoid of amplitude 1 and corrupt it with some zero-mean random noise:



It is difficult to identify the frequency components by looking at the original signal. Converting to the frequency domain, the discrete Fourier transform of the noisy signal y is found by taking the fast Fourier transform (FFT):

```
NFFT = 2^nextpow2(L); % Next power of 2 from length of y
Y = fft(y,NFFT)/L;
f = Fs/2*linspace(0,1,NFFT/2+1);
% Plot single-sided amplitude spectrum.
plot(f,2*abs(Y(1:NFFT/2+1)))
title('Single-Sided Amplitude Spectrum of y(t)')
xlabel('Frequency (Hz)')
ylabel('|Y(f)|')
```



The main reason the amplitudes are not exactly at 0.7 and 1 is because of the noise. Several executions of this code (including recomputation of y) will produce different approximations to 0.7 and 1. The other reason is that you have a finite length signal. Increasing L from 1000 to

10000 in the example above will produce much better approximations on average.

Algorithm

The FFT functions (fft, fft2, fftn, ifft, ifft2, ifftn) are based on a library called FFTW [3],[4]. To compute an N-point DFT when N is composite (that is, when $N = N_1 N_2$), the FFTW library decomposes the problem using the Cooley-Tukey algorithm [1], which first computes N_1 transforms of size N_2 , and then computes N_2 transforms of size N_2 . The decomposition is applied recursively to both the N_1 - and N_2 -point DFTs until the problem can be solved using one of several machine-generated fixed-size "codelets." The codelets in turn use several algorithms in combination, including a variation of Cooley-Tukey [5], a prime factor algorithm [6], and a split-radix algorithm [2]. The particular factorization of N is chosen heuristically.

When N is a prime number, the FFTW library first decomposes an N-point problem into three (N-1)-point problems using Rader's algorithm [7]. It then uses the Cooley-Tukey decomposition described above to compute the (N-1)-point DFTs.

For most N, real-input DFTs require roughly half the computation time of complex-input DFTs. However, when N has large prime factors, there is little or no speed difference.

The execution time for fft depends on the length of the transform. It is fastest for powers of two. It is almost as fast for lengths that have only small prime factors. It is typically several times slower for lengths that are prime or which have large prime factors.

Note You might be able to increase the speed of fft using the utility function fftw, which controls the optimization of the algorithm used to compute an FFT of a particular size and dimension.

Data Type Support

fft supports inputs of data types double and single. If you call fft with the syntax y = fft(X, ...), the output y has the same data type as the input X.

See Also

fft2, fftn, fftw, fftshift, ifft

dftmtx, filter, and freqz in the Signal Processing Toolbox

References

- [1] Cooley, J. W. and J. W. Tukey, "An Algorithm for the Machine Computation of the Complex Fourier Series," *Mathematics of Computation*, Vol. 19, April 1965, pp. 297-301.
- [2] Duhamel, P. and M. Vetterli, "Fast Fourier Transforms: A Tutorial Review and a State of the Art," *Signal Processing*, Vol. 19, April 1990, pp. 259-299.
- [3] FFTW (http://www.fftw.org)
- [4] Frigo, M. and S. G. Johnson, "FFTW: An Adaptive Software Architecture for the FFT," *Proceedings of the International Conference on Acoustics, Speech, and Signal Processing*, Vol. 3, 1998, pp. 1381-1384.
- [5] Oppenheim, A. V. and R. W. Schafer, *Discrete-Time Signal Processing*, Prentice-Hall, 1989, p. 611.
- [6] Oppenheim, A. V. and R. W. Schafer, *Discrete-Time Signal Processing*, Prentice-Hall, 1989, p. 619.
- [7] Rader, C. M., "Discrete Fourier Transforms when the Number of Data Samples Is Prime," *Proceedings of the IEEE*, Vol. 56, June 1968, pp. 1107-1108.

2-D discrete Fourier transform

Syntax

Y = fft2(X)Y = fft2(X,m,n)

Description

Y = fft2(X) returns the two-dimensional discrete Fourier transform (DFT) of X, computed with a fast Fourier transform (FFT) algorithm. The result Y is the same size as X.

Y = fft2(X,m,n) truncates X, or pads X with zeros to create an m-by-n array before doing the transform. The result is m-by-n.

Algorithm

fft2(X) can be simply computed as

fft(fft(X).').'

This computes the one-dimensional DFT of each column X, then of each row of the result. The execution time for fft depends on the length of the transform. It is fastest for powers of two. It is almost as fast for lengths that have only small prime factors. It is typically several times slower for lengths that are prime or which have large prime factors.

Note You might be able to increase the speed of fft2 using the utility function fftw, which controls how MATLAB software optimizes the algorithm used to compute an FFT of a particular size and dimension.

Data Type Support

fft2 supports inputs of data types double and single. If you call fft2 with the syntax y = fft2(X, ...), the output y has the same data type as the input X.

See Also

 ${\tt fft,\,fftn,\,fftw,\,fftshift,\,ifft2}$

N-D discrete Fourier transform

Syntax

```
Y = fftn(X)
Y = fftn(X,siz)
```

Description

Y = fftn(X) returns the discrete Fourier transform (DFT) of X, computed with a multidimensional fast Fourier transform (FFT) algorithm. The result Y is the same size as X.

Y = fftn(X,siz) pads X with zeros, or truncates X, to create a multidimensional array of size siz before performing the transform. The size of the result Y is siz.

Algorithm

fftn(X) is equivalent to

```
Y = X;
for p = 1:length(size(X))
    Y = fft(Y,[],p);
end
```

This computes in-place the one-dimensional fast Fourier transform along each dimension of X. The execution time for fft depends on the length of the transform. It is fastest for powers of two. It is almost as fast for lengths that have only small prime factors. It is typically several times slower for lengths that are prime or which have large prime factors.

Note You might be able to increase the speed of fftn using the utility function fftw, which controls the optimization of the algorithm used to compute an FFT of a particular size and dimension.

Data Type Support

fftn supports inputs of data types double and single. If you call fftn with the syntax y = fftn(X, ...), the output y has the same data type as the input X.

fftn

See Also

fft, fft2, fftn, fftw, ifftn

Shift zero-frequency component to center of spectrum


Syntax

Y = fftshift(X) Y = fftshift(X,dim)

Description

Y = fftshift(X) rearranges the outputs of fft, fft2, and fftn by moving the zero-frequency component to the center of the array. It is useful for visualizing a Fourier transform with the zero-frequency component in the middle of the spectrum.


For vectors, fftshift(X) swaps the left and right halves of X. For matrices, fftshift(X) swaps the first quadrant with the third and the second quadrant with the fourth.




For higher-dimensional arrays, fftshift(X) swaps "half-spaces" of X along each dimension.

Y = fftshift(X,dim) applies the fftshift operation along the dimension dim.

For dim = 1:



For dim = 2:



Note ifftshift will undo the results of fftshift. If the matrix X contains an odd number of elements, ifftshift(fftshift(X)) must be done to obtain the original X. Simply performing fftshift(X) twice will not produce X.

Examples

For any matrix X

$$Y = fft2(X)$$

has Y(1,1) = sum(sum(X)); the zero-frequency component of the signal is in the upper-left corner of the two-dimensional FFT. For

```
Z = fftshift(Y)
```

this zero-frequency component is near the center of the matrix.

The difference between fftshift and ifftshift is important for input sequences of odd-length.

```
N = 5;
X = 0:N-1;
Y = fftshift(fftshift(X));
Z = ifftshift(fftshift(X));
```

Notice that Z is a correct replica of X, but Y is not.

```
isequal(X,Y),isequal(X,Z)
ans =
     0
ans =
     1
```

See Also

circshift, fft, fft2, fftn, ifftshift

Interface to FFTW library run-time algorithm tuning control

Syntax

```
fftw('planner', method)
method = fftw('planner')
str = fftw('dwisdom')
str = fftw('swisdom')
fftw('dwisdom', str)
fftw('swisdom', str)
```

Description

fftw enables you to optimize the speed of the MATLAB FFT functions fft, ifft, fft2, ifft2, fftn, and ifftn. You can use fftw to set options for a tuning algorithm that experimentally determines the fastest algorithm for computing an FFT of a particular size and dimension at run time. MATLAB software records the optimal algorithm in an internal data base and uses it to compute FFTs of the same size throughout the current session. The tuning algorithm is part of the FFTW library that MATLAB software uses to compute FFTs.

fftw('planner', method) sets the method by which the tuning algorithm searches for a good FFT algorithm when the dimension of the FFT is not a power of 2. You can specify method to be one of the following. The default method is estimate:

- 'estimate'
- 'measure'
- 'patient'
- 'exhaustive'
- 'hybrid'

When you call fftw('planner', method), the next time you call one of the FFT functions, such as fft, the tuning algorithm uses the specified method to optimize the FFT computation. Because the tuning involves trying different algorithms, the first time you call an FFT function, it might run more slowly than if you did not call fftw. However,

subsequent calls to any of the FFT functions, for a problem of the same size, often run more quickly than they would without using fftw.

Note The FFT functions only use the optimal FFT algorithm during the current MATLAB session. "Reusing Optimal FFT Algorithms" on page 2-1393 explains how to reuse the optimal algorithm in a future MATLAB session.

If you set the method to 'estimate', the FFTW library does not use run-time tuning to select the algorithms. The resulting algorithms might not be optimal.

If you set the method to 'measure', the FFTW library experiments with many different algorithms to compute an FFT of a given size and chooses the fastest. Setting the method to 'patient' or 'exhaustive' has a similar result, but the library experiments with even more algorithms so that the tuning takes longer the first time you call an FFT function. However, subsequent calls to FFT functions are faster than with 'measure'.

If you set 'planner' to 'hybrid', MATLAB software

- Sets method to 'measure' method for FFT dimensions 8192 or smaller.
- Sets method to 'estimate' for FFT dimensions greater than 8192.

method = fftw('planner') returns the current planner method.

str = fftw('dwisdom') returns the information in the FFTW library's internal double-precision database as a string. The string can be saved and then later reused in a subsequent MATLAB session using the next syntax.

str = fftw('swisdom') returns the information in the FFTW library's
internal single-precision database as a string.

fftw('dwisdom', str) loads fftw wisdom represented by the string str into the FFTW library's internal double-precision wisdom database. fftw('dwisdom','') or fftw('dwisdom',[]) clears the internal wisdom database.

fftw('swisdom', str) loads fftw wisdom represented by the string str into the FFTW library's internal single-precision wisdom database. fftw('swisdom','') or fftw('swisdom',[]) clears the internal wisdom database.

Note on large powers of 2 For FFT dimensions that are powers of 2, between 2^{14} and 2^{22} , MATLAB software uses special preloaded information in its internal database to optimize the FFT computation. No tuning is performed when the dimension of the FTT is a power of 2, unless you clear the database using the command fftw('wisdom', []).

For more information about the FFTW library, see http://www.fftw.org.

Example

Comparison of Speed for Different Planner Methods

The following example illustrates the run times for different settings of planner. The example first creates some data and applies fft to it using the default method, estimate.

```
t=0:.001:5;
x = sin(2*pi*50*t)+sin(2*pi*120*t);
y = x + 2*randn(size(t));
tic; Y = fft(y,1458); toc
Elapsed time is 0.000521 seconds.
```

If you execute the commands

```
tic; Y = fft(y,1458); toc
Elapsed time is 0.000151 seconds.
```

a second time, MATLAB software reports the elapsed time as essentially 0. To measure the elapsed time more accurately, you can execute the command Y = fft(y,1458) 1000 times in a loop.

```
tic; for k=1:1000
Y = fft(y,1458);
end; toc
Elapsed time is 0.056532 seconds.
```

This tells you that it takes on order of 1/10000 of a second to execute fft(y, 1458) a single time.

For comparison, set planner to patient. Since this planner explores possible algorithms more thoroughly than hybrid, the first time you run fft, it takes longer to compute the results.

```
fftw('planner', 'patient')
tic;Y = fft(y,1458);toc
Elapsed time is 0.100637 seconds.
```

However, the next time you call fft, it runs at approximately the same speed as before you ran the method patient.

```
tic;for k=1:1000
Y=fft(y,1458);
end;toc
Elapsed time is 0.057209 seconds.
```

Reusing Optimal FFT Algorithms

In order to use the optimized FFT algorithm in a future MATLAB session, first save the "wisdom" using the command

```
str = fftw('wisdom')
```

You can save str for a future session using the command

```
save str
```

The next time you open a MATLAB session, load str using the command

load str

and then reload the "wisdom" into the FFTW database using the command

fftw('wisdom', str)

See Also

fft, fft2, fftn, ifft, ifft2, ifftn, fftshift.

Purpose

Read line from file, removing newline characters

Syntax

tline = fgetl(fileID)

Description

tline = fgetl(fileID) returns the next line of the specified file,
removing the newline characters. fileID is an integer file identifier
obtained from fopen. tline is a text string unless the line contains only
the end-of-file marker. In this case, tline is the numeric value -1.

fget1 reads characters using the encoding scheme associated with the file. To specify the encoding scheme, use fopen.

Examples

Read and display the file fgetl.m one line at a time:

```
fid = fopen('fgetl.m');
tline = fgetl(fid);
while ischar(tline)
    disp(tline)
    tline = fgetl(fid);
end
fclose(fid);
```

Compare these results to the fgets example, which replaces the calls to fget1 with fgets.

See Also

fclose | ferror | fgets | fopen | fprintf | fread | fscanf | fwrite

How To

· "Testing for EOF with fgetl and fgets"

Purpose

Read line of text from device and discard terminator

Syntax

```
tline = fgetl(obj)
[tline,count] = fgetl(obj)
[tline,count,msg] = fgetl(obj)
```

Description

tline = fgetl(obj) reads one line of text from the device connected to the serial port object, obj, and returns the data to tline. This returned data does not include the terminator with the text line. To include the terminator, use fgets.

[tline,count] = fgetl(obj) returns the number of values read to count, including the terminator.

[tline,count,msg] = fgetl(obj) returns a warning message to msg if the read operation was unsuccessful.

Remarks

Before you can read text from the device, it must be connected to obj with the fopen function. A connected serial port object has a Status property value of open. An error is returned if you attempt to perform a read operation while obj is not connected to the device.

If msg is not included as an output argument and the read operation was not successful, then a warning message is returned to the command line.

The ValuesReceived property value is increased by the number of values read — including the terminator — each time fget1 is issued.

If you use the help command to display help for fgetl, then you need to supply the pathname shown below.

```
help serial/fgetl
```

Rules for Completing a Read Operation with fgetl

A read operation with fget1 blocks access to the MATLAB command line until:

• The terminator specified by the Terminator property is reached.

- The time specified by the Timeout property passes.
- The input buffer is filled.

Example

On a Windows platform, create the serial port object s, connect s to a Tektronix® TDS 210 oscilloscope, and write the RS232? command with the fprintf function. RS232? instructs the scope to return serial port communications settings.

```
s = serial('COM1');
fopen(s)
fprintf(s,'RS232?')
```

Because the default value for the ReadAsyncMode property is continuous, data is automatically returned to the input buffer.

```
s.BytesAvailable
ans =
     17
```

Use fget1 to read the data returned from the previous write operation, and discard the terminator.

```
settings = fgetl(s)
settings =
9600;0;0;NONE;LF
length(settings)
ans =
16
```

Disconnect s from the scope, and remove s from memory and the workspace.

```
fclose(s)
delete(s)
clear s
```

fgetl (serial)

See Also Functions

fgets, fopen

Properties

BytesAvailable, InputBufferSize, ReadAsyncMode, Status, Terminator, Timeout, ValuesReceived

Purpose

Read line from file, keeping newline characters

Syntax

```
tline = fgets(fileID)
tline = fgets(fileID, nchar)
```

Description

tline = fgets(fileID) reads the next line of the specified file, including the newline characters. fileID is an integer file identifier obtained from fopen. tline is a text string unless the line contains only the end-of-file marker. In this case, tline is the numeric value -1. fgets reads characters using the encoding scheme associated with the file. To specify the encoding scheme, use fopen.

tline = fgets(fileID, nchar) returns at most nchar characters of the next line. tline does not include any characters after the newline characters or the end-of-file marker.

Examples

Read and display the file fgets.m. Because fgets keeps newline characters and disp adds a newline character, this code displays the file with double-spacing:

```
fid = fopen('fgets.m');
tline = fgets(fid);
while ischar(tline)
    disp(tline)
    tline = fgets(fid);
end

fclose(fid);
```

Compare these results to the fget1 example, which replaces the calls to fgets with fget1.

See Also

```
fclose | ferror | fgetl | fopen | fprintf | fread | fscanf | fwrite
```

How To

· "Testing for EOF with fgetl and fgets"

Purpose

Read line of text from device and include terminator

Syntax

```
tline = fgets(obj)
[tline,count] = fgets(obj)
[tline,count,msg] = fgets(obj)
```

Description

tline = fgets(obj) reads one line of text from the device connected to the serial port object, obj, and returns the data to tline. This returned data includes the terminator with the text line. To exclude the terminator, use fgetl.

[tline,count] = fgets(obj) returns the number of values read to count, including the terminator.

[tline,count,msg] = fgets(obj) returns a warning message to msg if the read operation was unsuccessful.

Remarks

Before you can read text from the device, it must be connected to obj with the fopenfunction. A connected serial port object has a Status property value of open. An error is returned if you attempt to perform a read operation while obj is not connected to the device.

If msg is not included as an output argument and the read operation was not successful, then a warning message is returned to the command line.

The ValuesReceived property value is increased by the number of values read — including the terminator — each time fgets is issued.

If you use the help command to display help for fgets, then you need to supply the pathname shown below.

help serial/fgets

Rules for Completing a Read Operation with fgets

A read operation with fgets blocks access to the MATLAB command line until:

• The terminator specified by the Terminator property is reached.

- The time specified by the Timeout property passes.
- The input buffer is filled.

Example

Create the serial port object s, connect s to a Tektronix TDS 210 oscilloscope, and write the RS232? command with the fprintf function. RS232? instructs the scope to return serial port communications settings.

```
s = serial('COM1');
fopen(s)
fprintf(s,'RS232?')
```

Because the default value for the ReadAsyncMode property is continuous, data is automatically returned to the input buffer.

```
s.BytesAvailable
ans =
    17
```

Use fgets to read the data returned from the previous write operation, and include the terminator.

```
settings = fgets(s)
settings =
9600;0;0;NONE;LF
length(settings)
ans =
17
```

Disconnect s from the scope, and remove s from memory and the workspace.

```
fclose(s)
delete(s)
clear s
```

fgets (serial)

See Also Functions

fgetl, fopen

Properties

BytesAvailable, BytesAvailableFcn, InputBufferSize, Status, Terminator, Timeout, ValuesReceived

Purpose

Field names of structure, or public fields of object

Syntax

```
names = fieldnames(s)
names = fieldnames(obj)
names = fieldnames(obj, '-full')
```

Description

names = fieldnames(s) returns a cell array of strings containing the structure field names associated with the structure s.

names = fieldnames(obj) returns a cell array of strings containing field names for obj. If obj is a MATLAB object, then return value names contains the names of the fields in that object. If obj is an object of the Java programming language, then names contains the names of the public fields. MATLAB objects may override fieldnames and define their own behavior.

names = fieldnames(obj, '-full') returns a cell array of strings containing the name, type, attributes, and inheritance of each field associated with obj, which is a COM or Java object. Note that fieldnames does not support the full option for MATLAB objects.

Examples

Given the structure

```
mystr(1,1).name = 'alice';
mystr(1,1).ID = 0;
mystr(2,1).name = 'gertrude';
mystr(2,1).ID = 1
```

the command n = fieldnames(mystr) yields

```
n =
'name'
'ID'
```

In another example, if i is an object of Java class java.awt.Integer, the command fieldnames(i) lists the properties of i.

```
i = java.lang.Integer(0);
```

fieldnames

```
fieldnames(i)

MATLAB displays:

ans =
    'MIN_VALUE'
    'MAX_VALUE'
    'TYPE'
    'SIZE'
```

See Also

setfield, getfield, isfield, orderfields, rmfield, dynamic field names $\,$

Purpose

Create figure graphics object

Syntax

```
figure
figure('PropertyName',propertyvalue,...)
figure(h)
h = figure(...)
```

Properties

For a list of properties, see Figure Properties.

Description

figure creates figure graphics objects. Figure objects are the individual windows on the screen in which the MATLAB software displays graphical output.

figure creates a new figure object using default property values. This automatically becomes the current figure and raises it above all other figures on the screen until a new figure is either created or called.

figure ('*PropertyName*', propertyvalue,...) creates a new figure object using the values of the properties specified. For a description of the properties, see Figure Properties. MATLAB uses default values for any properties that you do not explicitly define as arguments.

figure(h) does one of two things, depending on whether or not a figure with handle h exists. If h is the handle to an existing figure, figure(h) makes the figure identified by h the current figure, makes it visible, and raises it above all other figures on the screen. The current figure is the target for graphics output. If h is not the handle to an existing figure, but is an integer, figure(h) creates a figure and assigns it the handle h. figure(h) where h is not the handle to a figure, and is not an integer, is an error.

h = figure(...) returns the handle to the figure object.

Remarks

To create a figure object, MATLAB creates a new window whose characteristics are controlled by default figure properties (both factory installed and user defined) and properties specified as arguments. See Figure Properties for a description of these properties.

You can specify properties as property name/property value pairs, structure arrays, and cell arrays (see the set and get reference pages for examples of how to specify these data types).

Use set to modify the properties of an existing figure or get to query the current values of figure properties.

The gcf command returns the handle to the current figure and is useful as an argument to the set and get commands.

Figures can be docked in the desktop. The DockControls property determines whether you can dock the figure.

Making a Figure Current

The current figure is the target for graphics output. There are two ways to make a figure h the current figure.

 Make the figure h current, visible, and displayed on top of other figures:

```
figure(h)
```

• Make the figure h current, but do not change its visibility or stacking with respect to other figures:

```
set(0, 'CurrentFigure',h)
```

Examples Specifying Figure Size and Screen Location

To create a figure window that is one quarter the size of your screen and is positioned in the upper left corner, use the root object's ScreenSize property to determine the size. ScreenSize is a four-element vector: [left, bottom, width, height]:

```
scrsz = get(0, 'ScreenSize');
figure('Position',[1 scrsz(4)/2 scrsz(3)/2 scrsz(4)/2])
```

To position the full figure window including the menu bar, title bar, tool bars, and outer edges, use the OuterPosition property in the same manner.

Specifying the Figure Window Title

You can add your own title to a figure by setting the Name property and you can turn off the figure number with the NumberTitle property:

figure('Name', 'Simulation Plot Window', 'NumberTitle', 'off')

See Figure Properties for a description of all properties.

Setting Default Properties

You can set default figure properties only on the root object level.

set(0, 'DefaultFigureProperty', PropertyValue...)

where *Property* is the name of the figure property and PropertyValue is the value you are specifying. Use set and get to access figure properties.

See Also

axes, close, clf, gcf, ishghandle ,rootobject, uicontrol, uimenu

Figure Properties for descriptions of all figure properties

"Object Creation" on page 1-104 for related functions

Tutorials

For more information on figures, see "Figure Properties" in the

MATLAB Graphics User Guide.

Purpose

Define figure properties

Creating Figure Objects

Use figure to create figure objects.

Modifying Properties

You can set and query graphics object properties in two ways:

- "The Property Editor" is an interactive tool that enables you to see and change object property values.
- The set and get commands enable you to set and query the values of Handle Graphics properties.

To change the default values of properties, see "Setting Default Property Values" in the Handle Graphics Objects documentation.

Figure Property Descriptions

This section lists property names along with the type of values each accepts. Curly braces {} enclose default values.

Alphamap

m-by-1 matrix of alpha values

Figure alphamap. This property is an m-by-1 array of non-NaN alpha values. MATLAB accesses alpha values by their row number. For example, an index of 1 specifies the first alpha value, an index of 2 specifies the second alpha value, and so on. Alphamaps can be any length. The default alphamap contains 64 values that progress linearly from 0 to 1.

Alphamaps affect the rendering of surface, image, and patch objects, but do not affect other graphics objects.

BeingDeleted

on | {off} read only

This object is being deleted. The BeingDeleted property provides a mechanism that you can use to determine if objects are in the process of being deleted. MATLAB sets the BeingDeleted property to on when the object's delete function callback is called (see the DeleteFcn property). It remains set to on while the delete function executes, after which the object no longer exists.

For example, an object's delete function might call other functions that act on a number of different objects. These functions may not need to perform actions on objects that are going to be deleted, and therefore, can check the object's BeingDeleted property before acting.

See the close and delete function reference pages for related information.

BusyAction cancel | {queue}

Callback function interruption. The BusyAction property enables you to control how MATLAB handles events that potentially interrupt executing callback functions. If there is a callback function executing, callback functions invoked subsequently always attempt to interrupt it. If the Interruptible property of the object whose callback is executing is set to on (the default), then interruption occurs at the next point where the event queue is processed. If the Interruptible property is off, the BusyAction property (of the object owning the executing callback) determines how MATLAB handles the event. The choices are

- cancel Discard the event that attempted to execute a second callback function.
- queue Queue the event that attempted to execute a second callback function until the current callback finishes.

ButtonDownFcn

function handle, cell array containing function handle and additional arguments, or string (not recommended)

Button press callback function. A callback function that executes whenever you press a mouse button while the pointer is in the figure window, but not over a child object (i.e., uicontrol, uipanel, axes, or axes child). Define the ButtonDownFcn as a function handle. The function must define at least two input arguments (handle of figure associated with the mouse button press and an empty event structure)

See the figure's SelectionType property to determine whether modifier keys were also pressed.

See "Function Handle Callbacks" for information on how to use function handles to define the callback function.

Using the ButtonDownFcn

This example creates a figure and defines a function handle callback for the ButtonDownFcn property. When the user **Ctrl**-clicks the figure, the callback creates a new figure having the same callback.

Click to view in editor — This link opens the MATLAB Editor with the following example.

Click to run example — **Ctrl**-click the figure to create a new figure.

```
fh_cb = @newfig; % Create function handle for newfig function
figure('ButtonDownFcn',fh_cb);

function newfig(src,evnt)
   if strcmp(get(src,'SelectionType'),'alt')
      figure('ButtonDownFcn',fh_cb)
   else
      disp('Use control-click to create a new figure')
   end
end
```

Children.

vector of handles

Children of the figure. A vector containing the handles of all axes, user-interface objects displayed within the figure. You can change the order of the handles and thereby change the stacking of the objects on the display.

When an object's HandleVisibility property is set to off, it is not listed in its parent's Children property. See HandleVisibility for more information.

Clipping

{on} | off

This property has no effect on figures.

CloseRequestFcn

function handle, cell array containing function handle and additional arguments, or string (not recommended)

Function executed on figure close. This property defines a function that MATLAB executes whenever you issue the close command (either a close (figure_handle) or a close all), when you close a figure window from the computer's window manager menu, or when you quit MATLAB.

The CloseRequestFcn provides a mechanism to intervene in the closing of a figure. It allows you to, for example, display a dialog box to ask a user to confirm or cancel the close operation or to prevent users from closing a figure that contains a GUI.

The basic mechanism is:

• A user issues the close command from the command line, by closing the window from the computer's window manager menu, or by quitting MATLAB.

 The close operation executes the function defined by the figure CloseRequestFcn. The default function is named closereq and is predefined as

These statements unconditionally delete the current figure, destroying the window. closereq takes advantage of the fact that the close command makes all figures specified as arguments the current figure before calling the respective close request function.

Note that closered honors the user's ShowHiddenHandles setting during figure deletion and will not delete hidden figures.

Redefining the CloseRequestFcn

Define the CloseRequestFcn as a function handle. For example,

```
set(gcf, 'CloseRequestFcn',@my_closefcn)
```

Where $\ensuremath{\texttt{Qmy_closefcn}}$ is a function handle referencing function $\ensuremath{\texttt{my_closefcn}}$.

Unless the close request function calls delete or close, MATLAB never closes the figure. (Note that you can always call delete(figure_handle) from the command line if you have created a window with a nondestructive close request function.)

A useful application of the close request function is to display a question dialog box asking the user to confirm the close operation. The following function illustrates how to do this.

Click to view in editor — This link opens the MATLAB editor with the following example.

Click to run example — **Ctrl**-click the figure to create a new figure.

```
function my_closereq(src,evnt)
% User-defined close request function
% to display a question dialog box
    selection = questdlg('Close This Figure?',...
        'Close Request Function',...
        'Yes','No','Yes');
    switch selection,
        case 'Yes',
            delete(gcf)
        case 'No'
        return
    end
end
```

Now create a figure using the CloseRequestFcn:

```
figure('CloseRequestFcn',@my_closereq)
```

To make this function your default close request function, set a default value on the root level.

```
set(0, 'DefaultFigureCloseRequestFcn',@my_closereq)
```

MATLAB then uses this setting for the CloseRequestFcn of all subsequently created figures.

See "Function Handle Callbacks" for information on how to use function handles to define the callback function.

Color

ColorSpec

Background color. This property controls the figure window background color. You can specify a color using a three-element vector of RGB values or one of the MATLAB predefined names. See ColorSpec for more information.

Colormap

m-by-3 matrix of RGB values

Figure colormap. This property is an m-by-3 array of red, green, and blue (RGB) intensity values that define m individual colors. MATLAB accesses colors by their row number. For example, an index of 1 specifies the first RGB triplet, an index of 2 specifies the second RGB triplet, and so on.

Number of Colors Allowed

Colormaps can be any length (up to 256 only on Microsoft Windows), but must be three columns wide. The default figure colormap contains 64 predefined colors.

Objects That Use Colormaps

Colormaps affect the rendering of surface, image, and patch objects, but generally do not affect other graphics objects. See colormap and ColorSpec for more information.

CreateFcn

function handle, cell array containing function handle and additional arguments, or string (not recommended)

Callback function executed during figure creation. This property defines a callback function that executes when MATLAB creates a figure object. You must define this property as a default value on the root level. For example, the statement

```
set(0, 'DefaultFigureCreateFcn',@fig create)
```

defines a default value on the root level that causes all figures created to execute the setup function fig_create, which is defined below:

```
function fig_create(src,evnt)
set(src,'Color',[.2 .1 .5],...
   'IntegerHandle','off',...
   'MenuBar','none',...
   'ToolBar','none')
end
```

MATLAB executes the create function after setting all properties for the figure. Setting this property on an existing figure object has no effect.

See "Function Handle Callbacks" for information on how to use function handles to define the callback function.

The handle of the object whose CreateFcn is being executed is accessible only through the root CallbackObject property, which you can query using gcbo.

CurrentAxes

handle of current axes

Target axes in this figure. MATLAB sets this property to the handle of the figure's current axes (i.e., the handle returned by the gca command when this figure is the current figure). In all figures for which axes children exist, there is always a current axes. The current axes does not have to be the topmost axes, and setting an axes to be the CurrentAxes does not restack it above all other axes.

You can make an axes current using the axes and set commands. For example, axes(axes_handle) and set(gcf,'CurrentAxes',axes_handle) both make the axes

identified by the handle axes_handle the current axes. In addition, axes(axes_handle) restacks the axes above all other axes in the figure.

If a figure contains no axes, get(gcf, 'CurrentAxes') returns the empty matrix. Note that the gca function actually creates an axes if one does not exist.

CurrentCharacter

single character

Last key pressed. MATLAB sets this property to the last key pressed in the figure window. CurrentCharacter is useful for obtaining user input.

CurrentObject

object handle

Handle of current object. MATLAB sets this property to the handle of the last object clicked on by the mouse. This object is the frontmost object in the view. You can use this property to determine which object a user has selected. The function gco provides a convenient way to retrieve the CurrentObject of the CurrentFigure.

Note that the HitTest property controls whether an object can become the CurrentObject.

Hidden Handle Objects

Clicking an object whose HandleVisibility property is set to off (such as axis labels and title) causes the CurrentObject property to be set to empty []. To avoid returning an empty value when users click hidden objects, set the hidden object's HitTest property to off.

Mouse Over

Note that cursor motion over objects does not update the CurrentObject; you must click objects to update this property. See the CurrentPoint property for related information.

CurrentPoint

two-element vector: [x-coordinate, y-coordinate]

Location of last button click in this figure. MATLAB sets this property to the location of the pointer at the time of the most recent mouse button press. MATLAB updates this property whenever you press the mouse button while the pointer is in the figure window.

Note that if you select a point in the figure and then use the values returned by the CurrentPoint property to plot that point, there can be differences in the position due to round-off errors.

CurrentPoint and Cursor Motion

In addition to the behavior described above, MATLAB updates CurrentPoint before executing callback routines defined for the figure WindowButtonMotionFcn and WindowButtonUpFcn properties. This enables you to query CurrentPoint from these callback routines. It behaves like this:

- If there is no callback routine defined for the WindowButtonMotionFcn or the WindowButtonUpFcn, then MATLAB updates the CurrentPoint only when the mouse button is pressed down within the figure window.
- If there is a callback routine defined for the WindowButtonMotionFcn, then MATLAB updates the CurrentPoint just before executing the callback. Note that the WindowButtonMotionFcn executes only within the figure window unless the mouse button is pressed down within the window and then held down while the pointer is moved around the screen. In this case, the routine executes (and the

CurrentPoint is updated) anywhere on the screen until the mouse button is released.

• If there is a callback routine defined for the WindowButtonUpFcn, MATLAB updates the CurrentPoint just before executing the callback. Note that the WindowButtonUpFcn executes only while the pointer is within the figure window unless the mouse button is pressed down initially within the window. In this case, releasing the button anywhere on the screen triggers callback execution, which is preceded by an update of the CurrentPoint.

The figure CurrentPoint is updated only when certain events occur, as previously described. In some situations (such as when the WindowButtonMotionFcn takes a long time to execute and the pointer is moved very rapidly), the CurrentPoint may not reflect the actual location of the pointer, but rather the location at the time when the WindowButtonMotionFcn began execution.

The CurrentPoint is measured from the lower-left corner of the figure window, in units determined by the Units property.

The root PointerLocation property contains the location of the pointer updated synchronously with pointer movement. However, the location is measured with respect to the screen, not a figure window.

See uicontrol for information on how this property is set when you click a uicontrol object.

DeleteFcn

function handle, cell array containing function handle and additional arguments, or string (not recommended)

Delete figure callback function. A callback function that executes when the figure object is deleted (for example, when you issue a delete or a close command). MATLAB executes the function before destroying the object's properties so these values are available to the callback routine.

See "Function Handle Callbacks" for information on how to use function handles to define the callback function.

The handle of the object whose DeleteFcn is being executed is accessible through the root CallbackObject property, which you can query using gcbo.

See also the figure CloseRequestFcn property

See "Function Handle Callbacks" for information on how to use function handles to define the callback function.

DockControls {on} | off

Displays controls used to dock figure. This property determines whether the figure enables the **Desktop** menu item and the dock figure button in the title bar that allow you to dock the figure into the MATLAB desktop.

By default, the figure docking controls are visible. If you set this property to off, the **Desktop** menu item that enables you to dock the figure is disabled and the figure dock button is not displayed.

See also the WindowStyle property for more information on docking figure.

DoubleBuffer

{on} | off

Flash-free rendering for simple animations. Double buffering is the process of drawing to an off-screen pixel buffer and then printing the buffer contents to the screen once the drawing is complete. Double buffering generally produces flash-free rendering for simple animations (such as those involving lines, as opposed to objects containing large numbers of polygons). Use double buffering with the animated objects' EraseMode property set to normal. Use the set command to disable double buffering.

```
set(figure handle, 'DoubleBuffer', 'off')
```

Double buffering works only when the figure Renderer property is set to painters.

FileName

String

GUI FIG-filename. GUIDE stores the name of the FIG-file used to save the GUI layout in this property. In non-GUIDE GUIs, by default FileName is empty. You can set the FileName property in non-GUIDE GUIs as well, and get it to verify what GUI is running or whether it has been previously saved.

FixedColors

m-by-3 matrix of RGB values (read only)

Noncolormap colors. Fixed colors define all colors appearing in a figure window that are not from the figure colormap. These colors include axis lines and labels, the colors of line, text, uicontrol, and uimenu objects, and any colors explicitly defined, for example, with a statement like

Fixed color definitions reside in the system color table and do not appear in the figure colormap. For this reason, fixed colors can limit the number of simultaneously displayed colors if the number of fixed colors plus the number of entries in the figure colormap exceed your system's maximum number of colors.

(See the root ScreenDepth property for information on determining the total number of colors supported on your system. See the MinColorMap property for information on how MATLAB shares colors between applications.)

Note The FixedColors property is being deprecated and will be removed in a future release

```
HandleVisibility
     {on} | callback | off
```

Control access to object's handle by command-line users and GUIs. This property determines when an object's handle is visible in its parent's list of children. HandleVisibility is useful for preventing command-line users from accidentally drawing into or deleting a figure that contains only user interface devices (such as a dialog box).

Handles are always visible when HandleVisibility is on.

Callback Visibility

Setting HandleVisibility to callback causes handles to be visible from within callback routines or functions invoked by callback routines, but not from within functions invoked from the command line. This provides a means to protect GUIs from command-line users, while allowing callback routines to have complete access to object handles.

Visibility Off

Setting HandleVisibility to off makes handles invisible at all times. This may be necessary when a callback routine invokes a function that might potentially damage the GUI (such as evaluating a user-typed string), and so temporarily hides its own handles during the execution of that function.

Visibility and Handles Returned by Other Functions

When a handle is not visible in its parent's list of children, it cannot be returned by functions that obtain handles by searching the object hierarchy or querying handle properties. This includes get, findobj, gca, gcf, gco, newplot, cla, clf, and close.

When a handle's visibility is restricted using callback or off, the object's handle does not appear in its parent's Children property, figures do not appear in the root's CurrentFigureproperty, objects do not appear in the root's CallbackObject property or in the figure's CurrentObject property, and axes do not appear in their parent's CurrentAxes property.

Making All Handles Visible

You can set the root ShowHiddenHandles property to on to make all handles visible, regardless of their HandleVisibility settings (this does not affect the values of the HandleVisibility properties).

Validity of Hidden Handles

Handles that are hidden are still valid. If you know an object's handle, you can pass it to any function that operates on handles, and set and get its properties.

```
HitTest
{on} | off
```

Selectable by mouse click. HitTest determines if the figure can become the current object (as returned by the gco command and the figure CurrentObject property) as a result of a mouse click on the figure. If HitTest is off, clicking the figure sets the CurrentObject to the empty matrix.

```
IntegerHandle
     {on} | off
```

Figure handle mode. Figure object handles are integers by default. When creating a new figure, MATLAB uses the lowest integer that is not used by an existing figure. If you delete a figure, its integer handle can be reused.

If you set this property to off, MATLAB assigns nonreusable real-number handles (for example, 67.0001221) instead of integers. This feature is designed for dialog boxes where removing the handle from integer values reduces the likelihood of inadvertently drawing into the dialog box.

Interruptible {on} | off

Callback routine interruption mode. The Interruptible property controls whether a figure callback function can be interrupted by subsequently invoked callbacks.

How Callbacks Are Interrupted

MATLAB checks for queued events that can interrupt a callback function only when it encounters a call to drawnow, figure, getframe, or pause in the executing callback function. When executing one of these functions, MATLAB processes all pending events, including executing all waiting callback functions. The interrupted callback then resumes execution.

What Property Callbacks Are Interruptible

The Interruptible property only affects callback functions defined for the ButtonDownFcn, KeyPressFcn, KeyReleaseFcn, WindowButtonDownFcn, WindowButtonMotionFcn, WindowButtonUpFcn, WindowKeyPressFcn, WindowKeyReleaseFcn, and WindowScrollWheelFcn.

See the BusyAction property for related information.

InvertHardcopy {on} | off

Change hardcopy to black objects on white background. This property affects only printed output. Printing a figure having a background color (Color property) that is not white results in poor contrast between graphics objects and the figure background and also consumes a lot of printer toner.

When InvertHardCopy is on, MATLAB eliminates this effect by changing the color of the figure and axes to white and the axis lines, tick marks, axis labels, etc., to black. lines, text, and the edges of patches and surfaces might be changed, depending on the print command options specified.

If you set InvertHardCopy to off, the printed output matches the colors displayed on the screen.

See print for more information on printing MATLAB figures.

KeyPressFcn

function handle, cell array containing function handle and additional arguments, or string (not recommended)

Key press callback function. This is a callback function invoked by a key press that occurs while the figure window has focus. Define the KeyPressFcn as a function handle. The function must define at least two input arguments (handle of figure associated with key release and an event structure).

See "Function Handle Callbacks" for information on how to use function handles to define the callback function.

When there is no callback specified for this property (which is the default state), MATLAB passes any key presses to the Command Window. However, when you define a callback for this property,

the figure retains focus with each key press and executes the specified callback with each key press.

KeyPressFcn Event Structure

When the callback is a function handle, MATLAB passes a structure to the callback function that contains the following fields.

Field	Contents
Character	The character displayed as a result of the key(s) pressed.
Modifier	This field is a cell array that contains the names of one or more modifier keys that the user pressed (i.e., control , alt , shift). On Macintosh computers, MATLAB can also return 'command' if the user pressed the command modifier key.
Key	The key pressed (lowercase label on key).

Some key combinations do not define a value for the Character field.

Using the KeyPressFcn

This example, creates a figure and defines a function handle callback for the KeyPressFcn property. When the e key is pressed, the callback exports the figure as an EPS file. When Ctrl-t is pressed, the callback exports the figure as a TIFF file.

```
function figure_keypress
figure('KeyPressFcn',@printfig);
function printfig(src,evnt)
   if evnt.Character == 'e'
      print ('-deps',['-f' num2str(src)])
   elseif length(evnt.Modifier) == 1 & strcmp(evnt.Modifier{:},'control') & ...
```

KeyReleaseFcn

function handle, or cell array containing function handle and additional arguments, string (not recommended)

Key release callback function. This is a callback function invoked by a key release that occurs while the figure window has focus. Define the KeyReleaseFcn as a function handle. The function must define at least two input arguments (handle of figure associated with key release and an event structure).

See "Function Handle Callbacks" for information on how to use function handles to define the callback function.

KeyReleaseFcn Event Structure

When the callback is a function handle, MATLAB passes a structure as the second argument to the callback function that contains the following fields.

Field	Contents
Character	The character displayed as a result of the key(s) released.
Modifier	This field is a cell array that contains the names of one or more modifier keys that the user releases (i.e., control , alt , shift , or empty if no modifier keys were released). On Macintosh computers, MATLAB can also return 'command' if the user released the command modifier key.
Key	The lowercase label on key that was released.

Some key combinations do not define a value for the Character field.

Properties Affected by the KeyReleaseFcn

When a callback is defined for the KeyReleaseFcn property, MATLAB updates the CurrentCharacter figure property just before executing the callback.

Multiple-Key Press Events and a Single-Key Release Event

Consider a figure having callbacks defined for both the KeyPressFcn and KeyReleaseFcn. In the case where a user presses multiple keys, one after another, MATLAB generates repeated KeyPressFcn events only for the last key pressed.

For example, suppose you press and hold down the **a** key, then press and hold down the **s** key. MATLAB generates repeated KeyPressFcn events for the **a** key until you press the **s** key, at which point MATLAB generates repeated KeyPressFcn events for the **s** key. If you then release the **s** key, MATLAB generates a KeyReleaseFcn event for the **s** key, but no new KeyPressFcn events for the **a** key. When you then release the **a** key, the KeyReleaseFcn again executes.

The KeyReleaseFcn behavior is such that it executes its callback every time you release a key while the figure is in focus, regardless of what KeyPressFcns MATLAB generates.

Modifier Keys

When the user presses and releases a key and a modifier key, the modifier key is returned in the event structure Modifier field. If a modifier key is the only key pressed and released, it is not returned in the event structure of the KeyReleaseFcn, but is returned in the event structure of the KeyPressFcn.

Explore the Results

Click to view in editor — This link opens the MATLAB editor with the following example.

Click to run example — Press and release various key combinations while the figure has focus to see the data returned in the event structure.

The following code creates a figure and defines a function handle callback for the KeyReleaseFcn property. The callback simply displays the values returned by the event structure and enables you to explore the KeyReleaseFcn behavior when you release various key combinations.

```
function key_releaseFcn
             figure('KeyReleaseFcn',@cb)
                function cb(src,evnt)
                if ~isempty(evnt.Modifier)
                   for ii = 1:length(evnt.Modifier)
                      out = sprintf('Character: %c\nModifier: %s\nKey: %s\n',...
               evnt.Character,evnt.Modifier{ii},evnt.Key);
                      disp(out)
                   end
                else
                   out = sprintf('Character: %c\nModifier: %s\nKey: %s\n',...
              evnt.Character,'No modifier key',evnt.Key);
                   disp(out)
                end
             end
          end
MenuBar
       none | {figure}
```

Enable-disable figure menu bar. This property enables you to display or hide the menu bar that MATLAB places at the top of a figure window. The default (figure) is to display the menu bar.

This property affects only built-in menus. This property does not affect menus defined with the uimenu command.

```
MinColormap
scalar (default = 64)
```

Minimum number of color table entries used. This property specifies the minimum number of system color table entries used by MATLAB to store the colormap defined for the figure (see the ColorMap property). In certain situations, you may need to increase this value to ensure proper use of colors.

For example, suppose you are running color-intensive applications in addition to MATLAB and have defined a large figure colormap (for example, 150 to 200 colors). MATLAB may select colors that are close but not exact from the existing colors in the system color table because there are not enough slots available to define all the colors you specified.

To ensure that MATLAB uses exactly the colors you define in the figure colormap, set MinColorMap equal to the length of the colormap.

```
set(gcf,'MinColormap',length(get(gcf,'ColorMap')))
```

Note that the larger the value of MinColorMap, the greater the likelihood that other windows (including other MATLAB figure windows) will be displayed in false colors.

Note The MinColormap property is being deprecated and will be removed in a future release

Name

string

Figure window title. This property specifies the title displayed in the figure window. By default, Name is empty and the figure title is displayed as Figure 1, Figure 2, and so on. When you set this parameter to a string, the figure title becomes Figure 1: <string>. See the NumberTitle property.

NextPlot

```
new | {add} | replace | replacechildren
```

How to add next plot. NextPlot determines which figure MATLAB uses to display graphics output. If the value of the current figure is

- new Create a new figure to display graphics (unless an existing parent is specified in the graphing function as a property/value pair).
- add Use the current figure to display graphics (the default).
- replace Reset all figure properties except Position to their defaults and delete all figure children before displaying graphics (equivalent to clf reset).
- replacechildren Remove all child objects, but do not reset figure properties (equivalent to clf).

The newplot function provides an easy way to handle the NextPlot property. Also see the NextPlot axes property and "Controlling Graphics Output" for more information.

NumberTitle

```
{on} | off (GUIDE default off)
```

Figure window title number. This property determines whether the string Figure No. N (where N is the figure number) is prefixed to the figure window title. See the Name property.

OuterPosition

four-element vector

Figure position including title bar, menu bar, tool bars, and outer edges. This property specifies the size and location on the screen of the full figure window including the title bar, menu bar, tool bars, and outer edges. Specify the position rectangle with a four-element vector of the form:

```
rect = [left, bottom, width, height]
```

where left and bottom define the distance from the lower-left corner of the screen to the lower-left corner of the full figure window. Width and height define the dimensions of the window. See the Units property for information on the units used in this specification. The left and bottom elements can be negative on systems that have more than one monitor.

Position of Docked Figures

If the figure is docked in the MATLAB desktop, then the OuterPosition property is specified with respect to the figure group container instead of the screen.

Moving and Resizing Figures

Use the get function to obtain this property and determine the position of the figure. Use the set function to resize and move the figure to a new location. You cannot set the figure OuterPosition when it is docked.

Note On Windows systems, figure windows cannot be less than 104 pixels wide, regardless of the value of the OuterPosition property.

PaperOrientation {portrait} | landscape

Horizontal or vertical paper orientation. This property determines how to orient printed figures on the page. portrait orients the longest page dimension vertically; landscape orients the longest page dimension horizontally. See the orient command for more detail.

PaperPosition

four-element rect vector

Location on printed page. A rectangle that determines the location of the figure on the printed page. Specify this rectangle with a vector of the form

```
rect = [left, bottom, width, height]
```

where left specifies the distance from the left side of the paper to the left side of the rectangle and bottom specifies the distance from the bottom of the page to the bottom of the rectangle. Together these distances define the lower-left corner of the rectangle. width and height define the dimensions of the rectangle. The PaperUnits property specifies the units used to define this rectangle.

PaperPositionMode auto | {manual}

WYSIWYG printing of figure. In manual mode, MATLAB honors the value specified by the PaperPosition property. In auto mode, MATLAB prints the figure the same size as it appears on the computer screen, centered on the page.

See Pixels Per Inch Solution at Technical Solutions for information on specifying a pixels per inch resolution setting for MATLAB figures. Doing so might be necessary to obtain a printed figure that is the same size as it is on the screen.

PaperSize

[width height]

Paper size. This property contains the size of the current PaperType, measured in PaperUnits. See PaperType to select standard paper sizes.

PaperType

Select a value from the following table.

Selection of standard paper size. This property sets the PaperSize to one of the following standard sizes.

Property Value	Size (Width x Height)
usletter (default)	8.5-by-11 inches
uslegal	8.5-by-14 inches
tabloid	11-by-17 inches
A0	841-by-1189 mm
A1	594-by-841 mm
A2	420-by-594 mm
A3	297-by-420 mm
A4	210-by-297 mm
A5	148-by-210 mm
В0	1029-by-1456 mm
B1	728-by-1028 mm
B2	514-by-728 mm
В3	364-by-514 mm
B4	257-by-364 mm
B5	182-by-257 mm
arch-A	9-by-12 inches

Property Value	Size (Width x Height)
arch-B	12-by-18 inches
arch-C	18-by-24 inches
arch-D	24-by-36 inches
arch-E	36-by-48 inches
A	8.5-by-11 inches
В	11-by-17 inches
С	17-by-22 inches
D	22-by-34 inches
Е	34-by-43 inches

Note that you may need to change the PaperPosition property in order to position the printed figure on the new paper size. One solution is to use normalized PaperUnits, which enables MATLAB to automatically size the figure to occupy the same relative amount of the printed page, regardless of the paper size.

PaperUnits

```
normalized | {inches} | centimeters | points
```

Hardcopy measurement units. This property specifies the units used to define the PaperPosition and PaperSize properties. MATLAB measures all units from the lower-left corner of the page. normalized units map the lower-left corner of the page to (0, 0) and the upper-right corner to (1.0, 1.0). inches, centimeters, and points are absolute units (one point equals 1/72 of an inch).

If you change the value of PaperUnits, it is good practice to return the property to its default value after completing your computation so as not to affect other functions that assume PaperUnits is set to the default value.

Parent

handle

Handle of figure's parent. The parent of a figure object is the root object object. The handle to the root is always 0.

Pointer

```
crosshair | {arrow} | watch | topl |
topr | botl | botr | circle | cross |
fleur | left | right | top | bottom |
fullcrosshair | ibeam | custom | hand
```

Pointer symbol selection. This property determines the symbol used to indicate the pointer (cursor) position in the figure window. Setting Pointer to custom allows you to define your own pointer symbol. See the PointerShapeCData property and "Specifying the Figure Pointer" for more information.

PointerShapeCData

16-by-16 matrix

User-defined pointer. This property defines the pointer that is used when you set the Pointer property to custom. It is a 16-by-16 element matrix defining the 16-by-16 pixel pointer using the following values:

- 1 Color pixel black.
- 2 Color pixel white.
- NaN Make pixel transparent (underlying screen shows through).

Element (1,1) of the PointerShapeCData matrix corresponds to the upper-left corner of the pointer. Setting the Pointer property to one of the predefined pointer symbols does not change the value of the PointerShapeCData. Computer systems supporting 32-by-32 pixel pointers fill only one quarter of the available pixmap.

PointerShapeHotSpot

two-element vector

Pointer active area. A two-element vector specifying the row and column indices in the PointerShapeCData matrix defining the pixel indicating the pointer location. The location is contained in the CurrentPoint property and the root object's PointerLocation property. The default value is element (1,1), which is the upper-left corner.

Position

four-element vector

Figure position. This property specifies the size and location on the screen of the figure window, not including title bar, menu bar, tool bars, and outer edges. Specify the position rectangle with a four-element vector of the form:

```
rect = [left, bottom, width, height]
```

where left and bottom define the distance from the lower-left corner of the screen to the lower-left corner of the figure window. Width and height define the dimensions of the window. See the Units property for information on the units used in this specification. The left and bottom elements can be negative on systems that have more than one monitor.

Position of Docked Figures

If the figure is docked in the MATLAB desktop, then the Position property is specified with respect to the figure group container instead of the screen.

Moving and Resizing Figures

You can use the get function to obtain this property and determine the position of the figure and you can use the set

function to resize and move the figure to a new location. You cannot set the figure Position when it is docked.

Note On Windows systems, figure windows cannot be less than 104 pixels wide, regardless of the value of the Position property.

Also, the figure window includes the area to which MATLAB can draw; it does not include the title bar, menu bar, tool bars, and outer edges. To place the full window, use the OuterPosition property.

Renderer

painters | zbuffer | OpenGL

Rendering method used for screen and printing. This property enables you to select the method used to render MATLAB graphics. The choices are

- painters The original rendering method used by MATLAB is faster when the figure contains only simple or small graphics objects.
- zbuffer MATLAB draws graphics objects faster and more accurately because it colors objects on a per-pixel basis and MATLAB renders only those pixels that are visible in the scene (thus eliminating front-to-back sorting errors). Note that this method can consume a lot of system memory if MATLAB is displaying a complex scene.
- OpenGL OpenGL is a renderer that is available on many computer systems. This renderer is generally faster than painters or zbuffer and in some cases enables MATLAB to access graphics hardware that is available on some systems.

Hardware vs. Software OpenGL Implementations

There are two kinds of OpenGL implementations — hardware and software.

The hardware implementation uses special graphics hardware to increase performance and is therefore significantly faster than the software version. Many computers have this special hardware available as an option or may come with this hardware right out of the box.

Software implementations of OpenGL are much like the ZBuffer renderer that is available on MATLAB Version 5.0 and later; however, OpenGL generally provides superior performance to ZBuffer.

OpenGL Availability

OpenGL is available on all computers that run MATLAB. MATLAB automatically finds hardware-accelerated versions of OpenGL if such versions are available. If the hardware-accelerated version is not available, then MATLAB uses the software version (except on Macintosh systems, which do not support software OpenGL).

The following software versions are available:

- On UNIX systems, MATLAB uses the software version of OpenGL that is included in the MATLAB distribution.
- On Windows, OpenGL is available as part of the operating system. If you experience problems with OpenGL, contact your graphics driver vendor to obtain the latest qualified version of OpenGL.
- On Macintosh systems, software OpenGL is not available.

MATLAB issues a warning if it cannot find a usable OpenGL library.

Selecting Hardware-Accelerated or Software OpenGL

MATLAB enables you to switch between hardware-accelerated and software OpenGL. However, Windows and UNIX systems behave differently:

- On Windows systems, you can toggle between software and hardware versions any time during the MATLAB session.
- On UNIX systems, you must set the OpenGL version before MATLAB initializes OpenGL. Therefore, you cannot issue the opengl info command or create graphs before you call opengl software. To reenable hardware accelerated OpenGL, you must restart MATLAB.
- On Macintosh systems, software OpenGL is not available.

If you do not want to use hardware OpenGL, but do want to use object transparency, you can issue the following command.

opengl software

This command forces MATLAB to use software OpenGL. Software OpenGL is useful if your hardware-accelerated version of OpenGL does not function correctly and you want to use image, patch, or surface transparency, which requires the OpenGL renderer. To reenable hardware OpenGL, use the command:

opengl hardware

on Windows systems or restart MATLAB on UNIX systems.

By default, MATLAB uses hardware-accelerated OpenGL.

See the opengl reference page for additional information

Determining What Version You Are Using

To determine the version and vendor of the OpenGL library that MATLAB is using on your system, type the following command at the MATLAB prompt:

opengl info

The returned information contains a line that indicates if MATLAB is using software (Software = true) or hardware-accelerated (Software = false) OpenGL.

This command also returns a string of extensions to the OpenGL specification that are available with the particular library MATLAB is using. This information is helpful to The MathWorks, so please include this information if you need to report bugs.

Note that issuing the opengl info command causes MATLAB to initialize OpenGL.

OpenGL vs. Other MATLAB Renderers

There are some differences between drawings created with OpenGL and those created with other renderers. The OpenGL specific differences include

- OpenGL does not do colormap interpolation. If you create a surface or patch using indexed color and interpolated face or edge coloring, OpenGL interpolates the colors through the RGB color cube instead of through the colormap.
- OpenGL does not support the phong value for the FaceLighting and EdgeLighting properties of surfaces and patches.
- OpenGL does not support logarithmic-scale axes.
- OpenGL and Zbuffer renderers display objects sorted in front to back order, as seen on the monitor, and lines always draw in front of faces when at the same location on the plane of the monitor. Painters sorts by child order (order specified).

If You Are Having Problems

Consult the OpenGL Technical Note if you are having problems using OpenGL. This technical note contains a wealth of information on MATLAB renderers.

RendererMode

{auto} | manual

Automatic or user selection of renderer. This property enables you to specify whether MATLAB should choose the Renderer based on the contents of the figure window, or whether the Renderer should remain unchanged.

When the RendererMode property is set to auto, MATLAB selects the rendering method for printing as well as for screen display based on the size and complexity of the graphics objects in the figure.

For printing, MATLAB switches to zbuffer at a greater scene complexity than for screen rendering because printing from a z-buffered figure can be considerably slower than one using the painters rendering method, and can result in large PostScript® files. However, the output does always match what is on the screen. The same holds true for OpenGL: the output is the same as that produced by the zbuffer renderer — a bitmap with a resolution determined by the print command's -r option.

Criteria for Autoselection of the OpenGL Renderer

When the RendererMode property is set to auto, MATLAB uses the following criteria to determine whether to select the OpenGL renderer:

If the opengl autoselection mode is autoselect, MATLAB selects OpenGL if

- The host computer has OpenGL installed and is in True Color mode (OpenGL does not fully support 8-bit color mode).
- The figure contains no logarithmic axes (OpenGL does not support logarithmic axes).
- MATLAB would select zbuffer based on figure contents.
- Patch objects' faces have no more than three vertices (some OpenGL implementations of patch tessellation are unstable).
- The figure contains less than 10 uicontrols (OpenGL clipping around uicontrols is slow).
- No line objects use markers (drawing markers is slow).
- You do not specify Phong lighting (OpenGL does not support Phong lighting; if you specify Phong lighting, MATLAB uses the ZBuffer renderer).

Or

• Figure objects use transparency (OpenGL is the only MATLAB renderer that supports transparency).

When the RendererMode property is set to manual, MATLAB does not change the Renderer, regardless of changes to the figure contents.

Resize

{on} | off

Window resize mode. This property determines if you can resize the figure window with the mouse. on means you can resize the window, off means you cannot. When Resize is off, the figure window does not display any resizing controls (such as boxes at the corners), to indicate that it cannot be resized.

ResizeFcn

function handle, cell array containing function handle and additional arguments, or string (not recommended)

Window resize callback function. MATLAB executes the specified callback function whenever you resize the figure window and also when the figure is created. You can query the figure's Position property to determine the new size and position of the figure. During execution of the callback routine, the handle to the figure being resized is accessible only through the root CallbackObject property, which you can query using gcbo.

You can use ResizeFcn to maintain a GUI layout that is not directly supported by the MATLAB Position/Units paradigm.

For example, consider a GUI layout that maintains an object at a constant height in pixels and attached to the top of the figure, but always matches the width of the figure. The following ResizeFcn accomplishes this; it keeps the uicontrol whose Tag is 'StatusBar' 20 pixels high, as wide as the figure, and attached to the top of the figure. Note the use of the Tag property to retrieve the uicontrol handle, and the gcbo function to retrieve the figure handle. Also note the defensive programming regarding figure Units, which the callback requires to be in pixels in order to work correctly, but which the callback also restores to their previous value afterwards.

```
u = findobj('Tag','StatusBar');
fig = gcbo;
old_units = get(fig,'Units');
set(fig,'Units','pixels');
figpos = get(fig,'Position');
upos = [0, figpos(4) - 20, figpos(3), 20];
set(u,'Position',upos);
set(fig,'Units',old_units);
```

You can change the figure Position from within the ResizeFcn callback; however, the ResizeFcn is not called again as a result.

Note that the print command can cause the ResizeFcn to be called if the PaperPositionMode property is set to manual and

you have defined a resize function. If you do not want your resize function called by print, set the PaperPositionMode to auto.

See "Introduction" for an example of how to implement a resize function for a GUI.

See "Function Handle Callbacks" for information on how to use function handles to define the callback function.

Selected

on | off

Is object selected? This property indicates whether the figure is selected. You can, for example, define the ButtonDownFcn to set this property, allowing users to select the object with the mouse.

SelectionHighlight {on} | off

Figures do not indicate selection.

SelectionType

```
{normal} | extend | alt | open
```

Mouse selection type. MATLAB maintains this property to provide information about the last mouse button press that occurred within the figure window. This information indicates the type of selection made. Selection types are actions that MATLAB generally associates with particular responses from the user interface software (for example, single-clicking a graphics object places it in move or resize mode; double-clicking a file name opens it, etc.).

The physical action required to make these selections varies on different platforms. However, all selection types exist on all platforms.

Selection Type	Microsoft Windows	X-Windows
Normal	Click left mouse button.	Click left mouse button.
Extend	Shift - click left mouse button or click both left and right mouse buttons.	Shift-click left mouse button or click middle mouse button.
Alternate	Control - click left mouse button or click right mouse button.	Control-click left mouse button or click right mouse button.
Open	Double-click any mouse button.	Double-click any mouse button.

Note For uicontrols whose Enable property is on, a single left-click, **Ctrl**-left click, or **Shift**-left click sets the figure SelectionType property to normal. For a list box uicontrol whose Enable property is on, the second click of a double-click sets the figure SelectionType property to open. All clicks on uicontrols whose Enable property is inactive or off and all right-clicks on uicontrols whose Enable property is on set the figure SelectionType property as specified in the preceding table.

Tag

string

User-specified object label. The Tag property provides a means to identify graphics objects with a user-specified label. This is particularly useful when you are constructing interactive graphics programs that would otherwise need to define object handles as global variables or pass them as arguments between callback routines.

For example, suppose you want to direct all graphics output from a file to a particular figure, regardless of user actions that may have changed the current figure. To do this, identify the figure with a Tag.

```
figure('Tag','Plotting Figure')
```

Then make that figure the current figure before drawing by searching for the Tag with findobj.

```
figure(findobj('Tag','Plotting Figure'))
```

Toolbar

```
none | {auto} | figure
```

Control display of figure toolbar. The Toolbar property enables you to control whether MATLAB displays the default figure toolbar on figures. There are three possible values:

- none Do not display the figure toolbar.
- auto Display the figure toolbar, but remove it if a uicontrol is added to the figure.
- figure Display the figure toolbar.

Note that this property affects only the figure toolbar; it does not affect other toolbars (for example, the Camera Toolbar or Plot Edit Toolbar). Selecting **Figure Toolbar** from the figure **View** menu sets this property to figure.

If you start MATLAB with the nojvm option, figures do not display the toolbar because most tools require Java figures. This option is obsolete and no longer supported in MATLAB

Type

```
string (read only)
```

Object class. This property identifies the kind of graphics object. For figures, Type is always the string 'figure'.

UIContextMenu

handle of a uicontextmenu object

Associate a context menu with the figure. Assign this property the handle of a uicontextmenu object created in the figure. Use the uicontextmenu function to create the context menu. MATLAB displays the context menu whenever you right-click over the figure.

Units

```
{pixels} | normalized | inches |
centimeters | points | characters
```

Units of measurement. This property specifies the units MATLAB uses to interpret size and location data. All units are measured from the lower-left corner of the window.

- normalized units map the lower-left corner of the figure window to (0,0) and the upper-right corner to (1.0,1.0).
- inches, centimeters, and points are absolute units (one point equals 1/72 of an inch).
- The size of a pixel depends on screen resolution.
- characters units are defined by characters from the default system font; the width of one character is the width of the letter x, the height of one character is the distance between the baselines of two lines of text.

This property affects the CurrentPoint and Position properties. If you change the value of Units, it is good practice to return it to its default value after completing your computation so as not to affect other functions that assume Units is set to the default value.

When specifying the units as property/value pairs during object creation, you must set the Units property before specifying the properties that you want to use these units.

UserData

matrix

User-specified data. You can specify UserData as any matrix you want to associate with the figure object. The object does not use this data, but you can access it using the set and get commands.

Visible

{on} | off

Object visibility. The Visible property determines whether an object is displayed on the screen. If the Visible property of a figure is off, the entire figure window is invisible.

A Note About Using the Window Button Properties

Your window button callback functions might need to update the display by calling drawnow or pause, which causes MATLAB to process all events in the queue. Processing the event queue can cause your window button callback functions to be reentered. For example, a drawnow in the WindowButtonDownFcn might result in the WindowButtonDownFcn being called again before the first call has finished. You should design your code to handle reentrancy and you should not depend on global variables that might change state during reentrance.

You can use the Interruptible and BusyAction figure properties to control how events interact.

WindowButtonDownFcn

function handle, cell array containing function handle and additional arguments, or string (not recommended)

Button press callback function. Use this property to define a callback that MATLAB executes whenever you press a mouse button while the pointer is in the figure window. See the WindowButtonMotionFcn property for an example.

Note When using a two- or three-button mouse on Macintosh systems, right-button and middle-button presses are not always reported. This happens *only* when a new figure window appears under the mouse cursor and the mouse is clicked without first moving it. In this circumstance, for the WindowButtonDownFcn to work, the user needs to do one of the following:

- Move the mouse after the figure is created, then click any mouse button
- Press **Shift** or **Ctrl** while clicking the left mouse button to perform the Extend and Alternate selection types Pressing the left mouse button (or single mouse button) works without having to take either of the above actions.

See "Function Handle Callbacks" for information on how to use function handles to define the callback function.

WindowButtonMotionFcn

function handle, cell array containing function handle and additional arguments, or string (not recommended)

Mouse motion callback function. Use this property to define a callback that MATLAB executes whenever you move the pointer within the figure window. Define the WindowButtonMotionFcn as a function handle. The function must define at least two input arguments (handle of figure associated with key release and an event structure).

See "Function Handle Callbacks" for information on how to use function handles to define the callback function.

Example Using All Window Button Properties

Click to view in editor — This example enables you to use mouse motion to draw lines. It uses all three window button functions.

Click to run example — Click the left mouse button in the axes and move the cursor, left-click to define the line end point, right-click to end drawing mode.

Note On some computer systems, the WindowButtonMotionFcn is executed when a figure is created even though there has been no mouse motion within the figure.

WindowButtonUpFcn

function handle, cell array containing function handle and additional arguments, or string (not recommended)

Button release callback function. Use this property to define a callback that MATLAB executes whenever you release a mouse button. Define the WindowButtonUpFcn as a function handle. The function must define at least two input arguments (handle of figure associated with key release and an event structure).

The button up event is associated with the figure window in which the preceding button down event occurred. Therefore, the pointer need not be in the figure window when you release the button to generate the button up event.

If the callback routines defined by WindowButtonDownFcn or WindowButtonMotionFcn contain drawnow commands or call other functions that contain drawnow commands and the Interruptible property is set to off, the WindowButtonUpFcn might not be called. You can prevent this problem by setting Interruptible to on.

See "Function Handle Callbacks" for information on how to use function handles to define the callback function.

WindowKevPressFcn

function handle, cell array containing function handle and additional arguments, or string (not recommended)

Key press callback function for the figure window. Use this property to define a callback that MATLAB executes whenever a key press occurs. This is a callback function invoked by a key press that occurs while either the figure window or any of its children has focus. Define the WindowKeyPressFcn as a function handle. The function must define at least two input arguments (handle of figure associated with key release and an event structure).

See "Function Handle Callbacks" for information on how to use function handles to define the callback function.

When there is no callback specified for this property (which is the default state), MATLAB passes any key presses to the command window. However, when you define a callback for this property, the figure retains focus with each key press and executes the specified callback.

WindowKeyPressFcn Event Structure

When the callback is a function handle, MATLAB passes a structure to the callback function that contains the following fields.

Field	Contents
Character	The character displayed as a result of the key(s) pressed.
Modifier	This field is a cell array that contains the names of one or more modifier keys that the user pressed (i.e., control , alt , shift). On Macintosh computers, MATLAB can also return 'command' if the user pressed the command modifier key.
Key	The key pressed (lowercase label on key).

WindowKeyReleaseFcn

function handle, or cell array containing function handle and additional arguments, string (not recommended)

Key release callback function for the figure window. Use this property to define a callback that MATLAB executes whenever a key release occurs. This is a callback function invoked by a key release that occurs while the figure window or any of its children has focus. Define the WindowKeyReleaseFcn as a function handle. The function must define at least two input arguments (handle of the figure associated with key release and an event structure).

See "Function Handle Callbacks" for information on how to use function handles to define the callback function.

WindowKeyReleaseFcn Event Structure

When the callback is a function handle, MATLAB passes a structure to the callback function that contains the following fields.

Field	Contents
Character	The character corresponding to the key(s) released.
Modifier	This field is a cell array that contains the names of one or more modifier keys that the user released (i.e., control, alt, shift). On Macintosh computers, MATLAB can also return 'command' if the user released the command modifier key.
Key	The key released (lower case label on key).

WindowScrollWheelFcn

string, function handle, or cell array containing function handle and additional arguments

Respond to mouse scroll wheel. Use this property to define a callback that MATLAB executes when the mouse wheel is scrolled while the figure has focus. MATLAB executes the callback with each single mouse wheel click.

Note that it is possible for another object to capture the event from MATLAB. For example, if the figure contains Java or ActiveX control objects that are listening for mouse scroll wheel events, then these objects can consume the events and prevent the WindowScrollWheelFcn from executing.

There is no default callback defined for this property.

WindowScrollWheelFcn Event Structure

When the callback is a function handle, MATLAB passes a structure to the callback function that contains the following fields.

Field	Contents
VerticalScrollCount	A positive or negative integer that indicates the number of scroll wheel clicks. Positive values indicate clicks of the wheel scrolled in the down direction. Negative values indicate clicks of the wheel scrolled in the up direction.
VerticalScrollAmount	The current system setting for the number of lines that are scrolled for each click of the scroll wheel. If the mouse property setting for scrolling is set to One screen at a time, VerticalScrollAmount returns a value of 1.

Effects on Other Properties

- CurrentObject property Mouse scrolling does not update this figure property.
- CurrentPoint property If there is no callback defined for the WindowScrollWheelFcn property, then MATLAB does not update the CurrentPoint property as the scroll wheel is turned. However, if there is a callback defined for the WindowScrollWheelFcn property, then MATLAB updates the CurrentPoint property just before executing the callback. This enables you to determine the point at which the mouse scrolling occurred.
- HitTest property The WindowScrollWheelFcn callback executes regardless of the setting of the figure HitTest property.
- SelectionType property The WindowScrollWheelFcn callback has no effect on this property.

Values Returned by VerticalScrollCount

When a user moves the mouse scroll wheel by one click, MATLAB increments the count by +/- 1, depending on the direction of the scroll (scroll down being positive). When MATLAB calls the WindowScrollWheelFcn callback, the counter is reset. In most cases, this means that the absolute value of the returned value is 1. However, if the WindowScrollWheelFcn callback takes a long enough time to return and/or the user spins the scroll wheel very fast, then the returned value can have an absolute value greater than one.

The actual value returned by VerticalScrollCount is the algebraic sum of all scroll wheel clicks that occurred since last processed. This enables your callback to respond correctly to the user's action.

Example

Click to view in editor — This example creates a graph of a function and enables you to use the mouse scroll wheel to change the range over which a mathematical function is evaluated and update the graph to reflect the new limits as you turn the scroll wheel.

Click to run example — Mouse over the figure and scroll your mouse wheel.

Related Information

See "Function Handle Callbacks" for information on how to use function handles to define the callback function.

WindowStyle

{normal} | modal | docked

Normal, modal, or dockable window behavior. When WindowStyle is set to modal:

- The figure window traps all keyboard and mouse events over all MATLAB windows as long as they are visible.
- Windows belonging to applications other than MATLAB are unaffected.
- Modal figures remain stacked above all normal figures and the MATLAB Command Window.
- When multiple modal windows exist, the most recently created window keeps focus and stays above all other windows until it becomes invisible, or is returned to WindowStyle normal, or is deleted. At that time, focus reverts to the window that last had focus.

Use modal figures to create dialog boxes that force the user to respond without being able to interact with other windows. Typing **Ctrl+C** while the figure has focus causes all figures with

WindowStyle modal to revert to WindowStyle normal, allowing you to type at the command line.

Invisible Modal Figures

Figures with WindowStyle modal and Visible off do not behave modally until they are made visible, so it is acceptable to hide a modal window for later reuse instead of destroying it.

Stacking Order of Modal Figures

Creating a figure with WindowStyle modal stacks it on top of all existing figure windows, making them inaccessible as long as the top figure exists and remains modal. However, any new figures created after a modal figure is displayed (for example, plots created by a modal GUI) stack on top of it and are accessible; they can be modal as well.

Changing Modes

You can change the WindowStyle of a figure at any time, including when the figure is visible and contains children. However, on some systems this may cause the figure to flash or disappear and reappear, depending on the windowing system's implementation of normal and modal windows. For best visual results, you should set WindowStyle at creation time or when the figure is invisible.

Window Decorations on Modal Figures

Modal figures do not display uimenu children, built-in menus, or toolbars but it is not an error to create uimenus in a modal figure or to change WindowStyle to modal on a figure with uimenu children. The uimenu objects exist and their handles are retained by the figure. If you reset the figure's WindowStyle to normal, the uimenus are displayed.

Docked WindowStyle

When WindowStyle is set to docked, the figure is docked in the desktop or a document window. When you issue the following command.

```
set(figure_handle,'WindowStyle','docked')
```

MATLAB docks the figure identified by *figure_handle* and sets the DockControls property to on, if it was off.

Note that if WindowStyle is docked, you cannot set the DockControls property to off.

The value of the WindowStyle property is not changed by calling reset on a figure.

WVisual

identifier string (Windows only)

Specify pixel format for figure. MATLAB automatically selects a pixel format for figures based on your current display settings, the graphics hardware available on your system, and the graphical content of the figure.

Usually, MATLAB chooses the best pixel format to use in any given situation. However, in cases where graphics objects are not rendered correctly, you might be able to select a different pixel format and improve results. See "Understanding the WVisual String" for more information.

Querying Available Pixel Formats on Window Systems

You can determine what pixel formats are available on your system for use with MATLAB using the following statement:

```
set(gcf,'WVisual')
```

MATLAB returns a list of the currently available pixel formats for the current figure. For example, the following are the first three entries from a typical list:

01 (RGB 16 bits(05 06 05 00) zdepth 24, Hardware Accelerated, OpenGL, GDI, Window)

02 (RGB 16 bits(05 06 05 00) zdepth 24, Hardware Accelerated, OpenGL, Double Buffered, Window)

03 (RGB 16 bits(05 06 05 00) zdepth 24, Hardware Accelerated, OpenGL, Double Buffered, Window)

Use the number at the beginning of the string to specify which pixel format to use. For example,

```
set(gcf, 'WVisual', '02')
```

specifies the second pixel format in the list above. Note that pixel formats might differ on your system.

Understanding the WVisual String

The string returned by querying the WVisual property provides information on the pixel format. For example:

- RGB 16 bits (05 06 05 00) Indicates true color with 16-bit resolution (5 bits for red, 6 bits for green, 5 bits for blue, and 0 for alpha (transparency). MATLAB requires true color.
- zdepth 24 Indicates 24-bit resolution for sorting object's front to back position on the screen. Selecting pixel formats with higher (24 or 32) zdepth might solve sorting problems.
- Hardware Accelerated Some graphics functions may be performed by hardware for increased speed. If there are incompatibilities between your particular graphic hardware and MATLAB, select a pixel format in which the term Generic appears instead of Hardware Accelerated.

- Openg1 Supports OpenGL. See the preceding "Pixel Formats and OpenGL" for more information.
- GDI Supports for Windows 2-D graphics interface.
- Double Buffered Support for double buffering with the OpenGL renderer. Note that the figure DoubleBuffer property applies only to the painters renderer.
- Bitmap Support for rendering into a bitmap (as opposed to drawing in the window).
- Window Support for rendering into a window.

Pixel Formats and OpenGL

If you are experiencing problems using hardware OpenGL on your system, you can try using generic OpenGL, which is implemented in software. To do this, first instruct MATLAB to use the software version of OpenGL with the following statement:

opengl software

Then allow MATLAB to select best pixel format to use.

See the Renderer property for more information on how MATLAB uses OpenGL.

WVisualMode

auto | manual (Windows only)

Auto or manual selection of pixel format. WVisualMode can take on two values — auto (the default) and manual. In auto mode, MATLAB selects the best pixel format to use based on your computer system and the graphical content of the figure. In manual mode, MATLAB does not change the visual from the one currently in use. Setting the WVisual property sets this property to manual.

XDisplay

display identifier (UNIX only)

Contains the display used for MATLAB. You can query this property to determine the name of the display that MATLAB is using. For example, if MATLAB is running on a system called mycomputer, querying XDisplay returns a string of the following form:

```
get(gcf,'XDisplay')
ans
mycomputer:0.0
```

Setting XDisplay on Motif

If your computer uses Motif-based figures, you can specify the display MATLAB uses for a figure by setting the value of the figure's XDisplay property. For example, to display the current figure on a system called fred, use the command

```
set(gcf,'XDisplay','fred:0.0')
```

XVisual

visual identifier (UNIX only)

Select visual used by MATLAB. You can select the visual used by MATLAB by setting the XVisual property to the desired visual ID. This can be useful if you want to test your application on an 8-bit or grayscale visual. To see what visuals are available on your system, use the UNIX xdpyinfo command. From MATLAB, type

```
!xdpyinfo
```

The information returned contains a line specifying the visual ID. For example:

```
visual id: 0x23
```

To use this visual with the current figure, set the XVisual property to the ID.

```
set(gcf, 'XVisual', '0x23')
```

To see which of the available visuals MATLAB can use, call set on the XVisual property:

```
set(gcf,'XVisual')
```

The following typical output shows the visual being used (in curly braces) and other possible visuals. Note that MATLAB requires a TrueColor visual.

```
{ 0x23 (TrueColor, depth 24, RGB mask 0xff0000 0xff00 0x00ff) }
0x24 (TrueColor, depth 24, RGB mask 0xff0000 0xff00 0x00ff)
0x25 (TrueColor, depth 24, RGB mask 0xff0000 0xff00 0x00ff)
0x26 (TrueColor, depth 24, RGB mask 0xff0000 0xff00 0x00ff)
0x27 (TrueColor, depth 24, RGB mask 0xff0000 0xff00 0x00ff)
0x28 (TrueColor, depth 24, RGB mask 0xff0000 0xff00 0x00ff)
0x29 (TrueColor, depth 24, RGB mask 0xff0000 0xff00 0x00ff)
0x2a (TrueColor, depth 24, RGB mask 0xff0000 0xff00 0x00ff)
```

You can also use the glxinfo UNIX command to see what visuals are available for use with the OpenGL renderer. From MATLAB, type

```
!glxinfo
```

After providing information about the implementation of OpenGL on your system, glxinfo returns a table of visuals. The partial listing below shows typical output:

```
0x25 24 tc 0 24 0 r y . 8 8 8 8 0 24 8 0 0 0 0 0 0 0 None
0x26 24 tc 0 24 0 r . . 8 8 8 8 8 0 24 8 0 0 0 0 0 0 None
0x27 24 tc 0 24 0 r y . 8 8 8 8 8 0 0 0 16 16 16 0 0 0 0 Slow
```

The third column is the class of visual. to means a true color visual. Note that some visuals may be labeled Slow under the caveat column. Such visuals should be avoided.

To determine which visual MATLAB will use by default with the OpenGL renderer, use the MATLAB opengl info command. The returned entry for the visual might look like the following:

```
Visual = 0x23 (TrueColor, depth 24, RGB mask 0xff0000 0xff00 0x00ff)
```

Experimenting with a different TrueColor visual may improve certain rendering problems.

XVisualMode


```
auto | manual (UNIX only)
```

Auto or manual selection of visual. XVisualMode can take on two values — auto (the default) and manual. In auto mode, MATLAB selects the best visual to use based on the number of colors, availability of the OpenGL extension, etc. In manual mode, MATLAB does not change the visual from the one currently in use. Setting the XVisual property sets this property to manual.

See Also figure

Purpose

Show or hide figure palette



GUI Alternatives

Click the larger Plotting Tools icon on the figure toolbar to

collectively enable plotting tools, and the smaller icon to collectively disable them. Open or close the **Figure Palette** tool from the figure's **View** menu. For details, see "The Figure Palette" in the MATLAB Graphics documentation.

Syntax

```
figurepalette('show')
figurepalette('hide')
figurepalette('toggle')
figurepalette(figure handle,...)
```

Description

 $\label{tigure} \mbox{figure palette ('show') displays the palette on the current figure.}$

 $\label{figure} \mbox{figurepalette('hide') hides the palette on the current figure.}$

figurepalette('toggle') or figurepalette toggles the visibility of the palette on the current figure.

figurepalette(figure_handle,...) shows or hides the palette on the figure specified by figure handle.

figurepalette

See Also

plottools, plotbrowser, propertyeditor

Purpose Set or get attributes of file or folder

Syntax fileattrib

```
fileattrib('name')
```

fileattrib('name','attrib')

fileattrib('name', 'attrib', 'users')
fileattrib('name', 'attrib', 'users', 's')

[status, message, messageid] = fileattrib(...)

Description

fileattrib displays the attributes, sometimes called properties, for the current folder. fileattrib is like the DOS attrib command, or the chmod command used on UNIX³ platforms.

Values are as follows.

Value	Description
0	Attribute is off
1	Attribute is on
NaN	Attribute does not apply

fileattrib('name') displays the attributes for name, where name is the absolute or relative path for a folder or file. Use a wildcard, *, at the end of name to view attributes for all matching files.

fileattrib('name', 'attrib') sets the attribute for name, where name is the absolute or relative path for a folder or file. Specify the + qualifier before the attribute to set it, and specify the - qualifier before the attribute to clear it. Use a wildcard, *, at the end of name to set attributes for all matches. Values for attrib are as follows.

Value for attrib	Description
а	Archive (Microsoft Windows platform only)
h	Hidden file (Windows platform only)
S	System file (Windows platform only)

3. UNIX is a registered trademark of The Open Group in the United States and other countries.

Value for attrib	Description
W	Write access (Windows and UNIX platforms). Results differ by platform and application. For example, even though fileattrib disables the "write" privilege for a folder, making it read only, files in the folder could be writable for some platforms or applications.
Х	Executable (UNIX platform only)

For example, fileattrib('myfile.m','+w') makes myfile.m a writable file.

fileattrib('name', 'attrib', 'users') sets the attribute for name, where name is the absolute or relative path for a folder or file. The users argument is applicable only for UNIX platforms. For more information about these attributes, see reference information for chmod in UNIX operating system documentation. The default value for users is u. The following table lists values for users.

Value for users	Description
a	All users
g	Group of users
0	All other users
u	Current user

fileattrib('name', 'attrib', 'users', 's') sets the attribute for name, where name is the absolute or relative path for a file or a folder and its contents. Here, s applies attrib to all contents of name, where name is a folder.

[status,message,messageid] = fileattrib(...) sets the attribute for name, returning the status, a message, and the MATLAB error message ID. Here, status is 1 for success and 0 for error. If you do not specify attrib, users, and s, and the status is 1, then message

is a structure containing the file attributes and messageid is blank. If status is 0, then messageid contains the error. To return message as a structure, use a wildcard * at the end of name.

Examples Get Attributes of File

To view the attributes of myfile.m, type:

```
fileattrib('myfile.m')
```

MATLAB returns:

```
Name: 'd:/work/myfile.m'
archive: 0
system: 0
hidden: 0
directory: 0
UserRead: 1
UserWrite: 0
UserExecute: 1
GroupRead: NaN
GroupWrite: NaN
OtherRead: NaN
OtherWrite: NaN
OtherExecute: NaN
OtherExecute: NaN
```

UserWrite is 0, meaning myfile.m is read only. The Group and Other values are NaN because they do not apply to the current operating system, Windows.

Set File Attribute

To make myfile.m become writable, type:

```
fileattrib('myfile.m','+w')
```

Running fileattrib('myfile.m') now shows UserWrite to be 1.

Set Attributes for Specified Users

To make the folder d:/work/results be a read-only folder for all users, type:

```
fileattrib('d:/work/results','-w','a')
```

The - preceding the write attribute, w, removes the write status.

Set Multiple Attributes for Folder and Its Contents

To make the folder d:/work/results and all its contents read only and hidden, on Windows platforms, type:

```
fileattrib('d:/work/results','+h-w','','s')
```

Because *users* is not applicable on Windows systems, the value is empty. Here, **s** applies the attribute to the contents of the specified folder.

Return Status and Structure of Attributes

[stat,mess]=fileattrib('results')

To return the attributes for the folder results to a structure, type:

```
MATLAB returns

stat =
    1

mess =

    Name: 'd:\work\results'
    archive: 0
    system: 0
    hidden: 0
    directory: 1
    UserRead: 1
    UserExecute: 1
    GroupRead: NaN
```

```
GroupWrite: NaN
GroupExecute: NaN
OtherRead: NaN
OtherWrite: NaN
OtherExecute: NaN
```

The operation is successful as indicated by the status, stat, being 1. The structure mess contains the file attributes. Access the attribute values in the structure. For example, type:

```
mess.Name
```

MATLAB returns the path for results

```
ans =
d:\work\results
```

Return Attributes with Wildcard for Name

To return the attributes for all files in the current folder whose names begin with new, type:

```
[stat,mess]=fileattrib('new*')
MATLAB returns:

stat =
    1

mess =
1x3 struct array with fields:
    Name
    archive
    system
    hidden
    directory
    UserRead
    UserWrite
    UserExecute
```

```
GroupRead
GroupWrite
GroupExecute
OtherRead
OtherWrite
OtherExecute
```

The results indicate there are three matching files. To view the file names, type:

```
mess.Name
```

MATLAB returns:

```
ans =
  d:\work\results\newname.m
  ans =
  d:\work\results\newone.m
  ans =
  d:\work\results\newtest.m
To view just the first file name, type:
```

```
mess(1).Name
ans =
d:\work\results\newname.m
```

See Also

```
copyfile, cd, dir, ls, mkdir, movefile, rmdir
"Managing Files in MATLAB"
```

filebrowser

Purpose Open Current Folder browser, or select it if already open

Graphical As an alternative to the filebrowser function, select **Desktop > Current Folder** in the MATLAB desktop.

Syntax filebrowser

Description filebrowser opens the Current Folder Browser, or if it is already open,

makes it the selected tool.

See Also cd, copyfile, fileattrib, ls, mkdir, movefile, pwd, rmdir

"Managing Files in MATLAB"

Supported file formats

Description

This table shows the file formats that you can import and export from the MATLAB application.

You can import any of these file formats using the Import Wizard or the importdata function, except:

- netCDF
- H5
- Motion JPEG 2000
- Platform-specific video

The importdata function cannot read HDF files.

File Content	Extension	Description	Import Function	Export Function
MATLAB formatted data	MAT	Saved MATLAB workspace	load	save
Text	any	White-space delimited numbers	load	save -ascii
		Delimited numbers	dlmread	dlmwrite
		Delimited numbers, or a mix of strings and numbers	textscan	
Spreadsheet	XLS	Microsoft Excel worksheet	xlsread	xlswrite
	XLSX XLSB XLSM	Formats supported with Excel 2007 for Windows installed		

File Formats

File Content	Extension	Description	Import Function	Export Function
Extended Markup Language	XML	XML-formatted text	xmlread	xmlwrite
Data Acquisition Toolbox file	DAQ	Data Acquisition Toolbox	daqread	none
Scientific data	CDF	Common Data Format	cdfread, or see cdflib	cdfwrite, or see cdflib
	FITS	Flexible Image Transport System	fitsread	none
	HDF	Hierarchical Data Format, version 4, or HDF-EOS v. 2	hdfread	
	H5	HDF or HDF-EOS, version 5	hdf5read	hdf5write
	NC	Network Common Data Form (netCDF)	See netcdf	See netcdf
Image	BMP	Windows Bitmap	imread	imwrite
	GIF	Graphics Interchange Format		
	HDF	Hierarchical Data Format		
	JPEG JPG	Joint Photographic Experts Group		
	JP2 JPF JPX J2C J2K	JPEG 2000		
	PBM	Portable Bitmap		

File Content	Extension	Description	Import Function	Export Function
	PCX	Paintbrush		
	PGM	Portable Graymap		
	PNG	Portable Network Graphics		
	PNM	Portable Any Map		
	PPM	Portable Pixmap		
	RAS	Sun Raster		
	TIFF TIF	Tagged Image File Format		
	XWD	X Window Dump		
	CUR	Windows Cursor resources	imread	none
	FITS FTS	Flexible Image Transport System		
	ICO	Windows Icon resources		
Audio file	AU SND	NeXT/Sun sound	auread	auwrite
	WAV	Microsoft WAVE sound	wavread	wavwrite
Video (all	AVI	Audio Video Interleave	mmreader	avifile
platforms)	MJ2	Motion JPEG 2000	mmreader	none

File Formats

File Content	Extension	Description	Import Function	Export Function
Video (Windows)	MPG	Motion Picture Experts Group, phases 1 and 2	mmreader	none
	ASF ASX WMV	Windows Media®		
	any	Formats supported by Microsoft DirectShow®		
Video (Mac®)	MPG MP4 M4V	MPEG-1 and MPEG-4	mmreader	none
	any	Formats supported by QuickTime®, including .mov, .3gp, .3g2, and .dv		
Video (Linux)	any	Formats supported by your installed GStreamer plug-ins, including .ogg	mmreader	none

See Also uiimport | fscanf | fread | fprintf | fwrite | imformats | hdf | hdf5 | Tiff

How To

- · "Importing Data"
- "Exporting Data"

Character to separate file name and internal function name

Syntax

M = filemarker

Description

M = filemarker returns the character that separates a file and a within-file function name.

Examples

On the Microsoft Windows platform, for example, filemarker returns the '>' character:

```
filemarker
ans =
>
```

You can use the following command on any platform to get the help text for subfunction pdeodes defined in pdepe.m:

```
helptext = help(['pdepe' filemarker 'pdeodes'])
helptext =
PDEODES Assemble the difference equations and
    evaluate the time derivative for the ODE system.
```

You can use the filemarker character to indicate a location within a MATLAB program file where you want to set a breakpoint, for example. On all platforms, if you need to distinguish between two nested functions with the same name, use the forward slash (/) character to indicate the path to a particular instance of a function.

For instance, suppose myfile.m contains the following code:

```
function x = A(p1, p2)
...
function y = B(p3)
    ...
end
function m = C(p4)
    ...
```

```
end
end

function z = C(p5)
...
  function y = D(p6)
    ...
  end
end
```

To indicate that you want to set a breakpoint at function y nested within function x, use the following command on the Windows platform:

```
dbstop myfile>x/y
```

To indicate that you want to set a breakpoint at function m nested within function x use the following command on the Windows platform:

```
dbstop myfile>m
```

In the first case, you specify x/y because myfile.m contains two nested functions named y. In the second case, there is no need to specify x/m because there is only one function m within myfile.m.

See Also filesep

Parts of file name and path

Syntax

[pathstr, name, ext, versn] = fileparts(filename)

Description

[pathstr, name, ext, versn] = fileparts(filename) returns the path name, file name, extension, and version for the specified file. filename is a string enclosed in single quotes. The returned ext field contains a dot (.) before the file extension.

Note The fourth output of fileparts, versn, will be removed in a future release.

The fileparts function is platform dependent.

You can reconstruct the file from the parts using:

```
fullfile(pathstr,[name ext])
```

Examples

Return the pieces of a file specification string to the separate string outputs pathstr, name, and ext. The full file specification is

```
file = '\home\user4\matlab\classpath.txt';
```

The character used to separate the segments of a path name is dependent on the operating system you are currently running on. In this example, it is the backslash (\) character, which is used as a separator on Microsoft Windows platforms. For portability, use the filesep function to insert the correct separator character:

```
sep = filesep;
file = ['' sep 'home' sep 'user4' sep 'matlab' sep 'classpath.txt'
```

Use fileparts to return the path name (including user name), file name, and file extension:

```
[pathstr, name, ext] = fileparts(file)
```

```
pathstr =
    \home\user4\matlab

name =
    classpath

ext =
    .txt
```

Remarks

On Windows platforms, C:\ and C: are two distinct entities, where C:\ (with backslash) is the C drive in your computer, and C: (without backslash) represents the current working directory.

See Also

filesep, fullfile, ver, verLessThan, version

Purpose Read contents of file into string

Description text = fileread(filename) returns the contents of the file filename

as a MATLAB string.

Examples

Read and search the file Contents.m in the MATLAB iofun directory for the reference to fileread:

```
% find the correct directory and file
io_contents = ...
  fullfile(matlabroot, 'toolbox', 'matlab', 'iofun', 'Contents.m');
% read the file
filetext = fileread(io_contents);
% search for the line of code that includes 'fileread'
% each line is separated by a newline ('\n')
expr = '[^\n]*fileread[^\n]*';
fileread_info = regexp(filetext, expr, 'match');
```

See Also

fgetl | fgets | fscanf | fread | importdata | textscan | type

filesep

Purpose File separator for current platform

Syntax f = filesep

Description f = filesep returns the platform-specific file separator character.

The file separator is the character that separates individual folder and

file names in a path string.

Examples Create a path to the iofun folder on a Microsoft Windows platform:

```
iofun_dir = ['toolbox' filesep 'matlab' filesep 'iofun']
iofun_dir =
   toolbox\matlab\iofun
```

Create a path to iofun on a UNIX⁴ platform.

```
iodir = ['toolbox' filesep 'matlab' filesep 'iofun']
iodir =
  toolbox/matlab/iofun
```

See Also fullfile, fileparts, pathsep

4. UNIX is a registered trademark of The Open Group in the United States and other countries.

Filled 2-D polygons



Syntax

```
fill(X,Y,C)
fill(X,Y,ColorSpec)
fill(X1,Y1,C1,X2,Y2,C2,...)
fill(...,'PropertyName',PropertyValue)
h = fill(...)
```

Description

The fill function creates colored polygons.

fill(X,Y,C) creates filled polygons from the data in X and Y with vertex color specified by C. C is a vector or matrix used as an index into the colormap. If C is a row vector, length(C) must equal size(X,2) and size(Y,2); if C is a column vector, length(C) must equal size(X,1) and size(Y,1). If necessary, fill closes the polygon by connecting the last vertex to the first.

fill(X,Y,ColorSpec) fills two-dimensional polygons specified by X and Y with the color specified by ColorSpec.

fill(X1,Y1,C1,X2,Y2,C2,...) specifies multiple two-dimensional filled areas.

fill(..., 'PropertyName', PropertyValue) allows you to specify property names and values for a patch graphics object.

h = fill(...) returns a vector of handles to patch graphics objects, one handle per patch object.

Remarks

If X or Y is a matrix, and the other is a column vector with the same number of elements as rows in the matrix, fill replicates the column vector argument to produce a matrix of the required size. fill forms a vertex from corresponding elements in X and Y and creates one polygon from the data in each column.

The type of color shading depends on how you specify color in the argument list. If you specify color using ColorSpec, fill generates flat-shaded polygons by setting the patch object's FaceColor property to the corresponding RGB triple.

If you specify color using C, fill scales the elements of C by the values specified by the axes property CLim. After scaling C, C indexes the current colormap.


If C is a row vector, fill generates flat-shaded polygons where each element determines the color of the polygon defined by the respective column of the X and Y matrices. Each patch object's FaceColor property is set to 'flat'. Each row element becomes the CData property value for the nth patch object, where n is the corresponding column in X or Y.

If C is a column vector or a matrix, fill uses a linear interpolation of the vertex colors to generate polygons with interpolated colors. It sets the patch graphics object FaceColor property to 'interp' and the elements in one column become the CData property value for the respective patch object. If C is a column vector, fill replicates the column vector to produce the required sized matrix.

Examples

Create a red octagon.

```
t = (1/16:1/8:1)'*2*pi;
x = sin(t);
y = cos(t);
fill(x,y,'r')
axis square
```



See Also

axis, caxis, colormap, ColorSpec, fill3, patch
"Polygons and Surfaces" on page 1-100 for related functions

Filled 3-D polygons



Syntax

```
fill3(X,Y,Z,C)
fill3(X,Y,Z,ColorSpec)
fill3(X1,Y1,Z1,C1,X2,Y2,Z2,C2,...)
fill3(...,'PropertyName',PropertyValue)
h = fill3(...)
```

Description

The fill3 function creates flat-shaded and Gouraud-shaded polygons.

fill3(X,Y,Z,C) fills three-dimensional polygons. X, Y, and Z triplets specify the polygon vertices. If X, Y, or Z is a matrix, fill3 creates n polygons, where n is the number of columns in the matrix. fill3 closes the polygons by connecting the last vertex to the first when necessary.

C specifies color, where C is a vector or matrix of indices into the current colormap. If C is a row vector, length(C) must equal size(X,2) and size(Y,2); if C is a column vector, length(C) must equal size(X,1) and size(Y,1).

fill3(X,Y,Z,ColorSpec) fills three-dimensional polygons defined by X, Y, and Z with color specified by ColorSpec.

fill3(X1,Y1,Z1,C1,X2,Y2,Z2,C2,...) specifies multiple filled three-dimensional areas.

fill3(..., 'PropertyName', PropertyValue) allows you to set values for specific patch properties.

h = fill3(...) returns a vector of handles to patch graphics objects, one handle per patch.

Algorithm

If X, Y, and Z are matrices of the same size, fill3 forms a vertex from the corresponding elements of X, Y, and Z (all from the same matrix location), and creates one polygon from the data in each column.

If X, Y, or Z is a matrix, fill3 replicates any column vector argument to produce matrices of the required size.

If you specify color using ColorSpec, fill3 generates flat-shaded polygons and sets the patch object FaceColor property to an RGB triple.


If you specify color using C, fill3 scales the elements of C by the axes property CLim, which specifies the color axis scaling parameters, before indexing the current colormap.

If C is a row vector, fill3 generates flat-shaded polygons and sets the FaceColor property of the patch objects to 'flat'. Each element becomes the CData property value for the respective patch object.

If C is a column vector or a matrix, fill3 generates polygons with interpolated colors and sets the patch object FaceColor property to 'interp'. fill3 uses a linear interpolation of the vertex colormap indices when generating polygons with interpolated colors. The elements in one column become the CData property value for the respective patch object. If C is a column vector, fill3 replicates the column vector to produce the required sized matrix.

Examples

Create four triangles with interpolated colors.



See Also

axis, caxis, colormap, ColorSpec, fill, patch

"Polygons and Surfaces" on page 1-100 for related functions

1-D digital filter

Syntax

```
y = filter(b,a,X)
[y,zf] = filter(b,a,X)
[y,zf] = filter(b,a,X,zi)
y = filter(b,a,X,zi,dim)
[...] = filter(b,a,X,[],dim)
```

Description

The filter function filters a data sequence using a digital filter which works for both real and complex inputs. The filter is a *direct form II transposed* implementation of the standard difference equation (see "Algorithm").

y = filter(b,a,X) filters the data in vector X with the filter described by numerator coefficient vector b and denominator coefficient vector a. If a(1) is not equal to 1, filter normalizes the filter coefficients by a(1). If a(1) equals 0, filter returns an error.

If X is a matrix, filter operates on the columns of X. If X is a multidimensional array, filter operates on the first nonsingleton dimension.

[y,zf] = filter(b,a,X) returns the final conditions, zf, of the filter delays. If X is a row or column vector, output zf is a column vector of max(length(a),length(b))-1. If X is a matrix, zf is an array of such vectors, one for each column of X, and similarly for multidimensional arrays.

[y,zf] = filter(b,a,X,zi) accepts initial conditions, zi, and returns the final conditions, zf, of the filter delays. Input zi is a vector of length max(length(a),length(b))-1, or an array with the leading dimension of size max(length(a),length(b))-1 and with remaining dimensions matching those of X.

y = filter(b,a,X,zi,dim) and [...] = filter(b,a,X,[],dim) operate across the dimension dim.


Example

You can use filter to find a running average without using a for loop. This example finds the running average of a 16-element vector, using a window size of 5.

```
data = [1:0.2:4]';
windowSize = 5;
filter(ones(1,windowSize)/windowSize,1,data)
ans =
    0.2000
    0.4400
    0.7200
    1.0400
    1.4000
    1.6000
    1.8000
    2.0000
    2.2000
    2.4000
    2.6000
    2.8000
    3.0000
    3.2000
    3.4000
    3.6000
```

Algorithm

The filter function is implemented as a direct form II transposed structure,



or

$$y(n) = b(1)*x(n) + b(2)*x(n-1) + ... + b(nb+1)*x(n-nb)$$

- $a(2)*y(n-1) - ... - a(na+1)*y(n-na)$

where n-1 is the filter order, which handles both FIR and IIR filters [1], na is the feedback filter order, and nb is the feedforward filter order.

The operation of filter at sample m is given by the time domain difference equations

$$y(m) = b(1)x(m) + z_1(m-1)$$

$$z_1(m) = b(2)x(m) + z_2(m-1) - a(2)y(m)$$

$$\vdots = \vdots$$

$$z_{n-2}(m) = b(n-1)x(m) + z_{n-1}(m-1) - a(n-1)y(m)$$

$$z_{n-1}(m) = b(n)x(m) - a(n)y(m)$$

The input-output description of this filtering operation in the **z**-transform domain is a rational transfer function,

$$Y(z) = \frac{b(1) + b(2)z^{-1} + \dots + b(nb+1)z^{-nb}}{1 + a(2)z^{-1} + \dots + a(na+1)z^{-na}}X(z)$$

See Also

filter2

filtfilt, filtic in the Signal Processing Toolbox

References

[1] Oppenheim, A. V. and R.W. Schafer. *Discrete-Time Signal Processing*, Englewood Cliffs, NJ: Prentice-Hall, 1989, pp. 311-312.

filter (timeseries)

Purpose

Shape frequency content of time series

Syntax

Description

ts2 = filter(ts1,b,a) applies the transfer function filter
$$b(z^{-1})/a(z^{-1})$$
 to the data in the timeseries object ts1.

b and a are the coefficient arrays of the transfer function numerator and denominator, respectively.

ts2 = filter(ts1,b,a,Index) uses the optional Index integer array to specify the columns or rows to filter. When ts.IsTimeFirst is true, Index specifies one or more data columns. When ts.IsTimeFirst is false, Index specifies one or more data rows.

Remarks

The time-series data must be uniformly sampled to use this filter.

The following function

$$y = filter(b,a,x)$$

creates filtered data y by processing the data in vector x with the filter described by vectors a and b.

The filter function is a general tapped delay-line filter, described by the difference equation

$$\begin{split} a(1)y(n) &= b(1)x(n) + b(2)x(n-1) + \dots + b(nb)x(n-nb+1) \\ &- a(2)y(n-1) - \dots - a(N_a)y(n-N_b+1) \end{split}$$

Here, n is the index of the current sample, $N_{\rm a}$ is the order of the polynomial described by vector ${\bf a}$, and $N_{\rm b}$ is the order of the polynomial described by vector ${\bf b}$. The output y(n) is a linear combination of current and previous inputs, x(n) x(n-1)..., and previous outputs, y(n-1) y(n-2)...

You use the discrete filter to shape the data by applying a transfer function to the input signal.

Depending on your objectives, the transfer function you choose might alter both the amplitude and the phase of the variations in the data at different frequencies to produce either a smoother or a rougher output.

In digital signal processing (DSP), it is customary to write transfer functions as rational expressions in z^{-1} and to order the numerator and denominator terms in ascending powers of z^{-1} .

Taking the z-transform of the difference equation

$$a(1)y(n) = b(1)x(n) + b(2)x(n-1) + \dots + b(nb)x(n-nb+1)$$
$$-a(2)y(n-1) - \dots - a(na)y(n-na+1)$$

results in the transfer function

$$Y(z) = H(z^{-1})X(z) = \frac{b(1) + b(2)z^{-1} + \dots + b(nb)z^{-nb+1}}{a(1) + a(2)z^{-1} + \dots + a(na)z^{-na+1}}X(z)$$

where Y(z) is the z-transform of the filtered output y(n). The coefficients b and a are unchanged by the z-transform.

Examples

Consider the following transfer function:

$$H(z^{-1}) = \frac{b(z^{-1})}{a(z^{-1})} = \frac{2 + 3z^{-1}}{1 + 0.2z^{-1}}$$

You will apply this transfer function to the data in count.dat.

1 Load the matrix count into the workspace.

load count.dat;

2 Create a time-series object based on this matrix.

count1=timeseries(count(:,1),[1:24]);

filter (timeseries)

3 Enter the coefficients of the denominator ordered in ascending powers of z^{-1} to represent $1 + 0.2z^{-1}$.

$$a = [1 \ 0.2];$$

4 Enter the coefficients of the numerator to represent $2 + 3z^{-1}$.


$$b = [2 \ 3];$$

5 Call the filter function.

```
filter_count = filter(count1,b,a)
```

6 Compare the original data and the shaped data with an overlaid plot of the two curves:

```
plot(count1,'-.'), grid on, hold on
plot(filter_count,'-')
legend('Original Data','Shaped Data',2)
```



See Also

idealfilter (timeseries), timeseries, tsprops

Purpose 2-D digital filter

Syntax Y = filter2(h,X)

Y = filter2(h, X, shape)

Description

Y = filter2(h,X) filters the data in X with the two-dimensional FIR filter in the matrix h. It computes the result, Y, using two-dimensional correlation, and returns the central part of the correlation that is the same size as X.

Y = filter2(h,X,shape) returns the part of Y specified by the shape parameter. shape is a string with one of these values:

'full' Returns the full two-dimensional correlation. In this case, Y is larger than X.

'same' (default) Returns the central part of the correlation. In this case, Y is the same size as X.

'valid' Returns only those parts of the correlation that are computed without zero-padded edges. In this case, Y is smaller than X.

Remarks

Two-dimensional correlation is equivalent to two-dimensional convolution with the filter matrix rotated 180 degrees. See the Algorithm section for more information about how filter2 performs linear filtering.

Algorithm

Given a matrix X and a two-dimensional FIR filter h, filter2 rotates your filter matrix 180 degrees to create a convolution kernel. It then calls conv2, the two-dimensional convolution function, to implement the filtering operation.

filter2 uses conv2 to compute the full two-dimensional convolution of the FIR filter with the input matrix. By default, filter2 then extracts the central part of the convolution that is the same size as the input

filter2

matrix, and returns this as the result. If the shape parameter specifies an alternate part of the convolution for the result, filter2 returns the appropriate part.

See Also

conv2, filter

Find indices and values of nonzero elements

Syntax

```
ind = find(X)
ind = find(X, k)
ind = find(X, k, 'first')
ind = find(X, k, 'last')
[row,col] = find(X, ...)
[row,col,v] = find(X, ...)
```

Description

ind = find(X) locates all nonzero elements of array X, and returns the linear indices of those elements in vector ind. If X is a row vector, then ind is a row vector; otherwise, ind is a column vector. If X contains no nonzero elements or is an empty array, then ind is an empty array.

ind = find(X, k) or ind = find(X, k, 'first') returns at most the first k indices corresponding to the nonzero entries of X. k must be a positive integer, but it can be of any numeric data type.

ind = find(X, k, 'last') returns at most the last k indices corresponding to the nonzero entries of X.

[row,col] = find(X, ...) returns the row and column indices of the nonzero entries in the matrix X. This syntax is especially useful when working with sparse matrices. If X is an N-dimensional array with N \geq 2, col contains linear indices for the columns. For example, for a 5-by-7-by-3 array X with a nonzero element at X(4,2,3), find returns 4 in row and 16 in col. That is, (7 columns in page 1) + (7 columns in page 2) + (2 columns in page 3) = 16.

[row,col,v] = find(X, ...) returns a column or row vector v of the nonzero entries in X, as well as row and column indices. If X is a logical expression, then v is a logical array. Output v contains the non-zero elements of the logical array obtained by evaluating the expression X. For example,

```
A= magic(4)
A =
16 2 3 13
5 11 10 8
```

Here the returned vector \boldsymbol{v} is a logical array that contains the nonzero elements of \boldsymbol{N} where

$$N = (A > 10)$$

Examples Example 1

$$X = [1 \ 0 \ 4 \ -3 \ 0 \ 0 \ 0 \ 8 \ 6];$$

indices = find(X)

returns linear indices for the nonzero entries of X.

Example 2

You can use a logical expression to define X. For example,

returns linear indices corresponding to the entries of \boldsymbol{X} that are greater than 2.

Example 3

The following find command

```
X = [3 \ 2 \ 0; -5 \ 0 \ 7; \ 0 \ 0 \ 1];

[r,c,v] = find(X)
```

returns a vector of row indices of the nonzero entries of X

a vector of column indices of the nonzero entries of X

and a vector containing the nonzero entries of X.

Example 4

The expression

returns a vector of row indices of the nonzero entries of N where N=(X>2)

```
r = 1 2
```

a vector of column indices of the nonzero entries of N where N=(X>2)

```
c = 1 3
```

and a logical array that contains the nonzero elements of N where N=(X>2).

```
v = 1
1
```

Recall that when you use find on a logical expression, the output vector v does not contain the nonzero entries of the input array. Instead, it contains the nonzero values returned after evaluating the logical expression.

Example 5

Some operations on a vector

```
x = [11 0 33 0 55]';
find(x)
ans =
    1
    3
    5

find(x == 0)
ans =
    2
```

```
4
find(0 < x & x < 10*pi)
ans =
    1</pre>
```

Example 6

For the matrix

returns the indices of the first four entries of M that are greater than 3.

```
ans = 1 3 5 6
```

Example 7

If X is a vector of all zeros, $\mbox{find}(X)$ returns an empty matrix. For example,

```
indices = find([0;0;0])
indices =
   Empty matrix: 0-by-1
```

See Also

nonzeros, sparse, colon, logical operators (elementwise and short-circuit), relational operators, ind2sub

```
Purpose
                   Find all graphics objects
Syntax
                   object handles = findall(handle list)
                   object handles = findall(handle list, 'property', 'value',...)
Description
                   object handles = findall(handle list) returns the handles,
                   including hidden handles, of all objects in the hierarchy under the
                   objects identified in handle list.
                   object handles =
                   findall(handle list, 'property', 'value',...) returns
                   the handles of all objects in the hierarchy under the objects
                   identified in handle list that have the specified properties set to
                   the specified values.
Remarks
                   findall is similar to findobj, except that it finds objects even if their
                   HandleVisibility is set to off.
Examples
                     plot(1:10)
                     xlabel xlab
                     a = findall(gcf)
                     b = findobj(gcf)
                     c = findall(b, 'Type', 'text') % return the xlabel handle twice
                     d = findobj(b, 'Type', 'text') % can't find the xlabel handle
See Also
```

allchild, findobj

Purpose Find visible offscreen figures

Syntax findfigs

Description findfigs finds all visible figure windows whose display area is off the

screen and positions them on the screen.

A window appears to the MATLAB software to be offscreen when its display area (the area not covered by the window's title bar, menu bar,

and toolbar) does not appear on the screen.

This function is useful when you are bringing an application from a larger monitor to a smaller one (or one with lower resolution). Windows visible on the larger monitor may appear offscreen on a smaller monitor.

Using findfigs ensures that all windows appear on the screen.

See Also "Graphics Object Identification" on page 1-103 for related functions.

Locate graphics objects with specific properties

Syntax

Description

findobj returns handles of the root object and all its descendants without assigning the result to a variable.

h = findobj returns handles of the root object and all its descendants.

h = findobj('PropertyName', PropertyValue,...) returns handles of all graphics objects having the property PropertyName, set to the value PropertyValue. You can specify more than one property/value pair, in which case, findobj returns only those objects having all specified values.

h =

findobj('PropertyName', PropertyValue,'-logicaloperator', PropertyName', PropertyValue,...) applies the logical operator to the property value matching. Possible values for -logicaloperator are:

- and
- -or
- -xor
- -not

See "Logical Operators" for an explanation of logical operators.

h = findobj('-regexp','PropertyName','regexp',...) matches objects using regular expressions as if the value of you passed the property PropertyName to the regexp function as

```
regexp(PropertyValue, 'regexp')
```

If a match occurs, findobj returns the object handle. See the regexp function for information on how the MATLAB software uses regular expressions.

h = findobj('-property','*PropertyName*') finds all objects having the specified property.

h = findobj(objhandles,...) restricts the search to objects listed in objhandles and their descendants.

h = findobj(objhandles,'-depth',d,...) specifies the depth of the search. The depth argument d controls how many levels under the handles in objhandles MATLAB traverses. Specify d as inf to get the default behavior of all levels. Specify d as 0 to get the same behavior as using the flat argument.

h =

findobj(objhandles, 'flat', '*PropertyName*', PropertyValue,...) restricts the search to those objects listed in objhandles and does not search descendants.

findobj returns an error if a handle refers to a nonexistent graphics object.

findobj correctly matches any legal property value. For example,

```
findobj('Color','r')
```

finds all objects having a Color property set to red, r, or [1 0 0].

When a graphics object is a descendant of more than one object identified in objhandles, MATLAB searches the object each time findobj encounters its handle. Therefore, implicit references to a graphics object can result in multiple returns of its handle.

To find handle objects that meet specified conditions, use handle.findobj.

Examples

Find all line objects in the current axes:

```
h = findobj(gca, 'Type', 'line')
```

Find all objects having a Label set to 'foo' and a String set to 'bar':

```
h = findobj('Label','foo','-and','String','bar');
```

Find all objects whose String is not 'foo' and is not 'bar':

```
h = findobj('-not', 'String', 'foo', '-not', 'String', 'bar');
```

Find all objects having a String set to 'foo' and a Tag set to 'button one' and whose Color is not 'red' or 'blue':

```
h = findobj('String','foo','-and','Tag','button one',...
'-and','-not',{'Color','red','-or','Color','blue'})
```

Find all objects for which you have assigned a value to the Tag property (that is, the value is not the empty string ''):

```
h = findobj('-regexp','Tag','[^'']')
```

Find all children of the current figure that have their BackgroundColor property set to a certain shade of gray ([.7 .7 .7]). This statement also searches the current figure for the matching property value pair.

```
h = findobj(gcf, '-depth', 1, 'BackgroundColor', [.7 .7 .7])
```

findobj

See Also

Tutorials

• "Example — Using Logical Operators and Regular Expression"

findobj (handle)

Purpose Find handle objects matching specified conditions

Syntax Hmatch = findobj(Hobj, <conditions>)

Description Hmatch = findobj(Hobj, <conditions>) finds handle class objects

that meet the specified conditions. The Hobj argument must be an array of handle objects. The returned value, Hmatch contains an array

of handles matching the conditions.

findobj has access only to public members of the objects in Hobj. See "Finding Handle Objects" for more information on using findobj.

See the Handle Graphics findobj function for information on specifying conditions. You cannot use regular expression with handle class objects.

See Also findprop, handle

```
Purpose
                  Find meta.property object associated with property name
Syntax
                  p = findprop(h,'Name')
Description
                  p = findprop(h, 'Name') returns the meta.property object associated
                  with the property Name of the object h. Name can be a property defined
                  by the class of h or a dynamic property defined only for the object h.
Examples
                  Use findprop to view property attribute settings:
                     findprop(containers.Map, 'Count')
                     ans =
                       meta.property handle
                       Package: meta
                       Properties:
                                         Name: 'Count'
                                  Description: 'Number of pairs in the collection'
                         DetailedDescription: ''
                                    GetAccess: 'public'
                                    SetAccess: 'private'
                                    Dependent: 1
                                     Constant: 0
                                     Abstract: 0
                                    Transient: 1
                                       Hidden: 0
                                GetObservable: 0
                                SetObservable: 0
                                     AbortSet: 0
                                    GetMethod: []
                                    SetMethod: []
                                DefiningClass: [1x1 meta.class]
                       Methods, Events, Superclasses
```

findprop (handle)

See Also

"Obtaining Information About Classes from Meta-Classes"

"Getting Information About Properties"

"Dynamic Properties — Adding Properties to an Instance"

handle, findobj (handle), meta.property

Find string within another, longer string

Note findstr is not recommended. Use strfind instead.

Syntax

```
k = findstr(str1, str2)
```

Description

k = findstr(str1, str2) searches the longer of the two input strings
for any occurrences of the shorter string, returning the starting index of
each such occurrence in the double array k. If no occurrences are found,
then findstr returns the empty array, [].

The search performed by findstr is case sensitive. Any leading and trailing blanks in either input string are explicitly included in the comparison.

Unlike the strfind function, the order of the input arguments to findstr is not important. This can be useful if you are not certain which of the two input strings is the longer one.

Examples

s = 'Find the starting indices of the shorter string.';

See Also

strfind, strtok, strcmp, strncmp, strcmpi, strncmpi, regexp, regexpi, regexprep

Termination M-file for MATLAB program

Description

When the MATLAB program quits, it runs a script called finish.m, if the script exists and is on the search path MATLAB uses or in the current directory. This is a file you create yourself that instructs MATLAB to perform any final tasks just prior to terminating. For example, you might want to save the data in your workspace to a MATLAB exits

finish.m is invoked whenever you do one of the following:

- Click the Close box **≥** in the MATLAB desktop on Microsoft Windows platforms or the equivalent on UNIX⁵ platforms
- Select Exit MATLAB from the desktop File menu
- Type quit or exit at the Command Window prompt

Remarks

When using Handle Graphics features in finish.m, use uiwait, waitfor, or drawnow so that figures are visible. See the reference pages for these functions for more information.

Examples

Two sample finish.m files are provided with MATLAB in <code>matlabroot/toolbox/local</code>. Use them to help you create your own finish.m, or rename one of the files to finish.m and add it to the path to use it:

- finishsav.m Saves the workspace to a MAT-file when MATLAB quits.
- finishdlg.m Displays a dialog allowing you to cancel quitting and saves the workspace. See also the "Confirmation Dialogs Preferences" and the option for exiting MATLAB.

See Also

quit, exit, startup

5. UNIX is a registered trademark of The Open Group in the United States and other countries.

finish

"Quitting the MATLAB Program" in the MATLAB Desktop Tools and Development Environment documentation

fitsinfo

Purpose

Information about FITS file

Syntax

info = fitsinfo(filename)

Description

info = fitsinfo(filename) returns the structure, info, with fields that contain information about the contents of a Flexible Image Transport System (FITS) file. filename is a string enclosed in single quotes that specifies the name of the FITS file.

The info structure contains the following fields, listed in the order they appear in the structure. In addition, the info structure can also contain information about any number of optional file components, called *extensions* in FITS terminology. For more information, see "FITS File Extensions" on page 2-1515.

Field Name	Description	Return Type
Filename	Name of the file	String
FileModDate	File modification date	String
FileSize	Size of the file in bytes	Double
Contents	List of extensions in the file in the order that they occur	Cell array of strings
PrimaryData	Information about the primary data in the FITS file	Structure array

PrimaryData

The PrimaryData field is a structure that describes the primary data in the file. The following table lists the fields in the order they appear in the structure.

Field Name	Description	Return Type
DataType	Precision of the data	String
Size	Array containing the size of each dimension	Double array

Field Name	Description	Return Type
DataSize	Size of the primary data in bytes	Double
MissingDataValue	Value used to represent undefined data	Double
Intercept	Value, used with Slope, to calculate actual pixel values from the array pixel values, using the equation: actual_value = Slope*array_value + Intercept	Double
Slope	Value, used with Intercept, to calculate actual pixel values from the array pixel values, using the equation: actual_value = Slope*array_value + Intercept	Double
Offset	Number of bytes from beginning of the file to the location of the first data value	Double
Keywords	A number-of-keywords-by-3 cell array containing keywords, values, and comments of the header in each column	Cell array of strings

FITS File Extensions

A FITS file can also include optional extensions. If the file contains any of these extensions, the info structure can contain these additional fields.

• AsciiTable — Numeric information in tabular format, stored as ASCII characters

- BinaryTable Numeric information in tabular format, stored in binary representation
- Image A multidimensional array of pixels
- Unknown Nonstandard extension

AsciiTable Extension

The AsciiTable structure contains the following fields, listed in the order they appear in the structure.

Field Name	Description	Return Type
Rows	Number of rows in the table	Double
RowSize	Number of characters in each row	Double
NFields	Number of fields in each row	Double array
FieldFormat	A 1-by-NFields cell containing formats in which each field is encoded. The formats are FORTRAN-77 format codes.	Cell array of strings
FieldPrecision	A 1-by-NFields cell containing precision of the data in each field	Cell array of strings
FieldWidth	A 1-by-NFields array containing the number of characters in each field	Double array
FieldPos	A 1-by-NFields array of numbers representing the starting column for each field	Double array
DataSize	Size of the data in the table in bytes	Double
MissingDataValue	A 1-by-NFields array of numbers used to represent undefined data in each field	Cell array of strings

Field Name	Description	Return Type
Intercept	A 1-by-NFields array of numbers used along with Slope to calculate actual data values from the array data values using the equation: actual_value = Slope*array_value+Intercept	Double array
Slope	A 1-by-NFields array of numbers used with Intercept to calculate true data values from the array data values using the equation: actual_value = Slope*array_value+Intercept	Double array
Offset	Number of bytes from beginning of the file to the location of the first data value in the table	Double
Keywords	A number-of-keywords-by-3 cell array containing all the Keywords, Values and Comments in the ASCII table header	Cell array of strings

BinaryTable Extension

The BinaryTable structure contains the following fields, listed in the order they appear in the structure.

Field Name	Description	Return Type
Rows	Number of rows in the table	Double
RowSize	Number of bytes in each row	Double
NFields	Number of fields in each row	Double

Field Name	Description	Return Type
FieldFormat	A 1-by-NFields cell array containing the data type of the data in each field. The data type is represented by a FITS binary table format code.	Cell array of strings
FieldPrecision	A 1-by-NFields cell containing precision of the data in each field	Cell array of strings
FieldSize	A 1-by-NFields array, where each element contains the number of values in the Nth field	Double array
DataSize	Size of the data in the Binary Table, in bytes. Includes any data past the main table.	Double
MissingDataValue	An 1-by-NFields array of numbers used to represent undefined data in each field	Cell array of double
Intercept	A 1-by-NFields array of numbers used along with Slope to calculate actual data values from the array data values using the equation: actual_value = slope*array_value+Intercept	Double array
Slope	A 1-by-NFields array of numbers used with Intercept to calculate true data values from the array data values using the equation: actual_value = Slope*array_value+Intercept	Double array

Field Name	Description	Return Type
Offset	Number of bytes from beginning of the file to the location of the first data value	Double
ExtensionSize	Size of any data past the main table, in bytes	Double
ExtensionOffset	Number of bytes from the beginning of the file to any data past the main table	Double
Keywords	A number-of-keywords-by-3 cell array containing all the Keywords, values, and comments in the Binary Table header	Cell array of strings

Image Extension

The ${\tt Image}$ structure contains the following fields, listed in the order they appear in the structure.

Field Name	Description	Return Type
DataType	Precision of the data	String
Size	Array containing sizes of each dimension	Double array
DataSize	Size of the data in the Image extension in bytes	Double
Offset	Number of bytes from the beginning of the file to the first data value	Double
MissingDataValue	Value used to represent undefined data	Double

Field Name	Description	Return Type
Intercept	Value, used with Slope, to calculate actual pixel values from the array pixel values, using the equation: actual_value = Slope*array_value+Intercept	Double
Slope	Value, used with Intercept, to calculate actual pixel values from the array pixel values, using the equation: actual_value = Slope*array_value + Intercept	Double
Keywords	A number-of-keywords-by-3 cell array containing all the Keywords, values, and comments in the Binary Table header	Cell array of strings

Unknown Structure

The $\mbox{Unknown}$ structure contains the following fields, listed in the order they appear in the structure.

Field Name	Description	Return Type
DataType	Precision of the data	String
Size	Sizes of each dimension	Double array
DataSize	Size of the data in nonstandard extensions, in bytes	Double
Offset	Number of bytes from beginning of the file to the first data value	Double

Field Name	Description	Return Type
MissingDataValue	Representation of undefined data	Double
Intercept	Value, used with Slope, to calculate actual data values from the array data values, using the equation: actual_value = Slope*array_value+Intercept	Double
Slope	Value, used with Intercept, to calculate actual data values from the array data values, using the equation: actual_value = Slope*array_value+Intercept	Double
Keywords	A number-of-keywords-by-3 cell array containing all the Keywords, values, and comments in the Binary Table header	Cell array of strings

Example

Use fitsinfo to obtain information about the FITS file tst0012.fits. In addition to its primary data, the file also contains an example of the extensions BinaryTable, Unknown, Image, and AsciiTable.

```
Unknown: [1x1 struct]
Image: [1x1 struct]
AsciiTable: [1x1 struct]
```

The PrimaryData field describes the data in the file. For example, the Size field indicates the data is a 102-by-109 matrix.

```
S.PrimaryData

DataType: 'single'
Size: [102 109]
DataSize: 44472

MissingDataValue: []
Intercept: 0
Slope: 1
Offset: 2880
Keywords: {25x3 cell}
```

The AsciiTable field describes the AsciiTable extension. For example, using the FieldWidth and FieldPos fields you can determine the length and location of each field within a row.

See Also fitsread

Read data from FITS file

Syntax

data = fitsread(filename)

data = fitsread(filename,extname)

data = fitsread(filename,extname,index)

data = fitsread(filename, 'raw')

data = fitsread(filename, 'info', info struct)

Description

data = fitsread(filename) reads the primary data of the Flexible Image Transport System (FITS) file specified by the text string filename. The function replaces undefined data values with NaN and scales numeric data by the slope and intercept values, always returning double precision values.

data = fitsread(filename, extname) reads data from the FITS file extension specified by extname. You can specify any of the following values for extname.

Data Arrays or Extensions

Extname	Description
'primary'	Read data from the primary data array.
'table'	Read data from the ASCII Table extension. The return value, data, is a 1-D cell array.
'bintable'	Read data from the Binary Table extension. The return value, data, is a 1-D cell array.
'image'	Read data from the Image extension.
'unknown'	Read data from the Unknown extension.

data = fitsread(filename,extname,index) reads data from the FITS file extension specified by extname and index. If there is more than one of the specified extensions in the file, index specifies the one to read.

data = fitsread(filename, 'raw') reads the primary or extension data of the FITS file, but, unlike the above syntaxes, does not replace undefined data values with NaN and does not scale the data. The data returned has the same class as the data stored in the file.

data = fitsread(filename, 'info', info_struct) reads data from FITS file where 'info' specifies the location of the data in the file. info_struct is the structure returned by fitsinfo.

Note Using the info structure returned by fitsinfo to specify the location of data in a FITS file can significantly improve performance, especially when reading multiple images from the file.

Example

Read FITS file tst0012.fits into a 109-by-102 matrix called data.

Here is the beginning of the data read from the file.

```
data(1:5,1:6)
ans =
  135.200
           134.9436
                     134.1752
                                132.8980
                                          131.1165
                                                    128.8378
  137.568
           134.9436
                     134.1752
                                132.8989
                                          131.1167
                                                    126.3343
 135.9946
           134.9437
                     134.1752
                                132.8989
                                          131.1185
                                                    128.1711
 134.0093
           134.9440
                     134.1749
                                132.8983
                                          131.1201
                                                     126.3349
 131.5855
           134.9439
                     134.1749
                                132.8989
                                          131.1204
                                                    126.3356
```

Read only the Binary Table extension from the file.

```
data = fitsread('tst0012.fits', 'bintable')
data =
```

```
Columns 1 through 4
{11x1 cell} [11x1 int16] [11x3 uint8] [11x2 double]

Columns 5 through 9
[11x3 cell] {11x1 cell} [11x1 int8] {11x1 cell} [11x3 int32]

Columns 10 through 13
[11x2 int32] [11x2 single] [11x1 double] [11x1 uint8]
```

See Also fitsinfo

Round toward zero

Syntax

B = fix(A)

Description

B = fix(A) rounds the elements of A toward zero, resulting in an array of integers. For complex A, the imaginary and real parts are rounded independently.

Examples

```
a =
Columns 1 through 4
-1.9000 -0.2000 3.4000 5.6000

Columns 5 through 6
7.0000 2.4000 + 3.6000i
```

5.0000

fix(a)
ans =

Columns 1 through 4 -1.0000 0 3.0000

a = [-1.9, -0.2, 3.4, 5.6, 7.0, 2.4+3.6i]

Columns 5 through 6 7.0000 2.0000 + 3.0000i

See Also

ceil, floor, round

Purpose Flip array along specified dimension

Syntax B = flipdim(A,dim)

Description B = flipdim(A,dim) returns A with dimension dim flipped.

When the value of dim is 1, the array is flipped row-wise down. When dim is 2, the array is flipped columnwise left to right. flipdim(A,1) is the same as flipud(A), and flipdim(A,2) is the same as fliplr(A).

Examples flipdim(A,1) where

A =

1 4 2 5 3 6

produces

3 6 2 5 1 4

See Also fliplr, flipud, permute, rot90

fliplr

Purpose

Flip matrix left to right

Syntax

B = fliplr(A)

Description

B = fliplr(A) returns A with columns flipped in the left-right direction, that is, about a vertical axis.

If A is a row vector, then fliplr(A) returns a vector of the same length with the order of its elements reversed. If A is a column vector, then fliplr(A) simply returns A.

Examples

If A is the 3-by-2 matrix,

A =

1 4
2 5
3 6

then fliplr(A) produces

4 1 5 2 6 3

If A is a row vector,

A = 1 3 5 7 9

then fliplr(A) produces

9 7 5 3 1

Limitations

The array being operated on cannot have more than two dimensions. This limitation exists because the axis upon which to flip a multidimensional array would be undefined.

See Also

flipdim, flipud, rot90

Flip matrix up to down

Syntax

B = flipud(A)

Description

B = flipud(A) returns A with rows flipped in the up-down direction, that is, about a horizontal axis.

If A is a column vector, then flipud(A) returns a vector of the same length with the order of its elements reversed. If A is a row vector, then flipud(A) simply returns A.

Examples

If A is the 3-by-2 matrix,

A = 1 2

then flipud(A) produces

5 6

3 6 2 5 1 4

If A is a column vector,

A = 3 5 7

then flipud(A) produces

A = 7 5 3

flipud

Limitations The array being operated on cannot have more than two dimensions.

This limitation exists because the axis upon which to flip a

multidimensional array would be undefined.

See Also flipdim, fliplr, rot90

5.6000

5.0000

Purpose

Round toward negative infinity

Syntax

B = floor(A)

Description

B = floor(A) rounds the elements of A to the nearest integers less than or equal to A. For complex A, the imaginary and real parts are rounded independently.

Examples

$$a = [-1.9, -0.2, 3.4, 5.6, 7.0, 2.4+3.6i]$$

a =

Columns 1 through 4

-1.9000 -0.2000

3.4000

0....

Columns 5 through 6

7.0000

2.4000 + 3.6000i

floor(a)

ans =

Columns 1 through 4

-2.0000 -1.0000

3.0000

Columns 5 through 6

7.0000

2.0000 + 3.0000i

See Also

ceil, fix, round

Simple function of three variables

Syntax

```
v = flow
v = flow(n)
v = flow(x,y,z)
[x,y,z,v] = flow(...)
```

Description

flow, a function of three variables, generates fluid-flow data that is useful for demonstrating slice, interp3, and other functions that visualize scalar volume data.

v = flow produces a 50-by-25-by-25 array.

v = flow(n) produces a n-by-2n-by-n array.

v = flow(x,y,z) evaluates the speed profile at the points x, y, and z.

[x,y,z,v] = flow(...) returns the coordinates as well as the volume data.

See Also

slice, interp3

"Volume Visualization" on page 1-111 for related functions

See "Example - Slicing Fluid Flow Data" for an example that uses flow.

Find minimum of single-variable function on fixed interval

Syntax

```
x = fminbnd(fun,x1,x2)
x = fminbnd(fun,x1,x2,options)
[x,fval] = fminbnd(...)
[x,fval,exitflag] = fminbnd(...)
[x,fval,exitflag,output] = fminbnd(...)
```

Description

fminbnd finds the minimum of a function of one variable within a fixed interval

x = fminbnd(fun,x1,x2) returns a value x that is a local minimizer of the function that is described in fun in the interval x1 < x < x2. fun is a function handle. See "Function Handles" in the MATLAB Programming documentation for more information.

"Parameterizing Functions" in the MATLAB Mathematics documentation, explains how to pass additional parameters to your objective function fun.

x = fminbnd(fun,x1,x2,options) minimizes with the optimization parameters specified in the structure options. You can define these parameters using the optimset function. fminbnd uses these options structure fields:

Display Level of display. 'off' displays no output; 'iter'

displays output at each iteration; 'final' displays just the final output; 'notify' (default) displays output only if the function does not converge.

FunValCheck Check whether objective function values are valid.

'on' displays an error when the objective function returns a value that is complex or NaN. 'off'

displays no error.

MaxFunEvals Maximum number of function evaluations allowed.

MaxIter Maximum number of iterations allowed.

fminbnd

OutputFcn	User-defined function that is called at each iteration. See "Output Functions" in MATLAB Mathematics for more information.	
PlotFcns	Plots various measures of progress while the algorithm executes, select from predefined plots or write your own. Pass a function handle or a cell array of function handles. The default is none ([]).	
	• @optimplotx plots the current point	
	• @optimplotfval plots the function value	
	• @optimplotfunccount plots the function count	
	See "Plot Functions" in MATLAB Mathematics for more information.	
TolX	Termination tolerance on x.	
[x,fval] = fminbnd() returns the value of the objective function computed in fun at x.		
<pre>[x,fval,exitflag] = fminbnd() returns a value exitflag that describes the exit condition of fminbnd:</pre>		
1	fminbnd converged to a solution x based on options.TolX.	
0	Maximum number of function evaluations or iterations was reached.	
- 1	Algorithm was terminated by the output function.	
- 2	Bounds are inconsistent $(x1 > x2)$.	
[x,fval,exitflag,output] = fminbnd() returns a structure output that contains information about the optimization in the following fields:		

algorithm Algorithm used

funcCount Number of function evaluations

iterations Number of iterations

message Exit message

Arguments

fun is the function to be minimized. fun accepts a scalar x and returns a scalar f, the objective function evaluated at x. The function fun can be specified as a function handle for an M-file function

```
x = fminbnd(@myfun, x1, x2);
```

where myfun.m is an M-file function such as

or as a function handle for an anonymous function:

```
x = fminbnd(@(x) sin(x*x),x1,x2);
```

Other arguments are described in the syntax descriptions above.

Examples

x = fminbnd(@cos,3,4) computes π to a few decimal places and gives a message on termination.

```
[x,fval,exitflag] = ...
fminbnd(@cos,3,4,optimset('TolX',1e-12,'Display','off'))
```

computes π to about 12 decimal places, suppresses output, returns the function value at x, and returns an exitflag of 1.

The argument fun can also be a function handle for an anonymous function. For example, to find the minimum of the function $f(x) = x^3 - 2x - 5$ on the interval (0,2), create an anonymous function f

$$f = @(x)x.^3-2*x-5;$$

Then invoke fminbnd with

```
x = fminbnd(f, 0, 2)
```

The result is

$$x = 0.8165$$

The value of the function at the minimum is

$$y = f(x)$$
 $y = -6.0887$

If fun is parameterized, you can use anonymous functions to capture the problem-dependent parameters. For example, suppose you want to minimize the objective function myfun defined by the following M-file function.

```
function f = myfun(x,a)

f = (x - a)^2;
```

Note that myfun has an extra parameter a, so you cannot pass it directly to fminbind. To optimize for a specific value of a, such as a = 1.5.

1 Assign the value to a.

```
a = 1.5; % define parameter first
```

2 Call fminbnd with a one-argument anonymous function that captures that value of a and calls myfun with two arguments:

```
x = fminbnd(@(x) myfun(x,a),0,1)
```

Algorithm

fminbnd is an M-file. The algorithm is based on golden section search and parabolic interpolation. Unless the left endpoint x_1 is very close to the right endpoint x_2 , fminbnd never evaluates fun at the endpoints,

so fun need only be defined for x in the interval $x_1 < x < x_2$. If the minimum actually occurs at x_1 or x_2 , fminbnd returns an interior point at a distance of no more than 2*To1X from x_1 or x_2 , where To1X is the termination tolerance. See [1] or [2] for details about the algorithm.

Limitations

The function to be minimized must be continuous. fminbnd may only give local solutions.

fminbnd often exhibits slow convergence when the solution is on a boundary of the interval.

fminbnd only handles real variables.

See Also

fminsearch, fzero, optimset, function_handle (@), anonymous function

References

[1] Forsythe, G. E., M. A. Malcolm, and C. B. Moler, *Computer Methods for Mathematical Computations*, Prentice-Hall, 1976.

[2] Brent, Richard. P., Algorithms for Minimization without Derivatives, Prentice-Hall, Englewood Cliffs, New Jersey, 1973

fminsearch

Purpose

Find minimum of unconstrained multivariable function using derivative-free method

Syntax

```
x = fminsearch(fun,x0)
x = fminsearch(fun,x0,options)
[x,fval] = fminsearch(...)
[x,fval,exitflag] = fminsearch(...)
[x,fval,exitflag,output] = fminsearch(...)
```

Description

fminsearch finds the minimum of a scalar function of several variables, starting at an initial estimate. This is generally referred to as *unconstrained nonlinear optimization*.

x = fminsearch(fun,x0) starts at the point x0 and returns a value x that is a local minimizer of the function described in fun. x0 can be a scalar, vector, or matrix. fun is a function handle. See "Function Handles" in the MATLAB Programming documentation for more information.

"Parameterizing Functions" in the MATLAB Mathematics documentation explains how to pass additional parameters to your objective function fun. See also "Example 2" on page 2-1541 and "Example 3" on page 2-1541 below.

x = fminsearch(fun,x0,options) minimizes with the optimization parameters specified in the structure options. You can define these parameters using the optimset function. fminsearch uses these options structure fields:

Display Level of display. 'off' displays no output; 'iter'

displays output at each iteration; 'final' displays just the final output; 'notify' (default) displays output only if the function does not converge.

FunValCheck Check whether objective function values are valid.

 $\mbox{'on'}$ displays an error when the objective function returns a value that is complex, Inf or NaN. $\mbox{'off'}$

(the default) displays no error.

fminsearch

MaxFunEvals Maximum number of function evaluations allowed MaxIter Maximum number of iterations allowed User-defined function that is called at each OutputFcn iteration. See "Output Functions" in MATLAB Mathematics for more information. **PlotFcns** Plots various measures of progress while the algorithm executes, select from predefined plots or write your own. Pass a function handle or a cell array of function handles. The default is none ([]). • @optimplotx plots the current point • @optimplotfval plots the function value • @optimplotfunccount plots the function count See "Plot Functions" in MATLAB Mathematics for more information. TolFun Termination tolerance on the function value TolX Termination tolerance on x [x,fval] = fminsearch(...) returns in fval the value of the objective function fun at the solution x. [x,fval,exitflag] = fminsearch(...) returns a value exitflag that describes the exit condition of fminsearch: 1 fminsearch converged to a solution x. 0 Maximum number of function evaluations or iterations was reached. - 1 Algorithm was terminated by the output function.

[x,fval,exitflag,output] = fminsearch(...) returns a structure output that contains information about the optimization in the following fields:

fminsearch

algorithm 'Nelder-Mead simplex direct search'

funcCount Number of function evaluations

iterations Number of iterations

message Exit message

Arguments

fun is the function to be minimized. It accepts an input x and returns a scalar f, the objective function evaluated at x. The function fun can be specified as a function handle for an M-file function

```
x = fminsearch(@myfun, x0)
```

where myfun is an M-file function such as

```
function f = myfun(x)
f = ... % Compute function value at x
```

or as a function handle for an anonymous function, such as

$$x = fminsearch(@(x)sin(x^2), x0);$$

Other arguments are described in the syntax descriptions above.

Examples

Example 1

The Rosenbrock banana function is a classic test example for multidimensional minimization:

$$f(x) = 100(x_2 - x_1^2)^2 + (1 - x_1)^2$$
.

The minimum is at (1,1) and has the value 0. The traditional starting point is (-1.2,1). The anonymous function shown here defines the function and returns a function handle called banana:

banana =
$$@(x)100*(x(2)-x(1)^2)^2+(1-x(1))^2$$
;

Pass the function handle to fminsearch:

```
[x,fval] = fminsearch(banana,[-1.2, 1])
This produces
  x =
     1.0000    1.0000
fval =
     8.1777e-010
```

This indicates that the minimizer was found to at least four decimal places with a value near zero.

Example 2

If fun is parameterized, you can use anonymous functions to capture the problem-dependent parameters. For example, suppose you want to minimize the objective function myfun defined by the following M-file function.

```
function f = myfun(x,a)

f = x(1)^2 + a*x(2)^2;
```

Note that myfun has an extra parameter a, so you cannot pass it directly to fminsearch. To optimize for a specific value of a, such as a = 1.5.

1 Assign the value to a.

```
a = 1.5; % define parameter first
```

2 Call fminsearch with a one-argument anonymous function that captures that value of a and calls myfun with two arguments:

```
x = fminsearch(@(x) myfun(x,a),[0,1])
```

Example 3

You can modify the first example by adding a parameter *a* to the second term of the banana function:

$$f(x) = 100(x_2 - x_1^2)^2 + (a - x_1)^2$$
.

This changes the location of the minimum to the point $[a,a^2]$. To minimize this function for a specific value of a, for example a = sqrt(2), create a one-argument anonymous function that captures the value of a.

```
a = sqrt(2);
banana = @(x)100*(x(2)-x(1)^2)^2+(a-x(1))^2;
```

Then the statement

```
[x,fval] = fminsearch(banana, [-1.2, 1], ...
  optimset('TolX',1e-8));
```

seeks the minimum [sqrt(2), 2] to an accuracy higher than the default on x.

Algorithm

fminsearch uses the simplex search method of Lagarias et al. [1]. This is a direct search method that does not use numerical or analytic gradients.

If n is the length of x, a simplex in n-dimensional space is characterized by the n+1 distinct vectors that are its vertices. In two-space, a simplex is a triangle; in three-space, it is a pyramid. At each step of the search, a new point in or near the current simplex is generated. The function value at the new point is compared with the function's values at the vertices of the simplex and, usually, one of the vertices is replaced by the new point, giving a new simplex. This step is repeated until the diameter of the simplex is less than the specified tolerance.

For more information, see "fminsearch Algorithm".

Limitations

fminsearch can often handle discontinuity, particularly if it does not occur near the solution. fminsearch may only give local solutions.

fminsearch only minimizes over the real numbers, that is, x must only consist of real numbers and f(x) must only return real numbers. When x has complex variables, they must be split into real and imaginary parts.

See Also

fminbnd, optimset, function_handle (@), anonymous function

References

[1] Lagarias, J.C., J. A. Reeds, M. H. Wright, and P. E. Wright, "Convergence Properties of the Nelder-Mead Simplex Method in Low Dimensions," *SIAM Journal of Optimization*, Vol. 9 Number 1, pp. 112-147, 1998.

Purpose

Open file, or obtain information about open files

Syntax

Description

fileID = fopen(filename) opens the file filename for read access,
and returns an integer file identifier.

fileID = fopen(filename, permission) opens the file with the
specified permission.

fileID = fopen(filename, permission, machineformat) specifies
the order for reading or writing bytes or bits in the file.

fileID = fopen(filename, permission, machineformat,
encoding) specifies the character encoding scheme associated with
the file.

[fileID, message] = fopen(filename, ...) opens a file. If the operation fails, message is a system-dependent error message. Otherwise, message is an empty string.

fIDs = fopen('all') returns a row vector containing the file identifiers of all open files.

[filename, permission, machineformat, encoding] = fopen(fileID) returns the file name, permission, machine format, and encoding that a previous call to fopen used when it opened the specified file. fopen does not read information from the file to determine these output values. An invalid fileID returns empty strings for all output arguments.

Input Arguments

filename

String in single quotation marks that specifies the name of the file to open. Can include a full or partial path.

On UNIX systems, if filename begins with '~/' or '~username/', the fopen function expands the path to the current or specified user's home directory, respectively.

If you open a file with read access and fopen cannot find *filename* in the current folder, fopen searches along the MATLAB search path. Otherwise, fopen creates a file in the current directory.

permission

String that describes the type of access for the file: read, write, append, or update. Also specifies whether to open files in binary or text mode.

To open files in binary mode, specify one of the following:

'r'	Open file for reading (default).
' W '	Open or create new file for writing. Discard existing contents, if any.
'a'	Open or create new file for writing. Append data to the end of the file.
'r+'	Open file for reading and writing.
' W+ '	Open or create new file for reading and writing. Discard existing contents, if any.
'a+'	Open or create new file for reading and writing. Append data to the end of the file.
'A'	Append without automatic flushing. (Used with tape drives.)
' W '	Write without automatic flushing. (Used with tape drives.)

To read and write to the same file:

fopen

- Open the file in update mode (with a *permission* that includes a plus sign, '+').
- Call fseek or frewind between read and write operations.
 For example, do not call fread followed by fwrite, or fwrite followed by fread, unless you call fseek or frewind between them.

To open files in text mode, attach the letter 't' to the *permission*, such as 'rt' or 'wt+'. For better performance, do not use text mode. The following applies on Windows systems, in text mode:

- Read operations that encounter a carriage return followed by a newline character ('\r\n') remove the carriage return from the input.
- Write operations insert a carriage return before any newline character in the output.

This additional processing is unnecessary for most cases. All MATLAB import functions, and most text editors (including Microsoft Word and WordPad), recognize both '\r\n' and '\n' as newline sequences. However, when you create files for use in Microsoft Notepad, end each line with '\r\n'. For an example, see fprintf.

machineformat

String that specifies the order for reading or writing bytes or bits in the file. Specify machineformat to:

- Read a file created on a different system.
- Read bits in a particular order.
- Create a file for use on a different system.

Possible values are:

'n' or 'native'	The byte ordering that your system uses (default)
'b' or 'ieee-be'	Big-endian ordering
'l' or 'ieee-le'	Little-endian ordering
's' or 'ieee-be.164'	Big-endian ordering, 64-bit data type
'a' or 'ieee-le.164'	Little-endian ordering, 64-bit data type

Windows systems use little-endian ordering, and most UNIX systems use big-endian ordering, for both bytes and bits.

encoding

String that specifies the character encoding scheme to use for subsequent read and write operations, including fscanf, fprintf, fgetl, fgets, fread, and fwrite.

Possible values are:

'Big5'	'ISO-8859-1'	'windows-932'
'EUC-JP'	'ISO-8859-2'	'windows-936'
'GBK'	'ISO-8859-3'	'windows-949'
'Shift_JIS'	'ISO-8859-4'	'windows-950'
'US-ASCII'	'ISO-8859-9'	'windows-1250'
'UTF-8'	'ISO-8859-13'	'windows-1251'
	'ISO-8859-15'	'windows-1252'
		'windows-1253'
		'windows-1254'
		'windows-1257'

Default: system-dependent

Output Arguments

fileID

An integer that identifies the file for all subsequent low-level file I/O operations. If fopen cannot open the file, *fileID* is -1.

MATLAB reserves file identifiers 0, 1, and 2 for standard input, standard output (the screen), and standard error, respectively. When fopen successfully opens a file, it returns a file identifier greater than or equal to 3.

message

A system-dependent error message when fopen cannot open the specified file. Otherwise, an empty string.

fIDs

Row vector containing the identifiers for all open files, except the identifiers reserved for standard input, output, and error. The number of elements in the vector is equal to the number of open files.

filename

Name of the file associated with the specified fileID.

permission

The *permission* that fopen assigned to the file specified by *fileID*.

machineformat

The value of machineformat that fopen used when it opened the file specified by fileID.

encoding

The character encoding scheme that fopen associated with the file specified by *fileID*.

The value that fopen returns for *encoding* is a standard character encoding scheme name. It is not always the same as the *encoding* argument that you used in the call to fopen to open the file.

Examples

Open a file. Pass the file identifier, fid, to other file I/O functions to read data and close the file.

```
fid = fopen('fgetl.m');
tline = fgetl(fid);
while ischar(tline)
    disp(tline);
    tline = fgetl(fid);
end
fclose(fid);
```

Create a prompt to request the name of a file to open. If fopen cannot open the file, display the relevant error message.

```
fid = -1;
msg = '';
while fid < 0
    disp(msg);
    filename = input('Open file: ', 's');
    [fid,msg] = fopen(filename);
end</pre>
```

Open a file to write Unicode characters to a file using the Shift-JIS character encoding scheme:

```
fid = fopen('japanese_out.txt', 'w', 'n', 'Shift_JIS');
```

See Also

fclose | ferror

Related Links

· http://www.iana.org/assignments/character-sets

fopen (serial)

Purpose Connect serial port object to device

Syntax fopen(obj)

Description fopen(obj) connects the serial port object, obj to the device.

RemarksBefore you can perform a read or write operation, obj must be connected to the device with the fopen function. When obj is connected to the device:

• Data remaining in the input buffer or the output buffer is flushed.

• The Status property is set to open.

• The BytesAvailable, ValuesReceived, ValuesSent, and BytesToOutput properties are set to 0.

An error is returned if you attempt to perform a read or write operation while obj is not connected to the device. You can connect only one serial port object to a given device.

Some properties are read-only while the serial port object is open (connected), and must be configured before using fopen. Examples include InputBufferSize and OutputBufferSize. Refer to the property reference pages to determine which properties have this constraint.

The values for some properties are verified only after obj is connected to the device. If any of these properties are incorrectly configured, then an error is returned when fopen is issued and obj is not connected to the device. Properties of this type include BaudRate, and are associated with device settings.

If you use the help command to display help for fopen, then you need to supply the pathname shown below.

help serial/fopen

Example

This example creates the serial port object s, connects s to the device using fopen, writes and reads text data, and then disconnects s from the device. This example works on a Windows platform.

```
s = serial('COM1');
fopen(s)
fprintf(s,'*IDN?')
idn = fscanf(s);
fclose(s)
```

See Also Functions

fclose

Properties

 ${\bf BytesAvailable,\ BytesToOutput,\ Status,\ ValuesReceived,}\\ {\bf ValuesSent}$

Purpose

Execute statements specified number of times

Syntax

for index = valuesprogram statements

end

Description

for index=values, program statements, end repeatedly executes one or more MATLAB statements in a loop. values has one of the following forms:

initval:endval

increments the index variable from initval to endval by 1, and repeats execution of program statements until index is greater than endval.

initval:step:endval increments index by the value step on each iteration, or decrements when step is negative.

valArrav

creates a column vector index from subsequent columns of array valArray on each iteration. For example, on the first iteration, index = valArray(:,1). The loop executes for a maximum of n times, where n is the number of columns of valArray.

Tips

- To force an immediate exit of the loop, use a break or return statement. To skip the rest of the instructions in the loop, increment the loop counter, and begin the next iteration, use a continue statement.
- Avoid assigning a value to the *index* variable within the body of a loop. The for statement overrides any changes made to the index within the loop.

Examples

Create a Hilbert matrix using nested for loops:

```
k = 10;
hilbert = zeros(k,k);  % Preallocate matrix
for m = 1:k
    for n = 1:k
        hilbert(m,n) = 1/(m+n -1);
    end
end
```

Step by increments of -0.1, and display the step values:

```
for s = 1.0: -0.1: 0.0
    disp(s)
end
```

Execute statements for a defined set of index values:

```
for s = [1,5,8,17]
    disp(s)
end
```

Successively set e to unit vectors:

```
for e = eye(5)
  disp('Current value of e:')
  disp(e)
end
```

See Also

How To

• "Program Control Statements"

format

Purpose

Set display format for output

Graphical Interface

As an alternative to using the format command, you also can use the MATLAB Preferences GUI. For more information, select File > Preferences > Command Window and press the Help button.

Syntax

format
format type
format('type')

Description

Use the format function to control the output format of numeric values displayed in the Command Window.

Note The format function affects only how numbers display, not how MATLAB computes or saves them.

format by itself specifies the default display type, format short (that is, 5-digit scaled, fixed-point values).

format type changes the format to the specified type. The following tables list the allowable values for type.

format('type') is the function form of the syntax.

The following tables show the allowable values for *type*, and provide an example for each type using pi.

Use these format types to switch between different output display formats for floating-point variables.

Туре	Result	
short (default)	Scaled fixed-point format, with 4 digits after the decimal point. For example, 3.1416.	
	If you are displaying a matrix with a wide range of values, consider using short g. See "Example 5" on page 2-1560.	
long	Scaled fixed-point format with 14 to 15 digits after the decimal point for double; and 7 digits after the decimal point for single. For example, 3.141592653589793.	
short e	Floating-point format, with 4 digits after the decimal point. For example, 3.1416e+000.	
long e	Floating-point format, with 14 to 15 digits after the decimal point for double; and 7 digits after the decimal point for single. For example, 3.141592653589793e+000.	
short g	Fixed- or floating-point, whichever is more readable, with 4 digits after the decimal point. For example, 3.1416.	
	See Example 5, for a comparison between this format with short.	
long g	Fixed- or floating-point, whichever is more readable, with 14 to 15 digits after the decimal point for double; and 7 digits after the decimal point for single. For example, 3.14159265358979.	
short eng	Engineering format that has 4 digits after the decimal point, and a power that is a multiple of three. For example, 3.1416e+000.	
long eng	Engineering format that has exactly 16 significant digits and a power that is a multiple of three. For example, 3.14159265358979e+000.	

Use these format types to switch between different output display formats for all numeric variables.

format

Value for type	Result
+	+, -, blank
bank	Fixed dollars and cents. For example, 3.14
hex	Hexadecimal (hexadecimal representation of a binary double-precision number). For example, 400921fb54442d18
rat	Ratio of small integers. For example, 355/113

Use these format types to affect the spacing in the display of all variables.

Value for type	Result	Example
compact	Suppresses excess line feeds to show more output in a single screen. Contrast with loose.	theta = pi/2 theta = 1.5708
loose	Adds linefeeds to make output more readable. Contrast with compact.	theta = pi/2 theta =
		1.5708

Remarks

Computations on floating-point variables, namely single or double, are done in appropriate floating-point precision, no matter how those variables are displayed. Computations on integer variables are done natively in integer.

MATLAB always displays integer variables to the appropriate number of digits for the class. For example, MATLAB uses three digits to display numbers of type int8 (for example, -128:127). Setting format to short or long does not affect the display of integer variables.

The specified format applies only to the current MATLAB session. To maintain a format across sessions, use MATLAB preferences. "Specifying Options for MATLAB Using Preferences"

To see which type is currently in use, type

```
get(0, 'Format')
```

To see if compact or loose formatting is currently selected, type

```
get(0, 'FormatSpacing')
```

Examples Example 1

Change the format to long by typing

```
format long
```

View the result for the value of pi by typing

```
pi
ans =
3.14159265358979
```

View the current format by typing

```
get(0,'format')
ans =
   long
```

Set the format to short e by typing

```
format short e
```

or use the function form of the syntax

```
format('short','e')
```

Example 2

When you set the format to short, both pi and single(pi) display as 5-digit values:

```
pi
ans =
     3.1416

single(pi)
ans =
     3.1416
```

Now set format to long, and pi displays a 15-digit value while single(pi) displays an 8-digit value:

```
pi
ans =
    3.14159265358979

single(pi)
ans =
    3.1415927
```

Example 3

Set the format to its default, and display the maximum values for integers and real numbers in MATLAB:

```
format
intmax('uint64')
ans =
    18446744073709551615

realmax
ans =
    1.7977e+308
```

Now change the format to hexadecimal, and display these same values:

The hexadecimal display corresponds to the internal representation of the value. It is not the same as the hexadecimal notation in the C programming language.

Example 4

This example illustrates the short eng and long eng formats. The value assigned to variable A increases by a multiple of 10 each time through the for loop.

```
A = 5.123456789;

for k=1:10

    disp(A)

    A = A * 10;

end
```

The values displayed for A are shown here. The power of 10 is always a multiple of 3. The value itself is expressed in 5 or more digits for the short eng format, and in exactly 15 digits for long eng:

format short eng	format long eng
5.1235e+000	5.12345678900000e+000
51.2346e+000	51.2345678900000e+000
512.3457e+000	512.345678900000e+000
5.1235e+003	5.12345678900000e+003
51.2346e+003	51.2345678900000e+003
512.3457e+003	512.345678900000e+003
5.1235e+006	5.12345678900000e+006
51.2346e+006	51.2345678900000e+006
512.3457e+006	512.345678900000e+006
5.1235e+009	5.12345678900000e+009

Example 5

This example illustrates the difference between using short g and the default type, short, when the values in a matrix cover a wide range.

Suppose you define x as follows:

```
x = [25 \ 56 \ 255 \ 9876899999]
```

When the type is short, the Command Window display appears as follows. Notice that it indicates each value is multiplied by 1.0e+009.

```
x =
1.0e+009 *
0.0000 0.0000 0.0000 9.8769
```

Set the format to short g and redisplay x:

```
format short g
x
```

Notice that the Command Window display is now:

```
x = 25 56 255 9.8769e+009
```

Algorithms

If the largest element of a matrix is larger than 10^3 or smaller than 10^{-3} , then MATLAB applies a common scale factor for the short and long formats. The function format + displays +, -, and blank characters for positive, negative, and zero elements. format hex displays the hexadecimal representation of a binary double-precision number. format rat uses a continued fraction algorithm to approximate floating-point values by ratios of small integers. See rat.m for the complete code.

See Also

disp, display, isnumeric, isfloat, isinteger, floor, sprintf, fprintf, num2str, rat, spy

Purpose

Plot function between specified limits

Syntax

```
fplot(fun,limits)
fplot(fun,limits,LineSpec)
fplot(fun,limits,tol)
fplot(fun,limits,tol,LineSpec)
fplot(fun,limits,n)
fplot(fun,limits,...)
fplot(axes_handle,...)
[X,Y] = fplot(fun,limits,...)
```

Description

fplot plots a function between specified limits. The function must be of the form y = f(x), where x is a vector whose range specifies the limits, and y is a vector the same size as x and contains the function's value at the points in x (see the first example). If the function returns more than one value for a given x, then y is a matrix whose columns contain each component of f(x) (see the second example).

fplot(fun, limits) plots fun between the limits specified by limits. limits is a vector specifying the x-axis limits ([xmin xmax]), or the x-and y-axes limits, ([xmin xmax ymin ymax]).

fun must be

- The name of a function
- A string with variable x that may be passed to eval, such as 'sin(x)', 'diric(x,10)', or '[sin(x),cos(x)]'
- A function handle

The function f(x) must return a row vector for each element of vector x. For example, if f(x) returns [f1(x),f2(x),f3(x)] then for input [x1;x2] the function should return the matrix

```
f1(x1) f2(x1) f3(x1)
f1(x2) f2(x2) f3(x2)
```

fplot(fun,limits,LineSpec) plots fun using the line specification LineSpec.

fplot(fun, limits, tol) plots fun using the relative error tolerance tol (the default is 2e-3, i.e., 0.2 percent accuracy).

fplot(fun, limits, tol, LineSpec) plots fun using the relative error tolerance tol and a line specification that determines line type, marker symbol, and color. See LineSpec for more information.

fplot(fun, limits, n) with $n \ge 1$ plots the function with a minimum of n+1 points. The default n is 1. The maximum step size is restricted to be (1/n)*(xmax-xmin).

fplot(fun,lims,...) accepts combinations of the optional arguments
tol, n, and LineSpec, in any order.

fplot(axes_handle,...) plots into the axes with handle axes_handle instead of the current axes (gca).

[X,Y] = fplot(fun,limits,...) returns the abscissas and ordinates for fun in X and Y. No plot is drawn on the screen; however, you can plot the function using plot(X,Y).


Remarks

fplot uses adaptive step control to produce a representative graph, concentrating its evaluation in regions where the function's rate of change is the greatest.

Examples

Plot the hyperbolic tangent function from -2 to 2:

```
fnch = @tanh;
fplot(fnch,[-2 2])
```



Create a file, myfun, that returns a two-column matrix:


```
function Y = myfun(x)
Y(:,1) = 200*sin(x(:))./x(:);
Y(:,2) = x(:).^2;
```

Create a function handle pointing to myfun:

```
fh = @myfun;
```

Plot the function with the statement

```
fplot(fh,[-20 20])
```




Additional Example

This example passes function handles to fplot, one created from a MATLAB function and the other created from an anonymous function.

```
hmp = @humps;
subplot(2,1,1);fplot(hmp,[0 1])
sn = @(x) sin(1./x);
subplot(2,1,2);fplot(sn,[.01 .1])
```

fplot



See Also

eval, ezplot, feval, LineSpec, plot

"Function Plots" on page 1-99 for related functions Anonymous Functions

Purpose

Write data to text file

Syntax

```
fprintf(fileID, format, A, ...)
fprintf(format, A, ...)
count = fprintf(...)
```

Description

fprintf(fileID, format, A, ...) applies the format to all elements of array A and any additional array arguments in column order, and writes the data to a text file. fprintf uses the encoding scheme specified in the call to fopen.

fprintf(format, A, ...) formats data and displays the results on the screen.

count = fprintf(...) returns the number of bytes that fprintf
writes

Input Arguments

fileID

One of the following:

- An integer file identifier obtained from fopen.
- 1 for standard output (the screen).
- 2 for standard error.

Default: 1 (the screen)

format

String in single quotation marks that describes the format of the output fields. Can include combinations of the following:


- Percent sign followed by a conversion character, such as '%s' for strings.
- Operators that describe field width, precision, and other options.

fprintf

- Literal text to print.
- Escape characters, including:

1 1	Single quotation mark	
%%	Percent character	
\\	Backslash	
\a	Alarm	
\b	Backspace	
\f	Form feed	
\ n	New line	
\r	Carriage return	
\t	Horizontal tab	
\ v	Vertical tab	
\ x N	Hexadecimal number, N	
\ <i>N</i>	Octal number, N	

Conversion characters and optional operators appear in the following order (includes spaces for clarity):



The following table lists the available conversion characters and subtypes.

Value Type	Conversion	Details
Integer, signed	%d or %i	Base 10 values
integer, signed		
	%ld or %li	64-bit base 10 values
	%hd or %hi	16-bit base 10 values
Integer,	%u	Base 10
unsigned	%0	Base 8 (octal)
	%X	Base 16 (hexadecimal), lowercase letters a-f
	%X	Same as %x, uppercase letters A–F
	%lu %lo %lx or %lX	64-bit values, base 10, 8, or 16
	%hu %ho %hx or %hX	16-bit values, base 10, 8, or 16
Floating-point	%f	Fixed-point notation
number	%e	Exponential notation, such as 3.141593e+00
	%E	Same as %e, but uppercase, such as 3.141593E+00
	%g	The more compact of %e or %f, with no trailing zeros
	%G	The more compact of %E or %f, with no trailing zeros
	%bx or %bX %bo %bu	Double-precision hexadecimal, octal, or decimal value Example: %bx prints pi as 400921fb54442d18

Value Type	Conversion	Details
	%tx or %tX %to %tu	Single-precision hexadecimal, octal, or decimal value Example: %tx prints pi as 40490fdb
Characters	%C	Single character
	%S	String of characters

Additional operators include:

• Field width

Minimum number of characters to print. Can be a number, or an asterisk (*) to refer to an argument in the input list. For example, the input list ('%12d', intmax) is equivalent to ('%*d', 12, intmax).

• Precision

For %f, %e, or %E:

Number of digits to the right of the decimal point.

Example: '%6.4f' prints pi as '3.1416'

For %g or %G

Number of significant digits.

Example: '%6.4g' prints pi as '3.142'

Can be a number, or an asterisk (*) to refer to an argument in the input list. For example, the input list ('%6.4f', pi) is equivalent to ('%*.*f', 6, 4, pi).

• Flags

Action	Flag	Example
Left-justify.	1 1	%-5.2f
Print sign character (+ or).	'+'	%+5.2f
Insert a space before the value.	1 1	% 5.2f
Pad with zeros.	'0'	%05.2f
Modify selected numeric conversions:	'#'	%#5.0f
• For %0, %x, or %X, print 0, 0x, or 0X prefix.		
• For %f, %e, or %E, print decimal point even when precision is 0.		
For %g or %G, do not remove trailing zeros or decimal point.		

• Identifier

Order for processing inputs. Use the syntax n\$, where n represents the position of the value in the input list.

For example, '%3\$s %2\$s %1\$s %2\$s' prints inputs 'A', 'B', 'C' as follows: C B A B.

The following limitations apply to conversions:

- Numeric conversions print only the real component of complex numbers.
- If you apply an integer or string conversion to a numeric value that contains a fraction, MATLAB overrides the specified conversion, and uses %e.
- If you apply a string conversion (%s) to integer values, MATLAB:
 - Issues a warning.

- Converts values that correspond to valid character codes to characters. For example, '%s' converts [65 66 67] to ABC.
- Different platforms display exponential notation (such as %e) with a different number of digits in the exponent.

Platform	Example
Windows	1.23e+004
UNIX	1.23e+04

• Different platforms display negative zero (-0) differently.

	Conversion Character		
Platform	%e or %E	%f	%g or %G
Windows	0.000000e+000	0.000000	0
Others	-0.000000e+00	-0.000000	-0

Α

Numeric or character array.

Examples

Print multiple values and literal text to the screen:

```
B = [8.8 7.7; ...
8800 7700];
fprintf('X is %4.2f meters or %8.3f mm\n', 9.9, 9900, B)
```

MATLAB displays:

```
X is 9.90 meters or 9900.000 mm
X is 8.80 meters or 8800.000 mm
X is 7.70 meters or 7700.000 mm
```

Explicitly convert double-precision values with fractions to integer values, and print to the screen:

```
a = [1.02 \ 3.04 \ 5.06];
fprintf('%d\n', round(a));
```

Write a short table of the exponential function to a text file called exp.txt:

```
x = 0:.1:1;
y = [x; exp(x)];
% open the file with write permission
fid = fopen('exp.txt', 'w');
fprintf(fid, '%6.2f %12.8f\n', y);
fclose(fid);
% view the contents of the file
type exp.txt
```

MATLAB import functions, all UNIX applications, and Microsoft Word and WordPad recognize '\n' as a newline indicator. However, if you plan to read the file with Microsoft Notepad, use '\r\n' to move to a new line when writing. For example, replace the previous call to fprintf with the following:

```
fprintf(fid, '%6.2f %12.8f\r\n', y);
```

On a Windows system, convert PC-style exponential notation (three digits in the exponent) to UNIX-style notation (two digits), and print data to a file:

```
a = [0.06 \ 0.1 \ 5 \ 300]
```

% use sprintf to convert the numeric data to text, using %e

```
a_str = sprintf('%e\t',a)
% use strrep to replace exponent prefix with shorter version
a_str = strrep(a_str,'e+0','e+');
a_str = strrep(a_str,'e-0','e-');
% call fprintf to print the updated text strings
fid = fopen('newfile.txt','w');
fprintf(fid, '%s', a_str);
fclose(fid);
% view the contents of the file
type newfile.txt
```

Display a hyperlink (The MathWorks Web Site) on the screen:

```
site = 'http://www.mathworks.com';
title = 'The MathWorks Web Site';

fprintf('<a href = "%s">%s</a>\n', site, title)
```

References

[1] Kernighan, B. W., and D. M. Ritchie, *The C Programming Language*, Second Edition, Prentice-Hall, Inc., 1988.

[2] ANSI specification X3.159-1989: "Programming Language C," ANSI, 1430 Broadway, New York, NY 10018.

See Also

disp | fclose | ferror | fopen | fread | fscanf | fwrite | sprintf

How To

- "Formatting Strings"
- "Appending or Overwriting Existing Files"

Purpose Write text to device

Syntax

```
fprintf(obj,'cmd')
fprintf(obj,'format','cmd')
fprintf(obj,'cmd','mode')
```

fprintf(obj,'format','cmd','mode')

Description

fprintf(obj,'cmd') writes the string cmd to the device connected to the serial port object, obj. The default format is $s\n$. The write operation is synchronous and blocks the command-line until execution completes.

fprintf(obj,'format','cmd') writes the string using the format
specified by format.

fprintf(obj,'cmd','mode') writes the string with command line access specified by mode. mode specifies if cmd is written synchronously or asynchronously.

fprintf(obj,'format','cmd','mode') writes the string using the specified format. format is a C language conversion specification.

You need an open connection from the serial port object, obj, to the device before performing read or write operations.

Use the fopen function to open a connection to the device. When obj has an open connection to the device it has a Status property value of open. Refer to "Troubleshooting Common Errors" for fprintf errors.

To understand the use of fprintf refer to "Completing a Write Operation with fprintf" and "Rules for Writing the Terminator".

Input Arguments

format

ANSI C conversion specification includes these conversion characters.

Specifier	Description
%C	Single character
%d or %i	Decimal notation (signed)

Specifier	Description
%e	Exponential notation (using lowercase e as in 3.1415e+00)
%E	Exponential notation (using uppercase E as in 3.1415E+00)
%f	Fixed-point notation
%g	The more compact of %e or %f, as defined above. Insignificant zeros do not print.
%G	Same as %g, but using uppercase E
%0	Octal notation (unsigned)
%S	String of characters
%u	Decimal notation (unsigned)
%X	Hexadecimal notation (using lowercase letters a-f)
%X	Hexadecimal notation (using uppercase letters A–F)

mode

Specifies whether the string cmd is written synchronously or asynchronously:

- sync: cmd is written synchronously and the command line is blocked.
- async: cmd is written asynchronously and the command line is not blocked.

If mode is not specified, the write operation is synchronous.

If you specify asynchronous *mode*, when the write operation occurs:

• The BytesToOutput property value continuously updates to reflect the number of bytes in the output buffer.

• The MATLAB file callback function specified for the OutputEmptyFcn property is executed when the output buffer is empty.

Use the TransferStatus property to determine whether an asynchronous write operation is in progress.

For more information on synchronous and asynchronous write operations, see Controlling Access to the MATLAB Command Line.

Examples

Create a serial port object s and connect it to a Tektronix TDS 210 oscilloscope. Write the RS232? command with fprintf. RS232? instructs the scope to return serial port communications settings. This example works on a Windows platform.

```
s = serial('COM1');
fopen(s)
fprintf(s,'RS232?')
```

Specify a format for the data that does not include the terminator, or configure the terminator to empty.

```
s = serial('COM1');
fopen(s)
fprintf(s,'%s','RS232?')
```

The default format for fprintf is %s\n. Therefore, the terminator specified by the Terminator property is automatically written. However, in some cases you might want to suppress writing the terminator.

Specify an array of formats and commands:

```
s = serial('COM1');
fopen(s)
fprintf(s,['ch:%d scale:%d'],[1 20e-3],'sync');
```

fprintf (serial)

See Also

fopen | fwrite | stopasync | BytesToOutput | OutputBufferSize |

OutputEmptyFcn | Status | TransferStatus | ValuesSent

Tutorials

• Writing and Reading Data

• Controlling Access to the MATLAB Command Line

Purpose Return image data associated with movie frame

Syntax [X,Map] = frame2im(F)

Description [X,Map] = frame2im(F) returns the indexed image X and associated

colormap Map from the single movie frame F. If the frame contains true-color data, the m-by-n-3 matrix Map is empty. The functions

getframe and im2frame create a movie frame.

Example Create and capture an image using getframe and frame2im:

peaks
f = getframe;
[im,map] = frame2im(f);
if isempty(map)
 rgb = im;
else
%Make figure
%Capture screen shot
%Return associated image data
%Truecolor system
%Indexed system

else %Indexed system rgb = ind2rgb(im,map); %Convert image data

end

See Also getframe, im2frame, movie

Read data from binary file

Syntax

A = fread(fileID)

A = fread(fileID, sizeA)

A = fread(fileID, sizeA, precision)

A = fread(fileID, sizeA, precision, skip)

A = fread(fileID, sizeA, precision, skip, machineformat)

[A, count] = fread(...)

Description

A = fread(fileID) reads data from a binary file into column vector A and positions the file pointer at the end-of-file marker.

A = fread(fileID, sizeA) reads sizeA elements into A and positions the file pointer after the last element read. sizeA can be an integer, or can have the form [m,n].

A = fread(fileID, sizeA, precision) interprets values in the file according to the form and size described by the precision. The sizeA parameter is optional.

A = fread(fileID, sizeA, precision, skip) skips skip bytes after reading each value. If precision is bitn or ubitn, specify skip in bits. The sizeA parameter is optional.

A = fread(fileID, sizeA, precision, skip, machineformat) reads data with the specified machineformat. The sizeA and skip parameters are optional.

[A, count] = fread(...) returns the number of elements fread reads into A.

Input Arguments

fileID

An integer file identifier obtained from fopen.

sizeA

Dimensions of the output array A. Specify in one of the following forms:

inf Column vector with the number of elements in the

file. (default)

n Column vector with *n* elements. If the file has fewer

than n elements, fread pads A with zeros.

[m,n] m-by-n matrix, filled in column order. If the file has

fewer than m^*n elements, fread pads A with zeros. n

can be inf, but m cannot.

precision

String that specifies the form and size of the values to read. Optionally includes the class for the output matrix A.

Use one of the following forms:

'source' Specifies class of input values. Output

matrix A is class double.

Example: 'int16'

'source=>output' Specifies classes of input and output.

Example: 'int8=>char'

'*source' Output has the same class as input.

Example: '*uint8'

For 'bitn' or 'ubitn' precisions, output has the smallest class that can

contain the input.

Example: '*ubit18' is equivalent to

'ubit18=>uint32'

'N*source' OR Valid if you specify a skip parameter.

'*N**source=>output' Read *N* values before each skip.

Example: '4*int8'

The following table shows possible values for source and output.

Value Type	Precision	Bits (Bytes)
Integers,	uint	32 (4)
unsigned	uint8	8 (1)
	uint16	16 (2)
	uint32	32 (4)
	uint64	64 (8)
	uchar	8 (1)
	unsigned char	8 (1)
	ushort	16 (2)
	ulong	system-dependent
	ubit <i>n</i>	1 ≤ n ≤ 64
Integers, signed	int	32 (4)
	int8	8 (1)
	int16	16 (2)
	int32	32 (4)
	int64	64 (8)
	integer*1	8 (1)
	integer*2	16 (2)
	integer*3	32 (4)
	integer*4	64 (8)
	schar	8 (1)
	signed char	8 (1)
	short	16 (2)
	long	system-dependent
	bit <i>n</i>	1 ≤ n ≤ 64

Value Type	Precision	Bits (Bytes)
Floating-point numbers	single double float float32 float64 real*4 real*8	32 (4) 64 (8) 32 (4) 32 (4) 64 (8) 32 (4) 64 (8)
Characters	char*1 char	8 (1) Depends on the encoding scheme associated with the file. Set encoding with fopen.

long and ulong are 32 bits on 32-bit systems, and 64 bits on 64-bit systems.

For most *source* precisions, if fread reaches the end of the file before reading a complete element, fread does not return a value for the final element. However, if *source* is bitn or ubitn, then fread returns a partial result for the final element.

Default: 'uint8=>double'

skip

Number of bytes to skip after reading each value. If you specify a *precision* of bitn or ubitn, specify *skip* in bits. Use this parameter to read data from noncontiguous fields in fixed-length records.

Default: 0

machineformat

String that specifies the order for reading bytes within the file. For bitn and ubitn precisions, specifies the order for reading bits

within a byte. Specify *machineformat* to read and write to the file on different systems, or to read parts of a byte in a specific order.

Possible values are:

```
'n' or 'native'

"b' or 'ieee-be'

Big-endian ordering

'1' or 'ieee-le'

Little-endian ordering

's' or 'ieee-be.164'

Big-endian ordering, 64-bit data type

'a' or 'ieee-le.164'

Little-endian ordering, 64-bit data type
```

Windows systems use little-endian ordering, and most UNIX systems use big-endian ordering, for both bytes and bits.

Output Arguments

Α

A column vector, unless you specify sizeA with the form [m,n]. Data in A is class double unless you specify a different class in the *precision* argument.

count

The number of elements that fread successfully reads.

Examples

Read the contents of a file:

```
% Create the file
fid = fopen('magic5.bin', 'w');
fwrite(fid, magic(5));
fclose(fid);
% Read the contents back into an array
fid = fopen('magic5.bin');
m5 = fread(fid, [5, 5], '*uint8');
fclose(fid);
```

Simulate the type function with fread, to display the contents of a text file:

```
fid = fopen('fread.m');
  % read the entire file as characters
  % transpose so that F is a row vector
  F = fread(fid, '*char')'
  fclose(fid);
If you do not specify the precision, fread applies the default
uint8=>double:
  fid = fopen('fread.m');
  F nums = fread(fid, 6)' % read the first 6 bytes ('%FREAD')
  fclose(fid);
This code returns
  F nums =
      37
                   82
                                65
             70
                          69
                                      68
```

Read selected rows or columns from a file:

```
% Create a file with values from 1 to 9
fid = fopen('nine.bin', 'w');
alldata = reshape([1:9],3,3);
fwrite(fid, alldata);
fclose(fid);
% Read the first six values into two columns
fid = fopen('nine.bin');
two_cols = fread(fid, [3, 2]);
```

```
% Return to the beginning of the file
frewind(fid);
% Read two values at a time, skip one
% Returns six values into two rows
% (first two rows of 'alldata')

two_rows = fread(fid, [2, 3], '2*uint8', 1);
% Close the file
fclose(fid);
```

Specify machineformat to read separate digits of binary coded decimal (BCD) values correctly:

```
% Create a file with BCD values
str = ['AB'; 'CD'; 'EF'; 'FA'];
fid = fopen('bcd.bin', 'w');
fwrite(fid, hex2dec(str), 'ubit8');
fclose(fid);
% If you read one byte at a time,
% no need to specify machine format
fid = fopen('bcd.bin');
onebyte = fread(fid, 4, '*ubit8');
disp('Correct data, read with ubit8:')
disp(dec2hex(onebyte))
% However, if you read 4 bits on a little-endian
% system, your results appear in the wrong order
frewind(fid);
                 % return to beginning of file
part err = fread(fid, 8, '*ubit4');
disp('Incorrect data on little-endian systems, ubit4:')
```

Read binary data from device

Syntax

```
A = fread(obj)
A = fread(obj,size,'precision')
[A,count] = fread(...)
[A,count,msg] = fread(...)
```

Description

A = fread(obj) and A = fread(obj,size) read binary data from the device connected to the serial port object, obj, and returns the data to A. The maximum number of values to read is specified by size. If size is not specified, the maximum number of values to read is determined by the object's InputBufferSize property. Valid options for size are:

n	Read at most n values into a column vector.
[m,n]	Read at most m-by-n values filling an m-by-n matrix in column order.

size cannot be inf, and an error is returned if the specified number of values cannot be stored in the input buffer. You specify the size, in bytes, of the input buffer with the InputBufferSize property. A value is defined as a byte multiplied by the *precision* (see below).

A = fread(obj, size, 'precision') reads binary data with precision specified by precision.

precision controls the number of bits read for each value and the interpretation of those bits as integer, floating-point, or character values. If precision is not specified, uchar (an 8-bit unsigned character) is used. By default, numeric values are returned in double-precision arrays. The supported values for precision are listed below in Remarks.

[A,count] = fread(...) returns the number of values read to count.

[A,count,msg] = fread(...) returns a warning message to msg if the read operation was unsuccessful.

Remarks

Before you can read data from the device, it must be connected to obj with the fopen function. A connected serial port object has a Status property value of open. An error is returned if you attempt to perform a read operation while obj is not connected to the device.

If msg is not included as an output argument and the read operation was not successful, then a warning message is returned to the command line.

The ValuesReceived property value is increased by the number of values read, each time fread is issued.

If you use the help command to display help for fread, then you need to supply the pathname shown below.

help serial/fread

Rules for Completing a Binary Read Operation

A read operation with fread blocks access to the MATLAB command line until:

- The specified number of values are read.
- The time specified by the Timeout property passes.

Note The Terminator property is not used for binary read operations.

Supported Precisions

The supported values for *precision* are listed below.

Data Type	Precision	Interpretation
Character	uchar	8-bit unsigned character
	schar	8-bit signed character
	char	8-bit signed or unsigned character

fread (serial)

Data Type	Precision	Interpretation
Integer	int8	8-bit integer
	int16	16-bit integer
	int32	32-bit integer
	uint8	8-bit unsigned integer
	uint16	16-bit unsigned integer
	uint32	32-bit unsigned integer
	short	16-bit integer
	int	32-bit integer
	long	32- or 64-bit integer
	ushort	16-bit unsigned integer
	uint	32-bit unsigned integer
	ulong	32- or 64-bit unsigned integer
Floating-point	single	32-bit floating point
	float32	32-bit floating point
	float	32-bit floating point
	double	64-bit floating point
	float64	64-bit floating point

See Also Functions

fgetl, fgets, fopen, fscanf

Properties

BytesAvailable, BytesAvailableFcn, InputBufferSize, Status, Terminator, ValuesReceived

Purpose Facets referenced by only one simplex

Syntax FF = freeBoundary(TR)

[FF XF] = freeBoundary(TR)

Description

FF = freeBoundary (TR) returns a matrix FF that represents the free boundary facets of the triangulation. A facet is on the free boundary if it is referenced by only one simplex (triangle/tetrahedron, etc). FF is of size m-by-n, where m is the number of boundary facets and n is the number of vertices per facet. The vertices of the facets index into the array of points representing the vertex coordinates TR.X. The array FF could be empty as in the case of a triangular mesh representing the surface of a sphere.

[FF XF] = freeBoundary(TR) returns a matrix of free boundary facets

Input Arguments

TR Triangulation representation.

Output Arguments

FF that has vertices defined in terms of a compact

array of coordinates XF.

XF is of size m-by-ndim where m is the number of free

facets, and ndim is the dimension of the space where

the triangulation resides

Definitions

A *simplex* is a triangle/tetrahedron or higher-dimensional equivalent. A *facet* is an edge of a triangle or a face of a tetrahedron.

Examples Example 1

Use TriRep to compute the boundary triangulation of an imported triangulation.

Load a 3-D triangulation:


TriRep.freeBoundary

```
load tetmesh;
trep = TriRep(tet, X);
```

Compute the boundary triangulation:

```
[tri xf] = freeBoundary(trep);
```

Plot the boundary triangulation:



Example 2

Perform a direct query of a 2-D triangulation created with DelaunayTri.

Plot the mesh:


```
x = rand(20,1);
y = rand(20,1);
```

```
dt = DelaunayTri(x,y);
fe = freeBoundary(dt)';
triplot(dt);
hold on;
```

Display the free boundary edges in red:

```
plot(x(fe), y(fe), '-r', 'LineWidth',2);
hold off;
```

In this instance the free edges correspond to the convex hull of (x, y).



See Also

DelaunayTri.convexHull TriRep.featureEdges TriRep.faceNormals

Frequency spacing for frequency response

Syntax

```
[f1,f2] = freqspace(n)
[f1,f2] = freqspace([m n])
[x1,y1] = freqspace(..., 'meshgrid')
f = freqspace(N)
f = freqspace(N, 'whole')
```

Description

freqspace returns the implied frequency range for equally spaced frequency responses. freqspace is useful when creating desired frequency responses for various one- and two-dimensional applications.

[f1,f2] = freqspace(n) returns the two-dimensional frequency vectors f1 and f2 for an n-by-n matrix.

For n odd, both f1 and f2 are [-n+1:2:n-1]/n.

For n even, both f1 and f2 are [-n:2:n-2]/n.

[f1,f2] = freqspace([m n]) returns the two-dimensional frequency vectors f1 and f2 for an m-by-n matrix.

```
[x1,y1] = freqspace(..., 'meshgrid') is equivalent to
[f1,f2] = freqspace(...);
[x1,y1] = meshgrid(f1,f2);
```

f = freqspace(N) returns the one-dimensional frequency vector f assuming N evenly spaced points around the unit circle. For N even or odd, f is (0:2/N:1). For N even, freqspace therefore returns (N+2)/2 points. For N odd, it returns (N+1)/2 points.

f = freqspace(N, 'whole') returns N evenly spaced points around the whole unit circle. In this case, f is 0:2/N:2*(N-1)/N.

See Also

meshgrid

Purpose Move file position indicator to beginning of open file

Syntax frewind(fileID)

Description frewind (file ID) sets the file position indicator to the beginning of a

file. fileID is an integer file identifier obtained from fopen.

If the file is on a tape device and the rewind operation fails, frewind

does not return an error message.

Alternatives frewind(fileID) is equivalent to:

fseek(fileID, 0, 'bof');

See Also fclose | feof | ferror | fopen | fseek | ftell

Read data from a text file

Syntax

A = fscanf(fileID, format)

A = fscanf(fileID, format, sizeA)

[A, count] = fscanf(...)

Description

A = fscanf(fileID, format) reads and converts data from a text file into array A in column order. To convert, fscanf uses the format and the encoding scheme associated with the file. To set the encoding scheme, use fopen. The fscanf function reapplies the format throughout the entire file, and positions the file pointer at the end-of-file marker. If fscanf cannot match the format to the data, it reads only the portion that matches into A and stops processing.

A = fscanf(fileID, format, sizeA) reads sizeA elements into A, and positions the file pointer after the last element read. sizeA can be an integer, or can have the form [m,n].

[A, count] = fscanf(...) returns the number of elements that fscanf successfully reads.

Input Arguments

fileID

Integer file identifier obtained from fopen.

format

String enclosed in single quotation marks that describes each type of element (field). Includes one or more of the following specifiers.

Field Type	Specifier	Details
Integer, signed	%d	Base 10
	%i	Base determined from the values. Defaults to base 10. If initial digits are 0x or 0X, it is base 16. If initial digit is 0, it is base 8.

Field Type	Specifier	Details
Integer,	%u	Base 10
unsigned	%0	Base 8 (octal)
	%X	Base 16 (hexadecimal)
Floating-point	%f	Floating-point fields can contain
number	%e	any of the following (not case sensitive): Inf, -Inf, NaN, or
	%g	-NaN.
Character string	%S	Read series of characters, until find white space.
	%C	Read any single character, including white space. (To read multiple characters, specify field length.)
	%[]	Read only characters in the brackets, until the first nonmatching character or white space.

Optionally:

- To skip fields, insert an asterisk (*) after the percent sign (%). For example, to skip integers, specify %*d.
- To specify the maximum width of a field, insert a number. For example, %10c reads exactly 10 characters at a time, including white space.
- To skip a specific set of characters, insert the literal characters in the *format*. For example, to read only the floating-point number from 'pi=3.14159', specify a *format* of 'pi=%f'.

sizeA

fscanf

Dimensions of the output array A. Specify in one of the following forms:

inf Read to the end of the file. (default)

n Read at most *n* elements.

[m,n] Read at most m*n elements in column order. n can

be inf, but m cannot.

When the *format* includes %s, A can contain more than n columns. n refers to elements, not characters.

Output Arguments

Α

An array. If the format includes:

- Only numeric specifiers, A is numeric, of class double. If sizeA is inf or n, then A is a column vector. If the input contains fewer than sizeA elements, MATLAB pads A with zeros.
- Only character or string specifiers (%c or %s), A is a character array. If sizeA is inf or n, A is a row vector. If the input contains fewer than sizeA characters, MATLAB pads A with char(0).
- A combination of numeric and character specifiers, A is numeric, of class double. MATLAB converts each character to its numeric equivalent. This conversion occurs even when the *format* explicitly skips all numeric values (for example, a *format* of '%*d %s').

If MATLAB cannot match the input to the *format*, and the *format* contains both numeric and character specifiers, A can be numeric or character. The class of A depends on the values MATLAB reads before processing stops.

count

The number of elements fscanf reads into A.

Examples

Read the contents of a file. fscanf reuses the *format* throughout the file, so you do not need a control loop:

```
% Create a file with an exponential table
x = 0:.1:1;
y = [x; exp(x)];
fid = fopen('exp.txt', 'w');
fprintf(fid, '%6.2f %12.8f\n', y);
fclose(fid);
% Read the data, filling A in column order
% First line of the file:
     0.00
            1.00000000
fid = fopen('exp.txt');
A = fscanf(fid, '%g %g', [2 inf]);
fclose(fid);
% Transpose so that A matches
% the orientation of the file
A = A';
```

Skip specific characters in a file, and return only numeric values:

```
% Create a file with temperatures
tempstr = '78 F 72 F 64 F 66 F 49 F';
fid = fopen('temperature.dat', 'w+');
fprintf(fid, '%s', tempstr);
% Return to the beginning of the file
frewind(fid);
% Read the numbers in the file, skipping the units
% num temps is a numeric column vector
```

```
degrees = char(176);
    num_temps = fscanf(fid, ['%d' degrees 'F']);

fclose(fid);

See Also

fclose | ferror | fgetl | fgets | fopen | fprintf | fread | fwrite | sscanf | textscan

How To

    "Reading Data in a Formatted Pattern"
    "Opening Files with Different Character Encodings"
```

Read data from device, and format as text

Syntax

```
A = fscanf(obj)
A = fscanf(obj, 'format')
A = fscanf(obj, 'format', size)
[A,count] = fscanf(...)
[A,count,msg] = fscanf(...)
```

Description

A = fscanf(obj) reads data from the device connected to the serial port object, obj, and returns it to A. The data is converted to text using the %c format.

A = fscanf(obj, 'format') reads data and converts it according to format. format is a C language conversion specification. Conversion specifications involve the % character and the conversion characters d, i, o, u, x, X, f, e, E, g, G, c, and s. Refer to the sscanf file I/O format specifications or a C manual for more information.

A = fscanf(obj,'format', size) reads the number of values specified by size. Valid options for size are:

n	Read at most n values into a column vector.
[m,n]	Read at most m-by-n values filling an m-by-n matrix in column order.

size cannot be inf, and an error is returned if the specified number of values cannot be stored in the input buffer. If size is not of the form [m,n], and a character conversion is specified, then A is returned as a row vector. You specify the size, in bytes, of the input buffer with the InputBufferSize property. An ASCII value is one byte.

[A,count] = fscanf(...) returns the number of values read to count.

[A,count,msg] = fscanf(...) returns a warning message to msg if the read operation did not complete successfully.

Remarks

Before you can read data from the device, it must be connected to obj with the fopen function. A connected serial port object has a Status property value of open. An error is returned if you attempt to perform a read operation while obj is not connected to the device.

If msg is not included as an output argument and the read operation was not successful, then a warning message is returned to the command line.

The ValuesReceived property value is increased by the number of values read — including the terminator — each time fscanf is issued.

If you use the help command to display help for fscanf, then you need to supply the pathname shown below.

```
help serial/fscanf
```

Rules for Completing a Read Operation with fscanf

A read operation with fscanf blocks access to the MATLAB command line until:

- The terminator specified by the Terminator property is read.
- The time specified by the Timeout property passes.
- The number of values specified by size is read.
- The input buffer is filled (unless size is specified)

Example

Create the serial port object s and connect s to a Tektronix TDS 210 oscilloscope, which is displaying sine wave. This example works on a Windows platform.

```
s = serial('COM1');
fopen(s)
```

Use the fprintf function to configure the scope to measure the peak-to-peak voltage of the sine wave, return the measurement type, and return the peak-to-peak voltage.

```
fprintf(s,'MEASUREMENT:IMMED:TYPE PK2PK')
fprintf(s,'MEASUREMENT:IMMED:TYPE?')
fprintf(s,'MEASUREMENT:IMMED:VALUE?')
```

Because the default value for the ReadAsyncMode property is continuous, data associated with the two query commands is automatically returned to the input buffer.

```
s.BytesAvailable
ans =
    21
```

Use fscanf to read the measurement type. The operation will complete when the first terminator is read.

```
meas = fscanf(s)
meas =
PK2PK
```

Use fscanf to read the peak-to-peak voltage as a floating-point number, and exclude the terminator.

```
pk2pk = fscanf(s,'%e',14)
pk2pk =
    2.0200
```

Disconnect **s** from the scope, and remove **s** from memory and the workspace.

```
fclose(s)
delete(s)
clear s
```

See Also Functions

```
fgetl, fgets, fopen, fread, textscan
```

fscanf (serial)

Properties

 $\label{thm:bytesAvailableFcn} \mbox{ InputBufferSize, Status, } \\ \mbox{ Terminator, Timeout}$

Move to specified position in file

Syntax

fseek(fileID, offset, origin)
status = fseek(fileID, offset, origin)

Description

fseek(fileID, offset, origin) sets the file position indicator

offset bytes from origin in the specified file.

status = fseek(fileID, offset, origin) returns 0 when the
operation is successful. Otherwise, it returns -1.

Input Arguments

fileID

Integer file identifier obtained from fopen.

offset

Number of bytes to move from origin. Can be positive, negative, or zero. The n bytes of a given file are in positions 0 through n-1.

origin

Starting location in the file:

'bof' or -1	Beginning of file
O 1 O 1	Dogimming of the

'cof' or 0 Current position in file

'eof' or 1 End of file

Examples

Copy 5 bytes from the file test1.dat, starting at the tenth byte, and append to the end of test2.dat:

```
% Create files test1.dat and test2.dat
% Each character uses 8 bits (1 byte)

fid1 = fopen('test1.dat', 'w+');
fwrite(fid1, 'ABCDEFGHIJKLMNOPQRSTUVWXYZ');
```

```
fid2 = fopen('test2.dat', 'w+');
                     fwrite(fid2, 'Second File');
                     % Seek to the 10th btye ('J'), read 5
                     fseek(fid1, 9, 'bof');
                     A = fread(fid1, 5, 'uint8=>char');
                     fclose(fid1);
                     % Append to test2.dat
                     fseek(fid2, 0, 'eof');
                     fwrite(fid2, A);
                     fclose(fid2);
Alternatives
                  To move to the beginning of a file, call
                     frewind(fileID)
                  This call is identical to
                     fseek(fileID, 0, 'bof')
See Also
                  fclose | feof | ferror | fopen | frewind | ftell
How To
                  · "Reading Portions of a File"
```

Purpose Position in open file

Syntax position = ftell(fileID)

Description position = ftell(fileID) returns the current position in the

specified file. *position* is a zero-based integer that indicates the number of bytes from the beginning of the file. If the query is unsuccessful, *position* is -1. *fileID* is an integer file identifier

obtained from fopen.

See Also fclose | feof | ferror | fopen | frewind | fseek

Connect to FTP server, creating FTP object

Syntax

```
f = ftp('host','username','password')
```

Description

f = ftp('host', 'username', 'password') connects to the FTP server, host, creating the FTP object, f. If a user name and password are not required for an anonymous connection, only use the host argument. Specify an alternate port by separating it from host using a colon (:). After running ftp, perform file operation functions on the FTP object, f, using methods such as cd and others listed under "See Also." When you're finished using the server, run close (ftp) to close the connection.

FTP is not a secure protocol; others can see your user name and password.

The ftp function is based on code from the Apache Jakarta Project.

Examples

Connect Without User Name

Connect to ftp.mathworks.com, which does not require a user name or password. Assign the resulting FTP object to tmw. You can access this FTP site to experiment with the FTP functions.

```
tmw=ftp('ftp.mathworks.com')

tmw =
FTP Object
  host: ftp.mathworks.com
  user: anonymous
  dir: /
  mode: binary
```

Connect to Specified Port

```
To connect to port 34, type:

tmw=ftp('ftp.mathworks.com:34')
```

Connect with User Name

Connect to ftp.testsite.com and assign the resulting FTP object to test.

```
test=ftp('ftp.testsite.com','myname','mypassword')

test =
FTP Object
  host: ftp.testsite.com
  user: myname
   dir: /
  mode: binary
  myname@ftp.testsite.com
  /
```

See Also

```
ascii | binary | cd (ftp) | close (ftp) | delete (ftp) | dir
(ftp) | mget | mkdir (ftp) | mput | rename | rmdir (ftp)
```

How To

• "Specifying Proxy Server Settings"

Convert sparse matrix to full matrix

Syntax

A = full(S)

Description

A = full(S) converts a sparse matrix S to full storage organization. If S is a full matrix, it is left unchanged. If A is full, issparse(A) is 0.

Remarks

Let X be an m-by-n matrix with nz = nnz(X) nonzero entries. Then full(X) requires space to store m*n real numbers while sparse(X) requires space to store nz real numbers and (nz+n) integers.

On most computers, a real number requires twice as much storage as an integer. On such computers, sparse(X) requires less storage than full(X) if the density, nnz/prod(size(X)), is less than one third. Operations on sparse matrices, however, require more execution time per element than those on full matrices, so density should be considerably less than two-thirds before sparse storage is used.

Examples

Here is an example of a sparse matrix with a density of about two-thirds. sparse(S) and full(S) require about the same number of bytes of storage.

See Also

issparse, sparse

Build full file name from parts

Syntax

f = fullfile(folderName1, folderName2, ..., fileName)

Description

f = fullfile(folderName1, folderName2, ..., fileName) builds a full file specification f from the folders and file name specified. Input arguments folderName1, folderName2, etc. and fileName are each strings enclosed in single quotation marks. The output of fullfile is conceptually equivalent to

```
f = [folderName1 filesep folderName2 filesep ... filesep filename]
```

except that care is taken to handle the cases when the folders begin or end with a file separator.

Examples

To create the full file name from a disk name, folders, and filename,

```
f = fullfile('C:', 'Applications', 'matlab', 'myfun.m')
f =
C:\Applications\matlab\myfun.m
```

fullfile

The following examples both produce the same result on UNIX⁶ platforms, but only the second one works on all platforms.

See Also

fileparts, filesep, path, pathsep, genpath

6. UNIX is a registered trademark of The Open Group in the United States and other countries

Construct function name string from function handle

Syntax

func2str(fhandle)

Description

func2str(fhandle) constructs a string s that holds the name of the function to which the function handle fhandle belongs.

When you need to perform a string operation, such as compare or display, on a function handle, you can use func2str to construct a string bearing the function name.

The func2str command does not operate on nonscalar function handles. Passing a nonscalar function handle to func2str results in an error.

Remarks

Any variables and their values originally stored in a function handle when it was created are lost if you convert the function handle to a string and back again using the func2str and str2func functions.

Examples

Example 1

Convert a sin function handle to a string:

```
fhandle = @sin;
func2str(fhandle)
ans =
    sin
```

Example 2

The catcherr function shown here accepts function handle and data arguments and attempts to evaluate the function through its handle. If the function fails to execute, catcherr uses sprintf to display an error message giving the name of the failing function. The function name must be a string for sprintf to display it. The code derives the function name from the function handle using func2str:

```
function catcherr(func, data)
try
```

```
ans = func(data);
disp('Answer is:');
ans
catch
disp(sprintf('Error executing function ''%s''\n', ...
func2str(func)))
end
```

The first call to catcherr passes a handle to the round function and a valid data argument. This call succeeds and returns the expected answer. The second call passes the same function handle and an improper data type (a MATLAB structure). This time, round fails, causing catcherr to display an error message that includes the failing function name:

```
catcherr(@round, 5.432)
ans =
Answer is 5

xstruct.value = 5.432;
catcherr(@round, xstruct)
Error executing function "round"
```

See Also

function_handle, str2func, functions

Purpose Declare function

Syntax function [out1, out2, ...] = myfun(in1, in2, ...)

Description

function [out1, out2, ...] = myfun(in1, in2, ...) declares the function myfun, and its inputs and outputs. The function declaration must be the first executable line of any MATLAB function.

The existing commands and functions that compose the new function reside in a text file that has a .m extension to its filename.

MATLAB program files can be either *scripts* or *functions*. Scripts are simply files containing a sequence of MATLAB statements. Functions make use of their own local variables and accept input arguments.

The name of a MATLAB function file begins with an alphabetic character and has a filename extension of .m. The file name, less its extension, is what MATLAB searches for when you try to use the script or function.

The first line of a function defines the syntax with which you call it. The name you give to a function, as defined in the first line, should be the same as the name of the file containing the function, but without the .m extension.

The variables within the body of the function are all local variables.

A *subfunction*, visible only to the other functions in the same file, is created by defining a new function with the function keyword after the body of the preceding function or subfunction. Subfunctions are not visible outside the file where they are defined.

You can terminate any type of function with an end statement, but doing so is not required unless the file containing the function also contains one or more nested functions. Within this file, *every* function (including primary, nested, private, and subfunctions) must be terminated with an end.

Functions normally return when the end of the function is reached. Use a return statement to force an early return.

When MATLAB does not recognize a function by name, it searches for a file of the same name on disk. If the function is found, MATLAB compiles it into memory for subsequent use. The section "Determining Which Function Gets Called" in the MATLAB Programming Fundamentals documentation explains how MATLAB interprets variable and function names that you enter, and also covers the precedence used in function dispatching.

When you call a function from the command line or from another function, MATLAB parses the function and stores it in memory. The parsed function remains in memory until cleared with the clear command or you quit MATLAB. The pcode command performs the parsing step and stores the result on the disk as a P-file to be loaded later.

Examples Example 1

The existence of a file on disk called stat.m containing this code defines a new function called stat that calculates the mean and standard deviation of a vector:

```
function [mean,stdev] = stat(x)
n = length(x);
mean = sum(x)/n;
stdev = sqrt(sum((x-mean).^2/n));
```

Call the function, supplying two output variables on the left side of the equation:

```
[mean stdev] = stat([12.7 45.4 98.9 26.6 53/1])
mean =
    47.3200
stdev =
    29.4085
```

Example 2

avg is a subfunction within the file stat.m:

```
function [mean, stdev] = stat2(x)
```

```
n = length(x);
mean = avg(x,n);
stdev = sqrt(sum((x-avg(x,n)).^2)/n);
function mean = avg(x,n)
mean = sum(x)/n;
```

Call the function and compare the answer with that of Example 1, above:

```
[mean stdev] = stat2([12.7 45.4 98.9 26.6 53/1])
mean =
    47.3200
stdev =
    29.4085
```

See Also

nargin, nargout, pcode, varargin, varargout, what

Handle used in calling functions indirectly

Syntax

handle = @functionname

handle = @(arglist)anonymous_function

Description

handle = @functionname returns a handle to the specified MATLAB function.

A function handle is a MATLAB value that provides a means of calling a function indirectly. You can pass function handles in calls to other functions (often called *function functions*). You can also store function handles in data structures for later use (for example, as Handle Graphics callbacks). A function handle is one of the standard MATLAB data types.

At the time you create a function handle, the function you specify must be on the MATLAB path and in the current scope of the code creating the handle. For example, you can create a handle to a subfunction as long as you do so from within the file that defines that subfunction. This condition does not apply when you evaluate the function handle. You can, for example, execute a subfunction from a separate (out-of-scope) file using a function handle. This requires that the handle was created by the subfunction (in-scope).

handle = @(arglist)anonymous_function constructs an anonymous function and returns a handle to that function. The body of the function, to the right of the parentheses, is a single MATLAB statement or command. arglist is a comma-separated list of input arguments. Execute the function by calling it by means of the function handle, handle.

Remarks

The function handle is a standard MATLAB data type. As such, you can manipulate and operate on function handles in the same manner as on other MATLAB data types. This includes using function handles in structures and cell arrays:

```
S.a = @sin; S.b = @cos; S.c = @tan; C = {@sin, @cos, @tan};
```

However, standard matrices or arrays of function handles are not supported:

```
A = [@sin, @cos, @tan]; % This is not supported
```

For nonoverloaded functions, subfunctions, and private functions, a function handle references just the one function specified in the @functionname syntax. When you evaluate an overloaded function by means of its handle, the arguments the handle is evaluated with determine the actual function that MATLAB dispatches to.

Use isa(h, 'function_handle') to see if variable h is a function handle.

Examples Example 1 — Constructing a Handle to a Named Function

The following example creates a function handle for the humps function and assigns it to the variable fhandle.

```
fhandle = @humps;
```

Pass the handle to another function in the same way you would pass any argument. This example passes the function handle just created to fminbnd, which then minimizes over the interval [0.3, 1].

```
x = fminbnd(fhandle, 0.3, 1)
x =
    0.6370
```

The fminbnd function evaluates the @humps function handle. A small portion of the fminbnd file is shown below. In line 1, the function input parameter receives the function handle @humps that was passed in. The statement, in line 113, evaluates the handle.

```
function [xf,fval,exitflag,output] = ...
fminbnd(funfcn,ax,bx,options,varargin)
.
.
```

```
113 fx = funfcn(x, varargin\{:\});
```

Example 2 — Constructing a Handle to an Anonymous Function

The statement below creates an anonymous function that finds the square of a number. When you call this function, MATLAB assigns the value you pass in to variable x, and then uses x in the equation x.^2:

```
sqr = @(x) x.^2;
```

The @ operator constructs a function handle for this function, and assigns the handle to the output variable sqr. As with any function handle, you execute the function associated with it by specifying the variable that contains the handle, followed by a comma-separated argument list in parentheses. The syntax is

```
fhandle(arg1, arg2, ..., argN)
```

To execute the sqr function defined above, type

```
a = sqr(5)
a =
   25
```

Because sqr is a function handle, you can pass it in an argument list to other functions. The code shown here passes the sqr anonymous function to the MATLAB quad function to compute its integral from zero to one:

```
quad(sqr, 0, 1)
ans =
    0.3333
```

See Also

str2func, func2str, functions, isa

Information about function handle

Syntax

S = functions(funhandle)

Description

S = functions(funhandle) returns, in MATLAB structure S, the function name, type, filename, and other information for the function handle stored in the variable funhandle.

functions does not operate on nonscalar function handles. Passing a nonscalar function handle to functions results in an error.

Caution The functions function is provided for querying and debugging purposes. Because its behavior may change in subsequent releases, you should not rely upon it for programming purposes.

This table lists the standard fields of the return structure.

Field Name	Field Description
function	Function name
type	Function type (e.g., simple, overloaded)
file	The file to be executed when the function handle is evaluated with a nonoverloaded data type

Examples Example 1

To obtain information on a function handle for the poly function, type

```
f = functions(@poly)
f =
   function: 'poly'
   type: 'simple'
```

file: '\$matlabroot\toolbox\matlab\polyfun\poly.m'

(The term \$matlabroot used in this example stands for the file specification of the directory in which MATLAB software is installed for your system. Your output will display this file specification.)

Access individual fields of the returned structure using dot selection notation:

```
f.type
ans =
    simple
```

Example 2

The function get_handles returns function handles for a subfunction and private function in output arguments s and p respectively:

```
function [s, p] = get_handles
s = @mysubfun;
p = @myprivatefun;
%
function mysubfun
disp 'Executing subfunction mysubfun'
```

Call get_handles to obtain the two function handles, and then pass each to the functions function. MATLAB returns information in a structure having the fields function, type, file, and parentage. The file field contains the file specification for the subfunction or private function:

```
[fsub fprv] = get_handles;
functions(fsub)
ans =
    function: 'mysubfun'
        type: 'scopedfunction'
        file: 'c:\matlab\get_handles.m'
    parentage: {'mysubfun' 'get_handles'}
functions(fprv)
```

```
ans =
   function: 'myprivatefun'
       type: 'scopedfunction'
       file: 'c:\matlab\private\myprivatefun.m'
   parentage: {'myprivatefun'}
```

Example 3

In this example, the function get_handles_nested.m contains a nested function nestfun. This function has a single output which is a function handle to the nested function:

```
function handle = get_handles_nested(A)
nestfun(A);

function y = nestfun(x)
    y = x + 1;
    end

handle = @nestfun;
end
```

Call this function to get the handle to the nested function. Use this handle as the input to functions to return the information shown here. Note that the function field of the return structure contains the names of the nested function and the function in which it is nested in the format. Also note that functions returns a workspace field containing the variables that are in context at the time you call this function by its handle:

```
fh = get_handles_nested(5);
fhinfo = functions(fh)
fhinfo =
    function: 'get_handles_nested/nestfun'
        type: 'nested'
        file: 'c:\matlab\get_handles_nested.m'
    workspace: [1x1 struct]
```

functions

fhinfo.workspace
ans =
 handle: @get_handles_nested/nestfun
 A: 5

See Also function_handle

Evaluate general matrix function

Syntax

```
F = funm(A,fun)
F = funm(A, fun, options)
F=funm(A, fun, options, p1, p2,...)
[F, exitflag] = funm(...)
[F, exitflag, output] = funm(...)
```

Description

F = funm(A, fun) evaluates the user-defined function fun at the square matrix argument A. F = fun(x, k) must accept a vector x and an integer k, and return a vector f of the same size of x, where f(i) is the kth derivative of the function fun evaluated at x(i). The function represented by fun must have a Taylor series with an infinite radius of convergence, except for fun = @log, which is treated as a special case.

You can also use funm to evaluate the special functions listed in the following table at the matrix A.

Function	Syntax for Evaluating Function at Matrix A
exp	funm(A, @exp)
log	funm(A, @log)
sin	funm(A, @sin)
cos	funm(A, @cos)
sinh	funm(A, @sinh)
cosh	funm(A, @cosh)

For matrix square roots, use sqrtm(A) instead. For matrix exponentials, which of expm(A) or funm(A, @exp) is the more accurate depends on the matrix A.

The function represented by fun must have a Taylor series with an infinite radius of convergence. The exception is @log, which is treated as a special case. "Parameterizing Functions", in the online MATLAB Mathematics documentation, explains how to provide additional parameters to the function fun, if necessary.

funm

F = funm(A, fun, options) sets the algorithm's parameters to the values in the structure options.

The following table lists the fields of options.

Field	Description	Values
options.Display	Level of display	'off' (default), 'on', 'verbose'
options.TolBlk	Tolerance for blocking Schur form	Positive scalar. The default is 0.1.
options.TolTay	Termination tolerance for evaluating the Taylor series of diagonal blocks	Positive scalar. The default is eps.
options.MaxTerms	Maximum number of Tayor series terms	Positive integer. The default is 250.
options.MaxSqrt	When computing a logarithm, maximum number of square roots computed in inverse scaling and squaring method.	Positive integer. The default is 100.
options.Ord	Specifies the ordering of the Schur form T.	A vector of length length(A). options.Ord(i) is the index of the block into which T(i,i) is placed. The default is [].

F=funm(A, fun, options, p1, p2,...) passes extra inputs p1, p2,... to the function.

[F, exitflag] = funm(...) returns a scalar exitflag that describes the exit condition of funm. exitflag can have the following values:

- 0 The algorithm was successful.
- 1 One or more Taylor series evaluations did not converge, or, in the case of a logarithm, too many square roots are needed. However, the computed value of F might still be accurate. This is different from R13 and earlier versions that returned an expensive and often inaccurate error estimate as the second output argument.

[F, exitflag, output] = funm(...) returns a structure output with the following fields:

Field	Description
output.terms	Vector for which output.terms(i) is the number of Taylor series terms used when evaluating the <i>i</i> th block, or, in the case of the logarithm, the number of square roots of matrices of dimension greater than 2.
output.ind	Cell array for which the (i,j) block of the reordered Schur factor T is T(output.ind{i}, output.ind{j}).
output.ord	Ordering of the Schur form, as passed to ordschur
output.T	Reordered Schur form

If the Schur form is diagonal then output = struct('terms',ones(n,1),'ind',{1:n}).

Examples Example 1

The following command computes the matrix sine of the 3-by-3 magic matrix.

```
F=funm(magic(3), @sin)
F =
```

```
-0.3850 1.0191 0.0162
0.6179 0.2168 -0.1844
0.4173 -0.5856 0.8185
```

Example 2

The statements

```
S = funm(X,@sin);
C = funm(X,@cos);
```

produce the same results to within roundoff error as

```
E = expm(i*X);
C = real(E);
S = imag(E);
```

In either case, the results satisfy S*S+C*C = I, where I = eye(size(X)).

Example 3

To compute the function exp(x) + cos(x) at A with one call to funm, use

```
F = funm(A,@fun_expcos)
```

where fun_expcos is the following M-file function.

```
function f = fun_expcos(x, k)
% Return kth derivative of exp + cos at X.
    g = mod(ceil(k/2),2);
    if mod(k,2)
        f = exp(x) + sin(x)*(-1)^g;
    else
        f = exp(x) + cos(x)*(-1)^g;
    end
```

Algorithm

The algorithm funm uses is described in [1].

See Also

expm, logm, sqrtm, function_handle (@)

References

- [1] Davies, P. I. and N. J. Higham, "A Schur-Parlett algorithm for computing matrix functions," *SIAM J. Matrix Anal. Appl.*, Vol. 25, Number 2, pp. 464-485, 2003.
- [2] Golub, G. H. and C. F. Van Loan, *Matrix Computation*, Third Edition, Johns Hopkins University Press, 1996, p. 384.
- [3] Moler, C. B. and C. F. Van Loan, "Nineteen Dubious Ways to Compute the Exponential of a Matrix, Twenty-Five Years Later" *SIAM Review 20*, Vol. 45, Number 1, pp. 1-47, 2003.

Write data to binary file

Syntax

```
fwrite(fileID, A)
fwrite(fileID, A, precision)
fwrite(fileID, A, precision, skip)
```

fwrite(fileID, A, precision, skip, machineformat)

count = fwrite(...)

Description

fwrite(fileID, A) writes the elements of array A to a binary file in column order.

fwrite(fileID, A, precision) translates the values of A according to the form and size described by the precision.

fwrite(fileID, A, precision, skip) skips skip bytes before writing each value. If precision is bitn or ubitn, specify skip in bits.

fwrite(fileID, A, precision, skip, machineformat) writes data with the specified machineformat. The skip parameter is optional.

count = fwrite(...) returns the number of elements of A that fwrite
successfully writes to the file.

Input Arguments

fileID

One of the following:

- An integer file identifier obtained from fopen.
- 1 for standard output (the screen).
- 2 for standard error.

Α

Numeric or character array.

precision

String in single quotation marks that controls the form and size of the output. The following table shows possible values for *precision*.

Value Type	Precision	Bits (Bytes)
Integers, unsigned	uint uint8 uint16 uint32 uint64 uchar unsigned char ushort ulong	32 (4) 8 (1) 16 (2) 32 (4) 64 (8) 8 (1) 8 (1) 16 (2) system-dependent
	ubit <i>n</i>	$1 \le n \le 64$
Integers, signed	int int8 int16 int32 int64 integer*1 integer*2 integer*3 integer*4 schar signed char short long bitn	32 (4) 8 (1) 16 (2) 32 (4) 64 (8) 8 (1) 16 (2) 32 (4) 64 (8) 8 (1) 8 (1) 8 (1) 16 (2) system-dependent 1 ≤ n ≤ 64

Value Type	Precision	Bits (Bytes)
Floating-point numbers	single double float float32 float64 real*4 real*8	32 (4) 64 (8) 32 (4) 32 (4) 64 (8) 32 (4) 64 (8)
Characters	char*1 char	8 (1) Depends on the encoding scheme associated with the file. Set encoding with fopen.

long and ulong are 32 bits on 32-bit systems, and 64 bits on 64-bit systems.

If you specify a precision of bitn or ubitn, and a value is out of range, fwrite sets all bits for that value.

Default: uint8

skip

Number of bytes to skip before writing each value. If you specify a *precision* of bitn or ubitn, specify *skip* in bits. Use this parameter to insert data into noncontiguous fields in fixed-length records.

Default: 0

machineformat

String that specifies the order for writing bytes within the file. For bitn and ubitn precisions, specifies the order for writing bits within a byte. Use this parameter when you plan to read and write to the same file on different systems.

Possible values are:

```
'n' or 'native'

The byte ordering that your system uses (default)

'b' or 'ieee-be'

Big-endian ordering

'1' or 'ieee-le'

Little-endian ordering, 64-bit data type

'a' or 'ieee-le.164'

Little-endian ordering, 64-bit data type
```

Windows systems use little-endian ordering, and most UNIX systems use big-endian ordering, for both bytes and bits.

Examples

Create a 100-byte binary file containing the 25 elements of the 5-by-5 magic square, stored as 4-byte integers:

```
fid = fopen('magic5.bin', 'w');
fwrite(fid, magic(5), 'integer*4');
fclose(fid);
```

See Also

fclose | ferror | fopen | fprintf | fscanf | fread

How To

- · "Overwriting or Appending to an Existing File"
- · "Creating a File for Use on a Different System"
- · "Writing and Reading Complex Numbers"

Write binary data to device

Syntax

fwrite(obj,A)

fwrite(obj,A,'precision')

fwrite(obj,A,'mode')

fwrite(obj,A,'precision','mode')

Description

fwrite(obj,A) writes the binary data A to the device connected to the serial port object, obj.

fwrite(obj,A,'precision') writes binary data with precision specified by precision.

precision controls the number of bits written for each value and the interpretation of those bits as integer, floating-point, or character values. If precision is not specified, uchar (an 8-bit unsigned character) is used. The supported values for precision are listed below in Remarks.

fwrite(obj,A,'mode') writes binary data with command line access specified by mode. If mode is sync, A is written synchronously and the command line is blocked. If mode is async, A is written asynchronously and the command line is not blocked. If mode is not specified, the write operation is synchronous.

fwrite(obj,A,'precision','mode') writes binary data with precision specified by precision and command line access specified by mode.

Remarks

Before you can write data to the device, it must be connected to obj with the fopen function. A connected serial port object has a Status property value of open. An error is returned if you attempt to perform a write operation while obj is not connected to the device.

The ValuesSent property value is increased by the number of values written each time fwrite is issued.

An error occurs if the output buffer cannot hold all the data to be written. You can specify the size of the output buffer with the OutputBufferSize property.

If you use the help command to display help for fwrite, then you need to supply the pathname shown below.

help serial/fwrite

fwrite will return an error message if you set the FlowControl property to hardware on a serial object, and a hardware connection is not detected. This occurs if a device is not connected, or a connected device is not asserting that is ready to receive data. Check you remote device's status and flow control settings to see if hardware flow control is causing errors in MATLAB.

Note If you want to check to see if the device is asserting that it is ready to receive data, set the FlowControl to none. Once you connect to the device check the PinStatus structure for ClearToSend. If ClearToSend is off, there is a problem on the remote device side. If ClearToSend is on, there is a hardware FlowControl device prepared to receive data and you can execute fwrite.

Synchronous Versus Asynchronous Write Operations

By default, data is written to the device synchronously and the command line is blocked until the operation completes. You can perform an asynchronous write by configuring the *mode* input argument to be async. For asynchronous writes:

- The BytesToOutput property value is continuously updated to reflect the number of bytes in the output buffer.
- The callback function specified for the OutputEmptyFcn property is executed when the output buffer is empty.

You can determine whether an asynchronous write operation is in progress with the TransferStatus property.

Synchronous and asynchronous write operations are discussed in more detail in Writing Data.

Rules for Completing a Write Operation with fwrite

A binary write operation using fwrite completes when:

- The specified data is written.
- The time specified by the Timeout property passes.

Note The Terminator property is not used with binary write operations.

Supported Precisions

The supported values for *precision* are listed below.

Data Type	Precision	Interpretation
Character	uchar	8-bit unsigned character
	schar	8-bit signed character
	char	8-bit signed or unsigned character
Integer	int8	8-bit integer
	int16	16-bit integer
	int32	32-bit integer
	uint8	8-bit unsigned integer
	uint16	16-bit unsigned integer
	uint32	32-bit unsigned integer
	short	16-bit integer
	int	32-bit integer
	long	32- or 64-bit integer
	ushort	16-bit unsigned integer
	uint	32-bit unsigned integer

Data Type	Precision	Interpretation
	ulong	32- or 64-bit unsigned integer
Floating-point	single	32-bit floating point
	float32	32-bit floating point
	float	32-bit floating point
	double	64-bit floating point
	float64	64-bit floating point

See Also Functions

fopen, fprintf

Properties

BytesToOutput, OutputBufferSize, OutputEmptyFcn, Status, Timeout, TransferStatus, ValuesSent

Find root of continuous function of one variable

Syntax

```
x = fzero(fun,x0)
x = fzero(fun,x0,options)
[x,fval] = fzero(...)
[x,fval,exitflag] = fzero(...)
[x,fval,exitflag,output] = fzero(...)
```

Description

x = fzero(fun,x0) tries to find a zero of fun near x0, if x0 is a scalar. fun is a function handle. See "Function Handles" in the MATLAB Programming documentation for more information. The value x returned by fzero is near a point where fun changes sign, or NaN if the search fails. In this case, the search terminates when the search interval is expanded until an Inf, NaN, or complex value is found.

"Parameterizing Functions" in the MATLAB Mathematics documentation, explains how to pass additional parameters to your objective function fun. See also "Example 2" on page 2-1641 and "Example 3" on page 2-1641 below.

If x0 is a vector of length two, fzero assumes x0 is an interval where the sign of fun(x0(1)) differs from the sign of fun(x0(2)). An error occurs if this is not true. Calling fzero with such an interval guarantees fzero will return a value near a point where fun changes sign.

x = fzero(fun,x0,options) minimizes with the optimization
parameters specified in the structure options. You can define these
parameters using the optimset function. fzero uses these options
structure fields:

Display	Level of display. 'off' displays no output; 'iter' displays output at each iteration; 'final' displays just the final output; 'notify' (default) displays output only if the function does not converge.
FunValCheck	Check whether objective function values are valid. 'on' displays an error when the objective function returns a value that is complex or NaN. 'off' (the default) displays no error.
OutputFcn	User-defined function that is called at each iteration. See "Output Functions" in MATLAB Mathematics for more information.
PlotFens	Plots various measures of progress while the algorithm executes, select from predefined plots or write your own. Pass a function handle or a cell array of function handles. The default is none ([]). • @optimplotx plots the current point • @optimplotfval plots the function value See "Plot Functions" in MATLAB Mathematics for more information.
TolX	Termination tolerance on x

[x,fval] = fzero(...) returns the value of the objective function fun at the solution x.

[x,fval,exitflag] = fzero(...) returns a value exitflag that describes the exit condition of fzero:

- 1 Function converged to a solution x.
- -1 Algorithm was terminated by the output function.
- -3 NaN or Inf function value was encountered during search for an interval containing a sign change.

- -4 Complex function value was encountered during search for an interval containing a sign change.
- -5 fzero might have converged to a singular point.
- -6 fzero can not detect a change in sign of the function.

[x,fval,exitflag,output] = fzero(...) returns a structure output that contains information about the optimization in the following fields:

 ${\bf algorithm} \qquad \qquad {\bf Algorithm} \ {\bf used}$

funcCount Number of function evaluations

intervaliterations Number of iterations taken to find an interval

iterations Number of zero-finding iterations

message Exit message

Note For the purposes of this command, zeros are considered to be points where the function actually crosses, not just touches, the *x*-axis.

Arguments

fun is the function whose zero is to be computed. It accepts a vector x and returns a scalar f, the objective function evaluated at x. The function fun can be specified as a function handle for an M-file function

```
x = fzero(@myfun,x0);
```

where myfun is an M-file function such as

```
function f = myfun(x)
f = ... % Compute function value at x
```

or as a function handle for an anonymous function:

```
x = fzero(@(x)sin(x*x),x0);
```

Other arguments are described in the syntax descriptions above.

Examples Example 1

Calculate π by finding the zero of the sine function near 3.

```
x = fzero(@sin,3)
x =
    3.1416
```

Example 2

To find the zero of cosine between 1 and 2

```
x = fzero(@cos,[1 2])
x =
    1.5708
```

Note that cos(1) and cos(2) differ in sign.

Example 3

To find a zero of the function $f(x) = x^3 - 2x - 5$, write an anonymous function f:

```
f = @(x)x.^3-2*x-5;
```

Then find the zero near 2:

```
z = fzero(f,2)
z =
2.0946
```

Because this function is a polynomial, the statement roots([1 0 -2 -5]) finds the same real zero, and a complex conjugate pair of zeros.

```
2.0946
-1.0473 + 1.1359i
-1.0473 - 1.1359i
```

If fun is parameterized, you can use anonymous functions to capture the problem-dependent parameters. For example, suppose you want to

minimize the objective function myfun defined by the following M-file function.

```
function f = myfun(x,a)
f = cos(a*x);
```

Note that myfun has an extra parameter a, so you cannot pass it directly to fzero. To optimize for a specific value of a, such as a = 2.

1 Assign the value to a.

```
a = 2; % define parameter first
```

2 Call fzero with a one-argument anonymous function that captures that value of a and calls myfun with two arguments:

```
x = fzero(@(x) myfun(x,a),0.1)
```

Algorithm

The fzero command is an M-file. The algorithm, which was originated by T. Dekker, uses a combination of bisection, secant, and inverse quadratic interpolation methods. An Algol 60 version, with some improvements, is given in [1]. A Fortran version, upon which the fzero M-file is based, is in [2].

Limitations

The fzero command finds a point where the function changes sign. If the function is *continuous*, this is also a point where the function has a value near zero. If the function is not continuous, fzero may return values that are discontinuous points instead of zeros. For example, fzero(@tan,1) returns 1.5708, a discontinuous point in tan.

Furthermore, the fzero command defines a zero as a point where the function crosses the x-axis. Points where the function touches, but does not cross, the x-axis are not valid zeros. For example, $y = x.^2$ is a parabola that touches the x-axis at 0. Because the function never crosses the x-axis, however, no zero is found. For functions with no valid zeros, fzero executes until Inf, NaN, or a complex value is detected.

See Also

roots, fminbnd, optimset, function_handle (@), "Anonymous $\underline{}$

Functions"

References

[1] Brent, R., Algorithms for Minimization Without Derivatives, Prentice-Hall, 1973.

[2] Forsythe, G. E., M. A. Malcolm, and C. B. Moler, *Computer Methods for Mathematical Computations*, Prentice-Hall, 1976.

Test matrices

Syntax

```
[A,B,C,...] = gallery(matname,P1,P2,...)
[A,B,C,...] = gallery(matname,P1,P2,...,classname)
gallery(3)
gallery(5)
```

Description

[A,B,C,...] = gallery(matname,P1,P2,...) returns the test matrices specified by the quoted string matname. The matname input is the name of a matrix family selected from the table below. P1,P2,... are input parameters required by the individual matrix family. The number of optional parameters P1,P2,... used in the calling syntax varies from matrix to matrix. The exact calling syntaxes are detailed in the individual matrix descriptions below.

[A,B,C,...] = gallery(matname,P1,P2,...,classname) produces a matrix of class classname. The classname input is a quoted string that must be either 'single' or 'double' (unless matname is 'integerdata', in which case 'int8', 'int16', 'int32', 'uint8', 'uint16', and 'uint32' are also allowed). If classname is not specified, then the class of the matrix is determined from those arguments among P1,P2,... that do not specify dimensions or select an option. If any of these arguments is of class single then the matrix is single; otherwise the matrix is double.

gallery(3) is a badly conditioned 3-by-3 matrix and gallery(5) is an interesting eigenvalue problem.

The gallery holds over fifty different test matrix functions useful for testing algorithms and other purposes.

- binomial
- cauchy
- chebspec
- chebvand
- chow

- circul
- clement
- compar
- condex
- cycol
- dorr
- dramadah
- fiedler
- forsythe
- frank
- gearmat
- gcdmat
- grcar
- hanowa
- house
- integerdata
- invhess
- invol
- ipjfact
- jordbloc
- kahan
- kms
- krylov
- lauchli
- lehmer

gallery

- leslie
- lesp
- lotkin
- minij
- moler
- neumann
- normaldata
- orthog
- parter
- pei
- poisson
- prolate
- randcolu
- randcorr
- randhess
- randjorth
- rando
- randsvd
- redheff
- riemann
- ris
- sampling
- smoke
- toeppd
- tridiag

- triw
- uniformdata
- wathen
- wilk

binomial - Multiple of involutory matrix

A = gallery('binomial',n) returns an n-by-n matrix,with integer entries such that $A^2 = 2^{(n-1)} eve(n)$.

Thus, $B = A*2^((1-n)/2)$ is involutory, that is, $B^2 = eye(n)$.

cauchy - Cauchy matrix

C = gallery('cauchy', x, y) returns an n-by-n matrix, C(i,j) = 1/(x(i)+y(j)). Arguments x and y are vectors of length n. If you pass in scalars for x and y, they are interpreted as vectors 1:x and 1:y.

C = gallery('cauchy',x) returns the same as above with y = x. That is, the command returns C(i,j) = 1/(x(i)+x(j)).

Explicit formulas are known for the inverse and determinant of a Cauchy matrix. The determinant det(C) is nonzero if x and y both have distinct elements. C is totally positive if $0 < x(1) < \dots < x(n)$ and $0 < y(1) < \dots < y(n)$.

chebspec — Chebyshev spectral differentiation matrix

C = gallery('chebspec',n,switch) returns a Chebyshev spectral differentiation matrix of order n. Argument switch is a variable that determines the character of the output matrix. By default, switch = 0.

For switch = 0 ("no boundary conditions"), C is nilpotent ($C^n = 0$) and has the null vector ones (n,1). The matrix C is similar to a Jordan block of size n with eigenvalue zero.

For switch = 1, C is nonsingular and well-conditioned, and its eigenvalues have negative real parts.

The eigenvector matrix of the Chebyshev spectral differentiation matrix is ill-conditioned.

chebvand — Vandermonde-like matrix for the Chebyshev polynomials

C = gallery('chebvand',p) produces the (primal) Chebyshev Vandermonde matrix based on the vector of points p, which define where the Chebyshev polynomial is calculated.

C = gallery('chebvand',m,p) where m is scalar, produces a rectangular version of the above, with m rows.

If p is a vector, then $C(i, j) = T_{i-1}(p(j))$ where T_{i-1} is the Chebyshev polynomial of degree i-1. If p is a scalar, then p equally spaced points on the interval [0,1] are used to calculate C.

chow - Singular Toeplitz lower Hessenberg matrix

A = gallery('chow',n,alpha,delta) returns A such that

A = H(alpha) + delta*eye(n), where $H_{i,j}(\alpha) = \alpha^{(i-j+1)}$ and argument n is the order of the Chow matrix. Default value for scalars alpha and delta are 1 and 0, respectively.

H(alpha) has p = floor(n/2) eigenvalues that are equal to zero. The rest of the eigenvalues are equal to $4*alpha*cos(k*pi/(n+2))^2$, k=1:n-p.

circul - Circulant matrix

C = gallery('circul', v) returns the circulant matrix whose first
row is the vector v.

A circulant matrix has the property that each row is obtained from the previous one by cyclically permuting the entries one step forward. It is a special Toeplitz matrix in which the diagonals "wrap around."

If v is a scalar, then C = gallery('circul',1:v).

The eigensystem of C (n-by-n) is known explicitly: If t is an nth root of unity, then the inner product of v and $w = [1 \ t \ t^2 ... t^{(n-1)}]$ is an eigenvalue of C and w(n:-1:1) is an eigenvector.

clement — Tridiagonal matrix with zero diagonal entries

A = gallery('clement',n,k) returns an n-by-n tridiagonal matrix with zeros on its main diagonal and known eigenvalues. It is singular if n is odd. About 64 percent of the entries of the inverse are zero. The eigenvalues include plus and minus the numbers n-1, n-3, n-5, ..., (1 or 0).

For k=0 (the default), A is nonsymmetric. For k=1, A is symmetric.

gallery('clement',n,1) is diagonally similar to gallery('clement',n).

For odd N = 2*M+1, M+1 of the singular values are the integers $sqrt((2*M+1)^2 - (2*K+1)^2)$, K = 0:M.

Note Similar properties hold for gallery('tridiag',x,y,z) where y = zeros(n,1). The eigenvalues still come in plus/minus pairs but they are not known explicitly.

compar — Comparison matrices

A = gallery('compar', A, 1) returns A with each diagonal element replaced by its absolute value, and each off-diagonal element replaced by minus the absolute value of the largest element in absolute value in its row. However, if A is triangular compar(A, 1) is too.

gallery('compar',A) is diag(B) - tril(B,-1) - triu(B,1), where B = abs(A). compar(A) is often denoted by M(A) in the literature.

gallery('compar',A,0) is the same as gallery('compar',A).

condex — Counter-examples to matrix condition number estimators

A = gallery('condex',n,k,theta) returns a "counter-example" matrix to a condition estimator. It has order n and scalar parameter theta (default 100).

The matrix, its natural size, and the estimator to which it applies are specified by k:

k = 1	4-by-4	LINPACK
k = 2	3-by-3	LINPACK
k = 3	arbitrary	LINPACK (rcond) (independent of theta)
k = 4	n >= 4	LAPACK (RCOND) (default). It is the inverse of this matrix that is a counter-example.

If n is not equal to the natural size of the matrix, then the matrix is padded out with an identity matrix to order n.

cycol - Matrix whose columns repeat cyclically

A = gallery('cycol', $[m \ n]$, k) returns an m-by-n matrix with cyclically repeating columns, where one "cycle" consists of randn(m,k). Thus, the rank of matrix A cannot exceed k, and k must be a scalar.

Argument k defaults to round(n/4), and need not evenly divide n.

A = gallery('cycol',n,k), where n is a scalar, is the same as gallery('cycol',[n n],k).

dorr — Diagonally dominant, ill-conditioned, tridiagonal matrix

[c,d,e] = gallery('dorr',n,theta) returns the vectors defining an n-by-n, row diagonally dominant, tridiagonal matrix that is ill-conditioned for small nonnegative values of theta. The default value of theta is 0.01. The Dorr matrix itself is the same as gallery('tridiag',c,d,e).

A = gallery('dorr',n,theta) returns the matrix itself, rather than the defining vectors.

dramadah — Matrix of zeros and ones whose inverse has large integer entries

A = gallery('dramadah',n,k) returns an n-by-n matrix of 0's and 1's for which mu(A) = norm(inv(A),'fro') is relatively large, although not necessarily maximal. An anti-Hadamard matrix A is a matrix with elements 0 or 1 for which mu(A) is maximal.

n and k must both be scalars. Argument k determines the character of the output matrix:

- k = 1 Default. A is Toeplitz, with abs(det(A)) = 1, and mu(A) > c(1.75)^n, where c is a constant. The inverse of A has integer entries.
- k=2 A is upper triangular and Toeplitz. The inverse of A has integer entries.
- k = 3
 A has maximal determinant among lower Hessenberg (0,1) matrices. det(A) = the nth Fibonacci number.
 A is Toeplitz. The eigenvalues have an interesting distribution in the complex plane.

fiedler - Symmetric matrix

A = gallery('fiedler',c), where c is a length n vector, returns the n-by-n symmetric matrix with elements abs(n(i)-n(j)). For scalar c, A = gallery('fiedler',1:c).

Matrix A has a dominant positive eigenvalue and all the other eigenvalues are negative.

Explicit formulas for inv(A) and det(A) are given in [Todd, J., Basic Numerical Mathematics, Vol. 2: Numerical Algebra, Birkhauser, Basel, and Academic Press, New York, 1977, p. 159] and attributed to Fiedler. These indicate that inv(A) is tridiagonal except for nonzero (1,n) and (n,1) elements.

forsythe - Perturbed Jordan block

A = gallery('forsythe',n,alpha,lambda) returns the n-by-n matrix equal to the Jordan block with eigenvalue lambda, excepting that A(n,1) = alpha. The default values of scalars alpha and lambda are sqrt(eps) and 0, respectively.

The characteristic polynomial of A is given by:

```
det(A-t*I) = (lambda-t)^N - alpha*(-1)^n.
```

frank - Matrix with ill-conditioned eigenvalues

F = gallery('frank',n,k) returns the Frank matrix of order n. It is upper Hessenberg with determinant 1. If k = 1, the elements are reflected about the anti-diagonal (1,n) - (n,1). The eigenvalues of F may be obtained in terms of the zeros of the Hermite polynomials. They are positive and occur in reciprocal pairs; thus if n is odd, 1 is an eigenvalue. F has floor(n/2) ill-conditioned eigenvalues — the smaller ones.

gcdmat — Greatest common divisor matrix

A = gallery('gcdmat',n) returns the n-by-n matrix with (i,j) entry gcd(i,j). Matrix A is symmetric positive definite, and A.^r is symmetric positive semidefinite for all nonnegative r.

gearmat – Gear matrix

A = gallery('gearmat',n,i,j) returns the n-by-n matrix with ones on the sub- and super-diagonals, sign(i) in the (1,abs(i)) position, sign(j) in the (n,n+1-abs(j)) position, and zeros everywhere else. Arguments i and j default to n and -n, respectively.

Matrix A is singular, can have double and triple eigenvalues, and can be defective.

All eigenvalues are of the form 2*cos(a) and the eigenvectors are of the form [sin(w+a), sin(w+2*a), ..., sin(w+n*a)], where a and w are given in Gear, C. W., "A Simple Set of Test Matrices for Eigenvalue Programs," *Math. Comp.*, Vol. 23 (1969), pp. 119-125.

grcar — Toeplitz matrix with sensitive eigenvalues

A = gallery('grcar',n,k) returns an n-by-n Toeplitz matrix with -1s on the subdiagonal, 1s on the diagonal, and k superdiagonals of 1s. The default is k = 3. The eigenvalues are sensitive.

hanowa — Matrix whose eigenvalues lie on a vertical line in the complex plane

A = gallery('hanowa',n,d) returns an n-by-n block 2-by-2 matrix of the form:

```
[d*eye(m) -diag(1:m)
diag(1:m) d*eye(m)]
```

Argument n is an even integer n=2*m. Matrix A has complex eigenvalues of the form $d \pm k*i$, for $1 \le k \le m$. The default value of d is -1.

house - Householder matrix

[v,beta,s] = gallery('house',x,k) takes x, an n-element column vector, and returns V and beta such that H*x = s*e1. In this expression, e1 is the first column of eye(n), abs(s) = norm(x), and H = eye(n) - beta*V*V' is a Householder matrix.

k determines the sign of s:

```
k = 0 sign(s) = -sign(x(1)) (default)

k = 1 sign(s) = sign(x(1))

k = 2 sign(s) = 1 (x must be real)
```

If x is complex, then sign(x) = x./abs(x) when x is nonzero.

If x = 0, or if x = alpha*e1 (alpha >= 0) and either k = 1 or k = 2, then V = 0, beta = 1, and s = x(1). In this case, H is the identity matrix, which is not strictly a Householder matrix.

[v, beta] = gallery('house',x) takes x, a scalar or n-element column vector, and returns v and beta such that eye(n,n) -

beta*v*v' is a Householder matrix. A Householder matrix H satisfies the relationship

```
H*x = -sign(x(1))*norm(x)*e1
```

where e1 is the first column of eye(n,n). Note that if x is complex, then sign(x) exp(i*arg(x)) (which equals x./abs(x) when x is nonzero).

If x = 0, then v = 0 and beta = 1.

integerdata — Array of arbitrary data from uniform distribution on specified range of integers

A = gallery('integerdata',imax,[m,n,...],j) returns an m-by-n-by-... array A whose values are a sample from the uniform distribution on the integers 1:imax. j must be an integer value in the interval [0, 2^32-1]. Calling gallery('integerdata', ...) with different values of J will return different arrays. Repeated calls to gallery('integerdata',...) with the same imax, size vector and j inputs will always return the same array.

In any call to gallery('integerdata', ...) you can substitute individual inputs m,n,... for the size vector input [m,n,...]. For example, gallery('integerdata',7,[1,2,3,4],5) is equivalent to gallery('integerdata',7,1,2,3,4,5).

A = gallery('integerdata',[imin imax],[m,n,...],j) returns an m-by-n-by-... array A whose values are a sample from the uniform distribution on the integers imin:imax.

[A,B,...] = gallery('integerdata',[imin imax],[m,n,...],j) returns multiple m-by-n-by-... arrays A, B, ..., containing different values.

A = gallery('integerdata',[imin imax],[m,n,...],j,classname)produces an array of class classname. classname must be 'uint8', 'uint16', 'uint32', 'int8', 'int16', int32', 'single' or 'double'.

invhess - Inverse of an upper Hessenberg matrix

A = gallery('invhess',x,y), where x is a length n vector and y is a length n-1 vector, returns the matrix whose lower triangle agrees

with that of ones(n,1)*x' and whose strict upper triangle agrees with that of $[1 \ y]*ones(1,n)$.

The matrix is nonsingular if $x(1) \sim 0$ and $x(i+1) \sim y(i)$ for all i, and its inverse is an upper Hessenberg matrix. Argument y defaults to -x(1:n-1).

If x is a scalar, invhess(x) is the same as invhess(1:x).

invol - Involutory matrix

A = gallery('invol',n) returns an n-by-n involutory (A*A = eye(n)) and ill-conditioned matrix. It is a diagonally scaled version of hilb(n).

B = (eve(n) - A)/2 and B = (eve(n) + A)/2 are idempotent (B*B = B).

ipjfact - Hankel matrix with factorial elements

[A,d] = gallery('ipjfact',n,k) returns A, an n-by-n Hankel matrix, and d, the determinant of A, which is known explicitly. If k = 0 (the default), then the elements of A are A(i,j) = (i+j)! If k = 1, then the elements of A are A(i,j) = (i+j)! If k = 1,

Note that the inverse of A is also known explicitly.

jordbloc – Jordan block

A = gallery('jordbloc',n,lambda) returns the n-by-n Jordan block with eigenvalue lambda. The default value for lambda is 1.

kahan — Upper trapezoidal matrix

A = gallery('kahan',n,theta,pert) returns an upper trapezoidal matrix that has interesting properties regarding estimation of condition and rank.

If n is a two-element vector, then A is n(1)-by-n(2); otherwise, A is n-by-n. The useful range of theta is 0 < theta < pi, with a default value of 1.2.

To ensure that the QR factorization with column pivoting does not interchange columns in the presence of rounding errors, the diagonal is perturbed by pert*eps*diag([n:-1:1]). The default pert is 25,

which ensures no interchanges for gallery ('kahan', n) up to at least n = 90 in IEEE arithmetic.

kms — Kac-Murdock-Szego Toeplitz matrix

A = gallery('kms',n,rho) returns the n-by-n Kac-Murdock-Szego Toeplitz matrix such that $A(i,j) = rho^{(abs(i-j))}$, for real rho.

For complex rho, the same formula holds except that elements below the diagonal are conjugated. rho defaults to 0.5.

The KMS matrix A has these properties:

- An LDL' factorization with L inv(gallery('triw',n,-rho,1))', and D(i,i) (1-abs(rho)^2)*eye(n), except D(1,1) = 1.
- Positive definite if and only if 0 < abs(rho) < 1.
- The inverse inv(A) is tridiagonal.

krylov - Krylov matrix

```
B = gallery('krylov',A,x,j) returns the Krylov matrix
[x, Ax, A^2x, ..., A^(j-1)x]
```

where A is an n-by-n matrix and x is a length n vector. The defaults are x ones(n,1), and j = n.

```
B = gallery('krylov',n) is the same as gallery('krylov',(randn(n)).
```

lauchli - Rectangular matrix

```
A = gallery('lauchli',n,mu) returns the (n+1)-by-n matrix
[ones(1,n); mu*eye(n)]
```

The Lauchli matrix is a well-known example in least squares and other problems that indicates the dangers of forming A'*A. Argument mu defaults to sqrt(eps).

lehmer — Symmetric positive definite matrix

A = gallery('lehmer',n) returns the symmetric positive definite n-by-n matrix such that A(i,j) = i/j for $j \ge i$.

The Lehmer matrix A has these properties:

- A is totally nonnegative.
- The inverse inv(A) is tridiagonal and explicitly known.
- The order n <= cond(A) <= 4*n*n.

leslie — Matrix of birth numbers and survival rates

L = gallery('leslie',a,b) is the n-by-n matrix from the Leslie population model with average birth numbers a(1:n) and survival rates b(1:n-1). It is zero, apart from the first row (which contains the a(i)) and the first subdiagonal (which contains the b(i)). For a valid model, the a(i) are nonnegative and the b(i) are positive and bounded by 1, i.e., 0 < b(i) <= 1.

L = gallery('leslie',n) generates the Leslie matrix with a = ones(n,1), b = ones(n-1,1).

lesp - Tridiagonal matrix with real, sensitive eigenvalues

A = gallery('lesp',n) returns an n-by-n matrix whose eigenvalues are real and smoothly distributed in the interval approximately [-2*N-3.5, -4.5].

The sensitivities of the eigenvalues increase exponentially as the eigenvalues grow more negative. The matrix is similar to the symmetric tridiagonal matrix with the same diagonal entries and with off-diagonal entries 1, via a similarity transformation with D = diag(1!, 2!, ..., n!).

lotkin — Lotkin matrix

A = gallery('lotkin',n) returns the Hilbert matrix with its first row altered to all ones. The Lotkin matrix A is nonsymmetric, ill-conditioned, and has many negative eigenvalues of small magnitude. Its inverse has integer entries and is known explicitly.

minij – Symmetric positive definite matrix

A = gallery('minij',n) returns the n-by-n symmetric positive definite matrix with A(i,j) = min(i,j).

The minij matrix has these properties:

- The inverse inv(A) is tridiagonal and equal to -1 times the second difference matrix, except its (n,n) element is 1.
- Givens' matrix, 2*A-ones(size(A)), has tridiagonal inverse and eigenvalues 0.5*sec((2*r-1)*pi/(4*n))^2, where r=1:n.
- (n+1)*ones(size(A))-A has elements that are max(i,j) and a tridiagonal inverse.

moler - Symmetric positive definite matrix

A = gallery('moler',n,alpha) returns the symmetric positive definite n-by-n matrix U'*U, where U = gallery('triw',n,alpha).

For the default alpha = -1, A(i,j) = min(i,j)-2, and A(i,i) = i. One of the eigenvalues of A is small.

neumann — Singular matrix from the discrete Neumann problem (sparse)

C = gallery('neumann',n) returns the sparse n-by-n singular, row diagonally dominant matrix resulting from discretizing the Neumann problem with the usual five-point operator on a regular mesh. Argument n is a perfect square integer $n=m^2$ or a two-element vector. C is sparse and has a one-dimensional null space with null vector ones(n,1).

normaldata — Array of arbitrary data from standard normal distribution

A = gallery('normaldata',[m,n,...],j) returns an m-by-n-by-... array A. The values of A are a random sample from the standard normal distribution. j must be an integer value in the interval [0, 2^32-1]. Calling gallery('normaldata', ...) with different values of j will return different arrays. Repeated calls to gallery('normaldata',...)

with the same size vector and j inputs will always return the same array.

In any call to gallery('normaldata', ...) you can substitute individual inputs m,n,... for the size vector input [m,n,...]. For example, gallery('normaldata',[1,2,3,4],5) is equivalent to gallery('normaldata',1,2,3,4,5).

[A,B,...] = gallery('normaldata',[m,n,...],j) returns multiple m-by-n-by-... arrays A, B, ..., containing different values.

A = gallery('normaldata',[m,n,...],j, classname) produces a matrix of class classname. classname must be either 'single' or 'double'.

Generate the arbitrary 6-by-4 matrix of data from the standard normal distribution N(0, 1) corresponding to j = 2:.

```
x = gallery('normaldata', [6, 4], 2);
```

Generate the arbitrary 1-by-2-by-3 single array of data from the standard normal distribution N(0, 1) corresponding to j = 17..

```
y = gallery('normaldata', 1, 2, 3, 17, 'single');
```

orthog — Orthogonal and nearly orthogonal matrices

Q = gallery('orthog',n,k) returns the kth type of matrix of order n, where k > 0 selects exactly orthogonal matrices, and k < 0 selects diagonal scalings of orthogonal matrices. Available types are:

```
k = 1  Q(i,j) = sqrt(2/(n+1)) * sin(i*j*pi/(n+1))
```

Symmetric eigenvector matrix for second difference matrix. This is the default.

$$k = 2$$
 $Q(i,j) = 2/(sqrt(2*n+1)) * $sin(2*i*j*pi/(2*n+1))$$

Symmetric.

- k = 3 Q(r,s) = exp(2*pi*i*(r-1)*(s-1)/n) / exp(1) Unitary, the Fourier matrix. Q^4 is the identity. This is essentially the same matrix as fft(eye(n))/sqrt(n)!
- k = 4 Helmert matrix: a permutation of a lower Hessenberg
 matrix, whose first row is ones(1:n)/sqrt(n).
- k = 5 Q(i,j) = sin(2*pi*(i-1)*(j-1)/n) + <math>cos(2*pi*(i-1)*(j-1)/n)

Symmetric matrix arising in the Hartley transform.

k = 6 Q(i,j) = sqrt(2/n)*cos((i-1/2)*(j-1/2)*pi/n)

Symmetric matrix arising as a discrete cosine transform.

- k = -2 Q(i,j) = cos((i-1)*(j-1/2)*pi/n)) Chebyshev Vandermonde-like matrix, based on zeros of T(n).

parter - Toeplitz matrix with singular values near pi

C = gallery('parter',n) returns the matrix C such that C(i,j) = 1/(i-j+0.5).

C is a Cauchy matrix and a Toeplitz matrix. Most of the singular values of C are very close to pi.

pei - Pei matrix

A = gallery('pei',n,alpha), where alpha is a scalar, returns the symmetric matrix alpha*eye(n) + ones(n). The default for alpha is 1. The matrix is singular for alpha equal to either 0 or -n.

poisson — Block tridiagonal matrix from Poisson's equation (sparse)

A = gallery('poisson',n) returns the block tridiagonal (sparse) matrix of order n^2 resulting from discretizing Poisson's equation with the 5-point operator on an n-by-n mesh.

prolate — Symmetric, ill-conditioned Toeplitz matrix

A = gallery('prolate',n,w) returns the n-by-n prolate matrix with parameter w. It is a symmetric Toeplitz matrix.

If 0 < w < 0.5 then A is positive definite

- The eigenvalues of A are distinct, lie in (0,1), and tend to cluster around 0 and 1.
- The default value of w is 0.25.

randcolu — Random matrix with normalized cols and specified singular values

A = gallery('randcolu',n) is a random n-by-n matrix with columns of unit 2-norm, with random singular values whose squares are from a uniform distribution.

A'*A is a correlation matrix of the form produced by gallery('randcorr',n).

gallery('randcolu',x) where x is an n-vector (n > 1), produces a random n-by-n matrix having singular values given by the vector x. The vector x must have nonnegative elements whose sum of squares is n.

gallery('randcolu',x,m) where m >= n, produces an m-by-n matrix.
gallery('randcolu',x,m,k) provides a further option:

k = 0	diag(x) is initially subjected to a random two-sided
	orthogonal transformation, and then a sequence of
	Givens rotations is applied (default).

k = 1 The initial transformation is omitted. This is much faster, but the resulting matrix may have zero entries.

For more information, see:

[1] Davies, P. I. and N. J. Higham, "Numerically Stable Generation of Correlation Matrices and Their Factors," *BIT*, Vol. 40, 2000, pp. 640-651.

randcorr — Random correlation matrix with specified eigenvalues

gallery('randcorr',n) is a random n-by-n correlation matrix with random eigenvalues from a uniform distribution. A correlation matrix is a symmetric positive semidefinite matrix with 1s on the diagonal (see corrcoef).

gallery('randcorr',x) produces a random correlation matrix having eigenvalues given by the vector x, where length(x) > 1. The vector x must have nonnegative elements summing to length(x).

gallery('randcorr',x,k) provides a further option:

k = 0	The diagonal matrix of eigenvalues is initially
	subjected to a random orthogonal similarity
	transformation, and then a sequence of Givens
	rotations is applied (default).

k = 1 The initial transformation is omitted. This is much faster, but the resulting matrix may have some zero entries.

For more information, see:

[1] Bendel, R. B. and M. R. Mickey, "Population Correlation Matrices for Sampling Experiments," *Commun. Statist. Simulation Comput.*, B7, 1978, pp. 163-182.

[2] Davies, P. I. and N. J. Higham, "Numerically Stable Generation of Correlation Matrices and Their Factors," *BIT*, Vol. 40, 2000, pp. 640-651.

randhess - Random, orthogonal upper Hessenberg matrix

H = gallery('randhess',n) returns an n-by-n real, random, orthogonal upper Hessenberg matrix.

H = gallery('randhess', x) if x is an arbitrary, real, length n vector with n > 1, constructs H nonrandomly using the elements of x as parameters.

Matrix H is constructed via a product of n-1 Givens rotations.

randjorth — Random J-orthogonal matrix

A = gallery('randjorth', n), for a positive integer n, produces a random n-by-n J-orthogonal matrix A, where

- J = blkdiag(eye(ceil(n/2)),-eye(floor(n/2)))
- cond(A) = sqrt(1/eps)

J-orthogonality means that $A^*J^*A = J$. Such matrices are sometimes called *hyperbolic*.

A = gallery('randjorth', n, m), for positive integers n and m, produces a random (n+m)-by-(n+m) J-orthogonal matrix A, where

- J = blkdiag(eye(n), -eye(m))
- cond(A) = sqrt(1/eps)

A = gallery('randjorth',n,m,c,symm,method)

uses the following optional input arguments:

- c Specifies cond(A) to be the scalar c.
- symm Enforces symmetry if the scalar symm is nonzero.
- method calls qr to perform the underlying orthogonal transformations if the scalar method is nonzero. A call to qr is much faster than the default method for large dimensions

rando — Random matrix composed of elements -1, 0 or 1

A = gallery('rando',n,k) returns a random n-by-n matrix with elements from one of the following discrete distributions:

```
k = 1   A(i,j) = 0 or 1 with equal probability (default).

k = 2   A(i,j) = -1 or 1 with equal probability.

k = 3   A(i,j) = -1, 0 or 1 with equal probability.
```

Argument n may be a two-element vector, in which case the matrix is n(1)-by-n(2).

randsvd - Random matrix with preassigned singular values

A = gallery('randsvd',n,kappa,mode,kl,ku) returns a banded (multidiagonal) random matrix of order n with cond(A) = kappa and singular values from the distribution mode. If n is a two-element vector, A is n(1)-by-n(2).

Arguments kl and ku specify the number of lower and upper off-diagonals, respectively, in A. If they are omitted, a full matrix is produced. If only kl is present, ku defaults to kl.

Distribution mode can be:

- 1 One large singular value.
- 2 One small singular value.
- 3 Geometrically distributed singular values (default).
- 4 Arithmetically distributed singular values.

- 5 Random singular values with uniformly distributed logarithm.
- If mode is -1, -2, -3, -4, or -5, then randsvd treats mode as abs(mode), except that in the original matrix of singular values the order of the diagonal entries is reversed: small to large instead of large to small.

Condition number kappa defaults to sqrt(1/eps). In the special case where kappa < 0, A is a random, full, symmetric, positive definite matrix with cond(A) = -kappa and eigenvalues distributed according to mode. Arguments kl and ku, if present, are ignored.

A = gallery('randsvd',n,kappa,mode,kl,ku,method) specifies how the computations are carried out. method = 0 is the default, while method = 1 uses an alternative method that is much faster for large dimensions, even though it uses more flops.

redheff - Redheffer's matrix of 1s and 0s

A = gallery('redheff',n) returns an n-by-n matrix of 0's and 1's defined by A(i,j) = 1, if j = 1 or if i divides j, and A(i,j) = 0 otherwise.

The Redheffer matrix has these properties:

- (n-floor(log2(n)))-1 eigenvalues equal to 1
- A real eigenvalue (the spectral radius) approximately sqrt(n)
- A negative eigenvalue approximately -sqrt(n)
- The remaining eigenvalues are provably "small."
- The Riemann hypothesis is true if and only if $\det(A) = O(n^{\frac{1}{2} + \varepsilon})$ for every epsilon > 0.

Barrett and Jarvis conjecture that "the small eigenvalues all lie inside the unit circle abs(Z) = 1," and a proof of this conjecture, together with a proof that some eigenvalue tends to zero as n tends to infinity, would yield a new proof of the prime number theorem.

riemann - Matrix associated with the Riemann hypothesis

A = gallery('riemann',n) returns an n-by-n matrix for which the Riemann hypothesis is true if and only if

$$\det(A) \,=\, O(n!n^{-\textstyle\frac{1}{2}+\varepsilon})$$

for every $\varepsilon > 0$.

The Riemann matrix is defined by:

$$A = B(2:n+1,2:n+1)$$

where B(i,j) = i-1 if i divides j, and B(i,j) = -1 otherwise.

The Riemann matrix has these properties:

- Each eigenvalue e(i) satisfies abs(e(i)) <= m-1/m, where m = n+1.
- i <= e(i) <= i+1 with at most m-sqrt(m) exceptions.
- All integers in the interval (m/3, m/2] are eigenvalues.

ris — Symmetric Hankel matrix

A = gallery('ris',n) returns a symmetric n-by-n Hankel matrix with elements

$$A(i,j) = 0.5/(n-i-j+1.5)$$

The eigenvalues of A cluster around $\pi/2$ and $-\pi/2$. This matrix was invented by F.N. Ris.

sampling — Nonsymmetric matrix with ill-conditioned integer eigenvalues.

A = gallery('sampling',x), where x is an n-vector, is the n-by-n matrix with A(i,j) = X(i)/(X(i)-X(j)) for $i \sim j$ and A(j,j) the sum of the off-diagonal elements in column j. A has eigenvalues 0:n-1. For the eigenvalues 0 and n-1, corresponding eigenvectors are X and ones(n,1), respectively.

The eigenvalues are ill-conditioned. A has the property that A(i,j) + A(j,i) = 1 for $i \sim j$.

Explicit formulas are available for the left eigenvectors of A. For scalar n, sampling(n) is the same as sampling(1:n). A special case of this matrix arises in sampling theory.

smoke — Complex matrix with a 'smoke ring' pseudospectrum

A = gallery('smoke',n) returns an n-by-n matrix with 1's on the superdiagonal, 1 in the (n,1) position, and powers of roots of unity along the diagonal.

A = gallery('smoke',n,1) returns the same except that element A(n,1) is zero.

The eigenvalues of gallery('smoke',n,1) are the nth roots of unity; those of gallery('smoke',n) are the nth roots of unity times $2^{(1/n)}$.

toeppd — Symmetric positive definite Toeplitz matrix

A = gallery('toeppd',n,m,w,theta) returns an n-by-n symmetric, positive semi-definite (SPD) Toeplitz matrix composed of the sum of m rank 2 (or, for certain theta, rank 1) SPD Toeplitz matrices. Specifically,

```
T = w(1)*T(theta(1)) + ... + w(m)*T(theta(m))
```

where T(theta(k)) has (i,j) element $\cos(2*pi*\text{theta}(k)*(i-j))$.

By default: m = n, w = rand(m,1), and theta = rand(m,1).

toeppen - Pentadiagonal Toeplitz matrix (sparse)

P = gallery('toeppen',n,a,b,c,d,e) returns the n-by-n sparse, pentadiagonal Toeplitz matrix with the diagonals: P(3,1) = a, P(2,1) = b, P(1,1) = c, P(1,2) = d, and P(1,3) = e, where a, b, c, d, and e are scalars.

By default, (a,b,c,d,e) = (1,-10,0,10,1), yielding a matrix of Rutishauser. This matrix has eigenvalues lying approximately on the line segment 2*cos(2*t) + 20*i*sin(t).

tridiag — Tridiagonal matrix (sparse)

A = gallery('tridiag',c,d,e) returns the tridiagonal matrix with subdiagonal c, diagonal d, and superdiagonal e. Vectors c and e must have length(d)-1.

A = gallery('tridiag',n,c,d,e), where c, d, and e are all scalars, yields the Toeplitz tridiagonal matrix of order n with subdiagonal elements c, diagonal elements d, and superdiagonal elements e. This matrix has eigenvalues

```
d + 2*sqrt(c*e)*cos(k*pi/(n+1))
where k = 1:n. (see [1].)
A = gallery('tridiag',n) is the same as A =
gallery('tridiag',n,-1,2,-1), which is a symmetric positive
```

definite M-matrix (the negative of the second difference matrix).

triw — Upper triangular matrix discussed by Wilkinson and others

A = gallery('triw',n,alpha,k) returns the upper triangular matrix with ones on the diagonal and alphas on the first $k \ge 0$ superdiagonals.

Order n may be a 2-element vector, in which case the matrix is n(1)-by-n(2) and upper trapezoidal.

Ostrowski ["On the Spectrum of a One-parametric Family of Matrices," J. Reine Angew. Math., 1954] shows that

```
cond(gallery('triw',n,2)) = cot(pi/(4*n))^2,
```

and, for large abs(alpha), cond(gallery('triw',n,alpha)) is approximately abs(alpha)^n*sin(pi/(4*n-2)).

Adding $-2^(2-n)$ to the (n,1) element makes triw(n) singular, as does adding $-2^(1-n)$ to all the elements in the first column.

uniformdata — Array of arbitrary data from standard uniform distribution

A = gallery('uniformdata',[m,n,...],j) returns an m-by-n-by-... array A. The values of A are a random sample from the standard uniform distribution. j must be an integer value in the interval [0, 2^32-1]. Calling gallery('uniformdata', ...) with different values of j will return different arrays. Repeated calls to gallery('uniformdata',...) with the same size vector and j inputs will always return the same array.

In any call to gallery ('uniformdata', ...) you can substitute individual inputs m,n,... for the size vector input [m,n,...]. For example, gallery ('uniformdata',[1,2,3,4],5) is equivalent to gallery ('uniformdata',1,2,3,4,5).

[A,B,...] = gallery('uniformdata',[m,n,...],j) returns multiple m-by-n-by-... arrays A, B, ..., containing different values.

A = gallery('uniformdata',[m,n,...],j, classname) produces a matrix of class classname. classname must be either 'single' or 'double'.

Generate the arbitrary 6-by-4 matrix of data from the uniform distribution on [0, 1] corresponding to j = 2.

```
x = gallery('uniformdata', [6, 4], 2);
```

Generate the arbitrary 1-by-2-by-3 single array of data from the uniform distribution on [0, 1] corresponding to j = 17.

```
y = gallery('uniformdata', 1, 2, 3, 17, 'single');
```

wathen — Finite element matrix (sparse, random entries)

A = gallery('wathen',nx,ny) returns a sparse, random, n-by-n finite element matrix where n = 3*nx*ny + 2*nx + 2*ny + 1.

Matrix A is precisely the "consistent mass matrix" for a regular nx-by-ny grid of 8-node (serendipity) elements in two dimensions. A is symmetric, positive definite for any (positive) values of the "density," rho(nx,ny), which is chosen randomly in this routine.

gallery

A = gallery('wathen',nx,ny,1) returns a diagonally scaled matrix such that

$$0.25 \le eig(inv(D)*A) \le 4.5$$

where D = diag(diag(A)) for any positive integers nx and ny and any densities rho(nx,ny).

wilk - Various matrices devised or discussed by Wilkinson

gallery('wilk',n) returns a different matrix or linear system depending on the value of n.

n = 3	Upper triangular system Ux=b illustrating inaccurate solution.
n = 4	Lower triangular system Lx=b, ill-conditioned.
n = 5	hilb(6)(1:5,2:6)*1.8144. A symmetric positive definite matrix.
n = 21	W21+, a tridiagonal matrix. eigenvalue problem. For more detail, see [2].

See Also

hadamard, hilb, invhilb, magic, wilkinson

References

[1] The MATLAB gallery of test matrices is based upon the work of Nicholas J. Higham at the Department of Mathematics, University of Manchester, Manchester, England. Further background can be found in the books *MATLAB Guide, Second Edition*, Desmond J. Higham and Nicholas J. Higham, SIAM, 2005, and *Accuracy and Stability of Numerical Algorithms*, Nicholas J. Higham, SIAM, 1996.

[2] Wilkinson, J. H., *The Algebraic Eigenvalue Problem*, Oxford University Press, London, 1965, p.308.

gamma, gammainc, gammaln

Purpose

Gamma functions

Syntax

Y = gamma(A)

Y = gammainc(X,A)

Y = gammainc(X,A,tail)

Y = gammaln(A)

Definition

The gamma function is defined by the integral:

$$\Gamma(a) = \int_0^\infty e^{-t} t^{a-1} dt$$

The gamma function interpolates the factorial function. For integer n:

$$gamma(n+1) = n! = prod(1:n)$$

The incomplete gamma function is:

$$P(x,a) = \frac{1}{\Gamma(a)} \int_0^x e^{-t} t^{a-1} dt$$

For any $a \ge 0$, gammainc(x,a) approaches 1 as x approaches infinity. For small x and a, gammainc(x,a) is approximately equal to x^a , so gammainc(0,0) = 1.

Description

Y = gamma(A) returns the gamma function at the elements of A. A must be real.

Y = gammainc(X,A) returns the incomplete gamma function of corresponding elements of X and A. Arguments X and A must be real and the same size (or either can be scalar).

Y = gammainc(X,A,tail) specifies the tail of the incomplete gamma function when X is non-negative. The choices are for tail are 'lower' (the default) and 'upper'. The upper incomplete gamma function is defined as

1 - gammainc(x,a)

gamma, gammainc, gammaln

Note When X is negative, Y can be inaccurate for abs(X)>A+1.

Y = gammaln(A) returns the logarithm of the gamma function, gammaln(A) = log(gamma(A)). The gammaln command avoids the underflow and overflow that may occur if it is computed directly using log(gamma(A)).

Algorithm

The computations of gamma and gammaln are based on algorithms outlined in [1]. Several different minimax rational approximations are used depending upon the value of A. Computation of the incomplete gamma function is based on the algorithm in [2].

References

[1] Cody, J., An Overview of Software Development for Special Functions, Lecture Notes in Mathematics, 506, Numerical Analysis Dundee, G. A. Watson (ed.), Springer Verlag, Berlin, 1976.

[2] Abramowitz, M. and I.A. Stegun, *Handbook of Mathematical Functions*, National Bureau of Standards, Applied Math. Series #55, Dover Publications, 1965, sec. 6.5.

Purpose

Inverse incomplete gamma function

Syntax

x = gammaincinv(y,a)
v = gammaincinv(x.a.tail)

Description

x = gammaincinv(y,a) evaluates the inverse incomplete gamma function for corresponding elements of y and a, such that y = gammainc(x,a). The elements of y must be in the closed interval [0,1], and those of a must be nonnegative. y and a must be real and the same size (or either can be a scalar).

y = gammaincinv(x,a,tail) specifies the tail of the incomplete gamma function. Choices are lower (the default) to use the integral from 0 to x, or upper to use the integral from x to infinity. These two choices are related as gammaincinv(y,a,'upper') = gammaincinv(1-y,a,'lower'). When y is close to 0, the upper option provides a way to compute x more accurately than by subtracting y from 1.

Definition

The lower incomplete gamma function is defined as:

$$\operatorname{gammainc}(x,a) = \frac{1}{\Gamma(a)} \int_{0}^{x} t^{(a-1)} e^{-t} dt$$

The upper incomplete gamma function is defined as:

$$\operatorname{gammainc}(x,a) = \frac{1}{\Gamma(a)} \int_{x}^{\infty} t^{(a-1)} e^{-t} dt$$

gammaincinv computes the inverse of the incomplete gamma function with respect to the integration limit x using Newton's method.

For any a>0, as y approaches 1, gammaincinv(y,a) approaches infinity. For small x and a, gammainc(x,a) $\cong x^a$, so gammaincinv(1,0) = 0.

See Also

gamma, gammainc, gammaln, psi

Purpose Current axes handle

Syntax h = gca

Description

h = gca returns the handle to the current axes for the current figure. If no axes exists, the MATLAB software creates one and returns its handle. You can use the statement

get(gcf, 'CurrentAxes')

if you do not want MATLAB to create an axes if one does not already exist.

Current Axes

The current axes is the target for graphics output when you create axes children. The current axes is typically the last axes used for plotting or the last axes clicked on by the mouse. Graphics commands such as plot, text, and surf draw their results in the current axes. Changing the current figure also changes the current axes.

See Also

axes, cla, gcf, findobj

figure CurrentAxes property

"Graphics Object Identification" on page 1-103 for related functions

Purpose Handle of figure containing object whose callback is executing

Syntax fig = gcbf

Description fig = gcbf returns the handle of the figure that contains the object

whose callback is currently executing. This object can be the figure

itself, in which case, gcbf returns the figure's handle.

When no callback is executing, gcbf returns the empty matrix, [].

The value returned by gcbf is identical to the figure output argument

returned by gcbo.

See Also gcbo, gco, gcf, gca

gcbo

Purpose

Handle of object whose callback is executing

Syntax

h = gcbo

[h,figure] = gcbo

Description

h = gcbo returns the handle of the graphics object whose callback is executing.

[h,figure] = gcbo returns the handle of the current callback object and the handle of the figure containing this object.

Remarks

The MATLAB software stores the handle of the object whose callback is executing in the root CallbackObject property. If a callback interrupts another callback, MATLAB replaces the CallbackObject value with the handle of the object whose callback is interrupting. When that callback completes, MATLAB restores the handle of the object whose callback was interrupted.

The root CallbackObject property is read only, so its value is always valid at any time during callback execution. The root CurrentFigure property, and the figure CurrentAxes and CurrentObject properties (returned by gcf, gca, and gco, respectively) are user settable, so they can change during the execution of a callback, especially if that callback is interrupted by another callback. Therefore, those functions are not reliable indicators of which object's callback is executing.

When you write callback routines for the CreateFcn and DeleteFcn of any object and the figure ResizeFcn, you must use gcbo since those callbacks do not update the root's CurrentFigure property, or the figure's CurrentObject or CurrentAxes properties; they only update the root's CallbackObject property.

When no callbacks are executing, gcbo returns [] (an empty matrix).

See Also

gca, gcf, gco, rootobject

"Graphics Object Identification" on page 1-103 for related functions.

Purpose

Greatest common divisor

Syntax

$$G = gcd(A,B)$$

 $[G,C,D] = gcd(A,B)$

Description

G = gcd(A,B) returns an array containing the greatest common divisors of the corresponding elements of integer arrays A and B. By convention, gcd(0,0) returns a value of 0; all other inputs return positive integers for G.

 $[G,C,D] = \gcd(A,B)$ returns both the greatest common divisor array G, and the arrays C and D, which satisfy the equation: A(i).*C(i) + B(i).*D(i) = G(i). These are useful for solving Diophantine equations and computing elementary Hermite transformations.

Examples

The first example involves elementary Hermite transformations.

For any two integers a and b there is a 2-by-2 matrix E with integer entries and determinant = 1 (a *unimodular* matrix) such that:

$$E * [a;b] = [g,0],$$

where g is the greatest common divisor of a and b as returned by the command [g,c,d] = gcd(a,b).

The matrix E equals:

In the case where a = 2 and b = 4:

So that

In the next example, we solve for x and y in the Diophantine equation 30x + 56y = 8.

By the definition, for scalars c and d:

$$30(-13) + 56(7) = 2$$
,

Multiplying through by 8/2:

$$30(-13*4) + 56(7*4) = 8$$

Comparing this to the original equation, a solution can be read by inspection:

$$x = (-13*4) = -52; y = (7*4) = 28$$

See Also

1cm

References

[1] Knuth, Donald, The Art of Computer Programming, Vol. 2, Addison-Wesley: Reading MA, 1973. Section 4.5.2, Algorithm X.

Purpose Current figure handle

Syntax h = gcf

Description h = gcf returns the handle of the current figure. The current figure is

the figure window in which graphics commands such as plot, title, and surf draw their results. If no figure exists, the MATLAB software

creates one and returns its handle. You can use the statement

get(0, 'CurrentFigure')

if you do not want MATLAB to create a figure if one does not already

exist.

See Also clf, figure, gca

Root CurrentFigure property

"Graphics Object Identification" on page 1-103 for related functions

Purpose

Handle of current object

Syntax

h = gco

h = gco(figure handle)

Description

h = gco returns the handle of the current object.

h = gco(figure_handle) returns the value of the current object for the figure specified by figure handle.

Remarks

The current object is the last object clicked on, excluding uimenus. If the mouse click did not occur over a figure child object, the figure becomes the current object. The MATLAB software stores the handle of the current object in the figure's CurrentObject property.

The CurrentObject of the CurrentFigure does not always indicate the object whose callback is being executed. Interruptions of callbacks by other callbacks can change the CurrentObject or even the CurrentFigure. Some callbacks, such as CreateFcn and DeleteFcn, and uimenu Callback, intentionally do not update CurrentFigure or CurrentObject.

gcbo provides the only completely reliable way to retrieve the handle to the object whose callback is executing, at any point in the callback function, regardless of the type of callback or of any previous interruptions.

Examples

This statement returns the handle to the current object in figure window 2:

h = gco(2)

See Also

gca, gcbo, gcf

The root object description

"Graphics Object Identification" on page 1-103 for related functions

Purpose

Test for greater than or equal to

Syntax

A >= B ge(A, B)

Description

A >= B compares each element of array A with the corresponding element of array B, and returns an array with elements set to logical 1 (true) where A is greater than or equal to B, or set to logical 0 (false) where A is less than B. Each input of the expression can be an array or a scalar value.

If both A and B are scalar (i.e., 1-by-1 matrices), then the MATLAB software returns a scalar value.

If both A and B are nonscalar arrays, then these arrays must have the same dimensions, and MATLAB returns an array of the same dimensions as A and B.

If one input is scalar and the other a nonscalar array, then the scalar input is treated as if it were an array having the same dimensions as the nonscalar input array. In other words, if input A is the number 100, and B is a 3-by-5 matrix, then A is treated as if it were a 3-by-5 matrix of elements, each set to 100. MATLAB returns an array of the same dimensions as the nonscalar input array.

ge(A, B) is called for the syntax $A \ge B$ when either A or B is an object.

Examples

Create two 6-by-6 matrices, A and B, and locate those elements of A that are greater than or equal to the corresponding elements of B:

```
A = magic(6);
B = repmat(3*magic(3), 2, 2);
A >= B
ans =
     1
            0
                                        1
     0
            1
                   0
                          1
                                 1
                                        1
     1
            0
                   0
     0
            1
                   1
                          0
                                 1
                                        0
```

1 0 1 1 0 0 0 1 1 1 0 1

See Also

gt, eq, le, lt, ne, "Relational Operators"

Purpose Generate path string

Syntax

genpath

genpath folderName

p = genpath('folderName')

Description

genpath returns a path string that includes all the folders and subfolders below matlabroot/toolbox, including empty subfolders.

genpath folderName returns a path string that includes folderName and multiple levels of subfolders below folderName. The path string does not include folders named private or folders that begin with the @ character (class folders) or the + character (package folders).

p = genpath('folderName') returns the path string to variable, p.

Examples

Generate a path that includes matlabroot/toolbox/images and all folders below it:

```
p = genpath(fullfile(matlabroot, 'toolbox', 'images'))
```

p =

C:\Program Files\MATLAB\R20nn\toolbox\images;C:\Program Files\MATLAB
R20nn\toolbox\images\images;C:\Program Files\MATLAB\R200nn\toolbox\images\images\ja;C:\Program Files\MATLAB\R200nn\toolbox\images\imdemos;C:\Program Files\MATLAB\R200nn\toolbox\images\ja;

R200nn represents the folder for the MATLAB release, for example, R2009b.

Use genpath in conjunction with addpath to add a folder and its subfolders to the search path. Add myfiles and its subfolders to the search path:

```
addpath(genpath('c:/matlab/myfiles'))
```

See Also

addpath, path, pathsep, pathtool, rehash, restoredefaultpath, rmpath, savepath

genpath

"Using the MATLAB Search Path"

Construct valid variable name from string

Syntax

varname = genvarname(str)

varname = genvarname(str, exclusions)

Description

varname = genvarname(str) constructs a string varname that is similar to or the same as the str input, and can be used as a valid variable name. str can be a single character array or a cell array of strings. If str is a cell array of strings, genvarname returns a cell array of strings in varname. The strings in a cell array returned by genvarname are guaranteed to be different from each other.

varname = genvarname(str, exclusions) returns a valid variable name that is different from any name listed in the exclusions input. The exclusions input can be a single character array or a cell array of strings. Specify the function who in the exclusions character array to create a variable name that will be unique in the current MATLAB workspace (see "Example 4" on page 2-1687, below).

Note genvarname returns a string that can be used as a variable name. It does not create a variable in the MATLAB workspace. You cannot, therefore, assign a value to the output of genvarname.

Remarks

A valid MATLAB variable name is a character string of letters, digits, and underscores, such that the first character is a letter, and the length of the string is less than or equal to the value returned by the namelengthmax function. Any string that exceeds namelengthmax is truncated in the varname output. See "Example 6" on page 2-1688, below.

The variable name returned by genvarname is not guaranteed to be different from other variable names currently in the MATLAB workspace unless you use the exclusions input in the manner shown in "Example 4" on page 2-1687, below.

If you use genvarname to generate a field name for a structure, MATLAB does create a variable for the structure and field in the MATLAB workspace. See "Example 3" on page 2-1686, below.

If the str input contains any whitespace characters, genvarname removes then and capitalizes the next alphabetic character in str. If str contains any nonalphanumeric characters, genvarname translates these characters into their hexadecimal value.

Examples Example 1

Create four similar variable name strings that do not conflict with each other:

```
v = genvarname({'A', 'A', 'A', 'A'})
v =
    'A' 'A1' 'A2' 'A3'
```

Example 2

Read a column header hdr from worksheet trial2 in Excel spreadsheet myproj_apr23:

```
[data hdr] = xlsread('myproj_apr23.xls', 'trial2');
```

Make a variable name from the text of the column header that will not conflict with other names:

```
v = genvarname(['Column ' hdr{1,3}]);
```

Assign data taken from the spreadsheet to the variable in the MATLAB workspace:

```
eval([v '= data(1:7, 3);']);
```

Example 3

Collect readings from an instrument once every minute over the period of an hour into different fields of a structure. genvarname not only generates unique fieldname strings, but also creates the structure and fields in the MATLAB workspace:

```
for k = 1:60 record.(genvarname(['reading' datestr(clock, 'HHMMSS')])) = takeReading; pause(60) end
```

After the program ends, display the recorded data from the workspace:

```
record
record =
    reading090446: 27.3960
    reading090546: 23.4890
    reading090646: 21.1140
    reading090746: 23.0730
    reading090846: 28.5650
    .
.
```

Example 4

Generate variable names that are unique in the MATLAB workspace by putting the output from the who function in the exclusions list.

```
for k = 1:5
    t = clock;
    pause(uint8(rand * 10));
    v = genvarname('time_elapsed', who);
    eval([v ' = etime(clock,t)'])
    end
```

As this code runs, you can see that the variables created by genvarname are unique in the workspace:

```
time_elapsed =
    5.0070
time_elapsed1 =
    2.0030
time_elapsed2 =
    7.0010
```

```
time_elapsed3 = 8.0010
time_elapsed4 = 3.0040
```

After the program completes, use the who function to view the workspace variables:

Example 5

If you try to make a variable name from a MATLAB keyword, genvarname creates a variable name string that capitalizes the keyword and precedes it with the letter x:

```
v = genvarname('global')
v =
    xGlobal
```

Example 6

If you enter a string that is longer than the value returned by the namelengthmax function, genvarname truncates the resulting variable name string:

```
namelengthmax
ans =
    63

vstr = genvarname(sprintf('%s%s', ...
    'This name truncates because it contains ', ...
    'more than the maximum number of characters'))
vstr =
ThisNameTruncatesBecauseItContainsMoreThanTheMaximumNumberOfCha
```

See Also

isvarname, iskeyword, isletter, namelengthmax, who, regexp

Query Handle Graphics object properties

Syntax

```
get(h)
get(h, 'PropertyName')
<m-by-n value cell array> = get(H,pn)
a = get(h)
a = get(0)
a = get(0, 'Factory')
a = get(0, 'FactoryObjectTypePropertyName')
a = get(h, 'Default')
a = get(h, 'DefaultObjectTypePropertyName')
```

Description

Note Do not use the get function on Java objects as it will cause a memory leak. For more information, see "Accessing Private and Public Data"

get(h) returns all properties of the graphics object identified by the handle h and their current values. For this syntax, h must be a scalar.

get(h, 'PropertyName') returns the value of the property
'PropertyName' of the graphics object identified by h.

<m-by-n value cell array> = get(H,pn) returns n property values
for m graphics objects in the m-by-n cell array, where m = length(H)
and n is equal to the number of property names contained in pn.

a = get(h) returns a structure whose field names are the object's property names and whose values are the current values of the corresponding properties. If you do not specify an output argument, MATLAB displays the information on the screen. For this syntax, h may be a scalar or a m-by-n array of handles. If h is a vector, a will be a (m*n)-by-1 struct array.

a = get(0) returns the current values of all user-settable properties.
 a is a structure array whose field names are the object property names and whose field values are the values of the corresponding properties.

If you do not specify an output argument, MATLAB displays the information on the screen.

- a = get(0, 'Factory') returns the factory-defined values of all user-settable properties. a is a structure array whose field names are the object property names and whose field values are the values of the corresponding properties. If you do not specify an output argument, MATLAB displays the information on the screen.
- a = get(0, 'FactoryObjectTypePropertyName') returns the factory-defined value of the named property for the specified object type. The argument FactoryObjectTypePropertyName is the word Factory concatenated with the object type (e.g., Figure) and the property name (e.g., Color)FactoryFigureColor.
- a = get(h, 'Default') returns all default values currently defined on object h. a is a structure array whose field names are the object property names and whose field values are the values of the corresponding properties. If you do not specify an output argument, MATLAB displays the information on the screen.
- a = get(h, 'DefaultObjectTypePropertyName') returns the factory-defined value of the named property for the specified object type. The argument DefaultObjectTypePropertyName is the word Default concatenated with the object type (e.g., Figure) and the property name (e.g., Color).

DefaultFigureColor

Examples

You can obtain the default value of the LineWidth property for line graphics objects defined on the root level with the statement

```
get(0, 'DefaultLineLineWidth')
ans =
  0.5000
```

To query a set of properties on all axes children, define a cell array of property names:

```
props = {'HandleVisibility', 'Interruptible';
```

```
'SelectionHighlight', 'Type'};
output = get(get(gca,'Children'),props);
```

The variable output is a cell array of dimension length(get(gca, 'Children')-by-4.

For example, type

```
patch; surface; text; line
output = get(get(gca, 'Children'),props)
output =
 'on'
          'on'
                   'on'
                           'line'
 'on'
          'off'
                   'on'
                           'text'
                  'on'
 'on'
          'on'
                           'surface'
 'on'
          'on'
                   'on'
                           'patch'
```

See Also

findobj, gca, gcf, gco, set

Handle Graphics Properties

"Graphics Object Identification" on page 1-103 for related functions

Query property values for audioplayer object

Syntax

```
Value = get(obj, 'PropertyName')
Values = get(obj, {'PropertyName1', ..., 'PropertyNameN'})
Values = get(obj)
get(obj)
```

Description

Value = get(obj, 'PropertyName') returns the value of the specified
property for object obj.

Values = get(obj, {'PropertyName1', ..., 'PropertyNameN'})
returns the values of the specified properties in a 1-by-N cell array.

Values = get(obj) returns a scalar structure that contains the values of all properties of obj. Each field name corresponds to a property name.

get(obj) displays all property names and their current values.

Example

Create an audioplayer object from the demo file handel.mat and query the object properties:

```
load handel.mat;
handelObj = audioplayer(y, Fs);
% Display all properties.
get(handelObj)
% Display only the SampleRate property.
get(handelObj, 'SampleRate')
% Create a cell array that contains
% values for two properties.
info = get(handelObj, {'BitsPerSample', 'NumberOfChannels'});
```

Alternatives

To access a single property, you can use dot notation. Reference each property as though it is a field of a structure array. For example, find the value of the TotalSamples property for an object named handelObj (as created in the Example):

audioplayer.get

```
numSamples = handelObj.TotalSamples;
This command is exactly equivalent to:
    numSamples = get(handelObj, 'TotalSamples');
See Also
audioplayer | set
```

Query property values for audiorecorder object

Syntax

```
Value = get(obj, 'PropertyName')
Values = get(obj, {'PropertyName1', ..., 'PropertyNameN'})
Values = get(obj)
get(obj)
```

Description

Value = get(obj, 'PropertyName') returns the value of the specified
property for object obj.

Values = get(obj, {'PropertyName1', ..., 'PropertyNameN'})
returns the values of the specified properties in a 1-by-N cell array.

Values = get(obj) returns a scalar structure that contains the values of all properties of obj. Each field name corresponds to a property name.

get(obj) displays all property names and their current values.

Example

Create an audiorecorder object and query the object properties:

```
recorderObj = audiorecorder;
% Display all properties.
get(recorderObj)
% Display only the SampleRate property.
get(recorderObj, 'SampleRate')
% Create a cell array that contains
% values for two properties.
info = get(recorderObj, {'BitsPerSample', 'NumberOfChannels'});
```

Alternatives

To access a single property, you can use dot notation. Reference each property as though it is a field of a structure array. For example, find the value of the TotalSamples property for an object named recorderObj (as created in the Example):

```
numSamples = recorderObj.TotalSamples;
```

audiorecorder.get

```
This command is exactly equivalent to:

numSamples = get(recorderObj, 'TotalSamples');

See Also

audiorecorder | set
```

Get property value from interface, or display properties

Syntax

```
V = h.get
V = h.get('propertyname')
V = get(h. ...)
```

Description

V = h.get returns a list of all properties and their values for the object or interface, h.

If V is empty, either there are no properties in the object, or the MATLAB software cannot read the object's type library. Refer to the COM vendor's documentation. For Automation objects, if the vendor provides documentation for a specific property, use the V = get(h, ...) syntax to call it.

V = h.get('propertyname') returns the value of the property specified in the string, propertyname.

V = get(h, ...) is an alternate syntax for the same operation.

Remarks

The meaning and type of the return value is dependent upon the specific property being retrieved. The object's documentation should describe the specific meaning of the return value. MATLAB may convert the data type of the return value. For a description of how MATLAB converts COM data types, see "Handling COM Data in MATLAB Software" in the External Interfaces documentation.

COM functions are available on Microsoft Windows systems only.

Examples

Create a COM server running Microsoft Excel software:

```
e = actxserver ('Excel.Application');
```

Retrieve a single property value:

```
e.Path
```

Depending on your spreadsheet program, MATLAB software displays:

```
ans =
     C:\Program Files\MSOffice\OFFICE11
Retrieve a list of all properties for the CommandBars interface:
  c = e.CommandBars.get
MATLAB displays information similar to the following:
  C =
                       Application: [1x1
  Interface.Microsoft_Excel_11.0_Object_Library._Application]
                           Creator: 1.4808e+009
                     ActionControl: []
                     ActiveMenuBar: [1x1
  Interface.Microsoft_Office_12.0_Object_Library.CommandBar]
                             Count: 129
                   DisplayTooltips: 1
            DisplayKeysInTooltips: 0
                      LargeButtons: 0
                MenuAnimationStyle: 'msoMenuAnimationNone'
                            Parent: [1x1
  Interface.Microsoft Excel 11.0 Object Library. Application]
                     AdaptiveMenus: 0
                      DisplayFonts: 1
                  DisableCustomize: 0
      DisableAskAQuestionDropdown: 0
```

See Also

set (COM), inspect, isprop, addproperty, deleteproperty

get (hgsetget)

Purpose

Query property values of handle objects derived from hgsetget class

Syntax

```
CV = get(H,'PropertyName')
SV = get(h)
get(h)
```

Description

CV = get(H, 'PropertyName') returns the value of the named property from the objects in the handle array H. If H is scalar, get returns a single value; if H is an array, get returns a cell array of property values. If you specify a cell array of property names, then get returns a cell array of values, where each row in the cell corresponds to an element in H and each column in the cell corresponds to an element in the property name cell array.

If H is nonscalar and PropertyName is the name of a dynamic property, get returns a value only if the property exists in all objects referenced in H.

SV = get(h) returns a struct array in which the field names are the object's property names and the values are the current values of the corresponding properties. If h is an array, then SV is a numel(h)-by-1 array of structs.

get(h) displays all property names and their current values for the MATLAB objects with handle h.

Your subclass can override the hgsetget getdisp method to control how MATLAB displays this information.

See Also

See "Implementing a Set/Get Interface for Properties"

get, handle, hgsetget, set (hgsetget)

Memmapfile object properties

Syntax

```
s = get(obj)
val = get(obj, prop)
```

Description

s = get(obj) returns the values of all properties of the memmapfile object obj in structure array s. Each property retrieved from the object is represented by a field in the output structure. The name and contents of each field are the same as the name and value of the property it represents.

Note Although property names of a memmapfile object are not case sensitive, field names of the output structure returned by get (named the same as the properties they represent) are case sensitive.

val = get(obj, prop) returns the value(s) of one or more properties specified by prop. The prop input can be a quoted string or a cell array of quoted strings, each containing a property name. If the latter is true, get returns the property values in a cell array.

Examples

You can use the get method of the memmapfile class to return information on any or all of the object's properties. Specify one or more property names to get the values of specific properties.

This example returns the values of the Offset, Repeat, and Format properties for a memmapfile object. Start by constructing the object:

Use the get method to return the specified property values in a 1-by-3 cell array m_props:

```
m props = get(m, {'Offset', 'Repeat', 'Format'})
m props =
    [2048]
              [Inf]
                       {3x3 cell}
m props{3}
ans =
    'int16'
                [1x2 double]
                                'model'
    'uint32'
               [1x2 double]
                                'serialno'
               [1x2 double]
    'single'
                                'expenses'
```

Another way to return the same information is to use the objname.property syntax:

```
m_props = {m.Offset, m.Repeat, m.Format}
m_props =
    [2048] [Inf] {3x3 cell}
```

To return the values for all properties with get, pass just the object name:

```
s = get(m)
   Filename: 'd:\matlab\mfiles\records.dat'
   Writable: 0
    Offset: 2048
   Format: {3x3 cell}
   Repeat: Inf
    Data: [753 1]
```

To see just the ${\tt Format}$ field of the returned structure, type

```
s.Format
ans =
    'int16'    [1x2 double]    'model'
    'uint32'    [1x2 double]    'serialno'
    'single'    [1x2 double]    'expenses'
```

get (memmapfile)

See Also memmapfile, disp(memmapfile)

Query property values for multimedia reader object

Syntax

```
Value = get(obj, 'PropertyName')
Values = get(obj, {'PropertyName1', ..., 'PropertyNameN'})
Values = get(obj)
get(obj)
```

Description

Value = get(obj, 'PropertyName') returns the value of the specified
property for object obj.

```
Values = get(obj, {'PropertyName1', ..., 'PropertyNameN'})
returns the values of the specified properties in a 1-by-N cell array.
```

Values = get(obj) returns a scalar structure that contains the values of all properties of obj. Each field name corresponds to a property name.

get(obj) displays all property names and their current values.

Examples

Display all properties of a reader object associated with the demo file xylophone.mpg:

```
xyloObj = mmreader('xylophone.mpg');
get(xyloObj)
```

Create a 1-by-3 cell array that contains the values of the Height, Width, and NumberOfFrames properties of a reader object associated with xylophone.mpg:

```
xyloObj = mmreader('xylophone.mpg');
xyloSize = get(xyloObj, {'Height', 'Width', 'NumberOfFrames'})
```

Alternatives

To access a single property, you can use dot notation. Reference each property as though it is a field of a structure array. For example, find the value of the NumberOfFrames property for a reader object called xyloObj (as created in the Examples):

```
numFrames = xyloObj.NumberOfFrames;
```

mmreader.get

```
This command is exactly equivalent to:

numFrames = get(xyloObj, 'NumberOfFrames');
```

See Also mmreader | set

get (RandStream)

Purpose Random stream properties

Class @RandStream

Syntax get(s)

P = get(s)

P = get(s, 'PropertyName')

Description get(s) prints the list of properties for the random stream s.

P = get(s) returns all properties of s in a scalar structure.

P = get(s, 'PropertyName') returns the property 'PropertyName'.

See Also @RandStream, set (RandStream)

Serial port object properties

Syntax

```
get(obj)
out = get(obj)
out = get(obj,'PropertyName')
```

Description

get(obj) returns all property names and their current values to the command line for the serial port object, obj.

out = get(obj) returns the structure out where each field name is the name of a property of obj, and each field contains the value of that property.

out = get(obj, 'PropertyName') returns the value out of the property specified by PropertyName for obj. If PropertyName is replaced by a 1-by-n or n-by-1 cell array of strings containing property names, then get returns a 1-by-n cell array of values to out. If obj is an array of serial port objects, then out will be a m-by-n cell array of property values where m is equal to the length of obj and n is equal to the number of properties specified.

Remarks

Refer to Displaying Property Names and Property Values for a list of serial port object properties that you can return with get.

When you specify a property name, you can do so without regard to case, and you can make use of property name completion. For example, if s is a serial port object, then these commands are all valid.

```
out = get(s, 'BaudRate');
out = get(s, 'baudrate');
out = get(s, 'BAUD');
```

If you use the help command to display help for get, then you need to supply the pathname shown below.

```
help serial/get
```

Example

This example illustrates some of the ways you can use get to return property values for the serial port object s on a Windows platform.

```
s = serial('COM1');
out1 = get(s);
out2 = get(s,{'BaudRate','DataBits'});
get(s,'Parity')
ans =
none
```

See Also Functions

set

Purpose Timer object properties

Syntax get(obj)

```
V = get(obj)
V = get(obj, 'PropertyName')
```

Description

get(obj) displays all property names and their current values for the timer object obj. obj must be a single timer object.

V = get(obj) returns a structure, V, where each field name is the name of a property of obj and each field contains the value of that property. If obj is an M-by-1 vector of timer objects, V is an M-by-1 array of structures.

V = get(obj, 'PropertyName') returns the value, V, of the timer object property specified in PropertyName.

If *PropertyName* is a 1-by-N or N-by-1 cell array of strings containing property names, V is a 1-by-N cell array of values. If obj is a vector of timer objects, V is an M-by-N cell array of property values where M is equal to the length of obj and N is equal to the number of properties specified.

Examples

```
t = timer;
get(t)
    AveragePeriod: NaN
        BusyMode: 'drop'
        ErrorFcn: ''
    ExecutionMode: 'singleShot'
    InstantPeriod: NaN
        Name: 'timer-1'
    ObjectVisibility: 'on'
        Period: 1
        Running: 'off'
    StartDelay: 1
        StartFcn: ''
        StopFcn: ''
        Tag: ''
```

get (timer)

See Also

```
TasksExecuted: 0
TasksToExecute: Inf
TimerFcn: ''
Type: 'timer'
UserData: []
get(t, {'StartDelay','Period'})
ans =

[0] [1]

timer, set(timer)
```

Purpose Query timeseries object property values

Syntax value = get(ts, 'PropertyName')

get(ts)

Description value = get(ts, 'PropertyName') returns the value of the specified

property of the timeseries object. The following syntax is equivalent:

value = ts.PropertyName

get(ts) displays all properties and values of the time series ts.

See Also set (timeseries), timeseries, tsprops

get (tscollection)

Purpose Query tscollection object property values

Syntax value = get(tsc, 'PropertyName')

Description value = get(tsc, 'PropertyName') returns the value of the specified

property of the tscollection object tsc. The following syntax is

equivalent:

value = tsc.PropertyName

get(tsc) displays all properties and values of the tscollection object

tsc.

See Also set (tscollection), tscollection

Extract date-string time vector into cell array

Syntax

getabstime(ts)

Description

getabstime(ts) extracts the time vector from the timeseries object ts as a cell array of date strings. To define the time vector relative to a calendar date, set the TimeInfo.StartDate property of the timeseries object. When the TimeInfo.StartDate format is a valid datestr format, the output strings from getabstime have the same format.

Examples

The following example shows how to extract a time vector as a cell array of date strings from a timeseries object.

1 Create a timeseries object.

```
ts = timeseries([3 6 8 0 10]);
```

The default time vector for ts is [0 1 2 3 4], which starts at 0 and increases in 1-second increments. The length of the time vector is equal to the length of the data.

2 Set the StartDate property.

```
ts.TimeInfo.StartDate = '10/27/2005 07:05:36';
```

3 Extract the time vector.

```
getabstime(ts)
ans =

'27-0ct-2005 07:05:36'
'27-0ct-2005 07:05:37'
'27-0ct-2005 07:05:38'
'27-0ct-2005 07:05:39'
'27-0ct-2005 07:05:40'
```

getabstime (timeseries)

4 Change the date-string format of the time vector.

```
ts.TimeInfo.Format = 'mm/dd/yy'
```

5 Extract the time vector with the new date-string format.

```
getabstime(ts)
ans =
    '10/27/05'
    '10/27/05'
    '10/27/05'
    '10/27/05'
```

See Also

setabstime (timeseries), timeseries, tsprops

getabstime (tscollection)

Purpose

Extract date-string time vector into cell array

Syntax

getabstime(tsc)

Description

getabstime(tsc) extracts the time vector from the tscollection object tsc as a cell array of date strings. To define the time vector relative to a calendar date, set the TimeInfo.StartDate property of the time-series collection. When the TimeInfo.StartDate format is a valid datestr format, the output strings from getabstime have the same format.

Examples

1 Create a tscollection object.

```
tsc = tscollection(timeseries([3 6 8 0 10]));
```

2 Set the StartDate property.

```
tsc.TimeInfo.StartDate = '10/27/2005 07:05:36';
```

3 Extract a vector of absolute time values.

```
getabstime(tsc)
ans =

'27-0ct-2005 07:05:36'
'27-0ct-2005 07:05:37'
'27-0ct-2005 07:05:38'
'27-0ct-2005 07:05:39'
'27-0ct-2005 07:05:40'
```

4 Change the date-string format of the time vector.

```
tsc.TimeInfo.Format = 'mm/dd/yy';
```

5 Extract the time vector with the new date-string format.

```
getabstime(tsc)
```

getabstime (tscollection)

```
ans =

'10/27/05'
'10/27/05'
'10/27/05'
'10/27/05'
'10/27/05'

See Also

datestr, setabstime (tscollection), tscollection
```

Purpose Value of application-defined data

Syntax value = getappdata(h,name)

values = getappdata(h)

Description value = getappdata(h, name) gets the value of the application-defined

data with the name specified by name, in the object with handle h. If the application-defined data does not exist, the MATLAB software returns

an empty matrix in value.

values = getappdata(h) returns all application-defined data for the

object with handle h.

Remarks Application data is data that is meaningful to or defined by your

application which you attach to a figure or any GUI component (other than ActiveX controls) through its AppData property. Only Handle

Graphics MATLAB objects use this property.

See Also setappdata, rmappdata, isappdata

audiorecorder.getaudiodata

Purpose

Store recorded audio signal in numeric array

Syntax

```
y = getaudiodata(recorder)
```

y = getaudiodata(recorder, dataType)

Description

y = getaudiodata(recorder) returns recorded audio data associated with audiorecorder object recorder to double array y.

y = getaudiodata(recorder, dataType) converts the signal data
to the specified data type: 'double', 'single', 'int16', 'int8', or
'uint8'.

Output Arguments

У

Audio signal data *y* contains the same number of columns as the number of channels in the recording: one for mono, two for stereo. The range of values depends on the data type, as shown in the following table.

Data Type	Sample Value Range
int8	-128 to 127
uint8	0 to 255
int16	-32768 to 32767
single	-1 to 1
double	-1 to 1

Example

Collect a sample of your speech with a microphone, and plot the signal data:

```
% Record your voice for 5 seconds.
recObj = audiorecorder;
disp('Start speaking.')
recordblocking(recObj, 5);
disp('End of Recording.');
```

audiorecorder.getaudiodata

```
% Play back the recording.
play(recObj);
% Store data in double-precision array.
myRecording = getaudiodata(recObj);
% Plot the waveform.
plot(myRecording);
```

See Also

audiorecorder

How To

- · "Characteristics of Audio Files"
- · "Recording Audio"

Character array from Automation server

Syntax

MATLAB Client

```
str = h.GetCharArray('varname', 'workspace')
str = GetCharArray(h, 'varname', 'workspace')
```

IDL Method Signature

HRESULT GetCharArray([in] BSTR varName, [in] BSTR Workspace, [out, re

Microsoft Visual Basic Client

GetCharArray(varname As String, workspace As String) As String

Description

str = h.GetCharArray('varname', 'workspace') gets the character array stored in varname from the specified workspace of the server attached to handle h and returns it in str. The values for workspace arebase or global.

str = GetCharArray(h, 'varname', 'workspace') is an alternate
syntax.

Examples

This example uses a MATLAB client.

```
h = actxserver('matlab.application');
%Assign a string to variable 'str' in the base workspace of the server
h.PutCharArray('str', 'base', ...
    'He jests at scars that never felt a wound.');
%Read 'str' back in the client
S = h.GetCharArray('str', 'base')
```

This example uses a Visual Basic client.

1 Create the Visual Basic application. Use the MsgBox command to control flow between MATLAB and the application.

```
Dim Matlab As Object
Dim S As String
```

The Visual Basic MsgBox displays what you typed in MATLAB.

See Also

PutCharArray | GetWorkspaceData | GetVariable

getdatasamplesize

Purpose

Size of data sample in timeseries object

Syntax

getdatasamplesize(ts)

Description

getdatasamplesize(ts) returns the size of each data sample in a timeseries object.

Remarks

A time-series *data sample* consists of one or more scalar values recorded at a specific time. The number of data samples in is the same as the length of the time vector.

Examples

The following example shows how to get the size of a data sample in a timeseries object.

1 Load a 24-by-3 data array.

load count.dat

2 Create a timeseries object with 24 time values.

```
count_ts = timeseries(count,[1:24],'Name','VehicleCount')
```

3 Get the size of the data sample for this timeseries object.

```
getdatasamplesize(count_ts)
ans =
    1    3
```

The size of each data sample in count_ts is 1-by-3, which means that each data sample is stored as a row with three values.

See Also

addsample, size (timeseries), tsprops

getDefaultStream (RandStream)

Purpose Default random number stream

Class @RandStream

Syntax stream = RandStream.getDefaultStream

Description stream = RandStream.getDefaultStream returns the default random

number stream. The MATLAB functions rand, randi, and randn use

the default stream to generate values.

rand, randi, and randn all rely on the default stream of uniform pseudorandom numbers. randi uses one uniform value from the default stream to generate each integer value; randn uses one or more uniform values from the default stream to generate each normal value. Note that there are also rand, randi, and randn methods for which you

specify a specific random stream from which to draw values.

See Also @RandStream, setDefaultStream (RandStream), rand, randi, randn

getdisp (hgsetget)

Purpose Override to change command window display

Syntax getdisp(H)

Description getdisp(H) called by get when get is called with no output arguments

and a single input argument that is a handle array. Override this hgsetget class method in a subclass to change how property

information is displayed in the command window.

See Also See "Implementing a Set/Get Interface for Properties"

hgsetget, get (hgsetget)

Purpose Environment variable

Syntax getenv 'name'

N = getenv('name')

Description getenv 'name' searches the underlying operating system's

environment list for a string of the form name=value, where name is the input string. If found, the MATLAB software returns the string value. If the specified name cannot be found, an empty matrix is returned.

N = getenv('name') returns value to the variable N.

Examples os = getenv('0S')

os =

Windows_NT

See Also setenv, computer, pwd, ver, path

Purpose

Field of structure array

Syntax

Description

value = getfield(struct, 'field'), where struct is a 1-by-1
structure, returns the contents of the specified field, equivalent to value
= struct.field. Pass field references as strings.

```
value =
```

getfield(struct, {sIndx1,...,sIndxM}, 'field', {fIndx1,...,fIndxN}) returns the contents of the specified field, equivalent to value = struct(sIndx1,...,sIndxM).field(fIndx1,...,fIndxN). The getfield function supports multiple sets of field and fIndx inputs, and all Indx inputs are optional. If structure struct or any of the fields is a nonscalar structure, and you do not specify an Indx, the getfield function returns the values associated with the first index. If you specify a single colon operator for an fIndx input, enclose it in single quotation marks: ':'.

Tips

- For most cases, retrieve data from a structure array by indexing rather than using the getfield function. For more information, see "Returning Data from a Struct Array" and "Creating Field Names Dynamically".
- Call getfield to simplify references to structure arrays with nested fields, or to avoid creating unnecessary temporary variables, as shown in the Examples section.

Examples

The what function returns a structure array that describes the MATLAB files in the current folder. Find the files with the .m extension:

```
files = getfield(what, 'm');
```

To perform the same task by indexing requires that you create a temporary variable:

```
templist = what;
files = templist.m;
```

Find values within a structure that contains nested fields:

Using the structure defined in the previous example, find all values in the tenth row of the specified field:

```
getfield(grades, {level}, fieldnames{:}, {10,':'})
```

See Also

setfield | fieldnames | isfield | orderfields | rmfield

How To

- "Creating Field Names Dynamically"
- "Returning Data from a Struct Array"

mmreader.getFileFormats

Purpose

File formats that mmreader supports

Syntax

formats = mmreader.getFileFormats()

Description

formats = mmreader.getFileFormats() returns an array of audiovideo.FileFormatInfo objects that indicate which formats mmreader can read on the current system. Each object has the following properties: Extension, Description, ContainsVideo, and ContainsAudio.

Tips

- On Windows and UNIX systems, the list of file formats does not always contain all the formats that mmreader can read on your system. getFileFormats returns a platform-dependent, static list of formats that mmreader can read on most systems.
- On all systems, mmreader cannot always read a particular video file even if getFileFormats lists its format. For more information, see Supported Video File Formats in the MATLAB Data Import and Export documentation.

Output Arguments

formats

Array of audiovideo.FileFormatInfo objects, which have the following properties:

Extension File extension.

Description Text description of the file

format.

ContainsVideo Whether mmreader can read

video from this format.

ContainsAudio Whether mmreader can read

audio from this format.

To convert this array to a filter list for dialog boxes generated with uigetfile, use the getFilterSpec method with the following syntax:

mmreader.getFileFormats

```
filterSpec = getFilterSpec(formats)
```

The filter list includes 'All Video Files' in the first row of the cell array, and 'All Files (*.*)' in the last row.

Examples

View the list of file formats that mmreader supports on your system:

```
mmreader.getFileFormats()
```

On a Windows system, this list appears as follows:

```
Video File Formats:
    .asf - ASF File
    .asx - ASX File
    .avi - AVI File
    .mj2 - Motion JPEG2000
    .mpg - MPEG-1
    .wmv - Windows Media Video
```

Create a dialog box to select a video file:

```
% Get the supported file formats.
formats = mmreader.getFileFormats();
% Convert to a filter list.
filterSpec = getFilterSpec(formats);
% Create the dialog box.
[filename, pathname] = uigetfile(filterSpec);
```

Check whether mmreader can read an .avi file on the current system:

```
fmtList = mmreader.getFileFormats();
if any(ismember({fmtList.Extension},'avi'))
```

mmreader.get File Formats

```
disp('mmreader can read AVI files on this system.');
else
    disp('mmreader cannot read AVI files on this system.');
end
```

See Also

mmreader

Purpose Ca₁

Capture movie frame

Syntax

```
getframe
F = getframe
F = getframe(h)
F = getframe(h,rect)
```

Description

getframe returns a movie frame. The frame is a snapshot (pixmap) of the current axes or figure.

F = getframe gets a frame from the current axes.

F = getframe(h) gets a frame from the figure or axes identified by handle h.

F = getframe(h,rect) specifies a rectangular area from which to copy the pixmap. rect is relative to the lower left corner of the figure or axes h, in pixel units. rect is a four-element vector in the form [left bottom width height], where width and height define the dimensions of the rectangle.

getframe returns a movie frame, which is a structure having two fields:

- cdata The image data stored as a matrix of uint8 values. The dimensions of F.cdata are height-by-width-by-3.
- colormap The colormap stored as an n-by-3 matrix of doubles. F.colormap is empty on true color systems.

To capture an image, use this approach:

```
F = getframe(gcf);
image(F.cdata)
colormap(F.colormap)
```

Remarks

getframe is usually used in a for loop to assemble an array of movie frames for playback using movie. For example,

```
for j = 1:n plotting commands
F(j) = getframe;
```

getframe

end
movie(F)

If you are capturing frames of a plot that takes a long time to generate or are repeatedly calling getframe in a loop, make sure that your computer's screen saver does not activate and that your monitor does not turn off for the duration of the capture; otherwise one or more of the captured frames can contain graphics from your screen saver or nothing at all.

Note In situations where MATLAB software is running on a virtual desktop that is not currently visible on your monitor, calls to getframe will complete, but will capture a region on your monitor that corresponds to the position occupied by the figure or axes on the hidden desktop. Therefore, make sure that the window to be captured by getframe exists on the currently active desktop.

Capture Regions

Note that F = getframe returns the contents of the current axes, exclusive of the axis labels, title, or tick labels. F = getframe(gcf) captures the entire interior of the current figure window. To capture the figure window menu, use the form F = getframe(h,rect) with a rectangle sized to include the menu.

Resolution of Captured Frames

The resolution of the framed image depends on the size of the axes in pixels when getframe is called. As the getframe command takes a snapshot of the screen, if the axes is small in size (e.g., because you have restricted the view to a window within the axes), getframe will capture fewer screen pixels, and the captured image might have poor resolution if enlarged for display.

Capturing UIControls and Information Bars

If your figure contains uicontrols or displays the linking and brushing message bar along its top, F = getframe(figure_handle) captures

them, along with the axes and any annotations displayed on the plot. F = getframe does not capture the message bar or uicontrols outside of the current axes. To avoid including the message bar when capturing the entire figure, click the X button on the message bar to dismiss it before running getframe. Once you do this, the message bar does not appear on subsequent figures unless you reset a preference to show it.

Examples

Make the peaks function vibrate.

```
Z = peaks; surf(Z)
axis tight
set(gca,'nextplot','replacechildren');
for j = 1:20
    surf(sin(2*pi*j/20)*Z,Z)
    F(j) = getframe;
end
movie(F,20) % Play the movie twenty times
```

See Also

frame2im, image, im2frame, movie

"Bit-Mapped Images" on page 1-101 for related functions

Purpose

Matrix from Automation server workspace

Syntax

MATLAB Client

```
[xreal ximag] = h.GetFullMatrix('varname',
  'workspace', zreal,
   zimag)
[xreal ximag] = GetFullMatrix(h, 'varname', 'workspace',
   zreal, zimag)
```

IDL Method Signature

```
GetFullMatrix([in] BSTR varname, [in] BSTR
workspace, [in, out] SAFEARRAY(double) *pr, [in,
out] SAFEARRAY(double) *pi)
```

Microsoft Visual Basic Client

```
GetFullMatrix(varname As String, workspace As String, [out] XReal As Double, [out] XImag As Double
```

Description

[xreal ximag] = h.GetFullMatrix('varname', 'workspace', zreal, zimag) gets matrix stored in variable varname from the specified workspace of the server attached to handle h. The function returns the real part in xreal and the imaginary part in ximag. The values for workspace are base or global.

```
[xreal ximag] = GetFullMatrix(h, 'varname', 'workspace',
zreal, zimag) is an alternate syntax.
```

The zreal and zimag arguments are matrices of the same size as the real and imaginary matrices (xreal and ximag) returned from the server. The zreal and zimag matrices are commonly set to zero.

Use GetFullMatrix for values of type double only. Use GetVariable or GetWorkspaceData for other types.

For VBScript clients, use the GetWorkspaceData and PutWorkspaceData functions to pass numeric data to and from the MATLAB workspace. These functions use the variant data type instead of the safearray

data type used by GetFullMatrix and PutFullMatrix. VBScript does not support safearray.

Examples

Use a MATLAB client to read data from a MATLAB Automation server:

```
%Create the MATLAB server
h = actxserver('matlab.application');
%Create variable M in the base workspace of the server
h.PutFullMatrix('M','base',rand(5),zeros(5));
MReal = h.GetFullMatrix('M','base',zeros(5),zeros(5))
```

Use a Visual Basic client to read data from a MATLAB Automation server:

1 Create the Visual Basic application. Use the MsgBox command to control flow between MATLAB and the application.

2 Open the MATLAB window and type:

```
M(3,4)
```

- 3 Click Ok.
- **4** At the MATLAB command line, type:

```
MatLab.GetFullMatrix("M", "base", XReal, XImag)
```

5 Click **Ok** to close and terminate MATLAB.

See Also

PutFullMatrix | GetVariable | GetWorkspaceData | Execute

How To

- "MATLAB COM Automation Server Support"
- "Exchanging Data with the Server"

getinterpmethod

Purpose Interpolation method for timeseries object

Syntax getinterpmethod(ts)

Description getinterpmethod(ts) returns the interpolation method as a string that

is used by the timeseries object ts. Predefined interpolation methods are 'zoh' (zero-order hold) and 'linear' (linear interpolation). The

method strings are case sensitive.

Examples

1 Create a timeseries object.

```
ts = timeseries(rand(5));
```

2 Get the interpolation method for this object.

getinterpmethod(ts)

ans =

linear

See Also

setinterpmethod, timeseries, tsprops

getpixelposition

Purpose

Get component position in pixels

Syntax

```
position = getpixelposition(handle)
position = getpixelposition(handle, recursive)
```

Description


position = getpixelposition(handle) gets the position, in pixel units, of the component with handle handle. The position is returned as a four-element vector that specifies the location and size of the component: [distance from left, distance from bottom, width, height].

position = getpixelposition(handle, recursive) gets the position as above. If recursive is true, the returned position is relative to the parent figure of handle.

Use the getpixelposition function only to obtain coordinates for children of figures and container components (uipanels, or uibuttongroups). Results are not reliable for children of axes or other Handle Graphics objects.

Example

This example creates a push button within a panel, and then retrieves its position, in pixels, relative to the panel.



The following statement retrieves the position of the push button, in pixels, relative to the figure.

See Also

setpixelposition, uicontrol, uipanel

Purpose

Preference

Syntax

```
getpref('group','pref')
getpref('group','pref',default)
getpref('group',{'pref1','pref2',...'prefn'})
getpref('group',{'pref1',...'prefn'},{default1,...defaultn})
getpref('group')
getpref
```

Description

getpref('group', 'pref') returns the value for the preference specified by group and pref. It is an error to get a preference that does not exist.

group labels a related collection of preferences. You can choose any name that is a legal variable name, and is descriptive enough to be unique, e.g. 'ApplicationOnePrefs'. The input argument prefidentifies an individual preference in that group, and must be a legal variable name.

getpref('group','pref',default) returns the current value if the preference specified by group and pref exists. Otherwise creates the preference with the specified default value and returns that value.

getpref('group',{'pref1','pref2',...'prefn'}) returns a cell array containing the values for the preferences specified by group and the cell array of preference names. The return value is the same size as the input cell array. It is an error if any of the preferences do not exist.

getpref('group',{'pref1',...'prefn'},{default1,...defaultn}) returns a cell array with the current values of the preferences specified by group and the cell array of preference names. Any preference that does not exist is created with the specified default value and returned.

getpref('group') returns the names and values of all preferences in the group as a structure.

getpref returns all groups and preferences as a structure.

Note Preference values are persistent and maintain their values between MATLAB sessions. Where they are stored is system dependent.

Examples Example 1

```
addpref('mytoolbox','version','1.0')
getpref('mytoolbox','version')
ans =
    1.0
```

Example 2

```
rmpref('mytoolbox','version')
getpref('mytoolbox','version','1.0');
getpref('mytoolbox','version')
ans =
    1.0
```

See Also

addpref, ispref, rmpref, setpref, uigetpref, uisetpref

getqualitydesc

Purpose Data quality descriptions

Syntax getqualitydesc(ts)

Description getqualitydesc(ts) returns a cell array of data quality descriptions

based on the Quality values you assigned to a timeseries object ts.

Examples

1 Create a timeseries object with Data, Time, and Quality values, respectively.

```
ts = timeseries([3; 4.2; 5; 6.1; 8], 1:5, [1; 0; 1; 0; 1]);
```

2 Set the QualityInfo property, consisting of Code and Description.

```
ts.QualityInfo.Code = [0 1];
ts.QualityInfo.Description = {'good' 'bad'};
```

3 Get the data quality description strings for ts.

```
getqualitydesc(ts)
ans =
    'bad'
    'good'
    'bad'
    'good'
    'bad'
```

See Also tsprops

Purpose

Get error message for exception

Syntax

msgString = getReport(exception)

msgString = getReport(exception, type)

msgString = getReport(exception, type, 'hyperlinks', value)

Description

msgString = getReport(exception) returns a formatted message string, msgString, from an exception. This exception is represented by the exception input which is a scalar object of the MException class. The message string returned by getReport is the same as the error message displayed by MATLAB when it throws this exception.

msgString = getReport(exception, type) returns a message string that either describes just the error (basic type), or shows the error and the stack as well (extended type). The type argument, when used, must be the second argument in the input argument list. See "Examples" on page 2-1742, below.

type Option	Displayed Text
'extended'	Display line number, error message, and cause and stack summary (default)
'basic'	Display line number and error message

msgString = getReport(exception, type, 'hyperlinks', value) returns a message string that either does or does not include active hyperlinks to the failing lines in the code. See the table below for the valid choices for value. The hyperlinks and value arguments, when used, must be the third and fourth arguments in the input argument list.

value Option	Action
'on'	Display hyperlinks to failing lines (default)
'off'	Do not display hyperlinks to failing lines
'default'	Use the default for the Command Window to determine whether or not to use hyperlinks in the error message

Examples

Try calling the MATLAB surf function without the required input argument. In the catch statement, capture the error in an MException object, exception. Then, use this object with getReport to retrieve a basic error string:

```
try
    surf
catch exception
    rep = getReport(exception, 'basic')
end

rep =
Error using ==> surf at 50
Not enough input arguments.
```

Run the try-catch again, this time replacing 'basic' with 'extended': In this case, the error message includes information from the stack:

```
rep = getReport(exception, 'extended')
rep =
Error using ==> surf at 50
Not enough input arguments.
Error in ==> getRep>getRep3 at 9
    surf
```

getReport (MException)

Error in ==> getRep>getRep2 at 5
getRep3(option, state)

Error in ==> getRep at 2
getRep2(option, state)

See Also

try, catch, error, assert, MException, throw(MException),
rethrow(MException), throwAsCaller(MException),
addCause(MException), last(MException),

getsampleusingtime (timeseries)

Purpose Extract data samples into new timeseries object

Syntax ts2 = getsampleusingtime(ts1,Time)

ts2 = getsampleusingtime(ts1,StartTime,EndTime)

Description ts2 = getsampleusingtime(ts1, Time) returns a new timeseries

object ts2 with a single sample corresponding to the time Time in ts1.

ts2 = getsampleusingtime(ts1, StartTime, EndTime) returns a new timeseries object ts2 with samples between the times StartTime and

EndTime in ts1.

Remarks When the time vector in ts1 is numeric, StartTime and EndTime must

also be numeric. When the times in ts1 are date strings and the StartTime and EndTime values are numeric, then the StartTime and

EndTime values are treated as datenum values.

See Also timeseries

getsampleusingtime (tscollection)

Purpose Extract data samples into new tscollection object

Syntax tsc2 = getsampleusingtime(tsc1,Time)

tsc2 = getsampleusingtime(tsc1,StartTime,EndTime)

Description tsc2 = getsampleusingtime(tsc1,Time) returns a new

tscollection tsc2 with a single sample corresponding to Time in tsc1.

tsc2 = getsampleusingtime(tsc1,StartTime,EndTime) returns a
new tscollection tsc2 with samples between the times StartTime

and EndTime in tsc1.

Remarks When the time vector in ts1 is numeric, StartTime and EndTime must

also be numeric. When the times in ts1 are date strings and the StartTime and EndTime values are numeric, then the StartTime and

EndTime values are treated as datenum values.

See Also tscollection

Tiff.getTag

Purpose

Value of specified tag

Syntax

tagValue = getTag(tagId)

Description

tagValue = getTag(tagId) retrieves the value of the TIFF tag specified by tagId. You can specify tagId as a character string ('ImageWidth') or using the numeric tag identifier defined by the TIFF specification (256). To see a list of all the tags with their numeric identifiers, view the value of the Tiff object TagID property. Use the TagID property to specify the value of a tag. For example, Tiff.TagID.ImageWidth is equivalent to the tag's numeric identifier.

Examples

Open a Tiff object, and get the value of a tag. Replace myfile.tif with the name of a TIFF file on your MATLAB path:

```
t = Tiff('myfile.tif', 'r');
% Specify tag by name.
tagval = t.getTag('ImageWidth');
%
% Specify tag by numeric identifier.
tagval1 = t.getTag(256);
%
% Specify tag by name.
tagval2 = t.getTag('t.TagID.ImageWidth');
```

References

This method corresponds to the TIFFGetField function in the LibTIFF C API. To use this method, you must be familiar with LibTIFF version 3.7.1, as well as the TIFF specification and technical notes. View this documentation at LibTiff - TIFF Library and Utilities.

See Also

Tiff.setTag

Tutorials

- "Exporting Image Data and Metadata to TIFF Files"
- "Reading Image Data and Metadata from TIFF Files"

Purpose List of recognized TIFF tags

Syntax tagNames = Tiff.getTagNames()

Description tagNames = Tiff.getTagNames() returns a cell array of TIFF tags

recognized by the Tiff object.

Examples Retrieve a list of TIFF tags recognized by the Tiff object.

Tiff.getTagNames

ans =

'SubFileType' 'ImageWidth'

'ImageLength'

'BitsPerSample'

'Compression'

'Photometric'

'Thresholding'

'FillOrder'

'DocumentName'

'ImageDescription'

.

.

See Also Tiff.getTag

Tutorials

• "Exporting Image Data and Metadata to TIFF Files"

• "Reading Image Data and Metadata from TIFF Files"

gettimeseriesnames

Purpose Cell array of names of timeseries objects in tscollection object

Syntax names = gettimeseriesnames(tsc)

Description names = gettimeseriesnames(tsc) returns names of timeseries

objects in a $\mathsf{tscollection}$ object $\mathsf{tsc.}$ names is a cell array of $\mathsf{strings.}$

Examples

1 Create timeseries objects a and b.

```
a = timeseries(rand(1000,1), 'name', 'position');
b = timeseries(rand(1000,1), 'name', 'response');
```

2 Create a tscollection object that includes these two time series.

```
tsc = tscollection({a,b});
```

3 Get the names of the timeseries objects in tsc.

```
names = gettimeseriesnames(tsc)
names =
    'position' 'response'
```

See Also

timeseries, tscollection, tsprops

Purpose

New timeseries object with samples occurring at or after event

Syntax

ts1 = gettsafteratevent(ts,event)
ts1 = gettsafteratevent(ts,event,n)

Description

ts1 = gettsafteratevent(ts, event) returns a new timeseries object ts1 with samples occurring at and after an event in ts, where event can be either a tsdata.event object or a string. When event is a tsdata.event object, the time defined by event is used. When event is a string, the first tsdata.event object in the Events property of the time series ts that matches the event name specifies the time.

ts1 = gettsafteratevent(ts, event, n) returns a new timeseries object ts1 with samples at and after an event in ts, where n is the number of the event occurrence with a matching event name.

Remarks

When the timeseries object ts contains date strings and event uses numeric time, the time selected by the event is treated as a date that is calculated relative to the StartDate property in ts.TimeInfo.

When ts uses numeric time and event uses calendar dates, the time selected by the event is treated as a numeric value that is not associated with a calendar date.

See Also

gettsafterevent, gettsbeforeevent, gettsbetweenevents,

tsdata.event, tsprops

gettsafterevent

Purpose 1

New timeseries object with samples occurring after event

Syntax

ts1 = gettsafterevent(ts,event)
ts1 = ttsafterevent(ts,event,n)

Description

ts1 = gettsafterevent(ts,event) returns a new timeseries object ts1 with samples occurring after an event in ts, where event can be either a tsdata.event object or a string. When event is a tsdata.event object, the time defined by event is used. When event is a string, the first tsdata.event object in the Events property of ts that matches the event name specifies the time.

ts1 = ttsafterevent(ts, event, n) returns a new timeseries object ts1 with samples occurring after an event in time series ts, where n is the number of the event occurrence with a matching event name.

Remarks

When the timeseries object ts contains date strings and event uses numeric time, the time selected by the event is treated as a date that is calculated relative to the StartDate property in ts.TimeInfo.

When ts uses numeric time and event uses calendar dates, the time selected by the event is treated as a numeric value that is not associated with a calendar date.

See Also

 ${\tt getts after at event}, \, {\tt getts before event}, \, {\tt getts between events}, \,$

tsdata.event, tsprops

Purpose

New timeseries object with samples occurring at event

Syntax

ts1 = gettsatevent(ts,event)
ts1 = gettsatevent(ts,event,n)

Description

ts1 = gettsatevent(ts,event) returns a new timeseries object ts1 with samples occurring at an event in ts, where event can be either a tsdata.event object or a string. When event is a tsdata.event object, the time defined by event is used. When event is a string, the first tsdata.event object in the Events property of ts that matches the event name specifies the time.

ts1 = gettsatevent(ts,event,n) returns a new time series ts1 with samples occurring at an event in time series ts, where n is the number of the event occurrence with a matching event name.

Remarks

When the timeseries object ts contains date strings and event uses numeric time, the time selected by the event is treated as a date that is calculated relative to the StartDate property in the ts.TimeInfo.

When ts uses numeric time and event uses calendar dates, the time selected by the event is treated as a numeric value that is not associated with a calendar date.

See Also

gettsafterevent, gettsafteratevent, gettsbeforeevent,

gettsbetweenevents, tsdata.event, tsprops

gettsbeforeatevent

Purpose

New timeseries object with samples occurring before or at event

Syntax

ts1 = gettsbeforeatevent(ts,event)
ts1 = gettsbeforeatevent(ts,event,n)

Description

ts1 = gettsbeforeatevent(ts,event) returns a new timeseries object ts1 with samples occurring at and before an event in ts, where event can be either a tsdata.event object or a string. When event is a tsdata.event object, the time defined by event is used. When event is a string, the first tsdata.event object in the Events property of ts that matches the event name specifies the time.

ts1 = gettsbeforeatevent(ts,event,n) returns a new timeseries object ts1 with samples occurring at and before an event in time series ts, where n is the number of the event occurrence with a matching event name.

Remarks

When the timeseries object to contains date strings and event uses numeric time, the time selected by the event is treated as a date that is calculated relative to the StartDate property in ts.TimeInfo.

When ts uses numeric time and event uses calendar dates, the time selected by the event is treated as a numeric value that is not associated with a calendar date.

See Also

gettsafterevent, gettsbeforeevent, gettsbetweenevents, tsdata.event, tsprops

Purpose

New timeseries object with samples occurring before event

Syntax

ts1 = gettsbeforeevent(ts,event)
ts1 = gettsbeforeevent(ts,event,n)

Description

ts1 = gettsbeforeevent(ts, event) returns a new timeseries object ts1 with samples occurring before an event in ts, where event can be either a tsdata.event object or a string. When event is a tsdata.event object, the time defined by event is used. When event is a string, the first tsdata.event object in the Events property of ts that matches the event name specifies the time.

ts1 = gettsbeforeevent(ts,event,n) returns a new timeseries object ts1 with samples occurring before an event in ts, where n is the number of the event occurrence with a matching event name.

Remarks

When the timeseries object ts contains date strings and event uses numeric time, the time selected by the event is treated as a date that is calculated relative to the StartDate property in ts.TimeInfo.

When ts uses numeric time and event uses calendar dates, the time selected by the event is treated as a numeric value that is not associated with a calendar date.

See Also

 ${\tt getts after event}, \, {\tt getts before a tevent}, \, {\tt getts between events}, \,$

tsdata.event, tsprops

gettsbetweenevents

Purpose

New timeseries object with samples occurring between events

Syntax

ts1 = gettsbetweenevents(ts,event1,event2)

ts1 = gettsbetweenevents(ts,event1,event2,n1,n2)

Description

ts1 = gettsbetweenevents(ts,event1,event2) returns a new timeseries object ts1 with samples occurring between events in ts, where event1 and event2 can be either a tsdata.event object or a string. When event1 and event2 are tsdata.event objects, the time defined by the events is used. When event1 and event2 are strings, the first tsdata.event object in the Events property of ts that matches the event names specifies the time.

ts1 = gettsbetweenevents(ts,event1,event2,n1,n2) returns a new timeseries object ts1 with samples occurring between events in ts, where n1 and n2 are the nth occurrences of the events with matching event names.

Remarks

When the timeseries object ts contains date strings and event uses numeric time, the time selected by the event is treated as a date that is calculated relative to the StartDate property in ts.TimeInfo.

When ts uses numeric time and event uses calendar dates, the time selected by the event is treated as a numeric value that is not associated with a calendar date.

See Also

gettsafterevent, gettsbeforeevent, tsdata.event, tsprops

Data from variable in Automation server workspace

Syntax

MATLAB Client

```
D = h.GetVariable('varname', 'workspace')
D = GetVariable(h, 'varname', 'workspace')
```

IDL Method Signature

```
HRESULT GetVariable([in] BSTR varname, [in] BSTR
workspace, [out, retval] VARIANT* pdata)
```

Microsoft Visual Basic Client

```
GetVariable(varname As String, workspace As String) As Object
```

Description

D = h.GetVariable('varname', 'workspace') gets data stored in variable varname from the specified workspace of the server attached to handle h and returns it in output argument D. The values for workspace are base or global.

D = GetVariable(h, 'varname', 'workspace') is an alternate syntax.

Do *not* use GetVariable on sparse arrays, structures, or function handles.

If your scripting language requires a result be returned explicitly, use the GetVariable function in place of GetWorkspaceData, GetFullMatrix or GetCharArray.

Examples

Use a MATLAB client to read data from a MATLAB Automation server:

```
%Create the MATLAB server
h = actxserver('matlab.application');
%Create variable C1 in the base workspace of the server
h.PutWorkspaceData('C1', 'base', {25.72, 'hello', rand(4)});
%The client reads the data
C2 = h.GetVariable('C1','base')
```

Use a Visual Basic client to read data from a MATLAB Automation server:

```
Dim Matlab As Object
Dim Result As String
Dim C2 As Object
Matlab = CreateObject("matlab.application")
Result = Matlab.Execute("C1 = {25.72, 'hello', rand(4)};")
C2 = Matlab.GetVariable("C1", "base")
MsgBox("Second item in cell array: " & C2(0, 1))
```



See Also

GetWorkspaceData | GetFullMatrix | GetCharArray | Execute

How To

- "MATLAB COM Automation Server Support"
- "Exchanging Data with the Server"

Purpose LibTIFF library version

Description versionString = Tiff.getVersion() returns the version number

and other information about the LibTIFF library.

Examples Display version of LibTIFF library:

Tiff.getVersion

ans =

LIBTIFF, Version 3.7.1

Copyright (c) 1988-1996 Sam Leffler

Copyright (c) 1991-1996 Silicon Graphics, Inc.

References This method corresponds to the TIFFGetVersion function in the

LibTIFF C API. To use this method, you must be familiar with LibTIFF version 3.7.1, as well as the TIFF specification and technical notes. View this documentation at LibTIFF - TIFF Library and Utilities.

Data from Automation server workspace

Syntax

MATLAB Client

```
D = h.GetWorkspaceData('varname', 'workspace')
D = GetWorkspaceData(h, 'varname', 'workspace')
```

IDL Method Signature

```
HRESULT GetWorkspaceData([in] BSTR varname, [in] BSTR
workspace, [out] VARIANT* pdata)
```

Microsoft Visual Basic Client

```
GetWorkspaceData(varname As String, workspace
As String) As Object
```

Description

D = h.GetWorkspaceData('varname', 'workspace') gets data stored in variable varname from the specified workspace of the server attached to handle h and returns it in output argument D. The values for workspace are base or global.

D = GetWorkspaceData(h, 'varname', 'workspace') is an alternate syntax.

Use GetWorkspaceData instead of GetFullMatrix and GetCharArray to get numeric and character array data, respectively. Do *not* use GetWorkspaceData on sparse arrays, structures, or function handles.

For VBScript clients, use the GetWorkspaceData and PutWorkspaceData functions to pass numeric data to and from the MATLAB workspace. These functions use the variant data type instead of the safearray data type used by GetFullMatrix and PutFullMatrix. VBScript does not support safearray.

Examples

Use a MATLAB client to read data from a MATLAB Automation server:

```
%Create the MATLAB server
h = actxserver('matlab.application');
%Create cell array C1 in the base workspace of the server
h.PutWorkspaceData('C1', 'base', ...
```

```
{25.72, 'hello', rand(4)});
C2 = h.GetWorkspaceData('C1', 'base')
```

Use a Visual Basic client to read data from a MATLAB Automation server:

```
Dim Matlab, C2 As Object
Dim Result As String
Matlab = CreateObject("matlab.application")
Result = MatLab.Execute("C1 = {25.72, 'hello', rand(4)};")
MsgBox("In MATLAB, type" & vbCrLf & "C1")
Matlab.GetWorkspaceData("C1", "base", C2)
MsgBox("second value of C1 = " & C2(0, 1))
```

See Also

PutWorkspaceData | GetFullMatrix | GetCharArray | GetVariable | Execute

How To

- "MATLAB COM Automation Server Support"
- · "Exchanging Data with the Server"

Graphical input from mouse or cursor

Syntax

```
[x,y] = ginput(n)
[x,y] = ginput
[x,y,button] = ginput(...)
```

Description

ginput raises crosshairs in the current axes to for you to identify points in the figure, positioning the cursor with the mouse. The figure must have focus before ginput can receive input. If it has no axes, one is created upon the first click or keypress.

[x,y] = ginput(n) enables you to identify n points from the current axes and returns their x- and y-coordinates in the x and y column vectors. Press the **Return** key to terminate the input before entering n points.

[x,y] = ginput gathers an unlimited number of points until you press the **Return** key.

[x,y,button] = ginput(...) returns the x-coordinates, the y-coordinates, and the button or key designation. button is a vector of integers indicating which mouse buttons you pressed (1 for left, 2 for middle, 3 for right), or ASCII numbers indicating which keys on the keyboard you pressed.

Clicking an axes makes that axes the current axes. Even if you set the current axes before calling ginput, whichever axes you click becomes the current axes and ginput returns points relative to that axes. If you select points from multiple axes, the results returned are relative to the coordinate system of the axes they come from.

Definitions

Coordinates returned by ginput are scaled to the XLim and YLim bounds of the axes you click (data units). Setting the axes or figure Units property has no effect on the output from ginput. You can click anywhere within the figure canvas to obtain coordinates. If you click outside the axes limits, ginput extrapolates coordinate values so they are still relative to the axes origin.


The figure CurrentPoint property, by contrast, is always returned in figure Units, irrespective of axes Units or limits.

Examples

Pick 4 two-dimensional points from the figure window.

```
[x,y] = ginput(4)
```

Position the cursor with the mouse. Enter data points by pressing a mouse button or a key on the keyboard. To terminate input before entering 4 points, press the **Return** key.



In this example, plot rescaled the axes x-limits and y-limits from [0 1] and [0 1] to [0.20 0.65] and [0.40 0.75]. The rescaling occured because the axes XLimMode and YLimMode are set to 'auto' (the default). Consider setting XLimMode and YLimMode to 'manual' if you want to maintain consistency when you gather results from ginput and plot them together.

See Also gtext

Tutorials

- "Example Selecting Plotting Points from the Screen"
- "Subsetting a Graphics Image (Cropping)"

Declare global variables

Syntax

global X Y Z

Description

global X Y Z defines X, Y, and Z as global in scope.

Ordinarily, each MATLAB function has its own local variables, which are separate from those of other functions, and from those of the base workspace. However, if several functions, and possibly the base workspace, all declare a particular name as global, they all share a single copy of that variable. Any assignment to that variable, in any function, is available to all the functions declaring it global.

If the global variable does not exist the first time you issue the global statement, it is initialized to the empty matrix.

If a variable with the same name as the global variable already exists in the current workspace, MATLAB issues a warning and changes the value of that variable to match the global.

Remarks

Use clear global *variable* to clear a global variable from the global workspace. Use clear *variable* to clear the global link from the current workspace without affecting the value of the global.

To use a global within a callback, declare the global, use it, then clear the global link from the workspace. This avoids declaring the global after it has been referenced. For example,

```
cbstr = sprintf('%s, %s, %s, %s, %s', ...
    'global MY_GLOBAL', ...
    'MY_GLOBAL = 100', ...
    'disp(MY_GLOBAL)', ...
    'MY_GLOBAL = MY_GLOBAL+1', ...
    'clear MY_GLOBAL');

uicontrol('style', 'pushbutton', 'CallBack', cbstr, ...
    'string', 'count')
```

There is no function form of the global command (i.e., you cannot use parentheses and quote the variable names).

Examples

Here is the code for the functions tic and toc (some comments abridged). These functions manipulate a stopwatch-like timer. The global variable TICTOC is shared by the two functions, but it is invisible in the base workspace or in any other functions that do not declare it.

```
function tic
     TIC Start a stopwatch timer.
         TIC; any stuff; TOC
     prints the time required.
     See also: TOC, CLOCK.
global TICTOC
TICTOC = clock;
function t = toc
     TOC Read the stopwatch timer.
     TOC prints the elapsed time since TIC was used.
     t = TOC; saves elapsed time in t, does not print.
     See also: TIC, ETIME.
global TICTOC
if nargout < 1
    elapsed time = etime(clock, TICTOC)
else
    t = etime(clock, TICTOC);
end
```

See Also

clear, isglobal, who

Generalized minimum residual method (with restarts)

Syntax

```
x = gmres(A,b)
gmres(A,b,restart)
gmres(A,b,restart,tol)
gmres(A,b,restart,tol,maxit)
gmres(A,b,restart,tol,maxit,M)
gmres(A,b,restart,tol,maxit,M1,M2)
gmres(A,b,restart,tol,maxit,M1,M2,x0)
[x,flag] = gmres(A,b,...)
[x,flag,relres] = gmres(A,b,...)
[x,flag,relres,iter] = gmres(A,b,...)
[x,flag,relres,iter,resvec] = gmres(A,b,...)
```

Description

x = gmres(A,b) attempts to solve the system of linear equations A*x = b for x. The n-by-n coefficient matrix A must be square and should be large and sparse. The column vector b must have length n. A can be a function handle afun such that afun(x) returns A*x. See "Function Handles" in the MATLAB Programming documentation for more information. For this syntax, gmres does not restart; the maximum number of iterations is min(n,10).

"Parameterizing Functions", in the MATLAB Mathematics documentation, explains how to provide additional parameters to the function afun, as well as the preconditioner function mfun described below, if necessary.

If gmres converges, a message to that effect is displayed. If gmres fails to converge after the maximum number of iterations or halts for any reason, a warning message is printed displaying the relative residual norm(b-A*x)/norm(b) and the iteration number at which the method stopped or failed.

gmres(A,b,restart) restarts the method every restart inner iterations. The maximum number of outer iterations is min(n/restart,10). The maximum number of total iterations is restart*min(n/restart,10). If restart is n or [], then gmres does not restart and the maximum number of total iterations is min(n,10).

gmres(A,b,restart,tol) specifies the tolerance of the method. If tol is [], then gmres uses the default, 1e-6.

gmres(A,b,restart,tol,maxit) specifies the maximum number of outer iterations, i.e., the total number of iterations does not exceed restart*maxit. If maxit is [] then gmres uses the default, min(n/restart,10). If restart is n or [], then the maximum number of total iterations is maxit (instead of restart*maxit).

gmres(A,b,restart,tol,maxit,M) and gmres(A,b,restart,tol,maxit,M1,M2) use preconditioner M or M = M1*M2 and effectively solve the system inv(M)*A*x = inv(M)*b for x. If M is [] then gmres applies no preconditioner. M can be a function handle mfun such that mfun(x) returns M\x.

gmres(A,b,restart,tol,maxit,M1,M2,x0) specifies the first initial guess. If x0 is [], then gmres uses the default, an all-zero vector.

[x,flag] = gmres(A,b,...) also returns a convergence flag:

flag = 1 gmres iterated maxit times but did not converge.

flag = 2 Preconditioner M was ill-conditioned.

flag = 3 gmres stagnated. (Two consecutive iterates were the same.)

Whenever flag is not 0, the solution x returned is that with minimal norm residual computed over all the iterations. No messages are displayed if the flag output is specified.

[x,flag,relres] = gmres(A,b,...) also returns the relative residual norm(b-A*x)/norm(b). If flag is 0, relres <= tol.

[x,flag,relres,iter] = gmres(A,b,...) also returns both the outer and inner iteration numbers at which x was computed, where 0 <= iter(1) <= maxit and 0 <= iter(2) <= restart.

[x,flag,relres,iter,resvec] = gmres(A,b,...) also returns a vector of the residual norms at each inner iteration, including norm(b-A*x0).

Examples Example 1

```
A = gallery('wilk',21);
b = sum(A,2);
tol = 1e-12;
maxit = 15;
M1 = diag([10:-1:1 1 1:10]);
x = gmres(A,b,10,tol,maxit,M1);
```

displays the following message:

gmres(10) converged at outer iteration 2 (inner iteration 9) to a solution with relative residual 3.3e-013

Example 2

This example replaces the matrix A in Example 1 with a handle to a matrix-vector product function afun, and the preconditioner M1 with a handle to a backsolve function mfun. The example is contained in an M-file run_gmres that

- Calls gmres with the function handle @afun as its first argument.
- Contains afun and mfun as nested functions, so that all variables in run_gmres are available to afun and mfun.

The following shows the code for run_gmres:

```
function x1 = run_gmres
n = 21;
A = gallery('wilk',n);
b = sum(A,2);
tol = 1e-12; maxit = 15;
x1 = gmres(@afun,b,10,tol,maxit,@mfun);
```

```
function y = afun(x)

y = [0; x(1:n-1)] + ...

[((n-1)/2:-1:0)'; (1:(n-1)/2)'].*x + ...

[x(2:n); 0];

end

function y = mfun(r)

y = r ./ [((n-1)/2:-1:1)'; 1; (1:(n-1)/2)'];

end

end
```

When you enter

```
x1 = run_gmres;
```

MATLAB software displays the message

gmres(10) converged at outer iteration 2 (inner iteration 9) to a solution with relative residual 3.3e-013

Example 3

```
load west0479
A = west0479
b = sum(A,2)
[x,flag] = gmres(A,b,5)
```

flag is 1 because gmres does not converge to the default tolerance 1e-6 within the default 10 outer iterations.


```
[L1,U1] = luinc(A,1e-5);
[x1,flag1] = gmres(A,b,5,1e-6,5,L1,U1);
```

flag1 is 2 because the upper triangular U1 has a zero on its diagonal, and gmres fails in the first iteration when it tries to solve a system such as U1*y = r for y using backslash.

```
[L2,U2] = luinc(A,1e-6);
```

```
tol = 1e-15;
[x4,flag4,relres4,iter4,resvec4] = gmres(A,b,4,to1,5,L2,U2);
[x6,flag6,relres6,iter6,resvec6] = gmres(A,b,6,to1,3,L2,U2);
[x8,flag8,relres8,iter8,resvec8] = gmres(A,b,8,to1,3,L2,U2);
```

flag4, flag6, and flag8 are all 0 because gmres converged when restarted at iterations 4, 6, and 8 while preconditioned by the incomplete LU factorization with a drop tolerance of 1e-6. This is verified by the plots of outer iteration number against relative residual. A combined plot of all three clearly shows the restarting at iterations 4 and 6. The total number of iterations computed may be more for lower values of restart, but the number of length n vectors stored is fewer, and the amount of work done in the method decreases proportionally.



See Also bicg, bicgstab, cgs, lsqr, ilu, luinc, minres, pcg, qmr, symmlq

function_handle (@), mldivide (\)

References

Barrett, R., M. Berry, T. F. Chan, et al., *Templates for the Solution of Linear Systems: Building Blocks for Iterative Methods*, SIAM, Philadelphia, 1994.

Saad, Youcef and Martin H. Schultz, "GMRES: A generalized minimal residual algorithm for solving nonsymmetric linear systems," *SIAM J. Sci. Stat. Comput.*, July 1986, Vol. 7, No. 3, pp. 856-869.

Plot nodes and links representing adjacency matrix

Syntax

```
gplot(A,Coordinates)
gplot(A,Coordinates,LineSpec)
```

Description

The gplot function graphs a set of coordinates using an adjacency matrix.

gplot(A, Coordinates) plots a graph of the nodes defined in Coordinates according to the n-by-n adjacency matrix A, where n is the number of nodes. Coordinates is an n-by-2 matrix, where n is the number of nodes and each coordinate pair represents one node.

gplot(A, Coordinates, *LineSpec*) plots the nodes using the line type, marker symbol, and color specified by *LineSpec*.


Remarks

For two-dimensional data, Coordinates(i,:) = [x(i) y(i)] denotes node i, and Coordinates(j,:) = [x(j)y(j)] denotes node j. If node i and node j are connected, A(i,j) or A(j,i) is nonzero; otherwise, A(i,j) and A(j,i) are zero.

Examples

To draw half of a Bucky ball with asterisks at each node,

```
k = 1:30;
[B,XY] = bucky;
gplot(B(k,k),XY(k,:),'-*')
axis square
```



See Also

LineSpec, sparse, spy

"Tree Operations" on page 1-55 for related functions

MATLAB code from files published to HTML

Syntax

```
grabcode('name.html')
grabcode('urlname')
codeString = grabcode('name.html')
```

Description

grabcode ('name.html') copies MATLAB code from the file name.html and pastes it into an untitled document in the Editor. Use grabcode to get MATLAB code from demos or other published files when the source code is not readily available. The file name.html was created by publishing name.m, a MATLAB code file containing cells. The MATLAB code from name.m is included at the end of name.html as HTML comments.

grabcode ('urlname') copies MATLAB code from the urlname location and pastes it into an untitled document in the Editor.

codeString = grabcode('name.html') get MATLAB code from the
file name.html and assigns it the variable codeString.

Examples Run

```
sineWaveString = grabcode('d:/mymfiles/sine_wave_.html')
and MATLAB displays
sineWaveString =
    %% Simple Sine Wave Plot
    %% Part One: Calculate Sine Wave
    % Define the range |x|.
    % Calculate the sine |y| over that range.
    x = 0:.01:6*pi;
    y = sin(x);

    %% Part Two: Plot Sine Wave
    % Graph the result.
```

grabcode

plot(x,y)

See Also

demo, publish

Numerical gradient

Syntax

Definition

The *gradient* of a function of two variables, F(x, y), is defined as

$$\nabla F = \frac{\partial F}{\partial x}\hat{i} + \frac{\partial F}{\partial y}\hat{j}$$

and can be thought of as a collection of vectors pointing in the direction of increasing values of F. In MATLAB software, numerical gradients (differences) can be computed for functions with any number of variables. For a function of N variables, $F(x, y, z, \ldots)$,

$$\nabla F = \frac{\partial F}{\partial x}\hat{i} + \frac{\partial F}{\partial y}\hat{j} + \frac{\partial F}{\partial z}\hat{k} + \dots$$

Description

FX = gradient(F) where F is a vector returns the one-dimensional numerical gradient of F. FX corresponds to $\partial F/\partial x$, the differences in x (horizontal) direction.

[FX,FY] = gradient(F) where F is a matrix returns the x and y components of the two-dimensional numerical gradient. FX corresponds to $\partial F/\partial x$, the differences in x (horizontal) direction. FY corresponds to $\partial F/\partial y$, the differences in the y (vertical) direction. The spacing between points in each direction is assumed to be one.

[FX,FY,FZ,...] = gradient(F) where F has N dimensions returns the N components of the gradient of F. There are two ways to control the spacing between values in F:

• A single spacing value, h, specifies the spacing between points in every direction.

• N spacing values (h1, h2,...) specifies the spacing for each dimension of F. Scalar spacing parameters specify a constant spacing for each dimension. Vector parameters specify the coordinates of the values along corresponding dimensions of F. In this case, the length of the vector must match the size of the corresponding dimension.

Note The first output FX is always the gradient along the 2nd dimension of F, going across columns. The second output FY is always the gradient along the 1st dimension of F, going across rows. For the third output FZ and the outputs that follow, the Nth output is the gradient along the Nth dimension of F.

[...] = gradient(F,h) where h is a scalar uses h as the spacing between points in each direction.


[...] = gradient(F,h1,h2,...) with N spacing parameters specifies the spacing for each dimension of F.

Examples

The statements

```
v = -2:0.2:2;
[x,y] = meshgrid(v);
z = x .* exp(-x.^2 - y.^2);
[px,py] = gradient(z,.2,.2);
contour(v,v,z), hold on, quiver(v,v,px,py), hold off
```

produce



See Also

2-1777

graymon

Purpose Set default figure properties for grayscale monitors

Syntax graymon

Description graymon sets defaults for graphics properties to produce more legible

displays for grayscale monitors.

See Also axes, figure

"Color Operations" on page 1-108 for related functions

Purpose (

Grid lines for 2-D and 3-D plots

GUI Alternative To control the presence and appearance of grid lines on a graph, use

the Property Editor, one of the plotting tools . For details, see The

Property Editor in the MATLAB Graphics documentation.

Syntax

grid on grid off

grid

grid(axes_handle,...)

grid minor

Description

The grid function turns the current axes' grid lines on and off.

grid on adds major grid lines to the current axes.

grid off removes major and minor grid lines from the current axes.

grid toggles the major grid visibility state.

 $grid(axes_handle,...)$ uses the axes specified by axes_handle

instead of the current axes.

Algorithm

grid sets the XGrid, YGrid, and ZGrid properties of the axes.

 grid minor sets the XMinorGrid, YMinorGrid, and ZMinorGrid

properties of the axes.

You can set the grid lines for just one axis using the set command and

the individual property. For example,

set(axes_handle,'XGrid','on')

turns on only x-axis grid lines.

You can set grid line width with the axes LineWidth property.

Examples

Create multiple plots within a single figure and manipulate their grid

visibility using the grid function:

```
for i = 1:4
axh(i) = subplot(2, 2, i);
plot(rand(1, 10));
end
for i = 1:4
grid(axh(i),'on')
end
```

You may also use the following code to avoid using for loops:

```
set(axh,'XGrid','on','YGrid','on','ZGrid','on')
```

See Also

box, axes, set

The properties of axes objects

"Axes Operations" on page 1-106 for related functions

Purpose Data gridding

griddata is not recommended. Use TriScatteredInterp instead

Syntax

```
ZI = griddata(x,y,z,XI,YI)
[XI,YI,ZI] = griddata(x,y,z,XI,YI)
[...] = griddata(...,method)
```

Description

ZI = griddata(x,y,z,XI,YI) fits a surface of the form z = f(x,y) to the data in the (usually) nonuniformly spaced vectors (x,y,z). griddata interpolates this surface at the points specified by (XI,YI) to produce ZI. The surface always passes through the data points. XI and YI usually form a uniform grid (as produced by meshgrid).

XI can be a row vector, in which case it specifies a matrix with constant columns. Similarly, YI can be a column vector, and it specifies a matrix with constant rows.

[XI,YI,ZI] = griddata(x,y,z,XI,YI) returns the interpolated matrix ZI as above, and also returns the matrices XI and YI formed from row vector XI and column vector yi. These latter are the same as the matrices returned by meshgrid.

 $[\ldots]$ = griddata $(\ldots,$ method) uses the specified interpolation method:

'linear' Triangle-based linear interpolation (default)

'cubic' Triangle-based cubic interpolation
'nearest' Nearest neighbor interpolation
'v4' MATLAB 4 griddata method

The method defines the type of surface fit to the data. The 'cubic' and 'v4' methods produce smooth surfaces while 'linear' and 'nearest' have discontinuities in the first and zero'th derivatives, respectively. All the methods except 'v4' are based on a Delaunay triangulation of the data. If method is [], then the default 'linear' method is used.

[...] = griddata(...,options) specifies a cell array of strings options that were previously used by Qhull. Qhull-specific options are no longer required and are currently ignored. Support for these options will be removed in a future release.

Occasionally, griddata might return points on or very near the convex hull of the data as NaNs. This is because roundoff in the computations sometimes makes it difficult to determine if a point near the boundary is in the convex hull.

griddata uses CGAL, see http://www.cgal.org.

Remarks

XI and YI can be matrices, in which case griddata returns the values for the corresponding points (XI(i,j),YI(i,j)). Alternatively, you can pass in the row and column vectors xi and yi, respectively. In this case, griddata interprets these vectors as if they were matrices produced by the command meshgrid(xi,yi).

Examples

Sample a function at 100 random points between ± 2.0 :


```
rand('seed',0)
x = rand(100,1)*4-2; y = rand(100,1)*4-2;
z = x.*exp(-x.^2-y.^2);
```

x, y, and z are now vectors containing nonuniformly sampled data. Define a regular grid, and grid the data to it:

```
ti = -2:.25:2;
[XI,YI] = meshgrid(ti,ti);
ZI = griddata(x,y,z,XI,YI);
```

Plot the gridded data along with the nonuniform data points used to generate it:

```
mesh(XI,YI,ZI), hold plot3(x,y,z,'o'), hold off
```



See Also delaunay, griddatan, interp2, meshgrid

Data gridding and hypersurface fitting for 3-D data

griddata3 will be removed in a future release. Use TriScatteredInterp instead.

Syntax

```
w = griddata3(x,y,z,v,xi,yi,zi)
w = griddata3(x,y,z,v,xi,yi,zi,method)
```

Description

w = griddata3(x,y,z,v,xi,yi,zi) fits a hypersurface of the form w = f(x, y, z) to the data in the (usually) nonuniformly spaced vectors (x, y, z, v). griddata3 interpolates this hypersurface at the points specified by (xi,yi,zi) to produce w. w is the same size as xi, yi, and zi.

(xi,yi,zi) is usually a uniform grid (as produced by meshgrid) and is where griddata3 gets its name.

w = griddata3(x,y,z,v,xi,yi,zi,method) defines the type of surface that is fit to the data, where method is either:

'linear' Tesselation-based linear interpolation (default)

'nearest' Nearest neighbor interpolation

If method is [], the default 'linear' method is used.

w = griddata3(...,options) specifies a cell array of strings options that were previously in Qhull. Qhull-specific options are no longer required and are currently ignored.

griddata3 uses CGAL, see http://www.cgal.org.

Examples

Create vectors x, y, and z containing nonuniformly sampled data:


```
x = gallery('uniformdata',[5000 1],0)-1;
y = gallery('uniformdata',[5000 1],1)-1;
z = gallery('uniformdata',[5000 1],2)-1;
v = x.^2 + y.^2 + z.^2;
```

Define a regular grid, and grid the data to it:

```
d = -0.8:0.05:0.8;
[xi,yi,zi] = meshgrid(d,d,d);
w = griddata3(x,y,z,v,xi,yi,zi);
```

Since it is difficult to visualize 4-D data sets, use isosurface at 0.8:

```
p = patch(isosurface(xi,yi,zi,w,0.8));
isonormals(xi,yi,zi,w,p);
set(p,'FaceColor','blue','EdgeColor','none');
view(3), axis equal, axis off, camlight, lighting phong
```



Data gridding and hypersurface fitting (dimension >= 2)

Syntax

```
yi = griddatan(x,y,xi)
yi = griddatan(x,y,xi,method)
yi = griddatan(x,y,xi,method,options)
```

Description

yi = griddatan(x,y,xi) fits a hyper-surface of the form y = f(x) to the data in the (usually) nonuniformly-spaced vectors (x, y). griddatan interpolates this hyper-surface at the points specified by xi to produce yi. xi can be nonuniform.

X is of dimension m-by-n, representing m points in n-dimensional space. y is of dimension m-by-1, representing m values of the hyper-surface f(X). xi is a vector of size p-by-n, representing p points in the n-dimensional space whose surface value is to be fitted. yi is a vector of length p approximating the values f(xi). The hypersurface always goes through the data points (X,y). xi is usually a uniform grid (as produced by meshgrid).

yi = griddatan(x,y,xi,method) defines the type of surface fit to the data, where 'method' is one of:

'linear' Tessellation-based linear interpolation (default)

'nearest' Nearest neighbor interpolation

All the methods are based on a Delaunay tessellation of the data.

If method is [], the default 'linear' method is used.

yi = griddatan(x,y,xi,method,options) specifies a cell array of strings options to be used in Qhull via delaunayn.

If options is [], the default options are used. If options is $\{'''\}$, no options are used, not even the default.


Examples

```
X=2*gallery('uniformdata',[5000 3],0)-1;;
Y = sum(X.^2,2);
d = -0.8:0.05:0.8;
```

```
[y0,x0,z0] = ndgrid(d,d,d);
XI = [x0(:) y0(:) z0(:)];
YI = griddatan(X,Y,XI);
```

Since it is difficult to visualize 4-D data sets, use isosurface at 0.8:

```
YI = reshape(YI, size(x0));
p = patch(isosurface(x0,y0,z0,YI,0.8));
isonormals(x0,y0,z0,YI,p);
set(p,'FaceColor','blue','EdgeColor','none');
view(3), axis equal, axis off, camlight, lighting phong
```



See Also

delaunayn, griddata, griddata3, meshgrid

Generalized singular value decomposition

Syntax

$$[U,V,X,C,S] = gsvd(A,B)$$

sigma = $gsvd(A,B)$

Description

[U,V,X,C,S] = gsvd(A,B) returns unitary matrices U and V, a (usually) square matrix X, and nonnegative diagonal matrices C and S so that

```
A = U*C*X'

B = V*S*X'

C'*C + S'*S = I
```

A and B must have the same number of columns, but may have different numbers of rows. If A is m-by-p and B is n-by-p, then U is m-by-m, V is n-by-n and X is p-by-q where q = min(m+n,p).

sigma = gsvd(A,B) returns the vector of generalized singular values, sqrt(diag(C'*C)./diag(S'*S)).

The nonzero elements of S are always on its main diagonal. If m >= p the nonzero elements of C are also on its main diagonal. But if m < p, the nonzero diagonal of C is diag(C,p-m). This allows the diagonal elements to be ordered so that the generalized singular values are nondecreasing.

gsvd(A,B,0), with three input arguments and either m or n >= p, produces the "economy-sized" decomposition where the resulting U and V have at most p columns, and C and S have at most p rows. The generalized singular values are diag(C)./diag(S).

When B is square and nonsingular, the generalized singular values, gsvd(A,B), are equal to the ordinary singular values, svd(A/B), but they are sorted in the opposite order. Their reciprocals are gsvd(B,A).

In this formulation of the gsvd, no assumptions are made about the individual ranks of A or B. The matrix X has full rank if and only if the matrix [A;B] has full rank. In fact, svd(X) and cond(X) are equal to svd([A;B]) and cond([A;B]). Other formulations, eg. G. Golub and

C. Van Loan [1], require that null(A) and null(B) do not overlap and replace X by inv(X) or inv(X').

Note, however, that when null(A) and null(B) do overlap, the nonzero elements of C and S are not uniquely determined.

Examples Example 1

The matrices have at least as many rows as columns.

The statement

$$[U,V,X,C,S] = gsvd(A,B)$$

produces a 5-by-5 orthogonal U, a 3-by-3 orthogonal V, a 3-by-3 nonsingular X,

and

Since A is rank deficient, the first diagonal element of C is zero.

The economy sized decomposition,

$$[U,V,X,C,S] = gsvd(A,B,0)$$

produces a 5-by-3 matrix U and a 3-by-3 matrix C.

The other three matrices, V, X, and S are the same as those obtained with the full decomposition.

The generalized singular values are the ratios of the diagonal elements of C and S.

5.0123

These values are a reordering of the ordinary singular values

```
svd(A/B)
ans =
     5.0123
     0.3325
     0.0000
```

Example 2

The matrices have at least as many columns as rows.

The statement

$$[U,V,X,C,S] = gsvd(A,B)$$

produces a 3-by-3 orthogonal $\rm U,\,a$ 5-by-5 orthogonal $\rm V,\,a$ 5-by-5 nonsingular $\rm X$ and

In this situation, the nonzero diagonal of C is diag(C,2). The generalized singular values include three zeros.

Reversing the roles of \boldsymbol{A} and \boldsymbol{B} reciprocates these values, producing two infinities.

```
gsvd(B,A)
ans =
1.0e+016 *
0.0000
0.0000
4.4126
Inf
Inf
```

Algorithm

The generalized singular value decomposition uses the C-S decomposition described in [1], as well as the built-in svd and qr functions. The C-S decomposition is implemented in a subfunction in the gsvd M-file.

Diagnostics

The only warning or error message produced by gsvd itself occurs when the two input arguments do not have the same number of columns.

See Also qr, svd

References [1] Golub, Gene H. and Charles Van Loan, *Matrix Computations*, Third

Edition, Johns Hopkins University Press, Baltimore, 1996

Test for greater than

Syntax

A > B gt(A, B)

Description

A > B compares each element of array A with the corresponding element of array B, and returns an array with elements set to logical 1 (true) where A is greater than B, or set to logical 0 (false) where A is less than or equal to B. Each input of the expression can be an array or a scalar value.

If both A and B are scalar (i.e., 1-by-1 matrices), then the MATLAB software returns a scalar value.

If both A and B are nonscalar arrays, then these arrays must have the same dimensions, and MATLAB returns an array of the same dimensions as A and B.

If one input is scalar and the other a nonscalar array, then the scalar input is treated as if it were an array having the same dimensions as the nonscalar input array. In other words, if input A is the number 100, and B is a 3-by-5 matrix, then A is treated as if it were a 3-by-5 matrix of elements, each set to 100. MATLAB returns an array of the same dimensions as the nonscalar input array.

gt(A, B) is called for the syntax A>B when either A or B is an object.

Examples

Create two 6-by-6 matrices, A and B, and locate those elements of A that are greater than the corresponding elements of B:

```
A = magic(6);
B = repmat(3*magic(3), 2, 2);
A > B
ans =
     1
                                 1
     0
            1
                   0
                          1
                                 1
                                        1
     1
            0
                   0
                                 0
                                        1
            1
     0
                   1
                          0
                                 1
                                        0
```

1 0 1 1 0 0 0 0 1 1 1 0 1

See Also 1t, ge, le, ne, eq, "Relational Operators"

Mouse placement of text in 2-D view

Syntax

```
gtext('string')
gtext({'string1','string2','string3',...})
gtext({'string1';'string2';'string3';...})
h = gtext(...)
```

Description

gtext displays a text string in the current figure window after you select a location with the mouse.

gtext('string') waits for you to press a mouse button or keyboard key while the pointer is within a figure window. Pressing a mouse button or any key places 'string' on the plot at the selected location.

gtext({'string1','string2','string3',...}) places all strings
with one click, each on a separate line.

gtext({'string1';'string2';'string3';...}) places one string
per click, in the sequence specified.

h = gtext(...) returns the handle to a text graphics object that is placed on the plot at the location you select.

Remarks

As you move the pointer into a figure window, the pointer becomes crosshairs to indicate that gtext is waiting for you to select a location. gtext uses the functions ginput and text.

Examples

Place a label on the current plot:

```
gtext('Note this divergence!')
```

See Also

ginput, text

"Annotating Plots" on page 1-97 for related functions

Store or retrieve GUI data

Syntax

guidata(object_handle,data)
data = guidata(object handle)

Description

guidata(object_handle,data) stores the variable data as GUI data. If object_handle is not a figure handle, then the object's parent figure is used. data can be any MATLAB variable, but is typically a structure, which enables you to add new fields as required.

guidata can manage only one variable at any time. Subsequent calls to guidata(object_handle,data) overwrite the previously created version of GUI data.

GUIDE Uses guidata

GUIDE uses guidata to store and maintain the handles structure. From a GUIDE-generated GUI code file, do *not* use guidata to store any data other than handles. If you do, you may overwrite the handles structure and your GUI will not work. If you need to store other data with your GUI, you can add new fields to the handles structure and place your data there. See GUI Data in the MATLAB documentation.

data = guidata(object_handle) returns previously stored data, or an empty matrix if nothing is stored.

To change the data managed by guidata:

- 1 Get a copy of the data with the command data =
 guidata(object_handle).
- **2** Make the desired changes to data.
- **3** Save the changed version of data with the command guidata(object_handle,data).

guidata provides application developers with a convenient interface to a figure's application data:

- You do not need to create and maintain a hard-coded property name for the application data throughout your source code.
- You can access the data from within a subfunction callback routine using the component's handle (which is returned by gcbo), without needing to find the figure's handle.

If you are not using GUIDE, guidata is particularly useful in conjunction with guihandles, which creates a structure containing the handles of all the components in a GUI.

Examples

This example calls guidata to save a structure containing a GUI figure's application data from within the initialization section of the application code file. The first section shows how to do this within a GUI you create manually. The second section shows how the code differs when you use GUIDE to create a template code file. GUIDE provides a handles structure as an argument to all subfunction callbacks, so you do not need to call guidata to obtain it. You do, however, need to call guidata to save changes you make to the structure.

Using guidata in a Programmed GUI

Calling the guihandles function creates the structure into which your code places additional data. It contains all handles used by the figure at the time it is called, generating field names based on each object's Tag property.

```
% Create figure to use as GUI in your main function or a subfunction
figure_handle = figure('Toolbar','none');
% create structure of handles
myhandles = guihandles(figure_handle);
% Add some additional data as a new field called numberOfErrors
myhandles.numberOfErrors = 0;
% Save the structure
guidata(figure_handle,myhandles)
```

You can recall the data from within a subfunction callback, modify it, and then replace the structure in the figure:

```
function My_Callback()
% ...
% Get the structure using guidata in the subfunction
myhandles = guidata(gcbo);
% Modify the value of your counter
myhandles.numberOfErrors = myhandles.numberOfErrors + 1;
% Save the change you made to the structure
guidata(gcbo,myhandles)
```

Using guidata in a GUIDE GUI

If you use GUIDE, you do not need to call guihandles to create a structure, because GUIDE generates a handles structure that contains the GUI's handles. You can add your own data to it, for example from within the OpeningFcn template that GUIDE creates:

```
% --- Executes just before simple_gui_tab is made visible.
function my_GUIDE_GUI_OpeningFcn(hObject, eventdata, handles, varargin)
% This function has no output args, see OutputFcn.
% hObject handle to figure
% eventdata reserved - to be defined in a future version of MATLAB
% handles structure with handles and user data (see GUIDATA)
% varargin command line arguments to simple_gui_tab (see VARARGIN)
% ...
% add some additional data as a new field called numberOfErrors
handles.numberOfErrors = 0;
% Save the change you made to the structure
guidata(hObject,handles)
```

Notice that you use the input argument hObject in place of gcbo to refer to the object whose callback is executing.

Suppose you needed to access the numberOfErrors field in a push button callback. Your callback code now looks something like this:

```
% --- Executes on button press in pushbutton1.
function my_GUIDE_GUI_pushbutton1_Callback(hObject, eventdata, handles)
% hObject handle to pushbutton1 (see GCBO)
% eventdata reserved - to be defined in a future version of MATLAB
% handles structure with handles and user data (see GUIDATA)
% ...
% No need to call guidata to obtain a structure;
% it is provided by GUIDE via the handles argument
handles.numberOfErrors = handles.numberOfErrors + 1;
% save the changes to the structure
guidata(hObject,handles)
```

See Also

guide, guihandles, getappdata, setappdata

Purpose Open GUI Layout Editor

Syntax guide

guide('filename.fig')
guide('fullpath')
guide(HandleList)

Description

guide initiates the GUI design environment (GUIDE) tools that allow you to create or edit GUIs interactively.

guide opens the GUIDE Quick Start dialog where you can choose to open a previously created GUI or create a new one using one of the provided templates.

guide('filename.fig') opens the FIG-file named filename.fig for editing if it is on the MATLAB path.

guide ('fullpath') opens the FIG-file at fullpath even if it is not on the MATLAB path.

guide(HandleList) opens the content of each of the figures in HandleList in a separate copy of the GUIDE design environment.

See Also inspect

Creating GUIs

guihandles

Purpose

Create structure of handles

Syntax

handles = guihandles(object_handle)

handles = quihandles

Description

handles = guihandles(object_handle) returns a structure containing the handles of the objects in a figure, using the value of their Tag properties as the fieldnames, with the following caveats:

- Objects are excluded if their Tag properties are empty, or are not legal variable names.
- If several objects have the same Tag, that field in the structure contains a vector of handles.
- Objects with hidden handles are included in the structure.

handles = guihandles returns a structure of handles for the current figure.

See Also

guidata, guide, getappdata, setappdata

Uncompress GNU zip files

Syntax

```
gunzip(files)
gunzip(files,outputdir)
gunzip(url, ...)
filenames = gunzip(...)
```

Description

gunzip(files) uncompresses GNU zip files from the list of files specified in files. Directories recursively gunzip all of their content. The output files have the same name, excluding the extension .gz, and are written to the same directory as the input files.

files is a string or cell array of strings containing a list of files or directories. Individual files that are on the MATLAB path can be specified as partial path names. Otherwise, an individual file can be specified relative to the current directory or with an absolute path.

Folders must be specified relative to the current folder or with absolute paths. On UNIX systems, folders can also start with ~/ or ~username/, which expands to the current user's home folder or the specified user's home folder, respectively. The wildcard character * can be used when specifying files or folders, except when relying on the MATLAB path to resolve a file name or partial path name.

gunzip(files, outputdir) writes the gunzipped file into the directory outputdir. If outputdir does not exist, MATLAB creates it.

gunzip(url, ...) extracts the GNU zip contents from an Internet universal resource locator (URL). The URL must include the protocol type (for example, 'http://'). MATLAB downloads the URL to the temp directory, and then deletes it.

filenames = gunzip(...) gunzips the files and returns the relative path names of the gunzipped files in the string cell array filenames.

Examples

To gunzip all .gz files in the current directory, type:

```
gunzip('*.gz');
```

To gunzip Cleve Moler's "Numerical Computing with MATLAB" examples to the output directory ncm, type:

```
url ='http://www.mathworks.com/moler/ncm.tar.gz';
gunzip(url,'ncm')
untar('ncm/ncm.tar','ncm')
```

See Also

gzip, tar, untar, unzip, zip

Compress files into GNU zip files

Syntax

```
gzip(files)
gzip(files,outputdir)
filenames = gzip(...)
```

Description

gzip(files) creates GNU zip files from the list of files specified in files. Directories recursively gzip all their contents. Each output gzipped file is written to the same directory as the input file and with the file extension .gz.

files is a string or cell array of strings containing a list of files or directories to gzip. Individual files that are on the MATLAB path can be specified as partial path names. Otherwise, an individual file can be specified relative to the current directory or with an absolute path.

Folders must be specified relative to the current folder or with absolute paths. On UNIX systems, folders can also start with ~/ or ~username/, which expands to the current user's home folder or the specified user's home folder, respectively. The wildcard character * can be used when specifying files or folders, except when relying on the MATLAB path to resolve a file name or partial path name.

gzip(files,outputdir) writes the gzipped files into the directory outputdir. If outputdir does not exist, MATLAB creates it.

filenames = gzip(...) gzips the files and returns the relative path names of all gzipped files in the string cell array filenames.

Example

To gzip all .m and .mat files in the current directory and store the results in the directory archive, type:

```
gzip({'*.m','*.mat'},'archive');
```

See Also

gunzip, tar, untar, unzip, zip

hadamard

Purpose Hadamard matrix

Syntax H = hadamard(n)

Description H = hadamard(n) returns the Hadamard matrix of order n.

Definition Hadamard matrices are matrices of 1's and -1's whose columns are orthogonal,

H'*H = n*I

where $[n \ n]$ =size(H) and I = eye(n,n),.

They have applications in several different areas, including combinatorics, signal processing, and numerical analysis, [1], [2].

An n-by-n Hadamard matrix with n > 2 exists only if rem(n,4) = 0. This function handles only the cases where n, n/12, or n/20 is a power of 2.

Examples The command hadamard (4) produces the 4-by-4 matrix:

1 1 1 1 1 -1 1 -1 1 1 -1 -1 1 -1 -1 1

See Also compan, hankel, toeplitz

References [1] Ryser, H. J., *Combinatorial Mathematics*, John Wiley and Sons, 1963.

[2] Pratt, W. K., Digital Signal Processing, John Wiley and Sons, 1978.

Abstract class for deriving handle classes

Syntax

classdef myclass < handle</pre>

Description

The handle class is the superclass for all classes that follow handle semantics. A handle is a reference to an object. If you copy an object's handle, MATLAB copies only the handle and both the original and copy refer to the same object data. If a function modifies a handle object passed as an input argument, the modification affects the original object. See "Passing Objects to Functions" for information on passing objects to functions.

Handle object behavior is equivalent to that of Handle Graphics objects, where the handle of a graphics object always refers to a particular object regardless of whether you save the handle when you create the object, store it in another variable, or obtain it with convenience functions like findobj or gca.

If you want to create a class that defines events, you must derive that class from the handle class.

The handle class is an abstract class so you cannot create an instance of this class directly. You use the handle class to derive other classes, which can be concrete classes whose instances are handle objects. See "Value or Handle Class — Which to Use" for information on using handle classes.

classdef myclass < handle makes myclass a subclass of the handle class.

Handle Class Methods

When you derive a class from the handle class, your class inherits the following methods.

handle

Method	Purpose	
addlistener	Creates a listener for the specified event and assigns a callback function to execute when the event occurs.	
notify	Broadcast a notice that a specific event is occurring on a specified handle object or array of handle objects.	
delete	Handle object destructor method that is called when the object's lifecycle ends.	
disp	Handle object disp method which is called by the display method. See the MATLAB disp function.	
display	Handle object display method called when MATLAB software interprets an expression returning a handle object that is not terminated by a semicolon. See the MATLAB display function.	
findobj	Finds objects matching the specified conditions from the input array of handle objects	
findprop	Returns a meta.property objects associated with the specified property name.	
fields	Returns a cell array of string containing the names of public properties.	
fieldnames	Returns a cell array of string containing the names of public properties. See the MATLAB fieldnames function.	
isvalid	Returns a logical array in which elements are true if the corresponding elements in the input array are valid handles. This method is Sealed so you cannot override it in a handle subclass.	

Method	Purpose
eq ne lt le gt ge relationaloper	Relational functions return a logical array of the same size as the pair of input handle object arrays. Comparisons use a number associated with each handle. You can assume that the same two handles will compare as equal and the repeated comparison of any two handles will yield the same result in the same MATLAB session. *19ff*erent handles are always not-equal. The order of handles is purely arbitrary, but consistent.
ctranspose transpose	Transposes the elements of the handle object array.
permute	Rearranges the dimensions of the handle object array. See the MATLAB permute function.
reshape	Changes the dimensions of the handle object array to the specified dimensions. See the MATLAB reshape function.
sort	Sort the handle objects in any array in ascending or descending order. The order of handles is purely arbitrary, but reproducible in a given MATLAB session. See the MATLAB sort function.

Handle Class Events

The handle class defines one event:

ObjectBeingDestroyed

This event is triggered when the handle object is about to be destroyed. If you define a listener for this event, its callback executes before the handle object is destroyed.

You can add a listener for this event using the addlistener method. See "Defining Events and Listeners — Syntax and Techniques" for more information on using events and listeners.

Handle Subclasses

There are two abstract handle subclasses that you can use to derive handle classes:

- hgsetget use when you want to create a handle class that inherits set and get methods having the same behavior as Handle Graphics set and get functions.
- dynamicprops use when you want to create a handle class that allows you to add instance data (dynamically defined properties) to objects.

Useful Functions

- properties list the class public properties
- methods list the class methods
- events list the events defined by the class

Note that ishandle does not test for handle class objects. Use isa instead.

Hankel matrix

Syntax

H = hankel(c)
H = hankel(c,r)

Description

H = hankel(c) returns the square Hankel matrix whose first column is c and whose elements are zero below the first anti-diagonal.

H = hankel(c,r) returns a Hankel matrix whose first column is c and whose last row is r. If the last element of c differs from the first element of r, the last element of c prevails.

Definition

A Hankel matrix is a matrix that is symmetric and constant across the anti-diagonals, and has elements h(i,j) = p(i+j-1), where vector $p = [c \ r(2:end)]$ completely determines the Hankel matrix.

Examples

A Hankel matrix with anti-diagonal disagreement is

See Also

hadamard, toeplitz, kron

Summary of MATLAB HDF4 capabilities

Description

The MATLAB software provides a set of low-level functions that enable you to access the HDF4 library developed by the National Center for Supercomputing Applications (NCSA). For information about HDF4, go to the HDF Web page at http://www.hdfgroup.org.

Note For information about MATLAB HDF5 capabilities, which is a completely separate, incompatible format, see hdf5.

The following table lists all the HDF4 application programming interfaces (APIs) supported by MATLAB with the name of the MATLAB function used to access the API. To use these functions, you must be familiar with the HDF library. For more information about using these MATLAB functions, see "Importing Scientific Data Files" and "Exporting to Scientific Data Files".

Application Programming Interface	Description	MATLAB Function
Annotations	Stores, manages, and retrieves text used to describe an HDF file or any of the data structures contained in the file.	hdfan
General Raster Images	Stores, manages, and retrieves raster images, their dimensions and palettes. It can also manipulate unattached palettes. Note: Use the MATLAB functions imread and imwrite with HDF raster image formats.	hdfdf24, hdfdfr8

Application Programming Interface	Description	MATLAB Function
HDF-EOS	Provides functions to read HDF-EOS grid (GD), point (PT), and swath (SW) data.	hdfgd, hdfpt, hdfsw
HDF Utilities	Provides functions to open and close HDF files and handle errors.	hdfh, hdfhd, hdfhe
MATLAB HDF Utilities	Provides utility functions that help you work with HDF files in the MATLAB environment.	hdfml
Scientific Data	Stores, manages, and retrieves multidimensional arrays of character or numeric data, along with their dimensions and attributes.	hdfsd
V Groups	Creates and retrieves groups of other HDF data objects, such as raster images or V data.	hdfv
V Data	Stores, manages, and retrieves multivariate data stored as records in a table.	hdfvf, hdfvh, hdfvs

For copyright information, see the hdf4copyright.txt file.

See Also hdfinfo,hdfread, hdftool, imread

Summary of MATLAB HDF5 capabilities

Description

The MATLAB software provides both high-level and low-level access to HDF5 files. The high-level access functions make it easy to read a data set from an HDF5 file or write a variable from the MATLAB workspace into an HDF5 file. The MATLAB low-level interface provides direct access to the more than 300 functions in the HDF5 library.

Note For information about MATLAB HDF4 capabilities, which is a completely separate, incompatible format, see hdf.

The following sections provide an overview of both this high- and low-level access. To use these MATLAB functions, you must be familiar with HDF5 programming concepts and, when using the low-level functions, details about the functions in the library. To get this information, go to the HDF Web page at http://www.hdfgroup.org.

High-level Access

MATLAB includes three functions that provide high-level access to HDF5 files:

- hdf5info
- hdf5read
- hdf5write

Using these functions you can read data and metadata from an HDF5 file and write data from the MATLAB workspace to a file in HDF5 format. For more information about these functions, see their individual reference pages.

Low-level Access

MATLAB provides direct access to the over 200 functions in the HDF5 Library. Using these functions, you can read and write complex

datatypes, utilize HDF5 data subsetting capabilities, and take advantage of other features present in the HDF5 library.

The HDF5 library organizes the routines in the library into interfaces. MATLAB organizes the corresponding MATLAB functions into packages that match these HDF5 library interfaces. For example, the MATLAB functions for the HDF5 Attribute Interface are in the H5A package.

The following table lists all the HDF5 library interfaces in alphabetical order by name. The following table lists all the HDF5 library interfaces with their associated MATLAB package.

HDF5 Library Interface	MATLAB Package Name	Description
Library	H5	General-purpose functions for use with the entire HDF5 library, such as initialization
Attribute	Н5А	Manipulate metadata associated with data sets or groups
Dataset	H5D	Manipulate multidimensional arrays of data elements, together with supporting metadata
Dimension Scale	H5DS	Manipulate dimension scale associated with dataset dimensions
Error	H5E	Handle errors
File	H5F	Access files
Group	H5G	Organize objects in a file; analogous to a directory structure
Identifier	H5I	Manipulate HDF5 object identifiers
Link	H5L	Manipulate links in a file

HDF5 Library Interface	MATLAB Package Name	Description
MATLAB	H5ML	MATLAB utility functions that are not part of the HDF5 library itself.
Object	H50	Manipulate objects in a file
Property	H5P	Manipulate object property lists
Reference	H5R	Manipulate HDF5 references, which are like UNIX links or Windows shortcuts
Dataspace	H5S	Define and work with data spaces, which describe the dimensionality of a data set
Datatype	H5T	Define the type of variable that is stored in a data set
Filters and Compression	H5Z	Create inline data filters and data compression

In most cases, the syntax of the MATLAB function is identical to the syntax of the HDF5 library function. To get detailed information about the MATLAB syntax of an HDF5 library function, view the help for the individual MATLAB function, as follows:

help H5F.open

To view a list of all the MATLAB HDF5 functions in a particular interface, type:

help H5F

See Also

hdf, hdf5info, hdf5read, hdf5write

Information about HDF5 file

Syntax

```
fileinfo = hdf5info(filename)
fileinfo = hdf5info(..., 'ReadAttributes', BOOL)
[...] = hdf5info(..., 'V71Dimensions', BOOL)
```

Description

fileinfo = hdf5info(filename) returns a structure fileinfo whose fields contain information about the contents of the HDF5 file filename. filename is a string that specifies the name of the HDF5 file.

fileinfo = hdf5info(..., 'ReadAttributes', BOOL) specifies whether hdf5info returns the values of the attributes or just information describing the attributes. By default, hdf5info reads in attribute values (BOOL = true).

[...] = hdf5info(..., 'V71Dimensions', B00L) specifies whether to report the dimensions of data sets and attributes as they were returned in previous versions of hdf5info (MATLAB 7.1 [R14SP3] and earlier). If B00L is true, hdf5info swaps the first two dimensions of the data set. This behavior was intended to account for the difference in how HDF5 and MATLAB express array dimenions. HDF5 describes data set dimensions in row-major order; MATLAB stores data in column-major order. However, swapping these dimensions may not correctly reflect the intent of the data in the file and may invalidate metadata. When B00L is false (the default), hdf5info returns data dimensions that correctly reflect the data ordering as it is written in the file—each dimension in the output variable matches the same dimension in the file.

Note If you use the 'V71Dimensions' parameter and intend on passing the fileinfo structure returned to the hdf5read function, you should also specify the 'V71Dimensions' parameters with hdf5read. If you do not, hdf5read uses the new behavior when reading the data set and certain metadata returned by hdf5info does not match the actual data returned by hdf5read.

Examples

To get more information about the contents of the HDF5 file, look at the GroupHierarchy field in the fileinfo structure returned by hdf5info.

```
toplevel = fileinfo.GroupHierarchy
toplevel =
    Filename: [1x64 char]
        Name: '/'
        Groups: [1x2 struct]
        Datasets: []
        Datatypes: []
        Links: []
        Attributes: [1x2 struct]
```

To probe further into the file hierarchy, keep examining the Groups field.

See also

hdf5read, hdf5write

Read HDF5 file

Syntax

```
data = hdf5read(filename,datasetname)
attr = hdf5read(filename,attributename)
[data, attr] = hdf5read(..., 'ReadAttributes',BOOL)
data = hdf5read(hinfo)
[...] = hdf5read(..., 'V71Dimensions', BOOL)
```

Description

data = hdf5read(filename,datasetname) reads all the data in the data set datasetname that is stored in the HDF5 file filename and returns it in the variable data. To determine the names of data sets in an HDF5 file, use the hdf5info function.

The return value, data, is a multidimensional array. hdf5read maps HDF5 data types to native MATLAB data types, whenever possible. If it cannot represent the data using MATLAB data types, hdf5read uses one of the HDF5 data type objects. For example, if an HDF5 file contains a data set made up of an enumerated data type, hdf5read uses the hdf5.h5enum object to represent the data in the MATLAB workspace. The hdf5.h5enum object has data members that store the enumerations (names), their corresponding values, and the enumerated data. For more information about the HDF5 data type objects, see the hdf5 reference page.

Note hdf5read performs best when reading numeric datasets. If you need to read string, compound, or variable length datasets, The MathWorks strongly recommends that you use the low-level HDF5 interface function, H5D.read. To read a subset of a dataset, you must use the low-level interface.

attr = hdf5read(filename,attributename) reads all the metadata in the attribute attributename, stored in the HDF5 file filename, and returns it in the variable attr. To determine the names of attributes in an HDF5 file, use the hdf5info function.

[data, attr] = hdf5read(..., 'ReadAttributes', BOOL) reads all the data, as well as all of the associated attribute information contained within that data set. By default, BOOL is false.

data = hdf5read(hinfo) reads all of the data in the data set specified in the structure hinfo and returns it in the variable data. The hinfo structure is extracted from the output returned by hdf5info, which specifies an HDF5 file and a specific data set.

[...] = hdf5read(..., 'V71Dimensions', B00L) specifies whether to change the majority of data sets read from the file. If B00L is true, hdf5read permutes the first two dimensions of the data set, as it did in previous releases (MATLAB 7.1 [R14SP3] and earlier). This behavior was intended to account for the difference in how HDF5 and MATLAB express array dimensions. HDF5 describes data set dimensions in row-major order; MATLAB stores data in column-major order. However, permuting these dimensions may not correctly reflect the intent of the data and may invalidate metadata. When B00L is false (the default), the data dimensions correctly reflect the data ordering as it is written in the file — each dimension in the output variable matches the same dimension in the file.

Examples

Use hdf5info to get information about an HDF5 file and then use hdf5read to read a data set, using the information structure (hinfo) returned by hdf5info to specify the data set.

```
hinfo = hdf5info('example.h5');
dset = hdf5read(hinfo.GroupHierarchy.Groups(2).Datasets(1));
```

See Also

hdf5, hdf5info, hdf5write

Write data to file in HDF5 format

Syntax

Description

hdf5write(filename,location,dataset) writes the data dataset to the HDF5 file, filename. If filename does not exist, hdf5write creates it. If filename exists, hdf5write overwrites the existing file, by default, but you can also append data to an existing file using an optional syntax.

location defines where to write the data set in the file. HDF5 files are organized in a hierarchical structure similar to a UNIX directory structure. location is a string that resembles a UNIX path.

hdf5write maps the data in dataset to HDF5 data types according to rules outlined below.

hdf5write(filename,details,dataset) writes dataset to filename using the values in the details structure. For a data set, the details structure can contain the following fields.

Field Name	Description	Data Type
Location	Location of the data set in the file	Character array
Name	Name to attach to the data set	Character array

hdf5write(filename,details,attribute) writes the metadata attribute to filename using the values in the details structure. For an attribute, the details structure can contain following fields.

Field Name	Description	Data Type
AttachedTo	Location of the object this attribute modifies	Structure array
AttachType	Identifies what kind of object this attribute modifies; possible values are 'group' and 'dataset'	Character array
Name	Name to attach to the data set	Character array

hdf5write(filename, details1, dataset1, details2, dataset2,...) writes multiple data sets and associated attributes to filename in one operation. Each data set and attribute must have an associated details structure.

hdf5write(filename,...,'WriteMode',mode,...) specifies whether hdf5write overwrites the existing file (the default) or appends data sets and attributes to the file. Possible values for mode are 'overwrite' and 'append'.

hdf5write(..., 'V71Dimensions', B00L) specifies whether to change the majority of data sets written to the file. If B00L is true, hdf5write permutes the first two dimensions of the data set, as it did in previous releases (MATLAB 7.1 [R14SP3] and earlier). This behavior was intended to account for the difference in how HDF5 and MATLAB express array dimensions. HDF5 describes data set dimensions in row-major order; MATLAB stores data in column-major order. However, permuting these dimensions may not correctly reflect the intent of the data and may invalidate metadata. When B00L is false (the default), the data written to the file correctly reflects the data ordering of the data sets — each dimension in the file's data sets matches the same dimension in the corresponding MATLAB variable.

Data Type Mappings

The following table lists how hdf5write maps the data type from the workspace into an HDF5 file. If the data in the workspace that is being written to the file is a MATLAB data type, hdf5write uses the following rules when translating MATLAB data into HDF5 data objects.

MATLAB Data Type	HDF5 Data Set or Attribute	
Numeric	Corresponding HDF5 native data type. For example, if the workspace data type is uint8, the hdf5write function writes the data to the file as 8-bit integers. The size of the HDF5 dataspace is the same size as the MATLAB array.	
String	Single, null-terminated string	
Cell array of strings	Multiple, null-terminated strings, each the same length. Length is determined by the length of the longest string in the cell array. The size of the HDF5 dataspace is the same size as the cell array.	
Cell array of numeric data	Numeric array, the same dimensions as the cell array. The elements of the array must all have the same size and type. The data type is determined by the first element in the cell array.	
Structure array	HDF5 compound type. Individual fields in the structure employ the same data translation rules for individual data types. For example, a cell array of strings becomes a multiple, null-terminated strings.	
HDF5 objects	If the data being written to the file is composed of HDF5 objects, hdf5write uses the same data type when writing to the file. For all HDF5 objects, except HDF5.h5enum objects, the dataspace has the same dimensions as the array of HDF5 objects passed to the function. For HDF5.h5enum objects, the size and dimensions of the data set in the HDF5 file is the same as the object's Data field.	

Examples

Write a 5-by-5 data set of uint8 values to the root group.

hdf5write('myfile.h5', '/dataset1', uint8(magic(5)))

```
Write a 2-by-2 string data set in a subgroup.
  dataset = {'north', 'south'; 'east', 'west'};
  hdf5write('myfile2.h5', '/group1/dataset1.1', dataset);
Write a data set and attribute to an existing group.
  dset = single(rand(10,10));
  dset details.Location = '/group1/dataset1.2';
  dset details.Name = 'Random';
  attr = 'Some random data';
  attr details.Name = 'Description';
  attr details.AttachedTo = '/group1/dataset1.2/Random';
  attr details.AttachType = 'dataset';
  hdf5write('myfile2.h5', dset details, dset, ...
              attr details, attr, 'WriteMode', 'append');
Write a data set using objects.
  dset = hdf5.h5array(magic(5));
  hdf5write('myfile3.h5', '/g1/objects', dset);
hdf5, hdf5read, hdf5info
```

See Also

Purpose Information about HDF4 or HDF-EOS file

Syntax S = hdfinfo(filename)

S = hdfinfo(filename, mode)

Description

S = hdfinfo(filename) returns a structure S whose fields contain information about the contents of an HDF4 or HDF-EOS file. filename is a string that specifies the name of the HDF4 file.

S = hdfinfo(filename, mode) reads the file as an HDF4 file, if mode is 'hdf', or as an HDF-EOS file, if mode is 'eos'. If mode is 'eos', only HDF-EOS data objects are queried. To retrieve information on the entire contents of a file containing both HDF4 and HDF-EOS objects, mode must be 'hdf'.

Note hdfinfo can be used on Version 4.x HDF files or Version 2.x HDF-EOS files. To get information about an HDF5 file, use hdf5info.

The set of fields in the returned structure S depends on the individual file. Fields that can be present in the S structure are shown in the following table.

Mode	Field Name	Description	Return Type
HDF	Attributes	Attributes of the data set	Structure array
	Description	Annotation description	Cell array
	Filename	Name of the file	String
	Label	Annotation label	Cell array
	Raster8	Description of 8-bit raster images	Structure array

Mode	Field Name	Description	Return Type
	Raster24	Description of 24-bit raster images	Structure array
	SDS	Description of scientific data sets	Structure array
	Vdata	Description of Vdata sets	Structure array
	Vgroup	Description of Vgroups	Structure array
EOS	Filename	Name of the file	String
	Grid	Grid data	Structure array
	Point	Point data	Structure array
	Swath	Swath data	Structure array

Those fields in the table above that contain structure arrays are further described in the tables shown below.

Fields Common to Returned Structure Arrays

Structure arrays returned by hdfinfo contain some common fields. These are shown in the table below. Not all structure arrays will contain all of these fields.

Field Name	Description	Data Type
Attributes	Data set attributes. Contains fields Name and Value.	Structure array
Description	Annotation description	Cell array
Filename	Name of the file	String
Label	Annotation label	Cell array

Field Name	Description	Data Type
Name	Name of the data set	String
Rank	Number of dimensions of the data set	Double
Ref	Data set reference number	Double
Туре	Type of HDF or HDF-EOS object	String

Fields Specific to Certain Structures

Structure arrays returned by hdfinfo also contain fields that are unique to each structure. These are shown in the tables below.

Fields of the Attribute Structure

Field Name	Description	Data Type
Name	Attribute name	String
Value	Attribute value or description	Numeric or string

Fields of the Raster8 and Raster24 Structures

Field Name	Description	Data Type
HasPalette	1 (true) if the image has an associated palette, otherwise 0 (false) (8-bit only)	Logical
Height	Height of the image, in pixels	Number
Interlace	Interlace mode of the image (24-bit only)	String
Name	Name of the image	String
Width	Width of the image, in pixels	Number

hdfinfo

Fields of the SDS Structure

Field Name	Description	Data Type
DataType	Data precision	String
Dims	Dimensions of the data set. Contains fields Name, DataType, Size, Scale, and Attributes. Scale is an array of numbers to place along the dimension and demarcate intervals in the data set.	Structure array
Index	Index of the SDS	Number

Fields of the Vdata Structure

Field Name	Description	Data Type
DataAttributes	Attributes of the entire data set. Contains fields Name and Value.	Structure array
Class	Class name of the data set	String
Fields	Fields of the Vdata. Contains fields Name and Attributes.	Structure array
NumRecords	Number of data set records	Double
IsAttribute	1 (true) if Vdata is an attribute, otherwise 0 (false)	Logical

Fields of the Vgroup Structure

Field Name	Description	Data Type
Class	Class name of the data set	String
Raster8	Description of the 8-bit raster image	Structure array
Raster24	Description of the 24-bit raster image	Structure array
SDS	Description of the Scientific Data sets	Structure array
Tag	Tag of this Vgroup	Number
Vdata	Description of the Vdata sets	Structure array
Vgroup	Description of the Vgroups	Structure array

Fields of the Grid Structure

Field Name	Description	Data Type
Columns	Number of columns in the grid	Number
DataFields	Description of the data fields in each Grid field of the grid. Contains fields Name, Rank, Dims, NumberType, FillValue, and TileDims.	Structure array
LowerRight	Lower right corner location, in meters	Number
Origin Code	Origin code for the grid	Number
PixRegCode	Pixel registration code	Number

hdfinfo

Fields of the Grid Structure (Continued)

Field Name	Description	Data Type
Projection	Projection code, zone code, sphere code, and projection parameters of the grid. Contains fields ProjCode, ZoneCode, SphereCode, and ProjParam.	Structure
Rows	Number of rows in the grid	Number
UpperLeft	Upper left corner location, in meters	Number

Fields of the Point Structure

Field Name	Description	Data Type
Level	Description of each level of the point. Contains fields Name, NumRecords, FieldNames, DataType, and Index.	Structure

Fields of the Swath Structure

Field Name	Description	Data Type
DataFields	Data fields in the swath. Contains fields Name, Rank, Dims, NumberType, and FillValue.	Structure array

Fields of the Swath Structure (Continued)

Field Name	Description	Data Type
GeolocationFie	l Ge olocation fields in the swath. Contains fields Name, Rank, Dims, NumberType, and FillValue.	Structure array
IdxMapInfo	Relationship between indexed elements of the geolocation mapping. Contains fields Map and Size.	Structure
MapInfo	Relationship between data and geolocation fields. Contains fields Map, Offset, and Increment.	Structure

Examples

To retrieve information about the file example.hdf,

```
fileinfo = hdfinfo('example.hdf')
fileinfo =
    Filename: 'example.hdf'
        SDS: [1x1 struct]
    Vdata: [1x1 struct]
```

And to retrieve information from this about the scientific data set in example.hdf,

hdfinfo

```
Rank: 2
DataType: 'int16'
Attributes: []
Dims: [2x1 struct]
Label: {}
Description: {}
Index: 0
```

See Also hdfread, hdf

Purpose

Read data from HDF4 or HDF-EOS file

Syntax

```
data = hdfread(filename, datasetname)
data = hdfread(hinfo.fieldname)
```

data = hdfread(...,param1,value1,param2,value2,...)

[data,map] = hdfread(...)

Description

data = hdfread(filename, datasetname) returns all the data in the data set specified by datasetname from the HDF4 or HDF-EOS file specified by filename. To determine the name of a data set in an HDF4 file, use the hdfinfo function.

Note hdfread can be used on Version 4.x HDF files or Version 2.x HDF-EOS files. To read data from and HDF5 file, use hdf5read.

data = hdfread(hinfo.fieldname) returns all the data in the data set specified by hinfo.fieldname, where hinfo is the structure returned by the hdfinfo function and fieldname is the name of a field in the structure that relates to a particular type of data set. For example, to read an HDF scientific data set, specify the SDS field, as in hinfo.SDS. To read HDF V data, specify the Vdata field, as in hinfo.Vdata. hdfread can get the name of the HDF file from these structures.

data = hdfread(...,param1,value1,param2,value2,...) returns subsets of the data according to the specified parameter and value pairs. See the tables below to find the valid parameters and values for different types of data sets.

[data,map] = hdfread(...) returns the image data and the colormap map for an 8-bit raster image.

Subsetting Parameters

The following tables show the subsetting parameters that can be used with the hdfread function for certain types of HDF4 data. These data types are

hdfread

- HDF Scientific Data (SD)
- HDF Vdata (V)
- HDF-EOS Grid Data
- HDF-EOS Point Data
- HDF-EOS Swath Data

Note the following:

• If a parameter requires multiple values, the values must be stored in a cell array. For example, the 'Index' parameter requires three values: start, stride, and edge. Enclose these values in curly braces as a cell array.

hdfread(dataset name, 'Index', {start,stride,edge})

• All values that are indices are 1-based.

Subsetting Parameters for HDF Scientific Data (SD) Data Sets

When you are working with HDF SD files, hdfread supports the parameters listed in this table.

Parameter	Description
'Index'	Three-element cell array, {start,stride,edge}, specifying the location, range, and values to be read from the data set
	• start — A 1-based array specifying the position in the file to begin reading
	Default: 1, start at the first element of each dimension. The values specified must not exceed the size of any dimension of the data set.
	• stride — A 1-based array specifying the interval between the values to read
	Default: 1, read every element of the data set.

Parameter	Description
	edge — A 1-based array specifying the length of each dimension to read
	Default: An array containing the lengths of the corresponding dimensions

For example, this code reads the data set Example SDS from the HDF file example.hdf. The 'Index' parameter specifies that hdfread start reading data at the beginning of each dimension, read until the end of each dimension, but only read every other data value in the first dimension.

```
data = hdfread('example.hdf', 'Example SDS', 'Index', {[], [2 1], []})
```

Subsetting Parameters for HDF Vdata Sets

When you are working with HDF Vdata files, hdfread supports these parameters.

Parameter	Description
'Fields'	Text string specifying the name of the field to be read. When specifying multiple field names, use a cell array.
'FirstRecord'	1-based number specifying the record from which to begin reading
'NumRecords'	Number specifying the total number of records to read

For example, this code reads the Vdata set Example Vdata from the HDF file example.hdf.

```
data = hdfread('example.hdf', 'Example Vdata', 'FirstRecord', 2, 'NumRecords', 5)
```

Subsetting Parameters for HDF-EOS Grid Data

When you are working with HDF-EOS grid data, hdfread supports three types of parameters:

• Required parameters

hdfread

- Optional parameters
- Mutually exclusive parameters You can only specify one of these parameters in a call to hdfread, and you cannot use these parameters in combination with any optional parameter.

Parameter	Description	
Required Paramet	Required Parameter	
'Fields'	String specifying the field to be read. You can specify only one field name for a Grid data set.	
Mutually Exclusive	e Optional Parameters	
'Index'	Three-element cell array, {start,stride,edge}, specifying the location, range, and values to be read from the data set	
	start — An array specifying the position in the file to begin reading	
	Default: 1, start at the first element of each dimension. The values must not exceed the size of any dimension of the data set.	
	stride — An array specifying the interval between the values to read	
	Default: 1, read every element of the data set.	
	edge — An array specifying the length of each dimension to read	
	Default: An array containing the lengths of the corresponding dimensions	
'Interpolate'	Two-element cell array, {longitude,latitude}, specifying the longitude and latitude points that define a region for bilinear interpolation. Each element is an N-length vector specifying longitude and latitude coordinates.	

Parameter	Description	
'Pixels'	Two-element cell array, {longitude,latitude}, specifying the longitude and latitude coordinates that define a region. Each element is an N-length vector specifying longitude and latitude coordinates. This region is converted into pixel rows and columns with the origin in the upper left corner of the grid.	
	Note: This is the pixel equivalent of reading a 'Box' region.	
'Tile'	Vector specifying the coordinates of the tile to read, for HDF-EOS Grid files that support tiles	
Optional Paramet	Optional Parameters	
'Box'	Two-element cell array, {longitude,latitude}, specifying the longitude and latitude coordinates that define a region. longitude and latitude are each two-element vectors specifying longitude and latitude coordinates.	
'Time'	Two-element cell array, [start stop], where start and stop are numbers that specify the start and end-point for a period of time	
'Vertical'	Two-element cell array, {dimension, range}	
	dimension — String specifying the name of the data set field to be read from. You can specify only one field name for a Grid data set.	
	range — Two-element array specifying the minimum and maximum range for the subset. If dimension is a dimension name, then range specifies the range of elements to extract. If dimension is a field name, then range specifies the range of values to extract.	
	'Vertical' subsetting can be used alone or in conjunction with 'Box' or 'Time'. To subset a region along multiple dimensions, vertical subsetting can be used up to eight times in one call to hdfread.	

For example,

hdfread(grid_dataset, 'Fields', fieldname, 'Vertical', {dimension, [min, max]})

Subsetting Parameters for HDF-EOS Point Data

When you are working with HDF-EOS Point data, hdfread has two required parameters and three optional parameters.

Parameter	Description
Required Parameters	
'Fields'	String naming the data set field to be read. For multiple field names, use a comma-separated list.
'Level'	1-based number specifying which level to read from in an HDF-EOS Point data set
Optional Parameters	
'Box'	Two-element cell array, {longitude,latitude}, specifying the longitude and latitude coordinates that define a region. longitude and latitude are each two-element vectors specifying longitude and latitude coordinates.
'RecordNumbers'	Vector specifying the record numbers to read
'Time'	Two-element cell array, [start stop], where start and stop are numbers that specify the start and endpoint for a period of time

For example,

```
hdfread(point_dataset, 'Fields', {field1, field2},...
'Level', level, 'RecordNumbers', [1:50, 200:250])
```

Subsetting Parameters for HDF-EOS Swath Data

When you are working with HDF-EOS Swath data, hdfread supports three types of parameters:

- Required parameters
- Optional parameters
- Mutually exclusive

You can only use one of the mutually exclusive parameters in a call to hdfread, and you cannot use these parameters in combination with any optional parameter.

Parameter	Description	
Required Paramete	Required Parameter	
'Fields'	String naming the data set field to be read. You can specify only one field name for a Swath data set.	
Mutually Exclusive	Optional Parameters	
'Index'	Three-element cell array, {start,stride,edge}, specifying the location, range, and values to be read from the data set	
	• start — An array specifying the position in the file to begin reading	
	Default: 1, start at the first element of each dimension. The values must not exceed the size of any dimension of the data set.	
	• stride — An array specifying the interval between the values to read	
	Default: 1, read every element of the data set.	
	• edge — An array specifying the length of each dimension to read	
	Default: An array containing the lengths of the corresponding dimensions	
'Time'	Three-element cell array, {start, stop, mode}, where start and stop specify the beginning and the endpoint for a period of time, and mode is a string defining the criterion for the inclusion of a cross track in a region. The cross track is within a region if any of these conditions is met:	
	• Its midpoint is within the box (mode='midpoint').	
	• Either endpoint is within the box (mode='endpoint').	
	• Any point is within the box (mode='anypoint').	

hdfread

Parameter	Description	
Optional Parame	Optional Parameters	
'Box'	Three-element cell array, {longitude, latitude, mode} specifying the longitude and latitude coordinates that define a region. longitude and latitude are two-element vectors that specify longitude and latitude coordinates. mode is a string defining the criterion for the inclusion of a cross track in a region. The cross track is within a region if any of these conditions is met:	
	• Its midpoint is within the box (mode='midpoint').	
	• Either endpoint is within the box (mode='endpoint').	
	• Any point is within the box (mode='anypoint').	
'ExtMode'	String specifying whether geolocation fields and data fields must be in the same swath (mode='internal'), or can be in different swaths (mode='external')	
	Note: mode is only used when extracting a time period or a region.	
'Vertical'	Two-element cell array, {dimension, range}dimension is a string specifying either a dimension name or field name to subset the data by.	
	• range is a two-element vector specifying the minimum and maximum range for the subset. If dimension is a dimension name, then range specifies the range of elements to extract. If dimension is a field name, then range specifies the range of values to extract.	
	'Vertical' subsetting can be used alone or in conjunction with 'Box' or 'Time'. To subset a region along multiple dimensions, vertical subsetting can be used up to eight times in one call to hdfread.	

For example,

 $\verb|hdfread('example.hdf', swath_dataset, 'Fields', fieldname, \dots|\\$

```
'Time', {start, stop, 'midpoint'})
```

Examples Example 1

Specify the name of the HDF file and the name of the data set. This example reads a data set named 'Example SDS' from a sample HDF file.

```
data = hdfread('example.hdf', 'Example SDS')
```

Example 2

Use data returned by hdfinfo to specify the data set to read.

1 Call hdfinfo to retrieve information about the contents of the HDF file.

2 Extract the structure containing information about the particular data set you want to import from the data returned by hdfinfo. The example uses the structure in the SDS field to retrieve a scientific data set.

```
Description: {}
    Index: 0
```

3 You can pass this structure to hdfread to import the data in the data set.

```
data = hdfread(sds_info)
```

Example 3

You can use the information returned by hdfinfo to check the size of the data set.

```
sds_info.Dims.Size
ans =
    16
ans =
    5
```

Using the 'index' parameter with hdfread, you can read a subset of the data in the data set. This example specifies a starting index of [3 3], an interval of 1 between values ([] meaning the default value of 1), and a length of 10 rows and 2 columns.

```
data = hdfread(sds_info, 'Index', {[3 3],[],[10 2]});

data(:,1)
ans =
    7
    8
    9
    10
    11
    12
    13
    14
    15
    16
```

```
data(:,2)
ans =
    8
    9
    10
    11
    12
    13
    14
    15
    16
    17
```

Example 4

This example uses the Vdata field from the information returned by hdfinfo to read two fields of the data, Idx and Temp.

```
s = hdfinfo('example.hdf');
data1 = hdfread(s.Vdata, 'Fields', {'Idx', 'Temp', 'Dewpt'});
data1{1}
ans =
      1
             2
                     3
                            4
                                   5
                                          6
                                                  7
                                                         8
                                                                9
data1{2}
ans =
      0
                                                                2
            12
                     3
                            5
                                  10
                                          - 1
                                                  3
                                                         0
data1{3}
ans =
      5
             5
                    7
                           11
                                   7
                                         10
                                                        14
                                                                4
```

hdfread

See Also

hdfinfo, hdf

Purpose Browse and import data from HDF4 or HDF-EOS files

Syntax hdftool

hdftool(filename)
h = hdftool(...)

Description

hdftool starts the HDF Import Tool, a graphical user interface used to browse the contents of HDF4 and HDF-EOS files and import data and subsets of data from these files. To open an HDF4 or HDF-EOS file, select **Open** from the **File** menu. You can open multiple files in the

HDF Import Tool by selecting **Open** from the **File** menu.

 ${\tt hdftool(filename)}$ opens the ${\tt HDF4}$ or ${\tt HDF\text{-}EOS}$ file specified by

filename in the HDF Import Tool.

h = hdftool(...) returns a handle h to the HDF Import Tool. To close

the tool from the command line, use close(h).

Example hdftool('example.hdf');

See Also hdf, hdfinfo, hdfread, uiimport

help

Purpose

Help for functions in Command Window

GUI Alternatives

Use the Function Browser by clicking its button, f_{ξ} , or run doc functionname to view more extensive help for a function in the Help browser.

Syntax

```
help
help /
help functionname
help modelname.mdl
help methodname
help classname
help packagename
help packagename.name
help packagename.classname.name
help toolboxname
help syntax
t = help('topic')
```

Description

help lists all primary help topics in the Command Window. Each main help topic corresponds to a folder name on the search path the MATLAB software uses.

help / lists all operators and special characters, along with their descriptions.

help functionname displays a brief description and the syntax for functionname in the Command Window. The information is known as the help comments because it comes from the comments at the top of the MATLAB function file. For more information or related help, use the links in the help output. If functionname is overloaded, that is, appears in multiple folders on the search path, help displays the help comments for the first functionname found on the search path, and displays a hyperlinked list of the overloaded functions and their folders. If functionname is also the name of a toolbox, help also displays a list of subfolders and hyperlinked list of functions in the toolbox, as defined in the Contents.m file for the toolbox.

help modelname.mdl displays the complete description for the MDL-file modelname as defined in **Model Properties > Description**. If the Simulink product is installed, you do not need to specify the .mdl extension.

help methodname displays help for the method methodname. You may need to qualify methodname with its class.

help classname displays help for the class classname. You may need to qualify classname with its package.

help packagename displays help for the package packagename.

help classname.name displays help for the method, property, or event name in classname. You may need to qualify classname with its package.

help packagename.classname.name displays help for the method, property, or event name in classname, which is part of packagename. If you do not know the packangename, create an instance of classname and then run class(obj).

help toolboxname displays the Contents.m file for the specified folder named toolboxname, where Contents.m contains a list and corresponding description of MATLAB program files in toolboxname. toolboxname can be a partial path. If toolboxname is also a function name, help also displays the help comments for the function.

help syntax displays help comments describing the syntax used in MATLAB functions.

t = help('topic') returns the help text for topic as a string, with each line separated by /n, where topic is any allowable argument for help.

Note Some help displayed in the Command Window uses all uppercase characters for the names to make them stand out from the rest of the text. When typing these names, use lowercase characters.

Some names use mixed case. The help comments accurately reflect that. Use mixed case when typing these names. For example, the java0bject function uses mixed case.

Remarks Prevent Scrolling of Long Help Pages

To prevent long descriptions from scrolling off the screen before you have time to read them, enter more on, and then enter the help statement.

Examples

help close displays help for the close function. It lists

help database.close displays help for the close function in the Database $Toolbox^{TM}$ product.

help throwAsCaller displays help for the MException.throwAsCaller method.

help MException displays help for the MException class.

help MException.cause displays help for the cause property of the MException class.

help containers displays help for the containers package.

help containers. Map displays help for the Map class in the containers package. Note that help Map does not provide help for the Map class, so include the packagename in the syntax.

help containers.Map.KeyType displays help for the KeyType property. Note that help Map.KeyType do not provide help for KeyType, so include the packagename in the syntax.

help datafeed displays help for the Datafeed Toolbox $^{\text{TM}}$ product.

help database lists the functions in the Database Toolbox product and displays help for the database function, because there is both a function and a toolbox called database.

help general lists all functions in the folder *matlabroot*/toolbox/matlab/general. This illustrates how to specify a partial path name rather than a full path name.

help f14_dap displays the description of the Simulink f14_dap.mdl model file (the Simulink product must be installed).

t = help('close') gets help for the function close and stores it as a string in t.

See Also

class, dbtype,doc, docsearch, helpbrowser, helpwin, lookfor, more, path, what, which, whos

Related topics in the MATLAB Desktop Tools and Development Environment documentation:

- "Getting Help"
- "Getting Help for Files Created by Others"
- "Providing Your Own Help and Demos"

helpbrowser

Purpose Open Help browser to access online documentation and demos

As an alternative to the helpbrowser function, select **Desktop > Help** or click the Help button on the toolbar in the MATLAB desktop.

Syntax helpbrowser

Description helpbrowser displays the Help browser, open to its default startup

page, providing direct access to a comprehensive library of demos and online documentation, including reference pages and user guides.

See Also demo, doc, docsearch, help, helpwin, web

"Getting Help"

helpdesk

Purpose Open Help browser

Syntax helpdesk

Description helpdesk opens the Help browser to the default startup page. In

previous releases, helpdesk displayed the Help Desk, which was the precursor to the Help browser. In a future release, the helpdesk function will be phased out — use the doc or helpbrowser function

instead.

See Also doc, helpbrowser

helpdlg

Purpose

Create and open help dialog box

Syntax

helpdlg

helpdlg('helpstring')

helpdlg('helpstring','dlgname')

h = helpdlg(...)

Description

helpdlg creates a nonmodal help dialog box or brings the named help dialog box to the front.

Note A nonmodal dialog box enables the user to interact with other windows before responding. For more information, see WindowStyle in the MATLAB Figure Properties.

helpdlg displays a dialog box named 'Help Dialog' containing the string 'This is the default help string.'

helpdlg('helpstring') displays a dialog box named 'Help Dialog' containing the string specified by 'helpstring'.

helpdlg('helpstring','dlgname') displays a dialog box named 'dlgname' containing the string 'helpstring'.

h = helpdlg(...) returns the handle of the dialog box.

Remarks

MATLAB wraps the text in 'helpstring' to fit the width of the dialog box. The dialog box remains on your screen until you press the **OK** button or the **Enter** key. After either of these actions, the help dialog box disappears.

Examples

The statement

helpdlg('Choose 10 points from the figure', 'Point Selection');

displays this dialog box:



See Also

dialog, errordlg, inputdlg, listdlg, msgbox, questdlg, warndlg figure, uiwait, uiresume

"Predefined Dialog Boxes" on page 1-113 for related functions

helpwin

Purpose Provide access to help comments for all functions

Syntax helpwin

helpwin topic

Description h

helpwin lists topics for groups of functions in the Help browser. It shows brief descriptions of the topics and provides links to display help comments for the functions in the Help browser. You cannot follow links in the helpwin list of functions if the MATLAB software is busy (for example, running a program).

helpwin topic displays help information for the topic in the Help browser. If topic is a folder, it displays all functions in the folder. If topic is a function, helpwin displays help for that function in the Help browser. From the page, you can access a list of folders (**Default Topics** link) as well as the reference page help for the function (**Go to online doc** link). You cannot follow links in the helpwin list of functions if MATLAB is busy (for example, running a program).

Examples Typing

helpwin datafun

displays the functions in the datafun folder and a brief description of each.

Typing

helpwin fft

displays the help for the fft function in the Help browser.

See Also doc, help, helpbrowser, web

Purpose

Hessenberg form of matrix

Syntax

```
H = hess(A)
[P,H] = hess(A)
[AA,BB,Q,Z] = hess(A,B)
```

Description

H = hess(A) finds H, the Hessenberg form of matrix A.

[P,H] = hess(A) produces a Hessenberg matrix H and a unitary matrix P so that A = P*H*P' and P'*P = eye(size(A)).

[AA,BB,Q,Z] = hess(A,B) for square matrices A and B, produces an upper Hessenberg matrix AA, an upper triangular matrix BB, and unitary matrices Q and Z such that Q*A*Z = AA and Q*B*Z = BB.

Definition

A Hessenberg matrix is zero below the first subdiagonal. If the matrix is symmetric or Hermitian, the form is tridiagonal. This matrix has the same eigenvalues as the original, but less computation is needed to reveal them.

Examples

H is a 3-by-3 eigenvalue test matrix:

Its Hessenberg form introduces a single zero in the (3,1) position:

Algorithm Inputs of Type Double

For inputs of type double, hess uses the following LAPACK routines to compute the Hessenberg form of a matrix:

Matrix A	Routine
Real symmetric	DSYTRD
	DSYTRD, DORGTR, (with output P)
Real	DGEHRD
nonsymmetric	DGEHRD, DORGHR (with output P)
Complex	ZHETRD
Hermitian	ZHETRD, ZUNGTR (with output P)
Complex	ZGEHRD
non-Hermitian	ZGEHRD, ZUNGHR (with output P)

Inputs of Type Single

For inputs of type single, hess uses the following LAPACK routines to compute the Hessenberg form of a matrix:

Matrix A	Routine
Real symmetric	SSYTRD
	SSYTRD, DORGTR, (with output P)
Real	SGEHRD
nonsymmetric	SGEHRD, SORGHR (with output P)
Complex	CHETRD
Hermitian	CHETRD, CUNGTR (with output P)
Complex	CGEHRD
non-Hermitian	CGEHRD, CUNGHR (with output P)

See Also

eig, qz, schur

References

Anderson, E., Z. Bai, C. Bischof, S. Blackford, J. Demmel, J. Dongarra, J. Du Croz, A. Greenbaum, S. Hammarling,

hess

A. McKenney, and D. Sorensen, *LAPACK User's Guide* (http://www.netlib.org/lapack/lug/lapack_lug.html), Third Edition, SIAM, Philadelphia, 1999.

hex2dec

Purpose

Convert hexadecimal number string to decimal number

Syntax

```
d = hex2dec('hex_value')
```

Description

d = hex2dec('hex_value') converts hex_value to its floating-point integer representation. The argument hex_value is a hexadecimal integer stored in a MATLAB string. The value of hex_value must be smaller than hexadecimal 10,000,000,000.

If *hex_value* is a character array, each row is interpreted as a hexadecimal string.

Examples

```
hex2dec('3ff')
ans =
1023
```

For a character array S,

```
S =
0FF
2DE
123
hex2dec(S)
ans =
255
734
291
```

See Also

dec2hex, format, hex2num, sprintf

Purpose

Convert hexadecimal number string to double-precision number

Syntax

n = hex2num(S)

Description

n = hex2num(S), where S is a 16 character string representing a hexadecimal number, returns the IEEE double-precision floating-point number n that it represents. Fewer than 16 characters are padded on the right with zeros. If S is a character array, each row is interpreted as a double-precision number.

NaNs, infinities and denorms are handled correctly.

Example

```
hex2num('400921fb54442d18')
```

returns Pi.

hex2num('bff')

returns

ans =

- 1

See Also

num2hex, hex2dec, sprintf, format

hgexport

Purpose Export figure

GUI Alternative

Use the **File** —> **Saveas** on the figure window menu to access the **Export Setup** GUI. Use **Edit** —> **Copy Figure** to copy the figure's contents to your system's clipboard. For details, see How to Print or

Export in the MATLAB Graphics documentation.

Syntax hgexport(h,filename)

hgexport(h, '-clipboard')

Description hgexport(h,filename) writes figure h to the file filename.

hgexport(h, '-clipboard') writes figure h to the Microsoft Windows

clipboard.

The format in which the figure is exported is determined by which renderer you use. The Painters renderer generates a metafile. The

ZBuffer and OpenGL renderers generate a bitmap.

See Also print

Purpose

Create hggroup object

Syntax

h = hggroup

h = hggroup(..., 'PropertyName', propertyvalue,...)

Properties

For a list of properties, see Hggroup Properties.

Description

h = hggroup creates an hggroup object as a child of the current axes and returns its handle, h.

h = hggroup(..., 'PropertyName', propertyvalue,...) creates an hggroup object with the property values specified in the argument list. For a description of the properties, see Hggroup Properties.

An hggroup object can be the parent of any axes children except light objects, as well as other hggroup objects. You can use hggroup objects to form a group of objects that can be treated as a single object with respect to the following cases:

- Visible Setting the hggroup object's Visible property also sets each child object's Visible property to the same value.
- Selectable Setting each hggroup child object's HitTest property to off enables you to select all children by clicking any child object.
- Current object Setting each hggroup child object's HitTest
 property to off enables the hggroup object to become the current
 object when any child object is picked. See the next section for an
 example.

Examples

This example defines a callback for the ButtonDownFcn property of an hggroup object. In order for the hggroup to receive the mouse button down event that executes the ButtonDownFcn callback, the HitTest properties of all the line objects must be set to off. The event is then passed up the hierarchy to the hggroup.

The following function creates a random set of lines that are parented to an hggroup object. The subfunction set_lines defines a callback that executes when the mouse button is pressed over any of the lines.

The callback simply increases the widths of all the lines by 1 with each button press.

Note If you are using the MATLAB help browser, you can run this example or open it in the MATLAB editor.


```
function doc_hggroup
hg = hggroup('ButtonDownFcn',@set_lines);
hl = line(randn(5),randn(5),'HitTest','off','Parent',hg);

function set_lines(cb,eventdata)
hl = get(cb,'Children');% cb is handle of hggroup object
lw = get(hl,'LineWidth');% get current line widths
set(hl,{'LineWidth'},num2cell([lw{:}]+1,[5,1])')
```

Note that selecting any one of the lines selects all the lines. (To select an object, enable plot edit mode by selecting **Plot Edit** from the **Tools** menu.)

Instance Diagram for This Example

The following diagram shows the object hierarchy created by this example.



Setting Default Properties

You can set default hggroup properties on the axes, figure, and root object levels:

```
set(0, 'DefaultHggroupProperty', PropertyValue...)
set(gcf, 'DefaultHggroupProperty', PropertyValue...)
set(gca, 'DefaultHggroupProperty', PropertyValue...)
```

where *Property* is the name of the hggroup property whose default value you want to set and PropertyValue is the value you are specifying. Use set and get to access the hggroup properties.

See Also

hgtransform

Hggroup Properties for property descriptions

"Group Objects" for more information and examples.

"Function Handle Callbacks" for information on how to use function handles to define callbacks.

Purpose

Hggroup properties

Creating Hggroup Objects

Use hggroup to create hggroup objects.

Modifying Properties

You can set and query graphics object properties using the set and get commands.

To change the default values of properties, see "Setting Default Property Values"

See "Group Objects" for general information on this type of object.

Hggroup Property Descriptions

This section provides a description of properties. Curly braces {} enclose default values.

Annotation

hg.Annotation object Read Only

Control the display of hggroup objects in legends. The Annotation property enables you to specify whether this hggroup object is represented in a figure legend.

Querying the Annotation property returns the handle of an hg.Annotation object. The hg.Annotation object has a property called LegendInformation, which contains an hg.LegendEntry object.

Once you have obtained the hg.LegendEntry object, you can set its IconDisplayStyle property to control whether the hggroup object is displayed in a figure legend:

IconDisplayStyle Value	Purpose
on	Include the hggroup object in a legend as one entry, but not its children objects
off	Do not include the hggroup or its children in a legend (default)
children	Include only the children of the hggroup as separate entries in the legend

Setting the IconDisplayStyle Property

These commands set the IconDisplayStyle of a graphics object with handle hobj to children, which causes each child object to have an entry in the legend:

```
hAnnotation = get(hobj, 'Annotation');
hLegendEntry = get(hAnnotation, 'LegendInformation');
set(hLegendEntry, 'IconDisplayStyle', 'children')
```

Using the IconDisplayStyle Property

See "Controlling Legends" for more information and examples.

```
BeingDeleted on | {off} Read Only
```

This object is being deleted. The BeingDeleted property provides a mechanism that you can use to determine whether objects are in the process of being deleted. The MATLAB software sets the BeingDeleted property to on when the object's delete function callback is called (see the DeleteFcn property). It remains set to on while the delete function executes, after which the object no longer exists.

For example, an object's delete function might call other functions that act on a number of different objects. These functions might

not need to perform actions on objects if the objects are going to be deleted, and therefore can check the object's BeingDeleted property before acting.

BusyAction cancel | {queue}

Callback routine interruption. The BusyAction property enables you to control how MATLAB handles events that potentially interrupt executing callbacks. If there is a callback function executing, callbacks invoked subsequently always attempt to interrupt it.

If the Interruptible property of the object whose callback is executing is set to on (the default), then interruption occurs at the next point where the event queue is processed. If the Interruptible property is off, the BusyAction property (of the object owning the executing callback) determines how MATLAB handles the event. The choices are

- cancel Discard the event that attempted to execute a second callback routine.
- queue Queue the event that attempted to execute a second callback routine until the current callback finishes.

ButtonDownFcn

function handle, cell array containing function handle and additional arguments, or string (not recommended)

Button press callback function. A callback function that executes whenever you press a mouse button while the pointer is over the children of the hggroup object. Define the ButtonDownFcn as a function handle. The function must define at least two input arguments (handle of figure associated with the mouse button press and an empty event structure).

See "Function Handle Callbacks" for information on how to use function handles to define the callbacks.

Children

array of graphics object handles

Children of the hggroup object. An array containing the handles of all objects parented to the hggroup object (whether visible or not).

Note that if a child object's HandleVisibility property is set to callback or off, its handle does not appear in the hggroup Children property unless you set the Root ShowHiddenHandles property to on:

```
set(0, 'ShowHiddenHandles', 'on')
```

Clipping

{on} | off

Clipping mode. MATLAB clips stairs plots to the axes plot box by default. If you set Clipping to off, lines might be displayed outside the axes plot box.

CreateFcn

function handle, cell array containing function handle and additional arguments, or string (not recommended)

Callback executed during object creation. This property defines a callback function that executes when MATLAB creates an hggroup object. You must define this property as a default value for hggroup objects or in a call to the hggroup function to create a new hggroup object. For example, the statement

```
set(0, 'DefaulthggroupCreateFcn',@myCreateFcn)
```

defines a default value on the root level that applies to every hggroup object created in that MATLAB session. Whenever you create an hggroup object, the function associated with the function handle <code>@myCreateFcn</code> executes.

MATLAB executes the callback after setting all the hggroup object's properties. Setting the CreateFcn property on an existing hggroup object has no effect.

The handle of the object whose CreateFcn is being executed is passed by MATLAB as the first argument to the callback function and is also accessible through the root CallbackObject property, which you can query using gcbo.

See Function Handle Callbacks for information on how to use function handles to define the callback function.

DeleteFcn

function handle, cell array containing function handle and additional arguments, or string (not recommended)

Callback executed during object deletion. A callback function that executes when the hggroup object is deleted (for example, this might happen when you issue a delete command on the hggroup object, its parent axes, or the figure containing it). MATLAB executes the callback before destroying the object's properties so the callback routine can query these values.

The handle of the object whose DeleteFcn is being executed is passed by MATLAB as the first argument to the callback function and is accessible through the root CallbackObject property, which you can query using gcbo.

See "Function Handle Callbacks" for information on how to use function handles to define the callback function.

See the BeingDeleted property for related information.

DisplayName

string (default is empty string)

String used by legend for this hggroup object. The legend function uses the string defined by the DisplayName property to label this hggroup object in the legend.

- If you specify string arguments with the legend function,
 DisplayName is set to this hggroup object's corresponding string and that string is used for the legend.
- If DisplayName is empty, legend creates a string of the form,
 ['data' n], where n is the number assigned to the object
 based on its location in the list of legend entries. However,
 legend does not set DisplayName to this string.
- If you edit the string directly in an existing legend, DisplayName
 is set to the edited string.
- If you specify a string for the DisplayName property and create the legend using the figure toolbar, then MATLAB uses the string defined by DisplayName.
- To add programmatically a legend that uses the DisplayName string, call legend with the toggle or show option.

See "Controlling Legends" for more examples.

EraseMode

{normal} | none | xor | background

Erase mode. This property controls the technique MATLAB uses to draw and erase hggroup child objects. Alternative erase modes are useful for creating animated sequences, where control of the way individual objects are redrawn is necessary to improve performance and obtain the desired effect.

normal — Redraw the affected region of the display, performing
the three-dimensional analysis necessary to ensure that all
objects are rendered correctly. This mode produces the most
accurate picture, but is the slowest. The other modes are faster,
but do not perform a complete redraw and are therefore less
accurate.

- none Do not erase objects when they are moved or destroyed.
 While the objects are still visible on the screen after erasing with EraseMode none, you cannot print these objects because MATLAB stores no information about their former locations.
- xor Draw and erase the object by performing an exclusive OR (XOR) with each pixel index of the screen behind it. Erasing the object does not damage the color of the objects behind it. However, the color of the erased object depends on the color of the screen behind it and it is correctly colored only when it is over the axes background color (or the figure background color if the axes Color property is set to none). That is, it isn't erased correctly if there are objects behind it.
- background Erase the graphics objects by redrawing them
 in the axes background color, (or the figure background color
 if the axes Color property is set to none). This damages other
 graphics objects that are behind the erased object, but the
 erased object is always properly colored.

Set the axes background color with the axes Color property. Set the figure background color with the figure Color property.

Printing with Nonnormal Erase Modes

MATLAB always prints figures as if the EraseMode of all objects is normal. This means graphics objects created with EraseMode set to none, xor, or background can look different on screen than on paper. On screen, MATLAB may mathematically combine layers of colors (for example, performing an XOR of a pixel color with that of the pixel behind it) and ignore three-dimensional sorting to obtain greater rendering speed. However, these techniques are not applied to the printed output.

You can use the MATLAB getframe command or other screen capture applications to create an image of a figure containing nonnormal mode objects.

```
HandleVisibility
{on} | callback | off
```

Control access to object's handle by command-line users and GUIs. This property determines when an object's handle is visible in its parent's list of children. HandleVisibility is useful for preventing command-line users from accidentally accessing the hggroup object.

- on Handles are always visible when HandleVisibility is on.
- callback Setting HandleVisibility to callback causes
 handles to be visible from within callback routines or functions
 invoked by callback routines, but not from within functions
 invoked from the command line. This provides a means to
 protect GUIs from command-line users, while allowing callback
 routines to have access to object handles.
- off Setting HandleVisibility to off makes handles invisible at all times. This might be necessary when a callback invokes a function that might potentially damage the GUI (such as evaluating a user-typed string) and so temporarily hides its own handles during the execution of that function.

Functions Affected by Handle Visibility

When a handle is not visible in its parent's list of children, it cannot be returned by functions that obtain handles by searching the object hierarchy or querying handle properties. This includes get, findobj, gca, gcf, gco, newplot, cla, clf, and close.

Properties Affected by Handle Visibility

When a handle's visibility is restricted using callback or off, the object's handle does not appear in its parent's Children property, figures do not appear in the root's CurrentFigure property, objects do not appear in the root's CallbackObject property or in

the figure's CurrentObject property, and axes do not appear in their parent's CurrentAxes property.

Overriding Handle Visibility

You can set the root ShowHiddenHandles property to on to make all handles visible regardless of their HandleVisibility settings (this does not affect the values of the HandleVisibility properties). See also findall.

Handle Validity

Handles that are hidden are still valid. If you know an object's handle, you can set and get its properties, and pass it to any function that operates on handles.

HitTest

{on} | off

Pickable by mouse click. HitTest determines whether the hggroup object can become the current object (as returned by the gco command and the figure CurrentObject property) as a result of a mouse click on the hggroup child objects. Note that to pick the hggroup object, its children must have their HitTest property set to off.

If the hggroup object's HitTest is off, clicking it picks the object behind it.

Interruptible

{on} | off

Callback routine interruption mode. The Interruptible property controls whether an hygroup object callback can be interrupted by callbacks invoked subsequently.

Only callbacks defined for the ButtonDownFcn property are affected by the Interruptible property. MATLAB checks for

events that can interrupt a callback only when it encounters a drawnow, figure, getframe, or pause command in the routine. See the BusyAction property for related information.

Setting Interruptible to on allows any graphics object's callback to interrupt callback routines originating from an hggroup property. Note that MATLAB does not save the state of variables or the display (for example, the handle returned by the gca or gcf command) when an interruption occurs.

Parent

axes handle

Parent of hggroup object. This property contains the handle of the hggroup object's parent object. The parent of an hggroup object is the axes, hggroup, or hgtransform object that contains it.

See "Objects That Can Contain Other Objects" for more information on parenting graphics objects.

Selected

on | {off}

Is object selected? When you set this property to on, MATLAB displays selection handles at the corners and midpoints of hggroup child objects if the SelectionHighlight property is also on (the default).

SelectionHighlight

{on} | off

Objects are highlighted when selected. When the Selected property is on, MATLAB indicates the selected state by drawing selection handles on the hggroup child objects. When SelectionHighlight is off, MATLAB does not draw the handles.

Tag

string

User-specified object label. The Tag property provides a means to identify graphics objects with a user-specified label. This is particularly useful when you are constructing interactive graphics programs that would otherwise need to define object handles as global variables or pass them as arguments between callbacks.

For example, you might create an hggroup object and set the Tag property:

```
t = hggroup('Tag', 'group1')
```

When you want to access the object, you can use findobj to find its handle. For example,

```
h = findobj('Tag', 'group1');
```

Type

string (read only)

Type of graphics object. This property contains a string that identifies the class of graphics object. For hggroup objects, Type is 'hggroup'. The following statement finds all the hggroup objects in the current axes.

```
t = findobj(gca, 'Type', 'hggroup');
```

UIContextMenu

handle of a uicontextmenu object

Associate a context menu with the hggroup object. Assign this property the handle of a uicontextmenu object created in the hggroup object's figure. Use the uicontextmenu function to create the context menu. MATLAB displays the context menu whenever you right-click the hggroup object.

UserData

array

User-specified data. This property can be any data you want to associate with the hggroup object (including cell arrays and structures). The hggroup object does not set values for this property, but you can access it using the set and get functions.

Visible

{on} | off

Visibility of hggroup object and its children. By default, hggroup object visibility is on. This means all children of the hggroup are visible unless the child object's Visible property is set to off. Setting an hggroup object's Visible property to off also makes its children invisible.

See Also hggroup

hgload

Purpose

Load Handle Graphics object hierarchy from file

GUI Alternative

Use the **File** —> **Open** on the figure window menu to access figure files with the **Open** dialog.

Syntax

```
h = hgload('filename')
[h,old_prop_values] = hgload(...,property_structure)
hgload(...,'all')
```

Description

h = hgload('filename') loads Handle Graphics objects and its children (if any) from the FIG-file specified by filename and returns handles to the top-level objects. If filename contains no extension, then the MATLAB software adds the .fig extension.

[h,old_prop_values] = hgload(...,property_structure) overrides the properties on the top-level objects stored in the FIG-file with the values in property_structure, and returns their previous values in old_prop_values.

property_structure must be a structure having field names that correspond to property names and values that are the new property values.

old_prop_values is a cell array equal in length to h, containing the old values of the overridden properties for each object. Each cell contains a structure having field names that are property names, each of which contains the original value of each property that has been changed. Any property specified in property_structure that is not a property of a top-level object in the FIG-file is not included in old_prop_values.

hgload(..., 'all') overrides the default behavior, which does not reload nonserializable objects saved in the file. These objects include the default toolbars and default menus. This option is obsolete and will be removed in a future release.

Nonserializable objects (such as the default toolbars and the default menus) are normally not reloaded because they are loaded from different files at figure creation time. This allows revisions of the default menus and toolbars to occur without affecting existing FIG-files.

Passing the string all to hgload ensures that any nonserializable objects contained in the file are also reloaded.

Note that, by default, hgsave excludes nonserializable objects from the FIG-file unless you use the all flag.

See Also

hgsave, open

"Figure Windows" on page 1-105 for related functions

hgsave

Purpose

Save Handle Graphics object hierarchy to file

GUI Alternative

Use the **File** —> **Saveas** on the figure window menu to access the Export Setup GUI. For details, see How to Print or Export in the MATLAB Graphics documentation.

Syntax

```
hgsave('filename')
hgsave(h,'filename')
hgsave(...,'all')
hgsave(...,'-v6')
hgsave(...,'-v7.3')
```

Description

hgsave('filename') saves the current figure to a file named filename.

hgsave(h, 'filename') saves the objects identified by the array of handles h to a file named filename. If you do not specify an extension for filename, then the extension .fig is appended. If h is a vector, none of the handles in h may be ancestors or descendents of any other handles in h.

hgsave(..., 'all') overrides the default behavior, which does not save nonserializable objects. Nonserializable objects include the default toolbars and default menus. This allows revisions of the default menus and toolbars to occur without affecting existing FIG-files and also reduces the size of FIG-files. Passing the string all to hgsave ensures that nonserializable objects are also saved. This option is obsolete and will be removed in a future release.

The default behavior of hgload is to ignore nonserializable objects in the file at load time. You can override this behavior using the all argument with hgload.

hgsave(..., '-v6') saves the FIG-file in a format that can be loaded by versions prior to MATLAB 7.

hgsave(...,'-v7.3') saves the FIG-file in a format that can be loaded only by MATLAB versions 7.3 and above. This format, based on HDF5 files, is intended for saving FIG-files larger than 2 GB.

You can make -v6 or -v7.3 your default format for saving MAT-files and FIG-files by setting a preference, which will eliminate the need to specify the flag each time you save. See "MAT-Files Preferences" in the MATLAB Desktop Tools and Development Environment documentation.

Full Backward Compatibility

When creating a figure you want to save and use in a MATLAB version prior to MATLAB 7, use the 'v6' option with the plotting function and the '-v6' option for hgsave. Check the reference page for the plotting function you are using for more information.

See "Plot Objects and Backward Compatibility" for more information.

See Also

hgload, open, save

"Figure Windows" on page 1-105 for related functions

hgsetget

Purpose

Abstract class used to derive handle class with set and get methods

Syntax

classdef myclass < hgsetget</pre>

Description

classdef myclass < hgsetget makes myclass a subclass of the hgsetget class, which is a subclass of the handle class.

Use the hgsetget class to derive classes that inherit set and get methods that behave like Handle Graphics set and get functions.

Methods

When you derive a class from the hgsetget class, your class inherits the following methods.

Method	Purpose
set	Assigns values to the specified properties or returns a cell array of possible values for writable properties.
get	Returns value of specified property or a struct with all property values.
setdisp	Called when set is called with no output arguments and a handle array, but no property name. Override this method to change what set displays.
getdisp	Called when get is called with no output arguments and handle array, but no property name. Override this method to change what get displays.

See Also

See "Implementing a Set/Get Interface for Properties"

handle, set (hgsetget), get (hgsetget), set, get

Purpose

Create hgtransform graphics object

Syntax

h = hgtransform

h = hgtransform('PropertyName',propertyvalue,...)

Properties

For a list of properties, see Hgtransform Properties.

Description

h = hgtransform creates an hgtransform object and returns its handle.

h = hgtransform('*PropertyName*',propertyvalue,...) creates an hgtransform object with the property value settings specified in the argument list. For a description of the properties, see Hgtransform Properties.

hgtransform objects can contain other objects, which lets you treat the hgtransform and its children as a single entity with respect to visibility, size, orientation, etc. You can group objects by parenting them to a single hgtransform object (i.e., setting the object's Parent property to the hgtransform object's handle):

```
h = hgtransform;
surface('Parent',h,...)
```

The primary advantage of parenting objects to an hydransform object is that you can perform *transforms* (for example, translation, scaling, rotation, etc.) on the child objects in unison.

The parent of an hytransform object is either an axes object or another hytransform.

Although you cannot see an hydransform object, setting its Visible property to off makes all its children invisible as well.

Exceptions and Limitations

- An hydransform object can be the parent of any number of axes child objects belonging to the same axes, except for light objects.
- hgtransform objects can never be the parent of axes objects and therefore can contain objects only from a single axes.

hgtransform

- hgtransform objects can be the parent of other hgtransform objects within the same axes.
- You cannot transform image objects because images are not true 3-D objects. Texture mapping the image data to a surface CData enables you to produce the effect of transforming an image in 3-D space.

Note Many plotting functions clear the axes (i.e., remove axes children) before drawing the graph. Clearing the axes also deletes any hydransform objects in the axes.


Examples Transforming a Group of Objects

This example shows how to create a 3-D star with a group of surface objects parented to a single hydransform object. The hydransform then rotates the object about the *z*-axis while scaling its size.

Tip If you are using the MATLAB Help browser, you can run this example or open it in the MATLAB Editor.


1 Create an axes and adjust the view. Set the axes limits to prevent auto limit selection during scaling.

```
ax = axes('XLim',[-1.5 1.5],'YLim',[-1.5 1.5],...
'ZLim',[-1.5 1.5]);
view(3); grid on; axis equal
```



2 Create the objects you want to parent to the hgtransform object.

```
[x y z] = cylinder([.2 0]);
h(1) = surface(x,y,z,'FaceColor','red');
h(2) = surface(x,y,-z,'FaceColor','green');
h(3) = surface(z,x,y,'FaceColor','blue');
h(4) = surface(-z,x,y,'FaceColor','cyan');
h(5) = surface(y,z,x,'FaceColor','magenta');
h(6) = surface(y,-z,x,'FaceColor','yellow');
```




3 Create an hytransform object and parent the surface objects to it. The figure should not change from the image above.

```
t = hgtransform('Parent',ax);
set(h,'Parent',t)
```

4 Select a renderer and show the objects.

```
set(gcf,'Renderer','opengl')
drawnow
```




5 Initialize the rotation and scaling matrix to the identity matrix (eye). Again, the image should not change.

```
Rz = eye(4);
Sxy = Rz;
```

6 Form the *z*-axis rotation matrix and the scaling matrix. Rotate 360 degrees (2*pi radians) and scale by using the increasing values of r.


```
for r = 1:.1:2*pi
% Z-axis rotation matrix
Rz = makehgtform('zrotate',r);
% Scaling matrix
Sxy = makehgtform('scale',r/4);
```

```
% Concatenate the transforms and
% set the hgtransform Matrix property
    set(t,'Matrix',Rz*Sxy)
    drawnow
end
pause(1)
```



7 Reset to the original orientation and size using the identity matrix.

```
set(t,'Matrix',eye(4))
```




Transforming Objects Independently

This example creates two hydransform objects to illustrate how to transform each independently within the same axes. A translation transformation moves one hydransform object away from the origin.

Tip If you are using the MATLAB Help browser, you can run this example or open it in the MATLAB Editor.


1 Create and set up the axes object that will be the parent of both hgtransform objects. Set the limits to accommodate the translated object.

```
ax = axes('XLim',[-2 1],'YLim',[-2 1],'ZLim',[-1 1]);
view(3); grid on; axis equal
```



2 Create the surface objects to group.

```
[x y z] = cylinder([.3 0]);
h(1) = surface(x,y,z,'FaceColor','red');
h(2) = surface(x,y,-z,'FaceColor','green');
h(3) = surface(z,x,y,'FaceColor','blue');
h(4) = surface(-z,x,y,'FaceColor','cyan');
h(5) = surface(y,z,x,'FaceColor','magenta');
h(6) = surface(y,-z,x,'FaceColor','yellow');
```




3 Create the hydransform objects and parent them to the same axes. The figure should not change.

```
t1 = hgtransform('Parent',ax);
t2 = hgtransform('Parent',ax);
```

4 Set the renderer to use OpenGL.

```
set(gcf,'Renderer','opengl')
```




5 Parent the surfaces to hyptransform t1, then copy the surface objects and parent the copies to hyptransform t2. This figure should not change.

```
set(h,'Parent',t1)
h2 = copyobj(h,t2);
```

6 Translate the second hytransform object away from the first hytransform object and display the result.

```
Txy = makehgtform('translate',[-1.5 -1.5 0]);
set(t2,'Matrix',Txy)
drawnow
```



7 Rotate both hydransform objects in opposite directions. The final image for this step is the same as for step 6. However, you should run the code to see the rotations.

```
% Rotate 10 times (2pi radians = 1 rotation)
for r = 1:.1:20*pi
% Form z-axis rotation matrix
Rz = makehgtform('zrotate',r);
% Set transforms for both hgtransform objects
set(t1,'Matrix',Rz)
set(t2,'Matrix',Txy*inv(Rz))
drawnow
end
```

hgtransform

Setting Default Properties

You can set default hyperansform properties on the axes, figure, and root object levels:

```
set(0, 'DefaultHgtransformPropertyName', propertyvalue,...)
set(gcf, 'DefaultHgtransformPropertyName', propertyvalue,...)
set(gca, 'DefaultHgtransformPropertyName', propertyvalue,...)
```

PropertyName is the name of the hydransform property and propertyvalue is the specified value. Use set and get to access hydransform properties.

See Also

hggroup, makehgtform

Hgtransform Properties for property descriptions.

"Group Objects" in MATLAB Graphics documentation for more information and examples.

Tomas Moller and Eric Haines, *Real-Time Rendering*, A K Peters, Ltd., 1999 for more information about transforms.

Purpose

Hgtransform properties

Creating Hgtransform Objects

Use hgtransform to create hgtransform objects.

Modifying Properties

You can set and query graphics object properties using the set and get commands.

To change the default values of properties, see "Setting Default Property Values"

See "Group Objects" for general information on this type of object.

Hgtransform Property Descriptions

This section provides a description of properties. Curly braces {} enclose default values.

Annotation

hg. Annotation object Read Only

Control the display of hgtransform objects in legends. The Annotation property enables you to specify whether this hgtransform object is represented in a figure legend.

Querying the Annotation property returns the handle of an hg.Annotation object. The hg.Annotation object has a property called LegendInformation, which contains an hg.LegendEntry object.

Once you have obtained the hg.LegendEntry object, you can set its IconDisplayStyle property to control whether the hgtransform object is displayed in a figure legend:

IconDisplayStyle Value	Purpose
on	Include the hgtransform object in a legend as one entry, but not its children objects
off	Do not include the hgtransform or its children in a legend (default)
children	Include only the children of the hgtransform as separate entries in the legend

Setting the IconDisplayStyle Property

These commands set the IconDisplayStyle of a graphics object with handle hobj to children, which causes each child object to have an entry in the legend:

```
hAnnotation = get(hobj, 'Annotation');
hLegendEntry = get(hAnnotation, 'LegendInformation');
set(hLegendEntry, 'IconDisplayStyle', 'children')
```

Using the IconDisplayStyle Property

See "Controlling Legends" for more information and examples.

BeingDeleted

```
on | {off} Read Only
```

This object is being deleted. The BeingDeleted property provides a mechanism that you can use to determine whether objects are in the process of being deleted. The MATLAB software sets the BeingDeleted property to on when the object's delete function callback is called (see the DeleteFcn property). It remains set to on while the delete function executes, after which the object no longer exists.

For example, an object's delete function might call other functions that act on a number of different objects. These functions might

not need to perform actions on objects if the objects are going to be deleted, and therefore can check the object's BeingDeleted property before acting.

BusyAction

cancel | {queue}

Callback routine interruption. The BusyAction property enables you to control how MATLAB handles events that potentially interrupt executing callback functions. If there is a callback executing, callbacks invoked subsequently always attempt to interrupt it.

If the Interruptible property of the object whose callback is executing is set to on (the default), then interruption occurs at the next point where the event queue is processed. If the Interruptible property is off, the BusyAction property (of the object owning the executing callback) determines how MATLAB handles the event. The choices are

- cancel Discard the event that attempted to execute a second callback routine.
- queue Queue the event that attempted to execute a second callback routine until the current callback finishes.

ButtonDownFcn

function handle, cell array containing function handle and additional arguments, or string (not recommended)

Button press callback function. A callback function that executes whenever you press a mouse button while the pointer is within the extent of the hydransform object, but not over another graphics object. The extent of an hydransform object is the smallest rectangle that encloses all the children. Note that you cannot execute the hydransform object's button down function if it has no children.

Define the ButtonDownFcn as a function handle. The function must define at least two input arguments (handle of figure associated with the mouse button press and an empty event structure).

See "Function Handle Callbacks" for information on how to use function handles to define the callbacks.

Children

array of graphics object handles

Children of the hyperansform object. An array containing the handles of all graphics objects parented to the hyperansform object (whether visible or not).

The graphics objects that can be children of an hydransform are images, lights, lines, patches, rectangles, surfaces, and text. You can change the order of the handles and thereby change the stacking of the objects on the display.

Note that if a child object's HandleVisibility property is set to callback or off, its handle does not show up in the hgtransform Children property unless you set the Root ShowHiddenHandles property to on.

Clipping

{on} | off

This property has no effect on hgtransform objects.

CreateFcn

function handle, cell array containing function handle and additional arguments, or string (not recommended)

Callback executed during object creation. This property defines a callback function that executes when MATLAB creates an hgtransform object. You must define this property as a default value for hgtransform objects. For example, the statement

set(0, 'DefaultHgtransformCreateFcn',@myCreateFcn)

defines a default value on the root level that applies to every hydransform object created in a MATLAB session. Whenever you create an hydransform object, the function associated with the function handle <code>@myCreateFcn</code> executes.

MATLAB executes the callback after setting all the hydransform object's properties. Setting the CreateFcn property on an existing hydransform object has no effect.

The handle of the object whose CreateFcn is being executed is passed by MATLAB as the first argument to the callback function and is accessible through the root CallbackObject property, which you can guery using gcbo.

See "Function Handle Callbacks" for information on how to use function handles to define the callback function.

DeleteFcn

function handle, cell array containing function handle and additional arguments, or string (not recommended)

Callback executed during object deletion. A callback function that executes when the hydransform object is deleted (for example, this might happen when you issue a delete command on the hydransform object, its parent axes, or the figure containing it). MATLAB executes the callback before destroying the object's properties so the callback routine can query these values.

The handle of the object whose DeleteFcn is being executed is passed by MATLAB as the first argument to the callback function and is accessible through the root CallbackObject property, which can be queried using gcbo.

See "Function Handle Callbacks" for information on how to use function handles to define the callback function.

See the BeingDeleted property for related information.

DisplayName

string (default is empty string)

String used by legend for this hgtransform object. The legend function uses the string defined by the DisplayName property to label this hgtransform object in the legend.

- If you specify string arguments with the legend function, DisplayName is set to this hgtransform object's corresponding string and that string is used for the legend.
- If DisplayName is empty, legend creates a string of the form, ['data' n], where n is the number assigned to the object based on its location in the list of legend entries. However, legend does not set DisplayName to this string.
- If you edit the string directly in an existing legend, DisplayName is set to the edited string.
- If you specify a string for the DisplayName property and create
 the legend using the figure toolbar, then MATLAB uses the
 string defined by DisplayName.
- To add programmatically a legend that uses the DisplayName string, call legend with the toggle or show option.

See "Controlling Legends" for more examples.

EraseMode

{normal} | none | xor | background

Erase mode. This property controls the technique MATLAB uses to draw and erase hyperansform child objects (light objects have no erase mode). Alternative erase modes are useful for creating animated sequences, where control of the way individual objects are redrawn is necessary to improve performance and obtain the desired effect.

- normal Redraw the affected region of the display, performing
 the three-dimensional analysis necessary to ensure that all
 objects are rendered correctly. This mode produces the most
 accurate picture, but is the slowest. The other modes are faster,
 but do not perform a complete redraw and are therefore less
 accurate.
- none Do not erase objects when they are moved or destroyed. While the objects are still visible on the screen after erasing with EraseMode none, you cannot print these objects because MATLAB stores no information about their former locations.
- xor—Draw and erase the object by performing an exclusive OR (XOR) with each pixel index of the screen behind it. Erasing the object does not damage the color of the objects behind it. However, the color of the erased object depends on the color of the screen behind it and it is correctly colored only when it is over the axes background color (or the figure background color if the axes Color property is set to none). That is, it isn't erased correctly if there are objects behind it.
- background Erase the graphics objects by redrawing them
 in the axes background color, (or the figure background color
 if the axes Color property is set to none). This damages other
 graphics objects that are behind the erased object, but the
 erased object is always properly colored.

Set the axes background color with the axes Color property. Set the figure background color with the figure Color property.

Printing with Nonnormal Erase Modes

MATLAB always prints figures as if the EraseMode of all objects is normal. This means graphics objects created with EraseMode set to none, xor, or background can look different on screen than on paper. On screen, MATLAB can mathematically combine layers of colors (for example, performing an XOR operation on a pixel color and the pixel behind it) and ignore three-dimensional sorting to

obtain greater rendering speed. However, these techniques are not applied to the printed output.

You can use the MATLAB getframe command or other screen capture applications to create an image of a figure containing nonnormal mode objects.

```
HandleVisibility
{on} | callback | off
```

Control access to object's handle by command-line users and GUIs. This property determines when an object's handle is visible in its parent's list of children. HandleVisibility is useful for preventing command-line users from accidentally accessing the hgtransform object.

- on Handles are always visible when HandleVisibility is on.
- callback Setting HandleVisibility to callback causes handles to be visible from within callback routines or functions invoked by callback routines, but not from within functions invoked from the command line. This provides a means to protect GUIs from command-line users, while allowing callback routines to have access to object handles.
- off Setting HandleVisibility to off makes handles invisible at all times. This might be necessary when a callback invokes a function that might potentially damage the GUI (such as evaluating a user-typed string) and so temporarily hides its own handles during the execution of that function.

Functions Affected by Handle Visibility

When a handle is not visible in its parent's list of children, it cannot be returned by functions that obtain handles by searching the object hierarchy or querying handle properties. This includes get, findobj, gca, gcf, gco, newplot, cla, clf, and close.

Properties Affected by Handle Visibility

When a handle's visibility is restricted using callback or off, the object's handle does not appear in its parent's Children property, figures do not appear in the root's CurrentFigure property, objects do not appear in the root's CallbackObject property or in the figure's CurrentObject property, and axes do not appear in their parent's CurrentAxes property.

Overriding Handle Visibility

You can set the root ShowHiddenHandles property to on to make all handles visible regardless of their HandleVisibility settings (this does not affect the values of the HandleVisibility properties). See also findall.

Handle Validity

Handles that are hidden are still valid. If you know an object's handle, you can set and get its properties and pass it to any function that operates on handles.

HitTest

{on} | off

Pickable by mouse click. HitTest determines whether the hgtransform object can become the current object (as returned by the gco command and the figure CurrentObject property) as a result of a mouse click within the limits of the hgtransform object. If HitTest is off, clicking the hgtransform picks the object behind it.

Interruptible

{on} | off

Callback routine interruption mode. The Interruptible property controls whether an hyperansform object callback can be interrupted by callbacks invoked subsequently. Only callbacks defined for the ButtonDownFcn property are affected by the Interruptible property. MATLAB checks for events that can

interrupt a callback only when it encounters a drawnow, figure, getframe, or pause command in the routine. See the BusyAction property for related information.

Setting Interruptible to on allows any graphics object's callback to interrupt callback routines originating from an hyperansform property. Note that MATLAB does not save the state of variables or the display (for example, the handle returned by the gca or gcf command) when an interruption occurs.

Matrix

4-by-4 matrix

Transformation matrix applied to hyperansform object and its children. The hyperansform object applies the transformation matrix to all its children.

See "Group Objects" for more information and examples.

Parent

figure handle

Parent of hydransform object. This property contains the handle of the hydransform object's parent object. The parent of an hydransform object is the axes, hygroup, or hydransform object that contains it.

See "Objects That Can Contain Other Objects" for more information on parenting graphics objects.

Selected

```
on | {off}
```

Is object selected? When you set this property to on, MATLAB displays selection handles on all child objects of the hydransform if the SelectionHighlight property is also on (the default).

```
SelectionHighlight {on} | off
```

Objects are highlighted when selected. When the Selected property is on, MATLAB indicates the selected state by drawing selection handles on the objects parented to the hgtransform. When SelectionHighlight is off, MATLAB does not draw the handles.

Tag

string

User-specified object label. The Tag property provides a means to identify graphics objects with a user-specified label. This is particularly useful when you are constructing interactive graphics programs that would otherwise need to define object handles as global variables or pass them as arguments between callbacks.

For example, you might create an hytransform object and set the Tag property:

```
t = hgtransform('Tag', 'subgroup1')
```

When you want to access the hgtransform object to add another object, you can use findobj to find the hgtransform object's handle. The following statement adds a line to subgroup1 (assuming x and y are defined).

```
line('XData',x,'YData',y,'Parent',findobj('Tag','subgroup1'))
```

Type

string (read only)

Type of graphics object. This property contains a string that identifies the class of graphics object. For hyperansform objects, Type is set to 'hgtransform'. The following statement finds all the hyperansform objects in the current axes.

```
t = findobj(gca, 'Type', 'hgtransform');
```

UIContextMenu

handle of a uicontextmenu object

Associate a context menu with the hgtransform object. Assign this property the handle of a uicontextmenu object created in the hgtransform object's figure. Use the uicontextmenu function to create the context menu. MATLAB displays the context menu whenever you right-click over the extent of the hgtransform object.

UserData

array

User-specified data. This property can be any data you want to associate with the hgtransform object (including cell arrays and structures). The hgtransform object does not set values for this property, but you can access it using the set and get functions.

Visible

{on} | off

Visibility of hyperansform object and its children. By default, hyperansform object visibility is on. This means all children of the hyperansform are visible unless the child object's Visible property is set to off. Setting an hyperansform object's Visible property to off also makes its children invisible.

See Also hgtransform

Purpose Remove hidden lines from mesh plot

Syntax hidden on

hidden off hidden

Description Hidden line removal draws only those lines that are not obscured by

other objects in the field of view.

hidden on turns on hidden line removal for the current graph so lines in the back of a mesh are hidden by those in front. This is the default

behavior.

hidden off turns off hidden line removal for the current graph.

hidden toggles the hidden line removal state.

Algorithm hidden on sets the FaceColor property of a surface graphics object to

the background Color of the axes (or of the figure if axes Color is none).

Examples Set hidden line removal off and on while displaying the peaks function.

mesh(peaks) hidden off hidden on

See Also shading, mesh

The surface properties FaceColor and EdgeColor

"Surface and Mesh Creation" on page 1-107 for related functions

hilb

Purpose Hilbert matrix

Syntax H = hilb(n)

Description H = hilb(n) returns the Hilbert matrix of order n.

Definition The Hilbert matrix is a notable example of a poorly conditioned matrix

[1]. The elements of the Hilbert matrices are $\hat{H}(i,j) = 1/(i+j-1)$.

Examples Even the fourth-order Hilbert matrix shows signs of poor conditioning.

cond(hilb(4)) = 1.5514e+04

See Also invhilb

References [1] Forsythe, G. E. and C. B. Moler, Computer Solution of Linear

Algebraic Systems, Prentice-Hall, 1967, Chapter 19.

Histogram plot



GUI Alternatives

To graph selected variables, use the Plot Selector workspace Browser, or use the Figure Palette Plot Catalog. Manipulate graphs in *plot edit* mode with the Property Editor. For details, see Plotting Tools — Interactive Plotting in the MATLAB Graphics documentation and Creating Graphics from the Workspace Browser in the MATLAB Desktop Tools documentation.

Syntax

```
n = hist(Y)
n = hist(Y,x)
n = hist(Y,nbins)
[n,xout] = hist(...)
hist(...)
hist(axes_handle,...)
```

Description

A histogram shows the distribution of data values.

n = hist(Y) bins the elements in vector Y into 10 equally spaced containers and returns the number of elements in each container as a row vector. If Y is an m-by-p matrix, hist treats the columns of Y as vectors and returns a 10-by-p matrix n. Each column of n contains the results for the corresponding column of Y. No elements of Y can be complex or of type integer.

n = hist(Y,x) where x is a vector, returns the distribution of Y among length(x) bins with centers specified by x. For example, if x is a 5-element vector, hist distributes the elements of Y into five bins centered on the x-axis at the elements in x, none of which can be complex. Note: use histc if it is more natural to specify bin edges instead of centers.

n = hist(Y, nbins) where nbins is a scalar, uses nbins number of bins.

[n,xout] = hist(...) returns vectors n and xout containing the
frequency counts and the bin locations. You can use bar(xout,n) to
plot the histogram.

hist(...) without output arguments produces a histogram plot of the output described above. hist distributes the bins along the *x*-axis between the minimum and maximum values of Y.

hist(axes_handle,...) plots into the axes with handle axes_handle instead of the current axes (gca).

Remarks

All elements in vector Y or in one column of matrix Y are grouped according to their numeric range. Each group is shown as one bin. If Y is a matrix, hist scales the current colormap and uses each column number (1:n) to assign each a unique color.

The histogram's *x*-axis reflects the range of values in Y. The histogram's *y*-axis shows the number of elements that fall within the groups; therefore, the *y*-axis ranges from 0 to the greatest number of elements deposited in any bin. The *x*-range of the leftmost and rightmost bins extends to include the entire data range in the case when the user-specified range does not cover the data range; this often results in "boxes" at either or both edges of the distribution. If you want a plot in which this does not happen (that is, all bins have equal width), you can create a histogram-like display using the bar command.


Histograms bins are created as patch objects and always plotted with a face color that maps to the first color in the current colormap (by default, blue) and with black edges. To change colors or other patch properties, use code similar to that given in the example.

The hist function does not accept data that contains inf values.

Example


Generate a bell-curve histogram from Gaussian data.

```
x = -4:0.1:4;
y = randn(10000,1);
hist(y,x)
```



Change the color of the graph so that the bins are red and the edges of the bins are white.

```
h = findobj(gca,'Type','patch');
set(h,'FaceColor','r','EdgeColor','w')
```



See Also

bar, ColorSpec, histc, mode, patch, rose, stairs

"Specialized Plotting" on page 1-98 for related functions

"Histograms" for examples

Histogram count

Syntax

```
n = histc(x,edges)
n = histc(x,edges,dim)
[n,bin] = histc(...)
```

Description

n = histc(x,edges) counts the number of values in vector x that
fall between the elements in the edges vector (which must contain
monotonically nondecreasing values). n is a length(edges) vector
containing these counts. No elements of x can be complex.

n(k) counts the value x(i) if edges(k) <= x(i) < edges(k+1). The last bin counts any values of x that match edges(end). Values outside the values in edges are not counted. Use -inf and inf in edges to include all non-NaN values.

For matrices, histc(x,edges) returns a matrix of column histogram counts. For N-D arrays, histc(x,edges) operates along the first nonsingleton dimension.

n = histc(x, edges, dim) operates along the dimension dim.

[n,bin] = histc(...) also returns an index matrix bin. If x is a vector, n(k) = sum(bin==k). bin is zero for out of range values. If x is an M-by-N matrix, then

```
for j=1:N,

n(k,j) = sum(bin(:,j)==k);

end
```


To plot the histogram, use the bar command.

Examples

Generate a cumulative histogram of a distribution.

Consider the following distribution:

```
x = -2.9:0.1:2.9;
y = randn(10000,1);
figure(1), hist(y,x)
```




Calculate number of elements in each bin

$$n_{elements} = histc(y,x);$$

Calculate the cumulative sum of these elements using cumsum

Plot the cumulative histogram



See Also

hist, mode

"Specialized Plotting" on page 1-98 for related functions

Retain current graph in figure

Syntax

hold on
hold off
hold all
hold
hold(axes handle,...)

Description

The hold function determines whether new graphics objects are added to the graph or replace objects in the graph. hold toggles the NextPlot property between the add and replace states.

hold on retains the current plot and certain axes properties so that subsequent graphing commands add to the existing graph. If no current axes exist before you call hold on, MATLAB creates new axes and retains the default properties. However, some axes properties change to accommodate additional graphics objects. For example, the axes' limits increase when the data requires them to do so. hold on sets the NextPlot property of the current figure and axes to add.

hold off resets axes properties to their defaults before drawing new plots. hold off is the default. hold off sets the NextPlot property of the current axes to replace.

hold all holds the plot and the current line color and line style so that subsequent plotting commands do not reset the ColorOrder and LineStyleOrder property values to the beginning of the list. Plotting commands continue cycling through the predefined colors and linestyles from where the last plot stopped in the list.

hold toggles the hold state between adding to the graph and replacing the graph.

hold (axes_handle,...) applies the hold to the axes identified by the handle axes_handle. The hold function sets the NextPlot property of the current figure and the current axes. If several axes objects exist in a figure window, each axes has its own hold state. hold also creates an axes if one does not exist.

Test the hold state using the ishold function.

hold

See Also axis | cla | ishold | newplot

How To • NextPlot

home

Purpose

Send the cursor home

Syntax

home

Description

home moves the cursor to the upper-left corner of the window. When using the MATLAB desktop, home also scrolls the visible text in the window up and out of view. You can use the scroll bar to see what was previously on the screen.

Examples

Execute a MATLAB command that displays something in the Command Window and then run the home function. home moves the cursor to the upper-left corner of the screen and clears the screen.

magic(5)

ans =

17	24	1	8	15
23	5	7	14	16
4	6	13	20	22
10	12	19	21	3
11	18	25	2	9

home

See Also

clc

Concatenate arrays horizontally

Syntax

C = horzcat(A1, A2, ...)

Description

C = horzcat(A1, A2, ...) horizontally concatenates matrices A1, A2, and so on. All matrices in the argument list must have the same number of rows.

horzcat concatenates N-dimensional arrays along the second dimension. The first and remaining dimensions must match.

MATLAB calls C = horzcat(A1, A2,...) for the syntax C = [A1 A2 ...] when any of A1, A2, etc., is an object.

Examples

Create a 3-by-5 matrix, A, and a 3-by-3 matrix, B. Then horizontally concatenate A and B.

$$A = magic(5);$$

 $A(4:5,:) = []$

% Create 3-by-5 matrix, A

A =

$$B = magic(3)*100$$

% Create 3-by-3 matrix, B

$$C = horzcat(A, B)$$

% Horizontally concatenate A and B

horzcat

See Also

vertcat, cat, strcat, strvcat, special character[]

horzcat (tscollection)

Purpose Horizontal concatenation for tscollection objects

Syntax tsc = horzcat(tsc1,tsc2,...)

Description tsc = horzcat(tsc1,tsc2,...) performs horizontal concatenation

for tscollection objects:

 $tsc = [tsc1 \ tsc2 \dots]$

This operation combines multiple tscollection objects, which must

have the same time vectors, into one tscollection containing

timeseries objects from all concatenated collections.

See Also tscollection, vertcat (tscollection)

hostid

Purpose Server host identification number

Syntax id = hostid

Description id = hostid usually returns a single element cell array containing the

MATLAB server host identifier as a string. On UNIX⁷ platforms, there can be more than one identifier. In that case, hostid returns a cell

array with an identifier in each cell.

7. UNIX is a registered trademark of The Open Group in the United States and other countries.

Convert HSV colormap to RGB colormap

Syntax

M = hsv2rgb(H)

rgb_image = hsv2rgb(hsv_image)

Description

M = hsv2rgb(H) converts a hue-saturation-value (HSV) colormap to a red-green-blue (RGB) colormap. H is an m-by-3 matrix, where m is the number of colors in the colormap. The columns of H represent hue, saturation, and value, respectively. M is an m-by-3 matrix. Its columns are intensities of red, green, and blue, respectively.

rgb_image = hsv2rgb(hsv_image) converts the HSV image to the equivalent RGB image. HSV is an *m*-by-*n*-by-3 image array whose three planes contain the hue, saturation, and value components for the image. RGB is returned as an *m*-by-*n*-by-3 image array whose three planes contain the red, green, and blue components for the image.

Remarks

As H(:,1) varies from 0 to 1, the resulting color varies from red through yellow, green, cyan, blue, and magenta, and returns to red. When H(:,2) is 0, the colors are unsaturated (i.e., shades of gray). When H(:,2) is 1, the colors are fully saturated (i.e., they contain no white component). As H(:,3) varies from 0 to 1, the brightness increases.

The MATLAB hsv colormap uses hsv2rgb([huesaturationvalue]) where hue is a linear ramp from 0 to 1, and saturation and value are all 1's.

See Also

brighten, colormap, rgb2hsv

"Color Operations" on page 1-108 for related functions

Square root of sum of squares

Syntax

c = hypot(a,b)

Description

c = hypot(a,b) returns the element-wise result of the following
equation, computed to avoid underflow and overflow:

```
c = sqrt(abs(a).^2 + abs(b).^2)
```

Inputs a and b must follow these rules:

- Both a and b must be single- or double-precision, floating-point arrays.
- The sizes of the a and b arrays must either be equal, or one a scalar and the other nonscalar. In the latter case, hypot expands the scalar input to match the size of the nonscalar input.
- If a or b is an empty array (0-by-N or N-by-0), the other must be the same size or a scalar. The result c is an empty array having the same size as the empty input(s).

 $\ensuremath{\mathsf{hypot}}$ returns the following in output c, depending upon the types of inputs:

• If the inputs to hypot are complex (w+xi and y+zi), then the statement c = hypot(w+xi,y+zi) returns the *positive real* result

```
c = sqrt(abs(w).^2+abs(x).^2+abs(y).^2+abs(z).^2)
```

- If a or b is -Inf. hypot returns Inf.
- If neither a nor b is Inf, but one or both inputs is NaN, hypot returns NaN.
- If all inputs are finite, the result is finite. The one exception is when both inputs are very near the value of the MATLAB constant realmax. The reason for this is that the equation c =

hypot(realmax, realmax) is theoretically sqrt(2)*realmax, which overflows to Inf.

Examples Example 1

To illustrate the difference between using the hypot function and coding the basic hypot equation in M-code, create an anonymous function that performs the same function as hypot, but without the consideration to underflow and overflow that hypot offers:

```
myhypot = @(a,b)sqrt(abs(a).^2+abs(b).^2);
```

Find the upper limit at which your coded function returns a useful value. You can see that this test function reaches its maximum at about 1e154, returning an infinite result at that point:

```
myhypot(1e153,1e153)
ans =
         1.4142e+153

myhypot(1e154,1e154)
ans =
         Inf
```

Do the same using the hypot function, and observe that hypot operates on values up to about 1e308, which is approximately equal to the value for realmax on your computer (the largest double-precision floating-point number you can represent on a particular computer):

```
hypot(1e308,1e308)
ans =
1.4142e+308
hypot(1e309,1e309)
ans =
Inf
```

Example 2

hypot(a,a) theoretically returns sqrt(2)*abs(a), as shown in this example:

```
x = 1.271161e308;
y = x * sqrt(2)
y =
   1.7977e+308
y = hypot(x,x)
y =
   1.7977e+308
```

Algorithm

hypot uses FDLIBM, which was developed at SunSoft, a Sun Microsystems business, by Kwok C. Ng, and others. For information about FDLIBM, see http://www.netlib.org.

See Also

sqrt, abs, norm

Purpose Imaginary unit

Syntax i

a+bi x+i*y

Description As

As the basic imaginary unit sqrt(-1), i is used to enter complex numbers. Since i is a function, it can be overridden and used as a variable. This permits you to use i as an index in for loops, etc.

If desired, use the character i without a multiplication sign as a suffix in forming a complex numerical constant.

You can also use the character j as the imaginary unit.

Examples Z = 2+3i

Z = x+i*y

Z = r*exp(i*theta)

See Also conj, imag, j, real

idealfilter (timeseries)

Purpose

Apply ideal (noncausal) filter to timeseries object

Syntax

ts2 = idealfilter(ts1,Interval,FilterType)

ts2 = idealfilter(ts1,Interval,FilterType,Index)

Description

ts2 = idealfilter(ts1,Interval,FilterType) applies an ideal filter of FilterType 'pass' or 'notch' to one or more frequency intervals specified by Interval for the timeseries object ts1. To specify several frequency intervals, use an n-by-2 array of start and end frequencies, where n represents the number of intervals.

ts2 = idealfilter(ts1,Interval,FilterType,Index) applies an ideal filter and uses the optional Index integer array to specify the columns or rows to filter. If you set ts1.IsTimeFirst to true, then Index specifies one or more data columns. If you set ts1.IsTimeFirst to false, then Index specifies one or more data rows.

When to Use the Ideal Filter

Ideal filters require data to have a mean of zero, and prepare the data by subtracting its mean. You can restore the filtered signal amplitude by adding the mean of the input data to the filter output values. The following example illustrates how to do this.

Use the ideal *notch* filter when you want to remove variations in a specific frequency range. Alternatively, use the ideal *pass* filter to allow only the variations in a specific frequency range.

These filters are *ideal* in the sense that they are *not realizable*; an ideal filter is noncausal and the ends of the filter amplitude are perfectly flat in the frequency domain.

If the time-series data is sampled nonuniformly, filtering resamples this data on a uniform time vector.

All NaNs in the time series are interpolated before filtering, using the interpolation method you assigned to the timeseries object.

Examples

First, apply an ideal notch filter, and then apply a pass filter to the data in count.dat:

idealfilter (timeseries)

1 Load the matrix count into the workspace:

```
load count.dat;
```

2 Create a timeseries object from column one of this matrix. Specify a time vector that ranges from 1 to 24 s in 1-s intervals. Also obtain the mean of the data:

```
count1=timeseries(count(:,1),1:24);
countmean = mean(count1);
```

3 Enter the frequency interval in hertz for filtering the data:

```
interval=[0.08 0.2];
```


4 Invoke an ideal notch filter:

```
idealfilter_countn = idealfilter(count1,interval,'notch')
```

5 Compare the original data and the shaped data on a line plot:


```
plot(count1,'-.'), grid on, hold on
plot(idealfilter countn,'-')
```

6 Restore the mean to the filtered data and show it on the line plot, adding a legend and a title:



7 Repeat the process using a pass rather than a notch filter:

idealfilter (timeseries)



See Also

filter (timeseries), timeseries

Integer division with rounding option

Syntax

```
C = idivide(A, B, opt)
C = idivide(A, B)
C = idivide(A, B, 'fix')
C = idivide(A, B, 'round')
C = idivide(A, B, 'floor')
C = idivide(A, B, 'ceil')
```

Description

C = idivide(A, B, opt) is the same as A./B for integer classes except that fractional quotients are rounded to integers using the optional rounding mode specified by opt. The default rounding mode is 'fix'. Inputs A and B must be real and must have the same dimensions unless one is a scalar. At least one of the arguments A and B must belong to an integer class, and the other must belong to the same integer class or be a scalar double. The result C belongs to the integer class.

C = idivide(A, B) is the same as A./B except that fractional quotients are rounded toward zero to the nearest integers.

C = idivide(A, B, 'fix') is the same as the syntax shown immediately above.

C = idivide(A, B, 'round') is the same as A./B for integer classes. Fractional quotients are rounded to the nearest integers.

C = idivide(A, B, 'floor') is the same as A./B except that fractional quotients are rounded toward negative infinity to the nearest integers.

C = idivide(A, B, 'ceil') is the same as A./B except that the fractional quotients are rounded toward infinity to the nearest integers.

Examples

idivide

idivide(a,b,'round') % Returns [-1 1]

See Also ldivide, rdivide, mldivide, mrdivide

Execute statements if condition is true

Syntax

if expression, statements, end

Description

if expression, statements, end evaluates expression and, if the evaluation yields logical 1 (true) or a nonzero result, executes one or more MATLAB commands denoted here as statements.

expression is a MATLAB expression, usually consisting of variables or smaller expressions joined by relational operators (e.g., count < limit), or logical functions (e.g., isreal(A)). Simple expressions can be combined by logical operators (&&, ||, ~) into compound expressions such as the following. MATLAB evaluates compound expressions from left to right, adhering to operator precedence rules.

```
(count < limit) && ((height - offset) >= 0)
```

Nested if statements must each be paired with a matching end.

The if function can be used alone or with the else and elseif functions. When using elseif and/or else within an if statement, the general form of the statement is

```
if expression1
    statements1
elseif expression2
    statements2
else
    statements3
end
```

See "Program Control Statements" in the MATLAB Programming Fundamentals documentation for more information on controlling the flow of your program code.

Remarks Nonscalar Expressions

If the evaluated expression yields a nonscalar value, then every element of this value must be true or nonzero for the entire expression to be considered true. For example, the statement if (A < B) is true only if each element of matrix A is less than its corresponding element in matrix B. See Example 2, below.

Partial Evaluation of the expression Argument

Within the context of an if or while expression, MATLAB does not necessarily evaluate all parts of a logical expression. In some cases it is possible, and often advantageous, to determine whether an expression is true or false through only partial evaluation.

For example, if A equals zero in statement 1 below, then the expression evaluates to false, regardless of the value of B. In this case, there is no need to evaluate B and MATLAB does not do so. In statement 2, if A is nonzero, then the expression is true, regardless of B. Again, MATLAB does not evaluate the latter part of the expression.

```
1) if (A && B) 2) if (A || B)
```

You can use this property to your advantage to cause MATLAB to evaluate a part of an expression only if a preceding part evaluates to the desired state. Here are some examples.

```
while (b \sim= 0) && (a/b > 18.5)
if exist('myfun.m') && (myfun(x) >= y)
if iscell(A) && all(cellfun('isreal', A))
```

Empty Arrays

In most cases, using if on an empty array treats the array as false. There are some conditions however under which if evaluates as true on an empty array. Two examples of this, where A is equal to [], are

```
if all(A), do_something, end
if 1|A, do_something, end
```

The latter expression is true because of short-circuiting, which causes MATLAB to ignore the right side operand of an OR statement whenever the left side evaluates to true.

Short-Circuiting Behavior

When used in the context of an if or while expression, and only in this context, the element-wise | and & operators use short-circuiting in evaluating their expressions. That is, A|B and A&B ignore the second operand, B, if the first operand, A, is sufficient to determine the result.

See "Short-Circuiting in Elementwise Operators" for more information on this.

Examples Example 1 - Simple if Statement

In this example, if both of the conditions are satisfied, then the student passes the course.

```
if ((attendance >= 0.90) && (grade_average >= 60))
  pass = 1;
end;
```

Example 2 - Nonscalar Expression

Given matrices A and B.

Expression	Evaluates As	Because
A < B	false	A(1,1) is not less than $B(1,1)$.
A < (B + 1)	true	Every element of A is less than that same element of B with 1 added.
A & B	false	A(1,2) is false, and B is ignored due to short-circuiting.
B < 5	true	Every element of B is less than 5.

See Also

else, elseif, end, for, while, switch, break, return, relational operators, logical operators (elementwise and short-circuit),

Inverse discrete Fourier transform

Syntax

```
y = ifft(X)
y = ifft(X,n)
y = ifft(X,[],dim)
y = ifft(X,n,dim)
y = ifft(..., 'symmetric')
y = ifft(..., 'nonsymmetric')
```

Description

y = ifft(X) returns the inverse discrete Fourier transform (DFT) of vector X, computed with a fast Fourier transform (FFT) algorithm. If X is a matrix, ifft returns the inverse DFT of each column of the matrix.

ifft tests X to see whether vectors in X along the active dimension are *conjugate symmetric*. If so, the computation is faster and the output is real. An N-element vector x is conjugate symmetric if x(i) = conj(x(mod(N-i+1,N)+1)) for each element of x.

If X is a multidimensional array, ifft operates on the first non-singleton dimension.

y = ifft(X,n) returns the n-point inverse DFT of vector X.

y = ifft(X,[],dim) and y = ifft(X,n,dim) return the inverse DFT of X across the dimension dim.

y = ifft(..., 'symmetric') causes ifft to treat X as conjugate symmetric along the active dimension. This option is useful when X is not exactly conjugate symmetric, merely because of round-off error.

y = ifft(..., 'nonsymmetric') is the same as calling ifft(...) without the argument 'nonsymmetric'.

For any X, ifft(fft(X)) equals X to within roundoff error.

Algorithm

The algorithm for ifft(X) is the same as the algorithm for fft(X), except for a sign change and a scale factor of n = length(X). As for fft, the execution time for ifft depends on the length of the transform. It is fastest for powers of two. It is almost as fast for lengths that have

only small prime factors. It is typically several times slower for lengths that are prime or which have large prime factors.

Note You might be able to increase the speed of ifft using the utility function fftw, which controls how MATLAB software optimizes the algorithm used to compute an FFT of a particular size and dimension.

Data Type Support

ifft supports inputs of data types double and single. If you call ifft with the syntax y = ifft(X, ...), the output y has the same data type as the input X.

See Also

fft, fft2, ifft1, ifftn, ifftshift, fftw, ifft2, ifftn dftmtx and freqz, in the Signal Processing Toolbox software.

2-D inverse discrete Fourier transform

Syntax

```
Y = ifft2(X)
Y = ifft2(X,m,n)
y = ifft2(..., 'symmetric')
y = ifft2(..., 'nonsymmetric')
```

Description

Y = ifft2(X) returns the two-dimensional inverse discrete Fourier transform (DFT) of X, computed with a fast Fourier transform (FFT) algorithm. The result Y is the same size as X.

ifft2 tests X to see whether it is *conjugate symmetric*. If so, the computation is faster and the output is real. An M-by-N matrix X is conjugate symmetric if X(i,j) = conj(X(mod(M-i+1, M) + 1, mod(N-j+1, N) + 1)) for each element of X.

Y = ifft2(X,m,n) returns the m-by-n inverse fast Fourier transform of matrix X.

y = ifft2(..., 'symmetric') causes ifft2 to treat X as conjugate symmetric. This option is useful when X is not exactly conjugate symmetric, merely because of round-off error.

y = ifft2(..., 'nonsymmetric') is the same as calling ifft2(...) without the argument 'nonsymmetric'.

For any X, ifft2(fft2(X)) equals X to within roundoff error.

Algorithm

The algorithm for ifft2(X) is the same as the algorithm for fft2(X), except for a sign change and scale factors of [m,n] = size(X). The execution time for ifft2 depends on the length of the transform. It is fastest for powers of two. It is almost as fast for lengths that have only small prime factors. It is typically several times slower for lengths that are prime or which have large prime factors.

Note You might be able to increase the speed of ifft2 using the utility function fftw, which controls how MATLAB software optimizes the algorithm used to compute an FFT of a particular size and dimension.

Data Type Support

ifft2 supports inputs of data types double and single. If you call ifft2 with the syntax y = ifft2(X, ...), the output y has the same data type as the input X.

See Also

dftmtx and freqz in the Signal Processing Toolbox, and:

fft2, fftw, fftshift, ifft, ifftn, ifftshift

N-D inverse discrete Fourier transform

Syntax

```
Y = ifftn(X)
Y = ifftn(X,siz)
y = ifftn(..., 'symmetric')
y = ifftn(..., 'nonsymmetric')
```

Description

Y = ifftn(X) returns the n-dimensional inverse discrete Fourier transform (DFT) of X, computed with a multidimensional fast Fourier transform (FFT) algorithm. The result Y is the same size as X.

ifftn tests X to see whether it is *conjugate symmetric*. If so, the computation is faster and the output is real. An N1-by-N2-by- ... Nk array X is conjugate symmetric if

```
X(i1,i2, ...,ik) = conj(X(mod(N1-i1+1,N1)+1, mod(N2-i2+1,N2)+1, ... mod(Nk-ik+1,Nk)+1))
```

for each element of X.

Y = ifftn(X,siz) pads X with zeros, or truncates X, to create a multidimensional array of size siz before performing the inverse transform. The size of the result Y is siz.

y = ifftn(..., 'symmetric') causes ifftn to treat X as conjugate symmetric. This option is useful when X is not exactly conjugate symmetric, merely because of round-off error.

y = ifftn(..., 'nonsymmetric') is the same as calling ifftn(...) without the argument 'nonsymmetric'.

Remarks

For any X, ifftn(fftn(X)) equals X within roundoff error.

Algorithm

ifftn(X) is equivalent to

```
Y = X;
for p = 1:length(size(X))
    Y = ifft(Y,[],p);
end
```

This computes in-place the one-dimensional inverse DFT along each dimension of X.

The execution time for ifftn depends on the length of the transform. It is fastest for powers of two. It is almost as fast for lengths that have only small prime factors. It is typically several times slower for lengths that are prime or which have large prime factors.

Note You might be able to increase the speed of ifftn using the utility function fftw, which controls how MATLAB software optimizes the algorithm used to compute an FFT of a particular size and dimension.

Data Type Support

ifftn supports inputs of data types double and single. If you call ifftn with the syntax y = ifftn(X, ...), the output y has the same data type as the input X.

See Also

fftn, fftw, ifft, ifft2, ifftshift

ifftshift

Purpose Inverse FFT shift

Syntax ifftshift(X)

ifftshift(X,dim)

Description ifftshift(X) swaps the left and right halves of the vector X. For

matrices, ifftshift(X) swaps the first quadrant with the third and the second quadrant with the fourth. If X is a multidimensional array,

ifftshift(X) swaps "half-spaces" of X along each dimension.

ifftshift(X,dim) applies the ifftshift operation along the

dimension dim.

Note ifftshift undoes the results of fftshift. If the matrix X contains an odd number of elements, ifftshift(fftshift(X)) must be done to obtain the original X. Simply performing fftshift(X) twice will not produce X.

See Also fft, fft2, fftn, fftshift

Purpose Sparse incomplete LU factorization

Syntax ilu(A,setup)

[L,U] = ilu(A,setup)
[L,U,P] = ilu(A,setup)

Description

ilu produces a unit lower triangular matrix, an upper triangular matrix, and a permutation matrix.

ilu(A, setup) computes the incomplete LU factorization of A. setup is an input structure with up to five setup options. The fields must be named exactly as shown in the table below. You can include any number of these fields in the structure and define them in any order. Any additional fields are ignored.

Field Name	Description
type	Type of factorization. Values for type include: • 'nofill'—Performs ILU factorization with 0 level of fill in, known as ILU(0). With type set to 'nofill', only the milu setup option is used; all other fields are ignored.
	• 'crout'—Performs the Crout version of ILU factorization, known as ILUC. With type set to 'crout', only the droptol and milu setup options are used; all other fields are ignored.
	• 'ilutp' (default)—Performs ILU factorization with threshold and pivoting.
	If type is not specified, the ILU factorization with pivoting ILUTP is performed. Pivoting is never performed with type set to 'nofill' or 'crout'.

Field Name	Description
droptol	Drop tolerance of the incomplete LU factorization. droptol is a non-negative scalar. The default value is 0, which produces the complete LU factorization.
	The nonzero entries of U satisfy
	<pre>abs(U(i,j)) >= droptol*norm((A:,j)),</pre>
	with the exception of the diagonal entries, which are retained regardless of satisfying the criterion. The entries of L are tested against the local drop tolerance before being scaled by the pivot, so for nonzeros in L
	abs(L(i,j)) >= droptol*norm(A(:,j))/U(j,j).
milu	Modified incomplete LU factorization. Values for milu include:
	• 'row'—Produces the row-sum modified incomplete LU factorization. Entries from the newly-formed column of the factors are subtracted from the diagonal of the upper triangular factor, U, preserving column sums. That is, A*e = L*U*e, where e is the vector of ones.
	• 'col'—Produces the column-sum modified incomplete LU factorization. Entries from the newly-formed column of the factors are subtracted from the diagonal of the upper triangular factor, U, preserving column sums. That is, e'*A = e'*L*U.
	• 'off' (default)—No modified incomplete LU factorization is produced.

Field Name	Description
udiag	If udiag is 1, any zeros on the diagonal of the upper triangular factor are replaced by the local drop tolerance. The default is 0.
thresh	Pivot threshold between 0 (forces diagonal pivoting) and 1, the default, which always chooses the maximum magnitude entry in the column to be the pivot.

ilu(A, setup) returns L+U-speye(size(A)), where L is a unit lower triangular matrix and U is an upper triangular matrix.

[L,U] = ilu(A, setup) returns a unit lower triangular matrix in L and an upper triangular matrix in U.

[L,U,P] = ilu(A,setup) returns a unit lower triangular matrix in L, an upper triangular matrix in U, and a permutation matrix in P.

Remarks

These incomplete factorizations may be useful as preconditioners for a system of linear equations being solved by iterative methods such as BICG (BiConjugate Gradients), GMRES (Generalized Minimum Residual Method).

Limitations

ilu works on sparse square matrices only.

Examples

Start with a sparse matrix and compute the LU factorization.

```
A = gallery('neumann', 1600) + speye(1600);
setup.type = 'crout';
setup.milu = 'row';
setup.droptol = 0.1;
[L,U] = ilu(A,setup);
e = ones(size(A,2),1);
norm(A*e-L*U*e)
ans =
```

1.4251e-014

This shows that A and L*U, where L and U are given by the modified Crout ILU, have the same row-sum.

Start with a sparse matrix and compute the LU factorization.

This shows that A has 7840 nonzeros, the complete LU factorization has 126478 nonzeros, and the incomplete LU factorization, with 0 level of fill-in, has 7840 nonzeros, the same amount as A.

See Also

bicg, cholinc,gmres,luinc

References

[1] Saad, Yousef, *Iterative Methods for Sparse Linear Systems*, PWS Publishing Company, 1996, Chapter 10 - Preconditioning Techniques.

Convert image to movie frame

Syntax

```
f = im2frame(X,map)
f = im2frame(X)
```

Description

f = im2frame(X,map) converts the indexed image X and associated colormap map into a movie frame f. If X is a truecolor (m-by-n-by-3) image, then map is optional and has no effect.

Typical usage:

```
M(1) = im2frame(X1,map);
M(2) = im2frame(X2,map);
...
M(n) = im2frame(Xn,map);
movie(M)
```

f = im2frame(X) converts the indexed image X into a movie frame f using the current colormap if X contains an indexed image.

See Also

frame2im, movie

"Bit-Mapped Images" on page 1-101 for related functions

Convert image to Java image

Syntax

```
jimage = im2java(I)
jimage = im2java(X,MAP)
jimage = im2java(RGB)
```

Description

To work with a MATLAB image in the Java environment, you must convert the image from its MATLAB representation into an instance of the Java image class, java.awt.Image.

jimage = im2java(I) converts the intensity image I to an instance of the Java image class, java.awt.Image.

jimage = im2java(X,MAP) converts the indexed image X, with
colormap MAP, to an instance of the Java image class, java.awt.Image.

jimage = im2java(RGB) converts the RGB image RGB to an instance of the Java image class, java.awt.Image.

Class Support

The input image can be of class uint8, uint16, or double.


Note Java requires uint8 data to create an instance of the Java image class, java.awt.Image. If the input image is of class uint8, jimage contains the same uint8 data. If the input image is of class double or uint16, im2java makes an equivalent image of class uint8, rescaling or offsetting the data as necessary, and then converts this uint8 representation to an instance of the Java image class, java.awt.Image.

Example

This example reads an image into the MATLAB workspace and then uses im2java to convert it into an instance of the Java image class.

```
I = imread('ngc6543a.jpg');
javaImage = im2java(I);
frame = javax.swing.JFrame;
icon = javax.swing.ImageIcon(javaImage);
label = javax.swing.JLabel(icon);
```

```
frame.getContentPane.add(label);
frame.pack
frame.show
```



See Also "Bit-Mapped Images" on page 1-101 for related functions

imag

Purpose Imaginary part of complex number

Syntax Y = imag(Z)

Description Y = imag(Z) returns the imaginary part of the elements of array Z.

Examples imag(2+3i)

ans =

3

See Also conj, i, j, real

Display image object



plot(t,y) ▼

GUI Alternatives

To plot a selected matrix as an image use the Plot Selector

in the Workspace Browser, or use the Figure Palette Plot Catalog. Manipulate image characteristics in *plot edit* mode with the Property Editor. For details, see Plotting Tools — Interactive Plotting in the MATLAB Graphics documentation and Creating Graphics from the Workspace Browser in the MATLAB Desktop Tools documentation.

Syntax

```
image(C)
image(x,y,C)
image(x,y,C,'PropertyName',PropertyValue,...)
image('PropertyName',PropertyValue,...)
handle = image(...)
```

Properties

For a list of properties, see Image Properties.

Description

image creates an image graphics object by interpreting each element in a matrix as an index into the figure's colormap or directly as RGB values, depending on the data specified.

The image function has two forms:

- A high-level function that calls newplot to determine where to draw the graphics objects and sets the following axes properties:
 - XLim and YLim to enclose the image
 - Layer to top to place the image in front of the tick marks and grid lines
 - YDir to reverse
 - View to [0 90]

image

• A low-level function that adds the image to the current axes without calling newplot. The low-level function argument list can contain only property name/property value pairs.

You can specify properties as property name/property value pairs, structure arrays, and cell arrays (see set and get for examples of how to specify these data types).

image(C) displays matrix C as an image. Each element of C specifies the color of a rectangular segment in the image.

image (x,y,C), where x and y are two-element vectors, specifies the range of the x- and y-axis labels, but produces the same image as image (C). This can be useful, for example, if you want the axis tick labels to correspond to real physical dimensions represented by the image. If x(1) > x(2) or y(1) > y(2), the image is flipped left-right or up-down, respectively. It can also be useful when you want to place the image within a set of axes already created. In this case, use hold on with the current figure and enter x and y values corresponding to the corners of the desired image location. The image is stretched and oriented as applicable.

image(x,y,C,'PropertyName',PropertyValue,...) is a high-level function that also specifies property name/property value pairs. For a description of the properties, see Image Properties. This syntax calls newplot before drawing the image.

image ('PropertyName', PropertyValue,...) is the low-level syntax of the image function. It specifies only property name/property value pairs as input arguments.

handle = image(...) returns the handle of the image object it creates. You can obtain the handle with all forms of the image function.

Remarks

Image data can be either indexed or true color. An indexed image stores colors as an array of indices into the figure colormap. A true color image does not use a colormap; instead, the color values for each pixel are stored directly as RGB triplets. In MATLAB graphics, the CData property of a truecolor image object is a three-dimensional (m-by-n-by-3)

array. This array consists of three m-by-n matrices (representing the red, green, and blue color planes) concatenated along the third dimension.

The imread function reads image data into MATLAB arrays from graphics files in various standard formats, such as TIFF. You can write MATLAB image data to graphics files using the imwrite function. imread and imwrite both support a variety of graphics file formats and compression schemes.

When you read image data into the MATLAB workspace using imread, the data is usually stored as an array of 8-bit integers. However, imread also supports reading 16-bit-per-pixel data from TIFF and PNG files. These are more efficient storage methods than the double-precision (64-bit) floating-point numbers that MATLAB typically uses. However, it is necessary to interpret 8-bit and 16-bit image data differently from 64-bit data. This table summarizes these differences.

You cannot interactively pan or zoom outside the *x*-limits or *y*-limits of an image, unless the axes limits are already been set outside the bounds of the image, in which case there is no such restriction. If other objects (such as lineseries) occupy the axes and extend beyond the bounds of the image, you can pan or zoom to the bounds of the other objects, but no further.

Image Type	Double-Precision Data (double Array)	8-Bit Data (uint8 Array) 16-Bit Data (uint16 Array)
Indexed (colormap)	Image is stored as a two-dimensional (m-by-n) array of integers in the range [1, length(colormap)]; colormap is an m-by-3 array of floating-point values in the range [0, 1].	Image is stored as a two-dimensional (m-by-n) array of integers in the range [0, 255] (uint8) or [0, 65535] (uint16); colormap is an m-by-3 array of floating-point values in the range [0, 1].

Image Type	Double-Precision Data (double Array)	8-Bit Data (uint8 Array) 16-Bit Data (uint16 Array)
True color (RGB)	Image is stored as a three-dimensional (m-by-n-by-3) array of floating-point values in the range [0, 1].	Image is stored as a three-dimensional (m-by-n-by-3) array of integers in the range [0, 255] (uint8) or [0, 65535] (uint16).

By default, image plots the *y*-axis from lowest to highest value, top to bottom. To reverse this, type set(gca, 'YDir', 'normal'). This will reverse both the *y*-axis and the image.

Indexed Images

In an indexed image of class double, the value 1 points to the first row in the colormap, the value 2 points to the second row, and so on. In a uint8 or uint16 indexed image, there is an offset; the value 0 points to the first row in the colormap, the value 1 points to the second row, and so on.

If you want to convert a uint8 or uint16 indexed image to double, you need to add 1 to the result. For example,

```
X64 = double(X8) + 1;
or
X64 = double(X16) + 1;
```

To convert from double to uint8 or uint16, you need to first subtract 1, and then use round to ensure all the values are integers.

```
X8 = uint8(round(X64 - 1));
or
X16 = uint16(round(X64 - 1));
```

When you write an indexed image using imwrite, values are automatically converted if necessary.

Colormaps

MATLAB colormaps are always m-by-3 arrays of double-precision floating-point numbers in the range [0, 1]. In most graphics file formats, colormaps are stored as integers, but MATLAB colormaps cannot have integer values. imread and imwrite automatically convert colormap values when reading and writing files.

True Color Images

In a true color image of class double, the data values are floating-point numbers in the range [0, 1]. In a true color image of class uint8, the data values are integers in the range [0, 255], and for true color images of class uint16 the data values are integers in the range [0, 65535].

If you want to convert a true color image from one data type to the other, you must rescale the data. For example, this statement converts a uint8 true color image to double.

```
RGB64 = double(RGB8)/255;

or for uint16 images,

RGB64 = double(RGB16)/65535;

This statement converts a double true color image to uint8:

RGB8 = uint8(round(RGB64*255));

or to obtain uint16 images, type


RGB16 = uint16(round(RGB64*65535));
```

When you write a true color image using imwrite, values are automatically converted if necessary..

Example

Example 1

Load a mat-file containing a photograph of a colorful primate. Display the indexed image using its associated colormap.




Example 2

Load a JPEG image file of the Cat's Eye Nebula from the Hubble Space Telescope (image courtesy NASA). Display the original image using its RGB color values (left) as a subplot. Create a linked subplot (same size and scale) to display the transformed intensity image as a heat map (right).

figure

```
ax(1) = subplot(1,2,1);
rgb = imread('ngc6543a.jpg');
image(rgb); title('RGB image')
ax(2) = subplot(122);
im = mean(rgb,3);
image(im); title('Intensity Heat Map')
colormap(hot(256))
linkaxes(ax,'xy')
axis(ax,'image')
```



Setting Default Properties

You can set default image properties on the axes, figure, and root object levels:

```
set(0, 'DefaultImageProperty', PropertyValue...)
set(gcf, 'DefaultImageProperty', PropertyValue...)
set(gca, 'DefaultImageProperty', PropertyValue...)
```

where *Property* is the name of the image property and *PropertyValue* is the value you are specifying. Use set and get to access image properties.

See Also

colormap, imagesc, imfinfo, imread, imwrite, newplot, pcolor, surface

image

Image Properties for property descriptions

"Bit-Mapped Images" on page 1-101 for related functions

Tutorials

For more information, see "Displaying Bit-Mapped Images" in the MATLAB Graphics User Guide.

Define image properties

Creating Image Objects

Use image to create image objects.

Modifying Properties

You can set and query graphics object properties in two ways:

- "The Property Editor" is an interactive tool that enables you to see and change object property values.
- The set and get commands enable you to set and query the values of properties.

To change the default values of properties, see "Setting Default Property Values".

See "Core Graphics Objects" for general information about this type of object.

Image Property Descriptions

This section lists property names along with the types of values each property accepts.

AlphaData

m-by-n matrix of double or uint8

The transparency data. A matrix of non-NaN values specifying the transparency of each face or vertex of the object. The AlphaData can be of class double or uint8.

MATLAB software determines the transparency in one of three ways:

- Using the elements of AlphaData as transparency values (AlphaDataMapping set to none)
- Using the elements of AlphaData as indices into the current alphamap (AlphaDataMapping set to direct)

 Scaling the elements of AlphaData to range between the minimum and maximum values of the axes ALim property (AlphaDataMapping set to scaled, the default)

AlphaDataMapping {none} | direct| scaled

Transparency mapping method. This property determines how MATLAB interprets indexed alpha data. It can be any of the following:

- none The transparency values of AlphaData are between 0 and 1 or are clamped to this range (the default).
- scaled Transform the AlphaData to span the portion of the alphamap indicated by the axes ALim property, linearly mapping data values to alpha values.
- direct Use the AlphaData as indices directly into the alphamap. When not scaled, the data are usually integer values ranging from 1 to length(alphamap). MATLAB maps values less than 1 to the first alpha value in the alphamap, and values greater than length(alphamap) to the last alpha value in the alphamap. Values with a decimal portion are fixed to the nearest, lower integer. If AlphaData is an array of uint8 integers, then the indexing begins at 0 (i.e., MATLAB maps a value of 0 to the first alpha value in the alphamap).

Annotation

hg.Annotation object Read Only

Control the display of image objects in legends. The Annotation property enables you to specify whether this image object is represented in a figure legend.

Querying the Annotation property returns the handle of an hg.Annotation object. The hg.Annotation object has a property called LegendInformation, which contains an hg.LegendEntry object.

Once you have obtained the hg.LegendEntry object, you can set its IconDisplayStyle property to control whether the image object is displayed in a figure legend:

IconDisplayStyle Value	Purpose
on	Represent this image object in a legend (default)
off	Do not include this image object in a legend
children	Same as on because image objects do not have children

Setting the IconDisplayStyle property

These commands set the IconDisplayStyle of a graphics object with handle hobj to off:

```
hAnnotation = get(hobj, 'Annotation');
hLegendEntry = get(hAnnotation', 'LegendInformation');
set(hLegendEntry, 'IconDisplayStyle', 'off')
```

Using the IconDisplayStyle property

See "Controlling Legends" for more information and examples.

```
BeingDeleted on | {off} Read Only
```

This object is being deleted. The BeingDeleted property provides a mechanism that you can use to determine if objects are in the process of being deleted. MATLAB sets the BeingDeleted property to on when the object's delete function callback is called (see the DeleteFcn property). It remains set to on while the delete function executes, after which the object no longer exists.

For example, an object's delete function might call other functions that act on a number of different objects. These functions might not need to perform actions on objects if the objects are going to be deleted, and therefore, can check the object's BeingDeleted property before acting.

BusyAction cancel | {queue}

Callback routine interruption. The BusyAction property enables you to control how MATLAB handles events that potentially interrupt executing callbacks. If there is a callback function executing, callbacks invoked subsequently always attempt to interrupt it.

If the Interruptible property of the object whose callback is executing is set to on (the default), then interruption occurs at the next point where the event queue is processed. If the Interruptible property is off, the BusyAction property (of the object owning the executing callback) determines how MATLAB handles the event. The choices are

- cancel Discard the event that attempted to execute a second callback routine.
- queue Queue the event that attempted to execute a second callback routine until the current callback finishes.

ButtonDownFcn

string or function handle

Button press callback function. A callback that executes whenever you press a mouse button while the pointer is over this object, but not over another graphics object.

See the figure's SelectionType property to determine if modifier keys were also pressed.

This property can be

- A string that is a valid MATLAB expression
- The name of a MATLAB file
- A function handle

Set this property to a function handle that references the callback. The expressions execute in the MATLAB workspace.

See "Function Handle Callbacks" for information on how to use function handles to define the callbacks.

CData

matrix or m-by-n-by-3 array

The image data. A matrix or 3-D array of values specifying the color of each rectangular area defining the image. image(C) assigns the values of C to CData. MATLAB determines the coloring of the image in one of three ways:


- Using the elements of CData as indices into the current colormap (the default) (CDataMapping set to direct)
- Scaling the elements of CData to range between the values min(get(gca, 'CLim')) and max(get(gca, 'CLim')) (CDataMapping set to scaled)
- Interpreting the elements of CData directly as RGB values (true color specification)

Note that the behavior of NaNs in image CData is not defined. See the image AlphaData property for information on using transparency with images.


A true color specification for CData requires an m-by-n-by-3 array of RGB values. The first page contains the red component, the second page the green component, and the third page the blue component of each element in the image. RGB values range from

0 to 1. The following picture illustrates the relative dimensions of CData for the two color models.

Indexed Colors




True Colors



If CData has only one row or column, the height or width respectively is always one data unit and is centered about the first YData or XData element respectively. For example, using a 4-by-1 matrix of random data,

```
C = rand(4,1);
image(C,'CDataMapping','scaled')
axis image
```

produces



scaled | {direct}

Direct or scaled indexed colors. This property determines whether MATLAB interprets the values in CData as indices into the figure colormap (the default) or scales the values according to the values of the axes CLim property.

When CDataMapping is direct, the values of CData should be in the range 1 to length(get(gcf, 'Colormap')). If you use true color specification for CData, this property has no effect. If CData is of type logical, 0's will index the first color of the colormap and 1's will index the second color.

Children

handles

The empty matrix; image objects have no children.

Clipping

on | off

Clipping mode. By default, MATLAB clips images to the axes rectangle. If you set Clipping to off, the image can be displayed outside the axes rectangle. For example, if you create an image, set hold to on, freeze axis scaling (with axis manual), and then create a larger image, it extends beyond the axis limits.

CreateFcn

string or function handle

Callback routine executed during object creation. This property defines a callback routine that executes when MATLAB creates an image object. You must define this property as a default value for images or in a call to the image function to create a new image object. For example, the statement

```
set(0, 'DefaultImageCreateFcn', 'axis image')
```

defines a default value on the root level that sets the aspect ratio and the axis limits so the image has square pixels. MATLAB executes this routine after setting all image properties. Setting this property on an existing image object has no effect.

The handle of the object whose CreateFcn is being executed is accessible only through the root CallbackObject property, which you can query using gcbo.

See "Function Handle Callbacks" for information on how to use function handles to define the callback function.

DeleteFcn

string or function handle

Callback executed during object deletion. A callback that executes when this object is deleted (e.g., this might happen when you issue a delete command on the object, its parent axes, or the figure containing it). MATLAB executes the callback before destroying the object's properties so the callback routine can query these values.

The handle of the object whose DeleteFcn is being executed is accessible only through the root CallbackObject property, which can be queried using gcbo.

See "Function Handle Callbacks" for information on how to use function handles to define the callback function.

See the BeingDeleted property for related information.

DisplayName

string (default is empty string)

String used by legend for this image object. The legend function uses the string defined by the DisplayName property to label this image object in the legend.

- If you specify string arguments with the legend function, DisplayName is set to this image object's corresponding string and that string is used for the legend.
- If DisplayName is empty, legend creates a string of the form, ['data' n], where n is the number assigned to the object based on its location in the list of legend entries. However, legend does not set DisplayName to this string.
- If you edit the string directly in an existing legend, DisplayName is set to the edited string.
- If you specify a string for the DisplayName property and create the legend using the figure toolbar, then MATLAB uses the string defined by DisplayName.

• To add programmatically a legend that uses the DisplayName string, call legend with the toggle or show option.

See "Controlling Legends" for more examples.

EraseMode

```
{normal} | none | xor | background
```

Erase mode. This property controls the technique MATLAB uses to draw and erase objects and their children. Alternative erase modes are useful for creating animated sequences, where control of the way individual objects are redrawn is necessary to improve performance and obtain the desired effect.

- normal Redraw the affected region of the display, performing the three-dimensional analysis necessary to ensure that all objects are rendered correctly. This mode produces the most accurate picture, but is the slowest. The other modes are faster, but do not perform a complete redraw and are therefore less accurate.
- none Do not erase objects when they are moved or destroyed.
 While the objects are still visible on the screen after erasing with EraseMode none, you cannot print these objects because MATLAB stores no information about their former locations.
- xor Draw and erase the object by performing an exclusive OR (XOR) with each pixel index of the screen behind it. Erasing the object does not damage the color of the objects behind it. However, the color of the erased object depends on the color of the screen behind it and it is correctly colored only when it is over the axes background color (or the figure background color if the axes Color property is set to none). That is, it isn't erased correctly if there are objects behind it.
- background Erase the graphics objects by redrawing them
 in the axes background color, (or the figure background color
 if the axes Color property is set to none). This damages other

graphics objects that are behind the erased object, but the erased object is always properly colored.

Printing with Nonnormal Erase Modes

MATLAB always prints figures as if the EraseMode of all objects is normal. This means graphics objects created with EraseMode set to none, xor, or background can look different on screen than on paper. On screen, MATLAB can mathematically combine layers of colors (e.g., performing an XOR on a pixel color with that of the pixel behind it) and ignore three-dimensional sorting to obtain greater rendering speed. However, these techniques are not applied to the printed output.

Set the axes background color with the axes Color property. Set the figure background color with the figure Color property.

You can use the MATLAB getframe command or other screen capture applications to create an image of a figure containing nonnormal mode objects.

```
HandleVisibility
{on} | callback | off
```

Control access to object's handle by command-line users and GUIs. This property determines when an object's handle is visible in its parent's list of children. HandleVisibility is useful for preventing command-line users from accidentally accessing objects that you need to protect for some reason.

- on Handles are always visible when HandleVisibility is on.
- callback Setting HandleVisibility to callback causes handles to be visible from within callback routines or functions invoked by callback routines, but not from within functions invoked from the command line. This provides a means to protect GUIs from command-line users, while allowing callback routines to have access to object handles.

• off — Setting HandleVisibility to off makes handles invisible at all times. This might be necessary when a callback invokes a function that might potentially damage the GUI (such as evaluating a user-typed string) and so temporarily hides its own handles during the execution of that function.

Functions Affected by Handle Visibility

When a handle is not visible in its parent's list of children, it cannot be returned by functions that obtain handles by searching the object hierarchy or querying handle properties. This includes get, findobj, gca, gcf, gco, newplot, cla, clf, and close.

Properties Affected by Handle Visibility

When a handle's visibility is restricted using callback or off, the object's handle does not appear in its parent's Children property, figures do not appear in the root's CurrentFigure property, objects do not appear in the root's CallbackObject property or in the figure's CurrentObject property, and axes do not appear in their parent's CurrentAxes property.

Overriding Handle Visibility

You can set the root ShowHiddenHandles property to on to make all handles visible regardless of their HandleVisibility settings (this does not affect the values of the HandleVisibility properties). See also findall.

Handle Validity

Handles that are hidden are still valid. If you know an object's handle, you can set and get its properties and pass it to any function that operates on handles.

Note If you change one data source property to a variable that contains data of a different dimension, you might cause the function to generate a warning and not render the graph until you have changed all data source properties to appropriate values.

HitTest

{on} | off

Selectable by mouse click. HitTest determines whether this object can become the current object (as returned by the gco command and the figure CurrentObject property) as a result of a mouse click on the objects that compose the area graph. If HitTest is off, clicking this object selects the object below it (which is usually the axes containing it).

Interruptible

{on} | off

Callback routine interruption mode. The Interruptible property controls whether an object's callback can be interrupted by callbacks invoked subsequently.

Only callbacks defined for the ButtonDownFcn property are affected by the Interruptible property. MATLAB checks for events that can interrupt a callback only when it encounters a drawnow, figure, getframe, or pause command in the routine. See the BusyAction property for related information.

Setting Interruptible to on allows any graphics object's callback to interrupt callback routines originating from a bar property. Note that MATLAB does not save the state of variables or the display (e.g., the handle returned by the gca or gcf command) when an interruption occurs.

Parent

handle of parent axes, hggroup, or hgtransform

Parent of this object. This property contains the handle of the object's parent. The parent is normally the axes, hggroup, or hgtransform object that contains the object.

See "Objects That Can Contain Other Objects" for more information on parenting graphics objects.

Selected

on | {off}

Is object selected? When you set this property to on, MATLAB displays selection "handles" at the corners and midpoints if the SelectionHighlight property is also on (the default). You can, for example, define the ButtonDownFcn callback to set this property to on, thereby indicating that this particular object is selected. This property is also set to on when an object is manually selected in plot edit mode.

SelectionHighlight

{on} | off

Objects are highlighted when selected. When the Selected property is on, MATLAB indicates the selected state by drawing four edge handles and four corner handles. When SelectionHighlight is off, MATLAB does not draw the handles except when in plot edit mode and objects are selected manually.

Tag

string

User-specified object label. The Tag property provides a means to identify graphics objects with a user-specified label. This is particularly useful when you are constructing interactive graphics programs that would otherwise need to define object handles as global variables or pass them as arguments between callbacks. You can define Tag as any string.

For example, you might create an areaseries object and set the Tag property.

```
t = area(Y, 'Tag', 'area1')
```

When you want to access objects of a given type, you can use findobj to find the object's handle. The following statement changes the FaceColor property of the object whose Tag is area1.

```
set(findobj('Tag', 'area1'), 'FaceColor', 'red')
```

Type

string (read only)

Type of graphics object. This property contains a string that identifies the class of graphics object. For image objects, Type is always 'image'.

UIContextMenu

handle of a uicontextmenu object

Associate a context menu with this object. Assign this property the handle of a uicontextmenu object created in the object's parent figure. Use the uicontextmenu function to create the context menu. MATLAB displays the context menu whenever you right-click over the object.

UserData

array

User-specified data. This property can be any data you want to associate with this object (including cell arrays and structures). The object does not set values for this property, but you can access it using the set and get functions.

Visible

{on} | off

Visibility of this object and its children. By default, a new object's visibility is on. This means all children of the object are visible unless the child object's Visible property is set to off. Setting an object's Visible property to off prevents the object from being displayed. However, the object still exists and you can set and query its properties.

XData

[1 size(CData,2)] by default

Control placement of image along x-axis. A vector specifying the locations of the centers of the elements CData(1,1) and CData(m,n), where CData has a size of m-by-n. Element CData(1,1) is centered over the coordinate defined by the first elements in XData and YData. Element CData(m,n) is centered over the coordinate defined by the last elements in XData and YData. The centers of the remaining elements of CData are evenly distributed between those two points.

The width of each CData element is determined by the expression

```
(XData(2)-XData(1))/(size(CData,2)-1)
```

You can also specify a single value for XData. In this case, image centers the first element at this coordinate and centers each following element one unit apart.

YData

```
[1 size(CData,1)] by default
```

Control placement of image along y-axis. A vector specifying the locations of the centers of the elements CData(1,1) and CData(m,n), where CData has a size of m-by-n. Element CData(1,1) is centered over the coordinate defined by the first elements in XData and YData. Element CData(m,n) is centered over the coordinate defined by the last elements in XData and YData. The centers of the remaining elements of CData are evenly distributed between those two points.

The height of each CData element is determined by the expression

```
(YData(2)-YData(1))/(size(CData,1)-1)
```

You can also specify a single value for YData. In this case, image centers the first element at this coordinate and centers each following element one unit apart.

See Also image

Purpose

Scale data and display image object



GUI Alternatives

To plot a selected matrix as an image use the Plot Selector

Catalog. Manipulate image characteristics in *plot edit* mode with the Property Editor. For details, see Plotting Tools — Interactive Plotting in the MATLAB Graphics documentation and Creating Graphics from the Workspace Browser in the MATLAB Desktop Tools documentation.

Syntax

```
imagesc(C)
imagesc(x,y,C)
imagesc(...,clims)
imagesc('PropertyName',PropertyValue,...)
h = imagesc(...)
```

Description

The imagesc function scales image data to the full range of the current colormap and displays the image. (See "Examples" on page 2-1977 for an illustration.)

imagesc(C) displays C as an image. Each element of C corresponds to a rectangular area in the image. The values of the elements of C are indices into the current colormap that determine the color of each patch.

imagesc(x,y,C) displays C as an image and specifies the bounds of the x- and y-axis with vectors x and y. If x(1) > x(2) or y(1) > y(2), the image is flipped left-right or up-down, respectively.

imagesc(...,clims) normalizes the values in C to the range specified by clims and displays C as an image. clims is a two-element vector that limits the range of data values in C. These values map to the full range of values in the current colormap. imagesc('PropertyName',PropertyValue,...) is the low-level syntax of the imagesc function. It specifies only property name/property value pairs as input arguments.

h = imagesc(...) returns the handle for an image graphics object.

Remarks

x and y do not affect the elements in C; they only affect the annotation of the axes. If length(x) > 2 or length(y) > 2, imagesc ignores all except the first and last elements of the respective vector.

imagesc creates an image with CDataMapping set to scaled, and sets the axes CLim property to the value passed in clims.

You cannot interactively pan or zoom outside the *x*-limits or *y*-limits of an image.


By default, imagesc plots the *y*-axis from lowest to highest value, top to bottom. To reverse this, type set(gca,'YDir','normal'). This will reverse both the *y*-axis and the image.

Examples

You can expand midrange color resolution by mapping low values to the first color and high values to the last color in the colormap by specifying color value limits (clims). If the size of the current colormap is 81-by-3, the statements

```
clims = [ 10 60 ]
imagesc(C,clims)
```

map the data values in C to the colormap as shown in this illustration and the code that follows:





In this example, the left image maps to the gray colormap using the statements

```
load clown
imagesc(X)
colormap(gray)
```

The right image has values between 10 and 60 scaled to the full range of the gray colormap using the statements

```
load clown
clims = [10 60];
imagesc(X,clims)
colormap(gray)
```





See Also

image, imfinfo, imread, imwrite, colorbar, colormap, pcolor, surface, surf

"Bit-Mapped Images" on page 1-101 for related functions

imapprox

Purpose

Approximate indexed image using one with fewer colors

Syntax

```
[Y,newmap] = imapprox(X,map,n)
[Y,newmap] = imapprox(X,map,tol)
Y = imapprox(X,map,newmap)
Y = imapprox(...,dither option)
```

Description

[Y,newmap] = imapprox(X,map,n) approximates the colors in the indexed image X and associated colormap map by using minimum variance quantization. imapprox returns the indexed image Y with colormap newmap, which has at most n colors.

[Y,newmap] = imapprox(X,map,tol) approximates the colors in X and map through uniform quantization. newmap contains at most $(floor(1/tol)+1)^3$ colors. tol must be between 0 and 1.0.

Y = imapprox(X, map, newmap) approximates the colors in map by using colormap mapping to find the colors in newmap that best match the colors in map.

Y = imapprox(...,dither_option) enables or disables dithering. dither option is a string that can have one of these values.

Value	Description
{'dither'}(default	Dithers, if necessary, to achieve better color resolution at the expense of spatial resolution.
'nodither'	Maps each color in the original image to the closest color in the new map. No dithering is performed.

Class Support

The input image X can be of class uint8, uint16, or double. The output image Y is of class uint8 if the length of newmap is less than or equal to 256. If the length of newmap is greater than 256, Y is of class double.

Algorithm

imapprox uses rgb2ind to create a new colormap that uses fewer colors.

Examples

Approximate the indexed image trees.tif by another indexed image containing only 16 colors.

```
[X, map] = imread('trees.tif');
[Y, newmap] = imapprox(X, map, 16);
figure, imshow(Y, newmap)
```

See Also

cmunique, dither, rgb2ind

imfinfo

Purpose

Information about graphics file

Syntax

```
info = imfinfo(filename, fmt)
info = imfinfo(filename)
info = imfinfo(URL,...)
```

Description

info = imfinfo(filename, fmt) returns a structure whose fields contain information about an image in a graphics file. filename is a string that specifies the name of the graphics file, and fmt is a string that specifies the format of the file. The file must be in the current folder or in a folder on the MATLAB path. If imfinfo cannot find a file named filename, it looks for a file named filename. fmt. The possible values for fmt are contained in the MATLAB file format registry. To view of list of these formats, run the imformats command.

If filename is a TIFF, HDF, ICO, GIF, or CUR file containing more than one image, info is a structure array with one element for each image in the file. For example, info(3) would contain information about the third image in the file.

info = imfinfo(filename) attempts to infer the format of the file from its contents.

info = imfinfo(URL,...) reads the image from the specified Internet
URL. The URL must include the protocol type (e.g., http://)

Information Returned

The set of fields in info depends on the individual file and its format. However, the first nine fields are always the same. This table lists these common fields, in the order they appear in the structure, and describes their values. "Format-Specific Notes" on page 2-1983 contains information about some fields returned by certain formats.

Field	Value	
Filename	A string containing the name of the file; if the file is not in the current folder, the string contains the full pathname of the file.	
FileModDate	A string containing the date when the file was last modified	
FileSize	An integer indicating the size of the file in bytes	
Format	A string containing the file format, as specified by fmt; for formats with more than one possible extension (e.g. JPEG and TIFF files), imfinfo returns the first variant in the file format registry.	
FormatVersion	A string or number describing the file format version	
Width	An integer indicating the width of the image in pixels	
Height	An integer indicating the height of the image in pixels	
BitDepth	An integer indicating the number of bits per pixel	
ColorType	A string indicating the type of image; this can include, but is not limited to, 'truecolor' for a truecolor (RGB) image, 'grayscale' for a grayscale intensity image, or 'indexed' for an indexed image	

Format-Specific Notes

- JPEG and TIFF only If filename contains Exchangeable Image File Format (EXIF) tags, the info structure returned by imfinfo might also contain 'DigitalCamera' or 'GPSInfo' (global positioning system information) fields.
- **GIF only** imfinfo returns the value of the 'DelayTime' field in hundredths of seconds.

imfinfo

```
Example
                    info = imfinfo('ngc6543a.jpg')
                    info =
                               Filename: [1x95 char]
                            FileModDate: '01-Oct-1996 17:19:44'
                               FileSize: 27387
                                 Format: 'jpg'
                          FormatVersion: ''
                                  Width: 600
                                 Height: 650
                               BitDepth: 24
                              ColorType: 'truecolor'
                        FormatSignature: ''
                        NumberOfSamples: 3
                           CodingMethod: 'Huffman'
                          CodingProcess: 'Sequential'
                                Comment: {[1x69 char]}
```

See Also

imformats, imread, imwrite

"Bit-Mapped Images" on page 1-101 for related functions

Purpose

Manage image file format registry

Syntax

imformats

formats = imformats

formats = imformats('fmt')

formats = imformats(format_struct)
formats = imformats('factory')

Description

imformats displays a table of information listing all the values in the MATLAB file format registry. This registry determines which file formats are supported by the imfinfo, imread, and imwrite functions.

formats = imformats returns a structure containing all the values in the MATLAB file format registry. The following tables lists the fields in the order they appear in the structure.

Field	Value
ext	A cell array of strings that specify filename extensions that are valid for this format
isa	A string specifying the name of the function that determines if a file is a certain format. This can also be a function handle.
info	A string specifying the name of the function that reads information about a file. This can also be a function handle.
read	A string specifying the name of the function that reads image data in a file. This can also be a function handle.
write	A string specifying the name of the function that writes MATLAB data to a file. This can also be a function handle.
alpha	Returns 1 if the format has an alpha channel, 0 otherwise
description	A text description of the file format

Note The values for the isa, info, read, and write fields must be functions on the MATLAB search path or function handles.

formats = imformats('fmt') searches the known formats in the MATLAB file format registry for the format associated with the filename extension 'fmt'. If found, imformats returns a structure containing the characteristics and function names associated with the format. Otherwise, it returns an empty structure.

formats = imformats(format_struct) sets the MATLAB file format registry to the values in format_struct. The output structure, formats, contains the new registry settings.

Caution Using imformats to specify values in the MATLAB file format registry can result in the inability to load any image files. To return the file format registry to a working state, use imformats with the 'factory' setting.

formats = imformats('factory') resets the MATLAB file format registry to the default format registry values. This removes any user-specified settings.

Changes to the format registry do not persist between MATLAB sessions. To have a format always available when you start MATLAB, add the appropriate imformats command to the MATLAB startup file, startup.m, located in \$MATLAB/toolbox/local on UNIX systems, or \$MATLAB\toolbox\local on Windows systems.

Example

imformats

isa: @isbmp
info: @imbmpinfo
read: @readbmp
write: @writebmp

alpha: 0

description: 'Windows Bitmap (BMP)'

See Also

fileformats, imfinfo, imread, imwrite, path

"Bit-Mapped Images" on page 1-101 for related functions

Purpose

Add package or class to current import list

Syntax

```
import package_name.*
import class_name
import cls_or_pkg_name1 cls_or_pkg_name2...
import
L = import
```

Description

import package_name.* adds specified package_name to the current
import list. Note that package name must be followed by .*.

import class_name adds a single class to the current import list. Note that class_name must be fully qualified (that is, it must include the package name).

import cls_or_pkg_name1 cls_or_pkg_name2... adds all named classes and packages to the current import list. Note that each class name must be fully qualified, and each package name must be followed by .*.

import with no input arguments displays the current import list, without adding to it.

L = import with no input arguments returns a cell array of strings containing the current import list, without adding to it.

The import function only affects the import list of the function within which it is used. When invoked at the command prompt, import uses the import list for the MATLAB command environment. If import is used in a script invoked from a function, it affects the import list of the function. If import is used in a script that is invoked from the command prompt, it affects the import list for the command environment.

The import list of a function is persistent across calls to that function and is only cleared when the function is cleared.

To clear the current import list, use the following command.

clear import

This command may only be invoked at the command prompt. Attempting to use clear import within a function results in an error.

Importing MATLAB Packages and Classes

You can import packages and classes into a MATLAB workspace (from the command line or in a function definition). For example:

```
import packagename.*
```

imports all classes and package functions so that you can reference those classes and functions by their simple names, without the package qualifier.

You can import just a single class from a package:

```
import packagename.ClassName
import Classname
```

You must still use the class name to call static methods:

```
ClassName.staticMethod()
```

For more information on how import works with MATLAB classes and packages, see "Importing Classes".

Remarks

The import function allows your code to refer to an imported class by class name only, rather than with the fully qualified class name. import is particularly useful in streamlining calls to constructors, where most references to Java classes occur.

Examples Add Java Class to Current Import List

```
import java.lang.String
s = String('hello'); % Create java.lang.String object
```

Add Multiple Java Packages to Current Import List

```
import java.util.* java.awt.*
f = Frame; % Create java.awt.Frame object
```

import

methods Enumeration % List java.util.Enumeration methods

See Also

clear, load, importdata

Purpose

Load data from file

Syntax

importdata(filename)

A = importdata(filename)

A = importdata(filename, delimiter)

A = importdata(filename, delimiter, nheaderlines)

[A, delimiter] = importdata(...)

[A, delimiter, nheaderlines] = importdata(...)

[...] = importdata('-pastespecial', ...)

Description

importdata(filename) loads data from filename into the workspace.

A = importdata(filename) loads data into A.

A = importdata(filename, delimiter) interprets delimiter as the column separator in ASCII file filename.

A = importdata(filename, delimiter, nheaderlines) loads data from ASCII file filename, reading numeric data starting from line nheaderlines+1.

[A, delimiter] = importdata(...) returns the detected delimiter character for the input ASCII file.

[A, delimiter, nheaderlines] = importdata(...) returns the detected number of header lines in the input ASCII file.

[...] = importdata('-pastespecial', ...) loads data from the system clipboard rather than from a file.

Input Arguments

filename

Name and extension of the file to import. If importdata recognizes the file extension, it calls the MATLAB helper function designed to import the associated file format (such as load for MAT-files or xlsread for spreadsheets). Otherwise, importdata interprets the file as a delimited ASCII file.

For a list of supported file formats, see the file formats table.

delimiter

importdata

Character in an ASCII file to interpret as a column separator, such as ', ' or '; '. Use '\t' for tab.

Default: interpreted from file

nheaderlines

Number of text header lines in the input ASCII file. importdata stores all the header text in the textdata field, and stores the last line of column header text in the colheaders field.

Default: interpreted from file

'-pastespecial'

Keyword to request that importdata load data from the system clipboard instead of a file.

Output Arguments

Α

Data from the file. The class of A depends on the characteristics of the input file.

As described in the Inputs section, importdata calls a helper function to read the data. When the helper function returns more than one nonempty output, importdata combines the outputs into a struct array.

The following table lists the file formats associated with helper functions that can return more than one output, and the possible fields in *A*.

File Format	Possible Fields	Class
MAT-files	One field for each variable	Associated with each variable.
ASCII files and Spreadsheets	data textdata colheaders rowheaders	For ASCII files, data contains a double array. Other fields contain cell arrays. For spreadsheets, each field contains a struct, with one field for each worksheet.
Images	cdata colormap alpha	See imread.
Audio files	data fs	See auread or wavread.

The MATLAB helper functions for all other supported file formats return one output. For more information about the class of each output, see the functions listed in the file formats table.

For ASCII files and spreadsheets, importdata expects to find numeric data in a rectangular form (that is, like a matrix). Text headers can appear above or to the left of the numeric data, as follows:

- Column headers or file description text at the top of the file, above the numeric data.
- Row headers to the left of the numeric data.

To import ASCII files with nonnumeric characters anywhere else, including columns of character data or formatted dates or times,

importdata

use textscan instead of importdata. For more information, see "Importing Nonnumeric ASCII Data".

When importing spreadsheets with columns of nonnumeric data, importdata cannot always correctly interpret the column and row headers.

If the ASCII file or spreadsheet contains either column or row headers, but not both, importdata returns a colheaders or rowheaders field in the output structure, where:

- colheaders contains only the lowest line of column header text. importdata stores all text in the textdata field.
- rowheaders is created only when the file or worksheet contains a single column of row headers.

delimiter

The character that importdata detected as the column separator in the input ASCII file.

nheaderlines

The number of text header lines that importdata detected in the input ASCII file.

Examples

Import and display the image ngc6543a.jpg:

```
nebula_im = importdata('ngc6543a.jpg');
image(nebula im);
```

nebula_im is class uint8 because the helper function, imread, returns empty results for colormap and alpha.

Using a text editor, create a space-delimited ASCII file with column headers called myfile.txt:

```
Day1 Day2 Day3 Day4 Day5 Day6 Day7 95.01 76.21 61.54 40.57 5.79 20.28 1.53
```

```
23.11 45.65 79.19 93.55 35.29 19.87 74.68 60.68 1.85 92.18 91.69 81.32 60.38 44.51 48.60 82.14 73.82 41.03 0.99 27.22 93.18 89.13 44.47 17.63 89.36 13.89 19.88 46.60
```

Import the file, specifying the space delimiter and the single column header, and view columns 3 and 5:

```
M = importdata('myfile.txt', ' ', 1);
for k = [3, 5]
    disp(M.colheaders{1, k})
    disp(M.data(:, k))
    disp(' ')
end
```

Alternatives

The easiest way to import data is to use the Import Wizard, a graphical user interface. The Import Wizard imports the same file formats as importdata, but allows direct control over the variables to create. To start the Wizard, select **File > Import Data** or call uiimport.

See Also

file formats | load | save | textscan | uiimport

How To

- · "Importing Text Data Files"
- · "Importing Excel Spreadsheets"
- · "Processing a Sequence of Files"

Purpose

Read image from graphics file

Syntax

```
A = imread(filename, fmt)
[X, map] = imread(...)
[...] = imread(filename)
[...] = imread(URL,...)
[...] = imread(...,Param1,Val1,Param2,Val2...)
```

Description

A = imread(filename, fmt) reads a grayscale or color image from the file specified by the string filename. If the file is not in the current folder, or in a folder on the MATLAB path, specify the full pathname.

The text string fmt specifies the format of the file by its standard file extension. For example, specify 'gif' for Graphics Interchange Format files. To see a list of supported formats, with their file extensions, use the imformats function. If imread cannot find a file named filename, it looks for a file named filename.fmt.

The return value A is an array containing the image data. If the file contains a grayscale image, A is an M-by-N array. If the file contains a truecolor image, A is an M-by-N-by-3 array. For TIFF files containing color images that use the CMYK color space, A is an M-by-N-by-4 array. See TIFF in the Format-Specific Information section for more information.

The class of A depends on the bits-per-sample of the image data, rounded to the next byte boundary. For example, imread returns 24-bit color data as an array of uint8 data because the sample size for each color component is 8 bits. See "Remarks" on page 2-1997 for a discussion of bitdepths, and see "Format-Specific Information" on page 2-1997 for more detail about supported bitdepths and sample sizes for a particular format.

[X, map] = imread(...) reads the indexed image in filename into X and its associated colormap into map. Colormap values in the image file are automatically rescaled into the range [0,1].

[...] = imread(filename) attempts to infer the format of the file from its content.

[...] = imread(URL,...) reads the image from an Internet URL. The URL must include the protocol type (e.g., http://).

[...] = imread(...,Param1,Val1,Param2,Val2...) specifies parameters that control various characteristics of the operations for specific formats. For more information, see "Format-Specific Information" on page 2-1997.

Remarks

Bitdepth is the number of bits used to represent each image pixel. Bitdepth is calculated by multiplying the bits-per-sample with the samples-per-pixel. Thus, a format that uses 8-bits for each color component (or sample) and three samples per pixel has a bitdepth of 24. Sometimes the sample size associated with a bitdepth can be ambiguous: does a 48-bit bitdepth represent six 8-bit samples, four 12-bit samples, or three 16-bit samples? The following format-specific sections provide sample size information to avoid this ambiguity.

Format-Specific The following sections provide information about the support for specific **Information** formats, listed in alphabetical order by format name. These sections include information about format-specific syntaxes, if they exist.

"BMP — Windows Bitmap" on page 2-1998	"JPEG — Joint Photographic Experts Group" on page 2-2000	"PNG — Portable Network Graphics" on page 2-2003
"CUR — Cursor File" on page 2-1998	"JPEG 2000 — Joint Photographic Experts Group 2000" on page 2-2001	"PPM — Portable Pixmap" on page 2-2004
"GIF — Graphics Interchange Format" on page 2-1999	"PBM — Portable Bitmap" on page 2-2002	"RAS — Sun Raster" on page 2-2004

"HDF4 — Hierarchical Data Format" on page 2-2000	"PCX — Windows Paintbrush" on page 2-2002	"TIFF — Tagged Image File Format" on page 2-2004
"ICO — Icon File" on page 2-2000	"PGM — Portable Graymap" on page 2-2003	"XWD — X Window Dump" on page 2-2007

BMP – Windows Bitmap

Supported Bitdepths		RLE si 6o mpressi	Output o 6 lass	Notes
1-bit	X	_	logical	
4-bit	X	X	uint8	
8-bit	X	X	uint8	
16-bit	X	_	uint8	1 sample/pixel
24-bit	X	_	uint8	3 samples/pixel
32-bit	x	_	uint8	3 samples/pixel (1 byte padding)

CUR - Cursor File

Supported Bitdepths	No Compression	Compression	Output Class
1-bit	X	_	logical
4-bit	X	_	uint8
8-bit	x	_	uint8

Format-specific syntaxes:

[...] = imread(..., idx) reads in one image from a multi-image icon or cursor file. idx is an integer value that specifies the order that the image appears in the file. For example, if idx is 3, imread reads

the third image in the file. If you omit this argument, imread reads the first image in the file.

[A, map, alpha] = imread(...) returns the AND mask for the resource, which can be used to determine the transparency information. For cursor files, this mask may contain the only useful data.

Note By default, Microsoft Windows cursors are 32-by-32 pixels. MATLAB pointers must be 16-by-16. You will probably need to scale your image. If you have Image Processing ToolboxTM, you can use the imresize function.

GIF - Graphics Interchange Format

Supported Bitdepths	No Compression		Output Class
1-bit	x	_	logical
2-bit to 8-bit	x	_	uint8

Format-specific syntaxes:

[...] = imread(..., idx) reads in one or more frames from a multiframe (i.e., animated) GIF file. idx must be an integer scalar or vector of integer values. For example, if idx is 3, imread reads the third image in the file. If idx is 1:5, imread returns only the first five frames.

[...] = imread(..., 'frames', idx) is the same as the syntax above except that idx can be 'all'. In this case, all the frames are read and returned in the order that they appear in the file.

Note Because of the way that GIF files are structured, all the frames must be read when a particular frame is requested. Consequently, it is much faster to specify a vector of frames or 'all' for idx than to call imread in a loop when reading multiple frames from the same GIF file.

HDF4 — Hierarchical Data Format

Supported Bitdepths	Raster Image with colormap	Raster image without colormap	Output Class	Notes
8-bit	X	X	uint8	
24-bit	_	x	uint8	3 samples/pixel

Format-specific syntaxes:

[...] = imread(..., ref) reads in one image from a multi-image HDF4 file. ref is an integer value that specifies the reference number used to identify the image. For example, if ref is 12, imread reads the image whose reference number is 12. (Note that in an HDF4 file the reference numbers do not necessarily correspond to the order of the images in the file. You can use imfinfo to match image order with reference number.) If you omit this argument, imread reads the first image in the file.

ICO - Icon File

See "CUR — Cursor File" on page 2-1998

JPEG - Joint Photographic Experts Group

imread can read any baseline JPEG image as well as JPEG images with some commonly used extensions. For information about support for JPEG 2000 files, see JPEG 2000.

Supported Bitdepths	Lossy Compress	Lossless i ct ompressi	Output orClass	Notes
8-bit	X	X	uint8	Grayscale or RGB
12-bit	X	X	uint16	Grayscale

Supported Bitdepths	Lossy Compress	Lossless i ct ompressi	Output orClass	Notes
16-bit	_	X	uint16	Grayscale
36-bit	X	x	uint16	RGB Three 12-bit samples/pixel

JPEG 2000 - Joint Photographic Experts Group 2000

For information about JPEG files, see JPEG.

Note Only 1- and 3-sample images are supported. Indexed JPEG 2000 images are not supported.

Supported Bitdepths (Bits-per-sa		Lossless i ct ompressio	Output orClass	Notes
1-bit	X	X	logical	Grayscale only
2- to 8-bit	X	X	uint8	Grayscale or RGB
9- to 16-bit	X	X	uint16	Grayscale or RGB

Format-specific syntaxes:

[...] = imread(..., 'Param1', value1, 'Param2', value2, ...) uses parameter-value pairs to control the read operation, described in the following table.

imread

Parameter	Value
'ReductionLevel'	A non-negative integer specifying the reduction in the resolution of the image. For a reduction level L , the image resolution is reduced by a factor of 2^L . Its default value is 0 implying no reduction. The reduction level is limited by the total number of decomposition levels as specified by the 'WaveletDecompositionLevels' field in the structure returned by the imfinfo function.
'PixelRegion'	{ROWS, COLS} — The imread function returns the sub-image specified by the boundaries in ROWS and COLS. ROWS and COLS must both be two-element vectors that denote the 1-based indices [START STOP]. If 'ReductionLevel' is greater than 0, then ROWS and COLS are coordinates in the reduced-sized image.

PBM — Portable Bitmap

Supported Bitdepths	Raw Binary	ASCII (Plain) Encoded	Output Class	
1-bit	X	X	logical	

PCX - Windows Paintbrush

Supported Bitdepths	Output Class	Notes
1-bit	logical	Grayscale only
8-bit	uint8	Grayscale or indexed
24-bit	uint8	RGB Three 8-bit samples/pixel

PGM - Portable Graymap

Supported Bitdepths	Raw Binary	ASCII (Plain) Encoded	Output Class
Up to 16-bit	X	_	uint8
Arbitrary	_	x	

PNG - Portable Network Graphics

Supported Bitdepths	Output Class	Notes
1-bit	logical	Grayscale
2-bit	uint8	Grayscale
4-bit	uint8	Grayscale
8-bit	uint8	Grayscale or Indexed
16-bit	uint16	Grayscale or Indexed
24-bit	uint8	RGB Three 8-bit samples/pixel.
48-bit	uint16	RGB Three 16-bit samples/pixel.

Format-specific syntaxes:

[...] = imread(..., 'BackgroundColor', BG) composites any transparent pixels in the input image against the color specified in BG. If BG is 'none', then no compositing is performed. If the input image is indexed, BG must be an integer in the range [1,P] where P is the colormap length. If the input image is grayscale, BG should be an integer in the range [0,1]. If the input image is RGB, BG should be a three-element vector whose values are in the range [0,1]. The string 'BackgroundColor' may be abbreviated.

[A, map, alpha] = imread(...) returns the alpha channel if one is present; otherwise alpha is []. Note that map may be empty if the file contains a grayscale or truecolor image.

If you specify thealpha output argument, BG defaults to 'none', if not specified. Otherwise, if the PNG file contains a background color chunk, that color is used as the default value for BG. If alpha is not used and the file does not contain a background color chunk, then the default value for BG is 1 for indexed images; 0 for grayscale images; and [0 0 0] for truecolor (RGB) images.

PPM - Portable Pixmap

Supported Bitdepths	Raw Binary	ASCII (Plain) Encoded	Output Class
Up to 16-bit	X	-	uint8
Arbitrary	_	x	

RAS - Sun Raster

The following table lists the supported bitdepths, compression, and output classes for RAS files.

Supported Bitdepths	Output Class	Notes
1-bit	logical	Bitmap
8-bit	uint8	Indexed
24-bit	uint8	RGB Three 8-bit samples/pixel
32-bit	uint8	RGB with Alpha Four 8-bit samples/pixel

TIFF - Tagged Image File Format

imread supports the following TIFF capabilities:

- Any number of samples-per-pixel
- CCITT group 3 and 4 FAX, Packbits, JPEG, LZW, Deflate, ThunderScan compression, and uncompressed images
- Logical, grayscale, indexed color, truecolor and hyperspectral images
- RGB, CMYK, CIELAB, ICCLAB color spaces. If the color image uses the CMYK color space, A is an M-by-N-by-4 array. To determine which color space is used, use imfinfo to get information about the graphics file and look at the value of the PhotometricInterpretation field. If a file contains CIELAB color data, imread converts it to ICCLAB before bringing it into the MATLAB workspace because 8- or 16-bit TIFF CIELAB-encoded values use a mixture of signed and unsigned data types that cannot be represented as a single MATLAB array.
- Data organized into tiles or scanlines

The following table lists the supported bit/sample and corresponding output classes for TIFF files.

Supporte Bitdepth						Output Class	Notes		
	None	Packbits	CCITT	RGB	ICCLAB	CIELAB	СМҮК		
1-bit	X	X	X	-	-	-	-	logical	
8-bit	X	X	-	-	-	-	-	uint8	
12-bit	-	-	-	-	-	-	-	uint16	Grayscale or Indexed
16-bit	-	-	-	-	-	-	-	uint16	Grayscale or Indexed
24-bit	X	X	-	X	X	X	-	uint8	3 samples

imread

Supporte Bitdepths					Output Class	Notes			
	Non	e Packbits	CCITT	RGB	ICCLAB	CIELAB	СМҮК		
32-bit	-	-	-	-	-	-	x	uint8	4 samples
36-bit	-	-	-	X	-	-	-	uint16	3 samples
48-bit	-	-	-	X	x	X	-	uint16	3 samples
64-bit	-	-	-	-	-	-	X	double	4 samples

Note imread supports 8-bit integral and 32-bit floating point tiled TIFF images, with any compression and color space combination listed above, and 32-bit IEEE floating point images.

The following are format-specific syntaxes for TIFF files.

A = imread(...) returns color data that uses the RGB, CIELAB, ICCLAB, or CMYK color spaces. If the color image uses the CMYK color space, A is an M-by-N-by-4 array.

[...] = imread(..., 'Param1', value1, 'Param2', value2, ...) uses parameter/value pairs to control the read operation. The following table lists the parameters you can use.

Parameter	Value
'Index'	Positive integer specifying which image to read. For example, if you specify the value 3, imread reads the third image in the file. If you omit this argument, imread reads the first image in the file.
'Info'	Structure array returned by imfinfo.
	Note: When reading images from a multi-image TIFF file, passing the output of imfinfo as the value of the 'Info' argument helps imread locate the images in the file more quickly.
'PixelRegion'	Cell array, {Rows, Cols}, specifying the boundaries of the region. Rows and Cols must be either two- or three-element vectors. If you specify two elements, the values denote the 1-based indices [start stop]. If you specify three elements, the values denote the 1-based indices [start increment stop], to allow image downsampling.

For copyright information, see the libtiffcopyright.txt file.

XWD - X Window Dump

The following table lists the supported bitdepths, compression, and output classes for XWD files.

Supported Bitdepths	ZPixmaps	XYBitmaps	XYPixmaps	Output Class
1-bit	X	_	X	logical
8-bit	X	_	_	uint8

Class Support

For most image file formats, imread uses 8 or fewer bits per color plane to store image pixels. The following table lists the class of the returned array for the data types used by the file formats.

Data Type Used in File	Class of Array Returned by imread
1-bit per pixel	logical
2- to 8-bits per color plane	uint8
9- to 16-bit per pixel	uint16 (BMP, JPEG, PNG, and TIFF) For the 16-bit BMP packed format (5-6-5), MATLAB returns uint8

Note For indexed images, imread always reads the colormap into an array of class double, even though the image array itself may be of class uint8 or uint16.

Examples

Read sample image.

```
imdata = imread('ngc6543a.jpg');
```

Read sixth image in a TIFF file.

```
[X,map] = imread('your_image.tif',6);
```

Read fourth image in an HDF4 file.

```
info = imfinfo('your_hdf_file.hdf');
[X,map] = imread('your hdf file.hdf',info(4).Reference);
```

Read a 24-bit PNG image and set any of its fully transparent (alpha channel) pixels to red.

```
bg = [1 \ 0 \ 0];
```

```
A = imread('your_image.png', 'BackgroundColor',bg);
Return the alpha channel (if any) of a PNG image.
  [A,map,alpha] = imread('your_image.png');
Read an ICO image, apply a transparency mask, and then display the image.
  [a,b,c] = imread('your_icon.ico');
% Augment colormap for background color (white).
b2 = [b; 1 1 1];
% Create new image for display.
d = ones(size(a)) * (length(b2) - 1);
% Use the AND mask to mix the background and
% foreground data on the new image
d(c == 0) = a(c == 0);
```

See Also

double, fread, image, imfinfo, imformats, imwrite, uint8, uint16 "Bit-Mapped Images" on page 1-101 for related functions

% Display new image

image(uint8(d)), colormap(b2)

Purpose

Write image to graphics file

Syntax

```
imwrite(A,filename,fmt)
imwrite(X,map,filename,fmt)
imwrite(...,filename)
imwrite(...,Param1,Val1,Param2,Val2...)
```

Description

imwrite(A, filename, fmt) writes the image A to the file specified by filename in the format specified by fmt.

A can be an M-by-N (grayscale image) or M-by-N-by-3 (truecolor image) array, but it cannot be an empty array. For TIFF files, A can be an M-by-N-by-4 array containing color data that uses the CMYK color space. For GIF files, A can be an M-by-N-by-1-by-P array containing grayscale or indexed images — RGB images are not supported. For information about the class of the input array and the output image, see "Class Support" on page 2-2011.

filename is a string that specifies the name of the output file.

fmt can be any of the text strings listed in the table in "Supported Image Types" on page 2-2012. This list of supported formats is determined by the MATLAB image file format registry. See imformats for more information about this registry.

imwrite(X,map,filename,fmt) writes the indexed image in X and its associated colormap map to filename in the format specified by fmt. If X is of class uint8 or uint16, imwrite writes the actual values in the array to the file. If X is of class double, imwrite offsets the values in the array before writing, using uint8(X 1). map must be a valid MATLAB colormap. Note that most image file formats do not support colormaps with more than 256 entries.

When writing multiframe GIF images, X should be an 4-dimensional M-by-N-by-1-by-P array, where P is the number of frames to write.

imwrite(...,filename) writes the image to filename, inferring the format to use from the filename's extension. The extension must be one of the values for fmt, listed in "Supported Image Types" on page 2-2012.

imwrite(...,Param1,Val1,Param2,Val2...) specifies parameters that control various characteristics of the output file for HDF, JPEG, PBM, PGM, PNG, PPM, and TIFF files. For example, if you are writing a JPEG file, you can specify the quality of the output image. For the lists of parameters available for each format, see "Format-Specific Parameters" on page 2-2014.

Class Support

The input array A can be of class logical, uint8, uint16, or double. Indexed images (X) can be of class uint8, uint16, or double; the associated colormap, map, must be of class double. Input values must be full (non-sparse).

The class of the image written to the file depends on the format specified. For most formats, if the input array is of class uint8, imwrite outputs the data as 8-bit values. If the input array is of class uint16 and the format supports 16-bit data (JPEG, PNG, and TIFF), imwrite outputs the data as 16-bit values. If the format does not support 16-bit values, imwrite issues an error. Several formats, such as JPEG and PNG, support a parameter that lets you specify the bit depth of the output data.

If the input array is of class double, and the image is a grayscale or RGB color image, imwrite assumes the dynamic range is [0,1] and automatically scales the data by 255 before writing it to the file as 8-bit values.

If the input array is of class double, and the image is an indexed image, imwrite converts the indices to zero-based indices by subtracting 1 from each element, and then writes the data as uint8.

If the input array is of class logical, imwrite assumes the data is a binary image and writes it to the file with a bit depth of 1, if the format allows it. BMP, PNG, or TIFF formats accept binary images as input arrays.

Supported Image Types

This table summarizes the types of images that imwrite can write. The MATLAB file format registry determines which file formats are supported. See imformats for more information about this registry. Note that, for certain formats, imwrite may take additional parameters, described in "Format-Specific Parameters" on page 2-2014.

Format	Full Name	Variants
'bmp'	Windows Bitmap (BMP)	1-bit, 8-bit, and 24-bit uncompressed images
'gif'	Graphics Interchange Format (GIF)	8-bit images
'hdf'	Hierarchical Data Format (HDF4)	8-bit raster image data sets, with or without associated colormap, 24-bit raster image data sets; uncompressed or with RLE or JPEG compression
'jpg' or 'jpeg'	Joint Photographic Experts Group	8-bit, 12-bit, and 16-bit Baseline JPEG images
	(JPEG)	Note imwrite converts indexed images to RGB before writing data to JPEG files, because the JPEG format does not support indexed images.

Format	Full Name	Variants
'jp2' or 'jpx'	"JPEG 2000 — Joint Photographic Experts Group 2000" on page 2-2017	1-bit, 8-bit, and 16-bit JPEG 2000 images
pbm	Portable Bitmap (PBM)	Any 1-bit PBM image, ASCII (plain) or raw (binary) encoding
'pcx'	Windows Paintbrush (PCX)	8-bit images
'pgm'	Portable Graymap (PGM)	Any standard PGM image; ASCII (plain) encoded with arbitrary color depth; raw (binary) encoded with up to 16 bits per gray value
'png'	Portable Network Graphics (PNG)	1-bit, 2-bit, 4-bit, 8-bit, and 16-bit grayscale images; 8-bit and 16-bit grayscale images with alpha channels; 1-bit, 2-bit, 4-bit, and 8-bit indexed images; 24-bit and 48-bit truecolor images; 24-bit and 48-bit truecolor images with alpha channels
'pnm'	Portable Anymap (PNM)	Any of the PPM/PGM/PBM formats, chosen automatically
'ppm'	Portable Pixmap (PPM)	Any standard PPM image. ASCII (plain) encoded with arbitrary color depth; raw (binary) encoded with up to 16 bits per color component

Format	Full Name	Variants
'ras'	Sun Raster (RAS)	Any RAS image, including 1-bit bitmap, 8-bit indexed, 24-bit truecolor and 32-bit truecolor with alpha
'tif' or 'tiff'	Tagged Image File Format (TIFF)	Baseline TIFF images, including 1-bit, 8-bit, 16-bit, and 24-bit uncompressed images, images with packbits compression, images with LZW compression, and images with Deflate compression; 1-bit images with CCITT 1D, Group 3, and Group 4 compression; CIELAB, ICCLAB, and CMYK images
'xwd'	X Windows Dump (XWD)	8-bit ZPixmaps

Format-SpecificGIF - Graphics Interchange Format Parameters Format-specific parameters.

Parameter	Values
'BackgroundColor'	A scalar integer that specifies which index in the colormap should be treated as the transparent color for the image and is used for certain disposal methods in animated GIFs. If X is uint8 or logical, indexing starts at 0. If X is double, indexing starts at 1.
'Comment'	A string or cell array of strings containing a comment to be added to the image. For a cell array of strings, a carriage return is added after each row.
'DelayTime'	A scalar value between 0 and 655 inclusive, that specifies the delay in seconds before displaying the next image.

Parameter	Values
'DisposalMethod'	One of the following strings, which sets the disposal method of an animated GIF: 'leaveInPlace', 'restoreBG', 'restorePrevious', or 'doNotSpecify'.
'Location'	A two-element vector specifying the offset of the top left corner of the screen relative to the top left corner of the image. The first element is the offset from the top, and the second element is the offset from the left.
'LoopCount'	A finite integer between 0 and 65535 or the value Inf (the default) which specifies the number of times to repeat the animation. By default, the animation loops continuously. If you specify 0, the animation will be played once. If you specify the value 1, the animation will be played twice, etc.
	To enable animation within Microsoft® PowerPoint®, specify a value for the 'LoopCount' parameter within the range [1 65535]. Some Microsoft applications interpret the value 0 to mean do not loop at all.
'ScreenSize'	A two-element vector specifying the height and width of the frame. When used with 'Location', ScreenSize provides a way to write frames to the image that are smaller than the whole frame. 'DisposalMethod' determines the fill value used for pixels outside the frame.
'TransparentColor'	A scalar integer. This value specifies which index in the colormap should be treated as the transparent color for the image. If X (the image) is uint8 or logical, indexing starts at 0. If X is double, indexing starts at 1.
'WriteMode'	'overwrite' (the default) or 'append'. In append mode, imwrite adds a single frame to the existing file.

HDF4 — Hierarchical Data Format

Format-specific parameters.

Parameter	Values		
'Compression'	'none' (the default)		
	'jpeg'(valid only for grayscale and RGB images)		
	'rle' (valid only for grayscale and indexed images)		
'Quality'	A number between 0 and 100; this parameter applies only if 'Compression' is 'jpeg'.		
	Higher numbers mean higher <i>quality</i> (less image degradation due to compression), but the resulting file size is larger. The default value is 75.		
'WriteMode'	'overwrite' (the default)		
	'append'		

JPEG - Joint Photographic Experts Group

Format-specific parameters. For information about support for JPEG 2000 files, see "JPEG 2000 — Joint Photographic Experts Group 2000" on page 2-2017.

Parameter	Values	Default
'Bitdepth'	A scalar value indicating desired bitdepth; for grayscale images this can be 8, 12, or 16; for color images this can be 8 or 12.	8 (grayscale) and 8 bit per plane for color images
'Comment'	A column vector cell array of strings or a character matrix. imwrite writes each row of input as a comment in the JPEG file.	Empty

Parameter	Values	Default
'Mode'	Specifies the type of compression used: 'lossy' or 'lossless'	'lossy'
'Quality'	A number between 0 and 100; higher numbers mean higher quality (less image degradation due to compression), but the resulting file size is larger.	75

JPEG 2000 - Joint Photographic Experts Group 2000

Format-specific parameters. For information about support for JPEG files, see "JPEG — Joint Photographic Experts Group" on page 2-2016.

Parameter	Values	Default
'Comment'	A column vector cell array of strings or a character matrix. imwrite writes each row of input as a comment in the JPEG file.	Empty
'CompressionRat Aoreal value greater than 1 specifying the target compression ratio which is defined as the ratio of input image size to the output compressed size. For example, a value of 2.0 implies that the output image size will be half of the input image size or less. A higher value implies a smaller file size and reduced image quality. This is valid only with 'lossy' mode. Note that the compression ratio doesn't take into		
	account the header size, and hence in some cases the output file size can be larger than expected.	
'Mode'	Specifies the type of compression used: 'lossy' or 'lossless'	'lossy'

imwrite

Parameter	Values	Default
'ProgressionOrdOm'e of the following text strings: 'LRCP', 'RLCP', 'RPCL', 'PCRL' or 'CPRL'. The characters in these text strings represent the following: L=layer, R=resolution, C=component and P=position. The first character refers to the index which progresses most slowly, while the last refers to the index which progresses most quickly.		'LRCP'
'QualityLayers	'A positive integer (not exceeding 20) specifying the number of quality layers.	1
'ReductionLevel A'positive integer (not exceeding 8) specifying the number of reduction levels or the wavelet decomposition levels		
'TileSize'	A 2-element vector specifying tile height and tile width. The minimum tile size that can be specified is [128 128].	tile size is same as the image size

PBM-, PGM-, and PPM-Specific Parameters

This table describes the available parameters for PBM, PGM, and PPM files.

Parameter	Values	Default
'Encoding'	One of these strings: 'ASCII' for plain encoding 'rawbits' for binary encoding	'rawbits'
'MaxValue'	A scalar indicating the maximum gray or color value. Available only for PGM and PPM files. For PBM files, this value is always 1.	Default is 65535 if image array is 'uint16'; 255 otherwise.

PNG-Specific Parameters

The following table lists the available parameters for PNG files, in alphabetical order. In addition to these PNG parameters, you can use any parameter name that satisfies the PNG specification for keywords; that is, uses only printable characters, contains 80 or fewer characters, and no contains no leading or trailing spaces. The value corresponding to these user-specified parameters must be a string that contains no control characters other than linefeed.

Parameter	Values	
'Alpha'	A matrix specifying the transparency of each pixel individually. The row and column dimensions must be the same as the data array; they can be uint8, uint16, or double, in which case the values should be in the range [0,1].	
'Author'	A string	
'Background'	The value specifies background color to be used when compositing transparent pixels. For indexed images: an integer in the range [1,P], where P is the colormap length. For grayscale images: a scalar in the range [0,1]. For truecolor images: a three-element vector in the range [0,1].	
'bitdepth'	A scalar value indicating desired bit depth.	
	For grayscale images this can be 1, 2, 4, 8, or 16.	
	For grayscale images with an alpha channel this can be 8 or 16.	
	For indexed images this can be 1, 2, 4, or 8.	
	For truecolor images with or without an alpha channel this can be 8 or 16.	
	By default, imwrite uses 8 bits per pixel, if image is double or uint8; 16 bits per pixel if image is uint16; 1 bit per pixel if image is logical.	

imwrite

Parameter	Values
'Chromaticities'	An eight-element vector [wx wy rx ry gx gy bx by] that specifies the reference white point and the primary chromaticities
'Comment'	A string
'Copyright'	A string
'CreationTime'	A string
'Description'	A string
'Disclaimer'	A string
'Gamma'	A nonnegative scalar indicating the file gamma
'ImageModTime'	A MATLAB serial date number (see the datenum function) or a string convertible to a date vector via the datevec function. Values should be in Coordinated Universal Time (UTC).
'InterlaceType'	Either 'none' (the default) or 'adam7'
'ResolutionUnit'	Either 'unknown' or 'meter'
'SignificantBits'	A scalar or vector indicating how many bits in the data array should be regarded as significant; values must be in the range [1,BitDepth].
	For indexed images: a three-element vector. For grayscale images: a scalar. For grayscale images with an alpha channel: a two-element vector. For truecolor images: a three-element vector. For truecolor images with an alpha channel: a four-element vector.
'Software'	A string
'Source'	A string

Parameter	Values	
'Transparency'	This value is used to indicate transparency information only when no alpha channel is used. Set to the value that indicates which pixels should be considered transparent. (If the image uses a colormap, this value represents an index number to the colormap.)	
	For indexed images: a Q-element vector in the range [0,1], where Q is no larger than the colormap length and each value indicates the transparency associated with the corresponding colormap entry. In most cases, Q = 1.	
	For grayscale images: a scalar in the range [0,1]. The value indicates the grayscale color to be considered transparent.	
	For truecolor images: a three-element vector in the range [0,1]. The value indicates the truecolor color to be considered transparent.	
	Note You cannot specify 'Transparency' and 'Alpha' at the same time.	
'Warning'	A string	
'XResolution'	A scalar indicating the number of pixels/unit in the horizontal direction	
'YResolution'	A scalar indicating the number of pixels/unit in the vertical direction	

RAS-Specific Parameters

This table describes the available parameters for RAS files.

Parameter	Values	Default
'Alpha'	A matrix specifying the transparency of each pixel individually; the row and column dimensions must be the same as the data array; can be uint8, uint16, or double. Can only be used with truecolor images.	Empty matrix ([])
'Type'	One of these strings: 'standard' (uncompressed, b-g-r color order with truecolor images) 'rgb' (like 'standard', but uses r-g-b color order for truecolor images) 'rle' (run-length encoding of 1-bit and 8-bit images)	'standard'

TIFF-Specific Parameters

This table describes the available parameters for TIFF files.

Parameter	Values	
'ColorSpace'	Specifies the color space used to represent the color data. 'rgb' 'cielab' 'icclab' ¹ (default is 'rgb').	
	Note: To use the CMYK color space in a TIFF file, do not use the 'ColorSpace' parameter. It is sufficient to specify an M-by-N-by-4 input array.	
'Compression'	'none' 'packbits' (default for non-binary images) 'lzw' 'deflate' 'jpeg' 'ccitt' (binary images only; default) 'fax3' (binary images only) 'fax4' (binary images only) Note: 'jpeg' is a lossy compression scheme; other compression modes are lossless. Also, if you specify 'jpeg' compression, you	

Parameter	Values	
	must specify the 'RowsPerStrip' parameter and the value must be a multiple of 8.	
'Description'	Any string; fills in the ImageDescription field returned by imfinfo. By default, the field is empty.	
'Resolution'	A two-element vector containing the XResolution and YResolution, or a scalar indicating both resolutions. The default value is 72.	
'RowsPerStrip'	A scalar value specifying the number of rows to include in each strip. The default will be such that each strip is about 8K bytes.	
	Note: You must specify the 'RowsPerStrip' parameter if you specify 'jpeg' compression. The value must be a multiple of 8.	
'WriteMode'	'overwrite' (default)	
	'append'	

¹imwrite can write color image data that uses the $L^*a^*b^*$ color space to TIFF files. The 1976 CIE $L^*a^*b^*$ specification defines numeric values that represent luminance (L^*) and chrominance $(a^*$ and $b^*)$ information. To store $L^*a^*b^*$ color data in a TIFF file, the values must be encoded to fit into either 8-bit or 16-bit storage. imwrite can store $L^*a^*b^*$ color data in a TIFF file using 8-bit and 16-bit encodings defined by the TIFF specification, called the CIELAB encodings, or using 8-bit and 16-bit encodings defined by the International Color Consortium, called ICCLAB encodings.

The output class and encoding used by imwrite depends on the class of the input array and the value of the TIFF-specific ColorSpace parameter. The following table explains these options. (The 8-bit and 16-bit CIELAB encodings cannot be input arrays because they use a mixture of signed and unsigned values and cannot be represented as a single MATLAB array.)

Input Class and Encoding	ColorSpace Parameter Value	Output Class and Encoding
8-bit ICCLAB	'icclab'	8-bit ICCLAB
Represents values as integers in the range [0 255]. L* values are multiplied by 255/100. 128 is added to both the a* and b* values.		
	'cielab'	8-bit CIELAB
16-bit ICCLAB	'icclab'	16-bit ICCLAB
Represents the values as integers in the range [0, 65280]. <i>L*</i> values are multiplied by 65280/100. 32768 is added to both the <i>a*</i> and <i>b*</i> values, which are represented as integers in the range [0,65535].		
	'cielab'	16-bit CIELAB

Input Class and Encoding	ColorSpace Parameter Value	Output Class and Encoding
Double-precision 1976 CIE $L^*a^*b^*$ values L^* is in the dynamic range [0, 100]. a^* and b^* can take any value. Setting a^* and b^* to 0 (zero) produces a neutral color (gray).	'icclab'	8-bit ICCLAB
	'cielab'	8-bit CIELAB

For copyright information, see the libtiffcopyright.txt file.

Example

This example appends an indexed image X and its colormap map to an existing uncompressed multipage HDF4 file.

```
imwrite(X,map,'your_hdf_file.hdf','Compression','none',...
'WriteMode','append')
```

See Also

 $fwrite,\,getframe,\,imfinfo,\,imformats,\,imread$

"Bit-Mapped Images" on page 1-101 for related functions

TriRep.incenters

Purpose Incenters of specified simplices

Syntax IC = incenters(TR,SI)

[IC RIC] = incenters(TR, SI)

Description IC = incenters(TR,SI) returns the coordinates of the incenter of each

specified simplex SI.

[IC RIC] = incenters(TR, SI) returns the incenters and the

corresponding radius of the inscribed circle/sphere.

Input Arguments

TR Triangulation representation.

SI Column vector of simplex indices that index into

the triangulation matrix TR.Triangulation. If SI is not specified the incenter information for the entire triangulation is returned, where the incenter associated with simplex i is the i'th row of IC.

Output Arguments

IC m-by-n matrix, where m = length(SI), the number

of specified simplices, and n is the dimension of the space where the triangulation resides. Each row IC(i,:) represents the coordinates of the incenter of

simplex SI(i).

RIC Vector of length length(SI), the number of specified

simplices.

Definitions

A simplex is a triangle/tetrahedron or higher-dimensional equivalent.

Examples Example 1

Load a 3-D triangulation:

load tetmesh

Use TriRep to compute the incenters of the first five tetrahedra.

```
trep = TriRep(tet, X)
ic = incenters(trep, [1:5]')
```

Example 2

Query a 2-D triangulation created with DelaunayTri.

```
x = [0 1 1 0 0.5]';
y = [0 0 1 1 0.5]';
dt = DelaunayTri(x,y);
```


Compute incenters of the triangles:

```
ic = incenters(dt);
```

Plot the triangles and incenters:

```
triplot(dt);
axis equal;
axis([-0.2 1.2 -0.2 1.2]);
hold on;
plot(ic(:,1),ic(:,2),'*r');
hold off;
```

TriRep.incenters



See Also

DelaunayTri circumcenters

DelaunayTri.inOutStatus

Purpose

Status of triangles in 2-D constrained Delaunay triangulation

Syntax

IN = inOutStatus(DT)

Description

IN = inOutStatus(DT) returns the in/out status of the triangles in a 2-D constrained Delaunay triangulation of a geometric domain. Given a Delaunay triangulation that has a set of constrained edges that define a bounded geometric domain. The i'th triangle in the triangulation is classified as inside the domain if IN(i) = 1 and outside otherwise.

Note inOutStatus is only relevant for 2-D constrained Delaunay triangulations where the imposed edge constraints bound a closed geometric domain.

Input Arguments

DT

Delaunay triangulation.

Output Arguments

ΙN

Logical array of length equal to the number of triangles in the triangulation. The constrained edges in the triangulation define the boundaries of a valid geometric domain.


Example

Create a geometric domain that consists of a square with a square hole:

```
outerprofile = [-5 -5; -3 -5; -1 -5; 1 -5; 3 -5; ...
5 -5; 5 -3; 5 -1; 5 1; 5 3;...
5 5; 3 5; 1 5; -1 5; -3 5; ...
-5 5; -5 3; -5 1; -5 -1; -5 -3; ];
innerprofile = outerprofile.*0.5;
profile = [outerprofile; innerprofile];
outercons = [(1:19)' (2:20)'; 20 1;];
innercons = [(21:39)' (22:40)'; 40 21];
```

```
edgeconstraints = [outercons; innercons];
Create a constrained Delaunay triangulation of the domain:
  dt = DelaunayTri(profile, edgeconstraints)
  subplot(1,2,1);
  triplot(dt);
  hold on:
  plot(dt.X(outercons',1), dt.X(outercons',2), ...
        '-r', 'LineWidth', 2);
  plot(dt.X(innercons',1), dt.X(innercons',2), ...
        '-r', 'LineWidth', 2);
  axis equal;
  % Plot showing interior and exterior
  % triangles with respect to the domain.
  hold off;
  subplot(1,2,2);
  inside = inOutStatus(dt);
  triplot(dt(inside, :), dt.X(:,1), dt.X(:,2));
  hold on;
  plot(dt.X(outercons',1), dt.X(outercons',2), ...
        '-r', 'LineWidth', 2);
  plot(dt.X(innercons',1), dt.X(innercons',2), ...
        '-r', 'LineWidth', 2);
  axis equal;
  % Plot showing interior triangles only
  hold off;
```

DelaunayTri.inOutStatus



ind2rgb

Purpose Convert indexed image to RGB image

Syntax RGB = ind2rgb(X,map)

Description RGB = ind2rgb(X,map) converts the matrix X and corresponding

colormap map to RGB (truecolor) format.

Class Support

 \mbox{X} can be of class uint8, uint16, or double. RGB is an m-by-n-by-3

array of class double.

See Also image

"Bit-Mapped Images" on page 1-101 for related functions

Purpose

Subscripts from linear index

Syntax

```
[I,J] = ind2sub(siz,IND)
[I1,I2,I3,...,In] = ind2sub(siz,IND)
```

Description

The ind2sub command determines the equivalent subscript values corresponding to a single index into an array.

[I,J] = ind2sub(siz,IND) returns the matrices I and J containing the equivalent row and column subscripts corresponding to each linear index in the matrix IND for a matrix of size siz. Siz is a vector with ndim(A) elements (in this case, 2), where siz(1) is the number of rows and siz(2) is the number of columns.

Note For matrices, [I,J] = ind2sub(size(A),find(A>5)) returns the same values as [I,J] = find(A>5).

[I1,I2,I3,...,In] = ind2sub(siz,IND) returns n subscript arrays I1,I2,...,In containing the equivalent multidimensional array subscripts equivalent to IND for an array of size siz. siz is an n-element vector that specifies the size of each array dimension.

Examples

Example 1 — Two-Dimensional Matrices

The mapping from linear indexes to subscript equivalents for a 3-by-3 matrix is

ind2sub

1	4	7
2	5	8
3	6	9




1,1	1,2	1,3
2,1	2,2	2,3
3,1	3,2	3,3

This code determines the row and column subscripts in a 3-by-3 matrix, of elements with linear indices $3,\,4,\,5,\,6.$

Example 2 — Three-Dimensional Matrices

The mapping from linear indexes to subscript equivalents for a 2-by-2-by-2 array is



This code determines the subscript equivalents in a 2-by-2-by-2 array, of elements whose linear indices 3, 4, 5, 6 are specified in the IND matrix.

Example 3 — Effects of Returning Fewer Outputs

When calling ind2sub for an N-dimensional matrix, you would typically supply N output arguments in the call: one for each dimension of the matrix. This example shows what happens when you return three, two, and one output when calling ind2sub on a 3-dimensional matrix.

The matrix is 2-by-2-by-2 and the linear indices are 1 through 8:

```
dims = [2 2 2];
indices = [1 2 3 4 5 6 7 8];
```

The 3-output call to ind2sub returns the expected subscripts for the 2-by-2-by-2 matrix:

[rowsub colsub		pagsub]	=	ind2sub(dims,		indices)	
rowsub	=						
1	2	1	2	1	2	1	2
colsub	=						
1	1	2	2	1	1	2	2
pagsub	=						
1	1	1	1	2	2	2	2

If you specify only two outputs (row and column), ind2sub still returns a subscript for each specified index, but drops the third dimension from the matrix, returning subscripts for a 2-dimensional, 2-by-4 matrix instead:

If you specify one output (row), ind2sub drops both the second and third dimensions from the matrix, and returns subscripts for a 1-dimensional, 1-by-8 matrix instead:

See Also

find, size, sub2ind

Purpose Infinity

Syntax

```
Inf
Inf('double')
Inf('single')
Inf(n)
Inf(m,n)
Inf(m,n,p,...)
```

Inf(m,n,p,...) Inf(...,classname)

Description

Inf returns the IEEE arithmetic representation for positive infinity. Infinity results from operations like division by zero and overflow, which lead to results too large to represent as conventional floating-point values.

Inf('double') is the same as Inf with no inputs.

Inf('single') is the single precision representation of Inf.

Inf(n) is an n-by-n matrix of Infs.

Inf(m,n) or inf([m,n]) is an m-by-n matrix of Infs.

Inf(m,n,p,...) or Inf([m,n,p,...]) is an m-by-n-by-p-by-... array of Infs.

Note The size inputs m, n, p, ... should be nonnegative integers. Negative integers are treated as 0.

Inf(...,classname) is an array of Infs of class specified by classname. classname must be either 'single' or 'double'.

Examples

1/0, 1.e1000, 2^2000, and exp(1000) all produce Inf.

log(0) produces - Inf.

 $\label{lem:inf-inf} \mbox{Inf-Inf both produce NaN (Not-a-Number)}.$

Inf

See Also

isinf, NaN

Purpose

Specify inferior class relationship

Syntax

inferiorto('class1','class2',...)

Description

inferiorto('class1','class2',...) establishes that the class invoking this function in its constructor has lower precedence than the classes in the argument list. MATLAB uses this precedence to determines which method or function MATLAB calls in any given situation.

Use this function only from a constructor that calls the class function to create objects (classes defined before MATLAB 7.6).

Examples

Specify class precedence.

Suppose a is an object of class class_a, b is an object of class class_b, and c is an object of class class_c. Suppose the constructor method of class c contains the statement:

```
inferiorto('class_a')
```

This function call establishes class_a as taking precedence over class_c for function dispatching. Therefore, either of the following two statements:

```
e = fun(a,c);
e = fun(c,a);
```

Invoke class a/fun.

If you call a function with two objects having an unspecified relationship, the two objects have equal precedence. In this case, MATLAB calls the method of the left-most object. So fun(b, c) calls class_b/fun, while fun(c, b) calls class c/fun.

See Also

superiorto

info

Purpose Information about contacting The MathWorks

Syntax info

Description info displays in the Command Window, information about contacting

The MathWorks.

See Also help, version

Purpose

Construct inline object

Syntax

inline(expr)

inline(expr,arg1,arg2,...)

inline(expr,n)

Description

inline(expr) constructs an inline function object from the MATLAB expression contained in the string expr. The input argument to the inline function is automatically determined by searching expr for an isolated lower case alphabetic character, other than i or j, that is not part of a word formed from several alphabetic characters. If no such character exists, x is used. If the character is not unique, the one closest to x is used. If two characters are found, the one later in the alphabet is chosen.

inline(expr, arg1, arg2,...) constructs an inline function whose input arguments are specified by the strings arg1, arg2,....

Multicharacter symbol names may be used.

inline(expr,n) where n is a scalar, constructs an inline function whose input arguments are x, P1, P2, ...

Remarks

Three commands related to inline allow you to examine an inline function object and determine how it was created.

char(fun) converts the inline function into a character array. This is identical to formula(fun).

argnames(fun) returns the names of the input arguments of the inline object fun as a cell array of strings.

formula(fun) returns the formula for the inline object fun.

A fourth command vectorize(fun) inserts a . before any ^, * or /' in the formula for fun. The result is a vectorized version of the inline function.

Examples Example 1

This example creates a simple inline function to square a number.

```
g = inline('t^2')
g =

Inline function:
    g(t) = t^2
```

You can convert the result to a string using the char function.

```
char(g)
ans =
t^2
```

Example 2

This example creates an inline function to represent the formula $f = 3\sin(2x^2)$. The resulting inline function can be evaluated with the argnames and formula functions.

Example 3

This call to inline defines the function f to be dependent on two variables, alpha and x:

If inline does not return the desired function variables or if the function variables are in the wrong order, you can specify the desired variables explicitly with the inline argument list.

```
g = inline('sin(alpha*x)','x','alpha')
g =
    Inline function:
    g(x,alpha) = sin(alpha*x)
```

Names of functions, MEX-files, Sun Java classes in memory

Syntax

```
M = inmem
[M, X] = inmem
[M, X, J] = inmem
[...] = inmem('-completenames')
```

Description

M = inmem returns a cell array of strings containing the names of the functions that are currently loaded.

[M, X] = inmem returns an additional cell array X containing the names of the MEX-files that are currently loaded.

[M, X, J] = inmem also returns a cell array J containing the names of the Java classes that are currently loaded.

[...] = inmem('-completenames') returns not only the names of the currently loaded function and MEX-files, but the path and filename extension for each as well. No additional information is returned for loaded Java classes.

Examples

Example 1

This example lists the functions that are required to run erf.

```
clear all; % Clear the workspace
erf(0.5);

M = inmem
M =
   'erf'
```

Example 2

Generate a plot, and then find the function and MEX-files that had been loaded to perform this operation:

```
clear all
surf(peaks)
```

```
[m x] = inmem('-completenames');

m{1:5}
ans =
    F:\matlab\toolbox\matlab\general\usejava.m
ans =
    F:\matlab\toolbox\matlab\graph3d\private\surfchk.m
ans =
    F:\matlab\toolbox\matlab\graphics\gcf.m
ans =
    F:\matlab\toolbox\matlab\datatypes\@opaque\char.m
ans =
    F:\matlab\toolbox\matlab\graphics\findall.m

x
x =
    Empty cell array: 0-by-1
```

See Also clear

Points inside polygonal region

Syntax

```
IN = inpolygon(X,Y,xv,yv)
[IN ON] = inpolygon(X,Y,xv,yv)
```

Description

IN = inpolygon(X,Y,xv,yv) returns a matrix IN the same size as X and Y. Each element of IN is assigned the value 1 or 0 depending on whether the point (X(p,q),Y(p,q)) is inside the polygonal region whose vertices are specified by the vectors xv and yv. In particular:

```
IN(p,q) = 1 If (X(p,q),Y(p,q)) is inside the polygonal region or on the polygon boundary
```

IN(p,q) = 0 If (X(p,q),Y(p,q)) is outside the polygonal region

[IN ON] = inpolygon(X,Y,xv,yv) returns a second matrix ON the same size as X and Y. Each element of ON is assigned the value 1 or 0 depending on whether the point (X(p,q),Y(p,q)) is on the boundary of the polygonal region whose vertices are specified by the vectors xv and yv. In particular:


```
ON(p,q) = 1 If (X(p,q),Y(p,q)) is on the polygon boundary
```

ON(p,q) = 0 If (X(p,q),Y(p,q)) is inside or outside the polygon boundary

Examples

```
L = linspace(0,2.*pi,6); xv = cos(L)';yv = sin(L)';
xv = [xv; xv(1)]; yv = [yv; yv(1)];
x = randn(250,1); y = randn(250,1);
in = inpolygon(x,y,xv,yv);
plot(xv,yv,x(in),y(in),'r+',x(~in),y(~in),'bo')
```

inpolygon



Request user input

Syntax

```
evalResponse = input(prompt)
strResponse = input(prompt, 's')
```

Description

evalResponse = input(prompt) displays the prompt string on the
screen, waits for input from the keyboard, evaluates any expressions
in the input, and returns the value in evalResponse. To evaluate
expressions, the input function accesses variables in the current
workspace.

strResponse = input(prompt, 's') returns the entered text as a
MATLAB string, without evaluating expressions.

Remarks

If you press the **Return** key without entering anything, input returns an empty matrix.

To create a prompt that spans several lines, use '\n' to indicate each new line. To include a backslash ('\') in the prompt, use '\\'.

If you enter an invalid expression at the prompt, MATLAB displays the relevant error message and then redisplays the prompt.

Examples

Request a text response. Assign a default value ('Y') by checking for an empty matrix.

```
reply = input('Do you want more? Y/N [Y]: ', 's');
if isempty(reply)
    reply = 'Y';
end
```

See Also

keyboard, inputdlg, menu, ginput, uicontrol

Create and open input dialog box

Syntax

```
answer = inputdlg(prompt)
```

answer = inputdlg(prompt,dlg_title)

answer = inputdlg(prompt,dlg_title,num_lines)

answer = inputdlg(prompt,dlg_title,num_lines,defAns)

answer = inputdlg(prompt,dlg_title,num_lines,defAns,options)

Description

answer = inputdlg(prompt) creates a modal dialog box and returns user input for multiple prompts in the cell array. prompt is a cell array containing prompt strings.

Note A modal dialog box prevents the user from interacting with other windows before responding. For more information, see WindowStyle in the MATLAB Figure Properties.

answer = inputdlg(prompt,dlg_title) dlg_title specifies a title
for the dialog box.

answer = inputdlg(prompt,dlg_title,num_lines) num_lines specifies the number of lines for each user-entered value. num_lines can be a scalar, column vector, or matrix.

- If num_lines is a scalar, it applies to all prompts.
- If num_lines is a column vector, each element specifies the number of lines of input for a prompt.
- If num_lines is a matrix, it should be size m-by-2, where m is the number of prompts on the dialog box. Each row refers to a prompt. The first column specifies the number of lines of input for a prompt. The second column specifies the width of the field in characters.

answer = inputdlg(prompt,dlg_title,num_lines,defAns) defAns
specifies the default value to display for each prompt. defAns must

contain the same number of elements as prompt and all elements must be strings.

answer =

inputdlg(prompt,dlg_title,num_lines,defAns,options) If options is the string 'on', the dialog is made resizable in the horizontal direction. If options is a structure, the fields shown in the following table are recognized:

Field	Description
Resize	Can be 'on' or 'off' (default). If 'on', the window is resizable horizontally.
WindowStyle	Can be either 'normal' or 'modal' (default).
Interpreter	Can be either 'none' (default) or 'tex'. If the value is 'tex', the prompt strings are rendered using LaTeX.

If the user clicks the **Cancel** button to close an inputdlg box, the dialog returns an empty cell array:

```
answer =
{}
```

Remarks

inputdlg uses the uiwait function to suspend execution until the user responds.

The returned variable answer is a cell array containing strings, one string per text entry field, starting from the top of the dialog box.

To convert a member of the cell array to a number, use str2num. To do this, you can add the following code to the end of any of the examples below:

```
[val status] = str2num(answer{1}); % Use curly bracket for subscript
if ~status
    % Handle empty value returned for unsuccessful conversion
    % ...
end
```

% val is a scalar or matrix converted from the first input


Users can enter scalar or vector values into inputdlg fields; str2num converts space- and comma-delimited strings into row vectors, and semicolon-delimited strings into column vectors. For example, if answer{1} contains '1 2 3;4 -5 6+7i', the conversion produces:

```
val = str2num(answer{1})
val =
   1.0000   2.0000   3.0000
   4.0000   -5.0000   6.0000 + 7.0000i
```

Example Example 1

Create a dialog box to input an integer and colormap name. Allow one line for each value.


```
prompt = {'Enter matrix size:','Enter colormap name:'};
dlg_title = 'Input for peaks function';
num_lines = 1;
def = {'20','hsv'};
answer = inputdlg(prompt,dlg_title,num_lines,def);
```



Example 2


Create a dialog box using the default options. Then use the options to make it resizable and not modal, and to interpret the text using LaTeX.

```
name='Input for Peaks function';
numlines=1;
defaultanswer={'20','hsv'};
answer=inputdlg(prompt,name,numlines,defaultanswer);
```



```
options.Resize='on';
options.WindowStyle='normal';
options.Interpreter='tex';
```

answer=inputdlg(prompt,name,numlines,defaultanswer,options);



See Also

dialog, errordlg, helpdlg, listdlg, msgbox, questdlg, warndlg, input

figure, str2num, uiwait, uiresume

"Predefined Dialog Boxes" on page 1-113 for related functions

Variable name of function input

Syntax

inputname(argnum)

Description

This command can be used only inside the body of a function.

inputname(argnum) returns the workspace variable name corresponding to the argument number argnum. If the input argument has no name (for example, if it is an expression instead of a variable), the inputname command returns the empty string ('').

Examples

Suppose the function myfun.m is defined as

```
function c = myfun(a,b)
  fprintf('First calling variable is "%s"\n.', inputname(1))

Then
    x = 5;    y = 3;    myfun(x,y)

produces
    First calling variable is "x".

But
    myfun(pi+1, pi-1)

produces
    First calling variable is "".
```

See Also

nargin, nargout, nargchk

inputParser

Purpose

Construct input parser object

Syntax

p = inputParser

Description

p = inputParser creates a data structure that is a key part of the Input Parser argument checking utility provided with MATLAB. The purpose of this utility is to verify that each input passed to a function conforms to the expected type and value.

You add this parsing capability to your function code by constructing an object p of the inputParser class, and recording the expected types and values for the inputs to your function in that object. With this done, every call to your function activates the Input Parser utility to compare the values passed into your function against the expected types and values you have recorded in the inputParser object.

For more information on the inputParser class, see "Validating Inputs with Input Parser" in the MATLAB Programming Fundamentals documentation.

Methods

Method	Description		
addOptional	Add an optional argument to the schema		
addParamValue	Add a parameter-value pair argument to the schema		
addRequired	Add a required argument to the schema		
createCopy	Create a copy of the inputParser object		
parse	Parse and validate the named inputs		

Properties

Property	Description		
CaseSensitive	Enable or disable case-sensitive matching of argument names		
FunctionName	Function name to be included in error messages		
KeepUnmatched	Enable or disable errors on unmatched arguments		
Parameters	Names of arguments defined in inputParser schema		
Results	Names and values of arguments passed in function call that are in the schema for this function		
StructExpand	Enable or disable passing arguments in a structure		
Unmatched	Names and values of arguments passed in function call that are not in the schema for this function		
UsingDefaults	Names of arguments not passed in function call that are given default values		

Property Descriptions

Properties of the inputParser class are described below.

CaseSensitive

Purpose — Enable or disable case sensitive matching of argument names

p.CaseSensitive = TF enables or disables case-sensitivity when matching entries in the argument list with argument names in the schema. Set CaseSensitive to logical 1 (true) to enable case-sensitive matching, or to logical 0 (false) to disable it. By default, case-sensitive matching is disabled.

FunctionName

Purpose — Function name to be included in error messages

p.FunctionName = name stores a function name that is to be included in error messages that might be thrown in the process of validating input arguments to the function. The name input is a string containing the name of the function for which you are parsing inputs with inputParser.

KeepUnmatched

Purpose — Enable or disable errors on unmatched arguments

p.KeepUnmatched = TF controls whether MATLAB throws an error when the function being called is passed an argument that has not been defined in the inputParser schema for this file. When this property is set to logical 1 (true), MATLAB does not throw an error, but instead stores the names and values of unmatched arguments in the Unmatched property of object p. When KeepUnmatched is set to logical 0 (false), MATLAB does throw an error whenever this condition is encountered and the Unmatched property is not affected.

Parameters

Purpose — Names of arguments defined in inputParser schema

c = p.Parameters is a cell array of strings containing the names of those arguments currently defined in the schema for the object. Each row of the Parameters cell array is a string containing the full name of a known argument.

Results

Purpose — Names and values of arguments passed in function call that are in the schema for this function

arglist = p.Results is a structure containing the results of the most recent parse of the input argument list. Each argument passed to the function is represented by a field in the Results structure, and the value of that argument is represented by the value of that field.

StructExpand

Purpose — Enable or disable passing arguments in a structure

p.StructExpand = TF, when set to logical 1 (true), tells MATLAB to accept a structure as an input in place of individual parameter-value arguments. If StructExpand is set to logical 0 (false), a structure is treated as a regular, single input.

Unmatched

Purpose — Names and values of arguments passed in function call that are not in the schema for this function

c = p.Unmatched is a structure array containing the names and values of all arguments passed in a call to the function that are not included in the schema for the function. Unmatched only contains this list of the KeepUnmatched property is set to true. If KeepUnmatched is set to false, MATLAB throws an error when unmatched arguments are passed in the function call. The Unmatched structure has the same format as the Results property of the inputParser class.

UsingDefaults

Purpose — Names of arguments not passed in function call that are given default values

defaults = p.UsingDefaults is a cell array of strings containing the names of those arguments that were not passed in the call to this function and consequently are set to their default values.

Example

This example writes a function called photoPrint that uses the Input Parser to check arguments passed to it. This function accepts up to eight input arguments. When called with the full set of inputs, the syntax is:

```
photoPrint(filename, format, finish, colorCode, ...
   'horizDim', hDim, 'vertDim', vDim);
```

Only the first two of these inputs are defined as required arguments; the rest are optional. The 'horizDim' and 'vertDim' arguments are in parameter name/value format. Pair the 'horizDim' parameter name

with its value *hDim*, and likewise the 'vertDim' name with its value *vDim*. Here are several possible calling syntaxes for the function:

```
photoPrint(filename, format);
photoPrint(filename, format, finish)
photoPrint(filename, format, finish, colorCode)
photoPrint(filename, format, finish, colorCode, ...
   'horizDim', hDim)
photoPrint(filename, format, finish, colorCode, ...
   'vertDim', vDim)
```

Begin writing the example function photoPrint by entering the following two statements into a file named photoPrint.m. The second statement calls the class constructor for inputParser to create an instance p of the class. This class instance, or object, gives you access to all of the methods and properties of the class:

```
function photoPrint(filename, format, varargin)
p = inputParser; % Create an instance of the class.
```

Add the following code to the photoPrint function. These statements call the addRequired, addOptional, and addParamValue methods to define the types of input data one can pass to this function:

Just after this, call the parse method to parse and validate the inputs. MATLAB puts the results of the parse into a property named Results:

```
p.parse(filename, format, varargin{:});
p.Results
```

Save and execute the file, passing the required and any number of the optional input arguments. Examining p.Results displays the name of each input as a field, and the value of each input as the value of that field:

See Also

addRequired(inputParser), addOptional(inputParser),
addParamValue(inputParser), parse(inputParser),
createCopy(inputParser), validateattributes, validatestring,
varargin, nargchk, nargin

inspect

Purpose

Open Property Inspector

Syntax

inspect
inspect(h)
inspect([h1,h2,...])

Description

inspect creates a separate Property Inspector window to enable the display and modification of the properties of any object you select in the figure window or Layout Editor. If no object is selected, the Property Inspector is blank.

inspect(h) creates a Property Inspector window for the object whose handle is h.

inspect([h1,h2,...]) displays properties that objects h1 and h2 have in common, or a blank window if there are no such properties; any number of objects can be inspected and edited in this way (for example, handles returned by the bar command).

The Property Inspector has the following behaviors:

- Only one Property Inspector window is active at any given time; when you inspect a new object, its properties replace those of the object last inspected.
- When the Property Inspector is open and plot edit mode is on, clicking any object in the figure window displays the properties of that object (or set of objects) in the Property Inspector.
- When you select and inspect two or more objects of different types, the Property Inspector only shows the properties that all objects have in common.
- To change the value of any property, click on the property name shown at the left side of the window, and then enter the new value in the field at the right.

The Property Inspector provides two different views:

- List view properties are ordered alphabetically (default); this is the only view available for annotation objects.
- Group view properties are grouped under classified headings (Handle Graphics objects only)

To view alphabetically, click the "AZ" Icon in the Property Inspector toolbar. To see properties in groups, click

the "++" icon . When properties are grouped, the "-" and "+" icons are enabled; click to expand all categories and click to collapse all categories. You can also expand and collapse individual categories by clicking on the "+" next to the category name. Some properties expand and collapse

Notes To see a complete description of any property, right-click on its name or value and select **What's This**; a help window opens that displays the reference page entry for it.

The Property Inspector displays most, but not all, properties of Handle Graphics objects. For example, the parent and children of HG objects are not shown.


inspect h displays a Property Inspector window that enables modification of the string 'h', not the object whose handle is h. If you modify properties at the MATLAB command line, you must refresh the Property Inspector window to see the change reflected there. Refresh the Property Inspector by reinvoking inspect on the object.

Examples Example 1


Create a surface mesh plot and view its properties with the Property Inspector:

```
Z = peaks(30);
h = surf(Z)
```


inspect(h)



Use the Property Inspector to change the FaceAlpha property from 1.0 to 0.4 (equivalent to the command set(h, 'FaceAlpha',0.4)). FaceAlpha controls the transparency of patch faces.




When you press $\bf Enter$ or click a different field, the FaceAlpha property of the surface object is updated:



Example 2

Create a serial port object for COM1 on a Windows platform and use the Property Inspector to peruse its properties:

```
s = serial('COM1');
inspect(s)
```



Because COM objects do not define property groupings, only the alphabetical list view of their properties is available.


Example 3

Create a COM Excel server and open a Property Inspector window with inspect:

```
h = actxserver('excel.application');
inspect(h)
```

Scroll down until you see the CalculationInterruptKey property, which by default is xlAnyKey. Click on the down-arrow in the right

margin of the property inspector and select xlEscKey from the drop-down menu, as shown below:



Check this field in the MATLAB command window using get to confirm that it has changed:

```
get(h, 'CalculationInterruptKey')
ans =
xlEscKey
```

inspect

See Also

get, set, isprop, guide, addproperty, deleteproperty

Event information when event occurs

Syntax

instrcallback(obj,event)

Description

instrcallback(obj, event) displays a message that contains the event type, event, the time the event occurred, and the name of the serial port object, obj, that caused the event to occur.

For error events, the error message is also displayed. For pin status events, the pin that changed value and its value are also displayed.

Remarks

You should use instrcallback as a template from which you create callback functions that suit your specific application needs.

Example

The following example creates the serial port objects s, on a Windows platform. It configures s to execute instrcallback when an output-empty event occurs. The event occurs after the *IDN? command is written to the instrument.

```
s = serial('COM1');
set(s,'OutputEmptyFcn',@instrcallback)
fopen(s)
fprintf(s,'*IDN?','async')
```

The resulting display from instrcallback is shown below.

```
OutputEmpty event occurred at 08:37:49 for the object: Serial-COM1.
```

Read the identification information from the input buffer and end the serial port session.

```
idn = fscanf(s);
fclose(s)
delete(s)
clear s
```

Read serial port objects from memory to MATLAB workspace

Syntax

```
out = instrfind
```

out = instrfind('PropertyName',PropertyValue,...)

out = instrfind(S)

out = instrfind(obj, 'PropertyName', PropertyValue,...)

Description

out = instrfind returns all valid serial port objects as an array to out.

out = instrfind('*PropertyName*', PropertyValue,...) returns an array of serial port objects whose property names and property values match those specified.

out = instrfind(S) returns an array of serial port objects whose property names and property values match those defined in the structure S. The field names of S are the property names, while the field values are the associated property values.

out = instrfind(obj, 'PropertyName', PropertyValue,...) restricts the search for matching property name/property value pairs to the serial port objects listed in obj.

Remarks

Refer to "Displaying Property Names and Property Values" for a list of serial port object properties that you can use with instrfind.

You must specify property values using the same format as the get function returns. For example, if get returns the Name property value as MyObject, instrfind will not find an object with a Name property value of myobject. However, this is not the case for properties that have a finite set of string values. For example, instrfind will find an object with a Parity property value of Even or even.

You can use property name/property value string pairs, structures, and cell array pairs in the same call to instrfind.

Example

Suppose you create the following two serial port objects on a Windows platform.

```
s1 = serial('COM1');
```

```
s2 = serial('COM2');
set(s2,'BaudRate',4800)
fopen([s1 s2])
```

You can use instrfind to return serial port objects based on property values.

```
out1 = instrfind('Port','COM1');
out2 = instrfind({'Port','BaudRate'},{'COM2',4800});
```

You can also use instrfind to return cleared serial port objects to the MATLAB workspace.

```
clear s1 s2
newobjs = instrfind
```

To close both s1 and s2

```
fclose(newobjs)
```

See Also Functions

clear, get

Find visible and hidden serial port objects

Syntax

```
out = instrfindall
out = instrfindall('P1',V1,...)
out = instrfindall(s)
out = instrfindall(objs,'P1',V1,...)
```

Description

out = instrfindall finds all serial port objects, regardless of the value of the objects' ObjectVisibility property. The object or objects are returned to out.

out = instrfindall('P1', V1,...) returns an array, out, of serial port objects whose property names and corresponding property values match those specified as arguments.

out = instrfindall(s) returns an array, out, of serial port objects whose property names and corresponding property values match those specified in the structure s, where the field names correspond to property names and the field values correspond to the current value of the respective property.

out = instrfindall(objs, 'P1', V1,...) restricts the search for objects with matching property name/value pairs to the serial port objects listed in objs.

Note that you can use string property name/property value pairs, structures, and cell array property name/property value pairs in the same call to instrfindall.

Remarks

instrfindall differs from instrfind in that it finds objects whose ObjectVisibility property is set to off.

Property values are case sensitive. You must specify property values using the same format as that returned by the get function. For example, if get returns the Name property value as 'MyObject', instrfindall will not find an object with a Name property value of 'myobject'. However, this is not the case for properties that have a finite set of string values. For example, instrfindall will find an object with a Parity property value of 'Even' or 'even'.

Examples

Suppose you create the following serial port objects on a Windows platform:

```
s1 = serial('COM1');
s2 = serial('COM2');
set(s2,'ObjectVisibility','off')
```

Because object s2 has its ObjectVisibility set to 'off', it is not visible to commands like instrfind:

```
instrfind
```

```
Serial Port Object : Serial-COM1
```

However, instrfindall finds all objects regardless of the value of ObjectVisibility:

instrfindall

The following statements use instrfindall to return objects with specific property settings, which are passed as cell arrays:

```
props = {'PrimaryAddress', 'SecondaryAddress};
vals = {2,0};
obj = instrfindall(props,vals);
```

You can use instrfindall as an argument when you want to apply the command to all objects, visible and invisible. For example, the following statement makes all objects visible:

```
set(instrfindall, 'ObjectVisibility', 'on')
```

instrfindall

See Also Functions

get, instrfind

Properties

ObjectVisibility

int2str

Purpose Convert integer to string **Syntax** str = int2str(N)**Description** str = int2str(N) converts an integer to a string with integer format. The input N can be a single integer or a vector or matrix of integers. Noninteger inputs are rounded before conversion. **Examples** int2str(2+3) is the string '5'. One way to label a plot is title(['case number ' int2str(n)]) For matrix or vector inputs, int2str returns a string matrix: int2str(eye(3)) ans = 0 1 0 0 See Also fprintf, num2str, sprintf

Purpose Convert to signed integer

Syntax I = int8(X)

I = int16(X)
I = int32(X)
I = int64(X)

Description

I = int*(X) converts the elements of array X into signed integers. X can be any numeric object (such as a double). The results of an int* operation are shown in the next table.

Operation	Output Range	Output Type	Bytes per Element	Output Class
int8	-128 to 127	Signed 8-bit integer	1	int8
int16	-32,768 to 32,767	Signed 16-bit integer	2	int16
int32	-2,147,483,648 to 2,147,483,647	Signed 32-bit integer	4	int32
int64	-9,223,372,036,854,775,808 to 9,223,372,036,854,775,807	Signed 64-bit integer	8	int64

double and single values are rounded to the nearest int* value on conversion. A value of X that is above or below the range for an integer class is mapped to one of the endpoints of the range. For example,

```
int16(40000)
ans =
32767
```

If X is already a signed integer of the same class, then int* has no effect.

You can define or overload your own methods for int* (as you can for any object) by placing the appropriately named method in an @int* folder within a folder on your path. Type help datatypes for the names of the methods you can overload.

Remarks

Most operations that manipulate arrays without changing their elements are defined for integer values. Examples are reshape, size, the logical and relational operators, subscripted assignment, and subscripted reference.

Some arithmetic operations are defined for integer arrays on interaction with other integer arrays of the same class (e.g., where both operands are int16). Examples of these operations are +, -, .*, ./, .\ and .^. If at least one operand is scalar, then *, /, \, and ^ are also defined. Integer arrays may also interact with scalar double variables, including constants, and the result of the operation is an integer array of the same class. Integer arrays saturate on overflow in arithmetic.

Note Only the lower order integer data types support math operations. Math operations are not supported for int64 and uint64.

A particularly efficient way to initialize a large array is by specifying the data type (i.e., class name) for the array in the zeros, ones, or eye function. For example, to create a 100-by-100 int64 array initialized to zero, type

```
I = zeros(100, 100, 'int64');
```

An easy way to find the range for any MATLAB integer type is to use the intmin and intmax functions as shown here for int32:

```
intmin('int32') intmax('int32')

ans = ans = 2147483647
```

See Also

double, single, uint8, uint16, uint32, uint64, intmax, intmin

interfaces

Purpose List custom interfaces exposed by COM server object

Syntax customlist = h.interfaces customlist = interfaces(h)

Description customlist = h.interfaces returns cell array of strings customlist

listing all custom interfaces implemented by the component in a specific COM server object. The server is designated by input argument h, the handle returned by the actxcontrol or actxserver function when

creating that server.

customlist = interfaces(h) is an alternate syntax.

The interfaces function only lists the custom interfaces exposed by the object; it does not return interfaces. Use the invoke function to

return a handle to a specific custom interface.

COM functions are available on Microsoft Windows systems only.

See Also actxcontrol | actxserver | invoke | get (COM)

How To • "Custom Interfaces"

1-D data interpolation (table lookup)

Syntax

```
yi = interp1(x,Y,xi)
yi = interp1(Y,xi)
```

yi = interp1(x,Y,xi,method)

yi = interp1(x,Y,xi,method,'extrap')
yi = interp1(x,Y,xi,method,extrapval)

pp = interp1(x,Y,method,'pp')

Description

yi = interp1(x,Y,xi) interpolates to find yi, the values of the underlying function Y at the points in the vector or array xi. x must be a vector. Y can be a scalar, a vector, or an array of any dimension, subject to the following conditions:

- If Y is a vector, it must have the same length as x. A scalar value for Y is expanded to have the same length as x. xi can be a scalar, a vector, or a multidimensional array, and yi has the same size as xi.
- If Y is an array that is not a vector, the size of Y must have the form [n,d1,d2,...,dk], where n is the length of x. The interpolation is performed for each d1-by-d2-by-...-dk value in Y. The sizes of xi and yi are related as follows:
 - If xi is a scalar or vector, size(yi) equals [length(xi), d1, d2, ..., dk].
 - If xi is an array of size [m1,m2,...,mj], yi has size [m1,m2,...,mj,d1,d2,...,dk].

yi = interp1(Y,xi) assumes that x = 1:N, where N is the length of Y for vector Y, or size(Y,1) for matrix Y.

yi = interp1(x,Y,xi,method) interpolates using alternative methods:

'nearest' Nearest neighbor interpolation
'linear' Linear interpolation (default)

interp 1

'spline' Cubic spline interpolation

'pchip' Piecewise cubic Hermite interpolation

'cubic' (Same as 'pchip')

'v5cubic' Cubic interpolation used in MATLAB 5. This method

does not extrapolate. Also, if x is not equally spaced,

'spline' is used/


For the 'nearest', 'linear', and 'v5cubic' methods, interp1(x,Y,xi,method) returns NaN for any element of xi that is outside the interval spanned by x. For all other methods, interp1 performs extrapolation for out of range values.

yi = interp1(x,Y,xi,method,'extrap') uses the specified method to perform extrapolation for out of range values.

yi = interp1(x,Y,xi,method,extrapval) returns the scalar extrapval for out of range values. NaN and 0 are often used for extrapval.

pp = interp1(x,Y,method,'pp') uses the specified method to generate the piecewise polynomial form (ppform) of Y. You can use any of the methods in the preceding table, except for 'v5cubic'. pp can then be evaluated via ppval. ppval(pp,xi) is the same as interp1(x,Y,xi,method,'extrap').

The interp1 command interpolates between data points. It finds values at intermediate points, of a one-dimensional function f(x) that underlies the data. This function is shown below, along with the relationship between vectors x, y, xi, and yi.




Interpolation is the same operation as *table lookup*. Described in table lookup terms, the *table* is [x,Y] and interp1 *looks up* the elements of xi in x, and, based upon their locations, returns values yi interpolated within the elements of Y.

Note interp1q is quicker than interp1 on non-uniformly spaced data because it does no input checking. For interp1q to work properly, x must be a monotonically increasing column vector and Y must be a column vector or matrix with length(X) rows. Type help interp1q at the command line for more information.

Example 1

Generate a coarse sine curve and interpolate over a finer abscissa.

```
x = 0:10;
y = sin(x);
xi = 0:.25:10;
yi = interp1(x,y,xi);
plot(x,y,'o',xi,yi)
```



Example 2

The following multidimensional example creates 2-by-2 matrices of interpolated function values, one matrix for each of the three functions x^2 , x^3 , and x^4 .

```
x = [1:10]'; y = [ x.^2, x.^3, x.^4 ];
xi = [1.5, 1.75; 7.5, 7.75];
yi = interp1(x,y,xi);
```

The result yi has size 2-by-2-by-3.

Example 3

Here are two vectors representing the census years from 1900 to 1990 and the corresponding United States population in millions of people.


```
t = 1900:10:1990;
p = [75.995 91.972 105.711 123.203 131.669...
150.697 179.323 203.212 226.505 249.633];
```

The expression interp1(t,p,1975) interpolates within the census data to estimate the population in 1975. The result is

```
ans = 214.8585
```

Now interpolate within the data at every year from 1900 to 2000, and plot the result.

```
x = 1900:1:2000;
y = interp1(t,p,x,'spline');
plot(t,p,'o',x,y)
```



Sometimes it is more convenient to think of interpolation in table lookup terms, where the data are stored in a single table. If a portion of the census data is stored in a single 5-by-2 table,

tab	=	
	1950	150.697
	1960	179.323
	1970	203.212
	1980	226.505
	1990	249.633


then the population in 1975, obtained by table lookup within the matrix tab, is

```
p = interp1(tab(:,1),tab(:,2),1975)
p =
    214.8585
```

Example 4

The following example uses the 'cubic' method to generate the piecewise polynomial form (ppform) of Y, and then evaluates the result using ppval.

```
x = 0:.2:pi; y = sin(x);
pp = interp1(x,y,'cubic','pp');
xi = 0:.1:pi;
yi = ppval(pp,xi);
plot(x,y,'ko'), hold on, plot(xi,yi,'r:'), hold off
```



Algorithm

The interp1 command is a MATLAB M-file. The 'nearest' and 'linear' methods have straightforward implementations.

interp 1

For the 'spline' method, interp1 calls a function spline that uses the functions ppval, mkpp, and unmkpp. These routines form a small suite of functions for working with piecewise polynomials. spline uses them to perform the cubic spline interpolation. For access to more advanced features, see the spline reference page, the M-file help for these functions, and the Spline ToolboxTM.

For the 'pchip' and 'cubic' methods, interp1 calls a function pchip that performs piecewise cubic interpolation within the vectors x and y. This method preserves monotonicity and the shape of the data. See the pchip reference page for more information.

Interpolating Complex Data

For Real x and Complex Y. For interp1(x,Y,...) where x is real and Y is complex, you can use any interp1 method except for 'pchip'. The shape-preserving aspect of the 'pchip' algorithm involves the signs of the slopes between the data points. Because there is no notion of sign with complex data, it is impossible to talk about whether a function is increasing or decreasing. Consequently, the 'pchip' algorithm does not generalize to complex data.

The 'spline' method is often a good choice because piecewise cubic splines are derived purely from smoothness conditions. The second derivative of the interpolant must be continuous across the interpolating points. This does not involve any notion of sign or shape and so generalizes to complex data.

For Complex x. For interp1(x,Y,...) where x is complex and Y is either real or complex, use the two-dimensional interpolation routine interp2(REAL(x), IMAG(x),Y,...) instead.

See Also

interp1q, interpft, interp2, interp3, interpn, pchip, spline

References

[1] de Boor, C., A Practical Guide to Splines, Springer-Verlag, 1978.

Quick 1-D linear interpolation

Syntax

yi = interp1q(x,Y,xi)

Description

yi = interplq(x,Y,xi) returns the value of the 1-D function Y at the points of column vector xi using linear interpolation. The vector x specifies the coordinates of the underlying interval. The length of output yi is equal to the length of xi.

interp1q is quicker than interp1 on non-uniformly spaced data because it does no input checking.

For interp1q to work properly,


- x must be a monotonically increasing column vector.
- Y must be a column vector or matrix with length(x) rows.
- xi must be a column vector

interp1q returns NaN for any values of xi that lie outside the coordinates in x. If Y is a matrix, then the interpolation is performed for each column of Y, in which case yi is length(xi)-by-size(Y,2).

Example

Generate a coarse sine curve and interpolate over a finer abscissa.

```
x = (0:10)';
y = sin(x);
xi = (0:.25:10)';
yi = interp1q(x,y,xi);
plot(x,y,'o',xi,yi)
```



See Also

interp1, interp2, interp3, interpn

2-D data interpolation (table lookup)

Syntax

ZI = interp2(X,Y,Z,XI,YI)
ZI = interp2(Z,XI,YI)

ZI = interp2(Z, ntimes)

ZI = interp2(X,Y,Z,XI,YI,method)
ZI = interp2(...,method, extrapval)

Description

ZI = interp2(X,Y,Z,XI,YI) returns matrix ZI containing elements corresponding to the elements of XI and YI and determined by interpolation within the two-dimensional function specified by matrices X, Y, and Z. X and Y must be monotonic, and have the same format ("plaid") as if they were produced by meshgrid. Matrices X and Y specify the points at which the data Z is given. Out of range values are returned as NaNs.

XI and YI can be matrices, in which case interp2 returns the values of Z corresponding to the points (XI(i,j),YI(i,j)). Alternatively, you can pass in the row and column vectors xi and yi, respectively. In this case, interp2 interprets these vectors as if you issued the command meshgrid(xi,yi).

ZI = interp2(Z,XI,YI) assumes that X = 1:n and Y = 1:m, where [m,n] = size(Z).

ZI = interp2(Z,ntimes) expands Z by interleaving interpolates between every element, working recursively for ntimes. interp2(Z) is the same as interp2(Z,1).

ZI = interp2(X,Y,Z,XI,YI,method) specifies an alternative interpolation method:

'nearest'

Nearest neighbor interpolation

'linear'

Linear interpolation (default)

'spline'	Cubic	spline	interpola	tion

'cubic' Cubic interpolation, as long as data is

uniformly-spaced. Otherwise, this method is the


same as 'spline'.

All interpolation methods require that X and Y be monotonic, and have the same format ("plaid") as if they were produced by meshgrid. If you provide two monotonic vectors, interp2 changes them to a plaid internally. Variable spacing is handled by mapping the given values in X, Y, XI, and YI to an equally spaced domain before interpolating. For faster interpolation when X and Y are equally spaced and monotonic, use the methods '*linear', '*cubic', '*spline', or '*nearest'.

ZI = interp2(...,method, extrapval) specifies a method and a scalar value for ZI outside of the domain created by X and Y. Thus, ZI equals extrapval for any value of YI or XI that is not spanned by Y or X respectively. A method must be specified to use extrapval. The default method is 'linear'.

Remarks

The interp2 command interpolates between data points. It finds values of a two-dimensional function f(x, y) underlying the data at intermediate points.



Interpolation is the same operation as table lookup. Described in table lookup terms, the table is tab = [NaN,Y;X,Z] and interp2 looks up


the elements of XI in X, YI in Y, and, based upon their location, returns values ZI interpolated within the elements of Z.

Examples

Example 1

Interpolate the peaks function over a finer grid.

```
[X,Y] = meshgrid(-3:.25:3);
Z = peaks(X,Y);
[XI,YI] = meshgrid(-3:.125:3);
ZI = interp2(X,Y,Z,XI,YI);
mesh(X,Y,Z), hold, mesh(XI,YI,ZI+15)
hold off
axis([-3 3 -3 3 -5 20])
```



Example 2

Given this set of employee data,

```
years = 1950:10:1990;
service = 10:10:30;
```

```
wage = [150.697 199.592 187.625
179.323 195.072 250.287
203.212 179.092 322.767
226.505 153.706 426.730
249.633 120.281 598.243];
```

it is possible to interpolate to find the wage earned in 1975 by an employee with 15 years' service:

```
w = interp2(service, years, wage, 15, 1975)
w =
   190.6287
```

See Also

griddata, interp1, interp1q, interp3, interpn, meshgrid

3-D data interpolation (table lookup)

Syntax

VI = interp3(X,Y,Z,V,XI,YI,ZI)

VI = interp3(V,XI,YI,ZI)
VI = interp3(V,ntimes)
VI = interp3(...,method)

VI = interp3(...,method,extrapval)

Description

VI = interp3(X,Y,Z,V,XI,YI,ZI) interpolates to find VI, the values of the underlying three-dimensional function V at the points in arrays XI, YI and ZI. XI,YI, ZI must be arrays of the same size, or vectors. Vector arguments that are not the same size, and have mixed orientations (i.e. with both row and column vectors) are passed through meshgrid to create the Y1, Y2, Y3 arrays. Arrays X, Y, and Z specify the points at which the data V is given. Out of range values are returned as NaN.

VI = interp3(V,XI,YI,ZI) assumes X=1:N, Y=1:M, Z=1:P where [M,N,P]=size(V).

VI = interp3(V,ntimes) expands V by interleaving interpolates between every element, working recursively for ntimes iterations. The command interp3(V) is the same as interp3(V,1).

VI = interp3(...,method) specifies alternative methods:

'nearest'	Nearest neighbor interpolation
'linear'	Linear interpolation (default)
'spline'	Cubic spline interpolation
'cubic'	Cubic interpolation, as long as data is uniformly-spaced. Otherwise, this method is the same as 'spline'.

VI = interp3(...,method,extrapval) specifies a method and a value for VI outside of the domain created by X, Y and Z. Thus, VI equals extrapval for any value of XI, YI or ZI that is not spanned by X, Y, and Z, respectively. You must specify a method to use extrapval. The default method is 'linear'.

Discussion

All the interpolation methods require that X,Y and Z be monotonic and have the same format ("plaid") as if they were created using meshgrid. X, Y, and Z can be non-uniformly spaced. For faster interpolation when X, Y, and Z are equally spaced and monotonic, use the methods '*linear', '*cubic', or '*nearest'.

Examples


To generate a coarse approximation of flow and interpolate over a finer mesh:

```
[x,y,z,v] = flow(10);

[xi,yi,zi] = meshgrid(.1:.25:10, -3:.25:3, -3:.25:3);

vi = interp3(x,y,z,v,xi,yi,zi); % vi is 25-by-40-by-25

slice(xi,yi,zi,vi,[6 9.5],2,[-2 .2]), shading flat
```



See Also

interp1, interp1q, interp2, interpn, meshgrid

1-D interpolation using FFT method

Syntax

```
y = interpft(x,n)
y = interpft(x,n,dim)
```

Description

y = interpft(x,n) returns the vector y that contains the value of the periodic function x resampled to n equally spaced points.

If length(x) = m, and x has sample interval dx, then the new sample interval for y is dy = dx*m/n. Note that n cannot be smaller than m.

If X is a matrix, interpft operates on the columns of X, returning a matrix Y with the same number of columns as X, but with n rows.

y = interpft(x, n, dim) operates along the specified dimension.

Algorithm

The interpft command uses the FFT method. The original vector x is transformed to the Fourier domain using fft and then transformed back with more points.

Examples

Interpolate a triangle-like signal using an interpolation factor of 5. First, set up signal to be interpolated:

```
y = [0 .5 1 1.5 2 1.5 1 .5 0 -.5 -1 -1.5 -2 -1.5 -1 -.5 0];

N = length(y);
```

Perform the interpolation:

```
L = 5;
M = N*L;
x = 0:L:L*N-1;
xi = 0:M-1;
yi = interpft(y,M);
plot(x,y,'o',xi,yi,'*')
legend('Original data','Interpolated data')
```

See Also interp1

N-D data interpolation (table lookup)

Syntax

```
VI = interpn(X1, X2, X3, ..., V, Y1, Y2, Y3, ...)
```

VI = interpn(V, Y1, Y2, Y3, ...)

VI = interpn(V,ntimes)

VI = interpn(...,method)

VI = interpn(...,method,extrapval)

Description

VI = interpn(X1,X2,X3,...,V,Y1,Y2,Y3,...) interpolates to find VI, the values of the underlying multidimensional function V at the points in the arrays Y1, Y2, Y3, etc. For an n-dimensional array V, interpn is called with 2*N+1 arguments. Arrays X1, X2, X3, etc. specify the points at which the data V is given. Out of range values are returned as NaNs. Y1, Y2, Y3, etc. must be arrays of the same size, or vectors. Vector arguments that are not the same size, and have mixed orientations (i.e. with both row and column vectors) are passed through ndgrid to create the Y1, Y2, Y3, etc. arrays. interpn works for all n-dimensional arrays with 2 or more dimensions.

```
VI = interpn(V,Y1,Y2,Y3,...) interpolates as above, assuming X1 = 1:size(V,1), X2 = 1:size(V,2), X3 = 1:size(V,3), etc.
```

VI = interpn(V,ntimes) expands V by interleaving interpolates between each element, working recursively for ntimes iterations. interpn(V) is the same as interpn(V,1).

VI = interpn(..., method) specifies alternative methods:

'nearest' Nearest neighbor interpolation
'linear' Linear interpolation (default)
'spline' Cubic spline interpolation

'cubic' Cubic interpolation, as long as data is

uniformly-spaced. Otherwise, this method is the

same as 'spline'.

VI = interpn(...,method,extrapval) specifies a method and a value for VI outside of the domain created by X1, X2, Thus, VI equals

extrapval for any value of Y1, Y2,... that is not spanned by X1, X2,... respectively. You must specify a method to use extrapval. The default method is 'linear'.

interpn requires that X1, X2, X3, ... be monotonic and plaid (as if they were created using ndgrid). X1, X2, X3, and so on can be non-uniformly spaced.

Discussion

All the interpolation methods require that X1,X2, X3 ... be monotonic and have the same format ("plaid") as if they were created using ndgrid. X1,X2,X3,... and Y1, Y2, Y3, etc. can be non-uniformly spaced. For faster interpolation when X1, X2, X3, etc. are equally spaced and monotonic, use the methods '*linear', '*cubic', or '*nearest'.

Examples

Start by defining an anonymous function to compute $f = te^{-x^2 - y^2 - z^2}$:

```
f = @(x,y,z,t) t.*exp(-x.^2 - y.^2 - z.^2);
```

Build the lookup table by evaluating the function f on a grid constructed by ndgrid:

```
[x,y,z,t] = ndgrid(-1:0.2:1,-1:0.2:1,-1:0.2:1,0:2:10);
v = f(x,y,z,t);
```

Now construct a finer grid:

```
[xi,yi,zi,ti] = ndgrid(-1:0.05:1,-1:0.08:1,-1:0.05:1, ... 0:0.5:10);
```


Compute the spline interpolation at xi, yi, zi, and ti:

```
vi = interpn(x,y,z,t,v,xi,yi,zi,ti,'spline');
```

Plot the interpolated function, and then create a movie from the plot:

```
nframes = size(ti, 4);
for j = 1:nframes
    slice(yi(:,:,:,j), xi(:,:,:,j), zi(:,:,:,j), ...
```

```
vi(:,:,:,j),0,0,0);
caxis([0 10]);
M(j) = getframe;
end
movie(M);
```



See Also

interp1, interp2, interp3, ndgrid

Interpolate stream-line vertices from flow speed

Syntax

interpstreamspeed(X,Y,Z,U,V,W,vertices)
interpstreamspeed(U,V,W,vertices)
interpstreamspeed(X,Y,Z,speed,vertices)
interpstreamspeed(speed,vertices)
interpstreamspeed(X,Y,U,V,vertices)
interpstreamspeed(U,V,vertices)
interpstreamspeed(X,Y,speed,vertices)
interpstreamspeed(speed,vertices)
interpstreamspeed(...,sf)
vertsout = interpstreamspeed(...)

Description

interpstreamspeed(X,Y,Z,U,V,W,vertices) interpolates streamline vertices based on the magnitude of the vector data U, V, W. The arrays X, Y, Z define the coordinates for U, V, W and must be monotonic and 3-D plaid (as if produced by meshgrid).

interpstreamspeed(U,V,W,vertices) assumes X,Y, and Z are determined by the expression

```
[X Y Z] = meshgrid(1:n,1:m,1:p)
```

```
where [m \ n \ p] = size(U).
```

interpstreamspeed(X,Y,Z,speed,vertices) uses the 3-D array speed for the speed of the vector field.

interpstreamspeed(speed, vertices) assumes X, Y, and Z are determined by the expression

```
[X Y Z] = meshgrid(1:n,1:m,1:p)
```

```
where [m n p]=size(speed).
```

interpstreamspeed(X,Y,U,V,vertices) interpolates streamline vertices based on the magnitude of the vector data U, V. The arrays X, Y define the coordinates for U, V and must be monotonic and 2-D plaid (as if produced by meshgrid).

interpstreamspeed(U,V,vertices) assumes X and Y are determined by the expression

```
[X Y] = meshgrid(1:n,1:m)
```

where [M N]=size(U).

interpstreamspeed(X,Y,speed,vertices) uses the 2-D array speed for the speed of the vector field.

interpstreamspeed(speed, vertices) assumes X and Y are determined by the expression

```
[X Y] = meshgrid(1:n,1:m)
```

where [M,N] = size(speed).


interpstreamspeed(...,sf) uses sf to scale the magnitude of the vector data and therefore controls the number of interpolated vertices. For example, if sf is 3, then interpstreamspeed creates only one-third of the vertices.

vertsout = interpstreamspeed(...) returns a cell array of vertex arrays.

Examples

This example draws streamlines using the vertices returned by interpstreamspeed. Dot markers indicate the location of each vertex. This example enables you to visualize the relative speeds of the flow data. Streamlines having widely spaced vertices indicate faster flow; those with closely spaced vertices indicate slower flow.


```
load wind
[sx sy sz] = meshgrid(80,20:1:55,5);
verts = stream3(x,y,z,u,v,w,sx,sy,sz);
iverts = interpstreamspeed(x,y,z,u,v,w,verts,.2);
sl = streamline(iverts);
set(sl,'Marker','.')
axis tight; view(2); daspect([1 1 1])
```



This example plots streamlines whose vertex spacing indicates the value of the gradient along the streamline.

```
z = membrane(6,30);
[u v] = gradient(z);
[verts averts] = streamslice(u,v);
iverts = interpstreamspeed(u,v,verts,15);
sl = streamline(iverts);
set(sl,'Marker','.')
hold on; pcolor(z); shading interp
axis tight; view(2); daspect([1 1 1])
```

interpstreamspeed



See Also

stream2, stream3, streamline, streamslice, streamparticles "Volume Visualization" on page 1-111 for related functions

Find set intersection of two vectors

Syntax

```
c = intersect(A, B)
c = intersect(A, B, 'rows')
[c, ia, ib] = intersect(a, b)
```

Description

c = intersect(A, B) returns the values common to both A and B. In set theoretic terms, this is $A \cap B$. Inputs A and B can be numeric or character vectors or cell arrays of strings. The resulting vector is sorted in ascending order.

c = intersect(A, B, 'rows') when A and B are matrices with the same number of columns returns the rows common to both A and B. MATLAB ignores the rows flag for all cell arrays.

[c, ia, ib] = intersect(a, b) also returns column index vectors ia and ib such that c = a(ia) and b(ib) (or c = a(ia,:) and b(ib,:)).

Remarks

Because NaN is considered to be not equal to itself, it is never included in the result c.

Examples

See Also

ismember, issorted, setdiff, setxor, union, unique

Largest value of specified integer type

Syntax

```
v = intmax
v = intmax('classname')
```

Description

v = intmax is the largest positive value that can be represented in the MATLAB software with a 32-bit integer. Any value larger than the value returned by intmax saturates to the intmax value when cast to a 32-bit integer.

v = intmax('classname') is the largest positive value in the integer class classname. Valid values for the string classname are

'int8'	'int16'	'int32'	'int64'
'uint8'	'uint16'	'uint32'	'uint64'

intmax('int32') is the same as intmax with no arguments.

Examples

Find the maximum value for a 64-bit signed integer:

```
v = intmax('int64')
v =
  9223372036854775807
```

Convert this value to a 32-bit signed integer:

```
x = int32(v)
x =
2147483647
```

Compare the result with the default value returned by intmax:

```
isequal(x, intmax)
ans =
    1
```

See Also

intmin, realmax, realmin, int8, uint8, isa, class

Smallest value of specified integer type

Syntax

```
v = intmin
v = intmin('classname')
```

Description

v = intmin is the smallest value that can be represented in the MATLAB software with a 32-bit integer. Any value smaller than the value returned by intmin saturates to the intmin value when cast to a 32-bit integer.

v = intmin('classname') is the smallest positive value in the integer class classname. Valid values for the string classname are

'int8'	'int16'	'int32'	'int64'
'uint8'	'uint16'	'uint32'	'uint64'

intmin('int32') is the same as intmin with no arguments.

Examples

Find the minimum value for a 64-bit signed integer:

```
v = intmin('int64')
v =
   -9223372036854775808
```

Convert this value to a 32-bit signed integer:

```
x = int32(v)
x =
  2147483647
```

Compare the result with the default value returned by intmin:

```
isequal(x, intmin)
ans =
    1
```

See Also

intmax, realmin, realmax, int8, uint8, isa, class

intwarning

Purpose

Control state of integer warnings

Note Support for the intwarning function will be removed in a future release of the MATLAB software.

Syntax

```
intwarning('action')
s = intwarning('action')
intwarning(s)
sold = intwarning(sNew)
```

Description

The MATLAB software offers four types of warnings on invalid operations that involve integers. The intwarning function enables, disables, or returns information on these warnings:

- MATLAB:intConvertNaN Warning on an attempt to convert NaN (Not a Number) to an integer. The result of the operation is zero.
- MATLAB:intConvertNonIntVal Warning on an attempt to convert
 a non-integer value to an integer. The result is that the input value
 is rounded to the nearest integer for that class.
- MATLAB:intConvertOverflow Warning on overflow when attempting to convert from a numeric class to an integer class. The result is the maximum value for the target class.
- MATLAB:intMathOverflow Warning on overflow when attempting an integer arithmetic operation. The result is the maximum value for the class of the input value. MATLAB also issues this warning when NaN is computed (e.g., int8(0)/0).

intwarning('action') sets or displays the state of integer warnings in MATLAB according to the string, action. There are three possible actions, as shown here. The default state is 'off'.

Action	Description
off	Disable the display of integer warnings
on	Enable the display of integer warnings
query	Display the state of all integer warnings

s = intwarning('action') sets the state of integer warnings in MATLAB according to the string action, and then returns the previous state in a 4-by-1 structure array, s. The return structure array has two fields: identifier and state.

intwarning(s) sets the state of integer warnings in MATLAB according to the identifier and state fields in structure array s.

sold = intwarning(sNew) sets the state of integer warnings in MATLAB according to sNew, and then returns the previous state in sold.

Remarks

Caution Enabling the MATLAB:intMathOverflow warning slows down integer arithmetic. It is recommended that you enable this particular warning only when you need to diagnose unusual behavior in your code, and disable it during normal program operation. The other integer warnings listed here do not affect program performance.

Examples General Usage

Examples of the four types of integer warnings are shown here:

MATLAB:intConvertNaN

Attempt to convert NaN (Not a Number) to an unsigned integer:

```
uint8(NaN);
Warning: NaN converted to uint8(0).
```

• MATLAB:intConvertNonIntVal

Attempt to convert a floating point number to an unsigned integer:

```
uint8(2.7);
Warning: Conversion rounded non-integer floating point
  value to nearest uint8 value.
```

• MATLAB:intConvertOverflow

Attempt to convert a large unsigned integer to a signed integer, where the operation overflows:

```
int8(uint8(200));
Warning: Out of range value converted to intmin('int8')
    or intmax('int8').
```

• MATLAB:intMathOverflow

Attempt an integer arithmetic operation that overflows:

```
intmax('uint8') + 5;
Warning: Out of range value or NaN computed in
integer arithmetic.
```

Example 1

Check the initial state of integer warnings:

```
intwarning('query')
The state of warning 'MATLAB:intConvertNaN' is 'off'.
The state of warning 'MATLAB:intConvertNonIntVal' is 'off'.
The state of warning 'MATLAB:intConvertOverflow' is 'off'.
The state of warning 'MATLAB:intMathOverflow' is 'off'.
```

Convert a floating point value to an 8-bit unsigned integer. MATLAB does the conversion, but that requires rounding the resulting value. Because all integer warnings have been disabled, no warning is displayed:

```
uint8(2.7)
ans =
```

3

Store this state in structure array iwState:

```
iwState = intwarning('query');
```

Change the state of the ConvertNonIntVal warning to 'on' by first setting the state to 'on' in the iwState structure array, and then loading iwState back into the internal integer warning settings for your MATLAB session:

Verify that the state of ConvertNonIntVal has changed:

```
intwarning('query')
The state of warning 'MATLAB:intConvertNaN' is 'off'.
The state of warning 'MATLAB:intConvertNonIntVal' is 'on'.
The state of warning 'MATLAB:intConvertOverflow' is 'off'.
The state of warning 'MATLAB:intMathOverflow' is 'off'.
```

Now repeat the conversion from floating point to integer. This time MATLAB displays the warning:

```
uint8(2.7)
Warning: Conversion rounded non-integer floating point
  value to nearest uint8 value.
ans =
  3
```

See Also

warning, lastwarn

Matrix inverse

Syntax

Y = inv(X)

Description

Y = inv(X) returns the inverse of the square matrix X. A warning message is printed if X is badly scaled or nearly singular.

In practice, it is seldom necessary to form the explicit inverse of a matrix. A frequent misuse of inv arises when solving the system of linear equations Ax = b. One way to solve this is with x = inv(A)*b. A better way, from both an execution time and numerical accuracy standpoint, is to use the matrix division operator $x = A \ b$. This produces the solution using Gaussian elimination, without forming the inverse. See \ and \ for further information.

Examples

Here is an example demonstrating the difference between solving a linear system by inverting the matrix with inv(A)*b and solving it directly with A\b. A random matrix A of order 500 is constructed so that its condition number, cond(A), is 1.e10, and its norm, norm(A), is 1. The exact solution x is a random vector of length 500 and the right-hand side is b = A*x. Thus the system of linear equations is badly conditioned, but consistent.

On a 300 MHz, laptop computer the statements

```
n = 500;
Q = orth(randn(n,n));
d = logspace(0,-10,n);
A = Q*diag(d)*Q';
x = randn(n,1);
b = A*x;
tic, y = inv(A)*b; toc
err = norm(y-x)
res = norm(A*y-b)
produce
elapsed_time =
```

```
1.4320
  err =
       7.3260e-006
  res =
       4.7511e-007
while the statements
  tic, z = A \setminus b, toc
  err = norm(z-x)
  res = norm(A*z-b)
produce
  elapsed time =
       0.6410
  err =
       7.1209e-006
  res =
       4.4509e-015
```

It takes almost two and one half times as long to compute the solution with y = inv(A)*b as with z = A\b. Both produce computed solutions with about the same error, 1.e-6, reflecting the condition number of the matrix. But the size of the residuals, obtained by plugging the computed solution back into the original equations, differs by several orders of magnitude. The direct solution produces residuals on the order of the machine accuracy, even though the system is badly conditioned.

The behavior of this example is typical. Using A\b instead of inv(A)*b is two to three times as fast and produces residuals on the order of machine accuracy, relative to the magnitude of the data.

Algorithm Inputs of Type Double

For inputs of type double, inv uses the following LAPACK routines to compute the matrix inverse:

Matrix	Routine
Real	DLANGE, DGETRF, DGECON, DGETRI
Complex	ZLANGE, ZGETRF, ZGECON, ZGETRI

Inputs of Type Single

For inputs of type single, inv uses the following LAPACK routines to compute the matrix inverse:

Matrix	Routine
Real	SLANGE, SGETRF, SGECON, SGETRI
Complex	CLANGE, CGETRF, CGECON, CGETRI

See Also

det, lu, rref

The arithmetic operators \, /

References

[1] Anderson, E., Z. Bai, C. Bischof, S. Blackford, J. Demmel,

J. Dongarra, J. Du Croz, A. Greenbaum, S. Hammarling,

A. McKenney, and D. Sorensen, LAPACK User's Guide

(http://www.netlib.org/lapack/lug/lapack_lug.html), Third Edition, SIAM, Philadelphia, 1999.

Inverse of Hilbert matrix

Syntax

H = invhilb(n)

Description

H = invhilb(n) generates the exact inverse of the exact Hilbert matrix for n less than about 15. For larger n, invhilb(n) generates an approximation to the inverse Hilbert matrix.

Limitations

The exact inverse of the exact Hilbert matrix is a matrix whose elements are large integers. These integers may be represented as floating-point numbers without roundoff error as long as the order of the matrix, n, is less than 15.

Comparing invhilb(n) with inv(hilb(n)) involves the effects of two or three sets of roundoff errors:

- The errors caused by representing hilb(n)
- The errors in the matrix inversion process
- The errors, if any, in representing invhilb(n)

It turns out that the first of these, which involves representing fractions like 1/3 and 1/5 in floating-point, is the most significant.

Examples

invhilb(4) is

16	-120	240	- 140
-120	1200	-2700	1680
240	-2700	6480	-4200
-140	1680	-4200	2800

See Also

hilb

References

[1] Forsythe, G. E. and C. B. Moler, *Computer Solution of Linear Algebraic Systems*, Prentice-Hall, 1967, Chapter 19.

Invoke method on COM object or interface, or display methods

Syntax

- S = h.invoke
- S = h.invoke('methodname')
- S = h.invoke('methodname', arg1, arg2, ...)
- S = h.invoke('custominterfacename')
- S = invoke(h, ...)

Description

- S = h.invoke returns structure array S containing a list of all methods supported by the object or interface, h, along with the prototypes for these methods. If S is empty, either there are no properties or methods in the object, or the MATLAB software cannot read the object's type library. Refer to the COM vendor's documentation.
- S = h.invoke('methodname') invokes the method specified in the string methodname, and returns an output value, if any, in S. The data type of the return value depends on the invoked method, which is determined by the control or server.
- S = h.invoke('methodname', arg1, arg2, ...) invokes the method specified in the string methodname with input arguments arg1, arg2, etc.
- S = h.invoke('custominterfacename') returns an Interface object S, which is a handle to a custom interface implemented by the COM component. The h argument is a handle to the COM object. The custominterfacename argument is a string returned by the interfaces function.
- S = invoke(h, ...) is an alternate syntax. For Automation objects, if the vendor provides documentation for specific properties or methods, use the S = invoke(h, ...) syntax to call them.

If the method returns a COM interface, then invoke returns a new MATLAB COM object that represents the interface returned. For a description of how MATLAB converts COM types, see Handling COM Data in MATLAB in the External Interfaces documentation.

COM functions are available on Microsoft Windows systems only.

Examples

Invoke the Redraw method in the mwsamp control:

```
f = figure ('position', [100 200 200 200]);
h = actxcontrol ('mwsamp.mwsampctrl.1', [0 0 200 200], f);
h.Radius = 100;
h.invoke('Redraw');

Call the method directly:
h.Redraw;

Display all mwsamp methods:
h.invoke

MATLAB displays (in part):
ans =
   AboutBox = void AboutBox(handle)
Beep = void Beep(handle)
   FireClickEvent = void FireClickEvent(handle)
   .
   .
}
```

Getting a Custom Interface Example

Once you have created a COM server, you can query the server component to see if any custom interfaces are implemented. Use the interfaces function to return a list of all available custom interfaces:

```
h = actxserver('mytestenv.calculator');
customlist = h.interfaces

MATLAB displays:

customlist =
    ICalc1
```

ICalc2 ICalc3

To get a handle to the custom interface you want, use the invoke function, specifying the handle returned by actxcontrol or actxserver and also the name of the custom interface:

```
c1 = h.invoke('ICalc1')
```

MATLAB displays:

```
c1 =
   Interface.Calc_1.0_Type_Library.ICalc_Interface
```

You can now use this handle with most of the COM client functions to access the properties and methods of the object through the selected custom interface.

See Also

methods | ismethod | interfaces

How To

- "Handling COM Data in MATLAB Software"
- · "Custom Interfaces"

Inverse permute dimensions of N-D array

Syntax

A = ipermute(B,order)

Description

A = ipermute(B,order) is the inverse of permute. ipermute rearranges the dimensions of B so that permute(A,order) will produce B. B has the same values as A but the order of the subscripts needed to access any particular element are rearranged as specified by order. All the elements of order must be unique.

Remarks

permute and ipermute are a generalization of transpose (.') for multidimensional arrays.

Examples

Consider the 2-by-2-by-3 array a:

$$a(:,:,1) = a(:,:,2) = 0$$
 $0 \quad 1 \quad 0 \quad 0 \quad 2$

a = cat(3, eye(2), 2*eye(2), 3*eye(2))

Permuting and inverse permuting a in the same fashion restores the array to its original form:

```
B = permute(a,[3 2 1]);
C = ipermute(B,[3 2 1]);
isequal(a,C)
ans=
```

1

See Also

permute

Interquartile range of timeseries data

Syntax

```
ts_iqr = iqr(ts)
iqr(ts,'PropertyName1',PropertyValue1,...)
```

Description

ts_iqr = iqr(ts) returns the interquartile range of ts.Data. When ts.Data is a vector, ts_iqr is the difference between the 75th and the 25th percentiles of the ts.Data values. When ts.Data is a matrix, ts_iqr is a row vector containing the interquartile range of each column of ts.Data (when IsTimeFirst is true and the first dimension of ts is aligned with time). For the N-dimensional ts.Data array, iqr always operates along the first nonsingleton dimension of ts.Data.

iqr(ts, 'PropertyName1', PropertyValue1,...) specifies the following optional input arguments:

- 'MissingData' property has two possible values, 'remove' (default) or 'interpolate', indicating how to treat missing data during the calculation.
- 'Quality' values are specified by a vector of integers, indicating which quality codes represent missing samples (for vector data) or missing observations (for data arrays with two or more dimensions).
- 'Weighting' property has two possible values, 'none' (default) or 'time'.

When you specify 'time', larger time values correspond to larger weights.

Examples

Create a time series with a missing value, represented by NaN.

```
ts = timeseries([3.0 NaN 5 6.1 8], 1:5);
```

Calculate the interquartile range of ts.Data after removing the missing value from the calculation.

```
iqr(ts,'MissingData','remove')
```

iqr (timeseries)

ans =

3.0500

See Also timeseries

Purpose Detect state

Description These functions detect the state of MATLAB entities:

isa	Detect object of given MATLAB class or Java class
isappdata	Determine if object has specific application-defined data
iscell	Determine if input is cell array
iscellstr	Determine if input is cell array of strings
ischar	Determine if input is character array
iscom	Determine if input is Component Object Model (COM) object
isdir	Determine if input is folder
isempty	Determine if input is empty array
isequal	Determine if arrays are numerically equal
isequalwithequalnans	Determine if arrays are numerically equal, treating NaNs as equal
isevent	Determine if input is object event
isfield	Determine if input is MATLAB structure array field
isfinite	Detect finite elements of array
isfloat	Determine if input is floating-point array
isglobal	Determine if input is global variable
ishandle	Detect valid graphics object handles
ishold	Determine if graphics hold state is on
isinf	Detect infinite elements of array
isinteger	Determine if input is integer array
isinterface	Determine if input is Component Object Model (COM) interface

******	D
isjava	Determine if input is Java object
iskeyword	Determine if input is MATLAB keyword
isletter	Detect elements that are alphabetic letters
islogical	Determine if input is logical array
ismac	Determine if running MATLAB for Macintosh OS X platform
ismember	Detect members of specific set
ismethod	Determine if input is object method
isnan	Detect elements of array that are not a number (NaN)
isnumeric	Determine if input is numeric array
isobject	Determine if input is MATLAB object
ispc	Determine if running MATLAB for PC (Windows) platform
isprime	Detect prime elements of array
isprop	Determine if input is object property
isreal	Determine if all array elements are real numbers
isscalar	Determine if input is scalar
issorted	Determine if set elements are in sorted order
isspace	Detect space characters in array
issparse	Determine if input is sparse array
isstrprop	Determine if string is of specified category
isstruct	Determine if input is MATLAB structure array
isstudent	Determine if Student Version of MATLAB

isunix	Determine if running MATLAB for UNIX ⁸ platform.
isvarname	Determine if input is valid variable name
isvector	Determine if input is vector

See Also isa, exist

8. UNIX is a registered trademark of The Open Group in the United States and other countries.

Purpose Determine whether input is object of given class

Syntax K = isa(obj, 'class_name')

Description

K = isa(obj, 'class_name') returns logical 1 (true) if obj is of class
(or a subclass of) class_name, and logical 0 (false) otherwise.

The argument obj is a MATLAB object or an object of the Java programming language. The argument class_name is the name of a MATLAB (predefined or user-defined) or a Java class. Predefined MATLAB classes include

logical Logical array of true and false values

char Characters array

numeric Integer or floating-point array
integer Signed or unsigned integer array

int8 8-bit signed integer array uint8 8-bit unsigned integer array int16 16-bit signed integer array uint16 16-bit unsigned integer array int32 32-bit signed integer array uint32 32-bit unsigned integer array int64 64-bit signed integer array uint64 64-bit unsigned integer array

float Single- or double-precision floating-point array

single Single-precision floating-point array
double Double-precision floating-point array

cell Cell array

structure array

```
function_handle Function handle
'class name' MATLAB class or Java class
```

To check for a sparse array, use issparse. To check for a complex array, use ~isreal.

Examples

```
isa(rand(3,4),'double')
ans =
    1
```

The following example creates an instance of the user-defined MATLAB class named polynom. The isa function identifies the object as being of the polynom class.

```
polynom_obj = polynom([1 0 -2 -5]);
isa(polynom_obj, 'polynom')
ans =
    1
```

See Also

class, is*, exist

isappdata

Purpose True if application-defined data exists

Syntax isappdata(h,name)

Description isappdata(h, name) returns 1 if application-defined data with the

specified name exists on the object specified by handle h, and returns

0 otherwise.

Remarks Application data is data that is meaningful to or defined by your

application which you attach to a figure or any GUI component (other than ActiveX controls) through its AppData property. Only Handle

Graphics MATLAB objects use this property.

See Also getappdata, rmappdata, setappdata

See Also

cell, iscellstr, isstruct, isnumeric, islogical, isobject, isa, is*

Purpose Determine whether input is cell array of strings

Syntax tf = iscellstr(A)

Description tf = iscellstr(A) returns logical 1 (true) if A is a cell array of strings

(or an empty cell array), and logical 0 (false) otherwise. A cell array of

strings is a cell array where every element is a character array.

Examples

```
A{1,1} = 'Thomas Lee';
A{1,2} = 'Marketing';
A{2,1} = 'Allison Jones';
A{2,2} = 'Development';
iscellstr(A)
ans =
```

See Also

cellstr, iscell, isstrprop, strings, char, isstruct, isa, is*

Determine whether item is character array

Syntax

tf = ischar(A)

Description

tf = ischar(A) returns logical 1 (true) if A is a character array and logical 0 (false) otherwise.

Examples

Given the following cell array,

ischar shows that only C{1,2} is a character array.

```
for k = 1:3
x(k) = ischar(C{1,k});
end

x
x =
0  1  0
```

See Also

char, strings, isletter, isspace, isstrprop, iscellstr, isnumeric, isa, is *

Determine whether input is COM or ActiveX object

Syntax

tf = h.iscom
tf = iscom(h)

Description

tf = h.iscom returns logical 1 (true) if handle h is a COM or Microsoft ActiveX object. Otherwise, returns logical 0 (false).

tf = iscom(h) is an alternate syntax.

COM functions are available on Microsoft Windows systems only.

Examples

Test an instance of a Microsoft Excel application:

```
h = actxserver('Excel.Application');
h.iscom
```

MATLAB displays true, indicating object h is a COM object.

Test an Excel interface:

```
h = actxserver('Excel.Application');
%Create a workbooks object
w = h.get('workbooks');
w.iscom
```

MATLAB displays false, indicating object w is not a COM object.

How To

• "COM Support for MATLAB Software"

isdir

Purpose Determine whether input is folder

Syntax
tf = isdir('A')

Description tf = isdir('A') returns logical 1 (true) if A is a folder. Otherwise, it

returns logical O (false).

Examples Run:

tf=isdir('myfiles/results')

MATLAB returns

tf = 1

indicating that myfiles/results is a folder.

See Also dir, is*

"Managing Files in MATLAB"

Purpose Test if vertices are joined by edge

Syntax TF = isEdge(TR, V1, V2) TF = isEdge(TR, EDGE)

Description

TF = isEdge(TR, V1, V2) returns an array of 1/0 (true/false) flags, where each entry TF(i) is true if V1(i), V2(i) is an edge in the triangulation. V1, V2 are column vectors representing the indices of the vertices in the mesh, that is, indices into the vertex coordinate arrays.

TF = isEdge(TR, EDGE) specifies the edge start and end indices in matrix format.

Input Arguments

TR Triangulation representation.

V1, V2 Column vectors of mesh vertices.

EDGE Matrix of size n-by-2 where n is the number of query

edges.

Output Arguments

TF Array of 1/0 (true/false) flags, where each entry

TF(i) is true if V1(i), V2(i) is an edge in the

triangulation.

Examples Example 1

Load a 2-D triangulation and use TriRep to query the presence of an edge between pairs of points.

```
load trimesh2d
trep = TriRep(tri, x,y);
```

Test if vertices 3 and 117 are connected by an edge

```
isEdge(trep, 3, 117)
```

TriRep.isEdge

Test if vertices 3 and 164 are connected by an edge

```
isEdge(trep, 3, 164)
```

Example 2

Direct query of a 3-D Delaunay triangulation created using DelaunayTri.

```
X = rand(10,3)
dt = DelaunayTri(X)
```

Test if vertices 2 and 7 are connected by an edge

```
isEdge(dt, 2, 7);
```

See Also

DelaunayTri

Purpose Determine whether array is empty

Syntax TF = isempty(A)

Description TF = isempty (A) returns logical 1 (true) if A is an empty array and

logical 0 (false) otherwise. An empty array has at least one dimension

of size zero, for example, 0-by-0 or 0-by-5.

Examples B = rand(2,2,2);

B(:,:,:) = [];

isempty(B)

ans = 1

See Also is*

isempty (timeseries)

Purpose Determine whether timeseries object is empty

Syntax isempty(ts)

Description isempty(ts) returns a logical value for timeseries object ts, as

follows:

• 1 — When ts contains no data samples or ts.Data is empty.

• 0 — When ts contains data samples

See Also length (timeseries), size (timeseries), timeseries, tsprops

isempty (tscollection)

Purpose Determine whether tscollection object is empty

Syntax isempty(tsc)

Description isempty(tsc) returns a logical value for tscollection object tsc,

as follows:

 $\bullet\,$ 1 — When tsc contains neither timeseries members nor a time

vector

• 0 — When tsc contains either timeseries members or a time vector

See Also length (tscollection), size (tscollection), timeseries,

tscollection

isequal

Purpose

Test arrays for equality

Syntax

tf = isequal(A, B, ...)

Description

tf = isequal(A, B, ...) returns logical 1 (true) if the input arrays have the same contents, and logical 0 (false) otherwise. Nonempty arrays must be of the same data type and size.

Remarks

When comparing structures, the order in which the fields of the structures were created is not important. As long as the structures contain the same fields, with corresponding fields set to equal values, isequal considers the structures to be equal. See Example 2, below.

When comparing numeric values, isequal does not consider the data type used to store the values in determining whether they are equal. See Example 3, below. This is also true when comparing numeric values with certain nonnumeric values, such as logical true and 1, or the character A and its numeric equivalent, 65.

NaNs (Not a Number), by definition, are not equal. Therefore, arrays that contain NaN elements are not equal, and isequal returns zero when comparing such arrays. See Example 4, below. Use the isequalwithequalnans function when you want to test for equality with NaNs treated as equal.

isequal recursively compares the contents of cell arrays and structures. If all the elements of a cell array or structure are numerically equal, isequal returns logical 1.

Examples

Example 1

Given

isequal(A,B,C) returns 0, and isequal(A,B) returns 1.

Example 2

When comparing structures with isequal, the order in which the fields of the structures were created is not important:

```
A.f1 = 25; A.f2 = 50

A =

   f1: 25

   f2: 50

B.f2 = 50; B.f1 = 25

B =

   f2: 50

   f1: 25

isequal(A, B)

ans =

   1
```

Example 3

When comparing numeric values, the data types used to store the values are not important:

```
A = [25 50]; B = [int8(25) int8(50)];
isequal(A, B)
ans =
    1
```

Example 4

Arrays that contain NaN (Not a Number) elements cannot be equal, since NaNs, by definition, are not equal:

```
A = [32 8 -29 NaN 0 5.7];
B = A;
isequal(A, B)
ans =
```

isequal

0

See Also

isequalwithequalnans, strcmp, isa, is*, relational operators

isequal (MException)

Purpose Compare MException objects for equality

Syntax TF = isequal(e0bj1, e0bj2)

Description TF = isequal(e0bj1, e0bj2) tests MException objects e0bj1 and

eObj2 for equality, returning logical 1 (true) if the two objects are

identical, otherwise returning logical 0 (false).

See Also try, catch, error, assert, MException, eq(MException),

ne(MException), getReport(MException), disp(MException),

throw(MException), rethrow(MException),

throwAsCaller(MException), addCause(MException),

last(MException),

isequalwithequalnans

Purpose

Test arrays for equality, treating NaNs as equal

Syntax

tf = isequalwithequalnans(A, B, ...)

Description

tf = isequalwithequalnans(A, B, ...) returns logical 1 (true) if the input arrays are the same type and size and hold the same contents, and logical 0 (false) otherwise. NaN (Not a Number) values are considered to be equal to each other. Numeric data types and structure field order do not have to match.

Remarks

isequalwithequalnans is the same as isequal, except isequalwithequalnans considers NaN (Not a Number) values to be equal, and isequal does not.

isequalwithequalnans recursively compares the contents of cell arrays and structures. If all the elements of a cell array or structure are numerically equal, isequalwithequalnans returns logical 1.

Examples

Arrays containing NaNs are handled differently by isequal and isequalwithequalnans. isequal does not consider NaNs to be equal, while isequalwithequalnans does.

```
A = [32 8 -29 NaN 0 5.7];
B = A;
isequal(A, B)
ans =
     0
isequalwithequalnans(A, B)
ans =
     1
```

The position of NaN elements in the array does matter. If they are not in the same position in the arrays being compared, then isequalwithequalnans returns zero.

```
A = [2 \ 4 \ 6 \ NaN \ 8]; B = [2 \ 4 \ NaN \ 6 \ 8];
```

isequalwithequalnans

```
isequalwithequalnans(A, B)
ans =
    0
```

See Also

is equal, strcmp, isa, is \star , relational operators

Determine whether input is COM object event

Syntax

```
tf = h.isevent('eventname')
tf = isevent(h, 'eventname')
```

Description

tf = h.isevent('eventname') returns logical 1 (true) if event_name is an event recognized by COM object h. Otherwise, returns logical 0 (false). The event_name argument is not case sensitive.

```
tf = isevent(h, 'eventname') is an alternate syntax.
```

COM functions are available on Microsoft Windows systems only.

Examples

Test events in a MATLAB sample control object:

1 Create an instance of the mwsamp control and test DblClick:

```
f = figure ('position', [100 200 200 200]);
h = actxcontrol ('mwsamp.mwsampctrl.2', [0 0 200 200], f);
h.isevent('DblClick')
```

MATLAB displays true, indicating DblClick is an event.

2 Try the same test onRedraw:

```
h.isevent('Redraw')
```

MATLAB displays false, indicating Redraw is not an event; it is a method.

Test events in a Microsoft Excel workbook object:

1 Create a Workbook object wb:

```
myApp = actxserver('Excel.Application');
wbs = myApp.Workbooks;
wb = wbs.Add;
```

2 Test Activate:

```
wb.isevent('Activate')
```

MATLAB displays true, indicating Activate is an event.

3 Test Save:

```
wb.isevent('Save')
```

MATLAB displays false, indicating Save is not an event; it is a method.

See Also

events (COM) | eventlisteners | registerevent

How To

- "Exploring Events"
- "Functions for Working with Events"

Determine whether input is structure array field

Syntax

```
tf = isfield(S, 'fieldname')
tf = isfield(S, C)
```

Description

tf = isfield(S, 'fieldname') examines structure S to see if it includes the field specified by the quoted string 'fieldname'. Output tf is set to logical 1 (true) if S contains the field, or logical 0 (false) if not. If S is not a structure array, isfield returns false.

tf = isfield(S, C) examines structure S for multiple fieldnames as specified in cell array of strings C, and returns an array of logical values to indicate which of these fields are part of the structure. Elements of output array tf are set to a logical 1 (true) if the corresponding element of C holds a fieldname that belongs to structure S. Otherwise, logical 0 (false) is returned in that element. In other words, if structure S contains the field specified in $C\{m,n\}$, isfield returns a logical 1 (true) in tf(m,n).

Note isfield returns false if the field or fieldnames input is empty.

Examples

Example 1 - Single Fieldname Syntax

Given the following MATLAB structure,

```
patient.name = 'John Doe';
patient.billing = 127.00;
patient.test = [79 75 73; 180 178 177.5; 220 210 205];
```

isfield identifies billing as a field of that structure.

```
isfield(patient, 'billing')
ans =
    1
```

Example 2 - Multiple Fieldname Syntax

Check structure S for any of four possible fieldnames. Only the first is found, so the first element of the return value is set to true:

See Also

fieldnames, setfield, getfield, orderfields, rmfield, struct, isstruct, iscell, isa, is*, dynamic field names

isfinite

Purpose

Array elements that are finite

Syntax

TF = isfinite(A)

Description

TF = isfinite(A) returns an array the same size as A containing logical 1 (true) where the elements of the array A are finite and logical 0 (false) where they are infinite or NaN. For a complex number z, isfinite(z) returns 1 if both the real and imaginary parts of z are finite, and 0 if either the real or the imaginary part is infinite or NaN.

For any real A, exactly one of the three quantities isfinite(A), isinf(A), and isnan(A) is equal to one.

Examples

See Also

isinf, isnan, is*

isfloat

Purpose Determine whether input is floating-point array

Syntax isfloat(A)

Description isfloat(A) returns a logical 1 (true) if A is a floating-point array and a

logical 0 (false) otherwise. The only floating-point data types in the

MATLAB programming language are single and double.

See Also isa, isinteger, double, single, isnumeric

Determine whether input is global variable

Note Support for the isglobal function will be removed in a future release of the MATLAB software. See Remarks below.

Syntax

tf = isglobal(A)

Description

tf = isglobal(A) returns logical 1 (true) if A has been declared to be a global variable in the context from which isglobal is called, and logical 0 (false) otherwise.

Remarks

isglobal is most commonly used in conjunction with conditional global declaration. An alternate approach is to use a pair of variables, one local and one declared global.

Instead of using

```
if condition
   global x
end

x = some_value

if isglobal(x)
   do_something
end
```

You can use

```
global gx
if condition
    gx = some_value
else
    x = some_value
end
```

ishandle

Purpose Determine whether input is valid Handle Graphics handle

Syntax ishandle(H)

Description ishandle(H) returns an array whose elements are 1 where the

elements of H are valid graphics or Sun Java object handles, and 0

where they are not.

You should use the isa function to determine the class and validity

of MATLAB objects.

See Also findobj, gca, gcf, gco, isa set

"Accessing Object Handles" for more information.

Purpose True for Handle Graphics object handles

Syntax ishghandle(h)

Description ishghandle(h) returns an array that contains 1's where the elements

of h are handles to existing graphic objects and 0's where they are not. Differs from ishandle in that Simulink objects handles return false.

Examples Create a plot and find the valid handles:

```
x = [1:10];
y = [1:10];
p=plot(x,y);
ishghandle([x y p])
% This returns a 1-by-21 array of values with ones at the first,
% eleventh, and last values, if the figure handle is 1.
```

See Also isa | ishandle | findobj | gca | gcf | set

How To • "Accessing Object Handles"

ishold

Purpose Current hold state

Syntax ishold

Description ishold returns 1 if hold is on, and 0 if it is off. When hold is on,

the current plot and most axis properties are held so that subsequent

graphing commands add to the existing graph.

A state of hold on implies that both figure and axes NextPlot

properties are set to add.

See Also hold, newplot

"Controlling Graphics Output" for related information

"Axes Operations" on page 1-106 for related functions

Array elements that are infinite

Syntax

TF = isinf(A)

Description

TF = isinf(A) returns an array the same size as A containing logical 1 (true) where the elements of A are +Inf or -Inf and logical 0 (false) where they are not. For a complex number z, isinf(z) returns 1 if either the real or imaginary part of z is infinite, and 0 if both the real and imaginary parts are finite or NaN.

0

For any real A, exactly one of the three quantities isfinite(A), isinf(A), and isnan(A) is equal to one.

Examples

$$a = [-2 -1 \ 0 \ 1 \ 2]$$

isinf(1./a)

Warning: Divide by zero.

0

0

Warning: Divide by zero.

See Also

isfinite, isnan, is*

isinteger

Purpose

Determine whether input is integer array

Syntax

Description

isinteger(A) returns a logical 1 (true) if the array A has integer data type and a logical 0 (false) otherwise. The integer data types in the MATLAB language are

- int8
- uint8
- int16
- uint16
- int32
- uint32
- int64
- uint64

See Also

isa, isnumeric, isfloat

Purpose Determine whether input is COM interface

Syntax tf = h.isinterface tf = isinterface(h)

Description tf = h.isinterface returns logical 1 (true) if handle h is a COM

interface. Otherwise, returns logical 0 (false).

tf = isinterface(h) is an alternate syntax.

COM functions are available on Microsoft Windows systems only.

Examples Test an instance of a Microsoft Excel application:

h = actxserver('Excel.Application');
h.isinterface

MATLAB displays false, indicating object h is not an interface.

Test a workbooks object:

w = h.get('workbooks'); w.isinterface

MATLAB displays true, indicating object w is an interface.

See Also iscom | interfaces

How To • "Exploring Interfaces"

isjava

Purpose

Determine whether input is Sun Java object

Syntax

tf = isjava(A)

Description

tf = isjava(A) returns logical 1 (true) if A is a Java object, and logical 0 (false) otherwise.

Examples

Create an instance of the Java Date class and isjava indicates that it is a Java object.

```
myDate = java.util.Date;
isjava(myDate)
```

The MATLAB software displays:

```
ans =
```

1

Note that isobject, which tests for MATLAB objects, returns logical 0 (false). Type:

```
isobject(myDate)
```

MATLAB displays:

```
ans =
```

0

See Also

isobject, javaArray, javaMethod, javaObject, isa, is*

Check if containers. Map contains key

Syntax

```
tf = isKey(M, keys)
```

Description

tf = isKey(M, keys) looks for the specified keys in the Map instance M, and returns logical 1 (true) for those elements that it finds, and logical 0 (false) for those it does not. keys is a scalar key or cell array of keys. If keys is nonscalar, then return value tf is a nonscalar logical array that has the same dimensions and size as keys.

Read more about Map Containers in the MATLAB Programming Fundamentals documentation.

Examples

Construct a Map object where the keys are states in the United States and the value associated with each key is that state's capital city:

```
US_Capitals = containers.Map( ...
{'Arizona', 'Nebraska', 'Nevada', 'New York', ...
'Georgia', 'Alaska', 'Vermont', 'Oregon'}, ...
{'Phoenix', 'Lincoln', 'Carson City', 'Albany', ...
'Atlanta', 'Juneau', 'Montpelier', 'Salem'})
```

Check three states to see if they are in the map:

```
isKey(US_Capitals, {'Georgia', 'Alaska', 'Wyoming'})
ans =
    1    1    0
```

Check two states and a capital to see if they are all keys in the map:

```
isKey(US_Capitals, {'Georgia'; 'Montpelier'; 'Alaska'})
ans =
    1    0    1
```

Identify the capital city of a specific state, but only attempt this if you know that this state is in the map:

```
S = 'Nebraska';
```

```
if isKey(US_Capitals, S)
sprintf(' The capital of %s is %s', S, US_Capitals(S))
else error('The state of %s is not in the map', S)
end
ans =
  The capital of Nebraska is Lincoln
S = Montana';
if isKey(US_Capitals, S)
sprintf(' The capital of %s is %s', S, US_Capitals(S))
else error('The state of %s is not in the map', S)
end
??? The state of Montana is not in the map
```

containers.Map, keys(Map), values(Map), size(Map), length(Map), remove(Map), handle

```
Purpose
                   Determine whether input is MATLAB keyword
Syntax
                   tf = iskeyword('str')
                   iskeyword str
                   iskeyword
Description
                   tf = iskeyword('str') returns logical 1 (true) if the string str is a
                   keyword in the MATLAB language and logical 0 (false) otherwise.
                   iskeyword str uses the MATLAB command format.
                  iskeyword returns a list of all MATLAB keywords.
Examples
                  To test if the word while is a MATLAB keyword,
                     iskeyword while
                     ans =
                          1
                  To obtain a list of all MATLAB keywords,
                     iskeyword
                          'break'
                          'case'
                          'catch'
                          'classdef'
                          'continue'
                          'else'
                          'elseif'
                          'end'
                          'for'
                          'function'
                          'global'
                          'if'
                          'otherwise'
                          'parfor'
                          'persistent'
```

'return'

iskeyword

```
'spmd'
'switch'
'try'
'while'
```

See Also

isvarname, genvarname, is*

Array elements that are alphabetic letters

Syntax

tf = isletter('str')

Description

tf = isletter('str') returns an array the same size as str containing logical 1 (true) where the elements of str are letters of the alphabet and logical 0 (false) where they are not.

Examples

Find the letters in character array s.

```
s = 'A1,B2,C3';
isletter(s)
ans =
    1     0     0     1     0     0     1     0
```

See Also

ischar, isspace, isstrprop, iscellstr, isnumeric, char, strings, isa, is *

islogical

Purpose

Determine whether input is logical array

Syntax

```
tf = islogical(A)
```

Description

tf = islogical(A) returns logical 1 (true) if A is a logical array and logical 0 (false) otherwise.

Examples

Given the following cell array,

is logical shows that only $C\{1,3\}$ is a logical array.

```
for k = 1:4
x(k) = islogical(C{1,k});
end

x
x =
    0    0    1    0
```

See Also

logical, isnumeric, ischar, isreal, logical operators (elementwise
and short-circuit), isa, is*

ismac

Purpose Determine if version is for Mac OS X platform

Syntax tf = ismac

Description tf = ismac returns logical 1 (true) if the version of MATLAB software

is for the Apple Mac OS X platform, and returns logical O (false)

otherwise.

See Also isunix, ispc, computer, isstudent, is*

Array elements that are members of set

Syntax

```
tf = ismember(A, S)
tf = ismember(A, S, 'rows')
[tf, loc] = ismember(A, S, ...)
```

Description

tf = ismember(A, S) returns an array the same size as A, containing logical 1 (true) where the elements of A are in the set S, and logical 0 (false) elsewhere. In set theory terms, k is 1 where A ϵ S. Inputs A and S can be numeric or character arrays or cell arrays of strings.

tf = ismember(A, S, 'rows'), when A and S are matrices with the same number of columns, returns a vector containing 1 where the rows of A are also rows of S and O otherwise. You cannot use this syntax if A or S is a cell array of strings.

[tf, loc] = ismember(A, S, ...) returns an array loc containing the highest index in S for each element in A that is a member of S. For those elements of A that do not occur in S. ismember returns 0.

Remarks

Because NaN is considered to be not equal to anything, it is never a member of any set.

Examples

```
set = [0 2 4 6 8 10 12 14 16 18 20];
a = (1:5)'
a =

    1
    2
    3
    4
    5

ismember(a, set)
ans =
    0
    1
    0
```

```
1
0
set = [5 2 4 2 8 10 12 2 16 18 20 3];
[tf, index] = ismember(a, set);
index
index =
0
8
12
3
1
```

See Also

issorted, intersect, setdiff, setxor, union, unique, is*

Purpose Determine

Determine whether input is COM object method

Syntax

```
tf = h.ismethod('methodname')
tf = ismethod(h, 'methodname')
```

Description

tf = h.ismethod('methodname') returns logical 1 (true) if the specified methodname is a method you can call on COM object h.

Otherwise, returns logical 0 (false).

tf = ismethod(h, 'methodname') is an alternate syntax.

COM functions are available on Microsoft Windows systems only.

Examples

Test members of an instance of a Microsoft Excel application:

```
h = actxserver ('Excel.Application');
ismethod(h, 'SaveWorkspace')
```

MATLAB displays true, SaveWorkspace is a method.

Try the same test on UsableWidth:

```
ismethod(h, 'UsableWidth')
```

MATLAB displays false, UsableWidth is not a method; it is a property.

See Also

methods | methodsview | isprop | isevent | isobject | class

How To

· "Exploring Methods"

Array elements that are NaN

Syntax

TF = isnan(A)

Description

TF = isnan(A) returns an array the same size as A containing logical 1 (true) where the elements of A are NaNs and logical 0 (false) where they are not. For a complex number z, isnan(z) returns 1 if either the real or imaginary part of z is NaN, and 0 if both the real and imaginary parts are finite or Inf.

0

For any real A, exactly one of the three quantities isfinite(A), isinf(A), and isnan(A) is equal to one.

Examples

$$a = [-2 -1 \ 0 \ 1 \ 2]$$

isnan(1./a)

Warning: Divide by zero.

0 0 0 0

isnan(0./a)

0

Warning: Divide by zero.

0 1 0

See Also

isfinite, isinf, is*

0

Determine whether input is numeric array

Syntax

tf = isnumeric(A)

Description

tf = isnumeric(A) returns logical 1 (true) if A is a numeric array and logical 0 (false) otherwise. For example, sparse arrays and double-precision arrays are numeric, while strings, cell arrays, and structure arrays and logicals are not.

Examples

Given the following cell array,

isnumeric shows that all but $C\{1,2\}$ and $C\{1,4\}$ are numeric arrays.

```
for k = 1:5
x(k) = isnumeric(C{1,k});
end

x
x =
    1    0    1    0    1
```

See Also

isstrprop, isnan, isreal, isprime, isfinite, isinf, isa, is*

Purpose Is input MATLAB object

Syntax tf = isobject(A)

Description tf = isobject(A) returns true if A is an object of a MATLAB class.

Otherwise, it returns false. Handle Graphics objects return false.

Use ishghandle to test for Handle Graphics objects.

Examples

Define the following MATLAB class:

Determine which objects are instances of MATLAB classes. For example:

Use is java to test for Sun Java objects in MATLAB, where it returns false for MATLAB objects:

isobject

isjava(h) ans = 0

See Also

class | isa | is*

Tutorials

• "Class Definition—Syntax Reference"

Compute isosurface end-cap geometry

Syntax

```
fvc = isocaps(X,Y,Z,V,isovalue)
fvc = isocaps(V,isovalue)
fvc = isocaps(..., 'enclose')
fvc = isocaps(..., 'whichplane')
[f,v,c] = isocaps(...)
isocaps(...)
```

Description

fvc = isocaps(X,Y,Z,V,isovalue) computes isosurface end-cap geometry for the volume data V at isosurface value isovalue. The arrays X, Y, and Z define the coordinates for the volume V.

The struct fvc contains the face, vertex, and color data for the end-caps and can be passed directly to the patch command.

fvc = isocaps(V,isovalue) assumes the arrays X, Y, and Z are defined as [X,Y,Z] = meshgrid(1:n,1:m,1:p) where [m,n,p] = size(V).

fvc = isocaps(..., 'enclose') specifies whether the end-caps enclose data values above or below the value specified in isovalue. The string enclose can be either above (default) or below.

fvc = isocaps(..., 'whichplane') specifies on which planes to draw the end-caps. Possible values for whichplane are all (default), xmin, xmax, ymin, ymax, zmin, or zmax.

[f,v,c] = isocaps(...) returns the face, vertex, and color data for the end-caps in three arrays instead of the struct fvc.

isocaps(...) without output arguments draws a patch with the computed faces, vertices, and colors.


Examples

This example uses a data set that is a collection of MRI slices of a human skull. It illustrates the use of isocaps to draw the end-caps on this cutaway volume.

The red isosurface shows the outline of the volume (skull) and the end-caps show what is inside of the volume.

The patch created from the end-cap data (p2) uses interpolated face coloring, which means the gray colormap and the light sources determine how it is colored. The isosurface patch (p1) used a flat red face color, which is affected by the lights, but does not use the colormap.

```
load mri
D = squeeze(D);
D(:,1:60,:) = [];
p1 = patch(isosurface(D, 5), 'FaceColor', 'red',...
    'EdgeColor', 'none');
p2 = patch(isocaps(D, 5), 'FaceColor', 'interp',...
    'EdgeColor', 'none');
view(3); axis tight; daspect([1,1,.4])
colormap(gray(100))
camlight left; camlight; lighting gouraud
isonormals(D,p1)
```



See Also

 $isosurface, isonormals, smooth 3, subvolume, reduce volume, \\ reduce patch$

"Isocaps Add Context to Visualizations" for more illustrations of isocaps

"Volume Visualization" on page 1-111 for related functions

Calculate isosurface and patch colors

Syntax

```
nc = isocolors(X,Y,Z,C,vertices)
nc = isocolors(X,Y,Z,R,G,B,vertices)
nc = isocolors(C,vertices)
nc = isocolors(R,G,B,vertices)
nc = isocolors(...,PatchHandle)
isocolors(...,PatchHandle)
```

Description

nc = isocolors(X,Y,Z,C,vertices) computes the colors of isosurface (patch object) vertices (vertices) using color values C. Arrays X, Y, Z define the coordinates for the color data in C and must be monotonic vectors or 3-D plaid arrays (as if produced by meshgrid). The colors are returned in nc. C must be 3-D (index colors).

nc = isocolors(X,Y,Z,R,G,B,vertices) uses R, G, B as the red, green, and blue color arrays (true color).

nc = isocolors(C,vertices), and nc =
isocolors(R,G,B,vertices) assume X, Y, and Z are determined by
the expression

```
[X Y Z] = meshgrid(1:n,1:m,1:p)
```

```
where [m \ n \ p] = size(C).
```

nc = isocolors(...,PatchHandle) uses the vertices from the patch
identified by PatchHandle.


isocolors(...,PatchHandle) sets the FaceVertexCData property of the patch specified by PatchHandle to the computed colors.

Examples Indexed Color Data

This example displays an isosurface and colors it with random data using indexed color. (See "Interpolating in Indexed Color Versus Truecolor" for information on how patch objects interpret color data.)

```
[x \ y \ z] = meshgrid(1:20,1:20,1:20);
```

```
data = sqrt(x.^2 + y.^2 + z.^2);
cdata = smooth3(rand(size(data)), 'box',7);
p = patch(isosurface(x,y,z,data,10));
isonormals(x,y,z,data,p);
isocolors(x,y,z,cdata,p);
set(p,'FaceColor','interp','EdgeColor','none')
view(150,30); daspect([1 1 1]);axis tight
camlight; lighting phong;
```




True Color Data

This example displays an isosurface and colors it with true color (RGB) data.

```
[x y z] = meshgrid(1:20,1:20,1:20);
data = sqrt(x.^2 + y.^2 + z.^2);
p = patch(isosurface(x,y,z,data,20));
isonormals(x,y,z,data,p);
[r g b] = meshgrid(20:-1:1,1:20,1:20);
```

```
isocolors(x,y,z,r/20,g/20,b/20,p);
set(p,'FaceColor','interp','EdgeColor','none')
view(150,30); daspect([1 1 1]);
camlight; lighting phong;
```




Modified True Color Data

This example uses isocolors to calculate the true color data using the isosurface's (patch object's) vertices, but then returns the color data in a variable (c) in order to modify the values. It then explicitly sets the isosurface's FaceVertexCData to the new data (1-c).

```
[x y z] = meshgrid(1:20,1:20,1:20);
data = sqrt(x.^2 + y.^2 + z.^2);
p = patch(isosurface(data,20));
isonormals(data,p);
[r g b] = meshgrid(20:-1:1,1:20,1:20);
c = isocolors(r/20,g/20,b/20,p);
set(p,'FaceVertexCData',1-c)
```

```
set(p, 'FaceColor', 'interp', 'EdgeColor', 'none')
view(150,30); daspect([1 1 1]);
camlight; lighting phong;
```



See Also

isosurface, isocaps, smooth3, subvolume, reducevolume, reducepatch, isonormals

"Volume Visualization" on page 1-111 for related functions

Compute normals of isosurface vertices

Syntax

```
n = isonormals(X,Y,Z,V,vertices)
n = isonormals(V,vertices)
n = isonormals(V,p) and n = isonormals(X,Y,Z,V,p)
n = isonormals(...,'negate')
isonormals(V,p) and isonormals(X,Y,Z,V,p)
```

Description

n = isonormals(X,Y,Z,V,vertices) computes the normals of the isosurface vertices from the vertex list, vertices, using the gradient of the data V. The arrays X, Y, and Z define the coordinates for the volume V. The computed normals are returned in n.

n = isonormals(V, vertices) assumes the arrays X, Y, and Z are defined as [X,Y,Z] = meshgrid(1:n,1:m,1:p) where [m,n,p] = size(V).

n = isonormals(V,p) and n = isonormals(X,Y,Z,V,p) compute normals from the vertices of the patch identified by the handle p.

n = isonormals(..., 'negate') negates (reverses the direction of) the normals.

isonormals(V,p) and isonormals(X,Y,Z,V,p) set the VertexNormals property of the patch identified by the handle p to the computed normals rather than returning the values.

Examples

This example compares the effect of different surface normals on the visual appearance of lit isosurfaces. In one case, the triangles used to draw the isosurface define the normals. In the other, the isonormals function uses the volume data to calculate the vertex normals based on the gradient of the data points. The latter approach generally produces a smoother-appearing isosurface.

Define a 3-D array of volume data (cat, interp3):

```
data = cat(3, [0 .2 0; 0 .3 0; 0 0 0], ...
[.1 .2 0; 0 1 0; .2 .7 0],...
[0 .4 .2; .2 .4 0; .1 .1 0]);
```

```
data = interp3(data,3,'cubic');
```

Draw an isosurface from the volume data and add lights. This isosurface uses triangle normals (patch, isosurface, view, daspect, axis, camlight, lighting, title):


```
subplot(1,2,1)
p1 = patch(isosurface(data,.5),...
'FaceColor','red','EdgeColor','none');
view(3); daspect([1,1,1]); axis tight
camlight; camlight(-80,-10); lighting phong;
title('Triangle Normals')
```

Draw the same lit isosurface using normals calculated from the volume data:

```
subplot(1,2,2)
p2 = patch(isosurface(data,.5),...
    'FaceColor','red','EdgeColor','none');
isonormals(data,p2)
view(3); daspect([1 1 1]); axis tight
camlight; camlight(-80,-10); lighting phong;
title('Data Normals')
```

These isosurfaces illustrate the difference between triangle and data normals:

isonormals



See Also

 $\verb|interp3|, \verb|isosurface|, \verb|isocaps|, \verb|smooth3|, \verb|subvolume|, \verb|reducevolume|, \\ \verb|reducepatch| \\$

"Volume Visualization" on page 1-111 for related functions

Extract isosurface data from volume data

Syntax

```
fv = isosurface(X,Y,Z,V,isovalue)
fv = isosurface(V,isovalue)
fvc = isosurface(...,colors)
fv = isosurface(...,'noshare')
fv = isosurface(...,'verbose')
[f,v] = isosurface(...)
[f,v,c] = isosurface(...)
isosurface(...)
```

Description

fv = isosurface(X,Y,Z,V,isovalue) computes isosurface data from the volume data V at the isosurface value specified in isovalue. That is, the isosurface connects points that have the specified value much the way contour lines connect points of equal elevation.

The arrays X, Y, and Z define the coordinates for the volume V. The structure fv contains the faces and vertices of the isosurface, which you can pass directly to the patch command.

fv = isosurface(V,isovalue) assumes the arrays X, Y, and Z are defined as [X,Y,Z] = meshgrid(1:n,1:m,1:p) where [m,n,p] = size(V).

fvc = isosurface(...,colors) interpolates the array colors
onto the scalar field and returns the interpolated values in the
facevertexcdata field of the fvc structure. The size of the colors
array must be the same as V. The colors argument enables you to
control the color mapping of the isosurface with data different from that
used to calculate the isosurface (e.g., temperature data superimposed
on a wind current isosurface).

fv = isosurface(..., 'noshare') does not create shared vertices.
This is faster, but produces a larger set of vertices.

fv = isosurface(..., 'verbose') prints progress messages to the command window as the computation progresses.

[f,v] = isosurface(...) or [f,v,c] = isosurface(...) returns the faces and vertices (and faceVertexcCData) in separate arrays instead of a struct.

isosurface(...) with no output arguments, creates a patch in the current axes with the computed faces and vertices. If no current axes exists, a new axes is created with a 3-D view and appropriate lighting.

Special Case Behavior — isosurface Called with No Output Arguments

If there is no current axes and you call isosurface with without assigning output arguments, MATLAB creates a new axes, sets it to a 3-D view, and adds lighting to the isosurface graph.

Remarks

You can pass the fv structure created by isosurface directly to the patch command, but you cannot pass the individual faces and vertices arrays (f, v) to patch without specifying property names. For example,

```
patch(isosurface(X,Y,Z,V,isovalue))
or
[f,v] = isosurface(X,Y,Z,V,isovalue);
patch('Faces',f,'Vertices',v)
```


Examples Example 1

This example uses the flow data set, which represents the speed profile of a submerged jet within an infinite tank (type help flow for more information). The isosurface is drawn at the data value of -3. The statements that follow the patch command prepare the isosurface for lighting by

- Recalculating the isosurface normals based on the volume data (isonormals)
- Setting the face and edge color (set, FaceColor, EdgeColor)
- Specifying the view (daspect, view)

• Adding lights (camlight, lighting)

```
[x,y,z,v] = flow;
p = patch(isosurface(x,y,z,v,-3));
isonormals(x,y,z,v,p)
set(p,'FaceColor','red','EdgeColor','none');
daspect([1 1 1])
view(3); axis tight
camlight
lighting gouraud
```




Example 2

Visualize the same flow data as above, but color-code the surface to indicate magnitude along the X-axis. Use a sixth argument to isosurface, which provides a means to overlay another data set by coloring the resulting isosurface. The colors variable is a vector containing a scalar value for each vertex in the isosurface, to be portrayed with the current color map. In this case, it is one of the

variables that define the surface, but it could be entirely independent. You can apply a different color scheme by changing the current figure color map.

```
[x,y,z,v] = flow;
[faces,verts,colors] = isosurface(x,y,z,v,-3,x);
patch('Vertices', verts, 'Faces', faces, ...
    'FaceVertexCData', colors, ...
    'FaceColor', 'interp', ...
    'edgecolor', 'interp');
view(30,-15);
axis vis3d;
colormap copper
```



See Also

isonormals, shrinkfaces, smooth3, subvolume

"Connecting Equal Values with Isosurfaces" for more examples

"Volume Visualization" on page 1-111 for related functions

ispc

Purpose Determine if version is for Windows (PC) platform

Syntax tf = ispc

Description tf = ispc returns logical 1 (true) if the version of MATLAB software

is for the Microsoft Windows platform, and returns logical O (false)

otherwise.

See Also isunix, ismac, computer, isstudent, is*

mmreader.isPlatformSupported

Purpose Determine whether mmreader is available on current platform

Note isPlatformSupported will be removed in a future release.

Syntax supported = mmreader.isPlatformSupported()

Description supported = mmreader.isPlatformSupported() returns true if

mmreader can read at least one file format on the current platform. Otherwise, it returns false. For a list of supported file formats, and the requirements to read these formats on each platform, see mmreader.

Tips Because mmreader can read Motion JPEG 2000 files on all platforms

that MATLAB supports, mmreader.isPlatformSupported always

returns true.

See Also getFileFormats | mmreader

Purpose Test for existence of preference **Syntax** ispref('group','pref') ispref('group') ispref('group',{'pref1','pref2',...'prefn'}) **Description** ispref('group', 'pref') returns 1 if the preference specified by group and pref exists, and 0 otherwise. ispref('group') returns 1 if the GROUP exists, and 0 otherwise. ispref('group', {'pref1', 'pref2', ...'prefn'}) returns a logical array the same length as the cell array of preference names, containing 1 where each preference exists, and 0 elsewhere. **Examples** addpref('mytoolbox','version','1.0') ispref('mytoolbox','version') ans = 1.0

addpref, getpref, rmpref, setpref, uigetpref, uisetpref

See Also

Array elements that are prime numbers

Syntax

TF = isprime(A)

Description

TF = isprime(A) returns an array the same size as A containing logical 1 (true) for the elements of A which are prime, and logical 0 (false) otherwise. A must contain only positive integers.

Examples

$$c = [2 \ 3 \ 0 \ 6 \ 10]$$

c =

2 3 0 6 10

isprime(c)

ans =

1 1 0 0 0

See Also

is*

Purpose Determine whether input is COM object property

f = h.isprop('propertyname')
tf = isprop(h, 'propertyname')

Description tf = h.isprop('propertyname') returns logical 1 (true) if the

specified name is a property of COM object h. Otherwise, returns logical

0 (false).

tf = isprop(h, 'propertyname') is an alternate syntax.

Examples Test a property of an instance of a Microsoft Excel application:

h = actxserver ('Excel.Application');
isprop(h, 'UsableWidth')

MATLAB displays true, UsableWidth is a property.

Try the same test on SaveWorkspace:

isprop(h, 'SaveWorkspace')

MATLAB displays false. SaveWorkspace is not a property; it is a method.

See Also

inspect | ismethod | isevent |

How To

• "Exploring Properties"

Check if input is real array

Syntax

TF = isreal(A)

Description

TF = isreal(A) returns logical 1 (true) if A does not have an imaginary part. It returns logical 0 (false) otherwise. If A has a stored imaginary part of value 0, isreal(A) returns logical 0 (false).

Note For logical and char data classes, isreal always returns true. For numeric data types, if A does not have an imaginary part isreal returns true; if A does have an imaginary part isreal returns false. For cell, struct, function_handle, and object data types, isreal always returns false.

~isreal(x) returns true for arrays that have at least one element with an imaginary component. The value of that component can be 0.

Remarks

If A is real, complex(A) returns a complex number whose imaginary component is 0, and isreal(complex(A)) returns false. In contrast, the addition A + 0i returns the real value A, and isreal(A + 0i) returns true.

If B is real and A = complex(B), then A is a complex matrix and isreal(A) returns false, while A(m:n) returns a real matrix and isreal(A(m:n)) returns true.

Because MATLAB software supports complex arithmetic, certain of its functions can introduce significant imaginary components during the course of calculations that appear to be limited to real numbers. Thus, you should use isreal with discretion.

Examples Example 1

If a computation results in a zero-value imaginary component, isreal returns true.

```
x=3+4i;
y=5-4i;
isreal(x+y)
ans =
```

Example 2

These examples use isreal to detect the presence or absence of imaginary numbers in an array. Let

```
x = magic(3);
y = complex(x);
```

isreal(x) returns true because no element of x has an imaginary component.

```
isreal(x)
ans =
    1
```

isreal(y) returns false, because every element of x has an imaginary component, even though the value of the imaginary components is 0.

```
isreal(y)
ans =
    0
```

This expression detects strictly real arrays, i.e., elements with 0-valued imaginary components are treated as real.

```
~any(imag(y(:)))
ans =
1
```

Example 3

Given the following cell array,

```
% double
  C{1} = pi;
                          % char array
  C{2} = 'John Doe';
  C{3} = 2 + 4i;
                          % complex double
                           % logical
  C{4} = ispc;
                            % double array
  C{5} = magic(3);
  C\{6\} = complex(5,0)
                            % complex double
  C =
    [3.1416] 'John Doe' [2.0000+ 4.0000i] [1] [3x3 double] [5]
isreal shows that all but C{1,3} and C{1,6} are real arrays.
  for k = 1:6
  x(k) = isreal(C\{k\});
  end
  Х
  x =
       1
            1 0 1 1 0
```

See Also

complex, isnumeric, isnan, isprime, isfinite, isinf, isa, is*

Determine whether input is scalar

Syntax

TF = isscalar(A)

Description

TF = isscalar(A) returns logical 1 (true) if A is a 1-by-1 matrix, and logical 0 (false) otherwise.

The A argument can be a structure or cell array. It also be a MATLAB object, as described in *Object-Oriented Programming*, as long as that object overloads the size function.

Examples

Test matrix A and one element of the matrix:

```
A = rand(5);
isscalar(A)
ans =
     0
isscalar(A(3,2))
ans =
     1
```

See Also

isvector, isempty, isnumeric, islogical, ischar, isa, is*

Determine whether set elements are in sorted order

Syntax

```
TF = issorted(A)
TF = issorted(A, 'rows')
```

Description

TF = issorted(A) returns logical 1 (true) if the elements of A are in sorted order, and logical 0 (false) otherwise. Input A can be a vector or an N-by-1 or 1-by-N cell array of strings. A is considered to be sorted if A and the output of sort(A) are equal.

TF = issorted(A, 'rows') returns logical 1 (true) if the rows of two-dimensional matrix A are in sorted order, and logical 0 (false) otherwise. Matrix A is considered to be sorted if A and the output of sortrows(A) are equal.

Note Only the issorted(A) syntax supports A as a cell array of strings.

Remarks

For character arrays, issorted uses ASCII, rather than alphabetical, order.

You cannot use issorted on arrays of greater than two dimensions.

Examples

Example 1 - Using issorted on a vector

```
A = [5 12 33 39 78 90 95 107 128 131];
issorted(A)
ans =
```

Example 2 — Using issorted on a matrix

```
A = magic(5)
A =
17 24 1 8 15
23 5 7 14 16
```

```
4
         6
              13
                    20
                          22
   10
         12
              19
                    21
                          3
   11
         18
              25
                     2
                           9
issorted(A, 'rows')
ans =
    0
B = sortrows(A)
B =
          6
                    20
                          22
    4
              13
   10
         12
              19
                    21
                          3
   11
         18
              25
                    2
                         9
   17
         24
               1
                    8
                         15
              7 14
   23
         5
                       16
issorted(B)
ans =
    1
```

Example 3 — Using issorted on a cell array

issorted

See Also

sort, sortrows, ismember, unique, intersect, union, setdiff, setxor, is $\mbox{\ensuremath{^{\star}}}$

isspace

Purpose

Array elements that are space characters

Syntax

```
tf = isspace('str')
```

Description

tf = isspace('str') returns an array the same size as 'str' containing logical 1 (true) where the elements of str are Unicode-represented whitespace characters, and logical 0 (false) where they are not.

Whitespace characters for which isspace returns true include tab, line feed, vertical tab, form feed, carriage return, and space, in addition to a number of other Unicode characters. To see all characters for which isspace returns true, enter the following command, and then look up the returned decimal codes in a Unicode reference:

```
find(isspace(char(1):char(intmax('uint16'))))
```

Examples

```
isspace(' Find spa ces ')
Columns 1 through 13
    1    1    0    0    0    1    0    0    0    1    0    0
Columns 14 through 15
    0    1
```

See Also

isletter, isstrprop, ischar, strings, isa, is*

issparse

Purpose Determine whether input is sparse

Syntax TF = issparse(S)

Description TF = issparse(S) returns logical 1 (true) if the storage class of S is

sparse and logical 0 (false) otherwise.

See Also is*, sparse, full

isstr

Purpose Determine whether input is character array

Note isstr will be removed in a future version. Use ischar instead.

See Also ischar, isa, is*

Determine whether string is of specified category

Syntax

tf = isstrprop('str', 'category')

Description

tf = isstrprop('str', 'category') returns a logical array the same size as str containing logical 1 (true) where the elements of str belong to the specified category, and logical 0 (false) where they do not.

The str input can be a character array, cell array, or any MATLAB numeric type. If str is a cell array, then the return value is a cell array of the same shape as str.

The *category* input can be any of the strings shown in the left column below:

Category	Description	
alpha	True for those elements of str that are alphabetic	
alphanum	True for those elements of str that are alphanumeric	
cntrl	True for those elements of str that are control characters (for example, char(0:20))	
digit	True for those elements of str that are numeric digits	
graphic	True for those elements of str that are graphic characters. These are all values that represent any characters except for the following: unassigned, space, line separator, paragraph separator, control characters, Unicode format control characters, private user-defined characters, Unicode surrogate characters, Unicode other characters	
lower	True for those elements of str that are lowercase letters	
print	True for those elements of str that are graphic characters, plus char(32)	

Category	Description
punct	True for those elements of str that are punctuation characters
wspace	True for those elements of str that are white-space characters. This range includes the ANSI® C definition of white space, {'','\t','\n','\r','\v','\f'}, in addition to a number of other Unicode characters.
upper	True for those elements of str that are uppercase letters
xdigit	True for those elements of str that are valid hexadecimal digits

Remarks

Numbers of type double are converted to int32 according to MATLAB rules of double-to-integer conversion. Numbers of type int64 and uint64 bigger than int32(inf) saturate to int32(inf).

MATLAB classifies the elements of the str input according to the Unicode definition of the specified category. If the numeric value of an element in the input array falls within the range that defines a Unicode character category, then this element is classified as being of that category. The set of Unicode character codes includes the set of ASCII character codes, but also covers a large number of languages beyond the scope of the ASCII set. The classification of characters is dependent on the global location of the platform on which MATLAB is installed.

Whitespace characters for which the wspace option returns true include tab, line feed, vertical tab, form feed, carriage return, and space, in addition to a number of other Unicode characters. To see all characters for which isspace returns true, enter the following command, and then look up the returned decimal codes in a Unicode reference:

```
find(isstrprop(char(1):char(intmax('uint16')), 'wspace'))
```

Examples

Test for alphabetic characters in a string:

```
A = isstrprop('abc123def', 'alpha')
```

```
A =
     1 1 1 0 0 0 1 1 1
Test for numeric digits in a string:
  A = isstrprop('abc123def', 'digit')
  A =
     0 0 0 1 1 1 0 0 0
Test for hexadecimal digits in a string:
  A = isstrprop('abcd1234efgh', 'xdigit')
  A =
     1 1 1 1 1 1 1 1 1 0 0
Test for numeric digits in a character array:
  A = isstrprop(char([97 98 99 49 50 51 101 102 103]), ...
                 'digit')
  A =
     000111000
Test for alphabetic characters in a two-dimensional cell array:
  A = isstrprop({'abc123def';'456ghi789'}, 'alpha')
  A =
     [1x9 logical]
     [1x9 logical]
  A{:,:}
  ans =
     1 1 1 0 0 0 1 1 1
     000111000
Test for white-space characters in a string:
  A = isstrprop(sprintf('a bc\n'), 'wspace')
     0 1 0 0 1
```

isstrprop

See Also

strings, ischar, isletter, isspace, iscellstr, isnumeric, isa, is*

Purpose Determine whether input is structure array

Syntax tf = isstruct(A)

Description tf = isstruct(A) returns logical 1 (true) if A is a MATLAB structure

and logical O (false) otherwise.

Examples

```
patient.name = 'John Doe';
patient.billing = 127.00;
patient.test = [79 75 73; 180 178 177.5; 220 210 205];
isstruct(patient)
ans =
    1
```

See Also

struct, isfield, iscell, ischar, isobject, isnumeric, islogical, isa, is*, dynamic field names

isstudent

Purpose Determine if version is Student Version

Syntax tf = isstudent

Description tf = isstudent returns logical 1 (true) if the version of MATLAB

software is the Student Version, and returns logical O (false) for

commercial versions.

See Also ver, version, license, ispc, isunix, is*

Purpose Determine if tiled image

Syntax bool = tiffobj.isTiled()

Description bool = tiffobj.isTiled() returns true if the image has a tiled

organization and false if the image has a stripped organization.

Open a Tiff object and check if the image in the TIFF file has a tiled or stipped organization. Replace myfile.tif with the name of a TIFF file on your MATLAB path.

```
t = Tiff('myfile.tif', 'r');
tf = t.isTiled();
```

References

Examples

This method corresponds to the TIFFISTILED function in the LibTIFF C API. To use this method, you must be familiar with LibTIFF version 3.7.1, as well as the TIFF specification and technical notes. View this documentation at LibTIFF - TIFF Library and Utilities.

Tutorials

- "Exporting Image Data and Metadata to TIFF Files"
- "Reading Image Data and Metadata from TIFF Files"

isunix

Purpose Determine if version is for UNIX platform

Syntax tf = isunix

Description tf = isunix returns logical 1 (true) if the version of MATLAB software

is for the UNIX⁹ platform, and returns logical 0 (false) otherwise.

See Also ispc, ismac, computer, isstudent, is*

9. UNIX is a registered trademark of The Open Group in the United States and other countries

isvalid (handle)

Purpose Is object valid handle class object

Syntax H1 = isvalid(Hobj)

Description H1 = isvalid(Hobj) returns a logical array (or scalar if Hobj is scalar)

in which each element is true if the corresponding element in Hobj is a valid handle. This method is Sealed, so you cannot override it in a

handle subclass.

Note This method does not work with Handle Graphics objects. To determine the validity of a Handle Graphics object handle, use the ishandle function.

See Also delete (handle), handle

isvalid (serial)

Purpose

Determine whether serial port objects are valid

Syntax

```
out = isvalid(obj)
```

Description

out = isvalid(obj) returns the logical array out, which contains a 0 where the elements of the serial port object, obj are invalid serial port objects and a 1 where the elements of obj are valid serial port objects.

Remarks

obj becomes invalid after it is removed from memory with the delete function. Because you cannot connect an invalid serial port object to the device, you should remove it from the workspace with the clear command.

Example

Suppose you create the following two serial port objects.

```
s1 = serial('COM1');
s2 = serial('COM1');
```

s2 becomes invalid after it is deleted.

```
delete(s2)
```

isvalid verifies that s1 is valid and s2 is invalid.

```
sarray = [s1 s2];
isvalid(sarray)
ans =
    1 0
```

See Also

Functions

clear, delete

Determine whether timer object is valid

Syntax

```
out = isvalid(obj)
```

Description

out = isvalid(obj) returns a logical array, out, that contains a 0 where the elements of obj are invalid timer objects and a 1 where the elements of obj are valid timer objects.

An invalid timer object is an object that has been deleted and cannot be reused. Use the clear command to remove an invalid timer object from the workspace.

Examples

Create a valid timer object.

```
t = timer;
out = isvalid(t)
out =
```

Delete the timer object, making it invalid.

```
delete(t)
out1 = isvalid(t)
out1 =
    0
```

See Also

timer, delete(timer)

Determine whether input is valid variable name

Syntax

```
tf = isvarname('str')
isvarname str
```

Description

tf = isvarname('str') returns logical 1 (true) if the string str is a valid MATLAB variable name and logical 0 (false) otherwise. A valid variable name is a character string of letters, digits, and underscores, totaling not more than namelengthmax characters and beginning with a letter.

MATLAB keywords are not valid variable names. Type the command iskeyword with no input arguments to see a list of MATLAB keywords.

isvarname str uses the MATLAB command format.

Examples

This variable name is valid:

```
isvarname foo
ans =
1
```

This one is not because it starts with a number:

```
isvarname 8th_column
ans =
   0
```

If you are building strings from various pieces, place the construction in parentheses.

```
d = date;
isvarname(['Monday_', d(1:2)])
ans =
   1
```

See Also

genvarname, isglobal, iskeyword, namelengthmax, is*

Determine whether input is vector

Syntax

TF = isvector(A)

Description

TF = isvector(A) returns logical 1 (true) if A is a 1-by-N or N-by-1 vector where N >= 0, and logical 0 (false) otherwise.

The A argument can also be a MATLAB object, as described in *Object-Oriented Programming*, as long as that object overloads the size function.

Examples

Test matrix A and its row and column vectors:

See Also

isscalar, isempty, isnumeric, islogical, ischar, isa, is*

Imaginary unit

Syntax

j x+yj x+j*y

Description

Use the character j in place of the character i, if desired, as the imaginary unit.

As the basic imaginary unit sqrt(-1), j is used to enter complex numbers. Since j is a function, it can be overridden and used as a variable. This permits you to use j as an index in for loops, etc.

It is possible to use the character j without a multiplication sign as a suffix in forming a numerical constant.

Examples

Z = 2+3jZ = x+j*y

Z = r*exp(j*theta)

See Also

conj, i, imag, real

Add entries to dynamic Sun Java class path

Syntax

```
javaaddpath('dpath')
javaaddpath('dpath', '-end')
```

Description

javaaddpath('dpath') adds one or more folders or JAR files to the beginning of the current dynamic Java class path. dpath is a string or cell array of strings containing the folder or JAR file. (See the Remarks section for a description of static and dynamic Java paths.)

javaaddpath('dpath', '-end') adds one or more folders or files to the end of the current dynamic Java path.

Remarks

The Java path consists of two segments: a static path (read only at startup) and a dynamic path. The MATLAB software always searches the static path (defined in classpath.txt) before the dynamic path. Java classes on the static path should not have dependencies on classes on the dynamic path. Use javaclasspath to see the current static and dynamic Java paths.

MATLAB calls the clear java command whenever you change the dynamic path.

Path Type	Description
Static	Loaded at the start of each MATLAB session from the file classpath.txt. The static Java path offers better Java class loading performance than the dynamic Java path. However, to modify the static Java path you need to edit the file classpath.txt and restart MATLAB.
Dynamic	Loaded at any time during a MATLAB session using the javaclasspath function. You can define the dynamic path (using javaclasspath), modify the path (using javaaddpath and javarmpath), and refresh the Java class definitions for all classes on the dynamic path (using clear java) without restarting MATLAB.

Examples

Create function to set initial dynamic Java class path:

```
function setdynpath
javaclasspath({
    'C:\Work\Java\ClassFiles', ...
    'C:\Work\JavaTest\curvefit.jar', ...
    'C:\Work\JavaTest\timer.jar', ...
    'C:\Work\JavaTest\patch.jar'});
% end of file
```

Call this function to set up your dynamic class path. Then, use the javaclasspath function with no arguments to display all current static and dynamic paths:

At some later time, add the following two entries to the dynamic path. (Calling javaaddpath clears all variables from the workspace). One entry specifies a folder and the other a Java Archive (JAR) file. When

you add a folder to the path, MATLAB includes all files in that folder as part of the path:

```
javaaddpath({
    'C:\Work\Java\Curvefit\Test', ...
    'C:\Work\Java\mywidgets.jar'});
```

Use javaclasspath with just an output argument to return the dynamic path alone:

```
p = javaclasspath
p =
    'C:\Work\Java\ClassFiles'
    'C:\Work\JavaTest\curvefit.jar'
    'C:\Work\JavaTest\timer.jar'
    'C:\Work\JavaTest\patch.jar'
    'C:\Work\Java\Curvefit\Test'
    'C:\Work\Java\mywidgets.jar'
```

Create an instance of the mywidgets class that is defined on the dynamic path:

```
h = mywidgets.calendar;
```

If you modify one or more classes that are defined on the dynamic path, you need to clear the former definition for those classes from MATLAB memory. You can clear all dynamic Java class definitions from memory using:

```
clear java
```

If you then create a new instance of one of these classes, MATLAB uses the latest definition of the class to create the object.

Use javarmpath to remove a file or folder from the current dynamic class path:

```
javarmpath('C:\Work\Java\mywidgets.jar');
```

Other Examples

Add a JAR file from an internet URL to your dynamic Java path:

```
javaaddpath http://www.example.com/my.jar
```

Add the current folder with the following statement:

javaaddpath(pwd)

See Also

javaclasspath, javarmpath, clear

See "Bringing Java Classes and Methods into MATLAB Workspace" for more information.

Construct Sun Java array

Syntax

javaArray('package_name.class_name',x1,...,xn)

Description

javaArray('package_name.class_name',x1,...,xn) constructs an empty Java array capable of storing objects of Java class, 'class_name'. The dimensions of the array are x1 by ... by xn. You must include the package name when specifying the class.

The array that you create with javaArray is equivalent to the array that you would create with the Java code

```
A = new class_name[x1]...[xn];
```

Examples

The following example constructs and populates a 4-by-5 array of java.lang.Double objects.

```
dblArray = javaArray ('java.lang.Double', 4, 5);
for m = 1:4
   for n = 1:5
   dblArray(m,n) = java.lang.Double((m*10) + n);
end
dblArray
dblArray =
java.lang.Double[][]:
    [11]
             [12]
                     [13]
                              [14]
                                       [15]
    [21]
            [22]
                     [23]
                                      [25]
                              [24]
    [31]
             [32]
                     [33]
                              [34]
                                       [35]
    [41]
             [42]
                     [43]
                              [44]
                                       [45]
```

See Also

javaObject, javaMethod, class, methodsview, isjava

javachk

Purpose Generate error message based on Sun Java feature support

Syntax javachk(feature)

javachk(feature, component)

Description

javachk(feature) returns a generic error message if the specified Java feature is not available in the current MATLAB session. If it is available, javachk returns an empty matrix.

The following table shows the valid feature arguments.

Feature	Description
'awt'	Java GUI components in the Abstract Window Toolkit components are available.
'desktop'	The MATLAB interactive desktop is running.
'jvm'	The Java Virtual Machine software(JVM™) is running.
'swing'	Swing components (Java lightweight GUI components in the Java Foundation Classes) are available.

javachk(feature, component) works the same as the above syntax, except that the specified component is also named in the error message.

See Also usejava

Get and set Sun Java class path

Syntax

```
javaclasspath
javaclasspath('-dynamic')
javaclasspath('-static')
dpath = javaclasspath
spath = javaclasspath('-static')
jpath = javaclasspath('-all')
javaclasspath(dpath)
javaclasspath(dpath1, dpath2)
javaclasspath(statusmsg)
```

Description

javaclasspath displays the static and dynamic segments of the Java path. (See the Remarks section, below, for a description of static and dynamic Java paths.)

javaclasspath('-dynamic') displays the dynamic Java path.

javaclasspath('-static') displays the static Java path.

dpath = javaclasspath returns the dynamic segment of the Java path in cell array, dpath. If no dynamic paths are defined, javaclasspath returns an empty cell array.

spath = javaclasspath('-static') returns the static segment of the Java path in cell array, spath. No path information is displayed unless you specify an output variable. If no static paths are defined, javaclasspath returns an empty cell array.

jpath = javaclasspath('-all') returns the entire Java path in cell array, jpath. The returned cell array contains first the static segment of the path, and then the dynamic segment. No path information is displayed unless you specify an output variable. If no dynamic paths are defined, javaclasspath returns an empty cell array.

javaclasspath(dpath) changes the dynamic Java path to dpath, where dpath can be a string or cell array of strings representing path entries. Relative paths are converted to absolute paths. Uses the clear java command to refresh the classes defined on the dynamic Java path.

javaclasspath

javaclasspath(dpath1, dpath2) changes the dynamic Java path to the concatenation of the two paths dpath1 and dpath2, where dpath1 and dpath2 can be a string or cell array of strings representing path entries. Relative paths are converted to absolute paths. Uses the clear java command to refresh the classes defined on the dynamic Java path.

javaclasspath(statusmsg) enables or disables the display of status messages from the javaclasspath, javaaddpath, and javarmpath functions. Values for the statusmsg argument are shown in the following table:

statusmsg	Description
'-v1'	Display status messages while loading the Java path from the file system.
' - v0 '	Do not display status messages. This is the default.

Remarks

The Java path consists of two segments: a static path (read only at startup) and a dynamic path. The MATLAB software always searches the static path (defined in classpath.txt) before the dynamic path. Java classes on the static path should not have dependencies on classes on the dynamic path. Use javaclasspath to see the current static and dynamic Java paths.

MATLAB calls the clear java command whenever you change the dynamic path.

Path Type	Description
Static	Loaded at the start of each MATLAB session from the file classpath.txt. The static Java path offers better Java class loading performance than the dynamic Java path. However, to modify the static Java path you need to edit the file classpath.txt and restart MATLAB.
Dynamic	Loaded at any time during a MATLAB session using the javaclasspath function. You can define the dynamic path (using javaclasspath), modify the path (using javaaddpath and javarmpath), and refresh the Java class definitions for all classes on the dynamic path (using clear java) without restarting MATLAB.

Examples

Create a function to set your initial dynamic Java class path:

```
function setdynpath
javaclasspath({
    'C:\Work\Java\ClassFiles', ...
    'C:\Work\JavaTest\curvefit.jar', ...
    'C:\Work\JavaTest\timer.jar', ...
    'C:\Work\JavaTest\patch.jar'});
    end of file
```

Call this function to set up your dynamic class path. Then, use the javaclasspath function with no arguments to display all current static and dynamic paths:

```
setdynpath;

javaclasspath

STATIC JAVA PATH

D:\Sys0\Java\util.jar
D:\Sys0\Java\widgets.jar
D:\Sys0\Java\beans.jar
```

:

DYNAMIC JAVA PATH

```
C:\Work\Java\ClassFiles
C:\Work\JavaTest\curvefit.jar
C:\Work\JavaTest\timer.jar
C:\Work\JavaTest\patch.jar
```

At some later time, add the following two entries to the dynamic path. One entry specifies a folder and the other a Java Archive (JAR) file. When you add a folder to the path, the MATLAB software includes all files in that folder as part of the path:

```
javaaddpath({
    'C:\Work\Java\Curvefit\Test', ...
    'C:\Work\Java\mywidgets.jar'});
```

Use javaclasspath with just an output argument to return the dynamic path alone:

```
p = javaclasspath
p =
    'C:\Work\Java\ClassFiles'
    'C:\Work\JavaTest\curvefit.jar'
    'C:\Work\JavaTest\timer.jar'
    'C:\Work\JavaTest\patch.jar'
    'C:\Work\Java\Curvefit\Test'
    'C:\Work\Java\mywidgets.jar'
```

Create an instance of the mywidgets class that is defined on the dynamic path:

```
h = mywidgets.calendar;
```

If, at some time, you modify one or more classes that are defined on the dynamic path, you will need to clear the former definition for those classes from MATLAB memory. You can clear all dynamic Java class definitions from memory using:

```
clear java
```

If you then create a new instance of one of these classes, MATLAB uses the latest definition of the class to create the object.

Use javarmpath to remove a file or folder from the current dynamic class path:

```
javarmpath('C:\Work\Java\mywidgets.jar');
```

See Also

javaaddpath, javarmpath, clear

Invoke Sun Java method

Syntax

```
javaMethod(MethodName, ClassName, x1, ..., xn)
javaMethod(MethodName, JavaObj, x1, ..., xn)
```

Description

javaMethod(MethodName, ClassName, x1, ..., xn) calls the static method MethodName in the class ClassName with the signature matching the arguments x1, ..., xn. MethodName and ClassName are strings.

javaMethod(MethodName, JavaObj, x1, ..., xn) calls the nonstatic method MethodName on the Java object array JavaObj.

Remarks

Use the javaMethod function to:

- Use methods having names longer than 31 characters.
- Specify the method you want to invoke at run-time, for example, as input from an application user.

The javaMethod function enables you to use methods having names longer than 31 characters. This is the only way you can invoke such a method in the MATLAB software. For example:

```
javaMethod('DataDefinitionAndDataManipulationTransactions', T);
```

With javaMethod, you can also specify the method to be invoked at run-time. In this situation, your code calls javaMethod with a string variable in place of the method name argument. When you use javaMethod to invoke a static method, you can also use a string variable in place of the class name argument.

Note Typically, you do not need to use javaMethod. Use the default MATLAB syntax for invoking a Java methods instead. Use javaMethod for the cases described above.

Examples

To invoke the static Java method $\verb"isNaN"$ on class $\verb"java.lang.Double"$ type:

```
javaMethod('isNaN','java.lang.Double',2.2)
```

The following example invokes the nonstatic method setMonth, where myDate is a java.util.Date object.

```
myDate = java.util.Date;
javaMethod('setMonth', myDate, 3);
```

See Also

javaArray, javaObject, import, methods, isjava, javaMethodEDT

Purpose Invoke Sun Java method from Event Dispatch Thread (EDT)

Syntax javaMethodEDT(MethodName, ClassName, x1, ..., xn) javaMethodEDT(MethodName, JavaObj, x1, ..., xn)

Description javaMethodEDT(MethodName, ClassName, x1, ..., xn) invokes the

Java method MethodName in the class ClassName with the signature matching the arguments x1, \dots , xn from the Event Dispatch Thread

(EDT). MethodName and ClassName are strings.

javaMethodEDT(MethodName, JavaObj, x1, ..., xn) invokes the nonstatic method MethodName on the Java object array JavaObj.

Examples

Invoke the static method setDefaultLookAndFeelDecorated in class javax.swing.JFrame from the EDT:

```
javaMethodEDT('setDefaultLookAndFeelDecorated', 'javax.swing.JFrame',
```

Create a vector v on the MATLAB thread and invoke the add method from the EDT.

```
v = java.util.Vector;
javaMethodEDT('add',v,'string');
```

See Also

javaMethod, javaObject, javaObjectEDT, import, methods, isjava

Invoke Sun Java constructor, letting MATLAB choose the thread

Syntax

```
javaObject(ClassName, x1, ..., xn)
```

Description

javaObject(ClassName, x1, ..., xn) calls the Java constructor for class ClassName with the argument list that matches x1, ..., xn, to return a new object. ClassName is a string.

If there is no constructor that matches the class name and argument list passed to javaObject, an error occurs.

Remarks

Use the javaObject function to:

- Use classes having names with more than 31 consecutive characters.
- Specify the class for an object at run-time, for example, as input from an application user.

The default MATLAB constructor syntax requires that no segment of the input class name be longer than 31 characters. (A name segment, is any portion of the class name before, between, or after a period. For example, there are three segments in class, java.lang.String.) Any class name segment that exceeds 31 characters is truncated by MATLAB. In the rare case where you need to use a class name of this length, you must use javaObject to instantiate the class.

The java0bject function also allows you to specify the Java class for the object being constructed at run-time. In this situation, you call java0bject with a string variable in place of the class name argument.

```
class = 'java.lang.String';
text = 'hello';
strObj = javaObject(class, text);
```

In the usual case, when the class to instantiate is known at development time, it is more convenient to use the MATLAB constructor syntax. For example, to create a java.lang.String object, type:

```
strObj = java.lang.String('hello');
```

Note Typically, you do not need to use <code>javaObject</code>. Use the default MATLAB syntax for instantiating a Java class instead. Use <code>javaObject</code> for the cases described above.

Examples

The following example constructs and returns a Java object of class java.lang.String:

```
strObj = javaObject('java.lang.String','hello')
```

See Also

javaArray, javaMethod, import, methods, fieldnames, isjava, javaObjectEDT

Invoke Sun Java object constructor on Event Dispatch Thread (EDT)

Syntax

javaObjectEDT(ClassName, x1, ..., xn)

Description

javaObjectEDT(ClassName, x1, ..., xn) invokes the Java constructor for class ClassName with the signature matching the arguments x1, ..., xn from the Event Dispatch Thread (EDT). If no parameters are specified, the no-argument constructor is called. The resulting Java object is returned as a Java object array. Subsequent methods invoked on the returned object are dispatched from the EDT.

Static methods on the specified class or Java object run on the MATLAB thread unless invoked using the javaMethodEDT function.

Examples

Construct and return a javax.swing.JFrame object array from the EDT.

```
f = javaObjectEDT('javax.swing.JFrame', 'New Title')
```

Create a JOption pane on the EDT and call the createDialog method.

```
% Create a JOption pane on the EDT
optPane = javaObjectEDT('javax.swing.JOptionPane');
% Call the createDialog method - automatically done on the EDT
dlg = optPane.createDialog([],'Sample Dialog');
% Tell MATLAB to dispatch methods on dlg from the EDT
javaObjectEDT(dlg);
```

See Also

javaMethod, javaMethodEDT, javaObject, import, methods, isjava

javarmpath

Purpose

Remove entries from dynamic Sun Java class path

Syntax

```
javarmpath('dpath')
javarmpath dpath1 dpath2 ... dpathN
javarmpath(v1, v2, ..., vN)
```

Description

javarmpath('dpath') removes a folder or file from the current dynamic Java path. dpath is a string containing the folder or file specification. (See the Remarks section, below, for a description of static and dynamic Java paths.)

javarmpath dpath1 dpath2 ... dpathN removes folders and files specified by dpath1, dpath2, ..., dpathN from the dynamic Java path. Each input argument is a string containing a folder or file specification.

javarmpath(v1, v2, ..., vN) removes folders and files specified by v1, v2, ..., vN from the dynamic Java path. Each input argument is a variable to which a folder or file specification is assigned.

Remarks

The Java path consists of two segments: a static path (read only at startup) and a dynamic path. The MATLAB software always searches the static path (defined in classpath.txt) before the dynamic path. Java classes on the static path should not have dependencies on classes on the dynamic path. Use javaclasspath to see the current static and dynamic Java paths.

MATLAB calls the clear java command whenever you change the dynamic path.

Path Type	Description
Static	Loaded at the start of each MATLAB session from the file classpath.txt. The static Java path offers better Java class loading performance than the dynamic Java path. However, to modify the static Java path you need to edit the file classpath.txt and restart MATLAB.
Dynamic	Loaded at any time during a MATLAB session using the javaclasspath function. You can define the dynamic path (using javaclasspath), modify the path (using javaaddpath and javarmpath), and refresh the Java class definitions for all classes on the dynamic path (using clear java) without restarting MATLAB.

Examples

Create a function to set your initial dynamic Java class path:

```
function setdynpath
javaclasspath({
    'C:\Work\Java\ClassFiles', ...
    'C:\Work\JavaTest\curvefit.jar', ...
    'C:\Work\JavaTest\timer.jar', ...
    'C:\Work\JavaTest\patch.jar'});
% end of file
```

Call this function to set up your dynamic class path. Then, use the javaclasspath function with no arguments to display all current static and dynamic paths:

```
setdynpath;

javaclasspath

STATIC JAVA PATH

D:\Sys0\Java\util.jar
D:\Sys0\Java\widgets.jar
D:\Sys0\Java\beans.jar
```

:

DYNAMIC JAVA PATH

```
C:\Work\Java\ClassFiles
C:\Work\JavaTest\curvefit.jar
C:\Work\JavaTest\timer.jar
C:\Work\JavaTest\patch.jar
```

At some later time, add the following two entries to the dynamic path. One entry specifies a folder and the other a Java Archive (JAR) file. When you add a folder to the path, MATLAB includes all files in that folder as part of the path:

```
javaaddpath({
    'C:\Work\Java\Curvefit\Test', ...
    'C:\Work\Java\mywidgets.jar'});
```

Use javaclasspath with just an output argument to return the dynamic path alone:

```
p = javaclasspath
p =
    'C:\Work\Java\ClassFiles'
    'C:\Work\JavaTest\curvefit.jar'
    'C:\Work\JavaTest\timer.jar'
    'C:\Work\JavaTest\patch.jar'
    'C:\Work\Java\Curvefit\Test'
    'C:\Work\Java\mywidgets.jar'
```

Create an instance of the mywidgets class that is defined on the dynamic path:

```
h = mywidgets.calendar;
```

If, at some time, you modify one or more classes that are defined on the dynamic path, you will need to clear the former definition for those classes from MATLAB memory. You can clear all dynamic Java class definitions from memory using:

```
clear java
```

If you then create a new instance of one of these classes, MATLAB uses the latest definition of the class to create the object.

Use javarmpath to remove a file or folder from the current dynamic class path:

```
javarmpath('C:\Work\Java\mywidgets.jar');
```

See Also

javaclasspath, javaaddpath, clear

keyboard

Purpose Input from keyboard

Syntax keyboard

Description keyboard, when placed in a program .m file, stops execution of the file

and gives control to the keyboard. The special status is indicated by a K appearing before the prompt. You can examine or change variables; all MATLAB commands are valid. This keyboard mode is useful for

debugging your functions.

To terminate the keyboard mode, type return, and then press **Enter**. To terminate keyboard mode and exit the function, type dbquit, and

press Enter.

See Also dbstop, input, quit, pause, return

Return all keys of containers. Map object

Syntax

k = keys(M)

Description

k = keys(M) returns cell array k that contains all of the keys stored in Map object M.

Read more about Map Containers in the MATLAB Programming Fundamentals documentation.

Examples

Construct a Map object that relates states in the United States to their capital cities:

```
US_Capitals = containers.Map( ...
{'Georgia', 'Alaska', 'Vermont', 'Oregon'}, ...
{'Atlanta', 'Juneau', 'Montpelier', 'Salem'})
```

Use the keys and values methods to list all keys and values in the map:

```
keys(US_Capitals)
ans =
    'Arizona' 'Nebraska' 'New York' 'Oregon'

values(US_Capitals)
ans =
    'Phoenix' 'Lincoln' 'Albany' 'Salem'
```

Use the map to look up a capital when given a specific state:

```
sprintf(' The capital of %s is %s', ...
'Alaska', US_Capitals('Alaska'))
ans =
   The capital of Alaska is Juneau
```

See Also

containers.Map, values(Map), size(Map), length(Map)isKey(Map),
remove(Map), handle

Kronecker tensor product

Syntax

K = kron(X,Y)

Description

K = kron(X,Y) returns the Kronecker tensor product of X and Y. The result is a large array formed by taking all possible products between the elements of X and those of Y. If X is m-by-n and Y is p-by-q, then kron(X,Y) is m*p-by-n*q.

Examples


If X is 2-by-3, then kron(X,Y) is

```
[ X(1,1)*Y X(1,2)*Y X(1,3)*Y X(2,1)*Y X(2,2)*Y X(2,3)*Y ]
```

The matrix representation of the discrete Laplacian operator on a two-dimensional, n-by-n grid is a n^2-by-n^2 sparse matrix. There are at most five nonzero elements in each row or column. The matrix can be generated as the Kronecker product of one-dimensional difference operators with these statements:

```
I = speye(n,n);
E = sparse(2:n,1:n-1,1,n,n);
D = E+E'-2*I;
A = kron(D,I)+kron(I,D);
```

Plotting this with the spy function for n = 5 yields:



See Also hankel, toeplitz

last (MException)

Purpose

Last uncaught exception

Syntax

exception = MException.last
MException.last('reset')

Description

exception = MException.last displays the contents of the MException object representing your most recent uncaught error. This is a static method of the MException class; it is not a method of an MException instance.

Note Use this method from the MATLAB command line only, and not within a function.

MException.last('reset') sets the identifier and message properties of the exception retreived by MException.last to the empty string, the stack property to a 0-by-1 structure, and cause property to an empty cell array.

MException.last is not set if an exception is caught by a try-catch statement.

Examples

This example displays the last error that was caught during this MATLAB session:

```
A = 25;
A(2)
??? Index exceeds matrix dimensions.

MException.last
ans =

MException object with properties:
   identifier: 'MATLAB:badsubscript'
      message: 'Index exceeds matrix dimensions.'
```

last (MException)

stack: [0x1 struct]
cause: {}

See Also

try, catch, error, assert, MException, throw(MException),
rethrow(MException), throwAsCaller(MException),
addCause(MException), getReport(MException),

Tiff.lastDirectory

Purpose Determine if current IFD is last in file

Syntax bool = tiffobj.lastDirectory()

Description bool = tiffobj.lastDirectory() returns true if the current image

file directory (IFD) is the last IFD in the TIFF file; otherwise, false.

Open a Tiff object and determine if the current directory is the last directory in the file. Replace myfile.tif with the name of a TIFF file

on your MATLAB path. If the file contains only one image, the current

IFD will be the last:

```
t = Tiff('myfile.tif', 'r');
tf = t.lastDirectory();
```

References This method corresponds to the TIFFLastDirectory function in the

LibTIFF C API. To use this method, you must be familiar with LibTIFF version 3.7.1, as well as the TIFF specification and technical notes. View this documentation at LibTIFF - TIFF Library and Utilities.

See Also Tiff.setDirectory

Tutorials • "Exporting Image Data and Metadata to TIFF Files"

· "Reading Image Data and Metadata from TIFF Files"

Last error message

Note lasterr will be removed in a future version. You can obtain information about any error that has been generated by catching an MException. See "Capturing Information About the Error" in the Programming Fundamentals documentation.

Syntax

```
msgstr = lasterr
[msgstr, msgid] = lasterr
lasterr('new_msgstr')
lasterr('new_msgstr', 'new_msgid')
[msgstr, msgid] = lasterr('new_msgstr', 'new_msgid')
```

Description

msgstr = lasterr returns the last error message generated by the MATLAB software.

[msgstr, msgid] = lasterr returns the last error in msgstr and its message identifier in msgid. If the error was not defined with an identifier, lasterr returns an empty string for msgid. See "Message Identifiers" in the MATLAB Programming Fundamentals documentation for more information on the msgid argument and how to use it.

lasterr('new_msgstr') sets the last error message to a new string, new_msgstr, so that subsequent invocations of lasterr return the new error message string. You can also set the last error to an empty string with lasterr('').

lasterr('new_msgstr', 'new_msgid') sets the last error message and its identifier to new strings new_msgstr and new_msgid, respectively. Subsequent invocations of lasterr return the new error message and message identifier.

[msgstr, msgid] = lasterr('new_msgstr', 'new_msgid') returns
the last error message and its identifier, also changing these values
so that subsequent invocations of lasterr return the message and
identifier strings specified by new_msgstr and new_msgid respectively.

Examples Example 1

Here is a function that examines the lasterr string and displays its own message based on the error that last occurred. This example deals with two cases, each of which is an error that can result from a matrix multiply:

```
function matrix_multiply(A, B)
try
    A * B
catch
    errmsg = lasterr;
    if(strfind(errmsg, 'Inner matrix dimensions'))
        disp('** Wrong dimensions for matrix multiply')
    else
        if(strfind(errmsg, 'not defined for variables of class'))
            disp('** Both arguments must be double matrices')
        end
    end
end
```

If you call this function with matrices that are incompatible for matrix multiplication (e.g., the column dimension of A is not equal to the row dimension of B), MATLAB catches the error and uses lasterr to determine its source:

```
A = [1 2 3; 6 7 2; 0 -1 5];
B = [9 5 6; 0 4 9];

matrix_multiply(A, B)
** Wrong dimensions for matrix multiply
```

Example 2

Specify a message identifier and error message string with error:

In your error handling code, use lasterr to determine the message identifier and error message string for the failing operation:

```
[errmsg, msgid] = lasterr
errmsg =
   The angle specified must be less than 90 degrees.
msgid =
   MyToolbox:angleTooLarge
```

See Also

error, lasterror, rethrow, warning, lastwarn

lasterror

Purpose

Last error message and related information

Note 1 asterror will be removed in a future version. You can obtain information about any error that has been generated by catching an MException. See "Capturing Information About the Error" in the Programming Fundamentals documentation.

Syntax

- s = lasterror
- s = lasterror(err)
- s = lasterror('reset')

Description

s = lasterror returns a structure s containing information about the most recent error issued by the MATLAB software. The return structure contains the following fields:

Fieldname	Description
message	Character array containing the text of the error message.
identifier	Character array containing the message identifier of the error message. If the last error issued by MATLAB had no message identifier, then the identifier field is an empty character array.
stack	Structure providing information on the location of the error. The structure has fields file, name, and line, and is the same as the structure returned by the dbstack function. If lasterror returns no stack information, stack is a 0-by-1 structure having the same three fields.

Note The lasterror return structure might contain additional fields in future versions of MATLAB.

The fields	of	the	structure	returned	in	stack are

Fieldname	Description
file	Name of the file in which the function generating the error appears. This field is the empty string if there is no file.
name	Name of the function in which the error occurred. If this is the primary function in the file, and the function name differs from the file name, name is set to the file name.
line	Line number of the file at which the error occurred.

See "Message Identifiers" in the MATLAB Programming Fundamentals documentation for more information on the syntax and usage of message identifiers.

- s = lasterror(err) sets the last error information to the error message and identifier specified in the structure err. Subsequent invocations of lasterror return this new error information. The optional return structure s contains information on the previous error.
- s = lasterror('reset') sets the last error information to the default state. In this state, the message and identifier fields of the return structure are empty strings, and the stack field is a 0-by-1 structure.

Remarks

The MathWorks is gradually transitioning MATLAB error handling to an object-oriented scheme that is based on the MException class. Although support for lasterror is expected to continue, using the static last method of MException is preferable.

Warning

lasterror and MException.last are not guaranteed to always return identical results. For example, MException.last updates its error status only on uncaught errors, where lasterror can update its error status on any error, whether it is caught or not.

Examples Example 1

Save the following MATLAB code in a file called average.m:

```
function y = average(x)
% AVERAGE Mean of vector elements.
% AVERAGE(X), where X is a vector, is the mean of vector elements.
% Nonvector input results in an error.
check_inputs(x)
y = sum(x)/length(x); % The actual computation

function check_inputs(x)
[m,n] = size(x);
if (-((m == 1) || (n == 1)) || (m == 1 && n == 1))
    error('AVG:NotAVector', 'Input must be a vector.')
end
```

Now run the function. Because this function requires vector input, passing a scalar value to it forces an error. The error occurs in subroutine check_inputs:

```
average(200)
??? Error using ==> average>check_inputs
Input must be a vector.

Error in ==> average at 5
check_inputs(x)
```

Get the three fields from lasterror:

```
err = lasterror
err =
          message: [1x61 char]
    identifier: 'AVG:NotAVector'
          stack: [2x1 struct]
```

Display the text of the error message:

```
msg = err.message
```

```
msg =
    Error using ==> average>check_inputs
    Input must be a vector.
```

Display the fields containing the stack information. err.stack is a 2-by-1 structure because it provides information on the failing subroutine check inputs and also the outer, primary function average:

```
st1 = err.stack(1,1)
st1 =
    file: 'd:\matlab_test\average.m'
    name: 'check_inputs'
    line: 11

st2 = err.stack(2,1)
st2 =
    file: 'd:\matlab_test\average.m'
    name: 'average'
    line: 5
```

Note As a rule, the name of your primary function should be the same as the name of the file that contains that function. If these names differ, MATLAB uses the file name in the name field of the stack structure.

Example 2

lasterror is often used in conjunction with the rethrow function in try-catch statements. For example,

```
try
    do_something
catch
    do_cleanup
    rethrow(lasterror)
end
```

lasterror

See Also

 ${\tt last(MException),\,MException,\,try,\,catch,\,error,\,assert,\,rethrow,\,}\\ {\tt lastwarn,\,dbstack}$

Last warning message

Syntax

```
msgstr = lastwarn
[msgstr, msgid] = lastwarn
lastwarn('new_msgstr')
lastwarn('new_msgstr', 'new_msgid')
[msgstr, msgid] = lastwarn('new_msgstr', 'new_msgid')
```

Description

msgstr = lastwarn returns the last warning message generated by the MATLAB software.

[msgstr, msgid] = lastwarn returns the last warning in msgstr and its message identifier in msgid. If the warning was not defined with an identifier, lastwarn returns an empty string for msgid. See "Message Identifiers" and "Warning Control" in the MATLAB Programming Fundamentals documentation for more information on the msgid argument and how to use it.

lastwarn('new_msgstr') sets the last warning message to a new string, new_msgstr, so that subsequent invocations of lastwarn return the new warning message string. You can also set the last warning to an empty string with lastwarn('').

lastwarn('new_msgstr', 'new_msgid') sets the last warning message and its identifier to new strings new_msgstr and new_msgid, respectively. Subsequent invocations of lastwarn return the new warning message and message identifier.

[msgstr, msgid] = lastwarn('new_msgstr', 'new_msgid') returns the last warning message and its identifier, also changing these values so that subsequent invocations of lastwarn return the message and identifier strings specified by new_msgstr and new_msgid, respectively.

Remarks

lastwarn does not return warnings that are reported during the parsing of MATLAB commands. (Warning messages that include the failing file name and line number are parse-time warnings.)

Examples

Write a short function that generates a warning message. At the start of the function, enable any warnings that have a message identifier called TestEnv:InvalidInput:

```
function myfun(p1)
warning on TestEnv:InvalidInput;

exceedMax = find(p1 > 5000);
if any(exceedMax)
    warning('TestEnv:InvalidInput', ...
    '%d values in the "%s" array exceed the maximum.', ...
    length(exceedMax), inputname(1))
end
```

Pass an invalid value to the function:

```
dataIn = magic(10) - 2;
myfun(dataIn)
Warning: 2 values in the "dataIn" array exceed the maximum.
> In myfun at 4
```

Use lastwarn to determine the message identifier and error message string for the operation:

```
[warnmsg, msgid] = lastwarn
warnmsg =
   2 values in the "dataIn" array exceed the maximum.
msgid =
   TestEnv:InvalidInput
```

See Also

warning, error, lasterr, lasterror

Purpose Least common multiple

Syntax L = lcm(A,B)

Description L = lcm(A,B) returns the least common multiple of corresponding

elements of arrays \boldsymbol{A} and $\boldsymbol{B}.$ Inputs \boldsymbol{A} and \boldsymbol{B} must contain positive integer

elements and must be the same size (or either can be scalar).

Examples 1cm(8,40)

ans =

40

lcm(pascal(3),magic(3))

See Also gcd

Block LDL' factorization for Hermitian indefinite matrices

Syntax

```
L = ldl(A)
[L,D] = ldl(A)
[L,D,P] = ldl(A)
[L,D,p] = ldl(A,'vector')
[U,D,P] = ldl(A,'upper')
[U,D,p] = ldl(A,'upper','vector')
[L,D,P,S] = ldl(A)
[L,D,P,S] = LDL(A,THRESH)
[U,D,p,S] = LDL(A,THRESH,'upper','vector')
```

Description

L = ldl(A) returns only the "psychologically lower triangular matrix" L as in the two-output form. The permutation information is lost, as is the block diagonal factor D. By default, ldl references only the diagonal and lower triangle of A, and assumes that the upper triangle is the complex conjugate transpose of the lower triangle. Therefore [L,D,P] = ldl(TRIL(A)) and [L,D,P] = ldl(A) both return the exact same factors. Note, this syntax is not valid for sparse A.

[L,D] = 1d1(A) stores a block diagonal matrix D and a "psychologically lower triangular matrix" (i.e a product of unit lower triangular and permutation matrices) in L such that A = L*D*L'. The block diagonal matrix D has 1-by-1 and 2-by-2 blocks on its diagonal. Note, this syntax is not valid for sparse A.

[L,D,P] = 1dl(A) returns unit lower triangular matrix L, block diagonal D, and permutation matrix P such that P'*A*P = L*D*L'. This is equivalent to [L,D,P] = 1dl(A,'matrix').

[L,D,p] = 1dl(A, 'vector') returns the permutation information as a vector, p, instead of a matrix. The p output is a row vector such that A(p,p) = L*D*L'.

[U,D,P] = Idl(A, 'upper') references only the diagonal and upper triangle of A and assumes that the lower triangle is the complex conjugate transpose of the upper triangle. This syntax returns a unit upper triangular matrix U such that P'*A*P = U'*D*U (assuming that

A is Hermitian, and not just upper triangular). Similarly, [L,D,P] = ldl(A, 'lower') gives the default behavior.

[U,D,p] = ldl(A, 'upper', 'vector') returns the
permutation information as a vector, p, as does [L,D,p] =
ldl(A, 'lower', 'vector'). A must be a full matrix.

[L,D,P,S] = ldl(A) returns unit lower triangular matrix L, block diagonal D, permutation matrix P, and scaling matrix S such that P'*S*A*S*P = L*D*L'. This syntax is only available for real sparse matrices, and only the lower triangle of A is referenced. ldl uses MA57 for sparse real symmetric A.

[L,D,P,S] = LDL(A,THRESH) uses THRESH as the pivot tolerance in MA57. THRESH must be a double scalar lying in the interval [0, 0.5]. The default value for THRESH is 0.01. Using smaller values of THRESH may give faster factorization times and fewer entries, but may also result in a less stable factorization. This syntax is available only for real sparse matrices.

[U,D,p,S] = LDL(A,THRESH, 'upper', 'vector') sets the pivot tolerance and returns upper triangular U and permutation vector p as described above.

Examples

These examples illustrate the use of the various forms of the ldl function, including the one-, two-, and three-output form, and the use of the vector and upper options. The topics covered are:

- "Example 1 Two-Output Form of ldl" on page 2-2256
- $\bullet\,$ "Example 2 Three Output Form of ldl" on page 2-2256
- $\bullet\,$ "Example 3 The Structure of D" on page 2-2257
- "Example 4 Using the 'vector' Option" on page 2-2257
- ullet "Example 5 Using the 'upper' Option" on page 2-2258
- "Example 6 linsolve and the Hermitian indefinite solver" on page 2-2258

Before running any of these examples, you will need to generate the following positive definite and indefinite Hermitian matrices:

```
A = full(delsq(numgrid('L', 10)));
B = gallery('uniformdata',10,0);
M = [eye(10) B; B' zeros(10)];
```

The structure of M here is very common in optimization and fluid-flow problems, and M is in fact indefinite. Note that the positive definite matrix A must be full, as 1d1 does not accept sparse arguments.

Example 1 - Two-Output Form of Idl

The two-output form of 1d1 returns L and D such that A-(L*D*L') is small, L is "psychologically unit lower triangular" (i.e., a permuted unit lower triangular matrix), and D is a block 2-by-2 diagonal. Note also that, because A is positive definite, the diagonal of D is all positive:

```
[LA,DA] = ldl(A);
fprintf(1, ...
'The factorization error ||A - LA*DA*LA''|| is %g\n', ...
norm(A - LA*DA*LA'));
neginds = find(diag(DA) < 0)</pre>
```

Given a b, solve Ax=b using LA, DA:

```
\begin{array}{lll} bA &=& sum(A,2); \\ x &=& LA' \setminus (DA \setminus (LA \setminus bA)); \\ fprintf(\dots \\ 'The absolute error norm \mid \mid x \text{ - ones}(size(bA)) \mid \mid \text{ is } \mbox{$^{n'}$, ...} \\ norm(x &-& ones(size(bA)))); \end{array}
```

Example 2 — Three Output Form of Idl

The three output form returns the permutation matrix as well, so that L is in fact unit lower triangular:

```
[Lm, Dm, Pm] = ldl(M);
fprintf(1, ...
'The error norm ||Pm''*M*Pm - Lm*Dm*Lm''|| is %g\n', ...
```

```
norm(Pm'*M*Pm - Lm*Dm*Lm'));
fprintf(1, ...
'The difference between Lm and tril(Lm) is %g\n', ...
norm(Lm - tril(Lm)));

Given b, solve Mx=b using Lm, Dm, and Pm:

bM = sum(M,2);
x = Pm*(Lm'\(Dm\(Lm\(Pm'*bM))));
fprintf(...
'The absolute error norm ||x - ones(size(b))|| is %g\n', ...
norm(x - ones(size(bM))));
```

Example 3 — The Structure of D

D is a block diagonal matrix with 1-by-1 blocks and 2-by-2 blocks. That makes it a special case of a tridiagonal matrix. When the input matrix is positive definite, D is almost always diagonal (depending on how definite the matrix is). When the matrix is indefinite however, D may be diagonal or it may express the block structure. For example, with A as above, DA is diagonal. But if you shift A just a bit, you end up with an indefinite matrix, and then you can compute a D that has the block structure.

```
figure; spy(DA); title('Structure of D from ldl(A)');
[Las, Das] = ldl(A - 4*eye(size(A)));
figure; spy(Das);
title('Structure of D from ldl(A - 4*eye(size(A)))');
```

Example 4 — Using the 'vector' Option

Like the 1u function, 1d1 accepts an argument that determines whether the function returns a permutation vector or permutation matrix. 1d1 returns the latter by default. When you select 'vector', the function executes faster and uses less memory. For this reason, specifying the 'vector' option is recommended. Another thing to note is that indexing is typically faster than multiplying for this kind of operation:

```
[Lm, Dm, pm] = ldl(M, 'vector');
```

```
fprintf(1, 'The error norm ||M(pm,pm) - Lm*Dm*Lm''|| is %g\n', ...
    norm(M(pm,pm) - Lm*Dm*Lm'));

% Solve a system with this kind of factorization.
clear x;
x(pm,:) = Lm'\(Dm\(Lm\(bM(pm,:))));
fprintf('The absolute error norm ||x - ones(size(b))|| is %g\n', ...
    norm(x - ones(size(bM))));
```

Example 5 — Using the 'upper' Option

Like the chol function, 1dl accepts an argument that determines which triangle of the input matrix is referenced, and also whether 1dl returns a lower (L) or upper (L') triangular factor. For dense matrices, there are no real savings with using the upper triangular version instead of the lower triangular version:

```
Ml = tril(M);
[Lml, Dml, Pml] = ldl(Ml, 'lower'); % 'lower' is default behavior.
fprintf(1, ...
'The difference between Lml and Lm is %g\n', norm(Lml - Lm));
[Umu, Dmu, pmu] = ldl(triu(M), 'upper', 'vector');
fprintf(1, ...
'The difference between Umu and Lm'' is %g\n', norm(Umu - Lm'));
% Solve a system using this factorization.
clear x;
x(pm,:) = Umu\(Dmu\(Umu'\(bM(pmu,:))));
fprintf(...
'The absolute error norm ||x - ones(size(b))|| is %g\n', ...
norm(x - ones(size(bM))));
```

When specifying both the 'upper' and 'vector' options, 'upper' must precede 'vector' in the argument list.

Example 6 — linsolve and the Hermitian indefinite solver

When using the linsolve function, you may experience better performance by exploiting the knowledge that a system has a symmetric

matrix. The matrices used in the examples above are a bit small to see this so, for this example, generate a larger matrix. The matrix here is symmetric positive definite, and below we will see that with each bit of knowledge about the matrix, there is a corresponding speedup. That is, the symmetric solver is faster than the general solver while the symmetric positive definite solver is faster than the symmetric solver:

```
Abig = full(delsq(numgrid('L', 30)));
bbig = sum(Abig, 2);
LSopts.POSDEF = false;
LSopts.SYM = false;
tic; linsolve(Abig, bbig, LSopts); toc;
LSopts.SYM = true;
tic; linsolve(Abig, bbig, LSopts); toc;
LSopts.POSDEF = true;
tic; linsolve(Abig, bbig, LSopts); toc;
```

Algorithm

1d1 uses the MA57 routines in the Harwell Subroutine Library (HSL) for real sparse matrices.

References

[1] Ashcraft, C., R.G. Grimes, and J.G. Lewis. "Accurate Symmetric Indefinite Linear Equations Solvers." *SIAM J. Matrix Anal. Appl.* Vol. 20. Number 2, 1998, pp. 513–561.

[2] Duff, I. S. "MA57 — A new code for the solution of sparse symmetric definite and indefinite systems." Technical Report RAL-TR-2002-024, Rutherford Appleton Laboratory, 2002.

See Also

chol, lu, qr

ldivide, rdivide

Purpose

Left or right array division

Syntax

```
ldivide(A,B)
```

A.\B

rdivide(A,B)

A./B

Description

Idivide (A,B) and the equivalent A.\B divides each entry of B by the corresponding entry of A. A and B must be arrays of the same size. A scalar value for either A or B is expanded to an array of the same size as the other.

rdivide(A,B) and the equivalent A./B divides each entry of A by the corresponding entry of B. A and B must be arrays of the same size. A scalar value for either A or B is expanded to an array of the same size as the other.

Example

```
A = [1 2 3;4 5 6];
B = ones(2, 3);
A.\B
ans =
1.0000 0.5000 0.3333
0.2500 0.2000 0.1667
```

See Also

Arithmetic Operators, mldivide, mrdivide

Test for less than or equal to

Syntax

 $A \le B$ le(A, B)

Description

A <= B compares each element of array A with the corresponding element of array B, and returns an array with elements set to logical 1 (true) where A is less than or equal to B, or set to logical 0 (false) where A is greater than B. Each input of the expression can be an array or a scalar value.

If both A and B are scalar (i.e., 1-by-1 matrices), then the MATLAB software returns a scalar value.

If both A and B are nonscalar arrays, then these arrays must have the same dimensions, and MATLAB returns an array of the same dimensions as A and B.

If one input is scalar and the other a nonscalar array, then the scalar input is treated as if it were an array having the same dimensions as the nonscalar input array. In other words, if input A is the number 100, and B is a 3-by-5 matrix, then A is treated as if it were a 3-by-5 matrix of elements, each set to 100. MATLAB returns an array of the same dimensions as the nonscalar input array.

le(A, B) is called for the syntax A < B when either A or B is an object.

Examples

Create two 6-by-6 matrices, A and B, and locate those elements of A that are less than or equal to the corresponding elements of B:

```
A = magic(6);
B = repmat(3*magic(3), 2, 2);
A <= B
ans =
     0
            1
                          0
                                 0
                                        0
     1
            0
                   1
                          0
                                 0
                                        0
                   1
     0
                          0
                                        0
            0
     1
                   0
                          1
                                 0
                                        1
```

le

0 1 0 0 1 1 1 0 0 0 1 0

See Also

1t, eq, ge, gt, ne, Relational Operators

Graph legend for lines and patches

Syntax

```
legend
legend('string1','string2',...)
legend(h,'string1','string2',...)
legend(M)
legend(h,M)
legend(M,'parameter_name','parameter_value',...)
legend(h,M,'parameter name','parameter value',...)
legend(axes handle,...)
legend('off'), legend(axes handle,'off')
legend('toggle'), legend(axes handle,'toggle')
legend('hide'), legend(axes handle,'hide')
legend('show'), legend(axes_handle,'show')
legend('boxoff'), legend(axes handle, 'boxoff')
legend('boxon'), legend(axes handle, 'boxon')
legend handle = legend(...)
legend(..., 'Location', 'location')
legend(..., 'Orientation', 'orientation')
[legend h,object h,plot h,text strings] = legend(...)
legend(li object,string1,string2,string3)
legend(li objects,M)
```

Description

legend places a legend on various types of graphs (line plots, bar graphs, pie charts, etc.). For each line plotted, the legend shows a sample of the line type, marker symbol, and color beside the text label you specify. When plotting filled areas (patch or surface objects), the legend contains a sample of the face color next to the text label.

The font size and font name for the legend strings match the axes FontSize and FontName properties.

legend('string1', 'string2',...) displays a legend in the current axes using the specified strings to label each set of data.

legend(h, 'string1', 'string2',...) displays a legend on the plot
containing the objects identified by the handles in the vector h and

uses the specified strings to label the corresponding graphics object (line, barseries, etc.).

legend(M) adds a legend containing the rows of the matrix or cell array of strings M as labels. For matrices, this is the same as legend(M(1,:),M(2,:),...).

legend(h,M) associates each row of the matrix or cell array of strings M with the corresponding graphics object (patch or line) in the vector of handles h.

legend(M,'parameter_name','parameter_value',...) and
legend(h,M,'parameter_name','parameter_value',...) allow
parameter/value pairs to be set when creating a legend (you can also
assign them with set or with the Property Editor or Property Inspector).
M must be a cell array of names. Legends inherit the properties of axes,
although not all of them are relevant to legend objects.

legend(axes_handle,...) displays the legend for the axes specified by axes handle.

legend('off'), legend(axes_handle,'off') removes the legend in the current axes or the axes specified by axes_handle.

legend('toggle'), legend(axes_handle, 'toggle') toggles the legend on or off. If no legend exists for the current axes, one is created using default strings.

The *default string* for an object is the value of the object's DisplayName property, if you have defined a value for DisplayName (which you can do using the Property Editor or calling set). Otherwise, legend constructs a string of the form data1, data2, etc. Setting display names is useful when you are experimenting with legends and might forget how objects in a lineseries, for example, are ordered.

When you specify legend strings in a legend command, their respective DisplayNames are set to these strings. If you delete a legend and then create a new legend without specifying labels for it, the values of DisplayName are (re)used as label names. Naturally, the associated plot objects must have a DisplayName property for this to happen: all

_series and _group plot objects have a DisplayName property; Handle Graphics primitives, such as line and patch, do not.

Legends for graphs that contain groups of objects such as lineseries, barseries, contourgroups, etc. created by high-level plotting commands such as plot, bar, contour, etc., by default display a single legend entry for the entire group, regardless of how many member objects it contains. However, you can customize such legends to show individual entries for all or selected member objects and assign a unique DisplayName to any of them. You control how groups appear in the legend by setting values for their Annotation and DisplayName properties with code. For information and examples about customizing legends in this manner, see "Controlling Legends" in the MATLAB Graphics documentation.

You can specify EdgeColor and TextColor as RGB triplets or as ColorSpecs. You cannot set these colors to 'none'. To hide the box surrounding a legend, set the Box property to 'off'. To allow the background to show through the legend box, set the legend's Color property to 'none', for example,

```
set(legend_handle, 'Box', 'off')
set(legend handle, 'Color', 'none')
```

This is similar to the effect of the command legend boxoff, except that boxoff also hides the legend's border.

You can use a legend's handle to set text properties for all the strings in a legend at once with a cell array of strings, rather than looping through each of them. See the last line of the example below, which demonstrates setting a legend's Interpreter property. In that example, you could reset the String property of the legend as follows:

```
set(h, 'String', {'cos(x)', 'sin(x)'})
```

See the documentation for Text Properties for additional details.

legend('hide'), legend(axes_handle,'hide') makes the legend in the current axes or the axes specified by axes handle invisible.

legend('show'), legend(axes_handle,'show') makes the legend in the current axes or the axes specified by axes_handle visible. A legend is created if one did not exist previously. Legends created automatically are limited to depict only the first 20 lines in the plot; if you need more legend entries, you can manually create a legend for them all with legend('string1','string2',...) syntax.

legend('boxoff'), legend(axes_handle, 'boxoff') removes the box from the legend in the current axes or the axes specified by axes handle, and makes its background transparent.

legend('boxon'), legend(axes_handle, 'boxon') adds a box with an opaque background to the legend in the current axes or the axes specified by axes handle.

You can also type the above six commands using the syntax

legend *keyword*

If the keyword is not recognized, it is used as legend text, creating a legend or replacing the current legend.

legend_handle = legend(...) returns the handle to the legend on
the current axes, or [] if no legend exists.

legend(..., 'Location', 'location') uses location to determine where to place the legend. location can be either a 1-by-4 position vector ([left bottom width height]) or one of the following strings.

Specifier	Location in Axes
North	Inside plot box near top
South	Inside bottom
East	Inside right
West	Inside left
NorthEast	Inside top right (default for 2-D plots)
NorthWest	Inside top left

Specifier	Location in Axes
SouthEast	Inside bottom right
SouthWest	Inside bottom left
NorthOutside	Outside plot box near top
SouthOutside	Outside bottom
EastOutside	Outside right
WestOutside	Outside left
NorthEastOutside	Outside top right (default for 3-D plots)
NorthWestOutside	Outside top left
SouthEastOutside	Outside bottom right
SouthWestOutside	Outside bottom left
Best	Least conflict with data in plot
BestOutside	Least unused space outside plot

If the legend text does not fit in the 1-by-4 position vector, the position vector is resized around the midpoint to fit the legend text given its font and size, making the legend taller or wider. The *location* string can be all lowercase and can be abbreviated by sentinel letter (e.g., N, NE, NEO, etc.). Using one of the ...Outside values for *location* ensures that the legend does not overlap the plot, whereas overlaps can occur when you specify any of the other cardinal values. The *location* property applies to colorbars and legends, but not to axes.

Obsolete Location Values

The first column of the following table shows the now-obsolete specifiers for legend locations that were in use prior to Version 7, along with a description of the locations and their current equivalent syntaxes:

Obsolete Specifier	Location in Axes	Current Specifier
-1	Outside axes on right side	NorthEastOutside
0	Inside axes	Best
1	Upper right corner of axes	NorthEast
2	Upper left corner of axes	NorthWest
3	Lower left corner of axes	SouthWest
4	Lower right corner of axes	SouthEast

legend(..., 'Orientation', 'orientation') creates a legend with the legend items arranged in the specified orientation. orientation can be vertical (the default) or horizontal.

[legend_h,object_h,plot_h,text_strings] = legend(...) returns

- legend h Handle of the legend axes
- object_h Handles of the line, patch, and text graphics objects used in the legend
- plot_h Handles of the lines and other objects used in the plot
- text_strings Cell array of the text strings used in the legend

These handles enable you to modify the properties of the respective objects.

legend(li_object,string1,string2,string3) creates a legend for legendinfo objects li_objects with strings string1, etc.

legend(li_objects,M) creates a legend of legendinfo objects
li_objects, where M is a string matrix or cell array of strings
corresponding to the legendinfo objects.

Relationship to Axes

legend associates strings with the objects in the axes in the same order that they are listed in the axes Children property. By default, the legend annotates the current axes.

You can only display one legend per axes. legend positions the legend based on a variety of factors, such as what objects the legend obscures.


The properties that legends do not share with axes are

- Location
- Orientation
- EdgeColor
- TextColor
- Interpreter
- String

Examples

Add a legend to a graph showing a sine and cosine function:

```
x = -pi:pi/20:pi;
plot(x,cos(x),'-ro',x,sin(x),'-.b')
h = legend('cos_x','sin_x',2);
set(h,'Interpreter','none')
```



In this example, the plot command specifies a solid, red line ('-r') for the cosine function and a dash-dot, blue line ('-.b') for the sine function.

Alternatives

Add a legend to a selected axes on a graph with the Insert Legend tool

on the figure toolbar, or use **Insert** —> **Legend** from the figure menu. Use the Property Editor to modify the position, font, and other properties of a legend. For details, see Using Plot Edit Mode in the MATLAB Graphics documentation.

Moving the Legend

Move the legend by pressing the left mouse button while the cursor is over the legend and dragging the legend to a new location. Double-clicking a label allows you to edit the label.

legend

See Also LineSpec | plot

How To • "Adding a Legend to a Graph"

legendre

Purpose

Associated Legendre functions

Syntax

P = legendre(n,X)
S = legendre(n,X,'sch')

N = legendre(n,X,'norm')

Definitions

Associated Legendre Functions

The Legendre functions are defined by

where

 $P_n(x)$

is the Legendre polynomial of degree *n*:

Schmidt Seminormalized Associated Legendre Functions

The Schmidt seminormalized associated Legendre functions are related to the nonnormalized associated Legendre functions by

Fully Normalized Associated Legendre Functions

The fully normalized associated Legendre functions are normalized such that

and are related to the unnormalized associated Legendre functions by

Description

P = legendre(n,X) computes the associated Legendre functions of degree n and order m = 0,1,...,n, evaluated for each element of X.

Argument n must be a scalar integer, and X must contain real values in the domain $-1 \le x \le 1$.

If X is a vector, then P is an (n+1)-by-q matrix, where q = length(X). Each element P(m+1,i) corresponds to the associated Legendre function of degree n and order m evaluated at X(i).

In general, the returned array P has one more dimension than X, and each element P(m+1,i,j,k,...) contains the associated Legendre function of degree n and order m evaluated at X(i,j,k,...). Note that the first row of P is the Legendre polynomial evaluated at X, i.e., the case where m=0.

S = legendre(n,X,'sch') computes the Schmidt seminormalized associated Legendre functions.

N = legendre(n, X, 'norm') computes the fully normalized associated Legendre functions.

Examples

Example 1

The statement legendre (2,0:0.1:0.2) returns the matrix

	x = 0	x = 0.1	x = 0.2
m = 0	-0.5000	-0.4850	-0.4400
m = 1	0	-0.2985	-0.5879
m = 2	3.0000	2.9700	2.8800

Example 2

```
Given,
    X = rand(2,4,5);
    n = 2;
    P = legendre(n,X)
then
    size(P)
```

legendre

Algorithm

legendre uses a three-term backward recursion relationship in m. This recursion is on a version of the Schmidt seminormalized associated Legendre functions , which are complex spherical harmonics. These functions are related to the standard Abramowitz and Stegun [1] functions by

They are related to the Schmidt form given previously by

References

[1] Abramowitz, M. and I. A. Stegun, *Handbook of Mathematical Functions*, Dover Publications, 1965, Ch.8.

[2] Jacobs, J. A., Geomagnetism, Academic Press, 1987, Ch.4.

Length of vector or largest array dimension

Syntax

numberOfElements = length(array)

Description

numberOfElements = length(array) finds the number of elements along the largest dimension of an array. array is an array of any MATLAB data type and any valid dimensions. numberOfElements is a whole number of the MATLAB double class.

For nonempty arrays, numberOfElements is equivalent to max(size(array)). For empty arrays, numberOfElements is zero.

Examples

Create a 1-by-8 array X and use length to find the number of elements in the second (largest) dimension:

```
X = [5, 3.4, 72, 28/4, 3.61, 17 94 89];
length(X)
ans =
    8
```

Create a 4-dimensional array Y in which the third dimension is the largest. Use length to find the number of elements in that dimension:

```
Y = rand(2, 5, 17, 13);
length(Y)
ans =
    17
```

Create a struct array S with character and numeric fields of different lengths. Use the structfun function to apply length to each field of S:

```
S = struct('f1', 'Name:', 'f2', 'Charlie', ...
'f3', 'DOB:', 'f4', 1917)
```

length

```
S =
    f1: 'Name:'
    f2: 'Charlie'
    f3: 'DOB:'
    f4: 1917

structfun(@(field)length(field), S)
ans =
    5
    7
    4
    1
```

See Also

numel | size | ndims

Length of containers. Map object

Syntax

L = length(M)

Description

L = length(M) returns the number of pairs in the map M. The number returned by this method is equivalent to size(M,1).

Read more about Map Containers in the MATLAB Programming Fundamentals documentation.

Examples

Create a Map object containing the names of several US states and the capital city of each:

```
US_Capitals = containers.Map( ...
{'Arizona', 'Nebraska', 'Nevada', 'New York', ...
'Georgia', 'Alaska', 'Vermont', 'Oregon'}, ...
{'Phoenix', 'Lincoln', 'Carson City', 'Albany', ...
'Atlanta', 'Juneau', 'Montpelier', 'Salem'});
```

Find out how many keys are in the map:

```
length(US_Capitals)
ans =
    8
```

This should be equal to the Count property for the object:

```
length(US_Capitals) == US_Capitals.Count
ans =
    1
```

See Also

containers.Map, keys(Map), values(Map), size(Map), isKey(Map),
remove(Map), handle

length (serial)

Purpose Length of serial port object array

Syntax length(obj)

Description length(obj) returns the length of the serial port object, obj. It is

equivalent to the command max(size(obj)).

See Also Functions

size

length (timeseries)

Purpose Length of time vector

Syntax length(ts)

Description length(ts) returns an integer that represents the length of the time

vector for the timeseries object ts. It returns 0 if ts is empty.

See Also isempty (timeseries), size (timeseries)

length (tscollection)

Purpose Length of time vector

Syntax length(tsc)

Description length(tsc) returns an integer that represents the length of the time

vector for the tscollection object tsc.

See Also isempty (tscollection), size (tscollection), tscollection

Purpose Return information on functions in shared library

Syntax m = libfunctions('libname')

m = libfunctions('libname', '-full')

libfunctions libname -full

Description

m = libfunctions('libname') returns the names of all functions defined in the external shared library, libname, that has been loaded into the MATLAB software with the loadlibrary function. The return value, m, is a cell array of strings.

m = libfunctions('libname', '-full') returns a full description of the functions in the library, including function signatures. This includes duplicate function names with different signatures. The return value, m, is a cell array of strings.

libfunctions libname -full is the command format for this function.

If you used an alias when initially loading the library, then you must use that alias for the libname argument.

Examples

To list the functions in the MATLAB libmx library, see "Viewing Functions in the Command Window".

See Also

loadlibrary, libfunctionsview, calllib, unloadlibrary

libfunctionsview

Purpose View functions in shared library

Syntax libfunctionsview('libname') libfunctionsview libname

Description libfunctionsview('libname') displays the names of the functions in

the external shared library, libname, that has been loaded into the

MATLAB software with the loadlibrary function.

libfunctionsview libname is the command format for this function.

If you used an alias when initially loading the library, then you must

use that alias for the libname argument.

MATLAB creates a new window in response to the libfunctionsview command. This window displays all of the functions defined in the specified library. For each of these functions, the following information is supplied:

• Type returned by the function

• Name of the function

• Arguments passed to the function

An additional column entitled "Inherited From" is displayed at the far right of the window. The information in this column is not useful for external libraries.

Examples T

To open a window showing functions in the libmx library, see "Viewing

Functions in a GUI".

See Also loadlibrary, libfunctions, calllib, unloadlibrary

Determine if shared library is loaded

Syntax

libisloaded('libname')
libisloaded libname

Description

libisloaded('libname') returns logical 1 (true) if the shared library libname is loaded and logical 0 (false) otherwise.

libisloaded libname is the command format for this function.

If you used an alias when initially loading the library, then you must use that alias for the libname argument.

Examples

Example 1

Load the shrlibsample library and check to see if the load was successful before calling one of its functions:

```
addpath([matlabroot '\extern\examples\shrlib'])
loadlibrary shrlibsample shrlibsample.h

if libisloaded('shrlibsample')
    x = calllib('shrlibsample', 'addDoubleRef', 1.78, 5.42, 13.3)
end
```

Since the library is successfully loaded, the call to addDoubleRef works as expected and returns

```
x = 20.5000
```

unloadlibrary shrlibsample

Example 2

Load the same library, this time giving it an alias. If you use libisloaded with the library name, shrlibsample, it now returns false. Since you loaded the library using an alias, all further references to the library must also use that alias:

libisloaded

```
addpath([matlabroot '\extern\examples\shrlib'])
loadlibrary shrlibsample shrlibsample.h alias lib
libisloaded shrlibsample
ans =
     0
libisloaded lib
ans =
     1
unloadlibrary lib
```

See Also

loadlibrary, unloadlibrary

Create pointer object for use with shared libraries

Syntax

p = libpointer

p = libpointer('type')

p = libpointer('type',value)

Description

p = libpointer returns an empty (void) pointer.

p = libpointer('type') returns an empty pointer that contains a reference to the specified type. This type can be any MATLAB numeric type, or a structure or enumerated type defined in an external library that has been loaded into MATLAB with the loadlibrary function. For valid types, see the table under "C and MATLAB Equivalent Types" in the MATLAB External Interfaces documentation.

Note Using this syntax, p is a NULL pointer. You, therefore, must ensure that any library function to which you pass p must be able to accept a NULL pointer as an argument.

p = libpointer('type',value) returns a pointer to the specified data type and initialized to the value supplied.

Remarks

MATLAB automatically converts data passed to and from external library functions to the data type expected by the external function. The libpointer function enables you to convert your argument data manually. This is an advanced feature available to experienced C programmers. For more information about using pointer objects, see "Working with Pointers" in the MATLAB External Interfaces documentation. Additional examples for using libpointer can be found in "Multilevel Pointers" in the same documentation.

Examples

This example passes an int16 pointer to a function that multiplies each value in a matrix by its index. The function multiplyShort is defined in the MATLAB sample shared library, shrlibsample.

Here is the C function:

```
void multiplyShort(short *x, int size)
{
    int i;
    for (i = 0; i < size; i++)
    *x++ *= i;
}</pre>
```

Load the shrlibsample library. Create the matrix, v, and also a pointer to it, pv:

Now call the C function in the library, passing the pointer to v. If you were to pass a *copy* of v, the results would be lost once the function terminates. Passing a pointer to v enables you to get back the results:

```
calllib('shrlibsample', 'multiplyShort', pv, 6);
get(pv, 'Value')
ans =
     0    12    32
     7    15    15
```

unloadlibrary shrlibsample

See Also

loadlibrary, libstruct

Create structure pointer for use with shared libraries

Syntax

- s = libstruct('structtype')
- s = libstruct('structtype',mlstruct)

Description

s = libstruct('structtype') returns a libstruct object s that is a MATLAB object designed to resemble a C structure of type specified by structtype. The structure type, structtype, is defined in an external library that must be loaded into MATLAB using the loadlibrary function.

Note Using this syntax, s is a NULL pointer. You, therefore, must ensure that any library function to which you pass s must be able to accept a NULL pointer as an argument.

s = libstruct('structtype', mlstruct) returns a libstruct object s with its fields initialized from MATLAB structure, mlstruct.

The libstruct function creates a C-style structure that you can pass to functions in an external library. You handle this structure in MATLAB as you would a true MATLAB structure.

What Types Are Available

To determine which MATLAB types to use when passing arguments to library functions, see the output of libfunctionsview or libfunctions -full. These functions list all of the functions found in a particular library along with a specification of the types required for each argument.

Examples

This example performs a simple addition of the fields of a structure. The function addStructFields is defined in the MATLAB sample shared library, shrlibsample.

Here is the C function:

double addStructFields(struct c_struct st)

```
{
       double t = st.p1 + st.p2 + st.p3;
       return t;
  }
Start by loading the shrlibsample library and creating the structure,
sm:
  addpath([matlabroot '\extern\examples\shrlib'])
  loadlibrary shrlibsample shrlibsample.h
                  sm.p2 = -299; sm.p3 = 1000;
  sm.p1 = 476;
Construct a libstruct object sc that uses the c struct template:
  sc = libstruct('c_struct', sm);
  get(sc)
       p1: 476
      p2: -299
       p3: 1000
Now call the function, passing the libstruct object, sc:
  calllib('shrlibsample', 'addStructFields', sc)
  ans =
       1177
```

Note In most cases, you can pass a MATLAB structure and MATLAB automatically converts the argument to a C structure. See "Working with Structures" in the MATLAB External Interfaces documentation for more information.

You must clear the libstruct object before unloading the library:

clear sc

unloadlibrary shrlibsample

libstruct

See Also loadlibrary, libpointer

Return license number or perform licensing task

Syntax

```
license
license('inuse')
S = license('inuse')
S = license('inuse', feature)
license('test',feature)
license('test',feature,toggle)
result = license('checkout',feature)
```

Description

license returns the license number for this MATLAB product. The return value is always a string but is not guaranteed to be a number. The following table lists text strings that license can return.

String	Description	
'demo'	MATLAB is a demonstration version	
'student'	MATLAB is the student version	
'unknown'	License number cannot be determined	

license ('inuse') returns a list of licenses checked out in the current MATLAB session. In the list, products are listed alphabetically by their license feature names, i.e., the text string used to identify products in the INCREMENT lines in a License File (license.dat). Note that the feature names returned in the list contain only lower-case characters.

S = license('inuse') returns an array of structures, where each structure represents a checked-out license. The structures contains two fields: feature and user. The feature field contains the license feature name. The user field contains the username of the person who has the license checked out.

S = license('inuse', feature) checks if the product specified by the text string feature is checked out in the current MATLAB session. If the product is checked out, the license function returns the product name and the username of the person who has it checked out in the

structure S. If the product is not currently checked out, the fields in the structure are empty.

The feature string must be a license feature name, spelled exactly as it appears in the INCREMENT lines in a License File. For example, the string 'Identification_Toolbox' is the feature name for the System Identification Toolbox TM . The feature string is not case-sensitive and must not exceed 27 characters.

license ('test', feature) tests if a license exists for the product specified by the text string feature. The license command returns 1 if the license exists and 0 if the license does not exist. The feature string identifies a product, as described in the previous syntax.

Note Testing for a license only confirms that the license exists. It does not confirm that the license can be checked out. For example, license will return 1 if a license exists, even if the license has expired or if a system administrator has excluded you from using the product in an options file. The existence of a license does not indicate that the product is installed.

license('test',feature,toggle) enables or disables testing of the product specified by the text string feature, depending on the value of toggle. The parameter toggle can have either of two values:

- 'enable' The syntax license('test',feature) returns 1 if the product license exists and 0 if the product license does not exist.
- 'disable 'The syntax license('test',feature) always returns 0 (product license does not exist) for the specified product.

Note Disabling a test for a particular product can impact other tests for the existence of the license, not just tests performed using the license command.

result = license('checkout',feature) checks out a license for the product identified by the text string feature. The license command returns 1 if it could check out a license for the product and 0 if it could not check out a license for the product.

Examples

Get the license number for this MATLAB.

license

Get a list of licenses currently being used. Note that the products appear in alphabetical order by their license feature name in the list returned.

```
license('inuse')
image_toolbox
map_toolbox
matlab
```

Get a list of licenses in use with information about who is using the license.

```
S = license('inuse');
S(1)
ans =
   feature: 'image_toolbox'
        user: 'juser'
```

Determine if the license for MATLAB is currently in use.

```
S = license('inuse', 'MATLAB')
  S =
       feature: 'matlab'
          user: 'jsmith'
Determine if a license exists for the Mapping Toolbox<sup>TM</sup>.
  license('test','map_toolbox')
   ans =
       1
Check out a license for the Control System Toolbox.
   license('checkout','control_toolbox')
   ans =
       1
Determine if the license for the Control System Toolbox is checked out.
  license('inuse')
   control_toolbox
   image\_toolbox
   map_toolbox
   matlab
isstudent
```

See Also

Purpose Create light object

Syntax light('PropertyName',propertyvalue,...)

handle = light(...)

Properties For a list of properties, see Light Properties.

Description

light creates a light object in the current axes. Lights affect only patch and surface objects.

light('PropertyName', propertyvalue,...) creates a light object using the specified values for the named properties. For a description of the properties, see Light Properties. The MATLAB software parents the light to the current axes unless you specify another axes with the Parent property.

handle = light(...) returns the handle of the light object created.

Remarks

You cannot see a light object *per se*, but you can see the effects of the light source on patch and surface objects. You can also specify an axes-wide ambient light color that illuminates these objects. However, ambient light is visible only when at least one light object is present and visible in the axes.

You can specify properties as property name/property value pairs, structure arrays, and cell arrays (see set and get for examples of how to specify these data types).

See also the patch and surface AmbientStrength, DiffuseStrength, SpecularStrength, SpecularExponent, SpecularColorReflectance, and VertexNormals properties. Also see the lighting and material commands.

Examples

Light the peaks surface plot with a light source located at infinity and oriented along the direction defined by the vector $[1\ 0\ 0]$, that is, along the *x*-axis.

h = surf(peaks);

Setting Default Properties

You can set default light properties on the axes, figure, and root object levels:

```
set(0, 'DefaultLightProperty', PropertyValue...)
set(gcf, 'DefaultLightProperty', PropertyValue...)
set(gca, 'DefaultLightProperty', PropertyValue...)
```

where *Property* is the name of the light property and *PropertyValue* is the value you are specifying. Use set and get to access light properties.

See Also

lighting, material, patch, surface

Light Properties for property descriptions

"Lighting" on page 1-111 for related functions

Tutorials

For more information about lighting, see "Lighting as a Visualization

Tool" in the MATLAB Graphics User Guide.

Light Properties

Purpose

Light properties

Creating Light Objects

Use light to create light objects.

Modifying Properties

You can set and query graphics object properties in two ways:

- "The Property Editor" is an interactive tool that enables you to see and change object property values.
- The set and get commands enable you to set and query the values of properties.

To change the default values of properties, see "Setting Default Property Values".

See "Core Graphics Objects" for general information about this type of object.

Light Property Descriptions

This section lists property names along with the type of values each accepts.

BeingDeleted

on | {off} Read Only

This object is being deleted. The BeingDeleted property provides a mechanism that you can use to determine if objects are in the process of being deleted. The MATLAB software sets the BeingDeleted property to on when the object's delete function callback is called (see the DeleteFcn property). It remains set to on while the delete function executes, after which the object no longer exists.

For example, an object's delete function might call other functions that act on a number of different objects. These functions may not need to perform actions on objects that are going to be deleted

and, therefore, can check the object's BeingDeleted property before acting.

```
BusyAction cancel | {queue}
```

Callback routine interruption. The BusyAction property enables you to control how MATLAB handles events that potentially interrupt executing callback routines. If there is a callback routine executing, callback routines invoked subsequently always attempt to interrupt it. If the Interruptible property of the object whose callback is executing is set to on (the default), then interruption occurs at the next point where the event queue is processed. If the Interruptible property is off, the BusyAction property (of the object owning the executing callback) determines how MATLAB handles the event. The choices are

- cancel Discard the event that attempted to execute a second callback routine.
- queue Queue the event that attempted to execute a second callback routine until the current callback finishes.

ButtonDownFcn

function handle

This property is not used on lights.

Children

handles

The empty matrix; light objects have no children.

Clipping

on | off

Clipping has no effect on light objects.

Color

ColorSpec

Light Properties

Color of light. This property defines the color of the light emanating from the light object. Define it as a three-element RGB vector or one of the MATLAB predefined names. See the ColorSpec reference page for more information.

CreateFcn

function handle, cell array containing function handle and additional arguments, or string (not recommended)

Callback function executed during object creation. A callback function that executes when MATLAB creates a light object. You must define this property as a default value for lights or in a call to the light function to create a new light object. For example, the following statement:

```
set(0, 'DefaultLightCreateFcn',@light_create)
```

defines a default value for the line CreateFcn property on the root level that sets the current figure colormap to gray and uses a reddish light color whenever you create a light object.

```
function light_create(src,evnt)
% src - the object that is the source of the event
% evnt - empty for this property
  set(src,'Color',[.9 .2 .2])
  set(gcbf,'Colormap',gray)
end
```

MATLAB executes this function after setting all light properties. Setting this property on an existing light object has no effect. The function must define at least two input arguments (handle of light object created and an event structure, which is empty for this property).

The handle of the object whose CreateFcn is being executed is passed by MATLAB as the first argument to the callback function and is also accessible through the root CallbackObject property, which you can query using gcbo.

See "Function Handle Callbacks" for information on how to use function handles to define the callback function.

DeleteFcn

function handle, cell array containing function handle and additional arguments, or string (not recommended

Delete light callback function. A callback function that executes when you delete the light object (for example, when you issue a delete command or clear the axes cla or figure clf). For example, the following function displays object property data before the object is deleted.

```
function delete_fcn(src,evnt)
% src - the object that is the source of the event
% evnt - empty for this property
  obj_tp = get(src,'Type');
  disp([obj_tp, ' object deleted'])
  disp('Its user data is:')
  disp(get(src,'UserData'))
end
```

MATLAB executes the function before deleting the object's properties so these values are available to the callback function. The function must define at least two input arguments (handle of object being deleted and an event structure, which is empty for this property).

The handle of the object whose DeleteFcn is being executed is passed by MATLAB as the first argument to the callback function and is also accessible through the root CallbackObject property, which you can query using gcbo.

See "Function Handle Callbacks" for information on how to use function handles to define the callback function.

```
HandleVisibility
{on} | callback | off
```

Light Properties

Control access to object's handle by command-line users and GUIs. This property determines when an object's handle is visible in its parent's list of children. HandleVisibility is useful for preventing command-line users from accidentally drawing into or deleting a figure that contains only user interface devices (such as a dialog box).

Handles are always visible when HandleVisibility is on.

Setting HandleVisibility to callback causes handles to be visible from within callback routines or functions invoked by callback routines, but not from within functions invoked from the command line. This provides a means to protect GUIs from command-line users, while allowing callback routines to have complete access to object handles.

Setting HandleVisibility to off makes handles invisible at all times. This may be necessary when a callback routine invokes a function that might potentially damage the GUI (such as evaluating a user-typed string), and so temporarily hides its own handles during the execution of that function.

When a handle is not visible in its parent's list of children, it cannot be returned by functions that obtain handles by searching the object hierarchy or querying handle properties. This includes get, findobj, gca, gcf, gco, newplot, cla, clf, and close.

When a handle's visibility is restricted using callback or off, the object's handle does not appear in its parent's Children property, figures do not appear in the root's CurrentFigure property, objects do not appear in the root's CallbackObject property or in the figure's CurrentObject property, and axes do not appear in their parent's CurrentAxes property.

You can set the root ShowHiddenHandles property to on to make all handles visible regardless of their HandleVisibility

settings (this does not affect the values of the HandleVisibility properties).

Handles that are hidden are still valid. If you know an object's handle, you can set and get its properties, and pass it to any function that operates on handles.

HitTest

{on} | off

This property is not used by light objects.

Interruptible

{on} | off

Callback routine interruption mode. Light object callback routines defined for the DeleteFcn property are not affected by the Interruptible property.

Parent

handle of parent axes

Parent of light object. This property contains the handle of the light object's parent. The parent of a light object is the axes object that contains it.

Note that light objects cannot be parented to hggroup or hgtransform objects.

See "Objects That Can Contain Other Objects" for more information on parenting graphics objects.

Position

[x,y,z] in axes data units

Location of light object. This property specifies a vector defining the location of the light object. The vector is defined from the origin to the specified *x*-, *y*-, and *z*-coordinates. The placement of the light depends on the setting of the Style property:

Light Properties

- If the Style property is set to local, Position specifies the actual location of the light (which is then a point source that radiates from the location in all directions).
- If the Style property is set to infinite, Position specifies the direction from which the light shines in parallel rays.

Selected

on | off

This property is not used by light objects.

SelectionHighlight {on} | off

This property is not used by light objects.

Style

```
{infinite} | local
```

Parallel or divergent light source. This property determines whether MATLAB places the light object at infinity, in which case the light rays are parallel, or at the location specified by the Position property, in which case the light rays diverge in all directions. See the Position property.

Tag

string

User-specified object label. The Tag property provides a means to identify graphics objects with a user-specified label. This is particularly useful when you are constructing interactive graphics programs that would otherwise need to define object handles as global variables or pass them as arguments between callback routines. You can define Tag as any string.

Type

string (read only)

Type of graphics object. This property contains a string that identifies the class of graphics object. For light objects, Type is always 'light'.

UIContextMenu

handle of a uicontextmenu object

This property is not used by light objects.

UserData

matrix

User-specified data. This property can be any data you want to associate with the light object. The light does not use this property, but you can access it using set and get.

Visible

{on} | off

Light visibility. While light objects themselves are not visible, you can see the light on patch and surface objects. When you set Visible to off, the light emanating from the source is not visible. There must be at least one light object in the axes whose Visible property is on for any lighting features to be enabled (including the axes AmbientLightColor and patch and surface AmbientStrength).

See Also light

lightangle

Purpose

Create or position light object in spherical coordinates

Syntax

```
lightangle(az,el)
light_handle = lightangle(az,el)
lightangle(light_handle,az,el)
[az,el] = lightangle(light_handle)
```

Description

lightangle(az,el) creates a light at the position specified by azimuth and elevation. az is the azimuthal (horizontal) rotation and el is the vertical elevation (both in degrees). The interpretation of azimuth and elevation is the same as that of the view command.

light_handle = lightangle(az,el) creates a light and returns the
handle of the light in light handle.

lightangle(light_handle,az,el) sets the position of the light specified by light handle.

[az,el] = lightangle(light_handle) returns the azimuth and elevation of the light specified by light_handle.

Remarks

By default, when a light is created, its style is infinite. If the light handle passed in to lightangle refers to a local light, the distance between the light and the camera target is preserved as the position is changed.

Examples

```
surf(peaks)
axis vis3d
h = light;
for az = -50:10:50
  lightangle(h,az,30)
  drawnow
end
```

See Also

light, camlight, view

"Lighting as a Visualization Tool" for more information about lighting

"Lighting" on page 1-111 for related functions

Purpose Specify lighting algorithm

Syntax lighting flat

lighting gouraud lighting phong lighting none

Description

lighting selects the algorithm used to calculate the effects of light objects on all surface and patch objects in the current axes. In order for the lighting command to have any effects, however, you must create a lighting object by using the light function.

lighting flat produces uniform lighting across each of the faces of the object. Select this method to view faceted objects.

lighting gouraud calculates the vertex normals and interpolates linearly across the faces. Select this method to view curved surfaces.

lighting phong interpolates the vertex normals across each face and calculates the reflectance at each pixel. Select this choice to view curved surfaces. Phong lighting generally produces better results than Gouraud lighting, but it takes longer to render.

lighting none turns off lighting.

Remarks

The surf, mesh, pcolor, fill, fill3, surface, and patch functions create graphics objects that are affected by light sources. The lighting command sets the FaceLighting and EdgeLighting properties of surfaces and patches appropriately for the graphics object.

See Also

fill, fill3, light, material, mesh, patch, pcolor, shading, surface "Lighting as a Visualization Tool" for more information about lighting "Lighting" on page 1-111 for related functions

lin2mu

Purpose Convert linear audio signal to mu-law

Syntax mu = lin2mu(y)

Description mu = lin2mu(y) converts linear audio signal amplitudes in the range

1 Y 1 to mu-law encoded "flints" in the range 0 u 255.

See Also auwrite, mu2lin

Purpose

Create line object

Syntax

```
line
line(X,Y)
line(X,Y,Z)
line(X,Y,Z,'PropertyName',propertyvalue,...)
line('XData',x,'YData',y,'ZData',z,...)
h = line(...)
```

Properties

For a list of properties, see Line Properties.

Description

line creates a line object in the current axes with default values $x = [0 \ 1]$ and $y = [0 \ 1]$. You can specify the color, width, line style, and marker type, as well as other characteristics.

The line function has two forms:

 Automatic color and line style cycling. When you specify matrix coordinate data using the informal syntax (i.e., the first three arguments are interpreted as the coordinates),

```
line(X,Y,Z)
```

MATLAB cycles through the axes ColorOrder and LineStyleOrder property values the way the plot function does. However, unlike plot, line does not call the newplot function.

• Purely low-level behavior. When you call line with only property name/property value pairs,

```
line('XData',x,'YData',y,'ZData',z)
```

MATLAB draws a line object in the current axes using the default line color (see the colordef function for information on color defaults). Note that you cannot specify matrix coordinate data with the low-level form of the line function.

line (X,Y) adds the line defined in vectors X and Y to the current axes. If X and Y are matrices of the same size, line draws one line per column.

line(X,Y,Z) creates lines in three-dimensional coordinates.

line(X,Y,Z,'*PropertyName*',propertyvalue,...) creates a line using the values for the property name/property value pairs specified and default values for all other properties. For a description of the properties, see Line Properties.

See the LineStyle and Marker properties for a list of supported values.

line ('XData',x,'YData',y,'ZData',z,...) creates a line in the current axes using the property values defined as arguments. This is the low-level form of the line function, which does not accept matrix coordinate data as the other informal forms described above.

h = line(...) returns a column vector of handles corresponding to each line object the function creates.

Remarks

In its informal form, the line function interprets the first three arguments (two for 2-D) as the X, Y, and Z coordinate data, allowing you to omit the property names. You must specify all other properties as name/value pairs. For example,

```
line(X,Y,Z,'Color','r','LineWidth',4)
```

The low-level form of the line function can have arguments that are only property name/property value pairs. For example,

```
line('XData',x,'YData',y,'ZData',z,'Color','r','LineWidth',4)
```

Line properties control various aspects of the line object and are described in Line Properties. You can also set and query property values after creating the line using set and get.

You can specify properties as property name/property value pairs, structure arrays, and cell arrays (see the set and get reference pages for examples of how to specify these data types).

Unlike high-level functions such as plot, line does not respect the settings of the figure and axes NextPlot properties. It simply adds line objects to the current axes. However, axes properties that are under automatic control, such as the axis limits, can change to accommodate the line within the current axes.

Connecting the dots

The coordinate data is interpreted as vectors of corresponding x, y, and z values:

```
X = [x(1) \ x(2) \ x(3)...x(n)]

Y = [y(1) \ x(2) \ y(3)...y(n)]

Z = [z(1) \ z(2) \ x(3)...z(n)]
```

where a point is determined by the corresponding vector elements:

```
p1(x(i),y(i),z(i))
```

For example, to draw a line from the point located at x = .3 and y = .4 and z = 1 to the point located at x = .7 and y = .9 and z = 1, use the following data:

```
axis([0 1 0 1])
line([.3 .7],[.4 .9],[1 1],'Marker','.','LineStyle','-')
```

Examples

This example uses the line function to add a shadow to plotted data. First, plot some data and save the line's handle:


```
t = 0:pi/20:2*pi;
hline1 = plot(t,sin(t),'k');
```

Next, add a shadow by offsetting the *x*-coordinates. Make the shadow line light gray and wider than the default LineWidth:

```
hline2 = line(t+.06,sin(t),'LineWidth',4,'Color',[.8 .8 .8]);
```

Finally, pull the first line to the front:

```
set(gca, 'Children',[hline1 hline2])
```



Drawing Lines Interactively

You can use the ginput function to select points from a figure. For example:

```
axis([0 1 0 1])
for n = 1:5
  [x(n),y(n)] = ginput(1);
end
line(x,y)
```

The for loop enables you to select five points and build the x and y arrays. Because line requires arrays of corresponding x and y coordinates, you can just pass these arrays to the line function.

Drawing with mouse motion

You can use the axes CurrentPoint property and the figure WindowButtonDownFcn and WindowButtonMotionFcn properties to select a point with a mouse click and draw a line to another point by dragging the mouse, like a simple drawing program. The following example illustrates a few useful techniques for doing this type of interactive drawing.

Click to view in editor — This example enables you to click and drag the cursor to draw lines.

Click to run example — Click the left mouse button in the axes and move the cursor, left-click to define the line end point, right-click to end drawing mode.

Input Argument Dimensions — Informal Form

This statement reuses the one-column matrix specified for ZData to produce two lines, each having four points.

```
line(rand(4,2), rand(4,2), rand(4,1))
```

If all the data has the same number of columns and one row each, MATLAB transposes the matrices to produce data for plotting. For example,

```
line(rand(1,4),rand(1,4),rand(1,4))
is changed to
line(rand(4,1),rand(4,1),rand(4,1))
```

This also applies to the case when just one or two matrices have one row. For example, the statement

```
line(rand(2,4),rand(2,4),rand(1,4))
is equivalent to
line(rand(4,2),rand(4,2),rand(4,1))
```

Setting Default Properties

You can set default line properties on the axes, figure, and root object levels:

```
set(0, 'DefaultLinePropertyName',PropertyValue,...)
set(gcf, 'DefaultLinePropertyName',PropertyValue,...)
set(gca, 'DefaultLinePropertyName',PropertyValue,...)
```

Where *PropertyName* is the name of the line property and PropertyValue is the value you are specifying. Use set and get to access line properties.

See Also

annotationaxes, newplot, plot, plot3

Line Properties for property descriptions

"Object Creation" on page 1-104 for related functions

Purpose

Line properties

Creating Line Objects

Use line to create line objects.

Modifying Properties

You can set and query graphics object properties in two ways:

- "The Property Editor" is an interactive tool that enables you to see and change object property values.
- The set and get commands enable you to set and query the values of properties.

To change the default values of properties, see "Setting Default Property Values".

See Core Graphics Objects for general information about this type of object.

Line Property Descriptions

This section lists property names along with the type of values each accepts. Curly braces {} enclose default values.

Annotation

hg. Annotation object Read Only

Control the display of line objects in legends. The Annotation property enables you to specify whether this line object is represented in a figure legend.

Querying the Annotation property returns the handle of an hg.Annotation object. The hg.Annotation object has a property called LegendInformation, which contains an hg.LegendEntry object.

Line Properties

Once you have obtained the hg.LegendEntry object, you can set its IconDisplayStyle property to control whether the line object is displayed in a figure legend:

IconDisplayStyle Value	Purpose
on	Represent this line object in a legend (default)
off	Do not include this line object in a legend
children	Same as on because line objects do not have children

Setting the IconDisplayStyle property

These commands set the IconDisplayStyle of a graphics object with handle hobj to off:

```
hAnnotation = get(hobj, 'Annotation');
hLegendEntry = get(hAnnotation', 'LegendInformation');
set(hLegendEntry, 'IconDisplayStyle', 'off')
```

Using the IconDisplayStyle property

See "Controlling Legends" for more information and examples.

BeingDeleted

```
on | {off} Read Only
```

This object is being deleted. Mechanism to use to determine if objects are in the process of being deleted. The MATLAB software sets the BeingDeleted property to on when the object's delete function callback is called (see the DeleteFcn property). It remains set to on while the delete function executes, after which the object no longer exists.

For example, an object's delete function might call other functions that act on a number of different objects. These functions may not need to perform actions on objects that are going to be deleted and, therefore, can check the object's BeingDeleted property before acting.

BusyAction cancel | {queue}

Callback routine interruption. Controls how MATLAB handles events that potentially interrupt executing callback routines. If there is a callback routine executing, callback routines invoked subsequently always attempt to interrupt it. If the Interruptible property of the object whose callback is executing is set to on (the default), then interruption occurs at the next point where the event queue is processed. If the Interruptible property is off, the BusyAction property (of the object owning the executing callback) determines how MATLAB handles the event. The choices are:

- cancel Discard the event that attempted to execute a second callback routine.
- queue (the default) Queue the event that attempted to execute a second callback routine until the current callback finishes.

ButtonDownFcn

function handle, cell array containing function handle and additional arguments, or string (not recommended)

Button press callback function. A callback function that executes whenever you press a mouse button while the pointer is over the line object.

See the figure's SelectionType property to determine if modifier keys were also pressed.

Set this property to a function handle that references the callback. The function must define at least two input arguments (handle of line associated with the button down event and an event structure, which is empty for this property).

The following example shows how to access the callback object's handle as well as the handle of the figure that contains the object from the callback function.

```
function button down(src,evnt)
% src - the object that is the source of the event
% evnt - empty for this property
   sel typ = get(gcbf, 'SelectionType')
   switch sel typ
      case 'normal'
         disp('User clicked left-mouse button')
         set(src,'Selected','on')
      case 'extend'
         disp('User did a shift-click')
         set(src,'Selected','on')
      case 'alt'
         disp('User did a control-click')
         set(src,'Selected','on')
         set(src, 'SelectionHighlight', 'off')
   end
end
```

Suppose h is the handle of a line object and this button_down function is on your MATLAB path. The following statement assigns the button down function to the ButtonDownFcn property:

```
set(h, 'ButtonDownFcn',@button_down)
```

See "Function Handle Callbacks" for information on how to use function handles to define the callback function.

Children

vector of handles

The empty matrix; line objects have no children.

Clipping

{on} | off

Clipping mode. MATLAB clips lines to the axes plot box by default. If you set Clipping to off, lines are displayed outside the axes plot box. This can occur if you create a line, set hold to on, freeze axis scaling (set axis to manual), and then create a longer line.

Color

ColorSpec

Line color. A three-element RGB vector, or one of the MATLAB predefined names, specifying the line color. See the ColorSpec reference page for more information on specifying color.

CreateFcn

function handle, cell array containing function handle and additional arguments, or string (not recommended)

Callback function executed during object creation. A callback function that executes when MATLAB creates a line object. You must define this property as a default value for lines or in a call to the line function to create a new line object.

For example, the statement:

```
set(0, 'DefaultLineCreateFcn',@line_create)
```

defines a default value for the line <code>CreateFcn</code> property on the root level that sets the axes <code>LineStyleOrder</code> whenever you create a line object. The following callback function must be on your MATLAB path when you execute the above statement.

```
function line_create(src,evnt)
% src - the object that is the source of the event
% evnt - empty for this property
```

```
axh = get(src,'Parent');
set(axh,'LineStyleOrder','-.|--')
end
```

MATLAB executes this function after setting all line properties. Setting this property on an existing line object has no effect. The function must define at least two input arguments (handle of line object created and an event structure, which is empty for this property).

The handle of the object whose CreateFcn is being executed is passed by MATLAB as the first argument to the callback function and is also accessible through the root CallbackObject property, which you can query using gcbo.

See "Function Handle Callbacks" for information on how to use function handles to define the callback function.

DeleteFcn

function handle, cell array containing function handle and additional arguments, or string (not recommended)

Delete line callback function. A callback function that executes when you delete the line object (for example, when you issue a delete command or clear the axes cla or figure clf).

For example, the following function displays object property data before the object is deleted.

```
function delete_fcn(src,evnt)
% src - the object that is the source of the event
% evnt - empty for this property
  obj_tp = get(src,'Type');
  disp([obj_tp, ' object deleted'])
  disp('Its user data is:')
  disp(get(src,'UserData'))
end
```

MATLAB executes the function before deleting the object's properties so these values are available to the callback function. The function must define at least two input arguments (handle of line object being deleted and an event structure, which is empty for this property).

The handle of the object whose DeleteFcn is being executed is passed by MATLAB as the first argument to the callback function and is also accessible through the root CallbackObject property, which you can guery using gcbo.

See "Function Handle Callbacks" for information on how to use function handles to define the callback function.

DisplayName

string (default is empty string)

String used by legend for this line object. The legend function uses the string defined by the DisplayName property to label this line object in the legend.

- If you specify string arguments with the legend function, DisplayName is set to this line object's corresponding string and that string is used for the legend.
- If DisplayName is empty, legend creates a string of the form, ['data' n], where n is the number assigned to the object based on its location in the list of legend entries. However, legend does not set DisplayName to this string.
- If you edit the string directly in an existing legend, DisplayName is set to the edited string.
- If you specify a string for the DisplayName property and create the legend using the figure toolbar, then MATLAB uses the string defined by DisplayName.
- To add programmatically a legend that uses the DisplayName string, call legend with the toggle or show option.

Line Properties

See "Controlling Legends" for more examples.

The following code shows how to use the DisplayName property from the command line or in a file.

```
t = 0:.1:2*pi;
a(:,1)=sin(t); a(:,2)=cos(t);
h = plot(a);
set(h,{'DisplayName'},{'Sine','Cosine'}')
legend show
```

EraseMode

```
{normal} | none | xor | background
```

Erase mode. Controls the technique MATLAB uses to draw and erase line objects. Alternative erase modes are useful for creating animated sequences, where control of the way individual objects are redrawn is necessary to improve performance and obtain the desired effect.

- normal (the default) Redraw the affected region of the display, performing the three-dimensional analysis necessary to ensure that all objects are rendered correctly. This mode produces the most accurate picture, but is the slowest. The other modes are faster, but do not perform a complete redraw and are therefore less accurate.
- none Do not erase the line when it is moved or destroyed.
 While the object is still visible on the screen after erasing with EraseMode none, you cannot print it, because MATLAB stores no information about its former location.
- xor Draw and erase the line by performing an exclusive OR (XOR) with the color of the screen beneath it. This mode does not damage the color of the objects beneath the line. However, the line's color depends on the color of whatever is beneath it on the display.
- background Erase the line by drawing it in the axes background Color, or the figure background Color if the axes

Color is set to none. This damages objects that are behind the erased line, but lines are always properly colored.

Printing with Nonnormal Erase Modes

MATLAB always prints figures as if the EraseMode of all objects is normal. This means graphics objects created with EraseMode set to none, xor, or background can look different on screen than on paper. On screen, MATLAB may mathematically combine layers of colors (for example, performing an XOR on a pixel color with that of the pixel behind it) and ignore three-dimensional sorting to obtain greater rendering speed. However, these techniques are not applied to the printed output.

You can use the MATLAB getframe command or other screen capture application to create an image of a figure containing nonnormal mode objects.

```
HandleVisibility
{on} | callback | off
```

Control access to object's handle by command-line users and GUIs. This property determines when an object's handle is visible in its parent's list of children. HandleVisibility is useful for preventing command-line users from accidentally drawing into or deleting a figure that contains only user interface devices (such as a dialog box).

Handles are always visible when HandleVisibility is on.

Setting HandleVisibility to callback causes handles to be visible from within callback routines or functions invoked by callback routines, but not from within functions invoked from the command line. This provides a means to protect GUIs from command-line users, while allowing callback routines to have complete access to object handles.

Line Properties

Setting HandleVisibility to off makes handles invisible at all times. This may be necessary when a callback routine invokes a function that might potentially damage the GUI (such as evaluating a user-typed string), and so temporarily hides its own handles during the execution of that function.

When a handle is not visible in its parent's list of children, it cannot be returned by functions that obtain handles by searching the object hierarchy or querying handle properties. This includes get, findobj, gca, gcf, gco, newplot, cla, clf, and close.

When a handle's visibility is restricted using callback or off, the object's handle does not appear in its parent's Children property, figures do not appear in the root's CurrentFigure property, objects do not appear in the root's CallbackObject property or in the figure's CurrentObject property, and axes do not appear in their parent's CurrentAxes property.

You can set the root ShowHiddenHandles property to on to make all handles visible regardless of their HandleVisibility settings (this does not affect the values of the HandleVisibility properties).

Handles that are hidden are still valid. If you know an object's handle, you can set and get its properties, and pass it to any function that operates on handles.

```
HitTest
{on} | off
```

Selectable by mouse click. Determines if the line can become the current object (as returned by the gco command and the figure CurrentObject property) as a result of a mouse click on the line. If HitTest is off, clicking the line selects the object below it (which may be the axes containing it).

```
Interruptible
{on} | off
```

Callback routine interruption mode. Controls whether a line callback routine can be interrupted by subsequently invoked callback routines. Only callback routines defined for the ButtonDownFcn are affected by the Interruptible property. MATLAB checks for events that can interrupt a callback routine only when it encounters a drawnow, figure, getframe, or pause command in the routine.

LineStyle

Line style. Specifies the line style. Supported line styles are shown in the following table.

Symbol	Line Style
1 1	Solid line (default)
11	Dashed line
1:1	Dotted line
1 .1	Dash-dot line
'none'	No line

Use LineStyle none when you want to place a marker at each point but do not want the points connected with a line (see the Marker property).

LineWidth

width in points

The width of the line object. Specify this value in points (1 point = $\frac{1}{79}$ inch). The default value is 0.5 points.

Marker

character (see table)

Marker symbol. Specifies marks displayed at data points. You can set values for the Marker property independently from

Line Properties

the LineStyle property. Supported markers are shown in the following table.

Marker Specifier	Description
'+'	Plus sign
0'	Circle
1 * 1	Asterisk
1.1	Point
' X '	Cross
'square' or 's'	Square
'diamond' or 'd'	Diamond
1 A I	Upward-pointing triangle
' V '	Downward-pointing triangle
'>'	Right-pointing triangle
'<'	Left-pointing triangle
'pentagram' or 'p'	Five-pointed star (pentagram)
'hexagram' or 'h'	Six-pointed star (hexagram)
'none'	No marker (default)

MarkerEdgeColor

ColorSpec | none | {auto}

Marker edge color. Color of the marker or the edge color for filled markers (circle, square, diamond, pentagram, hexagram, and the four triangles). ColorSpec defines the color to use. none specifies no color, which makes nonfilled markers invisible. auto sets MarkerEdgeColor to the same color as the line's Color property.

MarkerFaceColor

ColorSpec | {none} | auto

Marker face color. Fill color for markers that are closed shapes (circle, square, diamond, pentagram, hexagram, and the four triangles). ColorSpec defines the color to use. none makes the interior of the marker transparent, allowing the background to show through. auto sets the fill color to the axes color, or the figure color, if the axes Color property is set to none (which is the factory default for axes).

MarkerSize

size in points

Marker size. A scalar specifying the size of the marker, in points. The default value is six points (1 point = $^{1}/_{72}$ inch). MATLAB draws the point marker (specified by the '.' symbol) at one-third the specified size.

Parent

handle of axes, hggroup, or hgtransform

Parent of line object. Handle of the line object's parent. The parent of a line object is the axes that contains it. You can reparent line objects to other axes, hggroup, or hgtransform objects.

See "Objects That Can Contain Other Objects" for more information on parenting graphics objects.

Selected

on | off

Is object selected? When this property is on. MATLAB displays selection handles if the SelectionHighlight property is also on. You can, for example, define the ButtonDownFcn to set this property, allowing users to select the object with the mouse.

SelectionHighlight

{on} | off

Objects are highlighted when selected. When the Selected property is on, MATLAB indicates the selected state by drawing

Line Properties

handles at each vertex. When SelectionHighlight is off, MATLAB does not draw the handles.

Tag

string

User-specified object label. Identify graphics objects with a user-specified label. This is particularly useful when you are constructing interactive graphics programs that would otherwise need to define object handles as global variables or pass them as arguments between callback routines. You can define Tag as any string.

Type

string (read only)

Class of graphics object. For line objects, Type is always the string 'line'.

UIContextMenu

handle of a uicontextmenu object

Associate a context menu with the line. Assign this property the handle of a uicontextmenu object created in the same figure as the line. Use the uicontextmenu function to create the context menu. MATLAB displays the context menu whenever you right-click over the line.

UserData

matrix

User-specified data. Any data you want to associate with the line object. MATLAB does not use this data, but you can access it using the set and get commands.

Visible

{on} | off

Line visibility. By default, all lines are visible. When set to off, the line is not visible, but still exists, and you can get and set its properties.

XData

vector of coordinates

X-coordinates. Vector of *x*-coordinates defining the line. YData and ZData must be the same length and have the same number of rows. (See "Examples" on page 2-2309.)

YData

vector of coordinates

Y-coordinates. Vector of *y*-coordinates defining the line. XData and ZData must be the same length and have the same number of rows.

ZData

vector of coordinates

Z-coordinates. Vector of z-coordinates defining the line. XData and YData must have the same number of rows.

See Also line

Lineseries Properties

Purpose

Define lineseries properties

Modifying Properties

You can set and query graphics object properties using the set and get commands or with the property editor (propertyeditor).

See "Plot Objects" for more information on lineseries objects.

Note that you cannot define default properties for lineseries objects.

Lineseries Property Descriptions

This section lists property names along with the type of values each accepts. Curly braces {} enclose default values.

Annotation

hg. Annotation object Read Only

Control the display of lineseries objects in legends. The Annotation property enables you to specify whether this lineseries object is represented in a figure legend.

Querying the Annotation property returns the handle of an hg.Annotation object. The hg.Annotation object has a property called LegendInformation, which contains an hg.LegendEntry object.

Once you have obtained the hg.LegendEntry object, you can set its IconDisplayStyle property to control whether the lineseries object is displayed in a figure legend:

IconDisplayStyle Value	Purpose
on	Include the lineseries object in a legend as one entry, but not its children objects
off	Do not include the lineseries or its children in a legend (default)
children	Include only the children of the lineseries as separate entries in the legend

Setting the IconDisplayStyle Property

These commands set the IconDisplayStyle of a graphics object with handle hobj to children, which causes each child object to have an entry in the legend:

```
hAnnotation = get(hobj, 'Annotation');
hLegendEntry = get(hAnnotation, 'LegendInformation');
set(hLegendEntry, 'IconDisplayStyle', 'children')
```

Using the IconDisplayStyle Property

See "Controlling Legends" for more information and examples.

```
BeingDeleted on | {off} Read Only
```

This object is being deleted. The BeingDeleted property provides a mechanism that you can use to determine if objects are in the process of being deleted. MATLAB sets the BeingDeleted property to on when the object's delete function callback is called (see the DeleteFcn property). It remains set to on while the delete function executes, after which the object no longer exists.

For example, an object's delete function might call other functions that act on a number of different objects. These functions might not need to perform actions on objects if the objects are going to be deleted, and therefore, can check the object's BeingDeleted property before acting.

```
BusyAction cancel | {queue}
```

Callback routine interruption. The BusyAction property enables you to control how MATLAB handles events that potentially interrupt executing callbacks. If there is a callback function executing, callbacks invoked subsequently always attempt to interrupt it.

Lineseries Properties

If the Interruptible property of the object whose callback is executing is set to on (the default), then interruption occurs at the next point where the event queue is processed. If the Interruptible property is off, the BusyAction property (of the object owning the executing callback) determines how MATLAB handles the event. The choices are

- cancel Discard the event that attempted to execute a second callback routine.
- queue Queue the event that attempted to execute a second callback routine until the current callback finishes.

ButtonDownFcn

string or function handle

Button press callback function. A callback that executes whenever you press a mouse button while the pointer is over this object, but not over another graphics object.

See the figure's SelectionType property to determine if modifier keys were also pressed.

This property can be

- A string that is a valid MATLAB expression
- The name of a MATLAB file
- A function handle

Set this property to a function handle that references the callback. The expressions execute in the MATLAB workspace.

See "Function Handle Callbacks" for information on how to use function handles to define the callbacks.

Children

vector of handles

The empty matrix; line objects have no children.

Clipping

{on} | off

Clipping mode. MATLAB clips graphs to the axes plot box by default. If you set Clipping to off, portions of graphs can be displayed outside the axes plot box. This can occur if you create a plot object, set hold to on, freeze axis scaling (axis manual), and then create a larger plot object.

Color

ColorSpec

Color of the object. A three-element RGB vector or one of the MATLAB predefined names, specifying the object's color.

See the ColorSpec reference page for more information on specifying color.

CreateFcn

string or function handle

Callback routine executed during object creation. This property defines a callback that executes when MATLAB creates an object. You must specify the callback during the creation of the object. For example,

```
graphicfcn(y, 'CreateFcn',@CallbackFcn)
```

where <code>@CallbackFcn</code> is a function handle that references the callback function and <code>graphicfcn</code> is the plotting function which creates this object.

MATLAB executes this routine after setting all other object properties. Setting this property on an existing object has no effect.

The handle of the object whose CreateFcn is being executed is accessible only through the root CallbackObject property, which you can query using gcbo.

See "Function Handle Callbacks" for information on how to use function handles to define the callback function.

DeleteFcn

string or function handle

Callback executed during object deletion. A callback that executes when this object is deleted (e.g., this might happen when you issue a delete command on the object, its parent axes, or the figure containing it). MATLAB executes the callback before destroying the object's properties so the callback routine can query these values.

The handle of the object whose DeleteFcn is being executed is accessible only through the root CallbackObject property, which can be queried using gcbo.

See "Function Handle Callbacks" for information on how to use function handles to define the callback function.

See the BeingDeleted property for related information.

DisplayName

string (default is empty string)

String used by legend for this lineseries object. The legend function uses the string defined by the DisplayName property to label this lineseries object in the legend.

- If you specify string arguments with the legend function, DisplayName is set to this lineseries object's corresponding string and that string is used for the legend.
- If DisplayName is empty, legend creates a string of the form, ['data' n], where n is the number assigned to the object

based on its location in the list of legend entries. However, legend does not set DisplayName to this string.

- If you edit the string directly in an existing legend, DisplayName is set to the edited string.
- If you specify a string for the DisplayName property and create the legend using the figure toolbar, then MATLAB uses the string defined by DisplayName.
- To add programmatically a legend that uses the DisplayName string, call legend with the toggle or show option.

See "Controlling Legends" for more examples.

EraseMode

```
{normal} | none | xor | background
```

Erase mode. This property controls the technique MATLAB uses to draw and erase objects and their children. Alternative erase modes are useful for creating animated sequences, where control of the way individual objects are redrawn is necessary to improve performance and obtain the desired effect.

- normal Redraw the affected region of the display, performing
 the three-dimensional analysis necessary to ensure that all
 objects are rendered correctly. This mode produces the most
 accurate picture, but is the slowest. The other modes are faster,
 but do not perform a complete redraw and are therefore less
 accurate.
- none Do not erase objects when they are moved or destroyed.
 While the objects are still visible on the screen after erasing with EraseMode none, you cannot print these objects because MATLAB stores no information about their former locations.
- xor Draw and erase the object by performing an exclusive OR (XOR) with each pixel index of the screen behind it. Erasing the object does not damage the color of the objects behind it. However, the color of the erased object depends on the color of

the screen behind it and it is correctly colored only when it is over the axes background color (or the figure background color if the axes Color property is set to none). That is, it isn't erased correctly if there are objects behind it.

background — Erase the graphics objects by redrawing them
in the axes background color, (or the figure background color
if the axes Color property is set to none). This damages other
graphics objects that are behind the erased object, but the
erased object is always properly colored.

Printing with Nonnormal Erase Modes

MATLAB always prints figures as if the EraseMode of all objects is normal. This means graphics objects created with EraseMode set to none, xor, or background can look different on screen than on paper. On screen, MATLAB can mathematically combine layers of colors (e.g., performing an XOR on a pixel color with that of the pixel behind it) and ignore three-dimensional sorting to obtain greater rendering speed. However, these techniques are not applied to the printed output.

Set the axes background color with the axes Color property. Set the figure background color with the figure Color property.

You can use the MATLAB getframe command or other screen capture applications to create an image of a figure containing nonnormal mode objects.

```
HandleVisibility
     {on} | callback | off
```

Control access to object's handle by command-line users and GUIs. This property determines when an object's handle is visible in its parent's list of children. HandleVisibility is useful for preventing command-line users from accidentally accessing objects that you need to protect for some reason.

- on Handles are always visible when HandleVisibility is on.
- callback Setting HandleVisibility to callback causes
 handles to be visible from within callback routines or functions
 invoked by callback routines, but not from within functions
 invoked from the command line. This provides a means to
 protect GUIs from command-line users, while allowing callback
 routines to have access to object handles.
- off Setting HandleVisibility to off makes handles invisible at all times. This might be necessary when a callback invokes a function that might potentially damage the GUI (such as evaluating a user-typed string) and so temporarily hides its own handles during the execution of that function.

Functions Affected by Handle Visibility

When a handle is not visible in its parent's list of children, it cannot be returned by functions that obtain handles by searching the object hierarchy or querying handle properties. This includes get, findobj, gca, gcf, gco, newplot, cla, clf, and close.

Properties Affected by Handle Visibility

When a handle's visibility is restricted using callback or off, the object's handle does not appear in its parent's Children property, figures do not appear in the root's CurrentFigure property, objects do not appear in the root's CallbackObject property or in the figure's CurrentObject property, and axes do not appear in their parent's CurrentAxes property.

Overriding Handle Visibility

You can set the root ShowHiddenHandles property to on to make all handles visible regardless of their HandleVisibility settings (this does not affect the values of the HandleVisibility properties). See also findall.

Handle Validity

Handles that are hidden are still valid. If you know an object's handle, you can set and get its properties and pass it to any function that operates on handles.

Note If you change one data source property to a variable that contains data of a different dimension, you might cause the function to generate a warning and not render the graph until you have changed all data source properties to appropriate values.

HitTest

{on} | off

Selectable by mouse click. HitTest determines whether this object can become the current object (as returned by the gco command and the figure CurrentObject property) as a result of a mouse click on the objects that compose the area graph. If HitTest is off, clicking this object selects the object below it (which is usually the axes containing it).

Interruptible

{on} | off

Callback routine interruption mode. The Interruptible property controls whether an object's callback can be interrupted by callbacks invoked subsequently.

Only callbacks defined for the ButtonDownFcn property are affected by the Interruptible property. MATLAB checks for events that can interrupt a callback only when it encounters a drawnow, figure, getframe, or pause command in the routine. See the BusyAction property for related information.

Setting Interruptible to on allows any graphics object's callback to interrupt callback routines originating from a bar property. Note that MATLAB does not save the state of variables or the display (e.g., the handle returned by the gca or gcf command) when an interruption occurs.

LineStyle

Line style. This property specifies the line style of the object. Available line styles are shown in the following table.

Specifier String	Line Style
-	Solid line (default)
	Dashed line
:	Dotted line
	Dash-dot line
none	No line

You can use LineStyle none when you want to place a marker at each point but do not want the points connected with a line (see the Marker property).

LineWidth

scalar

The width of linear objects and edges of filled areas. Specify this value in points (1 point = $^{1}/_{72}$ inch). The default LineWidth is 0.5 points.

Marker

character (see table)

Marker symbol. The Marker property specifies the type of markers that are displayed at plot vertices. You can set values for the

Marker property independently from the LineStyle property. Supported markers include those shown in the following table.

Marker Specifier	Description
+	Plus sign
0	Circle
*	Asterisk
	Point
Х	Cross
S	Square
d	Diamond
^	Upward-pointing triangle
V	Downward-pointing triangle
>	Right-pointing triangle
<	Left-pointing triangle
р	Five-pointed star (pentagram)
h	Six-pointed star (hexagram)
none	No marker (default)

MarkerEdgeColor

ColorSpec | none | {auto}

Marker edge color. The color of the marker or the edge color for filled markers (circle, square, diamond, pentagram, hexagram, and the four triangles). ColorSpec defines the color to use. none specifies no color, which makes nonfilled markers invisible. auto sets MarkerEdgeColor to the same color as the Color property.

MarkerFaceColor

ColorSpec | {none} | auto

Marker face color. The fill color for markers that are closed shapes (circle, square, diamond, pentagram, hexagram, and the four triangles). ColorSpec defines the color to use. none makes the interior of the marker transparent, allowing the background to show through. auto sets the fill color to the axes color, or to the figure color if the axes Color property is set to none (which is the factory default for axes objects).

MarkerSize

size in points

Marker size. A scalar specifying the size of the marker in points. The default value for MarkerSize is 6 points (1 point = 1/72 inch). Note that MATLAB draws the point marker (specified by the '.' symbol) at one-third the specified size.

Parent

handle of parent axes, hggroup, or hgtransform

Parent of this object. This property contains the handle of the object's parent. The parent is normally the axes, hggroup, or hgtransform object that contains the object.

See "Objects That Can Contain Other Objects" for more information on parenting graphics objects.

Selected

on | {off}

Is object selected? When you set this property to on, MATLAB displays selection "handles" at the corners and midpoints if the SelectionHighlight property is also on (the default). You can, for example, define the ButtonDownFcn callback to set this property to on, thereby indicating that this particular object is selected. This property is also set to on when an object is manually selected in plot edit mode.

```
SelectionHighlight
{on} | off
```

Objects are highlighted when selected. When the Selected property is on, MATLAB indicates the selected state by drawing four edge handles and four corner handles. When SelectionHighlight is off, MATLAB does not draw the handles except when in plot edit mode and objects are selected manually.

Tag

string

User-specified object label. The Tag property provides a means to identify graphics objects with a user-specified label. This is particularly useful when you are constructing interactive graphics programs that would otherwise need to define object handles as global variables or pass them as arguments between callbacks. You can define Tag as any string.

For example, you might create an areaseries object and set the Tag property.

```
t = area(Y, 'Tag', 'area1')
```

When you want to access objects of a given type, you can use findobj to find the object's handle. The following statement changes the FaceColor property of the object whose Tag is area1.

```
set(findobj('Tag', 'area1'), 'FaceColor', 'red')
```

Type

string (read only)

Class of graphics object. For lineseries objects, Type is always the string line.

UIContextMenu

handle of a uicontextmenu object

Associate a context menu with this object. Assign this property the handle of a uicontextmenu object created in the object's parent figure. Use the uicontextmenu function to create the

context menu. MATLAB displays the context menu whenever you right-click over the object.

UserData

array

User-specified data. This property can be any data you want to associate with this object (including cell arrays and structures). The object does not set values for this property, but you can access it using the set and get functions.

Visible

{on} | off

Visibility of this object and its children. By default, a new object's visibility is on. This means all children of the object are visible unless the child object's Visible property is set to off. Setting an object's Visible property to off prevents the object from being displayed. However, the object still exists and you can set and query its properties.

XData

vector or matrix

The x-axis values for a graph. The x-axis values for graphs are specified by the X input argument. If XData is a vector, length(XData) must equal length(YData) and must be monotonic. If XData is a matrix, size(XData) must equal size(YData) and each column must be monotonic.

You can use XData to define meaningful coordinates for an underlying surface whose topography is being mapped. See "Changing the Offset of a Contour" for more information.

XDataMode

{auto} | manual

Use automatic or user-specified x-axis values. If you specify XData (by setting the XData property or specifying the x input

argument), MATLAB sets this property to manual and uses the specified values to label the *x*-axis.

If you set XDataMode to auto after having specified XData, MATLAB resets the *x*-axis ticks to 1:size(YData,1) or to the column indices of the ZData, overwriting any previous values for XData.

XDataSource

string (MATLAB variable)

Link XData to MATLAB variable. Set this property to a MATLAB variable that is evaluated in the base workspace to generate the XData.

MATLAB reevaluates this property only when you set it. Therefore, a change to workspace variables appearing in an expression does not change XData.

You can use the refreshdata function to force an update of the object's data. refreshdata also enables you to specify that the data source variable be evaluated in the workspace of a function from which you call refreshdata.

See the refreshdata reference page for more information.

Note If you change one data source property to a variable that contains data of a different dimension, you might cause the function to generate a warning and not render the graph until you have changed all data source properties to appropriate values.

YData

vector or matrix of coordinates

Y-coordinates. A vector of *y-*coordinates defining the values along the *y-*axis for the graph. XData and ZData must be the same length and have the same number of rows.

YDataSource

string (MATLAB variable)

Link YData to MATLAB variable. Set this property to a MATLAB variable that is evaluated in the base workspace to generate the YData.

MATLAB reevaluates this property only when you set it. Therefore, a change to workspace variables appearing in an expression does not change YData.

You can use the refreshdata function to force an update of the object's data. refreshdata also enables you to specify that the data source variable be evaluated in the workspace of a function from which you call refreshdata.

See the refreshdata reference page for more information.

Note If you change one data source property to a variable that contains data of a different dimension, you might cause the function to generate a warning and not render the graph until you have changed all data source properties to appropriate values.

ZData

vector of coordinates

Z-coordinates. A vector defining the z-coordinates for the graph. XData and YData must be the same length and have the same number of rows.

ZDataSource

string (MATLAB variable)

Link ZData to MATLAB variable. Set this property to a MATLAB variable that is evaluated in the base workspace to generate the ZData.

MATLAB reevaluates this property only when you set it. Therefore, a change to workspace variables appearing in an expression does not change ZData.

You can use the refreshdata function to force an update of the object's data. refreshdata also enables you to specify that the data source variable be evaluated in the workspace of a function from which you call refreshdata.

See the refreshdata reference page for more information.

Note If you change one data source property to a variable that contains data of a different dimension, you might cause the function to generate a warning and not render the graph until you have changed all data source properties to appropriate values.

Purpose

Line specification string syntax

GUI Alternative To modify the style, width, and color of lines on a graph, use the

Property Editor, one of the plotting tools . For details, see The Property Editor in the MATLAB Graphics documentation.

Description

This page describes how to specify the properties of lines used for plotting. MATLAB graphics give you control over these visual characteristics:

- Line style
- Line width
- Color
- Marker type
- Marker size
- Marker face and edge coloring (for filled markers)

You indicate the line styles, marker types, and colors you want to display using *string specifiers*, detailed in the following tables:

Line Style Specifiers

Specifier	Line Style
-	Solid line (default)
	Dashed line
:	Dotted line
	Dash-dot line

Marker Specifiers

Specifier	Marker Type
+	Plus sign
0	Circle
*	Asterisk
	Point (see note below)
X	Cross
'square' or s	Square
'diamond' or d	Diamond
^	Upward-pointing triangle
V	Downward-pointing triangle
>	Right-pointing triangle
<	Left-pointing triangle
'pentagram' or p	Five-pointed star (pentagram)
'hexagram' or h	Six-pointed star (hexagram)

Note The point (.) marker type does not change size when the specified value is less than 5.

Color Specifiers

Specifier	Color
r	Red
g	Green
b	Blue
С	Cyan

Specifier	Color
m	Magenta
У	Yellow
k	Black
W	White

All high-level plotting functions (except for the ez... family of function-plotting functions) accept a LineSpec argument that defines three components used to specify lines:

- Line style
- · Marker symbol
- Color

For example:

plots y versus x using a dash-dot line (-.), places circular markers (0) at the data points, and colors both line and marker red (r). Specify the components (in any order) as a quoted string after the data arguments. Note that linespecs are single strings, not property-value pairs.

Plotting Data Points with No Line

If you specify a marker, but not a line style, only the markers are plotted. For example:

Related Properties

When using the plot and plot3 functions, you can also specify other characteristics of lines using graphics properties:

• LineWidth — Specifies the width (in points) of the line.


- MarkerEdgeColor Specifies the color of the marker or the edge color for filled markers (circle, square, diamond, pentagram, hexagram, and the four triangles).
- MarkerFaceColor Specifies the color of the face of filled markers.
- MarkerSize Specifies the size of the marker in points (must be greater than 0).

In addition, you can specify the LineStyle, Color, and Marker properties instead of using the symbol string. This is useful if you want to specify a color that is not in the list by using RGB values. See Line Properties for details on these properties and ColorSpec for more information on color.


Examples

Plot the sine function over three different ranges using different line styles, colors, and markers.

```
t = 0:pi/20:2*pi;
plot(t,sin(t),'-.r*')
hold on
plot(t,sin(t-pi/2),'--mo')
plot(t,sin(t-pi),':bs')
hold off
```



Create a plot illustrating how to set line properties:



See Also

axes, line, plot, patch, set, surface, Line Properties, ColorSpec

"Line Styles Used for Plotting — LineStyleOrder" for information about defining an order for applying linestyles

"Types of MATLAB Plots" for functions that use line specs $\,$

"Basic Plots and Graphs" on page 1-96 for related functions $\,$

Purpose

Synchronize limits of specified 2-D axes

Syntax

linkaxes(axes_handles)
linkaxes(axes handles, 'option')

Description

Use linkaxes to synchronize the individual axis limits across several figures or subplots within a figure. Calling linkaxes makes all input axes have identical limits. Linking axes is best when you want to zoom or pan in one subplot and display the same range of data in another subplot.

linkaxes(axes_handles) links the *x*- and *y*-axis limits of the axes specified in the vector axes_handles. You can link any number of existing plots or subplots. The axes_handles input should be a vector of the handles for each plot or subplot. Entering an array of values results in an error message.

linkaxes(axes_handles, 'option') links the axes' axes_handles according to the specified option. The option argument can be one of the following strings:

X Link x-axis only.Y Link y-axis only.

xy Link x-axis and y-axis.

off Remove linking.

See the linkprop function for more advanced capabilities that allow you to link object properties on any graphics object.

Remarks

The first axes you supply to linkaxes determines the *x*- and *y*-limits for all linked axes. This can cause plots to partly or entirely disappear if their limits or scaling are very different. To override this behavior, after calling linkaxes, specify the limits of the axes that you want to control with the set command, as shown in Example 3.

Note linkaxes is not designed to be transitive across multiple invocations. If you have three axes, ax1, ax2, and ax3 and want to link them together, call linkaxes with [ax1, ax2, ax3] as the first argument. Linking ax1 to ax2, then ax2 to ax3, "unbinds" the ax1-ax2 linkage.

Examples

You can use interactive zooming or panning (selected from the figure toolbar) to see the effect of axes linking. For example, pan in one graph and notice how the *x*-axis also changes in the other. The axes responds in the same way to zoom and pan directives you type in the Command Window.

Example 1

This example creates two subplots and links the *x*-axis limits of the two axes:


```
ax(1) = subplot(2,2,1);
plot(rand(1,10)*10, 'Parent',ax(1));
ax(2) = subplot(2,2,2);
plot(rand(1,10)*100, 'Parent',ax(2));
linkaxes(ax,'x');
```

Example 2

This example creates two figures and links the *x*-axis limits of the two axes. The illustration shows the effect of manually panning the top subplot:

```
load count.dat
figure; ax(1) = subplot(2,1,1);
h(1) = bar(ax(1),count(:,1),'g');
ax(2) = subplot(2,1,2);
h(2) = bar(ax(2),count(:,2),'b');
linkaxes(ax,'x');
```

Choose the Pan tool (**Tools** > **Pan**) and drag the top axes. Both axes pans in step in x, but only the top one pans in y.



Example 3

Create two subplots containing data having different ranges. The first axes handle passed to linkaxes determines the data range for all other linked axes. In this example, calling set for the lower axes overrides the *x*-limits established by the call to linkaxes:

```
a1 = subplot(2,1,1);
 plot(randn(10,1));
                             % Plot 10 numbers on top
 a2 = subplot(2,1,2);
 plot(a2,randn(100,1))
                             % Plot 100 numbers below
                             % Link the axes; subplot 2 now out of range
 linkaxes([a1 a2], 'x');
 set(a2,'xlimmode','auto'); % Now both axes run from 1-100 in x
                             % You could also use set(a2,'xlim',[1 100])
0
       10
              20
                    30
                           40
                                  50
                                        60
                                               70
                                                      80
                                                            90
-2
       10
              20
                    30
                           40
                                 50
                                        60
                                               70
                                                      80
                                                            90
```

See Also

linkdata, linkprop, pan, zoom

Purpose

Automatically update graphs when variables change

GUI Alternatives

To turn data linking on or off, click the Data Linking tool in the figure toolbar. When on, an information bar appears below the figure's toolbar to identify and specify data sources for graphs.



For details, see "Making Graphs Responsive with Data Linking" in the MATLAB Data Analysis documentation.

Syntax

linkdata on linkdata off linkdata

linkdata(figure_handle,...)

linkobj = linkdata(figure_handle)

Description

linkdata on turns on data linking for the current figure.

linkdata off turns data linking off.

linkdata by itself toggles the state of data linking.

linkdata(figure_handle,...) applies the function to the specified figure handle.

linkobj = linkdata(figure_handle) returns a *linkdata object* for the specified figure. The object has one read-only property, Enable, the string 'on' or 'off', depending on the linked state of the figure.

Data linking connects graphs in figure windows to variables in the base or a function's workspace via their XDataSource, YDataSource, and ZDataSource properties. When you turn on data linking for a figure, variables in the current (base or caller) workspace are compared to the XData, YData, and ZData properties of graphs in the affected figure to try to match them. When a match is found, the appropriate XDataSource, YDataSource and/or ZDataSource for the graph are set to strings that name the matching variables.

linkdata

Any subsequent changes to linked variables are then reflected in graphs that use them as data sources and in the Variable Editor, if the linked variables are displayed there. Conversely, any changes to plotted data values made at the command line, in the Variable Editor, or with the Brush tool (such as deleting or replacing data points), are immediately reflected in the workspace variables linked to the data points.

When a figure containing graphs is linked and any variable identified as XDataSource, YDataSource, and/or ZDataSource changes its values in the workspace, all graphs displaying it in that and other linked figures automatically update. This operation is equivalent to automatically calling the refreshdata function on the corresponding figure when a variable changes.

Linked figure windows identify themselves by the appearance of the Linked Plot information bar at the top of the window. When linkdata is off for a figure, the Linked Plot information bar is removed. If linkdata cannot unambiguously identify data sources for a graph in a linked figure, it reports this via the Linked Plot information bar, which gives the user an opportunity to identify data sources. The information bar displays a warning icon and a message, **Graphics have no data sources** and also prompts **Click here to fix it**. Clicking the word **here** opens the Specify Data Sources dialog box for specifying names and ranges of data sources for the figure.

Remarks

- "Types of Variables You Can Link" on page 2-2356
- "Restoring Links that Break" on page 2-2357
- "Linking Rapidly Changing Data" on page 2-2357
- "Linking Brushed Graphs" on page 2-2357

Types of Variables You Can Link

You can use linkdata to connect a graph with scalar, vector and matrix numeric variables of any class (including complex, if the graphing function can plot it) — essentially any data for which isnumeric equals true. See "Example 3" on page 2-2359 for instructions on linking complex variables. You can also link plots to numeric fields within

structures. You can specify MATLAB expressions as data sources, for example, sqrt(y)+1.

Restoring Links that Break

Refreshing data on a linked plot fails if the strings in the XDataSource, YDataSource, or ZDataSource properties, when evaluated, are incompatible with what is in the current workspace, such that the corresponding XData, YData, or ZData are unable to respond. The visual appearance of the object in the graph is not affected by such failures, so graphic objects show no indication of broken links. Instead, a warning icon and the message **Failing links** appear on the Linked Plot information bar along with an **Edit** button that opens the Specify Data Sources dialog box.

Linking Rapidly Changing Data

linkdata buffers updates to data and dispatches them to plots at roughly half-second intervals. This makes data linking not suitable for smoothly animating changes in data values unless they are updated in loops that are forced to execute two times per second or less.

One consequence of buffering link updates is that linkdata might not detect changes in data streams it monitors. If you are running a function that uses assignin or evalin to update workspace variables, linkdata can sometimes fail to process updates that change values but not the size and class of workspace variables. Such failures only happen when the function itself updates the plot.

Linking Brushed Graphs


If you link data sources to graphs that have been brushed, their brushing marks can change or vanish. This is because the workspace variables in those graphs now dictate which, if any, observations are brushed, superseding any brushing annotations that were applied to their graphical data (YData, etc.). For more details, see "How Data Linking Affects Data Brushing" on page 2-442 in the brush reference page.

Examples

Example 1

Create two variables, graph them as areaseries, and link the plot to them:


```
x = [1:20];
y = rand(20,3);
area(x,y)
linkdata on
```



Change values for linked variable \boldsymbol{y} in the workspace:

$$y(10,:) = 0;$$

The area graph immediately updates.



Example 2

Delete a figure if it is not linked, based on a returned linkdata object:

```
ld = linkdata(fig)

ld =
          graphics.linkdata

if strcmp(ld.Enable,'off')
          delete(fig)
end
```

Example 3

If a graphing function can display a complex variable, you can link such plots. To do so, you need to describe the data sources as expressions to separate the real and imaginary parts of the variable. For example,


linkdata

```
x = eig(randn(20,20))
whos
Name Size Bytes Class Attributes
x 20x1 320 double complex
```

yields a complex vector. You can use plot to display the real portion as x and the imaginary portion as y, then link the graph to the variable:

```
plot(x)
linkdata
```

However, linkdata cannot unambiguously identify the graph's data sources, and you must tell it by typing real(x) and imag(x) into the Specify Data Source Properties dialog box that displays when you click fix it in the Linked Plot information bar.



To avoid having to type the data source names in the dialog box, you can specify them when you plot:

```
plot(x,'XDataSource','real(x)','YDataSource','imag(x)')
```

If you subsequently change values of x programmatically or manually, the plot updates accordingly.

linkdata

Note Although you can use data brushing on linked plots of complex data, your brush marks only appear in the plot you are brushing, not in other plots or in the Variable Editor. This is because function calls, such as real(x) and imag(x), that you specify as data sources are not interpreted when brushing graphed data.

See Also

brush, linkaxes, linkprop, refreshdata

Purpose

Keep same value for corresponding properties

Syntax

```
hlink = linkprop(obj_handles, 'PropertyName')
hlink = linkprop(obj handles, {'PropertyName1', 'PropertyName2',...})
```

Description

Use linkprop to maintain the same values for the corresponding properties of different objects.

hlink = linkprop(obj_handles, 'PropertyName') maintains the same value for the property PropertyName on all objects whose handles appear in obj_handles. linkprop returns the link object in hlink. See "Link Object" on page 2-2363 for more information.

hlink =

linkprop(obj_handles, {'PropertyName1', 'PropertyName2',...}) maintains the same respective values for all properties passed as a cell array on all objects whose handles appear in obj handles.

Note that the linked properties of all linked objects are updated immediately when linkprop is called. The first object in the list (obj_handles) determines the property values for the rest of the objects.

Link Object

The mechanism to link the properties of different graphics objects is stored in the link object, which is returned by linkprop. Therefore, the link object must exist within the context where you want property linking to occur (such as in the base workspace if users are to interact with the objects from the command line or figure tools).

The following list describes ways to maintain a reference to the link object.

- Return the link object as an output argument from a function and keep it in the base workspace while interacting with the linked objects.
- Make the hlink variable global.

linkprop

• Store the hlink variable in an object's UserData property or in application data. See the "Examples" on page 2-2364 section for an example that uses application data.

Modifying Link Object

If you want to change either the graphics objects or the properties that are linked, you need to use the link object methods designed for that purpose. These methods are functions that operate only on link objects. To use them, you must first create a link object using linkprop.

Method	Purpose
addtarget	Add specified graphics object to the link object's targets.
removetarget	Remove specified graphics object from the link object's targets.
addprop	Add specified property to the linked properties.
removeprop	Remove specified property from the linked properties.

Method Syntax

addtarget(hlink,obj_handles)
removetarget(hlink,obj_handles)
addprop(hlink,'PropertyName')
removeprop(hlink,'PropertyName')

Arguments

- hlink Link object returned by linkprop
- $\bullet\,$ obj_handles One or more graphic object handles
- \bullet PropertyName Name of a property common to all target objects

Examples

This example creates four isosurface graphs of fluid flow data, each displaying a different isovalue. The CameraPosition and CameraUpVector properties of each subplot axes are linked so that the user can rotate all subplots in unison.

After running the example, select **Rotate 3D** from the figure **Tools** menu and observe how all subplots rotate together.

Note If you are using the MATLAB help browser, you can run this example or open it in the MATLAB editor.

The property linking code is in step 3.

1 Define the data using flow and specify property values for the isosurface (which is a patch object).

```
function linkprop_example
[x y z v] = flow;
isoval = [-3 -1 0 1];
props.FaceColor = [0 0 .5];
props.EdgeColor = 'none';
props.AmbientStrength = 1;
props.FaceLighting = 'gouraud';
```

2 Create four subplot axes and add an isosurface graph to each one. Add a title and set viewing and lighting parameters using a local function (set_view). (subplot, patch, isosurface, title, num2str)

```
for k = 1:4
    h(k) = subplot(2,2,k);
    patch(isosurface(x,y,z,v,isoval(k)),props)
    title(h(k),['Isovalue = ',num2str(k)])
    set_view(h(k))
end
```

3 Link the CameraPosition and CameraTarget properties of all subplot axes. Since this example function will have completed execution when the user is rotating the subplots, the link object is stored in the first subplot axes application data. See setappdata for more information on using application data.

```
hlink = linkprop(h,{'CameraPosition','CameraUpVector'});
key = 'graphics_linkprop';
% Store link object on first subplot axes
setappdata(h(1),key,hlink);
```

4 The following local function contains viewing and lighting commands issued on each axes. It is called with the creation of each subplot (view, axis, camlight).

```
function set_view(ax)
% Set the view and add lighting
view(ax,3); axis(ax,'tight','equal')
camlight left; camlight right
% Make axes invisible and title visible
axis(ax,'off')
set(get(ax,'title'),'Visible','on')
```

Linking an Additional Property

Suppose you want to add the axes PlotBoxAspectRatio to the linked properties in the previous example. You can do this by modifying the link object that is stored in the first subplot axes' application data.

1 First click the first subplot axes to make it the current axes (since its handle was saved only within the creating function). Then get the link object's handle from application data (getappdata).

```
hlink = getappdata(gca, 'graphics linkprop');
```

2 Use the addprop method to add a new property to the link object.

```
addprop(hlink, 'PlotBoxAspectRatio')
```

Since hlink is a reference to the link object (i.e., not a copy), addprop can change the object that is stored in application data.

See Also

getappdata, linkaxes, linkdata, setappdata

Purpose

Solve linear system of equations

Syntax

X = linsolve(A,B)

X = linsolve(A,B,opts)

Description

X = linsolve(A,B) solves the linear system A*X = B using LU factorization with partial pivoting when A is square and QR factorization with column pivoting otherwise. The number of rows of A must equal the number of rows of B. If A is m-by-n and B is m-by-k, then X is n-by-k. linsolve returns a warning if A is square and ill conditioned or if it is not square and rank deficient.

[X, R] = linsolve(A,B) suppresses these warnings and returns R, which is the reciprocal of the condition number of A if A is square, or the rank of A if A is not square.

X = linsolve(A,B,opts) solves the linear system A*X = B or A'*X = B, using the solver that is most appropriate given the properties of the matrix A, which you specify in opts. For example, if A is upper triangular, you can set opts.UT = true to make linsolve use a solver designed for upper triangular matrices. If A has the properties in opts, linsolve is faster than mldivide, because linsolve does not perform any tests to verify that A has the specified properties.

Notes If A does not have the properties that you specify in opts, linsolve returns incorrect results and does not return an error message. If you are not sure whether A has the specified properties, use mldivide instead.

For small problems, there is no speed benefit in using linsolve on triangular matrices as opposed to using the mldivide function.

The TRANSA field of the opts structure specifies the form of the linear system you want to solve:

linsolve

- If you set opts.TRANSA = false, linsolve(A,B,opts) solves A*X = B.
- If you set opts.TRANSA = true, linsolve(A,B,opts) solves A'*X = B.

The following table lists all the field of opts and their corresponding matrix properties. The values of the fields of opts must be logical and the default value for all fields is false.

Field Name	Matrix Property
LT	Lower triangular
UT	Upper triangular
UHESS	Upper Hessenberg
SYM	Real symmetric or complex Hermitian
POSDEF	Positive definite
RECT	General rectangular
TRANSA	Conjugate transpose — specifies whether the function solves A*X = B or A'*X = B

The following table lists all combinations of field values in opts that are valid for linsolve. A true/false entry indicates that linsolve accepts either true or false.

LT	UT	UHESS	SYM	POSDEF	RECT	TRANSA
true	false	false	false	false	true/false	true/false
false	true	false	false	false	true/false	true/false
false	false	true	false	false	false	true/false
false	false	false	true	true/fa]	.sfealse	true/false
false	false	false	false	false	true/false	true/false

Example

The following code solves the system A'x = b for an upper triangular matrix A using both mldivide and linsolve.

```
A = triu(rand(5,3)); x = [1 1 1 0 0]'; b = A'*x;
y1 = (A') b
opts.UT = true; opts.TRANSA = true;
y2 = linsolve(A,b,opts)
y1 =
    1.0000
    1.0000
    1.0000
         0
         0
y2 =
    1.0000
    1.0000
    1.0000
         0
         0
```

Note If you are working with matrices having different properties, it is useful to create an options structure for each type of matrix, such as opts_sym. This way you do not need to change the fields whenever you solve a system with a different type of matrix A.

See Also

mldivide

linspace

Purpose Generate linearly spaced vectors

Syntax y = linspace(a,b)

y = linspace(a,b,n)

Description The linspace function generates linearly spaced vectors. It is similar to

the colon operator ":", but gives direct control over the number of points.

y = linspace(a,b) generates a row vector y of 100 points linearly

spaced between and including a and b.

y = linspace(a,b,n) generates a row vector y of n points linearly spaced between and including a and b. For n < 2, linspace returns b.

See Also logspace

The colon operator:

Purpose Random number generator algorithms

Class @RandStream

Syntax RandStream.list

Description

RandStream.list lists all the generator algorithms that may be used when creating a random number stream with RandStream or RandStream.create. The available generator algorithms and their properties are given in the following table.

Keyword	Generator	Multiple Stream and Substream Support	Approximate Period In Full Precision
mt19937ar	Mersenne twister (used by default stream at MATLAB startup)	No	$2^{19936} - 1$
mcg16807	Multiplicative congruential generator	No	$2^{31} - 2$
mlfg6331_64	Multiplicative lagged Fibonacci generator	Yes	2 ¹²⁴
mrg32k3a	Combined multiple recursive generator	Yes	2^{127}

list (RandStream)

Keyword	Generator	Multiple Stream and Substream Support	Approximate Period In Full Precision
shr3cong	Shift-register generator summed with linear congruential generator	No	2^{64}
swb2712	Modified subtract with borrow generator	No	2 ¹⁴⁹²

For a full description of the Mersenne twister algorithm, see http://www.math.sci.hiroshima-u.ac.jp/~m-mat/MT/emt.html.

All of the generator and transformation algorithms that were available in MATLAB versions 7.6 and earlier are available in the current version. To create random streams that are equivalent to the legacy generators without entering into legacy mode, use the following syntaxes:

Legacy mode	RandStream syntax
rand('seed',0)	(RandStream('mcg16807', 'Seed',0))
rand('state'0)	(RandStream('swb2712','Seed',0))
rand('twister',5489)	(RandStream('mt19937ar', 'Seed', 5489))
randn('seed',0)	(RandStream('mcg16807', 'Seed',0))
randn('state',0)	(RandStream('shr3cong'))

list (RandStream)

For more information on compatibility issues with MATLAB versions 7.6 and earlier, see "Legacy Mode" in the *MATLAB Mathematics* documentation.

listdlg

Purpose

Create and open list-selection dialog box

Syntax

[Selection,ok] = listdlg('ListString',S)

Description

[Selection,ok] = listdlg('ListString',S) creates a modal dialog box that enables you to select one or more items from a list. Selection is a vector of indices of the selected strings (in single selection mode, its length is 1). Selection is [] when ok is 0. ok is 1 if you click the OK button, or 0 if you click the Cancel button or close the dialog box. Double-clicking on an item or pressing Return when multiple items are selected has the same effect as clicking the OK button. The dialog box has a Select all button (when in multiple selection mode) that enables you to select all list items.

Inputs are in parameter/value pairs:

Parameter	Description
'ListString'	Cell array of strings that specify the list box items.
'SelectionMode'	String indicating whether one or many items can be selected: 'single' or 'multiple' (the default).
'ListSize'	List box size in pixels, specified as a two-element vector [width height]. Default is [160 300].
'InitialValue'	Vector of indices of the list box items that are initially selected. Default is 1, the first item.
'Name'	String for the dialog box's title. Default is ".
'PromptString'	String matrix or cell array of strings that appears as text above the list box. Default is \{\}.
'OKString'	String for the OK button. Default is 'OK'.
'CancelString'	String for the Cancel button. Default is 'Cancel'.
'uh'	Uicontrol button height, in pixels. Default is 18.


Parameter	Description
'fus'	Frame/uicontrol spacing, in pixels. Default is 8.
'ffs'	Frame/figure spacing, in pixels. Default is 8.

Note A modal dialog box prevents the user from interacting with other windows before responding. For more information, see WindowStyle in the MATLAB Figure Properties.

Example

This example displays a dialog box that enables the user to select a file from the current directory. The function returns a vector. Its first element is the index to the selected file; its second element is 0 if no selection is made, or 1 if a selection is made.

listdlg



See Also

dialog, errordlg, helpdlg, inputdlg, msgbox, questdlg, warndlg dir, figure, uiwait, uiresume

"Predefined Dialog Boxes" on page 1-113 for related functions $\,$

Purpose List available system fonts

Description c = listfonts returns sorted list of available system fonts.

c = listfonts(h) returns sorted list of available system fonts and includes the FontName property of the object with handle h.

Remarks

Calling listfonts returns a list of all fonts residing on your system, possibly including fonts that cannot be used because they are bitmapped. You can instead use the uisetfont utility (a GUI) to preview fonts you might want to use; it only displays fonts that can be rendered in MATLAB figures and GUIs. Like uisetfont, the **Custom Fonts** pane of MATLAB Preferences also previews available fonts and only shows those that can be rendered.

Examples Example 1

This example returns a list of available system fonts similar in format to the one shown.

```
list = listfonts

list =
    'Agency FB'
    'Algerian'
    'Arial'
    ...
    'ZapfChancery'
    'ZapfDingbats'
    'ZWAdobeF'
```

Example 2

This example returns a list of available system fonts with the value of the Font Name property, for the object with handle h, sorted into the list.

listfonts

```
h = uicontrol('Style','text','String','My Font','FontName','MyFont');
list = listfonts(h)

list =
    'Agency FB'
    'Algerian'
    'Arial'
    ...
    'MyFont'
    ...
    'ZapfChancery'
    'ZapfDingbats'
    'ZWAdobeF'
```

See Also

uisetfont

Purpose

Load data from MAT-file into workspace

Syntax

```
S = load(filename)
S = load(filename, variables)
S = load(filename, '-mat', variables)
S = load(filename, '-ascii')
load(...)
load ...
```

Description

S = load(filename) loads the variables from a MAT-file into a structure array, or data from an ASCII file into a double-precision array.

S = load(filename, variables) loads the specified variables from a MAT-file.

S = load(filename, '-mat', variables) forces load to treat the file as a MAT-file, regardless of the extension. Specifying variables is optional.

S = load(filename, '-ascii') forces load to treat the file as an ASCII file, regardless of the extension.

load(...) loads without combining MAT-file variables into a structure array.

load ... is the command form of the syntax, for convenient loading from the command line. With command syntax, you do not need to enclose input strings in single quotation marks. Separate inputs with spaces instead of commas. Do not use command syntax if inputs such as *filename* are variables. For more information, see "Command vs. Function Syntax" in the MATLAB Programming Fundamentals documentation.

Input Arguments

filename

Name of a file. If you do not specify *filename*, the load function searches for a file named matlab.mat.

filename can include a file extension and a full or partial path. If filename has no extension (that is, no text after a period),

load looks for a file named *filename*.mat. If *filename* has an extension other than .mat, the load function treats the file as ASCII data.

Default: 'matlab.mat'

variables

List of variables to load from the file. Valid for MAT-files only. Use one of the following forms:

Var1, var2, ...

Load the listed variables.

Use the '*' wildcard to match patterns. For example, load('A*') loads all variables that start with A.

'-regexp', expressions

Load only the variables or fields that match the specified regular expressions.

Default: all variables in file

'-mat'

Keyword that indicates that the specified file is a MAT-file, regardless of the extension.

'-ascii'

Keyword that indicates that the specified file is an ASCII file, regardless of the extension.

The following remarks apply to loading all ASCII files, even when you do not include the -ascii keyword, but load a file with an extension other than .mat:

• The file must contain a rectangular table of numbers, with an equal number of elements in each row. The file delimiter

(the character between elements in each row) can be a blank, comma, semicolon, or tab character. The file can contain MATLAB comments (lines that begin with a percent sign, %).

- MATLAB returns the data as a single two-dimensional array of type double. The number of rows in the array is equal to the number of lines in the file. The number of columns is equal to the number of values on a line.
- If you do not specify an output for the load function, MATLAB creates a variable named after the loaded file (minus any file extension). For example, the command

```
load mydata.dat
```

reads data into a variable called mydata.

To create the variable name, load precedes any leading underscores or digits in *filename* with an X and replaces any other nonalphabetic characters with underscores. For example, the command

```
load 10-May-data.dat
```

creates a variable called X10 May data.

Examples

Load all variables from the demo MAT-file gong.mat. Check the contents of the workspace before and after the load operation.

```
disp('Contents of workspace before loading file:')
whos

disp('Contents of gong.mat:')
whos -file gong.mat

load gong.mat
disp('Contents of workspace after loading file:')
whos
```

Load only the variable y from the demo file handel.mat. If the workspace already contains a variable y, the load operation overwrites it with data from the file.

```
load('handel.mat', 'y')
```

Create a list of variables to load using a cell array. Call load using function syntax.

```
%This demo file contains variables X, caption, and map.
demoFile = 'durer.mat';
% Load selected variables.
vars = {'X', 'caption'};
load(demoFile, vars{:});
```

Use regular expressions to load four variables from the demo file accidents.mat that do not begin with 'hwy':

```
load('accidents.mat', '-regexp', '^(?!hwy)...');
```

Load the first three variables from accidents.mat, determined alphabetically by variable name:

```
vars = whos('-file', 'accidents.mat');
load('accidents.mat', vars(1:3).name);
```

Create an ASCII file from several 4-column matrices, and load the data back into a double array named mydata:

```
a = magic(4);
```

```
b = ones(2, 4) * -5.7;
c = [8 6 4 2];
save -ascii mydata.dat a b c
clear a b c
load mydata.dat
```

Alternatives

The easiest way to import data is to use the Import Wizard, a graphical user interface. The Import Wizard imports both MAT-files and ASCII files, and provides direct control over the variables to create. To start the Wizard, select **File > Import Data** or call uiimport.

See Also

clear | fileformats | importdata | regexp | save | uiimport | whos

How To

- "Importing MAT-Files"
- · "Importing Text Data Files"
- "Troubleshooting: Loading Variables within a Function"
- "Processing a Sequence of Files"

Purpose

Initialize control object from file

Syntax

```
h.load('filename')
load(h, 'filename')
```

Description

h.load('filename') initializes the COM object associated with the interface represented by the MATLAB COM object h from file specified in the string filename. The file must have been created previously by serializing an instance of the same control.

load(h, 'filename') is an alternate syntax for the same operation.

Note The COM load function is only supported for controls at this time.

Remarks

COM functions are available on Microsoft Windows systems only.

Examples

Create an mwsamp control and save its original state to the file mwsample:

```
f = figure('position', [100 200 200 200]);
h = actxcontrol('mwsamp.mwsampctrl.2', [0 0 200 200], f);
h.save('mwsample')
```

Now, alter the figure by changing its label and the radius of the circle:

```
h.Label = 'Circle';
h.Radius = 50;
h.Redraw;
```

Using the load function, you can restore the control to its original state:

```
h.load('mwsample');
h.get
```

MATLAB displays the original values:

```
ans =
```

load (COM)

Label: 'Label' Radius: 20

See Also

save (COM), actxcontrol, actxserver, release, delete (COM)

Purpose

Load serial port objects and variables into MATLAB workspace

Syntax

```
load filename load filename obj1 obj2...
```

Description

load filename returns all variables from the file specified by filename into the MATLAB workspace.

load filename obj1 obj2... returns the serial port objects specified by obj1 obj2 ... from the file filename into the MATLAB workspace.

out = load('filename','obj1','obj2',...) returns the specified serial port objects from the file filename as a structure to out instead of directly loading them into the workspace. The field names in out match the names of the loaded serial port objects.

Remarks

Values for read-only properties are restored to their default values upon loading. For example, the Status property is restored to closed. To determine if a property is read-only, examine its reference pages.

Example

Note This example is based on a Windows platform.

Suppose you create the serial port objects \$1 and \$2, configure a few properties for \$1, and connect both objects to their instruments:

```
s1 = serial('COM1');
s2 = serial('COM2');
set(s1, 'Parity', 'mark', 'DataBits',7);
fopen(s1);
fopen(s2);
```

Save s1 and s2 to the file MyObject.mat, and then load the objects back into the workspace:

```
save MyObject s1 s2;
load MyObject s1;
```

```
load MyObject s2;

get(s1, {'Parity', 'DataBits'})
ans =
    'mark' [7]
get(s2, {'Parity', 'DataBits'})
ans =
    'none' [8]
```

See Also Functions

save

Properties

Status

loadlibrary

Purpose

Load shared library into MATLAB software

Syntax

```
loadlibrary('shrlib', 'hfile')
loadlibrary('shrlib', @protofile)
loadlibrary('shrlib', ..., 'options')
loadlibrary shrlib hfile options
[notfound, warnings] = loadlibrary('shrlib', 'hfile')
```

Description

loadlibrary('shrlib', 'hfile') loads the functions defined in header file hfile and found in shared library shrlib into MATLAB.

The hfile and shrlib file names are case sensitive. The name you use in loadlibrary must use the same case as the file on your system.

On Microsoft Windows systems, shrlib refers to the name of a Shared library (.dll) file. On Linux systems, it refers to the name of a shared object (.so) file. On Apple Macintosh systems, it refers to a dynamic shared library (.dylib). See "File Extensions for Libraries" on page 2-2388 for more information.

loadlibrary('shrlib', @protofile) uses a prototype file protofile in place of a header file in loading the library shrlib. The string @protofile specifies a function handle to the prototype file. (See the description of "Prototype Files" on page 2-2391 below).

Note The MATLAB Generic Shared Library interface does not support library functions that have function pointer inputs.

File Extensions for Libraries

If you do not include a file extension with the shrlib argument, loadlibrary attempts to find the library with either the appropriate platform MEX-file extension or the appropriate platform library extension (usually .dll, .so, or .dylib). For a list of file extensions, see "Binary MEX-File Extensions".

If you do not include a file extension with the second argument, and this argument is not a function handle, loadlibrary uses .h for the extension.

loadlibrary('shrlib', ..., 'options') loads the library shrlib with one or more of the following options.

Option	Description	
addheader hfileN	Loads the functions defined in the additional header file, hfileN. Note that each file specified by addheader must be referenced by a corresponding #include statement in the base header file.	
	Specify the string hfileN as a file name without a file extension. MATLAB does not verify the existence of the header files and ignores any that are not needed.	
	You can specify additional header files using the syntax:	
	loadlibrary shrlib hfile addheader hfile1 addheader hfile2 % and so on	
alias name	Associates the specified alias name with the library. All subsequent calls to MATLAB functions that reference this library must use this alias until the library is unloaded.	
<pre>includepath path</pre>	Specifies an additional path in which to look for included header files.	

loadlibrary

Option	Description
mfilename mfile	Generates a prototype file mfile in the current folder. The mfile name must be different from the shrlib library name. You can use this file in place of a header file when loading the library. (See the following description of "Prototype Files" on page 2-2391).
thunkfilename tfile	Overrides the default thunk file name with tfile. For more information, see "Using loadlibrary on 64-Bit Platforms" on page 2-2392.

Only the **alias** option is available when loading using a prototype file.

If you have more than one library file of the same name, load the first using the library file name, and load the additional libraries using the **alias** option.

loadlibrary shrlib hfile options is the command format for this function.

[notfound, warnings] = loadlibrary('shrlib', 'hfile') returns warning information from the shrlib library file. notfound is a cell array of the names of functions found in the header file hfile, or any header added with the addheader option, but not found in the shrlib library. warnings contains a single character array of warnings produced while processing the header file hfile.

Remarks How to Use the addheader Option

The addheader option enables you to add functions for MATLAB to load from those listed in header files included in the base header file (with a #include statement). For example, if your library header file contains the statement:

#include header2.h

then to load the functions in header2.h, you need to use addheader in the call to loadlibrary:

loadlibrary libname libname.h addheader header2.h

You can use the addheader option with a header file that lists function prototypes for only the functions that are needed by your library, and thereby avoid loading functions that you do not define in your library. To do this, you might need to create a header file that contains a subset of the functions listed in large header file.

addheader Syntax

When using addheader to specify which functions to load, ensure that there are #include statements in the base header file for each additional header file in the loadlibrary call. For example, to use the following statement:

loadlibrary mylib mylib.h addheader header2.h

the file mylib.h must contain this statement:

#include header2.h

Prototype Files

When you use the **mfilename** option with loadlibrary, MATLAB generates a file of MATLAB commands called a *prototype file*. Use this file on subsequent calls to loadlibrary in place of a header file.

Note The mfilename name must be different from the shrlib library name.

Like a header file, the prototype file supplies MATLAB with function prototype information for the library. You can make changes to the prototypes by editing this file and reloading the library.

Here are some reasons for using a prototype file, along with the changes you would need to make to the file:

loadlibrary

 You want to make temporary changes to signatures of the library functions.

Edit the prototype file, changing the fcns.LHS or fcns.RHS field for that function. This changes the types of arguments on the left hand side or right hand side, respectively.

• You want to rename some of the library functions.

Edit the prototype file, defining the fcns.alias field for that function.

 You expect to use only a small percentage of the functions in the library you are loading.

Edit the prototype file, commenting out the unused functions. This reduces the amount of memory required for the library.

 You need to specify a number of include files when loading a particular library.

Specify the full list of include files (plus the **mfilename** option) in the first call to loadlibrary. This puts all the information from the include files into the prototype file. After that, specify just the prototype file.

• You want to use functions with a variable number of arguments.

Create an alias function in a prototype file for each set of arguments you use to call the function.

Using loadlibrary on 64-Bit Platforms

You must install a C compiler to use loadlibrary on a 64-bit platform and Perl must be available. The supported compilers are shown in the following table.

64-bit Platform	Required Compiler
Windows	Microsoft® Visual C++® 2005 SP1 Version 8.0 Professional Edition
	Microsoft Visual C++ 2008 SP1 Version 9.0 Professional Edition
Linux	gcc / g++ Version 4.1.1
Sun Solaris™ SPARC®	Sun Studio 12 cc / CC Version 5.9

MATLAB generates a *thunk file*, which is a compatibility layer to your 64-bit library. The name of the thunk file is:

```
BASENAME_thunk_COMPUTER.c
```

where BASENAME is either the name of the shared library or the mfilename, if specified. COMPUTER is the string returned by the computer function.

MATLAB compiles this file and creates the file:

```
BASENAME_thunk_COMPUTER.LIBEXT
```

where *LIBEXT* is the platform-dependent default shared library extension, for example, dll on Windows.

Examples Load shrlibsample Example

Use loadlibrary to load the MATLAB sample shared library, shrlibsample:

addpath([matlabroot '\extern\examples\shrlib'])
loadlibrary shrlibsample shrlibsample.h

Using alias Example

Load sample library shrlibsample, giving it an alias name of lib. Once you have set an alias, you need to use this name in all further interactions with the library for this session:

```
addpath([matlabroot '\extern\examples\shrlib'])
loadlibrary shrlibsample shrlibsample.h alias lib
libfunctionsview lib

str = 'This was a Mixed Case string';
calllib('lib', 'stringToUpper', str)
ans =
   THIS WAS A MIXED CASE STRING
unloadlibrary lib
```

Using addpath Example

Load the library, specifying an additional path in which to search for included header files:

Using Prototype Example

Load the libmx library and generate a prototype file containing the prototypes defined in header file matrix.h:

```
hfile = [matlabroot '\extern\include\matrix.h'];
loadlibrary('libmx', hfile, 'mfilename', 'mxproto')
dir mxproto.m
   mxproto.m
```

Edit the generated file mxproto.m and locate the function mxGetNumberOfDimensions. Give it an alias of mxGetDims by adding this text to the line before fcnNum is incremented:

```
fcns.alias{fcnNum}='mxGetDims';
```

Here is the new function prototype. The change is shown in bold:

```
fcns.name{fcnNum}='mxGetNumberOfDimensions';
```

```
fcns.calltype{fcnNum}='cdecl';
fcns.LHS{fcnNum}='int32';
fcns.RHS{fcnNum}={'MATLAB array'};
fcns.alias{fcnNum}= mxGetDims; % Alias defined
fcnNum=fcnNum+1; % Increment fcnNum

Unload the library, and then reload it using the prototype file.
    unloadlibrary libmx
    loadlibrary('libmx', @mxproto)

Now call mxGetNumberOfDimensions using the alias function name:
    y = rand(4, 7, 2);
    calllib('libmx', 'mxGetDims', y)
    ans =
        3
    unloadlibrary libmx

unloadlibrary, libisloaded, libfunctions, computer
```

See Also

loadobj

Purpose

Modify load process for object

Syntax

b = loadobj(a)

Description

b = loadobj(a) is called by the load function if the class of a defines a loadobj method. load returns b as the value loaded from a MAT-file.

Define a loadobj method when objects of the class require special processing when loaded from MAT-files. If you define a saveobj method, then define a loadobj method to restore the object to the desired state. Define loadobj as a static method so it can accept as an argument whatever object or structure that you saved in the MAT-file. See "Implement loadobj as a Static Method".

When loading a subclass object, load calls only the subclass loadobj method. If a superclass defines a loadobj method, the subclass inherits this method. However, it is possible that the inherited method does not perform the necessary operations to load the subclass object. Consider overriding superclass loadobj methods.

If any superclass in a class hierarchy defines a loadobj method, then the subclass loadobj method must ensure that the subclass and superclass objects load properly. Ensure proper loading by calling the superclass loadobj (or other methods) from the subclass loadobj method. See "Saving and Loading Objects from Class Hierarchies".

Input Arugments

а

The input argument, a, can be:

- The object as loaded from the MAT-file.
- A structure created by load (if load cannot resolve the object).
- A struct returned by the saveobj method.

See Also

load | save | saveobj

Tutorials

· "Saving and Loading Objects"

Purpose Natural logarithm

Syntax Y = log(X)

Description

The log function operates element-wise on arrays. Its domain includes complex and negative numbers, which may lead to unexpected results if used unintentionally.

Y = log(X) returns the natural logarithm of the elements of X. For complex or negative z, where $z = x + y^*i$, the complex logarithm is returned.

log(z) = log(abs(z)) + i*atan2(y,x)

Examples

The statement abs(log(-1)) is a clever way to generate π .

ans =

3.1416

See Also

exp, log10, log2, logm, reallog

log10

Purpose Common (base 10) logarithm

Syntax Y = log10(X)

Description The log10 function operates element-by-element on arrays. Its domain

includes complex numbers, which may lead to unexpected results if

used unintentionally.

Y = log10(X) returns the base 10 logarithm of the elements of X.

Examples log10(realmax) is 308.2547

and

log10(eps) is -15.6536

See Also exp, log, log2, logm

Purpose Compute log(1+x) accurately for small values of x

Syntax y = log1p(x)

Description y = log1p(x) computes log(1+x), compensating for the roundoff in

1+x. log1p(x) is more accurate than log(1+x) for small values of x. For small x, log1p(x) is approximately x, whereas log(1+x) can be zero.

See Also log, expm1

log2

Purpose

Base 2 logarithm and dissect floating-point numbers into exponent and

mantissa

Syntax

$$Y = log2(X)$$

[F,E] = $log2(X)$

Description

Y = log2(X) computes the base 2 logarithm of the elements of X.

[F,E] = log2(X) returns arrays F and E. Argument F is an array of real values, usually in the range 0.5 <= abs(F) < 1. For real X, F satisfies the equation: $X = F.*2.^E$. Argument E is an array of integers that, for real X, satisfy the equation: $X = F.*2.^E$.

Remarks

This function corresponds to the ANSI C function frexp() and the IEEE floating-point standard function logb(). Any zeros in X produce F = 0 and E = 0.

Examples

For IEEE arithmetic, the statement [F,E] = log2(X) yields the values:

X	F	E
1	1/2	1
pi	pi/4	2
-3	-3/4	2
eps	1/2	-51
realmax	1-eps/2	1024
realmin	1/2	-1021

See Also

log, pow2

Purpose

Convert numeric values to logical

Syntax

K = logical(A)

Description

K = logical(A) returns an array that can be used for logical indexing or logical tests.

A(B), where B is a logical array that is the same size as A, returns the values of A at the indices where the real part of B is nonzero.

A(B), where B is a logical array that is smaller than A, returns the values of column vector A(:) at the indices where the real part of column vector B(:) is nonzero.

Remarks

Most arithmetic operations remove the logicalness from an array. For example, adding zero to a logical array removes its logical characteristic. A = +A is the easiest way to convert a logical array, A, to a numeric double array.

Logical arrays are also created by the relational operators (==,<,>,~, etc.) and functions like any, all, isnan, isinf, and isfinite.

Examples

Given A = [1 2 3; 4 5 6; 7 8 9], the statement B = logical(eye(3)) returns a logical array

which can be used in logical indexing that returns A's diagonal elements:

logical

However, attempting to index into A using the numeric array eye(3) results in:

```
\label{eq:A(eye(3))} \ref{eq:A(eye(3))} \ref{eq:A(eye(3))} \ref{eq:A(eye(3))} \ \ref{eq:
```

See Also

Purpose

Log-log scale plot



GUI Alternatives

To graph selected variables, use the Plot Selector workspace Browser, or use the Figure Palette Plot Catalog. Manipulate graphs in *plot edit* mode with the Property Editor. For details, see Plotting Tools — Interactive Plotting in the MATLAB Graphics documentation and Creating Graphics from the Workspace Browser in the MATLAB Desktop Tools documentation.

Syntax

```
loglog(Y)
loglog(X1,Y1,...)
loglog(X1,Y1,LineSpec,...)
loglog(...,'PropertyName',PropertyValue,...)
h = loglog(...)
```

Description

loglog(Y) plots the columns of Y versus their index if Y contains real numbers. If Y contains complex numbers, loglog(Y) and loglog(real(Y),imag(Y)) are equivalent. loglog ignores the imaginary component in all other uses of this function.

loglog(X1,Y1,...) plots all Xn versus Yn pairs. If only Xn or Yn is a matrix, loglog plots the vector argument versus the rows or columns of the matrix, depending on whether the vector's row or column dimension matches the matrix.

loglog(X1,Y1,LineSpec,...) plots all lines defined by the Xn,Yn,LineSpec triples, where LineSpec determines line type, marker symbol, and color of the plotted lines. You can mix Xn,Yn,LineSpec triples with Xn,Yn pairs, for example,

loglog(X1,Y1,X2,Y2,LineSpec,X3,Y3)

loglog(..., 'PropertyName', PropertyValue,...) sets property values for all lineseries graphics objects created by loglog. See the line reference page for more information.

h = loglog(...) returns a column vector of handles to lineseries graphics objects, one handle per line.


If you do not specify a color when plotting more than one line, loglog automatically cycles through the colors and line styles in the order specified by the current axes.

If you attempt to add a loglog, semilogx, or semilogy plot to a linear axis mode graph with hold on, the axis mode will remain as it is and the new data will plot as linear.

Examples

Create a simple loglog plot with square markers.

```
x = logspace(-1,2);
loglog(x,exp(x),'-s')
grid on
```



See Also

LineSpec, plot, semilogx, semilogy

"Basic Plots and Graphs" on page 1-96 for related functions

Purpose

Matrix logarithm

Syntax

```
L = logm(A)
[L, exitflag] = logm(A)
```

Description

L = logm(A) is the principal matrix logarithm of A, the inverse of expm(A). L is the unique logarithm for which every eigenvalue has imaginary part lying strictly between - π and π . If A is singular or has any eigenvalues on the negative real axis, the principal logarithm is undefined. In this case, logm computes a non-principal logarithm and returns a warning message.

[L, exitflag] = logm(A) returns a scalar exitflag that describes the exit condition of logm:

- If exitflag = 0, the algorithm was successfully completed.
- If exitflag = 1, too many matrix square roots had to be computed. However, the computed value of L might still be accurate. This is different from R13 and earlier versions that returned an expensive and often inaccurate error estimate as the second output argument.

The input A can have class double or single.

Remarks

If A is real symmetric or complex Hermitian, then so is logm(A).

Some matrices, like A = [0 1; 0 0], do not have any logarithms, real or complex, so logm cannot be expected to produce one.

Limitations

For most matrices:

```
logm(expm(A)) = A = expm(logm(A))
```

These identities may fail for some A. For example, if the computed eigenvalues of A include an exact zero, then logm(A) generates infinity. Or, if the elements of A are too large, expm(A) may overflow.

Examples

Suppose A is the 3-by-3 matrix

and Y = expm(A) is

Then A = logm(Y) produces the original matrix A.

But log(A) involves taking the logarithm of zero, and so produces

Algorithm

The algorithm logm uses is described in [1].

See Also

expm, funm, sqrtm

References

[1] Davies, P. I. and N. J. Higham, "A Schur-Parlett algorithm for computing matrix functions," *SIAM J. Matrix Anal. Appl.*, Vol. 25, Number 2, pp. 464-485, 2003.

[2] Cheng, S. H., N. J. Higham, C. S. Kenney, and A. J. Laub, "Approximating the logarithm of a matrix to specified accuracy," *SIAM J. Matrix Anal. Appl.*, Vol. 22, Number 4, pp. 1112-1125, 2001.

logm

- [3] Higham, N. J., "Evaluating Pade approximants of the matrix logarithm," *SIAM J. Matrix Anal. Appl.*, Vol. 22, Number 4, pp. 1126-1135, 2001.
- [4] Golub, G. H. and C. F. Van Loan, *Matrix Computation*, Johns Hopkins University Press, 1983, p. 384.
- [5] Moler, C. B. and C. F. Van Loan, "Nineteen Dubious Ways to Compute the Exponential of a Matrix," *SIAM Review* 20, 1978, pp. 801-836.

Purpose Generate logarithmically spaced vectors

Syntax y = logspace(a,b)

y = logspace(a,b,n)
y = logspace(a,pi)

Description

The logspace function generates logarithmically spaced vectors. Especially useful for creating frequency vectors, it is a logarithmic equivalent of linspace and the ":" or colon operator.

y = logspace(a,b) generates a row vector y of 50 logarithmically spaced points between decades 10^a and 10^b.

y = logspace(a,b,n) generates n points between decades 10^a and 10^b.

y = logspace(a,pi) generates the points between 10^a and pi, which is useful for digital signal processing where frequencies over this interval go around the unit circle.

Remarks

All the arguments to logspace must be scalars.

See Also linspace

The colon operator:

lookfor

Purpose

Search for keyword in all help entries

GUI Alternatives

As an alternative to the lookfor function, use the Function Browser.

Syntax

lookfor topic lookfor topic -all

Description

lookfor topic searches for the string topic in the first comment line (the H1 line) of the help text in all MATLAB program files found on the search path. For all files in which a match occurs, lookfor displays the H1 line.

lookfor topic -all searches the entire first comment block of a MATLAB program file looking for topic.

Examples

For example:

lookfor inverse

finds at least a dozen matches, including H1 lines containing "inverse hyperbolic cosine," "two-dimensional inverse FFT," and "pseudoinverse." Contrast this with

which inverse

or

what inverse

These functions run more quickly, but probably fail to find anything because MATLAB does not have a function inverse.

In summary, what lists the functions in a given folder, which finds the folder containing a given function or file, and lookfor finds all functions in all folders that might have something to do with a given keyword.

Even more extensive than the lookfor function are the find features in the Current Folder browser. For example, you can look for all occurrences of a specified word in all the MATLAB program files in the current folder and its subfolders. For more information, see "Finding Files and Folders"

See Also

 $\label{eq:dir_doc} \mbox{dir, doc, filebrowser, findstr, help, helpdesk, helpwin, regexp,} \\ \mbox{what, which, who}$

Topics in the User Guide:

- "Searching for Documentation and Demos"
- "Finding Functions Using the Function Browser"

lower

Purpose Convert string to lowercase

B = lower(A)

Description t = lower('str') returns the string formed by converting any

 $uppercase\ characters\ in\ {\tt str}\ to\ the\ corresponding\ lowercase\ characters$

and leaving all other characters unchanged.

B = lower(A) when A is a cell array of strings, returns a cell array the same size as A containing the result of applying lower to each string

within A.

Examples lower('MathWorks') is mathworks.

Remarks Character sets supported:

• PC: Latin-1 for the Microsoft Windows operating system

• Other: ISO Latin-1 (ISO 8859-1)

See Also upper

Purpose Folder contents

Syntax 1s

Graphical Interface

As an alternative to the 1s function, use the Current Folder browser.

Description

1s lists the contents of the current folder. On $UNIX^{10}$ platforms, 1s returns a character row vector of names separated by tab and space characters. On Microsoft Windows platforms, 1s returns an m-by-n character array of names. m is the number of names and n is the number of characters in the longest name found. Names shorter than n characters are padded with space characters.

On UNIX platforms, you add any flags to 1s that the operating system supports.

See Also

dir, pwd

"Working with Files and Folders"

10. UNIX is a registered trademark of The Open Group in the United States and other countries.

Purpose

Least-squares solution in presence of known covariance

Syntax

```
x = lscov(A,b)
x = lscov(A,b,w)
x = lscov(A,b,V)
x = lscov(A,b,V,alg)
[x,stdx] = lscov(...)
[x,stdx,mse] = lscov(...)
[x,stdx,mse,S] = lscov(...)
```

Description

x = 1scov(A,b) returns the ordinary least squares solution to the linear system of equations A*x = b, i.e., x is the n-by-1 vector that minimizes the sum of squared errors (b - A*x)'*(b - A*x), where A is m-by-n, and b is m-by-1. b can also be an m-by-k matrix, and 1scov returns one solution for each column of b. When rank(A) < n, 1scov sets the maximum possible number of elements of x to zero to obtain a "basic solution".

x = 1scov(A, b, w), where w is a vector length m of real positive weights, returns the weighted least squares solution to the linear system A*x = b, that is, x minimizes $(b - A*x) \cdot *diag(w)*(b - A*x)$. w typically contains either counts or inverse variances.

x = 1scov(A,b,V), where V is an m-by-m real symmetric positive definite matrix, returns the generalized least squares solution to the linear system A*x = b with covariance matrix proportional to V, that is, x minimizes (b - A*x)'*inv(V)*(b - A*x).

More generally, V can be positive semidefinite, and lscov returns x that minimizes e^+e , subject to $A^*x + T^*e = b$, where the minimization is over x and e, and $T^*T^+ = V$. When V is semidefinite, this problem has a solution only if b is consistent with A and V (that is, b is in the column space of [A T]), otherwise lscov returns an error.

By default, 1scov computes the Cholesky decomposition of V and, in effect, inverts that factor to transform the problem into ordinary least squares. However, if 1scov determines that V is semidefinite, it uses an orthogonal decomposition algorithm that avoids inverting V.

x = lscov(A,b,V,alg) specifies the algorithm used to compute x when V is a matrix. alg can have the following values:

- 'chol' uses the Cholesky decomposition of V.
- 'orth' uses orthogonal decompositions, and is more appropriate when V is ill-conditioned or singular, but is computationally more expensive.

[x,stdx] = 1scov(...) returns the estimated standard errors of x. When A is rank deficient, stdx contains zeros in the elements corresponding to the necessarily zero elements of x.

[x,stdx,mse] = lscov(...) returns the mean squared error.

[x,stdx,mse,S] = 1scov(...) returns the estimated covariance matrix of x. When A is rank deficient, S contains zeros in the rows and columns corresponding to the necessarily zero elements of x. 1scov cannot return S if it is called with multiple right-hand sides, that is, if size(B,2) > 1.

The standard formulas for these quantities, when A and V are full rank, are

- x = inv(A'*inv(V)*A)*A'*inv(V)*B
- mse = B'*(inv(V) inv(V)*A*inv(A'*inv(V)*A)*A'*inv(V))*B./(m-n)
- S = inv(A'*inv(V)*A)*mse
- stdx = sqrt(diag(S))

However, 1scov uses methods that are faster and more stable, and are applicable to rank deficient cases.

1scov assumes that the covariance matrix of B is known only up to a scale factor. mse is an estimate of that unknown scale factor, and 1scov scales the outputs S and stdx appropriately. However, if V is known to be exactly the covariance matrix of B, then that scaling is unnecessary.

To get the appropriate estimates in this case, you should rescale S and stdx by 1/mse and sqrt(1/mse), respectively.

Algorithm

The vector x minimizes the quantity (A*x-b)'*inv(V)*(A*x-b). The classical linear algebra solution to this problem is

```
x = inv(A'*inv(V)*A)*A'*inv(V)*b
```

but the 1scov function instead computes the QR decomposition of A and then modifies Q by V.

Examples

Example 1 — Computing Ordinary Least Squares

The MATLAB backslash operator (\) enables you to perform linear regression by computing ordinary least-squares (OLS) estimates of the regression coefficients. You can also use 1scov to compute the same OLS estimates. By using 1scov, you can also compute estimates of the standard errors for those coefficients, and an estimate of the standard deviation of the regression error term:

```
x1 = [.2 .5 .6 .8 1.0 1.1]';
x2 = [.1 .3 .4 .9 1.1 1.4]';
X = [ones(size(x1)) x1 x2];
y = [.17 .26 .28 .23 .27 .34]';
a = X \setminus y
a =
    0.1203
    0.3284
   -0.1312
[b,se_b,mse] = lscov(X,y)
b =
    0.1203
    0.3284
   -0.1312
seb =
    0.0643
```

```
0.2267
0.1488
mse =
0.0015
```

Example 2 — Computing Weighted Least Squares

Use 1scov to compute a weighted least-squares (WLS) fit by providing a vector of relative observation weights. For example, you might want to downweight the influence of an unreliable observation on the fit:

Example 3 — Computing General Least Squares

Use 1scov to compute a general least-squares (GLS) fit by providing an observation covariance matrix. For example, your data may not be independent:

```
0.0672
0.2267
0.1488
mseg =
0.0019
```

Example 4 — Estimating the Coefficient Covariance Matrix

Compute an estimate of the coefficient covariance matrix for either OLS, WLS, or GLS fits. The coefficient standard errors are equal to the square roots of the values on the diagonal of this covariance matrix:

```
[b,se\ b,mse,S] = lscov(X,y);
S
S =
    0.0041
              -0.0130
                          0.0075
   -0.0130
               0.0514
                         -0.0328
    0.0075
              -0.0328
                         0.0221
[se_b sqrt(diag(S))]
ans =
    0.0643
               0.0643
    0.2267
               0.2267
    0.1488
               0.1488
```

See Also

lsqnonneg, qr

The arithmetic operator \

Reference

[1] Strang, G., Introduction to Applied Mathematics, Wellesley-Cambridge, 1986, p. 398.

Isqnonneg

Purpose

Solve nonnegative least-squares constraints problem

Equation

Solves nonnegative least-squares curve fitting problems of the form

$$\min_{x} \|C \cdot x - d\|_{2}^{2}, \text{ where } x \ge 0.$$

Syntax

```
x = lsqnonneg(C,d)
x = lsqnonneg(C,d,options)
[x,resnorm] = lsqnonneg(...)
[x,resnorm,residual] = lsqnonneg(...)
[x,resnorm,residual,exitflag] = lsqnonneg(...)
[x,resnorm,residual,exitflag,output] = lsqnonneg(...)
[x,resnorm,residual,exitflag,output,lambda] = lsqnonneg(...)
```

Description

x = lsqnonneg(C,d) returns the vector x that minimizes norm(C*x-d) subject to $x \ge 0$. C and d must be real.

x = lsqnonneg(C,d,options) minimizes with the optimization parameters specified in the structure options. You can define these parameters using the optimset function. lsqnonneg uses these options structure fields:

Display Level of display. 'off' displays no output; 'final' displays just the final output; 'notify' (default) displays output only if the function does not converge.

TolX Termination tolerance on x.

[x,resnorm] = lsqnonneg(...) returns the value of the squared 2-norm of the residual: $norm(C*x-d)^2$.

[x,resnorm,residual] = lsqnonneg(...) returns the residual, d-C*x.

[x,resnorm,residual,exitflag] = lsqnonneg(...) returns a value exitflag that describes the exit condition of lsqnonneg:

>0 Indicates that the function converged to a solution x.

Indicates that the iteration count was exceeded.

Increasing the tolerance (TolX parameter in options)
may lead to a solution.

[x,resnorm,residual,exitflag,output] = lsqnonneg(...) returns a structure output that contains information about the operation in the following fields:

```
algorithm 'active-set'
iterations The number of iterations taken
message Exit message
```

[x,resnorm,residual,exitflag,output,lambda] = lsqnonneg(...) returns the dual vector (Lagrange multipliers) lambda, where lambda(i) <= 0 when x(i) is (approximately) 0, and lambda(i) is (approximately) 0 when x(i) > 0.

Examples

Compare the unconstrained least squares solution to the lsqnonneg solution for a 4-by-2 problem:

```
C = \Gamma
    0.0372
               0.2869
    0.6861
               0.7071
    0.6233
               0.6245
    0.6344
               0.6170];
1 = b
    0.8587
    0.1781
    0.0747
    0.8405];
[C\d lsqnonneg(C,d)] =
    -2.5627
                      0
     3.1108
                0.6929
[norm(C*(C\backslash d)-d) norm(C*lsqnonneg(C,d)-d)] =
     0.6674 0.9118
```

Isqnonneg

The solution from 1sqnonneg does not fit as well (has a larger residual), as the least squares solution. However, the nonnegative least squares solution has no negative components.

Algorithm

lsqnonneg uses the algorithm described in [1]. The algorithm starts
with a set of possible basis vectors and computes the associated dual
vector lambda. It then selects the basis vector corresponding to the
maximum value in lambda in order to swap out of the basis in exchange
for another possible candidate. This continues until lambda <= 0.</pre>

See Also

The arithmetic operator \, optimset

References

[1] Lawson, C.L. and R.J. Hanson, *Solving Least Squares Problems*, Prentice-Hall, 1974, Chapter 23, p. 161.

Purpose

LSQR method

Syntax

```
x = lsqr(A,b)
lsqr(A,b,tol)
lsqr(A,b,tol,maxit)
lsqr(A,b,tol,maxit,M)
lsqr(A,b,tol,maxit,M1,M2)
lsqr(A,b,tol,maxit,M1,M2,x0)
[x,flag] = lsqr(A,b,tol,maxit,M1,M2,x0)
[x,flag,relres] = lsqr(A,b,tol,maxit,M1,M2,x0)
[x,flag,relres,iter] = lsqr(A,b,tol,maxit,M1,M2,x0)
[x,flag,relres,iter,resvec] = lsqr(A,b,tol,maxit,M1,M2,x0)
[x,flag,relres,iter,resvec,lsvec] = lsqr(A,b,tol,maxit,M1,M2,x0)
[x,flag,relres,iter,resvec,lsvec] = lsqr(A,b,tol,maxit,M1,M2,x0)
```

Description

x = lsqr(A,b) attempts to solve the system of linear equations A*x=b for x if A is consistent, otherwise it attempts to solve the least squares solution x that minimizes norm(b-A*x). The m-by-n coefficient matrix A need not be square but it should be large and sparse. The column vector b must have length m. A can be a function handle afun such that afun(x,'notransp') returns A*x and afun(x,'transp') returns A'*x. See "Function Handles" in the MATLAB Programming documentation for more information.

"Parameterizing Functions", in the MATLAB Mathematics documentation, explains how to provide additional parameters to the function afun, as well as the preconditioner function mfun described below, if necessary.

If lsqr converges, a message to that effect is displayed. If lsqr fails to converge after the maximum number of iterations or halts for any reason, a warning message is printed displaying the relative residual norm(b-A*x)/norm(b) and the iteration number at which the method stopped or failed.

lsqr(A,b,tol) specifies the tolerance of the method. If tol is [], then
lsqr uses the default, 1e-6.

lsqr(A,b,tol,maxit) specifies the maximum number of iterations.

lsqr(A,b,tol,maxit,M) and lsqr(A,b,tol,maxit,M1,M2) use n-by-n preconditioner M or M = M1*M2 and effectively solve the system A*inv(M)*y = b for y, where y = M*x. If M is [] then lsqr applies no preconditioner. M can be a function mfun such that mfun(x,'notransp') returns M\x and mfun(x,'transp') returns M\x.

lsqr(A,b,tol,maxit,M1,M2,x0) specifies the n-by-1 initial guess. If x0 is [], then lsqr uses the default, an all zero vector.

[x,flag] = lsqr(A,b,tol,maxit,M1,M2,x0) also returns a convergence flag.

Flag	Convergence
0	lsqr converged to the desired tolerance tol within maxit iterations.
1	lsqr iterated maxit times but did not converge.
2	Preconditioner M was ill-conditioned.
3	1sqr stagnated. (Two consecutive iterates were the same.)
4	One of the scalar quantities calculated during 1sqr became too small or too large to continue computing.

Whenever flag is not 0, the solution x returned is that with minimal norm residual computed over all the iterations. No messages are displayed if you specify the flag output.

[x,flag,relres] = lsqr(A,b,tol,maxit,M1,M2,x0) also returns an estimate of the relative residual norm(b-A*x)/norm(b). If flag is 0, relres <= tol.

[x,flag,relres,iter] = lsqr(A,b,tol,maxit,M1,M2,x0) also
returns the iteration number at which x was computed, where 0 <=
iter <= maxit.</pre>

[x,flag,relres,iter,resvec] = lsqr(A,b,tol,maxit,M1,M2,x0) also returns a vector of the residual norm estimates at each iteration, including norm(b-A*x0).

[x,flag,relres,iter,resvec,lsvec] =
lsqr(A,b,tol,maxit,M1,M2,x0) also returns a vector of estimates
of the scaled normal equations residual at each iteration:
norm((A*inv(M))'*(B-A*X))/norm(A*inv(M),'fro'). Note that the
estimate of norm(A*inv(M),'fro') changes, and hopefully improves,
at each iteration.

Examples Example 1

```
n = 100;
on = ones(n,1);
A = spdiags([-2*on 4*on -on],-1:1,n,n);
b = sum(A,2);
tol = 1e-8;
maxit = 15;
M1 = spdiags([on/(-2) on],-1:0,n,n);
M2 = spdiags([4*on -on],0:1,n,n);
x = lsqr(A,b,tol,maxit,M1,M2);
```

displays the following message:

lsqr converged at iteration 11 to a solution with relative residual 3.5e-009

Example 2

This example replaces the matrix A in Example 1 with a handle to a matrix-vector product function afun. The example is contained in an M-file run_lsqr that

- Calls 1sqr with the function handle @afun as its first argument.
- Contains afun as a nested function, so that all variables in run_lsqr are available to afun.

The following shows the code for run lsqr:

```
function x1 = run_lsqr
```

```
n = 100;
  on = ones(n,1);
  A = spdiags([-2*on 4*on -on], -1:1,n,n);
  b = sum(A,2);
  tol = 1e-8;
  maxit = 15;
  M1 = spdiags([on/(-2) on], -1:0,n,n);
  M2 = spdiags([4*on -on], 0:1, n, n);
  x1 = lsqr(@afun,b,tol,maxit,M1,M2);
      function y = afun(x, transp flag)
          if strcmp(transp flag, 'transp')
                                                 % V = A' * X
             v = 4 * x;
             y(1:n-1) = y(1:n-1) - 2 * x(2:n);
             y(2:n) = y(2:n) - x(1:n-1);
          elseif strcmp(transp flag, 'notransp') % y = A*x
             y = 4 * x;
             y(2:n) = y(2:n) - 2 * x(1:n-1);
             y(1:n-1) = y(1:n-1) - x(2:n);
          end
       end
  end
When you enter
  x1=run lsqr;
MATLAB software displays the message
  lsqr converged at iteration 11 to a solution with relative
  residual 3.5e-009
bicg, bicgstab, cgs, gmres, minres, norm, pcg, gmr, symmlg,
function handle (@)
[1] Barrett, R., M. Berry, T. F. Chan, et al., Templates for the Solution
```

of Linear Systems: Building Blocks for Iterative Methods, SIAM,

Philadelphia, 1994.

See Also

References

Isqr

[2] Paige, C. C. and M. A. Saunders, "LSQR: An Algorithm for Sparse Linear Equations And Sparse Least Squares," $ACM\ Trans.\ Math.\ Soft.$, Vol.8, 1982, pp. 43-71.

Purpose

Test for less than

Syntax

A < B lt(A, B)

Description

A < B compares each element of array A with the corresponding element of array B, and returns an array with elements set to logical 1 (true) where A is less than B, or set to logical 0 (false) where A is greater than or equal to B. Each input of the expression can be an array or a scalar value.

If both A and B are scalar (i.e., 1-by-1 matrices), then the MATLABsoftware returns a scalar value.

If both A and B are nonscalar arrays, then these arrays must have the same dimensions, and MATLAB returns an array of the same dimensions as A and B.

If one input is scalar and the other a nonscalar array, then the scalar input is treated as if it were an array having the same dimensions as the nonscalar input array. In other words, if input A is the number 100, and B is a 3-by-5 matrix, then A is treated as if it were a 3-by-5 matrix of elements, each set to 100. MATLAB returns an array of the same dimensions as the nonscalar input array.

lt(A, B) is called for the syntax A < B when either A or B is an object.

Examples

Create two 6-by-6 matrices, A and B, and locate those elements of A that are less than the corresponding elements of B:

```
A = magic(6);
B = repmat(3*magic(3), 2, 2);
A < B
ans =
      0
             1
                           0
                                  0
                                         0
      1
             0
                    1
                           0
                                  0
                                         0
                                         0
      0
                           0
                                  0
      1
             0
                    0
                           1
                                  0
                                         1
```

See Also

 ${\tt gt},\,{\tt le},\,{\tt ge},\,{\tt ne},\,{\tt eq},\,{\tt `Relational Operators''}$ in the MATLAB Programming documentation

Purpose

LU matrix factorization

Syntax

```
Y = lu(A)
[L,U] = lu(A)
[L,U,P] = lu(A)
[L,U,P,Q] = lu(A)
[L,U,P,Q,R] = lu(A)
[...] = lu(A,'vector')
[...] = lu(A,thresh)
[...] = lu(A,thresh,'vector')
```

Description

The 1u function expresses a matrix A as the product of two essentially triangular matrices, one of them a permutation of a lower triangular matrix and the other an upper triangular matrix. The factorization is often called the LU, or sometimes the LR, factorization. A can be rectangular. For a full matrix A, 1u uses the Linear Algebra Package (LAPACK) routines described in "Algorithm" on page 2-2436.

Y = lu(A) returns matrix Y that, for sparse A, contains the strictly lower triangular L, i.e., without its unit diagonal, and the upper triangular U as submatrices. That is, if [L,U,P] = lu(A), then Y = U+L-eye(size(A)). For nonsparse A, Y is the output from the LAPACK dgetrf or zgetrf routine. The permutation matrix P is not returned.

[L,U] = lu(A) returns an upper triangular matrix in U and a permuted lower triangular matrix in L such that A = L*U. Return value L is a product of lower triangular and permutation matrices.

[L,U,P] = lu(A) returns an upper triangular matrix in U, a lower triangular matrix L with a unit diagonal, and a permutation matrix P, such that L*U = P*A. The statement lu(A, 'matrix') returns identical output values.

[L,U,P,Q] = lu(A) for sparse nonempty A, returns a unit lower triangular matrix L, an upper triangular matrix U, a row permutation matrix P, and a column reordering matrix Q, so that P*A*Q = L*U. This syntax uses UMFPACK and is significantly more time and memory efficient than the other syntaxes, even when used with colamd. If A

is empty or not sparse, lu displays an error message. The statement lu(A, 'matrix') returns identical output values.

[L,U,P,Q,R] = lu(A) returns unit lower triangular matrix L, upper triangular matrix U, permutation matrices P and Q, and a diagonal scaling matrix R so that P*(R\A)*Q = L*U for sparse non-empty A. This uses UMFPACK as well. Typically, but not always, the row-scaling leads to a sparser and more stable factorization. Note that this factorization is the same as that used by sparse mldivide when UMFPACK is used. The statement lu(A, 'matrix') returns identical output values.

[...] = lu(A, 'vector') returns the permutation information in two row vectors p and q. You can specify from 1 to 5 outputs. Output p is defined as A(p,:)=L*U, output q is defined as A(p,q)=L*U, and output R is defined as R(:,p) A(:,q)=L*U.

[...] = lu(A,thresh) controls pivoting in UMFPACK. This syntax applies to sparse matrices only. The thresh input is a one-or two-element vector of type single or double that defaults to [0.1, 0.001]. If A is a square matrix with a mostly symmetric structure and mostly nonzero diagonal, UMFPACK uses a symmetric pivoting strategy. For this strategy, the diagonal where

```
A(i,j) >= thresh(2) * max(abs(A(j:m,j)))
```

is selected. If the diagonal entry fails this test, a pivot entry below the diagonal is selected, using thresh(1). In this case, L has entries with absolute value 1/min(thresh) or less.

If A is not as described above, UMFPACK uses an asymmetric strategy. In this case, the sparsest row i where

```
A(i,j) >= thresh(1) * max(abs(A(j:m,j)))
```

is selected. A value of 1.0 results in conventional partial pivoting. Entries in L have an absolute value of 1/thresh(1) or less. The second element of the thresh input vector is not used when UMFPACK uses an asymmetric strategy.

Smaller values of thresh(1) and thresh(2) tend to lead to sparser LU factors, but the solution can become inaccurate. Larger values can lead to a more accurate solution (but not always), and usually an increase in the total work and memory usage. The statement lu(A,thresh,'matrix') returns identical output values.

[...] = lu(A,thresh,'vector') controls the pivoting strategy and also returns the permutation information in row vectors, as described above. The thresh input must precede 'vector' in the input argument list.

Note In rare instances, incorrect factorization results in $P*A*Q \neq L*U$. Increase thresh, to a maximum of 1.0 (regular partial pivoting), and try again.

Remarks

Most of the algorithms for computing LU factorization are variants of Gaussian elimination. The factorization is a key step in obtaining the inverse with inv and the determinant with det. It is also the basis for the linear equation solution or matrix division obtained with \ and /.

Arguments

Α	Rectangular matrix to be factored.	
thresh	Pivot threshold for sparse matrices. Valid values are in the interval [0,1]. If you specify the fourth output Q, the default is 0.1. Otherwise, the default is 1.0.	
L	Factor of A. Depending on the form of the function, L is either a unit lower triangular matrix, or else the product of a unit lower triangular matrix with P'.	
U	Upper triangular matrix that is a factor of A.	
P	Row permutation matrix satisfying the equation L*U = P*A, or L*U = P*A*Q. Used for numerical stability.	

- Column permutation matrix satisfying the equation P*A*Q = L*U. Used to reduce fill-in in the sparse case.
- R Row-scaling matrix

Examples Example 1

Start with

To see the LU factorization, call lu with two output arguments.

Notice that L1 is a permutation of a lower triangular matrix: if you switch rows 2 and 3, and then switch rows 1 and 2, the resulting matrix is lower triangular and has 1s on the diagonal. Notice also that U is upper triangular. To check that the factorization does its job, compute the product

L1*U

which returns the original A. The inverse of the example matrix, X = inv(A), is actually computed from the inverses of the triangular factors

```
X = inv(U)*inv(L1)
```

Using three arguments on the left side to get the permutation matrix as well,

$$[L2,U,P] = lu(A)$$

returns a truly lower triangular L2, the same value of U, and the permutation matrix P.

Note that L2 = P*L1.

To verify that L2*U is a permuted version of A, compute L2*U and subtract it from P*A:

In this case, inv(U)*inv(L) results in the permutation of inv(A) given by inv(P)*inv(A).

The determinant of the example matrix is

$$d = det(A)$$
$$d = 27$$

It is computed from the determinants of the triangular factors

$$d = det(L)*det(U)$$

The solution to Ax = b is obtained with matrix division

$$x = A \setminus b$$

The solution is actually computed by solving two triangular systems

$$y = L b$$

 $x = U y$

Example 2

The 1-norm of their difference is within roundoff error, indicating that L*U = P*B*Q.

Generate a 60-by-60 sparse adjacency matrix of the connectivity graph of the Buckminster-Fuller geodesic dome.

$$B = bucky;$$

Use the sparse matrix syntax with four outputs to get the row and column permutation matrices.

```
[L,U,P,Q] = lu(B);
```

Apply the permutation matrices to B, and subtract the product of the lower and upper triangular matrices.

```
Z = P*B*Q - L*U;
norm(Z,1)
ans =
7.9936e-015
```

Example 3

This example illustrates the benefits of using the 'vector' option. Note how much memory is saved by using the lu(F, 'vector') syntax.

```
F = gallery('uniformdata',[1000 1000],0);
g = sum(F,2);
[L,U,P] = lu(F);
[L,U,p] = lu(F,'vector');
whos P p
Name
              Size
                             Bytes Class
                                                Attributes
                           8000000
Ρ
           1000x1000
                                    double
              1x1000
                              8000
                                    double
р
```

The following two statements are equivalent. The first typically requires less time:

```
x = U\(L\(g(p,:)));
y = U\(L\(P*g));
```

Algorithm

For full matrices X, 1u uses the LAPACK routines listed in the following table.

	Real	Complex
X double	DGETRF	ZGETRF
X single	SGETRF	CGETRF

For sparse X, with four outputs, 1u uses UMFPACK routines. With three or fewer outputs, 1u uses its own sparse matrix routines.

See Also

cond, det, inv, luinc, qr, rref

The arithmetic operators \ and /

References

[1] Anderson, E., Z. Bai, C. Bischof, S. Blackford, J. Demmel, J. Dongarra, J. Du Croz, A. Greenbaum, S. Hammarling, A. McKenney, and D. Sorensen, *LAPACK User's Guide* (http://www.netlib.org/lapack/lug/lapack_lug.html), Third Edition, SIAM, Philadelphia, 1999.

[2] Davis, T. A., *UMFPACK Version 4.6 User Guide* (http://www.cise.ufl.edu/research/sparse/umfpack), Dept. of Computer and Information Science and Engineering, Univ. of Florida, Gainesville, FL, 2002.

Purpose

Sparse incomplete LU factorization

Syntax

```
luinc(A, '0')
luinc(A, droptol)
luinc(A, options)
[L,U] = luinc(A,0)
[L,U] = luinc(A, options)
[L,U,P] = luinc(...)
```

Description

luinc produces a unit lower triangular matrix, an upper triangular matrix, and a permutation matrix.

luinc(A, '0') computes the incomplete LU factorization of level 0 of a square sparse matrix. The triangular factors have the same sparsity pattern as the permutation of the original sparse matrix A, and their product agrees with the permuted A over its sparsity pattern. luinc(A, '0') returns the strict lower triangular part of the factor and the upper triangular factor embedded within the same matrix. The permutation information is lost, but nnz(luinc(A, '0')) = nnz(A), with the possible exception of some zeros due to cancellation.

luinc(A,droptol) computes the incomplete LU factorization of any sparse matrix using the drop tolerance specified by the non-negative scalar droptol. The result is an approximation of the complete LU factors returned by lu(A). For increasingly smaller values of the drop tolerance, this approximation improves until the drop tolerance is 0, at which time the complete LU factorization is produced, as in lu(A).

As each column j of the triangular incomplete factors is being computed, the entries smaller in magnitude than the local drop tolerance (the product of the drop tolerance and the norm of the corresponding column of A)

```
droptol*norm(A(:,j))
```

are dropped from the appropriate factor.

The only exceptions to this dropping rule are the diagonal entries of the upper triangular factor, which are preserved to avoid a singular factor.

luinc (A, options) computes the factorization with up to four options. These options are specified by fields of the input structure options. The fields must be named exactly as shown in the table below. You can include any number of these fields in the structure and define them in any order. Any additional fields are ignored.

Field Name	Description
droptol	Drop tolerance of the incomplete factorization.
milu	If milu is 1, luinc produces the modified incomplete LU factorization that subtracts the dropped elements in any column from the diagonal element of the upper triangular factor. The default value is 0.
udiag	If udiag is 1, any zeros on the diagonal of the upper triangular factor are replaced by the local drop tolerance. The default is 0.
thresh	Pivot threshold between 0 (forces diagonal pivoting) and 1, the default, which always chooses the maximum magnitude entry in the column to be the pivot. thresh is described in greater detail in the 1u reference page.

luinc(A, options) is the same as luinc(A, droptol) if options has droptol as its only field.

[L,U] = luinc(A,0) returns the product of permutation matrices and a unit lower triangular matrix in L and an upper triangular matrix in U. The exact sparsity patterns of L, U, and A are not comparable but the number of nonzeros is maintained with the possible exception of some zeros in L and U due to cancellation:

$$nnz(L)+nnz(U) = nnz(A)+n$$
, where A is n-by-n.

The product L*U agrees with A over its sparsity pattern. (L*U).*spones(A)-A has entries of the order of eps.

[L,U] = luinc(A,options) returns a permutation of a unit lower triangular matrix in L and an upper triangular matrix in U. The product L*U is an approximation to A. luinc(A,options) returns the strict lower triangular part of the factor and the upper triangular factor embedded within the same matrix. The permutation information is lost.

[L,U,P] = luinc(...) returns a unit lower triangular matrix in L, an upper triangular matrix in U, and a permutation matrix in P.

[L,U,P] = luinc(A,'0') returns a unit lower triangular matrix in L, an upper triangular matrix in U and a permutation matrix in P. L has the same sparsity pattern as the lower triangle of permuted A

```
spones(L) = spones(tril(P*A))
```

with the possible exceptions of 1s on the diagonal of L where P*A may be zero, and zeros in L due to cancellation where P*A may be nonzero. U has the same sparsity pattern as the upper triangle of P*A

```
spones(U) = spones(triu(P*A))
```

with the possible exceptions of zeros in U due to cancellation where P*A may be nonzero. The product L*U agrees within rounding error with the permuted matrix P*A over its sparsity pattern. (L*U).*spones(P*A)-P*A has entries of the order of eps.

[L,U,P] = luinc(A,options) returns a unit lower triangular matrix in L, an upper triangular matrix in U, and a permutation matrix in P. The nonzero entries of U satisfy

```
abs(U(i,j)) >= droptol*norm((A:,j)),
```

with the possible exception of the diagonal entries, which were retained despite not satisfying the criterion. The entries of L were tested against the local drop tolerance before being scaled by the pivot, so for nonzeros in L

```
abs(L(i,j)) >= droptol*norm(A(:,j))/U(j,j).
```

The product L*U is an approximation to the permuted P*A.

Remarks

These incomplete factorizations may be useful as preconditioners for solving large sparse systems of linear equations. The lower triangular factors all have 1s along the main diagonal but a single 0 on the diagonal of the upper triangular factor makes it singular. The incomplete factorization with a drop tolerance prints a warning message if the upper triangular factor has zeros on the diagonal. Similarly, using the udiag option to replace a zero diagonal only gets rid of the symptoms of the problem but does not solve it. The preconditioner may not be singular, but it probably is not useful and a warning message is printed.


Limitations


luinc(X, '0') works on square matrices only.

Examples

Start with a sparse matrix and compute its LU factorization.

```
load west0479;
S = west0479;
[L,U] = lu(S);
```






Compute the incomplete LU factorization of level 0.

```
[L,U,P] = luinc(S,'0');
D = (L*U).*spones(P*S)-P*S;
```


spones(U) and spones(triu(P*S)) are identical.


spones(L) and spones(tril(P*S)) disagree at 73 places on the diagonal, where L is 1 and P*S is 0, and also at position (206,113), where L is 0 due to cancellation, and P*S is -1. D has entries of the order of eps.



A drop tolerance of 0 produces the complete LU factorization. Increasing the drop tolerance increases the sparsity of the factors (decreases the number of nonzeros) but also increases the error in the factors, as seen in the plot of drop tolerance versus norm(L*U-P*S,1)/norm(S,1) in the second figure below.

luinc





Algorithm

luinc(A, '0') is based on the "KJI" variant of the LU factorization with partial pivoting. Updates are made only to positions which are nonzero in A.

luinc(A,droptol) and luinc(A,options) are based on the column-oriented lu for sparse matrices.

See Also

bicg, cholinc,ilu, lu

References

[1] Saad, Yousef, *Iterative Methods for Sparse Linear Systems*, PWS Publishing Company, 1996, Chapter 10 - Preconditioning Techniques.

Magic square

Syntax

M = magic(n)

Description

M = magic(n) returns an n-by-n matrix constructed from the integers 1 through n^2 with equal row and column sums. The order n must be a scalar greater than or equal to 3.

Remarks

A magic square, scaled by its magic sum, is doubly stochastic.

Examples

The magic square of order 3 is

$$M = magic(3)$$

M =

8 1 6 3 5 7 4 9 2

This is called a magic square because the sum of the elements in each column is the same.

And the sum of the elements in each row, obtained by transposing twice, is the same.

This is also a special magic square because the diagonal elements have the same sum.

```
sum(diag(M)) =
15
```

The value of the characteristic sum for a magic square of order \boldsymbol{n} is

```
sum(1:n^2)/n
```

which, when n = 3, is 15.

Algorithm

There are three different algorithms:

- n odd
- n even but not divisible by four
- n divisible by four

To make this apparent, type


```
for n = 3:20
    A = magic(n);
    r(n) = rank(A);
end
```


For n odd, the rank of the magic square is n. For n divisible by 4, the rank is 3. For n even but not divisible by 4, the rank is n/2 + 2.


```
[(3:20)',r(3:20)']
ans =
      3
             3
      4
             3
      5
             5
             5
      6
     7
             7
      8
             3
     9
             9
             7
    10
    11
            11
```

12	3
13	13
14	9
15	15
16	3
17	17
18	11
19	19
20	3

Plotting A for $n=18,\,19,\,20$ shows the characteristic plot for each category.







Limitations

If you supply n less than 3, magic returns either a nonmagic square, or else the degenerate magic squares 1 and [].

See Also

ones, rand

Create 4-by-4 transform matrix

Syntax

```
M = makehgtform
M = makehgtform('translate',[tx ty tz])
M = makehgtform('scale',s)
M = makehgtform('scale',[sx,sy,sz])
M = makehgtform('xrotate',t)
M = makehgtform('yrotate',t)
M = makehgtform('zrotate',t)
M = makehgtform('axisrotate',[ax,ay,az],t)
```

Description

Use makehgtform to create transform matrices for translation, scaling, and rotation of graphics objects. Apply the transform to graphics objects by assigning the transform to the Matrix property of a parent hgtransform object. See Examples for more information.

M = makehgtform returns an identity transform.

M = makehgtform('translate',[tx ty tz]) or M = makehgtform('translate',tx,ty,tz) returns a transform that translates along the x-axis by tx, along the y-axis by ty, and along the z-axis by tz.

M = makehgtform('scale',s) returns a transform that scales uniformly along the x-, y-, and z-axes.

M = makehgtform('scale',[sx,sy,sz]) returns a transform that scales along the x-axis by sx, along the y-axis by sy, and along the z-axis by sz.

M = makehgtform('xrotate',t) returns a transform that rotates around the x-axis by t radians.

M = makehgtform('yrotate',t) returns a transform that rotates around the y-axis by t radians.

M = makehgtform('zrotate',t) returns a transform that rotates around the z-axis by t radians.

M = makehgtform('axisrotate',[ax,ay,az],t) Rotate around axis [ax ay az] by tradians.

Note that you can specify multiple operations in one call to makehgtform and the MATLAB software returns a transform matrix that is the result of concatenating all specified operations. For example,

```
m = makehgtform('xrotate',pi/2,'yrotate',pi/2);
is the same as
m = makehgtform('xrotate',pi/2)*makehgtform('yrotate',pi/2);
```

See Also

hggroup, hgtransform

Tomas Moller and Eric Haines, *Real-Time Rendering*, A K Peters, Ltd., 1999 for more information about transforms.

"Group Objects" in MATLAB Graphics documentation for more information and examples.

Hgtransform Properties for property descriptions.

Construct containers. Map object

Syntax

M = containers.Map

M = containers.Map('KeyType', kType, 'ValueType', vType)

M = containers.Map(keys, values)

M = containers.Map(keys, values, 'uniformvalues', tf)

Description

M = containers.Map constructs an empty Map container, M, a data structure similar to a MATLAB array except for the means by which you address the data stored inside. Rather than being restricted to the use of integer array indices 1 through N, you can select elements of a Map using indices of various data types, (strings, for example).

Object M has properties KeyType, ValueType and Count. KeyType specifies the data type of the keys (indices) used in accessing elements of the map. ValueType specifies the data type of the values in the map. If these values are of different data types, then ValueType is set to 'any'. Count specifies the number of key-value pairs in the Map object once the map has been constructed. This syntax for the above constructor sets these properties to 'O', 'char', and 'any', respectively.

M = containers.Map('KeyType', kType, 'ValueType', vType) constructs an empty Map object with properties KeyType and ValueType set to string values kType and vType, respectively. The Count property is set to zero. The order of the key type and value type argument pairs is not important. However, you must pass all four inputs.

Valid values for kType and vType are:

kType	'char', 'double', 'single', 'int32', 'uint32', 'int64', 'uint64'
vТуре	'char', 'double', 'single', 'int8', 'uint8', 'int16', 'uint16', 'int32', 'int64', 'uint64', 'logical', 'any'

M = containers.Map(keys, values) constructs a Map object M that contains one or more keys and a value for each of these keys, as specified in the keys and values arguments. A value is some unit of data that

you want stored in the Map object, and a key is a unique reference to that data. Valid data types for the *keys* argument are any numeric real scalars or character arrays. Values can be of any type.

To specify multiple keys, make the keys argument a 1-by-n array or cell array, where n is the number of keys to be stored in the map. Elements of this array should belong to the same type. For strings, use a cell array of strings. You can specify values of mixed numeric, or numeric and logical, types, without generating an error. If you do this, the Map constructor converts all elements to the type of the leftmost element in the keys array.

To specify multiple values, use a 1-by-n array or cell array, where n is equal to numel (keys). There must be exactly one value for each key argument.

M = containers.Map(keys, values, 'uniformvalues', tf) constructs Map M in which all values are required to be of the same type when tf is set to logical 1 (true). If they are not, MATLAB throws an error. If you want to be able to store values of mixed types, set tf to logical 0 (false). This flag is only needed if you want to override the default.

Read more about Map Containers in the MATLAB Programming Fundamentals documentation.

Properties

Property	Description
Count	Unsigned 64-bit integer that represents the total number of key-value pairs contained in the Map object when the initial object is constructed.
КеуТуре	Character array that indicates the data type of all keys contained in the Map object.
ValueType	Character array that indicates the data type of all values contained in the Map object. If not all values have the same data type, then ValueType is 'any'.

Methods

Method	Description
isKey	Check if containers.Map object contains key.
keys	Return all keys of containers.Map object.
size	Return size of containers.Map object.
length	Return length of containers.Map object.
values	Return all values of containers. Map object in cell array.
remove	Remove key-value pairs from containers.Map.

Examples

Example 1 - Constructing a New Map Object

Construct a one-member Map object, US_Capitals:

```
US Capitals = containers.Map('Arizona', 'Phoenix');
```

To call methods of the class, just use the method name followed by the name of the Map object in parentheses. Call the keys and values methods of the US Capitals object you just constructed:

```
keys(US_Capitals), values(US_Capitals)
ans =
    'Arizona'
ans =
    'Phoenix'
```

Create a second Map object by specifying the key and value types at the time you call the constructor:

```
Account_Info = containers.Map( ...
    'KeyType', 'int32', 'ValueType', 'char')
Account_Info =
    containers.Map handle
    Package: containers
```

```
Properties:
    Count: 0
    KeyType: 'int32'
    ValueType: 'char'
Methods, Events, Superclasses
```

Example 2 – Finding Map Properties

```
List the properties of the US_Capitals object:
```

```
properties(US_Capitals)

Properties for class containers.Map:
    Count
    KeyType
    ValueType
```

Examine each property:

```
US_Capitals.Count
ans =
    1

US_Capitals.KeyType
ans =
    char

US_Capitals.ValueType
ans =
    char
```

Example 3 — Storing Multiple Keys and Values

Construct a new Map object and store six key and value parameters in it. Specify multiple keys and values by listing them in a cell array as shown here:

```
US_Capitals = containers.Map( ...
{'Arizona', 'Nebraska', 'Nevada', ... % 6 States
```

```
'New York', 'Georgia', 'Alaska'}, ...
{'Phoenix', 'Lincoln', 'Carson City', ... % 6 Capitals
'Albany', 'Atlanta', 'Juneau'})

US_Capitals =
  containers.Map handle
  Package: containers

Properties:
     Count: 6
     KeyType: 'char'
     ValueType: 'char'
     Methods, Events, Superclasses
```

Example 4 — Displaying the Map Contents

Use the keys and values methods to see the mapping order defined within the map. The keys method lists all keys of the character array type in alphabetical order. The values method lists the value associated with each of these keys. These are listed in an order determined by their associated keys:

```
keys(US_Capitals), values(US_Capitals)
ans =
    'Alaska' 'Arizona' 'Georgia' 'Nebraska' 'Nevada'

'New York'
ans =
    'Juneau' 'Phoenix' 'Atlanta' 'Lincoln' 'Carson City'
    'Albany'
```

When using the values method, you can either list all values in the map, as shown above, or list only those values that belong to those keys you specify in the command:

```
values(US_Capitals, {'Arizona', 'New York', 'Nebraska'})
ans =
    'Phoenix' 'Albany' 'Lincoln'
```

Example 5 — Adding More Keys and Values Later

Once the object has been created, store two additional keys (Vermont and Oregon), and their related values (Montpelier and Salem) in it. You do not need to call the constructor this time as you are adding to an existing Map object:

```
US_Capitals('Vermont') = 'Montpelier';
US_Capitals('Oregon') = 'Salem';
keys(US_Capitals)
ans =
   Columns 1 through 4
   'Alaska' 'Arizona' 'Georgia' 'Nebraska'
Columns 5 through 8
   'Nevada' 'New York' 'Oregon' 'Vermont'
```

Note that the Count property has gone from 6 to 8:

```
US_Capitals.Count
ans =
8
```

If you want to add more than one key-value pair at a time, you can concatenate your existing map with a new map that contains the new keys and values that you want to add. Only vertical concatenation is allowed. This example adds four more state/capital pairs to the US_Capitals map in just one concatenation operation. The US Capitals map now contains twelve key-value pairs:

```
newSta = {'New Jersey', 'Ohio', 'Delaware', 'Montana'};
newCap = {'Trenton', 'Columbus', 'Dover', 'Helena'};
newMap = containers.Map(newSta, newCap);

% Construct a new map. Concatenate it to the existing one.
US_Capitals = [US_Capitals; newMap]
US_Capitals = containers.Map handle
Package: containers
```

Example 6 - Looking Up Values with the Map

Use the map to find the capital cities of two states in the US:

Example 7 - Using Cell and Numeric Arrays

Create a map of US state populations by entering the keys of the map (which are strings) in a cell array, and the values (which are doubles) in a numeric array:

Example 8 — Removing Keys and Values

To remove a key-value pair, use the remove method of the Map class, as shown here:

```
keys(US_Capitals)
ans =
  Columns 1 through 4
    'Alaska'
                'Arizona'
                              'Delaware'
                                             'Georgia'
  Columns 5 through 8
    'Montana'
                  'Nebraska'
                                'Nevada'
                                             'New Jersey'
  Columns 9 through 12
    'New York'
                  'Ohio'
                             'Oregon'
                                         'Vermont'
remove(US Capitals, {'Nebraska', 'Nevada', 'New York'});
keys(US Capitals)
ans =
  Columns 1 through 4
    'Alaska'
                 'Arizona'
                              'Delaware'
                                             'Georgia'
  Columns 5 through 8
    'Montana'
                 'New Jersey'
                                  'Ohio'
                                             'Oregon'
  Column 9
    'Vermont'
```

Removing keys and their values from the Map object also decrements the setting of the Count property.

See Also

```
keys(Map), values(Map), size(Map), length(Map), isKey(Map),
remove(Map), handle
```

Divide matrix into cell array of matrices


Syntax

```
c = mat2cell(x, m, n)
c = mat2cell(x, d1, d2, ..., dn)
c = mat2cell(x, r)
```

Description

c = mat2cell(x, m, n) divides the two-dimensional matrix x into adjacent submatrices, each contained in a cell of the returned cell array c. Vectors m and n specify the number of rows and columns, respectively, to be assigned to the submatrices in c.

The example shown below divides a 60-by-50 matrix into six smaller matrices. The MATLAB software returns the new matrices in a 3-by-2 cell array:



The sum of the element values in m must equal the total number of rows in x. And the sum of the element values in n must equal the number of columns in x.

The elements of m and n determine the size of each cell in c by satisfying the following formula for i = 1:length(m) and j = 1:length(n):

```
size(c\{i,j\}) == [m(i) n(j)]
```

c = mat2cell(x, d1, d2, ..., dn) divides the multidimensional array x and returns a multidimensional cell array of adjacent submatrices of x. Each of the vector arguments d1 through dn should sum to the respective dimension sizes of x such that, for p = 1:n,

```
size(x,p) == sum(dp)
```

The elements of d1 through dn determine the size of each cell in c by satisfying the following formula for ip = 1:length(dp):

```
size(c\{i1,i2,...,in\}) == [d1(i1) d2(i2) ... dn(in)]
```

If x is an empty array, mat2cell returns an empty cell array. This requires that all dn inputs that correspond to the zero dimensions of x be equal to [].

For example,

```
a = rand(3,0,4);

c = mat2cell(a, [1 2], [], [2 1 1]);
```

c = mat2cell(x, r) divides an array x by returning a single-column cell array containing full rows of x. The sum of the element values in vector r must equal the number of rows of x.

The elements of r determine the size of each cell in c, subject to the following formula for i = 1:length(r):

$$size(c\{i\},1) == r(i)$$

Remarks

mat2cell supports all array types.

Examples

Divide matrix X into 2-by-3 and 2-by-2 matrices contained in a cell array:

```
16
         17 18 19
                           20
C = mat2cell(X, [2 2], [3 2])
C =
    [2x3 double]
                 [2x2 double]
    [2x3 double] [2x2 double]
C{1,1}
                               C{1,2}
ans =
                               ans =
     1
          2
                3
                                    4
                                          5
          7
     6
                8
                                    9
                                         10
C{2,1}
                               C{2,2}
ans =
                               ans =
    11
          12
                13
                                   14
                                         15
    16
         17
                                   19
                                         20
               18
```

See Also

cell2mat, num2cell

Convert matrix to string

Syntax

```
str = mat2str(A)
str = mat2str(A,n)
str = mat2str(A, 'class')
str = mat2str(A, n, 'class')
```

Description

str = mat2str(A) converts matrix A into a string. This string is
suitable for input to the eval function such that eval(str) produces
the original matrix to within 15 digits of precision.

str = mat2str(A,n) converts matrix A using n digits of precision.

str = mat2str(A, 'class') creates a string with the name of the
class of A included. This option ensures that the result of evaluating str
will also contain the class information.

str = mat2str(A, n, 'class') uses n digits of precision and includes
the class information.

Limitations

The mat2str function is intended to operate on scalar, vector, or rectangular array inputs only. An error will result if A is a multidimensional array.

Examples

Example 1

Consider the matrix

```
x = [3.85 2.91; 7.74 8.99]
x =
3.8500 2.9100
7.7400 8.9900
```

The statement

```
A = mat2str(x)
```

produces

```
A = [3.85 2.91;7.74 8.99]
```

where A is a string of 21 characters, including the square brackets, spaces, and a semicolon.

eval(mat2str(x)) reproduces x.

Example 2

Create a 1-by-6 matrix of signed 16-bit integers, and then use mat2str to convert the matrix to a 1-by-33 character array, A. Note that output string A includes the class name, int16:

```
x1 = int16([-300 407 213 418 32 -125]);
A = mat2str(x1, 'class')
A =
   int16([-300 407 213 418 32 -125])

class(A)
ans =
   char
```

Evaluating the string A gives you an output x2 that is the same as the original int16 matrix:

```
x2 = eval(A);
if isnumeric(x2) && isa(x2, 'int16') && all(x2 == x1)
   disp 'Conversion back to int16 worked'
end
```

Conversion back to int16 worked

See Also

num2str, int2str, str2num, sprintf, fprintf

Control reflectance properties of surfaces and patches

Syntax

material shiny
material dull
material metal
material([ka kd ks])
material([ka kd ks n])
material([ka kd ks n sc])
material default

Description

material sets the lighting characteristics of surface and patch objects.

material shiny sets the reflectance properties so that the object has a high specular reflectance relative to the diffuse and ambient light, and the color of the specular light depends only on the color of the light source.

material dull sets the reflectance properties so that the object reflects more diffuse light and has no specular highlights, but the color of the reflected light depends only on the light source.

material metal sets the reflectance properties so that the object has a very high specular reflectance, very low ambient and diffuse reflectance, and the color of the reflected light depends on both the color of the light source and the color of the object.

material([ka kd ks]) sets the ambient/diffuse/specular strength of the objects.

material([ka kd ks n]) sets the ambient/diffuse/specular strength
and specular exponent of the objects.

material([ka kd ks n sc]) sets the ambient/diffuse/specular strength, specular exponent, and specular color reflectance of the objects.

material default sets the ambient/diffuse/specular strength, specular exponent, and specular color reflectance of the objects to their defaults.

material

Remarks The material command sets the AmbientStrength,

DiffuseStrength, SpecularStrength, SpecularExponent,

and SpecularColorReflectance properties of all surface and patch objects in the axes. There must be visible light objects in the axes for lighting to be enabled. Look at the materal.m file to see the actual

values set (enter the command type material).

See Also light, lighting, patch, surface

Lighting as a Visualization Tool for more information on lighting

"Lighting" on page 1-111 for related functions

Run specified function via hyperlink

Syntax

disp('hyperlink_text')

Description

matlab: executes stmnt_1 through stmnt_n when you click in hyperlink_text. This must be used with another function, such as disp, where disp creates and displays underlined and colored hyperlink_text in the Command Window. Use disp, error, fprintf, help, or warning functions to display the hyperlink. The hyperlink_text is interpreted as HTML—you might need to use ASCII values for some special characters. Include the full hypertext string, from '<a href=to ' within a single line, that is, do not continue a long string on a new line. No spaces are allowed after the opening < and before the closing >. A single space is required between a and href.

Remarks

The matlab: function behaves differently with diary, notebook, type, and similar functions than might be expected. For example, if you enter the following statement

```
disp('<a href="matlab:magic(4)">Generate magic square</a>')
```

the diary file, when viewed in a text editor, shows

```
disp('<a href="matlab:magic(4)">Generate magic square</a>')
<a href="matlab:magic(4)">Generate magic square</a>
```

If you view the output of diary in the Command Window, the Command Window interprets the <a href ...> statement and displays it as a hyperlink.

Examples

Single Function

The statement

```
disp('<a href="matlab:magic(4)">Generate magic square</a>')
```

displays

matlabcolon (matlab:)

Generate magic square

in the Command Window. When you click the link Generate magic square, the MATLAB software runs magic (4).

Multiple Functions

You can include multiple functions in the statement, such as

```
\label{eq:continuous} \begin{array}{ll} disp('<a href="matlab: x=0:1:8;y=sin(x);plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,y)">Plot(x,
```

which displays

Plot x,y

in the Command Window. When you click the link, MATLAB runs

```
x = 0:1:8;
y = sin(x);
plot(x,y)
```

Clicking the Hyperlink Again

After running the statements in the hyperlink Plot x,y defined in the previous example, "Multiple Functions" on page 2-2466, you can subsequently redefine x in the base workspace, for example, as

```
x = -2*pi:pi/16:2*pi;
```

If you then click the hyperlink, Plot x, y, it changes the current value of x back to

```
0:1:8
```

because the matlab: statement defines x in the base workspace. In the matlab: statement that displayed the hyperlink, Plot x,y,x was defined as 0:1:8.

Presenting Options

Use multiple matlab: statements in a file to present options, such as

```
disp('<a href = "matlab:state = 0">Disable feature</a>')
disp('<a href = "matlab:state = 1">Enable feature</a>')
```

The Command Window displays the links that follow, and depending on which link is clicked, sets state to 0 or 1.

Disable feature Enable feature

Special Characters

MATLAB correctly interprets most strings that include special characters, such as a greater than symbol (>). For example, the following statement includes a >

```
disp('<a href="matlab:str = ''Value > 0''">Positive</a>')
```

and generates the following hyperlink.

Positive

Some symbols might not be interpreted correctly and you might need to use the ASCII value for the symbol. For example, an alternative way to run the previous statement is to use ASCII 62 instead of the greater than symbol (>):

```
disp('<a href="matlab:str=[''Value '' char(62) '' 0'']">Positive</a>')
```

Links from Function Help

For functions you create, you can include matlab: links within the help, but you do not need to include a disp or similar statement because the help function already includes it for displaying hyperlinks. Use the links to display additional help in a browser when the user clicks them. The file soundspeed.m contains the following statements:

```
function c=soundspeed(s,t,p)
```

matlabcolon (matlab:)

```
% Speed of sound in water, using
% <a href="matlab: web('http://www.zu.edu')">Wilson's formula</a>
% Where c is the speed of sound in water in m/s
```

etc.

Run help soundspeed and MATLAB displays the following in the Command Window.

```
>> help soundspeed
  Speed of sound in water, using
  <u>Wilson's formula</u>
  Where c is the speed of sound in water in m/s
```

When you click the link Wilson's formula, MATLAB displays the HTML page http://www.zu.edu in the Web browser. Note that this URL is only an example and is intentionally invalid.

See Also

disp, error, fprintf, input, run, warning

Startup M-file for MATLAB program

Description

At startup time, MATLAB automatically executes the master M-file matlabrc.m and, if it exists, startup.m. On multiuser or networked systems, matlabrc.m is reserved for use by the system manager. The file matlabrc.m invokes the file startup.m if it exists on the search path MATLAB uses.

As an individual user, you can create a startup file in your own MATLAB directory. Use the startup file to define physical constants, engineering conversion factors, graphics defaults, or anything else you want predefined in your workspace.

Algorithm

Only matlabrc is actually invoked by MATLAB at startup. However, matlabrc.m contains the statements

```
if exist('startup') == 2
    startup
end
```

that invoke startup.m. Extend this process to create additional startup M-files, if required.

Remarks

You can also start MATLAB using options you define at the Command Window prompt or in your Microsoft Windows shortcut for MATLAB.

Examples

Turning Off the Figure Window Toolbar

If you do not want the toolbar to appear in the figure window, remove the comment marks from the following line in the matlabrc.m file, or create a similar line in your own startup.m file.

```
set(0,'defaultfiguretoolbar','none')
```

See Also

matlabroot, quit, restoredefaultpath, startup

Startup Options in the MATLAB Desktop Tools and Development Environment documentation

matlabroot

Purpose Root folder

Syntax matlabroot

mr = matlabroot

Description matlabroot returns the name of the folder where the MATLAB

software is installed. Use ${\tt matlabroot}$ to create a path to MATLAB and toolbox folders that does not depend on a specific platform, MATLAB

version, or installation location.

 \mbox{mr} = $\mbox{matlabroot}$ returns the name of the folder in which the \mbox{MATLAB}

software is installed and assigns it to mr.

Remarks matlabroot as Folder Name

The term <code>matlabroot</code> also refers to the folder where MATLAB files are installed. For example, "save to <code>matlabroot/toolbox/local</code>" means save to the toolbox/local folder in the MATLAB root folder.

Using \$matlabroot as a Literal

In some files, such as info.xml and classpath.txt, \$matlabroot is literal. In those files, MATLAB interprets \$matlabroot as the full path to the MATLAB root folder. For example, including the line

\$matlabroot/toolbox/local/myfile.jar

in classpath.txt, adds myfile.jar, which is located in the toolbox/local folder, to classpath.txt.

Sometimes, particularly in older code examples, the term \$matlabroot or \$MATLABROOT is not meant to be interpreted literally but is used to represent the value returned by the matlabroot function.

matlabroot on Macintosh Platforms

In R2008b (V7,7) and more recent versions, running ${\tt matlabroot}$ on Apple Macintosh platforms returns

```
/Applications/MATLAB_R2008b.app
```

In versions prior to R2008b (V7.7), such as R2008a (V7.6), running matlabroot on Macintosh platforms returns, for example

```
/Applications/MATLAB R2008a
```

When you use GUIs on Macintosh platforms, you cannot directly view the contents of the MATLAB root folder. For more information, see "Using File Browser GUIs on Macintosh Platforms to Navigate Within the MATLAB Root Folder".

Use in Compiled Mode

To return the path to the executable in compiled mode, use the MATLAB® Compiler™ ctfroot function, or the MATLAB toolboxdir function. For details, see the MATLAB or MATLAB Compiler documentation.

Examples

Get the location where MATLAB is installed:

matlabroot

MATLAB returns:

```
C:\Program Files\MATLAB\R2009a
```

Produce a full path to the toolbox/matlab/general folder that is correct for the platform on which it is executed:

```
fullfile(matlabroot, 'toolbox', 'matlab', 'general')
```

Change the current folder to the MATLAB root folder:

```
cd(matlabroot)
```

To add the folder myfiles to the MATLAB search path, run

```
addpath([matlabroot '/toolbox/local/myfiles'])
```

matlabroot

See Also

 ${\tt ctfroot} \ (in \ MATLAB \ Compiler \ product), \ {\tt fullfile}, \ {\tt path}, \ {\tt toolboxdir} \\ "Managing \ Files \ in \ MATLAB"$

Purpose Start MATLAB program (UNIX platforms)

Syntax

matlab helpOption
matlab envDispOption
matlab archOption
matlab dispOption
matlab modeOption
matlab -c licensefile
matlab -r matlab_command
matlab -logfile filename
matlab -mwvisual visualid
matlab -nosplash
matlab -singleCompThread
matlab -debug
matlab -Ddebugger options

Note You can enter more than one of these options in the same matlab command. If you use -Ddebugger to start MATLAB in debug mode, the first option in the command must be -Ddebugger.

matlab (UNIX)

Description

matlab is a Bourne shell script that starts the MATLAB executable on UNIX¹¹ platforms. (In this document, matlab refers to this script; MATLAB refers to the application program). Before actually initiating the execution of MATLAB, this script configures the run-time environment by

- Determining the MATLAB root directory
- Determining the host machine architecture
- · Processing any command line options
- Reading the MATLAB startup file, .matlab7rc.sh
- Setting MATLAB environment variables

There are two ways in which you can control the way the matlab script works:

- By specifying command line options
- By assigning values in the MATLAB startup file, .matlab7rc.sh

Specifying Options at the Command Line

Options that you can enter at the command line are as follows:

matlab helpOption displays information that matches the specified helpOption argument without starting MATLAB. helpOption can be any one of the keywords shown in the table below. Enter only one helpOption keyword in a matlab command.

Values for helpOption

Option	Description
-help	Display matlab command usage.
-h	The same as -help.

11. UNIX is a registered trademark of The Open Group in the United States and other countries.

matlab envDispOption displays the values of environment variables passed to MATLAB or their values just prior to exiting MATLAB. envDispOption can be either one of the options shown in the table below.

Values for envDispOption

Option	Description
-n	Display all the final values of the environment variables and arguments passed to the MATLAB executable as well as other diagnostic information. Does not start MATLAB.
- e	Display <i>all</i> environment variables and their values just prior to exiting. This argument must have been parsed before exiting for anything to be displayed. The last possible exiting point is just before the MATLAB image would have been executed and a status of 0 is returned. If the exit status is not 0 on return, then the variables and values may not be correct. Does not start MATLAB.

matlab archOption starts MATLAB and assumes that you are running on the system architecture specified by arch, or using the MATLAB version specified by variant, or both. The values for the archOption argument are shown in the table below. Enter only one of these options in a matlab command.

Values for archOption

Option	Description
-arch	Run MATLAB assuming this architecture rather than the actual architecture of the machine you are using. Replace the term arch with a string representing a recognized system architecture.
v =variant	Execute the version of MATLAB found in the directory bin/\$ARCH/variant instead of bin/\$ARCH. Replace the term variant with a string representing a MATLAB version.
v=arch/variant	Execute the version of MATLAB found in the directory bin/arch/variant instead of bin/\$ARCH. Replace the terms arch and variant with strings representing a specific architecture and MATLAB version.

matlab dispOption starts MATLAB using one of the display options shown in the table below. Enter only one of these options in a matlab command.

Values for dispOption

Option	Description
-display xDisp	Send X commands to X Window Server display xDisp. This supersedes the value of the DISPLAY environment variable.
-nodisplay	Start the Sun Microsystems JVM software, but do not start the MATLAB desktop. Do not display any X commands, and ignore the DISPLAY environment variable,

matlab modeOption starts MATLAB without its usual desktop component. Enter only one of the options shown below.

Values for modeOption

Option	Description
-desktop	Allow the MATLAB desktop to be started by a process without a controlling terminal. This is usually a required command line argument when attempting to start MATLAB from a window manager menu or desktop icon.
-nodesktop	Start MATLAB without bringing up the MATLAB desktop. The JVM software is started. Use the current window in the operating system to enter commands. Use this option to run without an X-window, for example, in VT100 mode, or in batch processing mode. Note that if you pipe to MATLAB using the > constructor, the nodesktop option is used automatically. With nodesktop, MATLAB does not save statements to the Command History. With nodesktop, you can still use most development environment tools by starting them via a function. For example, use preferences to open the Preferences dialog box and helpbrowser to open the Help browser. Do not use nodesktop to provide a Command Window-only interface; instead, select Desktop > Desktop Layout > Command Window Only.
-nojvm	Start MATLAB without the JVM software. Use the current window to enter commands. The MATLAB desktop does not open. Any tools that require Java software, such as the desktop tools, cannot be used. Handle Graphics and related functionality are not supported; MATLAB produces a warning when you use them.

matlab (UNIX)

matlab -c licensefile starts MATLAB using the specified license file. The licensefile argument can have the form port@host or it can be a colon-separated list of license filenames. This option causes the LM_LICENSE_FILE and MLM_LICENSE_FILE environment variables to be ignored.

matlab -r matlab_command starts MATLAB and executes the specified MATLAB command.

matlab -logfile filename starts MATLAB and makes a copy of any output to the command window in file log. This includes all crash reports.

matlab -mwvisual visualid starts MATLAB and uses visualid as the default X visual for figure windows. visualid is a hexadecimal number that can be found using xdpyinfo.

matlab -nosplash starts MATLAB but does not display the splash screen during startup.

matlab **-singleCompThread** limits MATLAB to a single computational thread. By default, MATLAB makes use of the multithreading capabilities of the computer on which it is running.

matlab -debug starts MATLAB and displays debugging information that can be useful, especially for X based problems. This option should be used only when working with a Technical Support Representative from The MathWorks, Inc.

matlab -Ddebugger options starts MATLAB in debug mode, using the named debugger (e.g., dbx, gdb, xdb, cvd). A full path can be specified for debugger.

The options argument can include *only* those options that follow the debugger name in the syntax of the actual debug command. For most debuggers, there is a very limited number of such options. Options that would normally be passed to the MATLAB executable should be used as parameters of a command inside the debugger (like run). They should not be used when running the matlab script.

If any other matlab command options are placed before the -Ddebugger argument, they will be handled as if they were part of the options after the -Ddebugger argument and will be treated as illegal options by most debuggers. The MATLAB_DEBUG environment variable is set to the filename part of the debugger argument.

To customize your debugging session, use a startup file. See your debugger documentation for details.

Note For certain debuggers like gdb, the SHELL environment variable is *always* set to /bin/sh.

Specifying Options in the MATLAB Startup File

The .matlab7rc.sh shell script contains definitions for a number of variables that the matlab script uses. These variables are defined within the matlab script, but can be redefined in .matlab7rc.sh. When invoked, matlab looks for the first occurrence of .matlab7rc.sh in the current directory, in the home directory (\$HOME), and in the matlabroot/bin directory, where the template version of .matlab7rc.sh is located.

You can edit the template file to redefine information used by the matlab script. If you do not want your changes applied systemwide, copy the edited version of the script to your current or home directory. Ensure that you edit the section that applies to your machine architecture.

The following table lists the variables defined in the .matlab7rc.sh file. See the comments in the .matlab7rc.sh file for more information about these variables.

Variable	Definition and Standard Assignment Behavior
ARCH	The machine architecture.
	The value ARCH passed with the -arch or -arch/ext argument to the script is tried first, then the value of the environment variable MATLAB_ARCH is tried next, and finally it is computed. The first one that gives a valid architecture is used.
DISPLAY	The hostname of the X Window display MATLAB uses for output.
	The value of Xdisplay passed with the -display argument to the script is used; otherwise, the value in the environment is used. DISPLAY is ignored by MATLAB if the -nodisplay argument is passed.
LD_LIBRARY_PATH	Final Load library path. The name LD_LIBRARY_PATH is platform dependent.
	The final value is normally a colon-separated list of four sublists, each of which could be empty. The first sublist is defined in .matlab7rc.sh as LDPATH_PREFIX. The second sublist is computed in the script and includes directories inside the MATLAB root directory and relevant Sun Microsystems Java directories. The third sublist contains any nonempty value of LD_LIBRARY_PATH from the environment possibly augmented in .matlab7rc.sh. The final sublist is defined in .matlab7rc.sh as LDPATH_SUFFIX.

Variable	Definition and Standard Assignment Behavior
LM_LICENSE_FILE	The FLEX lm license variable.
	The license file value passed with the -c argument to the script is used; otherwise it is the value set in .matlab7rc.sh. In general, the final value is a colon-separated list of license files and/or port@host entries. The shipping .matlab7rc.sh file starts out the value by prepending LM_LICENSE_FILE in the environment to a default license.file.
	Later in the matlab script, if the -c option is not used, the matlabroot/etc directory is searched for the files that start with license.dat.DEMO. These files are assumed to contain demo licenses and are added automatically to the end of the current list.
MATLAB	The MATLAB root directory.
	The default computed by the script is used unless MATLABdefault is reset in .matlab7rc.sh.
	Currently MATLABdefault is not reset in the shipping .matlab7rc.sh.
MATLAB_DEBUG	Normally set to the name of the debugger.
	The -Ddebugger argument passed to the script sets this variable. Otherwise, a nonempty value in the environment is used.

Variable	Definition and Standard Assignment Behavior
MATLAB_JAVA	The path to the root of the Java Runtime Environment.
	The default set in the script is used unless MATLAB_JAVA is already set. Any nonempty value from .matlab7rc.sh is used first, then any nonempty value from the environment. Currently there is no value set in the shipping .matlab67rc.sh, so that environment alone is used.
MATLABPATH	The MATLAB search path.
	The final value is a colon-separated list with the MATLABPATH from the environment prepended to a list of computed defaults. You can add subdirectories of userpath to the MATLAB search path upon startup. See userpath for details.
SHELL	The shell to use when the "!" or unix command is issued in MATLAB. This is taken from the environment unless SHELL is reset in .matlab7rc.sh.
	Note that an additional environment variable called MATLAB_SHELL takes precedence over SHELL. MATLAB checks internally for MATLAB_SHELL first and, if empty or not defined, then checks SHELL. If SHELL is also empty or not defined, MATLAB uses /bin/sh. The value of MATLAB_SHELL should be an absolute path, i.e. /bin/sh, not simply sh.
	Currently, the shipping .matlab7rc.sh file does not reset SHELL and also does not reference or set MATLAB_SHELL.

Variable	Definition and Standard Assignment Behavior
T00LB0X	Path of the toolbox directory.
	A nonempty value in the environment is used first. Otherwise, matlabroot/toolbox, computed by the script, is used unless TOOLBOX is reset in .matlab7rc.sh. Currently TOOLBOX is not reset in the shipping .matlab7rc.sh.
XAPPLRESDIR	The X application resource directory.
	A nonempty value in the environment is used first unless XAPPLRESDIR is reset in .matlab7rc.sh. Otherwise, matlabroot/X11/app-defaults, computed by the script, is used.
XKEYSYMDB	The X keysym database file.
	A nonempty value in the environment is used first unless XKEYSYMDB is reset in .matlab7rc.sh. Otherwise, matlabroot/X11/app-defaults/XKeysymDB, computed by the script, is used. The matlab script determines the path of the MATLAB root directory as one level up the directory tree from the location of the script.

The matlab script determines the path of the MATLAB root directory by looking up the directory tree from the matlabroot/bin directory (where the matlab script is located). The MATLAB variable is then used to locate all files within the MATLAB directory tree.

You can change the definition of MATLAB if, for example, you want to run a different version of MATLAB or if, for some reason, the path determined by the matlab script is not correct. (This can happen when certain types of automounting schemes are used by your system.)

matlab (UNIX)

See Also

matlab (Windows), mex

"Starting the MATLAB Program on UNIX Platforms", "Starting the MATLAB Program on Macintosh Platforms", and "Startup Options" in the MATLAB Desktop Tools and Development Environment documentation

Start MATLAB program (Windows platforms)

Syntax

```
matlab helpOption
matlab -automation
matlab -c licensefile
matlab -logfile filename
matlab -nosplash
matlab -noFigureWindows
matlab -r "statement"
matlab -regserver
matlab -sd "startdir"
matlab shieldOption
matlab -singleCompThread
matlab -unregserver
matlab -wait
```

Note You can enter more than one of these options in the same matlab command.

Description

matlab is a script that runs the main MATLAB executable on Microsoft Windows platforms. (In this document, the term matlab refers to the script, and MATLAB refers to the main executable). Before actually initiating the execution of MATLAB, it configures the run-time environment by

- Determining the MATLAB root directory
- Determining the host machine architecture
- Selectively processing command line options with the rest passed to MATLAB.
- Setting certain MATLAB environment variables

There are two ways in which you can control the way matlab works:

- By specifying command line options
- By setting environment variables before calling the program

Specifying Options at the Command Line

Options that you can enter at the command line are as follows:

matlab *helpOption* displays information that matches the specified *helpOption* argument without starting MATLAB. *helpOption* can be any one of the keywords shown in the table below. Enter only one *helpOption* keyword in a matlab statement.

Values for helpOption

Option	Description
-help	Display matlab command usage.
- h	The same as -help.
-?	The same as -help.

matlab -automation starts MATLAB as an automation server. The server window is minimized, and the MATLAB splash screen does not display on startup.

matlab -c licensefile starts MATLAB using the specified license file. The licensefile argument can have the form port@host. This option causes MATLAB to ignore the LM_LICENSE_FILE and MLM_LICENSE_FILE environment variables.

matlab -logfile filename starts MATLAB and makes a copy of any output to the Command Window in filename. This includes all crash reports.

matlab -nosplash starts MATLAB, but does not display the splash screen during startup.

matlab -noFigureWindows starts MATLAB, but disables the display of any figure windows in MATLAB.

matlab -r "statement" starts MATLAB and executes the specified MATLAB statement. Any required file must be on the MATLAB search path or in the startup directory.

matlab -regserver registers MATLAB as a Component Object Model (COM) server.

matlab -sd "startdir" specifies the startup directory for MATLAB (the current directory in MATLAB after startup). The -sd option has been deprecated. For information about alternatives, see "Startup Folder on Windows Platforms".

matlab shieldOption provides the specified level of protection of the address space used by MATLAB during startup on Windows 32-bit platforms. It attempts to help ensure the largest contiguous block of memory available after startup, which is useful for processing large data sets. The shieldOption does this by ensuring resources such as DLLs, are loaded into locations that will not fragment the address space. With shieldOption set to a value other than none, address space is protected up to or after the processing of matlabrc. Use higher levels of protection to secure larger initial blocks of contiguous memory, however a higher level might not always provide a larger size block and might cause startup problems. Therefore, start with a lower level of protection, and if successful, try the next higher level. You can use the memory function after startup to see the size of the largest contiguous block of memory; this helps you determine the actual effect of the shieldOption setting you used. If your matlabre (or startup.m) requires significant memory, a higher level of protection for shieldOption might cause startup to fail: in that event try a lower level. Values for shieldOption can be any one of the keywords shown in the table below.

• ••	.
Option	Description
-shield minimum	This is the default setting. It protects the range 0x50000000 to 0x70000000 during MATLAB startup until just before startup processes matlabrc. It ensures there is at least approximately 500 MB of contiguous memory up to this point.
	Start with this, the default value. To use the default, do not specify a shield option upon startup.
	If MATLAB fails to start successfully using the default option, -shield minimum, instead use -shield none.
	If MATLAB starts successfully with the default value for <code>shieldOption</code> and you want to try to ensure an even larger contiguous block after startup, try using the <code>-shield medium</code> option.
-shield medium	This protects the same range as for minimum, 0x50000000 to 0x70000000, but protects the range until just after startup processes matlabrc. It ensures there is at least approximately 500 MB of contiguous memory up to this point.
	If MATLAB fails to start successfully with the -shield medium option, instead use the default option (-shield minimum).
	If MATLAB starts successfully with the -shield medium option and you want to try to ensure an even larger contiguous block after startup, try using the -shield maximum option.

Option	Description
-shield maximum	This protects the maximum possible range, which can be up to approximately 1.5 GB, until just after startup processes matlabrc.
	If MATLAB fails to start successfully with the -shield maximum option, instead use the -shield medium option.
-shield none	This completely disables address shielding. Use this if MATLAB fails to start successfully with the default (-shield minimum) option.

matlab -singleCompThread limits MATLAB to a single computational thread. By default, MATLAB makes use of the multithreading capabilities of the computer on which it is running.

matlab -unregserver removes all MATLAB COM server entries from the registry.

matlab -wait MATLAB is started by a separate starter program which normally launches MATLAB and then immediately quits. Using this option tells the starter program not to quit until MATLAB has terminated. This option is useful when you need to process the results from MATLAB in a script. Calling MATLAB with this option blocks the script from continuing until the results are generated.

Setting Environment Variables

You can set the following environment variables before starting MATLAB.

Variable Name	Description
LM_LICENSE_FILE	This variable specifies the License File to use. If you use the -c argument to specify the License File it overrides this variable. The value of this variable can be a list of License Files, separated by semi-colons, or port@host entries.

See Also

matlab (UNIX), mex, userpath

"Starting the MATLAB Program on Windows Platforms", and "Startup Options" in the MATLAB Desktop Tools and Development Environment documentation

Largest elements in array

Syntax

```
C = max(A)
C = max(A,B)
C = max(A,[],dim)
[C,I] = max(...)
```

Description

C = max(A) returns the largest elements along different dimensions of an array.

If A is a vector, max(A) returns the largest element in A.

If A is a matrix, max(A) treats the columns of A as vectors, returning a row vector containing the maximum element from each column.

If A is a multidimensional array, max(A) treats the values along the first non-singleton dimension as vectors, returning the maximum value of each vector.

C = max(A,B) returns an array the same size as A and B with the largest elements taken from A or B. The dimensions of A and B must match, or they may be scalar.

 $C = \max(A,[],\dim)$ returns the largest elements along the dimension of A specified by scalar dim. For example, $\max(A,[],1)$ produces the maximum values along the first dimension (the rows) of A.

[C,I] = max(...) finds the indices of the maximum values of A, and returns them in output vector I. If there are several identical maximum values, the index of the first one found is returned.

Remarks

For complex input A, max returns the complex number with the largest complex modulus (magnitude), computed with max(abs(A)). Then computes the largest phase angle with max(angle(x)), if necessary.

The max function ignores NaNs.

See Also

isnan, mean, median, min, sort

max (timeseries)

Purpose

Maximum value of timeseries data

Syntax

```
ts_max = max(ts)
ts max = max(ts, 'PropertyName1', PropertyValue1,...)
```

Description

ts_max = max(ts) returns the maximum value in the time-series data. When ts.Data is a vector, ts_max is the maximum value of ts.Data values. When ts.Data is a matrix, ts_max is a row vector containing the maximum value of each column of ts.Data (when IsTimeFirst is true and the first dimension of ts is aligned with time). For the N-dimensional ts.Data array, max always operates along the first nonsingleton dimension of ts.Data.

ts_max = max(ts, 'PropertyName1', PropertyValue1,...)
specifies the following optional input arguments:

- 'MissingData' property has two possible values, 'remove' (default) or 'interpolate', indicating how to treat missing data during the calculation.
- 'Quality' values are specified by a vector of integers, indicating
 which quality codes represent missing samples (for vector data) or
 missing observations (for data arrays with two or more dimensions).
- 'Weighting' property has two possible values, 'none' (default) or 'time'.

When you specify 'time', larger time values correspond to larger weights.

Examples

The following example illustrates how to find the maximum values in multivariate time-series data.

1 Load a 24-by-3 data array.

load count.dat

2 Create a timeseries object with 24 time values.

```
count_ts = timeseries(count,[1:24],'Name','CountPerSecond')
```

3 Find the maximum in each data column for this timeseries object.

```
max(count_ts)

ans =

114 145 257
```

The maximum is found independently for each data column in the timeseries object.

See Also

iqr (timeseries), min (timeseries), median (timeseries), mean
(timeseries), std (timeseries), timeseries, var (timeseries)

MaximizeCommandWindow

Purpose

Open Automation server window

Syntax

MATLAB Client

h.MaximizeCommandWindow
MaximizeCommandWindow(h)

IDL Method Signature

HRESULT MaximizeCommandWindow(void)

Microsoft Visual Basic Client

MaximizeCommandWindow

Description

h.MaximizeCommandWindow displays the window for the server attached to handle h, and makes it the currently active window on the desktop.

MaximizeCommandWindow(h) is an alternate syntax.

MaximizeCommandWindow restores the window to the size it had at the time it was minimized, not to the maximum size on the desktop. If the server window was not previously in a minimized state, MaximizeCommandWindow does nothing.

Examples

From a MATLAB client, modify the size of the command window in a MATLAB Automation server:

```
h = actxserver('matlab.application');
```

h.MinimizeCommandWindow;

% Now return the server window to its former state on

% the desktop and make it the currently active window.

h.MaximizeCommandWindow;

From a Visual Basic client, modify the size of the command window in a MATLAB Automation server:

Dim Matlab As Object

MaximizeCommandWindow

Matlab = CreateObject("matlab.application")
Matlab.MinimizeCommandWindow

'Now return the server window to its former state on 'the desktop and make it the currently active window.

Matlab.MaximizeCommandWindow

See Also MinimizeCommandWindow

How To• "MATLAB COM Automation Server Support"

· "Controlling the Server Window"

maxNumCompThreads

Purpose

Control maximum number of computational threads

Note maxNumCompThreads will be removed in a future version. You can set the -singleCompThread option when starting MATLAB to limit MATLAB to a single computational thread. By default, MATLAB makes use of the multithreading capabilities of the computer on which it is running.

Syntax

N = maxNumCompThreads

LASTN = maxNumCompThreads(N)

LASTN = maxNumCompThreads('automatic')

Description

N = maxNumCompThreads returns the current maximum number of computational threads N.

LASTN = maxNumCompThreads(N) sets the maximum number of computational threads to N, and returns the previous maximum number of computational threads, LASTN.

LASTN = maxNumCompThreads('automatic') sets the maximum number of computational threads using what the MATLAB software determines to be the most desirable. It additionally returns the previous maximum number of computational threads, LASTN.

Currently, the maximum number of computational threads is equal to the number of computational cores on your machine.

Note Setting the maximum number of computational threads using maxNumCompThreads does not propagate to your next MATLAB session.

Average or mean value of array

Syntax

```
M = mean(A)
M = mean(A,dim)
```

Description

M = mean(A) returns the mean values of the elements along different dimensions of an array.

If A is a vector, mean(A) returns the mean value of A.

If A is a matrix, mean(A) treats the columns of A as vectors, returning a row vector of mean values.

If A is a multidimensional array, mean(A) treats the values along the first non-singleton dimension as vectors, returning an array of mean values.

M = mean(A,dim) returns the mean values for elements along the dimension of A specified by scalar dim. For matrices, mean(A,2) is a column vector containing the mean value of each row.

Examples

See Also

corrcoef, cov, max, median, min, mode, std, var

mean (timeseries)

Purpose

Mean value of timeseries data

Syntax

```
ts_mn = mean(ts)
ts_mn = mean(ts, 'PropertyName1', PropertyValue1,...)
```

Description

ts_mn = mean(ts) returns the mean value of ts.Data. When ts.Data is a vector, ts_mn is the mean value of ts.Data values. When ts.Data is a matrix, ts_mn is a row vector containing the mean value of each column of ts.Data (when IsTimeFirst is true and the first dimension of ts is aligned with time). For the N-dimensional ts.Data array, mean always operates along the first nonsingleton dimension of ts.Data.

ts_mn = mean(ts, 'PropertyName1', PropertyValue1,...)
specifies the following optional input arguments:

- 'MissingData' property has two possible values, 'remove' (default)
 or 'interpolate', indicating how to treat missing data during the
 calculation.
- 'Quality' values are specified by a vector of integers, indicating which quality codes represent missing samples (for vector data) or missing observations (for data arrays with two or more dimensions).
- 'Weighting' property has two possible values, 'none' (default) or 'time'.

When you specify 'time', larger time values correspond to larger weights.

Examples

The following example illustrates how to find the mean values in multivariate time-series data.

1 Load a 24-by-3 data array.

load count.dat

2 Create a timeseries object with 24 time values.

```
count ts = timeseries(count,[1:24],'Name','CountPerSecond')
```

3 Find the mean of each data column for this timeseries object.

```
mean(count_ts)

ans =

32.0000 46.5417 65.5833
```

The mean is found independently for each data column in the timeseries object.

See Also

iqr (timeseries), max (timeseries), min (timeseries), median
(timeseries), std (timeseries), timeseries, var (timeseries)

Median value of array

Syntax

M = median(A)
M = median(A,dim)

Description

M = median(A) returns the median values of the elements along different dimensions of an array. A should be of type single or double.

If A is a vector, median(A) returns the median value of A.

If A is a matrix, median(A) treats the columns of A as vectors, returning a row vector of median values.

If A is a multidimensional array, median(A) treats the values along the first nonsingleton dimension as vectors, returning an array of median values.

M = median(A,dim) returns the median values for elements along the dimension of A specified by scalar dim.

Examples

```
A = [1 2 4 4; 3 4 6 6; 5 6 8 8; 5 6 8 8];
median(A)
ans =
```

4 5 7 7

median(A,2)

ans =

3

5

7

7

See Also

corrcoef, cov, max, mean, min, mode, std, var

Median value of timeseries data

Syntax

```
ts_med = median(ts)
```

ts_med = median(ts, 'PropertyName1', PropertyValue1,...)

Description

ts_med = median(ts) returns the median value of ts.Data. When ts.Data is a vector, ts_med is the median value of ts.Data values. When ts.Data is a matrix, ts_med is a row vector containing the median value of each column of ts.Data (when IsTimeFirst is true and the first dimension of ts is aligned with time). For the N-dimensional ts.Data array, median always operates along the first nonsingleton dimension of ts.Data.

ts_med = median(ts,'PropertyName1',PropertyValue1,...)
specifies the following optional input arguments:

- 'MissingData' property has two possible values, 'remove' (default) or 'interpolate', indicating how to treat missing data during the calculation.
- 'Quality' values are specified by a vector of integers, indicating which quality codes represent missing samples (for vector data) or missing observations (for data arrays with two or more dimensions).
- 'Weighting' property has two possible values, 'none' (default) or 'time'.

When you specify 'time', larger time values correspond to larger weights.

Examples

The following example illustrates how to find the median values in multivariate time-series data.

1 Load a 24-by-3 data array.

load count.dat

2 Create a timeseries object with 24 time values.

```
count_ts = timeseries(count,[1:24],'Name','CountPerSecond')
```

3 Find the median of each data column for this timeseries object.

```
median(count_ts)

ans =

23.5000 36.0000 39.0000
```

The median is found independently for each data column in the timeseries object.

See Also

iqr (timeseries), max (timeseries), min (timeseries), mean
(timeseries), std (timeseries), timeseries, var (timeseries)

Construct memmapfile object

Syntax

m = memmapfile(filename)

m = memmapfile(filename, prop1, value1, prop2, value2, ...)

Description

m = memmapfile(filename) constructs an object of the memmapfile class that maps file filename to memory using the default property values. The filename input is a quoted string that specifies the path and name of the file to be mapped into memory. filename must include a filename extension if the name of the file being mapped has an extension. The filename argument cannot include any wildcard characters (e.g., * or ?), is case sensitive on The Open Group UNIX platforms, but is not case sensitive on Microsoft Windows platforms.

m = memmapfile(filename, prop1, value1, prop2, value2, ...) constructs an object of the memmapfile class that maps file filename into memory and sets the properties of that object that are named in the argument list (prop1, prop2, etc.) to the given values (value1, value2, etc.). All property name arguments must be quoted strings (e.g., 'Writable'). Any properties that are not specified are given their default values.

Optional properties are shown in the table below and are described in the sections that follow.

Property	Description	Data Type	Default
Format	Format of the contents of the mapped region, including data type, array shape, and variable or field name by which to access the data	char array or N-by-3 cell array	uint8

memmapfile

Property	Description	Data Type	Default
Offset	Number of bytes from the start of the start of the start of the mapped region. This number is zero-based. That is, offset 0 represents the start of the file.	double	0
Repeat	Number of times to apply the specified format to the mapped region of the file	double	Inf
Writable	Type of access allowed to the mapped region	logical	false

There are three different ways you can specify a value for the Format property. See the following sections in the MATLAB Data Import and Export documentation for more information:

- "Mapping a Single Data Type"
- "Formatting the Mapped Data to an Array"
- "Mapping Multiple Data Types and Arrays"

Any of the following data types can be used when you specify a Format value. The default type is uint8.

Format String	Data Type Description
'int8'	Signed 8-bit integers
'int16'	Signed 16-bit integers
'int32'	Signed 32-bit integers
'int64'	Signed 64-bit integers
'uint8'	Unsigned 8-bit integers
'uint16'	Unsigned 16-bit integers
'uint32'	Unsigned 32-bit integers
'uint64'	Unsigned 64-bit integers
'single'	32-bit floating-point
'double'	64-bit floating-point

Remarks

You can only map an existing file. You cannot create a new file and map that file to memory in one operation. Use the MATLAB file I/O functions to create the file before attempting to map it to memory.

Once memmapfile locates the file, MATLAB stores the absolute pathname for the file internally, and then uses this stored path to locate the file from that point on. This enables you to work in other directories outside your current work directory and retain access to the mapped file.

Once a memmapfile object has been constructed, you can change the value of any of its properties. Use the objname.property syntax in assigning the new value. To set a new offset value for memory map object m, type

```
m.Offset = 2048;
```

Property names are not case sensitive. For example, MATLAB considers m.Offset to be the same as m.offset.

Examples

To run the following examples, create a file in your current folder called records.dat. Example 2 expects that records.dat contains

5000 double-precision values. The following code shows one method to create this file:

```
randData = gallery('uniformdata', [5000, 1], 0, 'double');
fid = fopen('records.dat','w');
fwrite(fid, randData, 'double');
fclose(fid);
```

Example 1

To construct a map for records.dat, type the following:

```
m = memmapfile('records.dat');
```

MATLAB constructs an instance of the memmapfile class, assigns it to the variable m, and maps the entire records.dat file to memory, setting all properties of the object to their default values. In this example, the command maps the entire file as a sequence of unsigned 8-bit integers and gives the caller read-only access to its contents.

Example 2

To construct a map using nondefault values for the Offset, Format, and Writable properties, type the following, enclosing all property names in single quotation marks:

Type the object name to see the current settings for all properties:

```
m =
    Filename: 'd:\matlab\mfiles\records.dat'
    Writable: true
    Offset: 1024
```

```
Format: 'uint32'
Repeat: Inf
Data: 9744x1 uint32 array
```

Example 3

Construct a memmapfile object for the entire file records.dat and set the Format property for that object to uint64. Any read or write operations made via the memory map will read and write the file contents as a sequence of unsigned 64-bit integers:

```
m = memmapfile('records.dat', 'Format', 'uint64');
```

Example 4

Construct a memmapfile object for a region of records.dat such that the contents of the region are handled by MATLAB as a 4-by-10-by-18 array of unsigned 32-bit integers, and can be referenced in the structure of the returned object using the field name x:

Example 5

Map a file to three different data types: int16, uint32, and single. The int16 data is mapped as a 2-by-2 matrix that can be accessed using the field name model. The uint32 data is a scalar value accessed as field serialno. The single data is a 1-by-3 matrix named expenses. Repeat the pattern 1000 times.

Each of the fields belongs to the 1000-by-1 structure array m.Data:

memmapfile

See Also

disp(memmapfile), get(memmapfile)

Display memory information

Syntax

memory

userview = memory

[userview systemview] = memory

Description

memory displays information showing how much memory is available and how much the MATLAB software is currently using. The information displayed at your computer screen includes the following items, each of which is described in a section below:

- "Maximum Possible Array" on page 2-2510
- "Memory Available for All Arrays" on page 2-2511
- "Memory Used By MATLAB" on page 2-2512
- "Total Physical Memory (RAM)" on page 2-2512

userview = memory returns user-focused information on memory use in structure userview. The information returned in userview includes the following items, each of which is described in a section below:

- "Maximum Possible Array" on page 2-2510
- "Memory Available for All Arrays" on page 2-2511
- "Memory Used By MATLAB" on page 2-2512

[userview systemview] = memory returns both user- and system-focused information on memory use in structures userview and systemview, respectively. The userview structure is described in the command syntax above. The information returned in systemview includes the following items, each of which is described in a section below:

- "Virtual Address Space" on page 2-2513
- "System Memory" on page 2-2513

• "Physical Memory" on page 2-2514

Output

Each of the sections below describes a value that is displayed or returned by the memory function.

Maximum Possible Array

Maximum Possible Array is the size of the largest contiguous free memory block. As such, it is an upper bound on the largest single array MATLAB can create at this time.

MATLAB derives this number from the smaller of the following two values:

- The largest contiguous memory block found in the MATLAB virtual address space
- The total available system memory

To see how many array elements this number represents, divide by the number of bytes in the array class. For example, for a double array, divide by 8. The actual number of elements MATLAB can create is always fewer than this number.

When you enter the memory command without assigning its output, MATLAB displays this information as a string. When you do assign the output, MATLAB returns the information in a structure field. See the table below.

Command	Returned in	
memory	String labelled Maximum possible array:	
user = memory	Structure field user.MaxPossibleArrayBytes	

All values are double-precision and in units of bytes.

Footnotes

When you enter the memory command without specifying any outputs, MATLAB may also display one of the following footnotes. 32-bit systems

show either the first or second footnote; 64-bit systems show only the second footnote:

Limited by contiguous virtual address space available.

There is sufficient system memory to allow mapping of all virtual addresses in the largest available block of the MATLAB process.

The maximum amount of total MATLAB virtual address space is either 2 GB or 3 GB, depending on whether the /3GB switch is in effect or not.

Limited by System Memory (physical + swap file) available. There is insufficient system memory to allow mapping of all virtual addresses in the largest available block of the MATLAB process.

Memory Available for All Arrays

Memory Available for All Arrays is the total amount of memory available to hold data. The amount of memory available is guaranteed to be at least as large as this field.

MATLAB derives this number from the smaller of the following two values:

- The total available MATLAB virtual address space
- The total available system memory

When you enter the memory command without assigning its output, MATLAB displays this information as a string. When you do assign the output, MATLAB returns the information in a structure field. See the table below.

Command	Returned in
memory	String labelled Memory available for all arrays:
user = memory	Structure field user.MemAvailableAllArrays

Footnotes

When you enter the memory command without specifying any outputs, MATLAB may also display one of the following footnotes. 32-bit systems show either the first or second footnote; 64-bit systems show only the latter footnote:

Limited by virtual address space available.

There is sufficient system memory to allow mapping of all available virtual addresses in the MATLAB process virtual address space to system memory. The maximum amount of total MATLAB virtual address space is either 2 GB or 3 GB, depending on whether the /3GB switch is in effect or not.

Limited by System Memory (physical + swap file) available. There is insufficient system memory to allow mapping of all available virtual addresses in the MATLAB process.

Memory Used By MATLAB

Memory Used By MATLAB is the total amount of system memory reserved for the MATLAB process. It is the sum of the physical memory and potential swap file usage.

When you enter the memory command without assigning its output, MATLAB displays this information as a string. When you do assign the output, MATLAB returns the information in a structure field. See the table below.

Command	Returned in
memory	String labelled Memory used by MATLAB:
user = memory	Structure field user.MemUsedMATLAB

Total Physical Memory (RAM)

Physical Memory (RAM) is the total physical memory (or RAM) in the computer.

When you enter the memory command without assigning its output, MATLAB displays this information as a string. See the table below.

Command	Returned in
memory	String labelled Physical Memory (RAM):

Virtual Address Space

Virtual Address Space is the amount of available and total virtual memory for the MATLAB process. MATLAB returns the information in two fields of the return structure: Available and Total.

Command	Return Value	Returned in Structure Field
[user,sys] = memory	Available memory	sys.VirtualAddressSpace.Available
	Total memory	sys.VirtualAddressSpace.Total

You can monitor the difference:

VirtualAddressSpace.Total - VirtualAddressSpace.Available

as the Virtual Bytes counter in the WindowsPerformance program. (e.g., Windows XP Control Panel/Administrative Tool/Performance program).

System Memory

System Memory is the amount of available system memory on your computer system. This number includes the amount of available physical memory and the amount of available swap file space on the computer running MATLAB. MATLAB returns the information in the SystemMemory field of the return structure.

Command	Return Value	Returned in Structure Field
[user,sys] = memory	Available memory	sys.SystemMemory

This is the same as the difference:

limit - total (in bytes)

found in the Windows Task Manager: Performance/Commit Charge.

Physical Memory

Physical Memory is the available and total amounts of physical memory (RAM) on the computer running MATLAB. MATLAB returns the information in two fields of the return structure: Available and Total.

Command	Value	Returned in Structure Field
<pre>[user,sys] = memory</pre>	Available memory	sys.PhysicalMemory.Available
	Total memory	sys.PhysicalMemory.Total

Available physical memory is the same as:

Available (in bytes)

found in the Windows Task Manager: Performance/Physical Memory The total physical memory is the same as

Total (in bytes)

found in the Windows Task Manager: Performance/Physical Memory

You can use the amount of available physical memory as a measure of how much data you can access quickly.

Remarks

The memory function is currently available on Microsoft Windows systems only. Results vary, depending on the computer running MATLAB, the load on that computer, and what MATLAB is doing at the time.

Details on Memory Used By MATLAB

MATLAB computes the value for Memory Used By MATLAB by walking the MATLAB process memory structures and summing all the sections that have physical storage allocated in memory or in the paging file on disk.

Using the Windows Task Manager, you have for the MATLAB.exe image:

Mem Usage < MemUsedMATLAB < Mem Usage + VM Size (in bytes)</pre>

where both of the following are true:

- Mem Usage is the working set size in kilobytes.
- VM Size is the page file usage, or private bytes, in kilobytes.

The working set size is the portion of the MATLAB virtual address space that is *currently* resident in RAM and can be referenced without a memory page fault. The page file usage gives the portion of the MATLAB virtual address space that requires a backup that doesn't already exist. Another name for page file usage is *private bytes*. It includes all MATLAB variables and workspaces. Since some of the pages in the page file may also be part of the working set, this sum is an overestimate of MemuseMatlab. Note that there are virtual pages in the MATLAB process space that already have a backup. For example, code loaded from EXEs and DLLs and memory-mapped files. If any part of those files is in memory when the memory builtin is called, that memory will be counted as part of MemusedMatlab.

Reserved Addresses

Reserved addresses are addresses sets aside in the process virtual address space for some specific future use. These reserved addresses reduce the size of MemAvailableAllArrays and can reduce the size of the current or future value of MaxPossibleArrayBytes.

Example 1 — Java Virtual Machine (JVM)

At MATLAB startup, part of the MATLAB virtual address space is reserved by the Java Virtual Machine (JVM) and cannot be used for storing MATLAB arrays.

Example 2 - Standard Windows Heap Manager

MATLAB, by default, uses the standard Windows heap manager except for a set of small preselected allocation sizes. One characteristic of this heap manager is that its behavior depends upon whether the requested allocation is less than or greater than the fixed number of 524,280 bytes. For, example, if you create a sequence of MATLAB arrays, each less then 524,280 bytes, and then clear them all, the MemUsedMATLAB value before and after shows little change, and the MemAvailableAllArrays value is now smaller by the total space allocated.

The result is that, instead of globally freeing the extra memory, the memory becomes reserved. It can *only* be reused for arrays less than 524,280 bytes. You cannot reclaim this memory for a larger array except by restarting MATLAB.

Examples

Display memory statistics on a 32-bit Windows system:

memory

```
Maximum possible array: 677 MB (7.101e+008 bytes) *

Memory available for all arrays: 1601 MB (1.679e+009 bytes) **

Memory used by MATLAB: 446 MB (4.681e+008 bytes)

Physical Memory (RAM): 3327 MB (3.489e+009 bytes)

* Limited by contiguous virtual address space available.
```

** Limited by virtual address space available.

Return in the structure userview, information on the largest array MATLAB can create at this time, how much memory is available to hold data, and the amount of memory currently being used by your MATLAB process:

Assign the output to two structures, user and sys, to obtain the information shown here:

```
[user sys] = memory;
% --- Largest array MATLAB can create ---
user.MaxPossibleArrayBytes
ans =
   710127616
% --- Memory available for data ---
user.MemAvailableAllArrays
ans =
   1.6797e+009
% --- Memory used by MATLAB process ---
user.MemUsedMATLAB
ans =
   467603456
% --- Virtual memory for MATLAB process ---
sys.VirtualAddressSpace
ans =
   Available: 1.6797e+009
       Total: 2.1474e+009
% --- Physical memory and paging file ---
sys.SystemMemory
ans =
   Available: 4.4775e+009
% --- Computer's physical memory ---
sys.PhysicalMemory
ans =
   Available: 2.3941e+009
       Total: 3.4889e+009
```

See Also

clear, pack, whos, inmem, save, load, mlock, munlock

Generate menu of choices for user input

Syntax

```
choice = menu('mtitle','opt1','opt2',...,'optn')
choice = menu('mtitle',options)
```

displays the

Description

choice = menu('mtitle','opt1','opt2',...,'optn') menu whose title is in the string variable 'mtitle' and whose choices are string variables 'opt1', 'opt2', and so on. The menu opens in a modal dialog box. menu returns the number of the selected menu item, or 0 if the user clicks the close button on the window.

choice = menu('mtitle', options), where options is a 1-by-N cell array of strings containing the menu choices.

If the user's terminal provides a graphics capability, menu displays the menu items as push buttons in a figure window (Example 1). Otherwise. they will be given as a numbered list in the Command Window (Example 2).

Remarks

To call menu from a uicontrol or other ui object, set that object's Interruptible property to 'on'. For more information, see Uicontrol Properties.

Examples

Example 1

On a system with a display, menu displays choices as buttons in a dialog box:

```
choice = menu('Choose a color', 'Red', 'Blue', 'Green')
```

displays the following dialog box.



The number entered by the user in response to the prompt is returned as choice (i.e., choice = 2 implies that the user selected Blue).

After input is accepted, the dialog box closes, returning the output in choice. You can use choice to control the color of a graph:

```
t = 0:.1:60;
s = sin(t);
color = ['r','g','b']
plot(t,s,color(choice))
```

Example 2

On a system without a display, menu displays choices in the Command Window:

```
choice = menu('Choose a color', 'Red', 'Blue', 'Green')
```

displays the following text.

```
----- Choose a color -----

1) Red

2) Blue

3) Green

Select a menu number:
```

See Also

guide, input, uicontrol, uimenu

Mesh plots







GUI Alternatives

To graph selected variables, use the Plot Selector in the Workspace Browser, or use the Figure Palette Plot Catalog. Manipulate graphs in *plot edit* mode with the Property Editor. For details, see Plotting Tools — Interactive Plotting in the MATLAB Graphics documentation and Creating Graphics from the Workspace Browser in the MATLAB Desktop Tools documentation.

Syntax

```
mesh(X,Y,Z)
mesh(Z)
mesh(...,C)
mesh(...,'PropertyName',PropertyValue,...)
mesh(axes_handles,...)
meshc(...)
meshz(...)
h = mesh(...)
```

Description

mesh, meshc, and meshz create wireframe parametric surfaces specified by X, Y, and Z, with color specified by C.

mesh(X,Y,Z) draws a wireframe mesh with color determined by Z so color is proportional to surface height. If X and Y are vectors, length(X) = n and length(Y) = m, where [m,n] = size(Z). In this case, (X(j), Y(i), Z(i,j)) are the intersections of the wireframe grid lines; X and Y correspond to the columns and rows of Z, respectively. If X and Y are matrices, (X(i,j), Y(i,j), Z(i,j)) are the intersections of the wireframe grid lines.

mesh(Z) draws a wireframe mesh using X = 1:n and Y = 1:m, where [m,n] = size(Z). The height, Z, is a single-valued function defined over a rectangular grid. Color is proportional to surface height.

mesh(...,C) draws a wireframe mesh with color determined by matrix C. MATLAB performs a linear transformation on the data in C to obtain colors from the current colormap. If X, Y, and Z are matrices, they must be the same size as C.

mesh(..., 'PropertyName', PropertyValue,...) sets the value of the specified surface property. Multiple property values can be set with a single statement.

mesh(axes_handles,...) plots into the axes with handle axes handle instead of the current axes (gca).

meshc(...) draws a contour plot beneath the mesh.

meshz(...) draws a curtain plot (i.e., a reference plane) around the mesh.

h = mesh(...), h = meshc(...), and h = meshz(...) return a handle to a surfaceplot graphics object.

Remarks


mesh, meshc, and meshz do not accept complex inputs.

A mesh is drawn as a surface graphics object with the viewpoint specified by view(3). The face color is the same as the background color (to simulate a wireframe with hidden-surface elimination), or none when drawing a standard see-through wireframe. The current colormap determines the edge color. The hidden command controls the simulation of hidden-surface elimination in the mesh, and the shading command controls the shading model.

Examples


Produce a combination mesh and contour plot of the peaks surface:

```
[X,Y] = meshgrid(-3:.125:3);
Z = peaks(X,Y);
meshc(X,Y,Z);
axis([-3 3 -3 3 -10 5])
```



Generate the curtain plot for the peaks function:

```
[X,Y] = meshgrid(-3:.125:3);
Z = peaks(X,Y);
meshz(X,Y,Z)
```



Algorithm

The range of X, Y, and Z, or the current settings of the axes XLimMode, YLimMode, and ZLimMode properties, determine the axis limits. axis sets these properties.

The range of C, or the current settings of the axes CLim and CLimMode properties (also set by the caxis function), determine the color scaling. The scaled color values are used as indices into the current colormap.

The mesh rendering functions produce color values by mapping the z data values (or an explicit color array) onto the current colormap. The MATLAB default behavior is to compute the color limits automatically using the minimum and maximum data values (also set using caxis auto). The minimum data value maps to the first color value in the colormap and the maximum data value maps to the last color value

mesh, meshc, meshz

in the colormap. MATLAB performs a linear transformation on the intermediate values to map them to the current colormap.

meshc calls mesh, turns hold on, and then calls contour and positions the contour on the *x-y* plane. For additional control over the appearance of the contours, you can issue these commands directly. You can combine other types of graphs in this manner, for example surf and pcolor plots.

meshc assumes that X and Y are monotonically increasing. If X or Y is irregularly spaced, contour3 calculates contours using a regularly spaced contour grid, then transforms the data to X or Y.

See Also

contour, hidden, meshgrid, surface, surf, surfc, surfl, waterfall

"Surface and Mesh Creation" on page 1-107 for related functions

Surfaceplot Properties for a list of surfaceplot properties

The functions axis, caxis, colormap, hold, shading, and view all set graphics object properties that affect mesh, meshc, and meshz.

For a discussion of parametric surfaces plots, refer to surf.

Generate X and Y arrays for 3-D plots

Syntax

```
[X,Y] = meshgrid(x,y)
[X,Y] = meshgrid(x)
[X,Y,Z] = meshgrid(x,y,z)
```

Description

[X,Y] = meshgrid(x,y) transforms the domain specified by vectors x and y into arrays X and Y, which can be used to evaluate functions of two variables and three-dimensional mesh/surface plots. The rows of the output array X are copies of the vector x; columns of the output array Y are copies of the vector y.

```
[X,Y] = meshgrid(x) is the same as [X,Y] = meshgrid(x,x).
```

[X,Y,Z] = meshgrid(x,y,z) produces three-dimensional arrays used to evaluate functions of three variables and three-dimensional volumetric plots.

Remarks

The meshgrid function is similar to ndgrid except that the order of the first two input and output arguments is switched. That is, the statement

$$[X,Y,Z] = meshgrid(x,y,z)$$

produces the same result as

$$[Y,X,Z] = ndgrid(y,x,z)$$

Because of this, meshgrid is better suited to problems in two- or three-dimensional Cartesian space, while ndgrid is better suited to multidimensional problems that aren't spatially based.


meshgrid is limited to two- or three-dimensional Cartesian space.

Examples

meshgrid

The following example shows how to use meshgrid to create a surface plot of a function.

```
[X,Y] = meshgrid(-2:.2:2, -2:.2:2);
Z = X .* exp(-X.^2 - Y.^2);
surf(X,Y,Z)
```



See Also

griddata, mesh, ndgrid, slice, surf

meta.class class describes MATLAB classes

Description

Instances of the meta.class class contains information about MATLAB classes. The read/write properties of the meta.class class correspond to class attributes and are set only from within class definitions on the classdef line. You can query the read—only properties of the meta.class object to obtain information that is specified syntactically by the class (for example, to obtain the name of the class).

You cannot instantiate a meta.class object directly. You can construct a meta.class object from an instance of a class or using the class name:

- metaclass returns a meta.class object representing the object passed as an argument.
- ?classname returns a meta.class object representing the named class.
- fromName static method returns a meta.class object representing the named class.

For example, the metaclass function returns the metaclass object representing myclass.

```
ob = myclass;
obmeta = metaclass(ob);
obmeta.Name
ans =
myclass
```

You can use the class name to obtain the meta.class object:

```
obmeta = ?myclass;
```

You can also use the from Name static method:

```
obmeta = meta.class.fromName('myclass');
```

Properties

Property	Purpose
ConstructOnLoad attribute, default = false	If true, the class constructor is called automatically when loading an object from a MAT-file. Therefore, the construction must be implemented so that calling it with no arguments does not produce an error.
	See "Tips for Saving and Loading"
ContainingPackage read only	A meta.package object describing the package within which this class is contained, or an empty object if this class is not in a package.
	See "Scoping Classes with Packages".
Description read only	Currently not used
DetailedDescription read only	Currently not used
Events read only	A cell array of meta.event objects describing each event defined by this class, including all inherited events.
	See "Events — Sending and Responding to Messages" .
Hidden attribute, default = false	If set to true, the class does not appear in the output of MATLAB commands or tools that display class names.
<pre>InferiorClasses attribute, default = {}</pre>	A cell array of meta.class objects defining the precedence of classes represented by the list as inferior to this class.
	See "Specifying Class Precedence"

Property	Purpose
Methods read only	A cell array of meta.method objects describing each method defined by this class, including all inherited public and protected methods.
	See "Class Methods".
Name read only	Name of the class associated with this meta.class object (char array)
Properties read only	A cell array of meta.property objects describing each property defined by this class, including all inherited public and protected properties.
	See "Properties — Storing Class Data".
Sealed attribute, default = false	If true, the class can be not be specialized with subclasses.
SuperClasses read only	A cell array of meta.class objects describing each direct superclass from which this class is derived.
	See "Creating Subclasses — Syntax and Techniques".

Methods

Method	Purpose
fromName	Returns the meta.class object associated with the specified class name.
tf = eq(cls)	Equality function (a == b). Use to test if two variables refer to equal classed (classes that contain exactly the same list of elements).
tf = ne(cls)	Not equal function (a ~= b). Use to test if two variables refer to different meta-classes.

meta.class

Method	Purpose
tf = lt(clsa,clsb)	Less than function (clsa < clsb). Use to determine if clsa is a strict subclass of clsb (i.e., clsb < clsb is false).
<pre>tf = le(clsa,clsb)</pre>	Less than or equal to function (clsa <= clsb). Use to determine if clsa is a subclass of clsb.
<pre>tf = gt(clsa,clsb)</pre>	Greater than function (clsb > clsa). Use to determine if clsb is a strict superclass of clsa (i.e., clsb > clsb is false).
<pre>tf = ge(clsa,clsb)</pre>	Greater than or equal to function (clsb >= clsa). Use to determine if clsb is a superclass of clsa.

See Also

See "Obtaining Information About Classes from Meta-Classes", fromName, meta.property, meta.method, meta.event, meta.package

Return meta.class object associated with named class

Syntax

```
mcls = meta.class.fromName('ClassName')
```

Description

mcls = meta.class.fromName('ClassName') is a static method that
returns the meta.class object associated with the class ClassName.
Note that you can also use the ? operator to obtain the meta.class
object for a class name:

```
mcls = ?ClassName;
```

The equivalent call to meta.class.fromName is:

```
mcls = meta.class.fromName('ClassName');
```

Use meta.class.fromName when using a char variable for the class name:

```
function mcls = getMetaClass(clname)
% Do error checking
mcls = meta.class.fromName(clname);
...
end
```

See Also

meta.class

meta.DynamicProperty

Purpose

meta.DynamicProperty class describes dynamic property of MATLAB object

Description

The meta.DynamicProperty class contains descriptive information about dynamic properties that you have added to an instance of a MATLAB classes. The MATLAB class must be a subclass of dynamicprops. The properties of the meta.DynamicProperty class correspond to property attributes that you specify from within class definitions. Dynamic properties are not defined in classdef blocks, but you can set their attributes by setting the meta.DynamicProperty object properties.

You add a dynamic property to an object using the addprop method of the dynamicprops class. The addprop method returns a meta.DynamicProperty instance representing the new dynamic property. You can modify the properties of the meta.DynamicProperty object to set the attributes of the dynamic property or to add set and get access methods, which would be defined in the classdef for regular properties.

You cannot instantiate the meta.DynamicProperty class. You must use addprop to obtain a meta.DynamicProperty object.

To remove the dynamic property, call the delete handle class method on the meta.DynamicProperty object.

Obtain a meta.DynamicProperty object from the addprops method, which returns an array of meta.DynamicProperty objects, one for each dynamic property.

See "Dynamic Properties — Adding Properties to an Instance" for more information.

Properties

Property	Purpose
Name	Name of the property.
Description	Can contain text

meta.DynamicProperty

Property	Purpose
DetailedDescription	Can contain text
Abstract attribute, default = false	If true, the property has no implementation, but a concrete subclass must redefine this property without Abstract being set to true.
	• Abstract properties cannot define set or get access methods. See "Controlling Property Access"
	• Abstract properties cannot define initial values. "Assigning a Default Value"
	 All subclasses must specify the same values as the superclass for the property SetAccess and GetAccess attributes.
	• Abstract=true should be used with the class attribute Sealed=false (the default).
Constant attribute, default = false	Set to true if you want only one value for this property in all instances of the class.
	• Subclasses inherit constant properties, but cannot change them.
	• Constant properties cannot be Dependent
	• SetAccess is ignored.
	See "Defining Named Constants"
GetAccess attribute, default = public	public – unrestricted access
	<pre>protected - access from class or derived classes</pre>
	private — access by class members only

meta.DynamicProperty

Property	Purpose
SetAccess attribute,	public – unrestricted access
default = public	protected – access from class or derived classes
	private — access by class members only
Dependent attribute, default = false	If false, property value is stored in object. If true, property value is not stored in object and the set and get functions cannot access the property by indexing into the object using the property name.
	See "Property Get Methods"
Transient attribute, default = false	If true, property value is not saved when object is saved to a file. See "The Save and Load Process" for more about saving objects.
Hidden attribute, default = false	Determines whether the property should be shown in a property list (e.g., Property Inspector, call to properties, etc.).
GetObservable attribute, default = false	If true, and it is a handle class property, then listeners can be created for access to this property. The listeners are called whenever property values are queried. See "Property-Set and Query Events"
SetObservable attribute, default = false	If true, and it is a handle class property, then listeners can be created for access to this property. The listeners are called whenever property values are modified. See "Property-Set and Query Events"
GetMethod	Function handle of the get method associated with this property. Empty if there is no get method specified. See "Property Get Method"

Property	Purpose
SetMethod	Function handle of the set method associated with this property. Empty if there is no set method specified. See "Property Set Methods"
HasDefault	Always false. Dynamic properties cannot define default values.
DefaultValue	Querying this property returns an error because dynamic properties cannot define default values.
DefiningClass	The meta.class object representing the class that defines this property.

Events

See "Listening for Changes to Property Values" for information on using property events.

Event Name	Purpose
PreGet	Event occurs just before property is queried.
PostGet	Event occurs just after property has been queried
PreSet	Event occurs just before this property is modified
PostSet	Event occurs just after this property has been modified
ObjectBeingDestroye	dInherited from handle

See Also

addprop, handle

meta.event class describes MATLAB class events

Description

The meta.event class provides information about MATLAB class events. The read/write properties of the meta.event class correspond to event attributes and are specified only from within class definitions.

You can query the read-only properties of the meta.event object to obtain information that is specified syntactically by the class (for example, to obtain the name of the class defining the event).

You cannot instantiate a meta.event object directly. Obtain a meta.event object from the meta.class Events property, which contains a cell array of meta.event objects, one for each event defined by the class. For example:

```
mco = ?classname;
eventcell = mco.Events;
eventcell{1}.Name; % name of first event
```

Use the metaclass function to obtain a meta.class object from a class instance:

```
mco = metaclass(obj);
```

Properties

Property	Purpose
Name read only	Name of the event.
Description read only	Currently not used
DetailedDescription read only	Currently not used
Hidden	If true, the event does not appear in the list of events returned by the events function (or other event listing functions or viewers)

Property	Purpose
ListenAccess	Determines where you can create listeners for the event.
	• public — unrestricted access
	 protected — access from methods in class or derived classes
	• private — access by class methods only (not from derived classes)
NotifyAccess	Determines where code can trigger the event.
	• public — any code can trigger event
	 protected — can trigger event from methods in class or derived classes
	• private — can trigger event by class methods only (not from derived classes)
DefiningClass	The meta.class object representing the class that defines this event.

See Also

meta.class, meta.property, meta.method, metaclass

"Events — Sending and Responding to Messages"

"Obtaining Information About Classes from Meta-Classes"

meta.method class describes MATLAB class methods

Description

The meta.method class provides information about the methods of MATLAB classes. The read/write properties of the meta.method class correspond to method attributes and are specified only from within class definitions.

You can query the read-only properties of the meta.method object to obtain information that is specified syntactically by the class (for example, to obtain the name of the class defining a method).

You cannot instantiate a meta.method object directly. Obtain a meta.method object from the meta.class Methods property, which contains a cell array of meta.method objects, one for each class method. For example:

```
mco = ?classname;
methodcell = mco.Methods;
methodcell{1}.Name; % name of first method
```

Use the metaclass function to obtain a meta.class object from a class instance:

```
mco = metaclass(obj);
```

Properties

Property	Purpose
Abstract	 If true, the method has no implementation. The method has a syntax line that can include arguments, which subclasses use when implementing the method. Subclasses are not required to define the same number of input and output
	arguments.The method can have comments after the function line

Property	Purpose
	 Does not contain function or end keywords, only the function syntax (e.g., [a,b] = myMethod(x,y))
Access attribute, default = public	Determines what code can call this method. • public — unrestricted access
	• protected — access from methods in class
DefiningClass	The meta.class object representing the class that defines this method.
Description read only	Currently not used
DetailedDescription read only	Currently not used
Hidden attribute, default = false	When false, the method name shows in the list of methods displayed using the methods or methodsview commands. If set to true, the method name is not included in these listings.
Name read only	Name of the method.
Sealed attribute, default = false	If true, the method cannot be redefined in a subclass. Attempting to define a method with the same name in a subclass causes an error.
Static attribute, default = false	Set to true to define a method that does not depend on an object of the class and does not require an object argument. You must use class name to call the method: classname.methodname See "Static Methods"

See Also

meta.class, meta.property, meta.event, metaclass

meta.method

 $\hbox{``Methods} - \hbox{Defining Class Operations''}$

"Obtaining Information About Classes from Meta-Classes"

meta.package class describes MATLAB packages

Description

The meta.package class contains information about MATLAB packages.

You cannot instantiate a meta.package object directly. Obtain a meta.package object from the meta.class ContainingPackage property, which contains a meta.package object, or an empty object, if the class is not in a package.

Properties

Property	Purpose
Name read only	Name of the package associated with this meta.package object
Packages read only	List of packages that are scoped to this package. A cell array of meta.package objects.
Classes read only	List of classes that are scoped to this package. A cell array of meta.class objects.
Functions read only	List of functions that are scoped to this package. A cell array of function handles.
ContainingPacka read only	meta.package object describing the package within which this package is contained, or an empty object if this package is not nested.

Methods

Method	Purpose
fromName	Static method returns a meta.package object for a specified package name.
getAllPackages	Static method returns a cell array of meta.package objects representing all top-level packages.

See Also

See "Obtaining Information About Classes from Meta-Classes" meta.class, meta.property, meta.method, meta.event

meta.package.fromName

Purpose Return meta.package object for specified package

Syntax mpkg = meta.package.fromName('pkgname')

Description mpkg = meta.package.fromName('pkgname') is a static method that

returns the meta.package object associated with the named package. If pkgname is a nested package, then you must provide the fully qualified

name (e.g., 'pkgname1.pkgname2').

Examples List the classes in the event package:

```
mev = meta.package.fromName('event');
for k=1:length(mev.Classes)
    disp(mev.Classes{k}.Name)
end
event.EventData
event.PropertyEvent
event.listener
event.proplistener
```

See Also meta.package, meta.package.getAllPackages

meta.package.getAllPackages

Purpose Get all top-level packages

Syntax P = meta.package.getAllPackages

Description P = meta.package.getAllPackages is a static method that returns

a cell array of meta.package objects representing all the top-level packages that are visible on the MATLAB path or defined as top-level built-in packages. You can access subpackages using the Packages

property of each meta.package object.

Note that the time required to find all the packages on the path might be excessively long in some cases. You should therefore avoid using this method in any code where execution time is a consideration. getAllPackages is generally intended for interactive use only.

See Also meta.package, meta.package.fromName

meta.property class describes MATLAB class properties

Description

The meta.property class provides information about the properties of MATLAB classes. The read/write properties of the meta.property class correspond to property attributes and are specified only from within your class definitions.

You can query the read-only properties of the meta.property object to obtain information that is specified syntactically by the class (for example, to obtain the function handle of a property's set access method).

You cannot instantiate a meta.property object directly. Obtain a meta.property object from the meta.class Properties property, which contains a cell array of meta.property objects, one for each class property. For example:

```
mco = ?classname;
propcell = mco.Properties;
propcell{1}.Name; % name of first property
```

Use the metaclass function to obtain a meta.class object from a class instance:

```
mco = metaclass(obj);
```

Properties

Property	Purpose
AbortSet attribute, default = false	If true, and this property belongs to a handle class, then MATLAB does not set the property value if the new value is the same as the current value. This prevents the triggering of property PreSet and PostSet events. See "Listening for Changes to Property

Property	Purpose
Abstract attribute, default = false	If true, the property has no implementation, but a concrete subclass must redefine this property without Abstract being set to true.
	• Abstract properties cannot define set or get access methods. See "Controlling Property Access"
	Abstract properties cannot define initial values. "Assigning a Default Value"
	All subclasses must specify the same values as the superclass for the property SetAccess and GetAccess attributes.
	• Abstract=true should be used with the class attribute Sealed=false (the default).
Constant attribute, default = false	Set to true if you want only one value for this property in all instances of the class.
	• Subclasses inherit constant properties, but cannot change them.
	Constant properties cannot be Dependent
	SetAccess is ignored.
	See "Defining Named Constants"
DefaultValue	Property default value (if specified in class definition). See also HasDefault property. Abstract, dependent and dynamic properties cannot specify default values.
DefiningClass	The meta.class object representing the class that defines this property.

Property	Purpose
Dependent attribute, default = false	If false, property value is stored in object. If true, property value is not stored in object and the set and get functions cannot access the property by indexing into the object using the property name.
	See "Property Get Methods"
Description read only	Currently not used
DetailedDescription read only	Currently not used
GetAccess attribute,	public – unrestricted access
default = public	<pre>protected - access from class or derived classes</pre>
	private — access by class members only
GetMethod read only	Function handle of the get method associated with this property. Empty if there is no get method specified. See "Property Get Method"
GetObservable attribute, default = false	If true, and it is a handle class property, then listeners can be created for access to this property. The listeners are called whenever property values are queried. See "Property-Set and Query Events"
HasDefault	Property contains a boolean value indicating if the property defines a default value. Test HasDefault before querying the DefaultValue property to avoid a MATLAB:class:NoDefaultDefined error.
Hidden attribute, default = false	Determines whether the property should be shown in a property list (e.g., Property Inspector, call to properties, etc.).

Property	Purpose		
Name read only	Name of the property.		
SetAccess attribute, default = public	public – unrestricted access		
doradir public	protected – access from class or derived classes		
	private — access by class members only		
SetMethod read only	Function handle of the set method associated with this property. Empty if there is no set method specified. See "Property Set Methods"		
SetObservable attribute, default = false	If true, and it is a handle class property, then listeners can be created for access to this property. The listeners are called whenever property values are modified. See "Property-Set and Query Events"		
Transient attribute, default = false	If true, property value is not saved when object is saved to a file. See "The Save and Load Process" for more about saving objects.		

Events

See for information on using property events.

Event Name	Purpose
PreGet	Event occurs just before property is queried.
PostGet	Event occurs just after property has been queried
PreSet	Event occurs just before this property is modified
PostSet	Event occurs just after this property has been modified

See Also

meta.class, meta.method, meta.event, metaclass

meta.property

"Properties — Storing Class Data"

"Obtaining Information About Classes from Meta-Classes"

Obtain meta.class object

Syntax

```
mc = metaclass(object)
mc = ?ClassName
```

Description

mc = metaclass(object) returns the meta.class object for the class of object. The object input argument can be a scalar or an array of objects. However, metaclass always returns a scalar meta.class object.

mc = ?ClassName returns the meta.class object for the class with name, ClassName. The ? operator works only with a class name, not an object.

If you pass a class name as a string to the metaclass function, it returns the meta.class object for the char class. Use the ? operator or the meta.class.fromName method to obtain the meta.class object from a class name. Use this method if you want to pass the class name in a string variable.

Examples

Return the meta.class object for an instance of the MException class:

```
obj = MException('Msg:ID','MsgTxt');
mc = metaclass(obj);
```

Use the ? operator to get the meta.class object for the hgsetget class:

```
mc = ?hgsetget;
```

See Also

meta.class | meta.class.fromName

Tutorials

· "Obtaining Information About Classes from Meta-Classes"

Class method names

Syntax

```
methods('classname')
methods(...,'-full')
m = methods(...)
```

Description

methods('classname') displays the names of the methods for the class classname. If classname is a MATLAB or Java class, then methods displays only public methods, including those methods inherited from superclasses.

methods(..., '-full') displays a full description of the methods, including inheritance information and, for MATLAB and Java methods, method attributes and signatures. methods does not remove duplicate method names with different signatures. Do not use this option with classes defined before MATLAB 7.6.

m = methods(...) returns the method names in a cell array of strings.

methods is also a MATLAB class-definition keyword. See classdef for more information on class-definition keywords.

This function does not show generic methods from classes based on the Microsoft .NET Framework. Use your product documentation to get information on generic methods.

Examples

Retrieve the names of the static methods in class MException:

```
methods('MException')

Methods for class MException:

addCause getReport ne throw eq isequal rethrow throwAsCaller

Static methods:
```

methods

See Also methodsview | properties | events | what | which

Tutorials

• "Methods — Defining Class Operations"

methodsview

Purpose

View class methods

Syntax

methodsview packagename.classname

methodsview classname
methodsview(object)

Description

methodsview packagename.classname displays information about the methods in the class, classname. If the class is in a package, include packagename. If classname is a MATLAB or Sun Java class, methodsview lists only public methods, including those methods inherited from superclasses.

methodsview classname displays information describing the class classname.

methodsview(object) displays information about the methods of the class of object.

methodsview creates a window that displays the methods defined in the specified class. methodsview provides additional information like arguments, returned values, and superclasses. It also includes method qualifiers (for example, abstract or synchronized) and possible exceptions thrown.

Examples

List information on all methods in the java.awt.MenuItem class:

methodsview java.awt.MenuItem

MATLAB displays this information in a new window.

See Also

methods | import | class | javaArray

Compile MEX-function from C/C++ or Fortran source code

Syntax

mex -help mex -setup mex filenames

mex options filenames

Description

mex -help displays the help file for mex.

mex -setup lets you select or change the compiler configuration. MATLAB software searches for installed compilers and allows you to choose an options file as the default for future invocations of mex. For more information, see "Building MEX-Files" and mex.getCompilerConfigurations.

mex *filenames* compiles and links one or more C/C++ or Fortran source files specified in *filenames* into a shared library called a binary MEX-file from MATLAB.

mex options filenames compiles and links one or more source files specified in filenames using one or more of the specified command-line options.

The MEX-file has a platform-dependent extension. Use the mexext function to return the extension for the current machine or for all supported platforms.

filenames can be any combination of source files, object files, and library files. Include both the file name and the file extension in filenames. A non-source-code filenames parameter is passed to the linker without being compiled.

All valid command-line options are shown in the MEX Script Switches on page 2-2554 table. These options are available on all platforms except where noted.

mex also can build executable files for stand alone MATLAB engine and MAT-file applications. For more information, see "Engine/MAT Stand Alone Application Details" on page 2-2559.

You can run mex from the MATLAB Command Prompt, the Microsoft Windows Command Prompt, or the UNIX¹² shell. mex is a script named mex.bat on Windows systems and mex on UNIX systems. It is located in the matlabroot/bin folder.

The first file listed in filenames becomes the name of the binary MEX-file. You can list other source, object, or library files as additional filenames parameters to satisfy external references.

mex uses an options file to specify variables and values that are passed as arguments to the compiler, linker, and other tools (e.g., the resource linker on Windows systems). For more information, see "Options File Details" on page 2-2558. The default name for the options file is mexopts.bat (Windows systems) or mexopts.sh (UNIX systems).

Command-line options to mex may supplement or override contents of the options file. For more information, see "Override Option Details" on page 2-2559.

For an up-to-date list of supported compilers, see the Supported and Compatible Compilers Web page.

MEX Script Switches

Switch	Function	
@rsp_file	(Windows systems only) Include the contents of the text file <i>rsp_file</i> as command-line arguments to mex.	
-arch	Build an output file for architecture arch. To determine the value for arch, type computer('arch') at the MATLAB Command Prompt on the target machine. Valid values for arch depend on the architecture of the build platform. You can get this information from the Help menu, as	

12. UNIX is a registered trademark of The Open Group in the United States and other countries.

Switch	Function		
	described in "Obtaining Information About your Installation" in the <i>Desktop Tools and Development Environment</i> documentation.		
-argcheck	(C/C++ functions only) Add argument checking. This adds code so arguments passed incorrectly to MATLAB API functions cause assertion failures.		
- C	Compile only. Creates an object file, but not a binary MEX-file.		
-compatibleArrayDim	sBuild a binary MEX-file using the MATLAB Version 7.2 array-handling API, which limits arrays to 2^31-1 elements. This option is the default, but in the future the -largeArrayDims option will be the default.		
-cxx	(UNIX systems only) Use the C++ linker to link the MEX-file if the first source file is in C and there are one or more C++ source or object files. This option overrides the assumption that the first source file in the list determines which linker to use.		
- Dname	Define a symbol name to the C preprocessor. Equivalent to a #define <i>name</i> directive in the source.		
	Do not add a space after this switch.		

Switch	Function	
-Dname=value	Define a symbol name and value to the C preprocessor. Equivalent to a #define name value directive in the source.	
	Do not add a space after this switch.	
-f optionsfile	Specify location and name of options file to use. Overrides the mex default-options-file search mechanism.	
-fortran	(UNIX systems only) Specify that the gateway routine is in Fortran. This option overrides the assumption that the first source file in the list determines which linker to use.	
- g	Create a binary MEX-file containing additional symbolic information for use in debugging. This option disables the mex default behavior of optimizing built object code (see the -0 option).	
-h[elp]	Print help for mex.	
-Ipathname	Add pathname to the list of folders to search for #include files.	
	Do not add a space after this switch.	
-inline	Inline matrix accessor functions (MX Matrix Library). This option is deprecated and will be removed in a future release. The generated MEX-function may not be compatible with future versions of MATLAB.	

Switch	Function	
-lname	Link with object library. On Windows systems, name expands to name.lib or libname.lib and on UNIX systems, to libname.so or libname.dylib.	
	Do not add a space after this switch.	
-Lfolder	Add <i>folder</i> to the list of folders to search for libraries specified with the -1 option. On UNIX systems, you must also set the run-time library path, as explained in "Setting Run-Time Library Path".	
	Do not add a space after this switch.	
-largeArrayDims	Build a binary MEX-file using the MATLAB large-array-handling API. This API can handle arrays with more than 2^31-1 elements when compiled on 64-bit platforms. (See also the -compatibleArrayDims option.)	
- n	No execute mode. Print any commands that mex would otherwise have executed, but do not actually execute any of them.	
-0	Optimize the object code. Optimization is enabled by default and by including this option on the command line. If the -g option appears without the -O option, optimization is disabled.	
-outdir <i>dirname</i>	Place all output files in folder dirname.	

Switch	Function	
-output resultname	Create binary MEX-file named resultname. Automatically appends the appropriate MEX-file extension. Overrides the default MEX-file naming mechanism.	
-setup	Specify the compiler options file to use when calling the mex function. When you use this option, all other command-line options are ignored.	
-Uname	Remove any initial definition of the C preprocessor symbol <i>name</i> . (Inverse of the -D option.)	
- V	Do not add a space after this switch. Verbose mode. Print the values for important internal variables after the options file is processed and all command-line arguments are considered. Prints each compile step and final link step fully evaluated.	
name=value	Override an options file variable for variable name. For examples, see Override Option Details in the Remarks section of the mex reference page.	

Remarks Options File Details

MATLAB provides template options files for the compilers that are supported by mex. These templates are located in the <code>matlabroot\bin\win32\mexopts</code> or the <code>matlabroot\bin\win64\mexopts</code> folders on Windows systems, or the <code>matlabroot/bin</code> folder on UNIX systems. These template options files are used by the -setup option to define the selected default options file.

Override Option Details

Use the *name=value* command-line argument to override a variable specified in the options file at the command line. When using this option, you may need to use the shell's quoting syntax to protect characters such as spaces, which have a meaning in the shell syntax.

This option is processed after the options file is processed and all command line arguments are considered.

On Windows platforms, at either the MATLAB prompt or the DOS prompt, use double quotes ("). For example:

```
mex -v COMPFLAGS="$COMPFLAGS -Wall" LINKFLAGS="$LINKFLAGS /VERBOSE"
```

At the MATLAB command line on UNIX platforms, use double quotes ("). Use the backslash (\) escape character before the dollar sign (\$). For example:

```
mex -v CFLAGS="\$CFLAGS -Wall" LDFLAGS="\$LDFLAGS-w" yprime.c
```

At the shell command line on UNIX platforms, use single quotes ('). For example:

```
mex -v CFLAGS='$CFLAGS -Wall' LDFLAGS='$LDFLAGS -w' yprime.c
```

Engine/MAT Stand Alone Application Details

mex can build executable files for stand alone MATLAB engine and MAT-file applications. For these applications, mex does not use the default options file; you must use the -f option to specify an options file.

The options files used to generate stand alone MATLAB engine and MAT-file executables are named *engmatopts.bat on Windows systems, or engopts.sh and matopts.sh on UNIX systems, and are located in the same folder as the template options files referred to above in Options File Details.

Examples Compiling a C File

The following command compiles yprime.c:

mex yprime.c

Using Verbose Mode

When debugging, it is often useful to use verbose mode, as well as include symbolic debugging information:

mex -v -g yprime.c

Overriding Command Line Options

For examples, see "Override Option Details" on page 2-2559.

See Also

computer, dbmex, inmem, loadlibrary, mexext, pcode, prefdir,
system, mex.getCompilerConfigurations

Purpose

Get compiler configuration information for building MEX-files

Syntax

```
cc = mex.getCompilerConfigurations()
cc = mex.getCompilerConfigurations('lang')
cc = mex.getCompilerConfigurations('lang','list')
```

Description

cc = mex.getCompilerConfigurations() returns a mex.CompilerConfiguration object cc containing information about the selected compiler configuration used by mex. The selected compiler is the one you choose when you run the mex -setup command. For details about the mex.CompilerConfiguration class, see "mex.CompilerConfiguration" on page 2-2562.

cc = mex.getCompilerConfigurations('lang') returns an array of mex.CompilerConfiguration objects cc containing information about the selected configuration for the given lang. If the language of the selected complier is different from lang, then cc is empty.

Language *lang* is a string with one of the following values:

- Any All supported languages. This is the default value.
- \bullet $\,$ C $\,$ All C compiler configurations, including C++ configurations.
- C++ or CPP All C++ compiler configurations.
- Fortran All Fortran compiler configurations.

cc = mex.getCompilerConfigurations('lang','list') returns
an array of mex.CompilerConfiguration objects cc containing
information about configurations for the given language and the given
list. Values for list are:

- **Selected** The compiler you choose when you run mex-setup. This is the default value.
- Installed All supported compilers mex finds installed on your system.

 Supported — All compilers supported in the current release. For an up-to-date list of supported compilers, see the Supported and Compatible Compilers Web page.

Classes mex.CompilerConfiguration

The mex.CompilerConfiguration class contains the following read-only properties about compiler configurations.

Property	Purpose		
Name	Name of the compiler		
Manufacturer	Name of the manufacturer of the compiler		
Language	Compiler language		
Version	(Windows platforms only) Version of the compiler		
Location	(Windows platforms only) Folder where compiler is installed		
Details	A mex.CompilerConfigurationDetails object containing specific information about build options. For details about this class, see "mex.CompilerConfigurationDetails" on page 2-2562.		

mex.CompilerConfigurationDetails

The mex.CompilerConfigurationDetails class provides information about the command options used by the compiler, linker and other build programs used to create MEX-files. These properties are read-only.

Property
CompilerExecutable
CompilerFlags
OptimizationFlags

Property DebugFlags LinkerExecutable LinkerFlags LinkerOptimizationFlags LinkerDebugFlags

Examples Selected Compiler Example

```
myCompiler = mex.getCompilerConfigurations()
```

MATLAB software displays information similar to the following (depending on your architecture, your version of MATLAB, and what you selected when you ran mex -setup):

Supported Compiler Configurations Example

```
allCC = mex.getCompilerConfigurations('Any', 'Supported')
```

MATLAB displays information similar to the following:

```
allCC =
  1x11 mex.CompilerConfiguration
Package: mex

Properties:
  Name
  Manufacturer
  Language
  Version
  Location
  Details

Methods
```

This version of MATLAB supports eleven configurations, hence, allCC is a 1-by-11 matrix.

Supported C Compilers Example

```
To see what \boldsymbol{C} compilers MATLAB supports, type:
```

```
cLanguageCC = mex.getCompilerConfigurations('C', 'Supported')
```

MATLAB displays the following information (the number of compilers for your version of MATLAB may be different):

```
cLanguageCC =
  1x9 mex.CompilerConfiguration
  Package: mex

Properties:
   Name
   Manufacturer
   Language
   Version
```

```
Location
Details
```

Methods

To display the compiler names, type:

```
format compact cLanguageCC.Name
```

MATLAB displays information similar to the following:

```
ans =
Intel C++
ans =
Lcc-win32
ans =
Microsoft Visual C++
ans =
Microsoft Visual C++ 2003
ans =
Microsoft Visual C++ 2005 Express Edition
ans =
Microsoft Visual C++ 2005
ans =
Microsoft Visual C++ 2008
ans =
Open WATCOM C/C++
ans =
Open WATCOM C/C++
```

Example — Viewing Build Options for a C Compiler

To see what build options MATLAB uses with a particular C compiler, create an array CC of all supported C compiler configurations:

```
CC = mex.getCompilerConfigurations('C','Supported');
disp('Compiler Name')
```

```
for i = 1:3; disp(CC(i).Name); end;
MATLAB displays a list similar to:
  Intel C++
  Lcc-win32
  Microsoft Visual C++
To see the build options for the Microsoft Visual C++ compiler, type:
  CC(3).Details
MATLAB displays information similar to the following (output is
formatted):
  ans =
    mex.CompilerConfigurationDetails
    Package: mex
    Properties:
            CompilerExecutable: 'cl'
                 CompilerFlags: '-c -Zp8 -G5 -W3 -EHs
                                 -DMATLAB_MEX_FILE -nologo /MD'
             OptimizationFlags: '-O2 -Oy- -DNDEBUG'
                    DebugFlags: '-Zi
                                 -Fd"%OUTDIR%%MEX NAME%.pdb"'
              LinkerExecutable: 'link'
                   LinkerFlags: [1x258 char]
       LinkerOptimizationFlags: ''
              LinkerDebugFlags: '/debug'
    Methods
```

See Also mex

Capture error information

Syntax

exception = MException(msgIdent, msgString, v_1 , v_2 , ..., v_N)

Description

exception = MException(msgIdent, msgString, v_1 , v_2 , ..., v_N) captures information about a specific error and stores it in MException object, exception. Information stored in the object includes a message identifier msgIdent and an error message string msgString. Optional arguments v_1 , v_2 , ... represent text or numeric values that replace conversion specifiers in msgString at run time.

Message identifier *msgIdent* is a character string composed of at least two substrings, the *component* and the *mnemonic*, separated by a colon (e.g., *component:mnemonic*). The purpose of the identifier is to better identify the source of the error. See the documentation on "Message Identifiers" for more information.

Message string msgString is a character string that informs the user about the cause of the error and can also suggest how to correct the faulty condition. The msgString string can include escape sequences such as \t or \n, as well as any of the format specifiers supported by the sprintf function (such as %s or %d). Additional arguments v_1 , v_2 , ..., v_N provide values that correspond to and replace the conversion specifiers.

For example, if msgString is "Error on line %d, command %s", then v_1 is the line number at which the error was detected, and v_2 is the command that failed. See "Formatting Strings" in the MATLAB Programming Fundamentals documentation for more detailed information on using string formatting commands.

The exception output is an object of the MException class. MException is the constructor for this class. In addition to calling the constructor directly, you can also create an object of MException with any of the following functions: error and assert. See the documentation and figure in the section "The MException Class" for more information on this class.

Properties

The MException object has four properties: identifier, message, stack, and cause. Click any of the links below to find out more about MException properties:

Property	Description
identifier	Identifies the error.
message	Formatted error message that is displayed.
stack	Structure containing stack trace information such as file name, function name, and line number where the MException was thrown.
cause	Cell array of MException that caused this exception to be created.

Methods

The MException class has the following methods. Click any of the links below to find out more about MException methods:

Method	Description	
addCause	Appends an MException to the cause field of another MException.	
getReport	Returns a formatted message string that uses the same format as errors thrown by internal MATLAB code.	
last	Returns an MException object for the most recently thrown exception.	
rethrow	Reissues an exception that has been caught, causing the program to stop.	
throw	Issues an exception from the currently running function.	
throwAsCaller	Issues an exception from the currently running function, also omitting the current stack frame from the stack field of the MException.	

Remarks

Valid escape sequences for the msgString argument are \b, \f, \n, \r, \t, and \x or \ when followed by a valid hexadecimal or octal number, respectively. Following a backslash in the msgString with any other character causes MATLAB to issue a warning. Conversion specifiers are similar to those used in the C programming language and in the sprintf function.

All string input arguments must be enclosed in single quotation marks.

Examples

Example 1 — Formatted Messages

If your message string requires formatting specifications like those used with the sprintf function, you can use this syntax to compose the error message string:

```
exception = MException(msgIdent, msgString, v1, v2, ...)
For example,
  exception = MException('AcctError:Incomplete', ...
        'Field ''%s.%s'' is not defined.', ...
        'Accounts', 'ClientName');
  exception.message
  ans =
        Field 'Accounts.ClientName' is not defined.
```

Example 2

The catch block in this example checks to see if the specified file could not be found. If this is the case, the program allows for the possibility that a common variation of the filename extension (e.g., jpeg instead of jpg) was used by retrying the operation with a modified extension. This is done using a try-catch statement that is nested within the original try-catch.

```
function d_in = read_image(filename)
[path name ext] = fileparts(filename);
try
```

```
fid = fopen(filename, 'r');
   d in = fread(fid);
catch exception
   % Did the read fail because the file could not be found?
   if ~exist(filename, 'file')
      % Yes. Try modifying the filename extension.
      switch ext
      case '.jpg'
                     % Change jpg to jpeg
          altFilename = strrep(filename, '.jpg', '.jpeg')
      case '.jpeg' % Change jpeg to jpg
          altFilename = strrep(filename, '.jpeg', '.jpg')
      case '.tif'
                     % Change tif to tiff
          altFilename = strrep(filename, '.tif', '.tiff')
      case '.tiff'
                     % Change tiff to tif
          altFilename = strrep(filename, '.tiff', '.tif')
      otherwise
         rethrow(exception);
      end
      % Try again, with modifed filename.
      trv
         fid = fopen(altFilename, 'r');
         d in = fread(fid);
      catch
         rethrow(exception)
      end
   end
end
```

Example 3 — Nested try-catch

This example attempts to open a file in a folder that is not on the MATLAB path. It uses a nested try-catch block to give the user the opportunity to extend the path. If the file still cannot be found, the program issues an exception with the first error appended to the second:

```
function data = read_it(filename);
try
   % Attempt to open and read from a file.
   fid = fopen(filename, 'r');
   data = fread(fid);
catch exception1
   % If the error was caused by an invalid file ID, try
   % reading from another location.
   if strcmp(exception1.identifier, 'MATLAB:FileIO:InvalidFid')
      msg = sprintf( ...
         '\nCannot open file %s. Try another location? ', ...
         filename);
      reply = input(msg, 's')
      if reply(1) == 'y'
          newFolder = input('Enter folder name: ', 's');
      else
          throw(exception1);
      end
      oldpath = addpath(newFolder);
      try
         fid = fopen(filename, 'r');
         data = fread(fid);
      catch exception2
         exception3 = addCause(exception2, exception1)
         path(oldpath);
         throw(exception3);
      end
      path(oldpath);
   end
end
fclose(fid);
```

If you run this function in a try-catch block at the command line, you can look at the MException object by assigning it to a variable (e) with the catch command.

MException

See Also

"The MException Class", try, catch, error, assert, throw(MException), rethrow(MException), throwAsCaller(MException), addCause(MException), getReport(MException),last(MException), dbstack

Binary MEX-file name extension

Syntax

```
ext = mexext
extlist = mexext('all')
```

Description

ext = mexext returns the file name extension for the current platform.

extlist = mexext('all') returns a struct with fields arch and ext describing MEX-file name extensions for all platforms.

Remarks

For a table of file extensions, see "Using Binary MEX-Files".

Examples

Find the MEX-file extension for the system you are currently working on:

```
ext = mexext
ext =
   mexw32
```

Find the MEX-file extension for an Apple Macintosh system:

See Also mex

mfilename

Purpose

File name of currently running function

Syntax

mfilename

p = mfilename('fullpath')
c = mfilename('class')

Description

mfilename returns a string containing the file name of the most recently invoked function. When called from within the file, it returns the name of that file. This allows a function to determine its name, even if the file name has been changed.

p = mfilename('fullpath') returns the full path and name of the file in which the call occurs, not including the filename extension.

c = mfilename('class') in a method, returns the class of the method, not including the leading @ sign. If called from a nonmethod, it yields the empty string.

Remarks

If mfilename is called with any argument other than the above two, it behaves as if it were called with no argument.

When called from the command line, mfilename returns an empty string.

To get the names of the callers of a MATLAB function file, use dbstack with an output argument.

See Also

dbstack, function, nargin, nargout, inputname

Download file from FTP server

Syntax

```
mget(f,'filename')
mget(f,'dirname')
mget(...,'target')
```

Description

mget(f, 'filename') retrieves filename from the FTP server f into the MATLAB current directory, where f was created using ftp.

mget(f, 'dirname') retrieves the directory dirname and its contents from the FTP server f into the MATLAB current directory, where f was created using ftp. You can use a wildcard (*) in dirname.

mget(..., 'target') retrieves the specified items from the FTP server f, where f was created using ftp, into the local directory specified by target, where target is an absolute path name.

Examples

Connect to an FTP server and retrieve the file README into the current MATLAB directory.

```
ftpobj = ftp('ftp.mathworks.com');
mget(ftpobj, 'README');
close(ftpobj);
```

See Also

```
cd( ftp), ftp, mput
```

Smallest elements in array

Syntax

```
C = min(A)
C = min(A,B)
C = min(A,[],dim)
[C,I] = min(...)
```

Description

C = min(A) returns the smallest elements along different dimensions of an array.

If A is a vector, min(A) returns the smallest element in A.

If A is a matrix, min(A) treats the columns of A as vectors, returning a row vector containing the minimum element from each column.

If A is a multidimensional array, min operates along the first nonsingleton dimension.

C = min(A,B) returns an array the same size as A and B with the smallest elements taken from A or B. The dimensions of A and B must match, or they may be scalar.

C = min(A,[],dim) returns the smallest elements along the dimension of A specified by scalar dim. For example, min(A,[],1) produces the minimum values along the first dimension (the rows) of A.

[C,I] = min(...) finds the indices of the minimum values of A, and returns them in output vector I. If there are several identical minimum values, the index of the first one found is returned.

Remarks

For complex input A, \min returns the complex number with the smallest complex modulus (magnitude), computed with $\min(abs(A))$. Then computes the smallest phase angle with $\min(angle(x))$, if necessary.

The min function ignores NaNs.

See Also

max, mean, median, sort

Minimum value of timeseries data

Syntax

```
ts_min = min(ts)
ts min = min(ts, 'PropertyName1', PropertyValue1,...)
```

Description

ts_min = min(ts) returns the minimum value in the time-series data. When ts.Data is a vector, ts_min is the minimum value of ts.Data values. When ts.Data is a matrix, ts_min is a row vector containing the minimum value of each column of ts.Data (when IsTimeFirst is true and the first dimension of ts is aligned with time). For the N-dimensional ts.Data array, min always operates along the first nonsingleton dimension of ts.Data.

ts_min = min(ts,'PropertyName1',PropertyValue1,...)
specifies the following optional input arguments:

- 'MissingData' property has two possible values, 'remove' (default) or 'interpolate', indicating how to treat missing data during the calculation.
- 'Quality' values are specified by a vector of integers, indicating which quality codes represent missing samples (for vector data) or missing observations (for data arrays with two or more dimensions).
- 'Weighting' property has two possible values, 'none' (default) or 'time'.

When you specify 'time', larger time values correspond to larger weights.

Examples

The following example illustrates how to find the minimum values in multivariate time-series data.

1 Load a 24-by-3 data array.

load count.dat

2 Create a timeseries object with 24 time values.

```
count_ts = timeseries(count,[1:24],'Name','CountPerSecond')
```

3 Find the minimum in each data column for this timeseries object.

The minimum is found independently for each data column in the timeseries object.

See Also

iqr (timeseries), max (timeseries), median (timeseries), mean
(timeseries), std (timeseries), timeseries, var (timeseries)

MinimizeCommandWindow

Purpose

Minimize size of Automation server window

Syntax

MATLAB Client

h.MinimizeCommandWindow
MinimizeCommandWindow(h)

IDL Method Signature

HRESULT MinimizeCommandWindow(void)

Microsoft Visual Basic Client

MinimizeCommandWindow

Description

h.MinimizeCommandWindow minimizes the window for the server attached to handle h. and makes it inactive.

MinimizeCommandWindow(h) is an alternate syntax.

If the server window was already in a minimized state, MinimizeCommandWindow does nothing.

Examples

From a MATLAB client, modify the size of the command window in a MATLAB Automation server:

```
h = actxserver('matlab.application');
```

h.MinimizeCommandWindow;

% Now return the server window to its former state on

% the desktop and make it the currently active window.

h.MaximizeCommandWindow;

From a Visual Basic client, modify the size of the command window in a MATLAB Automation server:

```
Dim Matlab As Object
```

```
Matlab = CreateObject("matlab.application")
Matlab.MinimizeCommandWindow
```

MinimizeCommandWindow

'Now return the server window to its former state on 'the desktop and make it the currently active window.

Matlab.MaximizeCommandWindow

See Also MaximizeCommandWindow

How To• "MATLAB COM Automation Server Support"

• "Controlling the Server Window"

Minimum residual method

Syntax

```
x = minres(A,b)
minres(A,b,tol)
minres(A,b,tol,maxit)
minres(A,b,tol,maxit,M)
minres(A,b,tol,maxit,M1,M2)
minres(A,b,tol,maxit,M1,M2,x0)
[x,flag] = minres(A,b,...)
[x,flag,relres] = minres(A,b,...)
[x,flag,relres,iter] = minres(A,b,...)
[x,flag,relres,iter,resvec] = minres(A,b,...)
[x,flag,relres,iter,resvec,resveccg] = minres(A,b,...)
```

Description

x = minres(A,b) attempts to find a minimum norm residual solution x to the system of linear equations A*x=b. The n-by-n coefficient matrix A must be symmetric but need not be positive definite. It should be large and sparse. The column vector b must have length n. A can be a function handle afun such that afun(x) returns A*x. See "Function Handles" in the MATLAB Programming documentation for more information.

"Parameterizing Functions", in the MATLAB Mathematics documentation, explains how to provide additional parameters to the function afun, as well as the preconditioner function mfun described below, if necessary.

If minres converges, a message to that effect is displayed. If minres fails to converge after the maximum number of iterations or halts for any reason, a warning message is printed displaying the relative residual norm(b-A*x)/norm(b) and the iteration number at which the method stopped or failed.

minres(A,b,tol) specifies the tolerance of the method. If tol is [], then minres uses the default, 1e-6.

minres(A,b,tol,maxit) specifies the maximum number of iterations. If maxit is [], then minres uses the default, min(n,20).

minres(A,b,tol,maxit,M) and minres(A,b,tol,maxit,M1,M2) use symmetric positive definite preconditioner M or M = M1*M2 and effectively solve the system inv(sqrt(M))*A*inv(sqrt(M))*y = inv(sqrt(M))*b for y and then return x = inv(sqrt(M))*y. If M is [] then minres applies no preconditioner. M can be a function handle mfun, such that mfun(x) returns $M \setminus x$.

minres(A,b,tol,maxit,M1,M2,x0) specifies the initial guess. If x0 is [], then minres uses the default, an all-zero vector.

[x,flag] =	minres(A,b,)	also returns a	convergence flag.
------------	--------------	----------------	-------------------

Flag	Convergence
0	minres converged to the desired tolerance tol within maxit iterations.
1	minres iterated maxit times but did not converge.
2	Preconditioner M was ill-conditioned.
3	minres stagnated. (Two consecutive iterates were the same.)
4	One of the scalar quantities calculated during minres became too small or too large to continue computing.

Whenever flag is not 0, the solution x returned is that with minimal norm residual computed over all the iterations. No messages are displayed if the flag output is specified.

[x,flag,relres] = minres(A,b,...) also returns the relative residual norm(b-A*x)/norm(b). If flag is 0, relres \leq tol.

[x,flag,relres,iter] = minres(A,b,...) also returns the iteration number at which x was computed, where 0 <= iter <= maxit.

[x,flag,relres,iter,resvec] = minres(A,b,...) also returns a vector of estimates of the minres residual norms at each iteration, including norm(b-A*x0).

[x,flag,relres,iter,resvec,resveccg] = minres(A,b,...) also returns a vector of estimates of the Conjugate Gradients residual norms at each iteration.

Examples Example 1

```
n = 100; on = ones(n,1);
A = spdiags([-2*on 4*on -2*on],-1:1,n,n);
b = sum(A,2);
tol = 1e-10;
maxit = 50;
M1 = spdiags(4*on,0,n,n);

x = minres(A,b,tol,maxit,M1);
minres converged at iteration 49 to a solution with relative residual 4.7e-014
```

Example 2

This example replaces the matrix A in Example 1 with a handle to a matrix-vector product function afun. The example is contained in an M-file $\operatorname{run_minres}$ that

- Calls minres with the function handle @afun as its first argument.
- Contains afun as a nested function, so that all variables in run minres are available to afun.

The following shows the code for run_minres:

```
function x1 = run_minres
n = 100;
on = ones(n,1);
A = spdiags([-2*on 4*on -2*on],-1:1,n,n);
b = sum(A,2);
tol = 1e-10;
maxit = 50;
M = spdiags(4*on,0,n,n);
x1 = minres(@afun,b,tol,maxit,M);
```

```
y = 4 * x;
y(2:n) = y(2:n) - 2 * x(1:n-1);
y(1:n-1) = y(1:n-1) - 2 * x(2:n);
end
end

When you enter
x1=run_minres;

MATLAB software displays the message
minres converged at iteration 49 to a solution with relative residual 4.7e-014

Example 3
```

Use a symmetric indefinite matrix that fails with pcg.

function y = afun(x)

```
A = diag([20:-1:1, -1:-20]);
b = sum(A,2);
x = pcg(A,b);
% The true solution is the vector of all ones.
```

displays the following message:

```
pcg stopped at iteration 1 without converging to the desired tolerance 1e-006 because a scalar quantity became too small or too large to continue computing.

The iterate returned (number 0) has relative residual 1
```

However, minres can handle the indefinite matrix A.

```
x = minres(A,b,1e-6,40);
minres converged at iteration 39 to a solution with relative
residual 1.3e-007
```

See Also

bicg, bicgstab, cgs, cholinc, gmres, lsqr, pcg, qmr, symmlq

function_handle (@), mldivide (\)

References

- [1] Barrett, R., M. Berry, T. F. Chan, et al., *Templates for the Solution of Linear Systems: Building Blocks for Iterative Methods*, SIAM, Philadelphia, 1994.
- [2] Paige, C. C. and M. A. Saunders, "Solution of Sparse Indefinite Systems of Linear Equations." *SIAM J. Numer. Anal.*, Vol.12, 1975, pp. 617-629.

mislocked

Purpose Determine if function is locked in memory

Syntax mislocked

mislocked(fun)

Description mislocked by itself returns logical 1 (true) if the currently running

function is locked in memory, and logical O (false) otherwise. Functions that are locked cannot be removed with the clear function unless you first unlock them using the munlock function. You can use locking on

functions that reside in MATLAB .m files or .mex files.

mislocked(fun) returns logical 1 (true) if the function named fun is

locked in memory, and logical O (false) otherwise.

See Also mlock, munlock

Purpose

Make new folder

Graphical Interface

As an alternative to mkdir, use the Current Folder browser.

Syntax

```
mkdir('folderName')
mkdir('parentFolder','folderName')
status = mkdir(...)
[status,message,messageid] = mkdir(...)
```

Description

mkdir('folderName') creates the folder folderName, where folderName can be an absolute or a relative path.

mkdir('parentFolder','folderName') creates the folder folderName in parentFolder, where parentFolder is an absolute or relative path. If parentFolder does not exist, MATLAB attempts to create it. See the Remarks section.

status = mkdir(...) creates the specified folder. When the operation is successful, it returns a status of logical 1. When the operation is unsuccessful, it returns logical 0.

[status,message,messageid] = mkdir(...) creates the specified folder, and returns the status, message string, and MATLAB message ID. The value given to status is logical 1 for success, and logical 0 for error.

Remarks

If an argument specifies a path that includes one or more nonexistent folders, MATLAB attempts to create the nonexistent folder. For example, for

```
mkdir('myFolder\folder1\folder2\targetFolder')
```

if folder1 does not exist, MATLAB creates folder1, creates folder2 within folder1, and creates targetFolder within folder2.

Examples

Creating a Subfolder in the Current Folder

Create a subfolder called newdir in the current folder:

```
mkdir('newdir')
```

Creating a Subfolder in the Specified Parent Folder

Create a subfolder called newFolder in the folder testdata, using a relative path, where newFolder is at the same level as the current folder:

```
mkdir('../testdata','newFolder')
```

Returning Status When Creating a Folder

In this example, the first attempt to create newFolder succeeds, returning a status of 1, and no error or warning message or message identifier:

```
[s, mess, messid] = mkdir('../testdata', 'newFolder')
s =
    1
mess =
    ''
messid =
```

Attempt to create the same folder again. mkdir again returns a success status, and also a warning and message identifier informing you that the folder exists:

```
[s,mess,messid] = mkdir('../testdata','newFolder')
s =
   1
mess =
   Directory "newFolder" already exists.
messid =
   MATLAB:MKDIR:DirectoryExists
```

See Also

copyfile, cd, dir, ls, movefile, rmdir

mkdir

"Managing Files in MATLAB"

mkdir (ftp)

Purpose

Description

mkdir(f,'dirname') creates the directory dirname in the current directory of the FTP server f, where f was created using ftp, and dirname is a path name relative to the current directory on f.

Examples

Connect to hypothetical server testsite and view the contents.

test=ftp('ftp.testsite.com');
dir(test)

Create new directory on FTP server

. . otherfile.m testfolder

Create the folder newfolder in testfolder and close the connection.

```
mkdir(test,'testfolder/newfolder');
close(test);
```

Suppose that the contents include the following:

See Also dir (ftp), ftp, rmdir (ftp)

Purpose

Make piecewise polynomial

Syntax

pp = mkpp(breaks,coefs)
pp = mkpp(breaks,coefs,d)

Description

pp = mkpp(breaks,coefs) builds a piecewise polynomial pp from its breaks and coefficients. breaks is a vector of length L+1 with strictly increasing elements which represent the start and end of each of L intervals. coefs is an L-by-k matrix with each row coefs(i,:) containing the coefficients of the terms, from highest to lowest exponent, of the order k polynomial on the interval [breaks(i),breaks(i+1)].

pp = mkpp(breaks,coefs,d) indicates that the piecewise polynomial pp is d-vector valued, i.e., the value of each of its coefficients is a vector of length d. breaks is an increasing vector of length L+1. coefs is a d-by-L-by-k array with coefs(r,i,:) containing the k coefficients of the ith polynomial piece of the rth component of the piecewise polynomial.

Use ppval to evaluate the piecewise polynomial at specific points. Use unmkpp to extract details of the piecewise polynomial.

Note. The *order* of a polynomial tells you the number of coefficients used in its description. A kth order polynomial has the form

$$c_1 x^{k-1} + c_2 x^{k-2} + \dots + c_{k-1} x + c_k$$

It has k coefficients, some of which can be 0, and maximum exponent k-1. So the order of a polynomial is usually one greater than its degree. For example, a cubic polynomial is of order 4.

Examples

The first plot shows the quadratic polynomial

$$1 - \left(\frac{x}{2} - 1\right)^2 = \frac{-x^2}{4} + x$$


shifted to the interval [-8,-4]. The second plot shows its negative

$$\left(\frac{x}{2} - 1\right)^2 - 1 = \frac{x^2}{4} - x$$

but shifted to the interval [-4,0].

The last plot shows a piecewise polynomial constructed by alternating these two quadratic pieces over four intervals. It also shows its first derivative, which was constructed after breaking the piecewise polynomial apart using unmkpp.

```
subplot(2,2,1)
cc = [-1/4 \ 1 \ 0];
pp1 = mkpp([-8 -4],cc);
xx1 = -8:0.1:-4;
plot(xx1,ppval(pp1,xx1),'k-')
subplot(2,2,2)
pp2 = mkpp([-4 \ 0], -cc);
xx2 = -4:0.1:0;
plot(xx2,ppval(pp2,xx2),'k-')
subplot(2,1,2)
pp = mkpp([-8 -4 0 4 8],[cc;-cc;cc;-cc]);
xx = -8:0.1:8;
plot(xx,ppval(pp,xx),'k-')
[breaks,coefs,1,k,d] = unmkpp(pp);
dpp = mkpp(breaks, repmat(k-1:-1:1, d*1, 1).*coefs(:, 1:k-1), d);
hold on, plot(xx,ppval(dpp,xx),'r-'), hold off
```



See Also

ppval, spline, unmkpp

mldivide \, mrdivide /

Purpose

Left or right matrix division

Syntax

mldivide(A,B) A\B mrdivide(B,A) B/A

Description

mldivide (A,B) and the equivalent A\B perform matrix left division (back slash). A and B must be matrices that have the same number of rows, unless A is a scalar, in which case A\B performs element-wise division — that is, $A\B = A.\B$.

If A is a square matrix, A\B is roughly the same as inv(A)*B, except it is computed in a different way. If A is an n-by-n matrix and B is a column vector with n elements, or a matrix with several such columns, then X = A\B is the solution to the equation AX = B (see "Algorithm" on page 2-2598 for details). A warning message is displayed if A is badly scaled or nearly singular.

If A is an m-by-n matrix with m \sim = n and B is a column vector with m components, or a matrix with several such columns, then X = A\B is the solution in the least squares sense to the under- or overdetermined system of equations AX = B. In other words, X minimizes norm(A*X - B), the length of the vector AX - B. The rank k of A is determined from the QR decomposition with column pivoting (see "Algorithm" on page 2-2598 for details). The computed solution X has at most k nonzero elements per column. If k < n, this is usually not the same solution as x = pinv(A)*B, which returns a least squares solution.

mrdivide(B,A) and the equivalent B/A perform matrix right division (forward slash). B and A must have the same number of columns.

If A is a square matrix, B/A is roughly the same as B*inv(A). If A is an n-by-n matrix and B is a row vector with n elements, or a matrix with several such rows, then X = B/A is the solution to the equation XA = B computed by Gaussian elimination with partial pivoting. A warning message is displayed if A is badly scaled or nearly singular.

If B is an m-by-n matrix with $m \sim n$ and A is a column vector with m components, or a matrix with several such columns, then X = B/A is

the solution in the least squares sense to the under- or overdetermined system of equations XA = B.

Note Matrix right division and matrix left division are related by the equation $B/A = (A' \setminus B')'$.

Least Squares Solutions

If the equation Ax = b does not have a solution (and A is not a square matrix), $x = A \setminus b$ returns a *least squares solution* — in other words, a solution that minimizes the length of the vector $Ax \cdot b$, which is equal to $norm(A*x \cdot b)$. See "Example 3" on page 2-2597 for an example of this.

Examples

Example 1

Suppose that A and b are the following.

To solve the matrix equation Ax = b, enter

$$x=A \setminus b$$

```
x = 0.0500
0.3000
0.0500
```

You can verify that x is the solution to the equation as follows.

```
A*x
ans =
1.0000
2.0000
3.0000
```

Example 2 - A Singular

If A is singular, A\b returns the following warning.

```
Warning: Matrix is singular to working precision.
```

In this case, Ax = b might not have a solution. For example,

```
A = magic(5);
A(:,1) = zeros(1,5); % Set column 1 of A to zeros
b = [1;2;5;7;7];
x = A\b
Warning: Matrix is singular to working precision.
ans =

NaN
NaN
NaN
NaN
NaN
NaN
NaN
```

If you get this warning, you can still attempt to solve Ax = b using the pseudoinverse function pinv.

The result x is least squares solution to Ax = b. To determine whether x is a exact solution — that is, a solution for which Ax - b = 0 — simply compute

```
A*x-b

ans =

-0.0603
    0.6246
    -0.4320
    0.0141
    0.0415
```

The answer is not the zero vector, so x is not an exact solution.

"Pseudoinverses", in the online MATLAB Mathematics documentation, provides more examples of solving linear systems using pinv.

Example 3

Suppose that

```
A = [1 \ 0 \ 0; 1 \ 0 \ 0];

b = [1; \ 2];
```

mldivide \, mrdivide /

Note that Ax = b cannot have a solution, because A*x has equal entries for any x. Entering

$$x = A \setminus b$$

returns the least squares solution

along with a warning that A is rank deficient. Note that x is not an exact solution:

Data Type Support

When computing $X = A \setminus B$ or $X = A \setminus B$, the matrices A and B can have data type double or single. The following rules determine the data type of the result:

- If both A and B have type double, X has type double.
- If either A or B has type single, X has type single.

Algorithm

The specific algorithm used for solving the simultaneous linear equations denoted by $X = A \setminus B$ and X = B / A depends upon the structure of the coefficient matrix A. To determine the structure of A and select the appropriate algorithm, MATLAB software follows this precedence:

1 If A is sparse and diagonal, X is computed by dividing by the diagonal elements of A.

- **2** If A is sparse, square, and banded, then banded solvers are used. Band density is (# nonzeros in the band)/(# nonzeros in a full band). Band density = 1.0 if there are no zeros on any of the three diagonals.
 - If A is real and tridiagonal, i.e., band density = 1.0, and B is real
 with only one column, X is computed quickly using Gaussian
 elimination without pivoting.
 - If the tridiagonal solver detects a need for pivoting, or if A or B is not real, or if B has more than one column, but A is banded with band density greater than the spparms parameter 'bandden' (default = 0.5), then X is computed using the Linear Algebra Package (LAPACK) routines in the following table.

	Real	Complex
A and B double	DGBTRF, DGBTRS	ZGBTRF, ZGBTRS
A or B single	SGBTRF, SGBTRS	CGBTRF, CGBTRS

3 If A is an upper or lower triangular matrix, then X is computed quickly with a backsubstitution algorithm for upper triangular matrices, or a forward substitution algorithm for lower triangular matrices. The check for triangularity is done for full matrices by testing for zero elements and for sparse matrices by accessing the sparse data structure.

If A is a full matrix, computations are performed using the Basic Linear Algebra Subprograms (BLAS) routines in the following table.

	Real	Complex
A and B double	DTRSV, DTRSM	ZTRSV, ZTRSM
A or B single	STRSV, STRSM	CTRSV, CTRSM

4 If A is a permutation of a triangular matrix, then X is computed with a permuted backsubstitution algorithm.

mldivide \, mrdivide /

5 If A is symmetric, or Hermitian, and has real positive diagonal elements, then a Cholesky factorization is attempted (see chol). If A is found to be positive definite, the Cholesky factorization attempt is successful and requires less than half the time of a general factorization. Nonpositive definite matrices are usually detected almost immediately, so this check also requires little time.

If successful, the Cholesky factorization for full A is

$$A = R'*R$$

where R is upper triangular. The solution X is computed by solving two triangular systems,

$$X = R \setminus (R' \setminus B)$$

Computations are performed using the LAPACK routines in the following table.

	Real	Complex
A and B double	DLANSY, DPOTRF, DPOTRS, DPOCON	ZLANHE, ZPOTRF, ZPOTRS, ZPOCON
A or B single	SLANSY, SPOTRF, SPOTRS, SDPOCON	CLANHE, CPOTRF, CPOTRS, CPOCON

6 If A is sparse, then MATLAB software uses CHOLMOD to compute X. The computations result in

$$P'*A*P = R'*R$$

where P is a permutation matrix generated by amd, and R is an upper triangular matrix. In this case,

$$X = P*(R\backslash(R'\backslash(P'*B)))$$

7 If A is not sparse but is symmetric, and the Cholesky factorization failed, then MATLAB solves the system using a symmetric, indefinite factorization. That is, MATLAB computes the factorization P'*A*P=L*D*L', and computes the solution X by X=P*(L'\(D\((L\((P*B)))))). Computations are performed using the LAPACK routines in the following table:

	Real	Complex
A and B double	DLANSY, DSYTRF, DSYTRS, DSYCON	ZLANHE, ZHETRF, ZHETRS, ZHECON
A or B single	SLANSY, SSYTRF, SSYTRS, SSYCON	CLANHE, CHETRF, CHETRS, CHECON

- **8** If A is Hessenberg, but not sparse, it is reduced to an upper triangular matrix and that system is solved via substitution.
- **9** If A is square and does not satisfy criteria 1 through 6, then a general triangular factorization is computed by Gaussian elimination with partial pivoting (see 1u). This results in

$$A = L*U$$

where L is a permutation of a lower triangular matrix and U is an upper triangular matrix. Then X is computed by solving two permuted triangular systems.

$$X = U \setminus (L \setminus B)$$

If A is not sparse, computations are performed using the LAPACK routines in the following table.

	Real	Complex
A and B double	DLANGE, DGESV, DGECON	ZLANGE, ZGESV, ZGECON
A or B single	SLANGE, SGESV, SGECON	CLANGE, CGESV, CGECON

If A is sparse, then UMFPACK is used to compute X. The computations result in

$$P*(R\backslash A)*Q = L*U$$

where

- P is a row permutation matrix
- R is a diagonal matrix that scales the rows of A
- Q is a column reordering matrix.

Then $X = Q^*(U \setminus L \setminus (P^*(R \setminus B)))$.

Note The factorization $P^*(R \setminus A)^*Q = L^*U$ differs from the factorization used by the function lu, which does not scale the rows of A.

10 If A is not square, then Householder reflections are used to compute an orthogonal-triangular factorization.

$$A*P = Q*R$$

where P is a permutation, Q is orthogonal and R is upper triangular (see qr). The least squares solution X is computed with

$$X = P*(R\setminus(Q^{\prime}*B))$$

If A is sparse, MATLAB computes a least squares solution using the sparse qr factorization of A.

If A is full, MATLAB uses the LAPACK routines listed in the following table to compute these matrix factorizations.

	Real	Complex
A and B double	DGEQP3, DORMQR, DTRTRS	ZGEQP3, ZORMQR, ZTRTRS
A or B single	SGEQP3, SORMQR, STRTRS	CGEQP3, CORMQR, CTRTRS

Note To see information about choice of algorithm and storage allocation for sparse matrices, set the spparms parameter 'spumoni' = 1.

See Also

Arithmetic Operators, linsolve, ldivide, rdivide

Purpose

Check MATLAB code files for possible problems

GUI Alternatives

From the Current Folder browser, click the **Actions** button , and then select **Reports > Code Analyzer Report**. See also "Checking for Coding Problems" in the Editor.

Syntax

```
mlint('filename')
mlint('filename','-config=settings.txt')
mlint('filename','-config=factory')
inform=mlint('filename', -struct )
msg=mlint('filename', -string )
[inform,filepaths]=mlint('filename')
inform=mlint('filename', -id )
inform=mlint('filename', -fullpath )
inform=mlint('filename', '-notok')
mlint('filename', -cyc )
mlint('filename', -eml )
%#eml
%#ok
```

Description

mlint('filename') displays messages, sometimes referred to as M-Lint messages, about filename, where the message reports potential problems and opportunities for code improvement. The line number in the message is a hyperlink that opens the file in the Editor, scrolled to that line. If filename is a cell array, information is displayed for each file. For mlint(F1,F2,F3,...), where each input is a character array, MATLAB software displays information about each input file name. You cannot combine cell arrays and character arrays of file names. Note that the exact text of the mlint messages is subject to some change between versions.

mlint('filename','-config=settings.txt') overrides the default active settings file with the settings that enable or suppress messages as indicated in the specified settings.txt file.

Note If used, you must specify the full path to the settings.txt file specified with the -config option.

For information about creating a settings.txt file, see "Setting Code Analyzer Preferences". If you specify an invalid file, mlint returns a message indicating that it cannot open or read the file you specified. In that case, mlint uses the factory default settings.

mlint('filename', '-config=factory') ignores all settings files and uses the factory default preference settings.

inform=mlint('filename', -struct) returns the information in a structure array whose length is the number of messages found. The structure has the fields that follow.

Field	Description
message	Message describing the suspicious construct that code analysis caught.
line	Vector of file line numbers to which the message refers.
column	Two-column array of file columns (column extents) to which the message applies. The first column of the array specifies the column in the Editor where the message begins. The second column of the array specifies the column in the Editor where the message ends. There is one row in the two-column array for each occurrence of a message.

If you specify multiple file names as input, or if you specify a cell array as input, inform contains a cell array of structures.

msg=mlint('filename', -string') returns the information as a string to the variable msg. If you specify multiple file names as input, or if you specify a cell array as input, msg contains a string where each

file's information is separated by 10 equal sign characters (=), a space, the file name, a space, and 10 equal sign characters.

If you omit the **-struct** or **-string** argument and you specify an output argument, the default behavior is **-struct**. If you omit the argument and there are no output arguments, the default behavior is to display the information to the command line.

[inform, filepaths] = mlint('filename') additionally returns filepaths, the absolute paths to the file names, in the same order as you specified them.

inform=mlint('filename', -id') requests the message ID, where ID is a string of the form ABC.... When returned to a structure, the output also has the id field, which is the ID associated with the message.

inform=mlint('filename', -fullpath) assumes that the input file names are absolute paths, so that mlint does not try to locate them.

inform=mlint('filename','-notok') runs mlint for all lines in filename, even those lines that end with the mlint suppression syntax, %#ok.

mlint('filename', -cyc) displays the McCabe complexity (also referred to as cyclomatic complexity) of each function in the file. Higher McCabe complexity values indicate higher complexity, and there is some evidence to suggest that programs with higher complexity values are more likely to contain errors. Frequently, you can lower the complexity of a function by dividing it into smaller, simpler functions. In general, smaller complexity values indicate programs that are easier to understand and modify. Some people advocate splitting up programs that have a complexity rating over 10.

 ${\tt mlint('filename', -eml})}$ enables $Embedded\ MATLAB^{\it @}$ messages for display in the Command Window.

If you include %#eml anywhere within a file, except within a comment, it causes mlint to behave as though you specified eml for that file. For more information, see "Adding the Compilation Directive %#eml". MATLAB comments can follow the %#eml directive.

If you include %#ok at the end of a line in a file, mlint ignores that line. mlint ignores specified messages id1 through idn on a given line when %#ok< id1,id2,...idn> appears at the end of that line. mlint ignores specified messages 1 through n throughout the file when %#ok<*id1,*id2,...*idn> appears at the end of a line. To determine the id for a given message, use the following command, where filename is the name of the file that elicits the message:

```
mlint filename -id
```

For information on adding the %#ok directive using the Editor context menu, see "Suppressing Message Indicators and Messages".

Examples

The following examples use lengthofline.m, which is a sample file with MATLAB code that can be improved. You can find it in <code>matlabroot/help/techdoc/matlab_env/examples</code>. If you want to run the examples, save a copy of lengthofline.m to a location on your MATLAB path.

Running mlint on a File with No Options

To run mlint on the example file, lengthofline.m, run

```
mlint('lengthofline')
```

MATLAB displays the M-Lint messages for lengthofline.m in the Command Window:

```
L 22 (C 1-9): The value assigned here to variable 'nothandle' might never be used.

L 23 (C 12-15): NUMEL(x) is usually faster than PROD(SIZE(x)).

L 24 (C 5-11): 'notline' might be growing inside a loop. Consider preallocating for speed.

L 24 (C 44-49): Use STRCMPI(str1,str2) instead of using LOWER in a call to STRCMP.

L 28 (C 12-15): NUMEL(x) is usually faster than PROD(SIZE(x)).

L 34 (C 13-16): 'data' might be growing inside a loop. Consider preallocating for speed.

L 34 (C 24-31): Use dynamic fieldnames with structures instead of GETFIELD.

Type 'doc struct' for more information.

L 38 (C 29): Use || instead of | as the OR operator in (scalar) conditional statements.

L 39 (C 47): Use || instead of | as the OR operator in (scalar) conditional statements.

L 40 (C 47): Use || instead of | as the OR operator in (scalar) conditional statements.
```

```
L 42 (C 13-16): 'data' might be growing inside a loop. Consider preallocating for speed.

L 43 (C 13-15): 'dim' might be growing inside a loop. Consider preallocating for speed.

L 45 (C 13-15): 'dim' might be growing inside a loop.Consider preallocating for speed.

L 48 (C 52): There may be a parenthesis imbalance around here.

L 48 (C 53): There may be a parenthesis imbalance around here.

L 48 (C 54): There may be a parenthesis imbalance around here.

L 48 (C 55): There may be a parenthesis imbalance around here.

L 49 (C 17): Terminate statement with semicolon to suppress output (in functions).

L 49 (C 23): Use of brackets [] is unnecessary. Use parentheses

to group, if needed.
```

For details about these messages and how to improve the code, see "Changing Code Based on Messages" in the MATLAB Desktop Tools and Development Environment documentation.

Running mlint with Options to Show IDs and Return Results to a Structure

To store the results to a structure and include message IDs, run

```
inform=mlint('lengthofline', '-id')

MATLAB returns

inform =

19x1 struct array with fields:
    message
    line
    column
    id

To see values for the first message, run
    inform(1)

MATLAB displays
    ans =
```

```
message: 'The value assigned here to variable 'nothandle' might never be used.'
    line: 22
column: [1 9]
    id: 'NASGU'
```

Here, the message is for the value that appears on line 22 that extends from column 1-9 in the file.NASGU is the ID for the message 'The value assigned here to variable 'nothandle' might never be used.'.

Suppressing Specific Messages with mlint

When you add <code>%#ok</code> to a line, it suppresses all <code>mlint</code> messages for that line. However, suppose there are multiple messages in a line and you want to suppress some, but not all of them. Or, suppose you want to suppress a specific message, but not all messages that might arise in the future due to changes you make to that line. Use the <code>%#ok</code> syntax in conjunction with message IDs.

This example uses the following code, displayAnonymousFunction.m:

```
function displayAnonymousFunction
% mini tutorial on anonymous function handles.
disp('
        ');
disp('
        Here is an example of an anonymous function that');
disp('
        retrieves the last modified date of a given file: ');
disp(' ');
fileDate = @(f)getfield(dir(f), 'date')
disp('
       ');
disp('
        You can call it by passing a filename into the ');
disp('
        function handle variable. We will use the currently');
disp('
        running file for example purposes: ');
disp('
        ');
thisFile = which(mfilename('fullpath'))
disp('
        ');
disp('
        Now call the anonymous function handle as you would');
```

```
disp(' call any function or function_handle: fileDate(thisFile)');
disp(' ');
fileDate(thisFile)
```

Run mlint with the -id option on displayAnonymousFunction.m:

```
mlint('displayAnonymousFunction','-id')
```

Results displayed to the Command Window show two messages for line 8:

```
L 8 (C 10): NOPRT: Terminate statement with semicolon to suppress output (in functions).
L 8 (C 16-23): GFLD: Use dynamic fieldnames with structures instead of GETFIELD.
```

To suppress the first message on the line (about using a semicolon), use its message ID, NOPRT, with the %#ok syntax as shown here:

```
fileDate = @(f)getfield(dir(f), 'date') %#ok<NOPRT>
```

When you run mlint for displayAnonymousFunction.m, only one message now displays for line 8.

To suppress multiple specific messages for a line, separate message IDs with commas in the %#ok syntax:

```
fileDate = @(f)getfield(dir(f), 'date') %#ok<NOPRT,GFLD>
```

Now when you run mlint for displayAnonymousFunction.m, no messages display for line 8.

Suppressing Specific Messages Throughout a File with mlint

To suppress a specific message throughout a file, use the **%#ok** syntax in conjunction with a message ID preceded by an asterisk (*).

Run mlint with the -id option on the original displayAnonymousFunction.m code presented in the previous example:

```
mlint('displayAnonymousFunction','-id')
```

Results displayed to the Command Window show two messages for line 8:

```
L 8 (C 10): NOPRT: Terminate statement with semicolon to suppress output (in functions).
L 8 (C 16-23): GFLD: Use dynamic fieldnames with structures instead of GETFIELD.
```

To suppress the semicolon message throughout the file, use its message ID, NOPRT, with an asterisk in the %#ok syntax as shown here:

```
fileDate = @(f)getfield(dir(f), 'date') %#ok<*NOPRT>
```

When you run mlint for displayAnonymousFunction.m, the semicolon message is suppressed throughout the file and only one message displays for line 8.

To suppress multiple specific messages throughout a file, separate message IDs with commas in the %#ok syntax, and precede each message ID with an asterisk:

```
fileDate = @(f)getfield(dir(f), 'date') %#ok<*NOPRT, *GFLD>
```

Now when you run mlint for displayAnonymousFunction.m, both the NOPRT andGFLD messages are suppressed throughout the file.

Error Message: An M-Lint message Was Once Suppressed Here, But the Message No Longer Appears

This examples shows how to interpret the message, "An M-Lint message was once suppressed here, but the message no longer appears."

Suppose you direct mlint to ignore line 15, in the file, displayAnonymousFunction.m (the code for which is presented in the third example in this section) by adding %#ok to the end of line 15:

```
thisFile = which(mfilename('fullpath') %#ok
```

When you run mlint for displayAnonymousFunction.m, typically no message is shown for line 15, because it contains the %#ok message suppression syntax. However, there are some exceptions, as follows:

- If you change the code so that it would not elicit the message, "Terminate statement with semicolon to suppress output (in functions)" if you removed the %#ok directive
- If you disable the message in the Code Analyzer preferences after you add the %#ok directive
- If the rules the code analyzer uses for generating the message change

If any one of these cases is true for line 15, then the following message now appears at line 15:

```
An M-Lint message was once suppressed here, but the message no longer appears.
```

To remove this message, use the context menu and select **Remove the Message Suppression**. The %#ok directive is removed and now no messages appear for line 15 of displayAnonymousFunction.m.

Displaying McCabe Complexity with mlint

To display the McCabe complexity of a MATLAB code file, run mlint with the -cyc option, as shown in the following example (assuming you have saved lengthofline.m to a local folder).

```
mlint lengthofline.m -cyc
```

Results displayed in the Command Window show the McCabe complexity of the file, followed by the M-Lint messages, as shown here:

```
L 1 (C 23-34): The McCabe complexity of 'lengthofline' is 12.

L 22 (C 1-9): The value assigned here to variable 'nothandle' might never be used.

L 23 (C 12-15): NUMEL(x) is usually faster than PROD(SIZE(x)).

L 24 (C 5-11): 'notline' might be growing inside a loop. Consider preallocating for speed.

L 24 (C 44-49): Use STRCMPI(str1,str2) instead of using UPPER/LOWER in a call to STRCMP.

L 28 (C 12-15): NUMEL(x) is usually faster than PROD(SIZE(x)).

L 34 (C 13-16): 'data' might be growing inside a loop. Consider preallocating for speed.

L 34 (C 24-31): Use dynamic fieldnames with structures instead of GETFIELD. Type 'doc struct' for mor L 38 (C 29): Use || instead of | as the OR operator in (scalar) conditional statements.

L 39 (C 47): Use || instead of | as the OR operator in (scalar) conditional statements.

L 40 (C 47): Use || instead of | as the OR operator in (scalar) conditional statements.
```

```
L 42 (C 13-16): 'data' might be growing inside a loop. Consider preallocating for speed.
L 43 (C 13-15): 'dim' might be growing inside a loop. Consider preallocating for speed.
L 45 (C 13-15): 'dim' might be growing inside a loop. Consider preallocating for speed.
L 48 (C 52): There may be a parenthesis imbalance around here.
L 48 (C 53): There may be a parenthesis imbalance around here.
L 48 (C 54): There may be a parenthesis imbalance around here.
L 48 (C 55): There may be a parenthesis imbalance around here.
L 49 (C 17): Terminate statement with semicolon to suppress output (in functions).
L 49 (C 23): Use of brackets [] is unnecessary. Use parentheses to group, if needed.
```

See Also mlintrpt, profile

Purpose

Run mlint for file or folder, reporting results in browser

GUI Alternatives

From the Current Folder browser, click the **Actions** button , and then select **Reports** > **Code Analyzer**. See also "Automatically Analyzing Code in the Editor".

Syntax

```
mlintrpt
mlintrpt('filename', file )
mlintrpt('dirname', dir )
mlintrpt('filename', file ,'settings.txt')
mlintrpt('dirname', dir ,'settings.txt')
```

Description

mlintrpt scans all files with an .m file extension in the current folder for M-Lint messages and reports the results in a MATLAB Web browser.

mlintrpt('filename', **file**) scans filename for M-Lint messages and reports results. You can omit **file** in this form of the syntax because it is the default.

mlintrpt('dirname', dir) scans the specified folder. Here, dirname can be in the current folder or can be a full path.

mlintrpt('filename', **file**, 'settings.txt') applies the Code Analyzer preference settings to enable or suppress messages as indicated in the specified settings.txt file. For information about creating a settings.txt file, select **File** > **Preferences** > **Code Analyzer**, and then click **Help**.

mlintrpt('dirname', dir, 'settings.txt') applies the settings indicated in the specified settings.txt file.

Note If you specify a settings.txt file, you must specify the full path to the file.

Examples


lengthofline.m is an example file with code that can be improved. It is found in matlabroot/matlab/help/techdoc/matlab env/examples.

Run Report for All Files in a Folder

Run

```
mlintrpt(fullfile(matlabroot, 'help', 'techdoc', 'matlab_env', 'examples'), 'dir')
```

and MATLAB displays a report of potential problems and improvements for all files with an .m file extension in the examples folder.



mlintrpt

For details about these messages and how to improve the code, see "Changing Code Based on Messages" in the MATLAB Desktop Tools and Development Environment documentation.

Run Report Using Code Analyzer Preference Settings

In **File > Preferences > Code Analyzer**, save preference settings to a file, for example, NoSemis.txt. To apply those settings when you run mlintrpt, use the file option and supply the full path to the settings file name as shown in this example:

```
mlintrpt('lengthofline.m', 'file', ...
'C:\WINNT\Profiles\me\Application Data\MathWorks\MATLAB\R2007a\NoSemis.txt')
```

Alternatively, use fullfile if the settings file is stored in the preferences folder:

```
mlintrpt('lengthofline.m', 'file', fullfile(prefdir,'NoSemis.txt'))
```

Assuming that in that example NoSemis.txt file, the setting for Terminate statement with semicolon to suppress output has been disabled, the results of mlintrpt for lengthofline do not show that message for line 49.

When mlintrpt cannot locate the settings file, the first message in the report is

```
O: Unable to open or read the configuration file 'NoSemis.txt'--using default settings.
```

See Also

mlint

Purpose

Prevent clearing function from memory

Syntax

mlock

Description

mlock locks the currently running function in memory so that subsequent clear functions do not remove it. Locking a function in memory also prevents any persistent variables defined in the file from getting reinitialized.

Use the munlock function to return the file to its normal, clearable state.

Examples

The function testfun begins with an mlock statement.

```
function testfun
mlock
.
```

When you execute this function, it becomes locked in memory. You can check this using the mislocked function.

```
testfun
mislocked('testfun')
ans =
    1
```

Using munlock, you unlock the testfun function in memory. Checking its status with mislocked shows that it is indeed unlocked at this point.

```
munlock('testfun')
mislocked('testfun')
ans =
    0
```

See Also

mislocked, munlock, persistent

mmfileinfo

Purpose

Information about multimedia file

Syntax

info = mmfileinfo(filename)

Description

info = mmfileinfo(filename) returns a structure, info, with fields
containing information about the contents of the multimedia file
identified by filename. The filename input is a string enclosed in
single quotation marks.

If *filename* is a URL, mmfileinfo might take a long time to return because it must first download the file. For large files, downloading can take several minutes. To avoid blocking the MATLAB command line while this processing takes place, download the file before calling mmfileinfo.

The *info* structure contains the following fields, listed in the order they appear in the structure.

Field	Description
Filename	String indicating the name of the file.
Path	String indicating the absolute path to the file.
Duration	Length of the file in seconds.
Audio	Structure containing information about the audio data in the file. See "Audio Data" on page 2-2619 for more information about this data structure.
Video	Structure containing information about the video data in the file. See "Video Data" on page 2-2619 for more information about this data structure.

Audio Data

The Audio structure contains the following fields, listed in the order they appear in the structure. If the file does not contain audio data, the fields in the structure are empty.

Field	Description
Format	Text string, indicating the audio format.
NumberOfChannels	Number of audio channels.

Video Data

The Video structure contains the following fields, listed in the order they appear in the structure. If the file does not contain video data, the fields in the structure are empty.

Field	Description
Format	Text string, indicating the video format.
Height	Height of the video frame.
Width	Width of the video frame.

Examples

Display information about the demo file xylophone.mpg:

```
info = mmfileinfo('xylophone.mpg')
audio = info.Audio
video = info.Video

MATLAB returns:
info =
    Filename: 'xylophone.mpg'
    Path: [1x75 char]
    Duration: 4.7020
```

Video: [1x1 struct]

Audio: [1x1 struct]

mmfileinfo

where Path is system-dependent.

See Also get, mmreader

Create multimedia reader object for reading video files

Description

Use mmreader with the read method to read video data from a multimedia file into the MATLAB workspace.

The file formats that mmreader supports vary by platform, as follows (with no restrictions on file extensions):

All Platforms Motion JPEG 2000 (.mj2)

Windows AVI (.avi),

MPEG-1 (.mpg),

Windows Media Video (.wmv, .asf, .asx),

and any format supported by Microsoft DirectShow.

Macintosh AVI (.avi),

$$\begin{split} & MPEG\text{-}1\;(\texttt{.mpg}),\\ & MPEG\text{-}4\;(\texttt{.mp4},\;\texttt{.m4v}), \end{split}$$

Apple QuickTime Movie (.mov),

and any format supported by QuickTime as listed on .

Linux Any format supported by your installed plug-ins for

GStreamer 0.10 or above, as listed on, including AVI

(.avi) and Ogg Theora (.ogg).

For more information, see "Supported Video File Formats" in the MATLAB Data Import and Export documentation.

Construction

obj = mmreader(filename) constructs obj to read video data from the file named filename. The mmreader constructor searches for the file on the MATLAB path. If it cannot construct the object for any reason, mmreader generates an error.

obj = mmreader(filename, 'PropertyName', PropertyValue) constructs the object using options, specified as property name/value pairs. Property name/value pairs can be in any format that the set method supports: name/value string pairs, structures, or name/value cell array pairs.

Properties

BitsPerPixel

Bits per pixel of the video data. (Read-only)

Duration

Total length of the file in seconds. (Read-only)

FrameRate

Frame rate of the video in frames per second. (Read-only)

Height

Height of the video frame in pixels. (Read-only)

Name

Name of the file associated with the object. (Read-only)

NumberOfFrames

Total number of frames in the video stream. (Read-only)

Some files store video at a variable frame rate, including many Windows Media Video files. For these files, mmreader cannot determine the number of frames until you read the last frame. When you construct the object, mmreader returns a warning and does not set the NumberOfFrames property.

To count the number of frames in a variable frame rate file, use the read method to read the last frame of the file. For example:

```
vidObj = mmreader('varFrameRateFile.wmv');
lastFrame = read(vidObj, inf);
numFrames = vidObj.NumberOfFrames;
```

For more information, see "Reading Variable Frame Rate Video" in the MATLAB Data Import and Export documentation.

Path

String containing the full path to the file associated with the reader. (Read-only)

mmreader class

Tag User-defined string to identify the object.

Default: ''

Type

Class name of the object: 'mmreader'. (Read-only)

UserData

Generic field for user-defined data.

Default: []

VideoFormat

String indicating the MATLAB representation of the video format, such as 'RGB24'. (Read-only)

Query property values for

multimedia reader object

Width

get

Width of the video frame in pixels. (Read-only)

Methods

	multimedia reader object
getFileFormats	File formats that mmreader supports
isPlatformSupported	Determine whether mmreader is available on current platform
read	Read video frame data from multimedia reader object
set	Set property values for

Copy Semantics

Handle. To learn how handle classes affect copy operations, see Copying Objects in the MATLAB Programming Fundamentals documentation.

Examples

Construct an mmreader object for the demo movie file xylophone.mpg and view its properties:

```
xyloObj = mmreader('xylophone.mpg', 'Tag', 'My reader object');
get(xyloObj)
```

Read and play back the movie file xylophone.mpg:

```
xyloObj = mmreader('xylophone.mpg');
nFrames = xyloObj.NumberOfFrames;
vidHeight = xyloObj.Height;
vidWidth = xyloObj.Width;
% Preallocate movie structure.
mov(1:nFrames) = ...
    struct('cdata', zeros(vidHeight, vidWidth, 3, 'uint8'),...
           'colormap', []);
% Read one frame at a time.
for k = 1: nFrames
    mov(k).cdata = read(xylo0bj, k);
end
% Size a figure based on the video's width and height.
hf = figure;
set(hf, 'position', [150 150 vidWidth vidHeight])
% Play back the movie once at the video's frame rate.
movie(hf, mov, 1, xyloObj.FrameRate);
```

See Also

mmfileinfo

mmreader class

How To

• "Reading Video Files"

Modulus after division

Syntax

M = mod(X,Y)

Description

M = mod(X,Y) if $Y \sim 0$, returns X - n.*Y where n = floor(X./Y). If Y is not an integer and the quotient X./Y is within roundoff error of an integer, then n is that integer. The inputs X and Y must be real arrays of the same size, or real scalars.

The following are true by convention:

- mod(X,0) is X
- mod(X,X) is 0
- mod(X,Y) for $X\sim=Y$ and $Y\sim=0$ has the same sign as Y.

Remarks

rem(X,Y) for $X\sim=Y$ and $Y\sim=0$ has the same sign as X.

mod(X,Y) and rem(X,Y) are equal if X and Y have the same sign, but differ by Y if X and Y have different signs.

The mod function is useful for congruence relationships: x and y are congruent (mod m) if and only if mod(x,m) == mod(y,m).

Examples

```
mod(13,5)
ans =
     3
mod([1:5],3)
ans =
     1
            2
                   0
                          1
                                 2
mod(magic(3),3)
ans =
     2
            1
                   0
     0
            2
                   1
            0
                   2
     1
```

See Also rem

Most frequent values in array

Syntax

```
M = mode(X)
M = mode(X, dim)
[M,F] = mode(X, ...)
[M,F,C] = mode(X, ...)
```

Description

M = mode(X) for vector X computes the sample mode M, (i.e., the most frequently occurring value in X). If X is a matrix, then M is a row vector containing the mode of each column of that matrix. If X is an N-dimensional array, then M is the mode of the elements along the first nonsingleton dimension of that array.

When there are multiple values occurring equally frequently, mode returns the smallest of those values. For complex inputs, this is taken to be the first value in a sorted list of values.

M = mode(X, dim) computes the mode along the dimension dim of X.

[M,F] = mode(X, ...) also returns array F, each element of which represents the number of occurrences of the corresponding element of M. The M and F output arrays are of equal size.

 $[M,F,C] = mode(X, \ldots)$ also returns cell array C, each element of which is a sorted vector of all values that have the same frequency as the corresponding element of M. All three output arrays M, F, and C are of equal size.

Remarks

The mode function is most useful with discrete or coarsely rounded data. The mode for a continuous probability distribution is defined as the peak of its density function. Applying the mode function to a sample from that distribution is unlikely to provide a good estimate of the peak; it would be better to compute a histogram or density estimate and calculate the peak of that estimate. Also, the mode function is not suitable for finding peaks in distributions having multiple modes.

Examples Example 1


Find the mode of the 3-by-4 matrix shown here:

Find the mode along the second (row) dimension:

```
mode(X, 2)
ans =
3
0
```

Example 2

Find the mode of a continuous variable grouped into bins:



See Also

mean, median, hist, histc

Control paged output for Command Window

Syntax

more on more off more(n)

A = more(state)

Description

more **on** enables paging of the output in the MATLAB Command Window. MATLAB displays output one page at a time. Use the keys defined in the table below to control paging.

more off disables paging of the output in the MATLAB Command Window

more(n) defines the length of a page to be n lines.

A = more(state) returns in A the number of lines that are currently defined to be a page. The state input can be one of the quoted strings 'on' or 'off', or the number of lines to set as the new page length.

By default, the length of a page is equal to the number of lines available for display in the MATLAB Command Window. Manually changing the size of the command window adjusts the page length accordingly.

If you set the page length to a specific value, MATLAB uses that value for the page size, regardless of the size of the command window. To have MATLAB return to matching page size to window size, type more off followed by more on.

To see the status of more, type get(0, 'More'). MATLAB returns either on or off indicating the more status. You can also set status for more by using set(0, More, 'status'), where 'status' is either 'on' or 'off'.

When you have enabled more and are examining output, you can do the following.

Press the	То
Return key	Advance to the next line of output.
Space bar	Advance to the next page of output.
Q (for quit) key	Terminate display of the text. Do not use Ctrl+C to terminate more or you might generate error messages in the Command Window.

more is in the ${\it off}$ state, by default.

See Also diary

Move or resize control in parent window

Syntax

```
V = h.move(position)
V = move(h, position)
```

Description

V = h.move(position) moves the control to the position specified by the position argument. When you use move with only the handle argument, h, it returns a four-element vector indicating the current position of the control.

```
V = move(h, position) is an alternate syntax.
```

The position argument is a four-element vector specifying the position and size of the control in the parent figure window. The elements of the vector are:

```
[x, y, width, height]
```

where x and y are offsets, in pixels, from the bottom left corner of the figure window to the same corner of the control, and width and height are the size of the control itself.

Examples

This example moves the control:

```
f = figure('Position', [100 100 200 200]);
h = actxcontrol('mwsamp.mwsampctrl.1', [0 0 200 200], f);
pos = h.move([50 50 200 200])
pos =
    50    50    200    200
```

The next example resizes the control to always be centered in the figure as you resize the figure window. Start by creating the script resizectrl.m that contains

```
% Get the new position and size of the figure window
fpos = get(gcbo, 'position');
```

% Resize the control accordingly

```
h.move([0 0 fpos(3) fpos(4)]);
```

Now execute the following:

```
f = figure('Position', [100 100 200 200]);
h = actxcontrol('mwsamp.mwsampctrl.1', [0 0 200 200]);
set(f, 'ResizeFcn', 'resizectrl');
```

As you resize the figure window, notice that the circle moves so that it is always positioned in the center of the window.

See Also

```
set (COM), get (COM)
```

Move file or folder

Graphical Interface

As an alternative to the movefile function, use the Current Folder browser.

Syntax

```
movefile('source')
movefile('source','destination')
movefile('source','destination','f')
[status,message,messageid]=movefile(...)
```

Description

movefile('source') moves the file or folder named source to the current folder, where source is the absolute or relative path name for the folder or file. To move multiple files or folders, use one or more wildcard characters (*) after the last file separator in source. The source argument permits a wildcard character in a path string. movefile does not preserve the archive attribute of source.

movefile ('source', 'destination') moves the file or folder named source to the location destination, where source and destination are the absolute or relative paths for the folder or file. To move multiple files or folders, you can use one or more wildcard characters (*) after the last file separator in source. You cannot use a wildcard character in destination. To rename a file or folder when moving it, make destination a different name than source, and specify only one file for source. When source and destination have the same location, movefile renames source to destination.

movefile('source', 'destination', 'f') moves the file or folder named source to the location destination, regardless of the read-only attribute of destination.

[status,message,messageid]=movefile(...) moves the file or folder named source to the location destination, returning the status, a message, and the MATLAB message ID. Here, status is logical 1 for success or logical 0 for error. movefile requires only one output argument.

Examples Moving a File to the Current Folder

Move the file myfiles/myfunction.m to the current folder:

```
movefile('myfiles/myfunction.m')
```

Move projects/myfiles and its contents to the current folder, when the current folder is projects/testcases:

```
movefile('../myfiles')
```

Renaming a File in the Current Folder

Rename myfunction.m to oldfunction.m:

```
movefile('myfunction.m','oldfunction.m')
```

Using a Wildcard to Move All Matching Files

Move all files in the folder myfiles, whose names begin with my, to the current folder:

```
movefile('myfiles/my*')
```

Moving a File to a Different Folder

Move the file myfunction.m from the current folder to the folder projects, where projects and the current folder are at the same level:

```
movefile('myfunction.m','../projects')
```

Moving a Folder Down One Level

Move the folder projects/testcases and all its contents down a level in projects to projects/myfiles:

```
movefile('projects/testcases','projects/myfiles/')
```

Moving a File to a Read-Only Folder and Renaming the File

Move the file myfile.m from the current folder to d:/work/restricted, assigning it the name test1.m, where restricted is a read-only folder:

```
movefile('myfile.m','d:/work/restricted/test1.m','f')
```

The read-only file myfile.m is no longer in the current folder. The file test1.m is in d:/work/restricted and is read only.

Returning Status When Moving Files

Move all files in the folder myfiles whose names start with new to the current folder, when there is an error. You mistype new* as nex* and no items in the current folder start with nex*:

See Also

```
cd, copyfile, delete, dir, fileattrib, ls, mkdir, rmdir "Managing Files in MATLAB"
```

movegui

Purpose

Move GUI figure to specified location on screen

Syntax

movegui(h,'position')
movegui(position)

movegui(h)
movegui

Description

movegui(h, 'position') moves the figure identified by handle h to the specified screen location, preserving the figure's size. The position argument is a string or a two-element vector, as defined in the following tables.

movegui(position) moves the callback figure (gcbf) or the current figure (gcf) to the specified position.

movegui(h) moves the figure identified by the handle h to the onscreen position.

movegui moves the callback figure (gcbf) or the current figure (gcf) to the onscreen position. You can specify 'movegui' as a CreateFcn callback for a figure. It ensures after you save it, the figure appears on screen when you reload it, regardless of its saved position. See the following example.

When it is a string, *position* is one of the following descriptors.

Position String	Description
north	Top center edge of screen
south	Bottom center edge of screen
east	Right center edge of screen
west	Left center edge of screen
northeast	Top right corner of screen
northwest	Top left corner of screen
southeast	Bottom right corner of screen

Position String	Description
southwest	Bottom left corner
center	Centered on screen
onscreen	Nearest location to current location that is entirely on screen

You can also specify the *position* argument as a two-element vector, [h,v]. Depending on sign, h specifies the figure's offset from the left or right edge of the screen, and v specifies the figure's offset from the top or bottom of the screen, in pixels. The following table summarizes the possible values.

h (for h >= 0)	Offset of left side from left edge of screen
h (for h < 0)	Offset of right side from right edge of screen
v (for v >= 0)	Offset of bottom edge from bottom of screen
v (for v < 0)	Offset of top edge from top of screen

When you apply movegui to a maximized figure window, the window can shrink in size by a few pixels. On Microsoft Windows platforms, using it to move a maximized window toward the Windows task bar creates a gap on the opposite side of the screen about as wide as the task bar.

GUIDE and openfig call movegui when loading figures to ensure they are visible.

Examples

Use movegui to ensure that a saved GUI appears on screen you reload it, regardless of the target computer screen size and resolution. Create a figure that is off the screen, assign movegui as its CreateFcn callback, save it, and then reload the figure.

```
f = figure('Position',[10000,10000,400,300]);
```

movegui

```
% The figure does not display because it is created offscreen
set(f,'CreateFcn','movegui')
hgsave(f,'onscreenfig')
close(f)
f2 = hgload('onscreenfig');
% The reloaded figure is now visible
```

Alternatives

See Also guide | openfig

Tutorials • "Creating a Simple GUI Programmatically"

· "An Address Book Reader"

How To • "Positioning Figures"

Play recorded movie frames

Syntax

```
movie(M)
movie(M,n)
movie(M,n,fps)
movie(h,...)
movie(h,M,n,fps,loc)
```

Description

The movie function plays the movie defined by a matrix whose columns are movie frames (usually produced by getframe).

movie(M) plays the movie in matrix M once, using the current axes as the default target. If you want to play the movie in the figure instead of the axes, specify the figure handle (or gcf) as the first argument: movie(figure_handle,...). M must be an array of movie frames (usually from getframe).

movie (M, n) plays the movie n times. If n is negative, each cycle is shown forward then backward. If n is a vector, the first element is the number of times to play the movie, and the remaining elements make up a list of frames to play in the movie.

For example, if M has four frames then $n = [10 \ 4 \ 4 \ 2 \ 1]$ plays the movie ten times, and the movie consists of frame 4 followed by frame 4 again, followed by frame 2 and finally frame 1.

movie (M,n,fps) plays the movie at fps frames per second. The default is 12 frames per second. Computers that cannot achieve the specified speed play as fast as possible.

movie(h,...) plays the movie centered in the figure or axes identified by the handle h.

movie(h,M,n,fps,loc) specifies loc, a four-element location vector, [x y 0 0], where the lower left corner of the movie frame is anchored (only the first two elements in the vector are used). The location is relative to the lower left corner of the figure or axes specified by handle h and in units of pixels, regardless of the object's Units property.

Remarks

The movie function uses a default figure size of 560-by-420 and does not resize figures to fit movies with larger or smaller frames. To accommodate other frame sizes, you can resize the figure to fit the movie, as shown in the second example below.

movie only accepts 8-bit image frames; it does not accept 16-bit grayscale or 24-bit truecolor image frames.

Buffering the movie places all frames in memory. As a result, on Microsoft Windows and perhaps other platforms, a long movie (on the order of several hundred frames) can exhaust memory, depending on system resources. In such cases an error message is issued that says

```
??? Error using ==> movie
Could not create movie frame
```

You can abort a movie by typing Ctrl-C.

Examples

Example 1: Animate the peaks function as you scale the values of Z:

```
Z = peaks; surf(Z);
axis tight
set(gca,'nextplot','replacechildren');
% Record the movie
for j = 1:20
   surf(sin(2*pi*j/20)*Z,Z)
   F(j) = getframe;
end
% Play the movie ten times
movie(F,10)
```

Example 2: Specify figure when calling movie to fit the movie to the figure:

```
r = subplot(2,1,1)
Z = peaks; surf(Z);
axis tight
set(gca,'nextplot','replacechildren');
```

```
Z = peaks; surf(Z);
  axis tight
  set(gca, 'nextplot', 'replacechildren');
  % Record the movie
  for j = 1:20
   axes(r)
      surf(sin(2*pi*j/20)*Z,Z)
   axes(s)
   surf(sin(2*pi*(j+5)/20)*Z,Z)
      F(j) = getframe(gcf);
   pause(.0333)
  end
  % Play the movie; note that it does not fit the figure properly:
  h2 = figure;
  movie(F,10)
  % Use the figure handle to make the frames fit:
  movie(h2,F,10)
Example 3: With larger frames, first adjust the figure's size to fit the
movie:
  figure('position',[100 100 850 600])
  Z = peaks; surf(Z);
  axis tight
  set(gca, 'nextplot', 'replacechildren');
  % Record the movie
  for j = 1:20
   surf(sin(2*pi*j/20)*Z,Z)
   F(j) = getframe;
  end
  [h, w, p] = size(F(1).cdata); % use 1st frame to get dimensions
  hf = figure;
  % resize figure based on frame's w x h, and place at (150, 150)
  set(hf, 'position', [150 150 w h]);
  axis off
  % tell movie command to place frames at bottom left
```

s = subplot(2,1,2)

movie

movie(hf,F,4,30,[0 0 0 0]);

See Also

aviread, getframe, frame2im, im2frame

"Animation" on page 1-101 for related functions

See Example – Visualizing an FFT as a Movie for another example

Purpose Create Audio/Video Interleaved (AVI) file from MATLAB movie

Syntax movie2avi(mov, filename)

movie2avi(mov, filename, ParameterName, ParameterValue)

Description

movie2avi(mov, filename) creates the AVI file filename from the MATLAB movie mov. The filename input is a string. The mov input is a 1-by-n structure array, where n is the number of frames. Each frame is a structure with two fields: cdata and colormap. For more information, see getframe.

movie2avi(mov, filename, ParameterName, ParameterValue) accepts one or more comma-separated parameter name/value pairs. The following table lists the available parameters and values.

Parameter Name	Value	Default
'colormap'	An m-by-3 matrix defining the colormap for indexed AVI movies, where m is no more than 256 (236 for Indeo compression).	No default
	Valid only when the 'compression' is 'MSVC', 'RLE', or 'None'.	
'compression'	A text string specifying the compression codec to use. To create an uncompressed file, specify a value of 'None'.	'Indeo5' on Windows systems.
	On UNIX operating systems, the only valid value is 'None'.	'None' on UNIX systems.
	On Windows systems, valid values include:	
	• 'MSVC' • 'RLE'	
	• 'Cinepak' on 32-bit systems.	

Parameter Name	Value	Default
	• 'Indeo3' or 'Indeo5' on 32-bit Windows XP systems. Alternatively, specify a custom compression codec on Windows systems using the four-character code that identifies the codec (typically included in the codec documentation). If MATLAB cannot find the specified codec, it returns an error.	
'fps'	A scalar value specifying the speed of the AVI movie in frames per second (fps).	15 fps
'keyframe'	For compressors that support temporal compression, the number of key frames per second.	2.1429 key frames per second
'quality'	A number between 0 and 100. Higher quality numbers result in higher video quality and larger file sizes. Lower quality numbers result in lower video quality and smaller file sizes. Valid only for compressed movies.	75
'videoname'	A descriptive name for the video stream, no more than 64 characters.	filename

Examples

Create a movie and write to an uncompressed AVI file, myPeaks.avi:

Upload file or directory to FTP server

Syntax

mput(f,'filename')

mput(ftp,'directoryname')

mput(f,'wildcard')

Description

mput(f, 'filename') uploads filename from the MATLAB current directory to the current directory of the FTP server f, where filename is a file, and where f was created using ftp. You can use a wildcard (*) in filename. MATLAB returns a cell array listing the full path to the uploaded files on the server.

mput(ftp, 'directoryname') uploads the directory directoryname and its contents. MATLAB returns a cell array listing the full path to the uploaded files on the server.

mput(f, 'wildcard') uploads a set of files or directories specified by a wildcard. MATLAB returns a cell array listing the full path to the uploaded files on the server.

See Also

ftp, mget, mkdir (ftp), rename

Create and open message box

Syntax

h = msgbox(Message)

h = msgbox(Message,Title)

h = msgbox(Message, Title, Icon)

h = msgbox(Message,Title,'custom',IconData,IconCMap)

h = msgbox(...,CreateMode)

Description

h = msgbox(Message) creates a message dialog box that automatically wraps Message to fit an appropriately sized figure. Message is a string vector, string matrix, or cell array. msgbox returns the handle of the message box in h.

h = msgbox(Message, Title) specifies the title of the message box.

h = msgbox(Message,Title,Icon) specifies which icon to display
in the message box. Icon is 'none', 'error', 'help', 'warn', or
'custom'. The default is 'none'.







Error Icon

Help Icon

Warning Icon

h = msgbox(Message,Title,'custom',IconData,IconCMap) defines a customized icon. IconData contains image data defining the icon. IconCMap is the colormap used for the image.

h = msgbox(...,CreateMode) specifies whether the message box is modal or nonmodal. Optionally, it can also specify an interpreter for Message and Title.

If *CreateMode* is a string, it must be one of the values shown in the following table.

CreateMode Value	Description
'modal'	Replaces the message box having the specified Title, that was last created or clicked on, with a modal message box as specified. All other message boxes with the same title are deleted. The message box which is replaced can be either modal or nonmodal.
'non-modal' (default)	Creates a new nonmodal message box with the specified parameters. Existing message boxes with the same title are not deleted.
'replace'	Replaces the message box having the specified Title, that was last created or clicked on, with a nonmodal message box as specified. All other message boxes with the same title are deleted. The message box which is replaced can be either modal or nonmodal.

Note A modal dialog box prevents the user from interacting with other windows before responding. To block MATLAB program execution as well, use the uiwait function.

If you open a dialog with errordlg, msgbox, or warndlg using 'CreateMode', 'modal' and a non-modal dialog created with any of these functions is already present and has the same name as the modal dialog, the non-modal dialog closes when the modal one opens.

For more information about modal dialog boxes, see WindowStyle in the Figure Properties.

If *CreateMode* is a structure, it can have fields WindowStyle and Interpreter. The WindowStyle field must be one of the values in the

table above. Interpreter is one of the strings'tex' or 'none'. The default value for Interpreter is 'none'.

See Also

dialog, errordlg, helpdlg, inputdlg, listdlg, questdlg, warndlg

figure, textwrap, uiwait, uiresume

"Predefined Dialog Boxes" on page 1-113 for related functions

Matrix multiplication

Syntax

C = A*B

Description

C = A*B is the linear algebraic product of the matrices A and B. If A is an m-by-p and B is a p-by-n matrix, the i, j entry of C is defined by

$$C(i,j) = \sum_{k=1}^{p} A(i,k)B(k,j)$$

The product C is an m-by-n matrix. For nonscalar A and B, the number of columns of A must equal the number of rows of B. You can multiply a scalar by a matrix of any size.

The preceding definition says that C(i,j) is the inner product of the ith row of A with the jth column of B. You can write this definition using the MATLAB colon operator as

$$C(i,j) = A(i,:)*B(:,j)$$

where A(i,:) is the ith row of A and B(:,j) is the jth row of B.

Note If A is an m-by-0 empty matrix and B is a 0-by-n empty matrix, where m and n are positive integers, A*B is an m-by-n matrix of all zeros.

Examples

Example 1

If A is a row vector and B is a column vector with the same number of elements as A, A*B is simply the inner product of A and B. For example,

$$A = [5 \ 3 \ 2 \ 6]$$

A =

5 3 2 6

Example 2

The product of \boldsymbol{A} and \boldsymbol{B} is

Note that the second row of A is

```
A(2,:)
ans =
2 4 7
```

while the third column of B is

```
B(:,3)
ans =
11
21
8
```

The inner product of A(2,:) and B(:,3) is

```
A(2,:)*B(:,3)
ans =
162
```

which is the same as C(2,3).

Algorithm

mtimes uses the following Basic Linear Algebra Subroutines (BLAS):

- DDOT
- DGEMV
- DGEMM
- DSYRK
- DSYRZK

mtimes

For inputs of type single, mtimes using corresponding routines that begin with "S" instead of "D".

See Also Arithmetic Operators

mu2lin

Purpose Convert mu-law audio signal to linear

Description y = mu2lin(mu) converts mu-law encoded 8-bit audio signals, stored

as "flints" in the range $0 \le mu \le 255$, to linear signal amplitude in the range -s < Y < s where $s = 32124/32768 \sim 9803$. The input mu is often obtained using fread(..., 'uchar') to read byte-encoded audio files. "Flints" are MATLAB integers — floating-point numbers whose

values are integers.

See Also auread, lin2mu

Read band-interleaved data from binary file


Syntax

X = multibandread(filename, size, precision, offset, interleave, byteorder)

X = multibandread(...,subset1,subset2,subset3)

Description

X = multibandread(filename, size, precision, offset, interleave, byteorder) reads band-sequential (BSQ), band-interleaved-by-line (BIL), or band-interleaved-by-pixel (BIP) data from the binary file filename. The filename input is a string enclosed in single quotes. This function defines *band* as the third dimension in a 3-D array, as shown in this figure.



You can use the parameters to multibandread to specify many aspects of the read operation, such as which bands to read. See "Parameters" on page 2-2658 for more information.

X is a 2-D array if only one band is read; otherwise it is 3-D. X is returned as an array of data type double by default. Use the precision parameter to map the data to a different data type.

X = multibandread(...,subset1,subset2,subset3) reads a subset of the data in the file. You can use up to three subsetting parameters to specify the data subset along row, column, and band dimensions. See "Subsetting Parameters" on page 2-2659 for more information.

Note In addition to BSQ, BIL, and BIP files, multiband imagery may be stored using the TIFF file format. In that case, use the imread function to import the data.

Parameters

This table describes the arguments accepted by multibandread.

Argument	Description
filename	String containing the name of the file to be read.
size	Three-element vector of integers consisting of [height, width, N], where
	 height is the total number of rows
	 width is the total number of elements in each row
	 N is the total number of bands.
	This will be the dimensions of the data if it is read in its entirety.
precision	String specifying the format of the data to be read, such as 'uint8', 'double', 'integer*4', or any of the other precisions supported by the fread function.
	Note: You can also use the precision parameter to specify the format of the output data. For example, to read uint8 data and output a uint8 array, specify a precision of 'uint8=>uint8' (or '*uint8'). To read uint8 data and output it in the MATLAB software in single precision, specify 'uint8=>single'. See fread for more information.

Argument	Description
offset	Scalar specifying the zero-based location of the first data element in the file. This value represents the number of bytes from the beginning of the file to where the data begins.
interleave	String specifying the format in which the data is stored
	• 'bsq' — Band-Sequential
	• 'bil'— Band-Interleaved-by-Line
	• 'bip'— Band-Interleaved-by-Pixel
	For more information about these interleave methods, see the multibandwrite reference page.
byteorder	String specifying the byte ordering (machine format) in which the data is stored, such as
	• 'ieee-le' — Little-endian
	• 'ieee-be' — Big-endian
	See fopen for a complete list of supported formats.

Subsetting Parameters

You can specify up to three subsetting parameters. Each subsetting parameter is a three-element cell array, {dim, method, index}, where

Parameter	Description
dim	Text string specifying the dimension to subset along. It can have any of these values:
	• 'Column'
	• 'Row'

Parameter	Description
	• 'Band'
method	Text string specifying the subsetting method. It can have either of these values:
	• 'Direct'
	• 'Range'
	If you leave out this element of the subset cell array, multibandread uses 'Direct' as the default.
index	If method is 'Direct', index is a vector specifying the indices to read along the Band dimension.
	If method is 'Range', index is a three-element vector of [start, increment, stop] specifying the range and step size to read along the dimension specified in dim. If index is a two-element vector, multibandread assumes that the value of increment is 1.

Examples Example 1

Setup initial parameters for a data set.

```
rows=3; cols=3; bands=5;
filename = tempname;

Define the data set.

fid = fopen(filename, 'w', 'ieee-le');
fwrite(fid, 1:rows*cols*bands, 'double');
fclose(fid);
```

Read every other band of the data using the Band-Sequential format.

Read the first two rows and columns of data using Band-Interleaved-by-Pixel format.

Read the data using Band-Interleaved-by-Line format.

Delete the file created in this example.

```
delete(filename);
```

Example 2

Read int16 BIL data from the FITS file tst0012.fits, starting at byte 74880.

See Also

fread, fwrite, imread, memmapfile, multibandwrite

multibandwrite

Purpose

Write band-interleaved data to file

Syntax

multibandwrite(data,filename,interleave)

multibandwrite(data, filename, interleave, start, totalsize)

multibandwrite(...,param,value...)

Description

multibandwrite(data, filename, interleave) writes data, a two- or three-dimensional numeric or logical array, to the binary file specified by filename. The filename input is a string enclosed in single quotes. The length of the third dimension of data determines the number of bands written to the file. The bands are written to the file in the form specified by interleave. See "Interleave Methods" on page 2-2664 for more information about this argument.

If filename already exists, multibandwrite overwrites it unless you specify the optional offset parameter. See the last alternate syntax for multibandwrite for information about other optional parameters.

multibandwrite(data,filename,interleave,start,totalsize) writes data to the binary file filename in chunks. In this syntax, data is a subset of the complete data set.

start is a 1-by-3 array [firstrow firstcolumn firstband] that specifies the location to start writing data. firstrow and firstcolumn specify the location of the upper left image pixel. firstband gives the index of the first band to write. For example, data(I,J,K) contains the data for the pixel at [firstrow+I-1, firstcolumn+J-1] in the (firstband+K-1)-th band.

totalsize is a 1-by-3 array, [totalrows,totalcolumns,totalbands], which specifies the full, three-dimensional size of the data to be written to the file.

Note In this syntax, you must call multibandwrite multiple times to write all the data to the file. The first time it is called, multibandwrite writes the complete file, using the fill value for all values outside the data subset. In each subsequent call, multibandwrite overwrites these fill values with the data subset in data. The parameters filename, interleave, offset, and totalsize must remain constant throughout the writing of the file.


multibandwrite(...,param,value...) writes the multiband data to a file, specifying any of these optional parameter/value pairs.

Parameter	Description
'precision'	String specifying the form and size of each element written to the file. See the help for fwrite for a list of valid values. The default precision is the class of the data.
'offset'	The number of bytes to skip before the first data element. If the file does not already exist, multibandwrite writes ASCII null values to fill the space. To specify a different fill value, use the parameter 'fillvalue'.
	This option is useful when you are writing a header to the file before or after writing the data. When writing the header to the file after the data is written, open the file with fopen using 'r+' permission.

Parameter	Description
'machfmt'	String to control the format in which the data is written to the file. Typical values are 'ieee-le' for little endian and 'ieee-be' for big endian. See the help for fopen for a complete list of available formats. The default machine format is the local machine format.
'fillvalue'	A number specifying the value to use in place of missing data. 'fillvalue' can be a single number, specifying the fill value for all missing data, or a 1-by-Number-of-bands vector of numbers specifying the fill value for each band. This value is used to fill space when data is written in chunks.

Interleave Methods

interleave is a string that specifies how multibandwrite interleaves the bands as it writes data to the file. If data is two-dimensional, multibandwrite ignores the interleave argument. The following table lists the supported methods and uses this example multiband file to illustrate each method.



Supported methods of interleaving bands include those listed below.

Method	String	Description	Example
Band-Interleaved-by-Line	'bil'	Write an entire row from each band	AAAAABBBBBCCCCC AAAAABBBBBCCCCC AAAAABBBBBCCCCC
Band-Interleaved-by-Pixel	'bip'	Write a pixel from each band	ABCABCABCABC
Band-Sequential	'bsq'	Write each band in its entirety	AAAAA AAAAA BBBBB BBBBB BBBBB CCCCC CCCCC

Examples

Note To run these examples successfully, you must be in a writable directory.

Example 1

Write all data (interleaved by line) to the file in one call.

```
data = reshape(uint16(1:600), [10 20 3]);
multibandwrite(data, 'data.bil', 'bil');
```

Example 2

Write the bands (interleaved by pixel) to the file in separate calls.

Example 3

Write a single-band tiled image with one call for each tile. This is only useful if a subset of each band is available at each call to multibandwrite.

multibandwrite

See Also

multibandread, fwrite, fread

Allow clearing functions from memory

Syntax

munlock
munlock fun
munlock('fun')

Description

munlock unlocks the currently running .m or .mex function in memory so that subsequent clear functions can remove it.

munlock fun unlocks the .m or .mex file named fun from memory. By default, these files are unlocked so that changes to the file are picked up. Calls to munlock are needed only to unlock .m or .mex functions that have been locked with mlock.

munlock('fun') is the function form of munlock.

Examples

The function testfun begins with an mlock statement.

```
function testfun
mlock
.
```

When you execute this function, it becomes locked in memory. You can check this using the mislocked function.

```
testfun
mislocked testfun
ans =
1
```

Using munlock, you unlock the testfun function in memory. Checking its status with mislocked shows that it is indeed unlocked at this point.

```
munlock testfun
mislocked testfun
ans =
```

0

See Also

mlock, mislocked, persistent

namelengthmax

Purpose Maximum identifier length

Syntax len = namelengthmax

Description

len = namelengthmax returns the maximum length allowed for MATLAB identifiers. MATLAB identifiers are

- Variable names
- Function and subfunction names
- Structure fieldnames
- Object names
- File names with a .m, .mex, or .mdl extension

Rather than hard-coding a specific maximum name length into your programs, use the namelengthmax function. This saves you the trouble of having to update these limits should the identifier length change in some future MATLAB release.

Examples

Call namelengthmax to get the maximum identifier length:

```
maxid = namelengthmax
maxid =
   63
```

See Also

isvarname, genvarname

Not-a-Number

Syntax

NaN

Description

NaN returns the IEEE arithmetic representation for Not-a-Number (NaN). These result from operations which have undefined numerical results.

NaN('double') is the same as NaN with no inputs.

NaN('single') is the single precision representation of NaN.

NaN(n) is an n-by-n matrix of NaNs.

NaN(m,n) or NaN([m,n]) is an m-by-n matrix of NaNs.

NaN(m,n,p,...) or NaN([m,n,p,...]) is an m-by-n-by-p-by-... array of NaNs.

Note The size inputs m, n, p, ... should be nonnegative integers. Negative integers are treated as 0.

NaN(...,classname) is an array of NaNs of class specified by classname. classname must be either 'single' or 'double'.

Examples

These operations produce NaN:

- Any arithmetic operation on a NaN, such as sqrt(NaN)
- Addition or subtraction, such as magnitude subtraction of infinities as (+Inf)+(-Inf)
- Multiplication, such as 0*Inf
- Division, such as 0/0 and Inf/Inf
- Remainder, such as rem(x,y) where y is zero or x is infinity

Remarks

Because two NaNs are not equal to each other, logical operations involving NaNs always return false, except ~= (not equal). Consequently,

```
NaN ~= NaN
ans =
1
NaN == NaN
ans =
0
```

and the NaNs in a vector are treated as different unique elements.

```
unique([1 1 NaN NaN])
ans =
          1 NaN NaN
```

Use the isnan function to detect NaNs in an array.

```
isnan([1 1 NaN NaN])
ans =
0 0 1 1
```

See Also

Inf, isnan

Validate number of input arguments

Syntax

```
msgstring = nargchk(minargs, maxargs, numargs)
msgstring = nargchk(minargs, maxargs, numargs, 'string')
msgstruct = nargchk(minargs, maxargs, numargs, 'struct')
```

Description

Use nargchk inside a function to check that the desired number of input arguments is specified in the call to that function.

msgstring = nargchk(minargs, maxargs, numargs) returns an error message string msgstring if the number of inputs specified in the call numargs is less than minargs or greater than maxargs. If numargs is between minargs and maxargs (inclusive), nargchk returns an empty matrix.

It is common to use the nargin function to determine the number of input arguments specified in the call.

msgstring = nargchk(minargs, maxargs, numargs, 'string') is essentially the same as the command shown above, as nargchk returns a string by default.

msgstruct = nargchk(minargs, maxargs, numargs, 'struct') returns an error message structure msgstruct instead of a string. The fields of the return structure contain the error message string and a message identifier. If numargs is between minargs and maxargs (inclusive), nargchk returns an empty structure.

When too few inputs are supplied, the message string and identifier are

```
message: 'Not enough input arguments.'
identifier: 'MATLAB:nargchk:notEnoughInputs'
```

When too many inputs are supplied, the message string and identifier are

```
message: 'Too many input arguments.'
identifier: 'MATLAB:nargchk:tooManyInputs'
```

nargchk

Remarks

nargchk is often used together with the error function. The error function accepts either type of return value from nargchk: a message string or message structure. For example, this command provides the error function with a message string and identifier regarding which error was caught:

```
error(nargchk(2, 4, nargin, 'struct'))
```

If nargchk detects no error, it returns an empty string or structure. When nargchk is used with the error function, as shown here, this empty string or structure is passed as an input to error. When error receives an empty string or structure, it simply returns and no error is generated.

Examples

Given the function foo,

S`

```
function f = foo(x, y, z)
error(nargchk(2, 3, nargin))
```

Then typing foo(1) produces

Not enough input arguments.

See Also

nargoutchk, nargin, nargout, varargin, varargout, error

Number of function arguments

Syntax

nargin
nargin(fun)
nargout
nargout(fun)

Description

In the body of a function, nargin and nargout indicate how many input or output arguments, respectively, a user has supplied. Outside the body of a function, nargin and nargout indicate the number of input or output arguments, respectively, for a given function. The number of arguments is negative if the function has a variable number of arguments.

nargin returns the number of input arguments specified for a function.

nargin(fun) returns the number of declared inputs for the function fun. If the function has a variable number of input arguments, nargin returns a negative value. fun may be the name of a function, or the name of "Function Handles" that map to specific functions.

nargout returns the number of output arguments specified for a function.

nargout (fun) returns the number of declared outputs for the function fun. If the function has a variable number of output arguments, nargout returns a negative value. fun may be the name of a function, or the name of "Function Handles" that map to specific functions.

Examples

This example shows portions of the code for a function called myplot, which accepts an optional number of input and output arguments:

```
function [x0, y0] = myplot(x, y, npts, angle, subdiv)
% MYPLOT Plot a function.
% MYPLOT(x, y, npts, angle, subdiv)
%    The first two input arguments are
%    required; the other three have default values.
...
if nargin < 5, subdiv = 20; end</pre>
```

```
if nargin < 4, angle = 10; end
if nargin < 3, npts = 25; end
...
if nargout == 0
    plot(x, y)
else
    x0 = x;
    y0 = y;
end</pre>
```

See Also

inputname, varargin, varargout, nargchk, nargoutchk

Validate number of output arguments

Syntax

```
msgstring = nargoutchk(minargs, maxargs, numargs)
msgstring = nargoutchk(minargs, maxargs, numargs, 'string')
msgstruct = nargoutchk(minargs, maxargs, numargs, 'struct')
```

Description

Use nargoutchk inside a function to check that the desired number of output arguments is specified in the call to that function.

msgstring = nargoutchk(minargs, maxargs, numargs) returns an error message string msgstring if the number of outputs specified in the call, numargs, is less than minargs or greater than maxargs. If numargs is between minargs and maxargs (inclusive), nargoutchk returns an empty matrix.

It is common to use the nargout function to determine the number of output arguments specified in the call.

msgstring = nargoutchk(minargs, maxargs, numargs, 'string') is essentially the same as the command shown above, as nargoutchk returns a string by default.

msgstruct = nargoutchk(minargs, maxargs, numargs, 'struct') returns an error message structure msgstruct instead of a string. The fields of the return structure contain the error message string and a message identifier. If numargs is between minargs and maxargs (inclusive), nargoutchk returns an empty structure.

When too few outputs are supplied, the message string and identifier are

```
message: 'Not enough output arguments.'
identifier: 'MATLAB:nargoutchk:notEnoughOutputs'
```

When too many outputs are supplied, the message string and identifier are

```
message: 'Too many output arguments.'
identifier: 'MATLAB:nargoutchk:tooManyOutputs'
```

Remarks

nargoutchk is often used together with the error function. The error function accepts either type of return value from nargoutchk: a message string or message structure. For example, this command provides the error function with a message string and identifier regarding which error was caught:

```
error(nargoutchk(2, 4, nargout, 'struct'))
```

If nargoutchk detects no error, it returns an empty string or structure. When nargoutchk is used with the error function, as shown here, this empty string or structure is passed as an input to error. When error receives an empty string or structure, it simply returns and no error is generated.

Examples

You can use nargoutchk to determine if a function has been called with the correct number of output arguments. This example uses nargout to return the number of output arguments specified when the function was called. The function is designed to be called with one, two, or three output arguments. If called with no arguments or more than three arguments, nargoutchk returns an error message:

```
function [s, varargout] = mysize(x)
msg = nargoutchk(1, 3, nargout);
if isempty(msg)
    nout = max(nargout, 1) - 1;
    s = size(x);
    for k = 1:nout, varargout(k) = {s(k)}; end
else
    disp(msg)
end
```

See Also

nargchk, nargout, nargin, varargout, varargin, error

Convert numeric bytes to Unicode characters

Syntax

```
unicodestr = native2unicode(bytes)
unicodestr = native2unicode(bytes, encoding)
```

Description

unicodestr = native2unicode(bytes) takes a vector containing numeric values in the range [0,255] and converts these values as a stream of 8-bit bytes to Unicode characters. The stream of bytes is assumed to be in the MATLAB default character encoding scheme. Return value unicodestr is a char vector that has the same general array shape as bytes.

unicodestr = native2unicode(bytes, encoding) does the conversion with the assumption that the byte stream is in the character encoding scheme specified by the string encoding. encoding must be the empty string ('') or a name or alias for an encoding scheme. Some examples are 'UTF-8', 'latin1', 'US-ASCII', and 'Shift_JIS'. For common names and aliases, see the Web site http://www.iana.org/assignments/character-sets. If encoding is unspecified or is the empty string (''), the MATLAB default encoding scheme is used.

Note If bytes is a char vector, it is returned unchanged.

Examples

This example begins with a vector of bytes in an unknown character encoding scheme. The user-written function detect_encoding determines the encoding scheme. If successful, it returns the encoding scheme name or alias as a string. If unsuccessful, it throws an error represented by an MException object, ME. The example calls native2unicode to convert the bytes to Unicode characters:

```
try
  enc = detect_encoding(bytes);
  str = native2unicode(bytes, enc);
  disp(str);
```

native2unicode

```
catch ME
    rethrow(ME);
end
```

Note that the computer must be configured to display text in a language represented by the detected encoding scheme for the output of disp(str) to be correct.

See Also

unicode2native

Binomial coefficient or all combinations

Syntax

C = nchoosek(n,k)
C = nchoosek(v,k)

Description

C = nchoosek(n,k) where n and k are nonnegative integers, returns $n!/((n-k)! \ k!)$. This is the number of combinations of n things taken k at a time.

C = nchoosek(v,k), where v is a row vector of length n, creates a matrix whose rows consist of all possible combinations of the n elements of v taken k at a time. Matrix C contains $n!/((n-k)! \ k!)$ rows and k columns.

Inputs n, k, and v support classes of float double and float single.

Examples

The command nchoosek(2:2:10,4) returns the even numbers from two to ten, taken four at a time:

2	4	6	8
2	4	6	10
2	4	8	10
2	6	8	10
4	6	8	10

Limitations

When C = nchoosek(n,k) has a large coefficient, a warning will be produced indicating possible inexact results. In such cases, the result is only accurate to 15 digits for double-precision inputs, or 8 digits for single-precision inputs.

C = nchoosek(v,k) is only practical for situations where n is less than about 15.

See Also

perms

Generate arrays for N-D functions and interpolation

Syntax

$$[X1, X2, X3,...] = ndgrid(x1, x2, x3,...)$$

 $[X1, X2,...] = ndgrid(x)$


Description

 $[X1,X2,X3,\ldots]$ = ndgrid(x1,x2,x3,...) transforms the domain specified by vectors x1,x2,x3... into arrays X1,X2,X3... that can be used for the evaluation of functions of multiple variables and multidimensional interpolation. The ith dimension of the output array Xi are copies of elements of the vector xi.

```
[X1,X2,...] = ndgrid(x) is the same as [X1,X2,...] = ndgrid(x,x,...).
```

Examples

Evaluate the function $x_1e^{-x_1^2-x_2^2}$ over the range $-2 < x_1 < 2, -2 < x_2 < 2$.



Remarks

The ndgrid function is like meshgrid except that the order of the first two input arguments are switched. That is, the statement

$$[X1, X2, X3] = ndgrid(x1, x2, x3)$$

produces the same result as

$$[X2,X1,X3] = meshgrid(x2,x1,x3)$$

Because of this, ndgrid is better suited to multidimensional problems that aren't spatially based, while meshgrid is better suited to problems in two- or three-dimensional Cartesian space.

See Also

meshgrid, interpn

ndims

Purpose Number of array dimensions

Syntax n = ndims(A)

Description n = ndims(A) returns the number of dimensions in the array A. The

number of dimensions in an array is always greater than or equal to 2. Trailing singleton dimensions are ignored. A singleton dimension is any

dimension for which size(A,dim) = 1.

Algorithm ndims(x) is length(size(x)).

See Also size

Test for inequality

Syntax

 $A \sim= B$ ne(A, B)

Description

A ~= B compares each element of array A with the corresponding element of array B, and returns an array with elements set to logical 1 (true) where A and B are unequal, or logical 0 (false) where they are equal. Each input of the expression can be an array or a scalar value.

If both A and B are scalar (i.e., 1-by-1 matrices), then the MATLAB software returns a scalar value.

If both A and B are nonscalar arrays, then these arrays must have the same dimensions, and MATLAB returns an array of the same dimensions as A and B.

If one input is scalar and the other a nonscalar array, then the scalar input is treated as if it were an array having the same dimensions as the nonscalar input array. In other words, if input A is the number 100, and B is a 3-by-5 matrix, then A is treated as if it were a 3-by-5 matrix of elements, each set to 100. MATLAB returns an array of the same dimensions as the nonscalar input array.

ne(A, B) is called for the syntax A ~= B when either A or B is an object.

Examples

Create two 6-by-6 matrices, A and B, and locate those elements of A that are not equal to the corresponding elements of B:

```
A = magic(6);
B = repmat(magic(3), 2, 2);
A ~= B
ans =
                          1
     1
            0
                   0
                                        1
     0
            1
                   0
                          1
                                        1
     1
            0
                   0
                          1
                                 1
                                        1
            1
                   1
     0
                          1
     1
            0
                   1
                                 1
                                        1
```

0 1 1 1 1 1

See Also

eq, le, ge, lt, gt, relational operators

DelaunayTri.nearestNeighbor

Purpose

Point closest to specified location

Syntax

PI = nearestNeighbor(DT, QX)
PI = nearestNeighbor(DT, QX,QY)
PI = nearestNeighbor(DT, QX,QY,QZ)

Description

PI = nearestNeighbor(DT, QX) returns the index of nearest point in DT.X for each guery point location in QX.

PI = nearestNeighbor(DT, QX,QY) and PI = nearestNeighbor(DT, QX,QY,QZ) allow the query points to be specified in alternative column vector format when working in 2-D and 3-D.

Note Note: nearestNeighbor is not supported for 2-D triangulations that have constrained edges.

Input Arguments

DT Delaunay triangulation.

QX

The matrix QX is of size mpts-by-ndim, mpts being the number of query points and ndim the dimension of the space where the points

reside.

Output Arguments

PΙ

PI is a column vector of point indices that index into the points DT.X. The length of PI is equal to the number of query points mpts.

Examples

Create a Delaunay triangulation:

```
x = rand(10,1);
y = rand(10,1);
dt = DelaunayTri(x,y);
```

DelaunayTri.nearestNeighbor

Create query points:

```
qrypts = [0.25 \ 0.25; \ 0.5 \ 0.5];
```

Find the nearest neighbors to the query points:

```
pid = nearestNeighbor(dt, qrypts)
```

See Also DelaunayTri.pointLocation

ne (MException)

Purpose Compare MException objects for inequality

Syntax e0bj1 ~= e0bj2

Description e0bj1 ~= e0bj2 tests MException objects e0bj1 and e0bj2 for

inequality, returning logical 1 (true) if the two objects are not identical,

otherwise returning logical 0 (false).

See Also try, catch, error, assert, MException, isequal(MException),

eq(MException), getReport(MException), disp(MException),

throw(MException), rethrow(MException),

throwAsCaller(MException), addCause(MException),

last(MException)

TriRep.neighbors

Purpose Simplex neighbor information

Syntax SN = neighbors(TR, SI)

Description SN = neighbors(TR, SI) returns the simplex neighbor information for

the specified simplices SI.

Input Arguments

TR Triangulation representation.

SI SI is a column vector of simplex indices that index

into the triangulation matrix TR.Triangulation. If SI is not specified the neighbor information for the entire triangulation is returned, where the neighbors associated with simplex i are defined by

the i'th row of SN.

Output Arguments

SN is an m-by-n matrix, where m = length(SI), the

number of specified simplices, and n is the number of neighbors per simplex. Each row SN(i,:) represents the neighbors of the simplex SI(i).

By convention, the simplex opposite vertex(j) of simplex SI(i) is SN(i,j). If a simplex has one or more boundary facets, the nonexistent neighbors

are represented by NaN.

Definitions

A *simplex* is a triangle/tetrahedron or higher-dimensional equivalent. A *facet* is an edge of a triangle or a face of a tetrahedron.

Examples Example 1

Load a 3-D triangulation and use TriRep to compute the neighbors of all tetrahedra.

load tetmesh

```
trep = TriRep(tet, X)
nbrs = neighbors(trep)
```

Example 2

Query a 2-D triangulation created using DelaunayTri.

```
x = rand(10,1)
y = rand(10,1)
dt = DelaunayTri(x,y)
```

Find the neighbors of the first triangle:

```
n1 = neighbors(dt, 1)
```

See Also

DelaunayTri

Purpose Summary of functions in MATLAB .NET interface

Description Use the following functions to bring assemblies from the Microsoft .NET Framework into the MATLAB environment. The functions are

implemented as a package called NET. To use these functions, prefix

the function name with package name NET.

enableNETfromNetworkDrive Enable access to .NET commands

from network drive

Make .NET assembly visible to NET.addAssembly

MATLAB

NET.Assembly Members of .NET assembly

Convert numeric MATLAB array NET.convertArray

to .NET array

NET.createArray Create single or multidimensional

.NET array

NET.createGeneric Create instance of specialized

.NET generic type

NET.GenericClass Represent parameterized generic

type definitions

NET.GenericClass Constructor for

NET.GenericClass class

NET.invokeGenericMethod Invoke generic method of object

NET.NetException .NET exception

NET.setStaticProperty Static property or field name

See Also "MATLAB Interface to .NET Framework"

Make .NET assembly visible to MATLAB

Syntax

asminfo = NET.addAssembly(assemblyname)

Description

asminfo = NET.addAssembly(assemblyname) loads .NET assembly assemblyname into MATLAB. The assemblyname argument is a string representing the name of a global assembly, a string representing the full path of a private assembly, or an instance of System.Reflection.AssemblyName class. Returns NET.Assembly object asminfo.

For more information about assemblies, see "What Is an Assembly?". To find information about the System.Reflection.AssemblyName class, see "To Learn More About the .NET Framework".

Examples

Load an assembly located in the Global Assembly Cache (GAC) by specifying the short name:

```
asm = NET.addAssembly('System.Windows.Forms');
import System.Windows.Forms.*;
MessageBox.Show('Simple Message Box')
```

Use pseudocode to load a private assembly MLDotNetTest.dll in the c:\work folder:

```
NET.addAssembly('c:\work\MLDotNetTest.dll');
```

See Also

NET.Assembly

NET.Assembly class

Purpose Members of .NET assembly

Description NET. Assembly object returns names of the members of an assembly.

Construction The NET.addAssembly function creates an instance of this class.

Properties AssemblyHandle

Instance of System.Reflection.Assembly class of the added assembly.

Classes

nClassx1 cell array of class names of the assembly, where nClass is the number of classes

Enums

nEnumx1 cell array of enums of the assembly, where nEnum is the number of enums

Structures

nStructx1 cell array of structures of the assembly, where nStruct is the number of structures

GenericTypes

nGenTypex1 cell array of generic types of the assembly, where nGenType is the number of generic types

Interfaces

nInterfacex1 cell array of interface names of the assembly, where nInterface is the number of interfaces

Delegates

nDelegatex1 cell array of delegates of the assembly, where nDelegate is the number of delegates

Copy Semantics

Handle. To learn how this affects your use of the class, see Copying Objects in the MATLAB Programming Fundamentals documentation.

NET.Assembly class

See Also NET.addAssembly

How To • "What Classes Are in a .NET Assembly?"

Convert numeric MATLAB array to .NET array

Syntax

```
arrObj = NET.convertArray(V, 'arrType', [m,n])
```

Description

arrObj = NET.convertArray(V, 'arrType', [m,n]) converts a MATLAB array V to a .NET array. Optional value arrType is a string representing a namespace-qualified .NET array type. Use optional values m,n to convert a MATLAB vector to a two-dimensional .NET array (either 1-by-n or m-by-1). If V is a MATLAB vector and you do not specify the number of dimensions and their sizes, the output arrObj is a one-dimensional .NET array.

If you do not specify arrType, MATLAB converts the type according to the "MATLAB Primitive Type Conversion Table".

Examples

Convert MATLAB Array Example

Convert an array of type double.

```
A =[1 2 3 4];
arr = NET.convertArray(A);
class(A)
class(arr)
```

MATLAB displays:

```
ans =
double
ans =
System.Double[]
```

Convert to System.String .NET Type Example

To convert a char array into a System.String object, type:

```
strArray = System.String('sample string');
```

Convert to Explicit .NET Type Example

Explicitly convert an array of double to an array of .NET type System.Int32.

```
A =[1 2 3 4];
arr =NET.convertArray(A, 'System.Int32');
class(A)
class(arr)

MATLAB displays:
ans =
double
ans =
System.Int32[]
```

Convert Multidimensional Array Example

```
A = [1 2 3 4; 5 6 7 8];
arr = NET.convertArray(A);
class(arr)

MATLAB displays:
   ans =
   System.Double[,]
```

Convert MATLAB Vector Example

Use the optional array dimension parameter to create a two-dimensional array from a MATLAB vector. To create a 4-by-1 array, type:

```
A =[1 2 3 4];
arr2 = NET.convertArray(A, 'System.Double', [4,1]);
arr2.GetLength(0)
arr2.GetLength(1)
```

MATLAB displays:

NET.convertArray

See Also

NET.createArray

Create single or multidimensional .NET array

Syntax

```
array = NET.createArray(typeName, [m,n,p,...])
array = NET.createArray(typeName, m,n,p,...)
```

Description

array = NET.createArray(typeName, [m,n,p,...]) creates an m-by-n-by-p-by-... MATLAB array of type typeName, which is either a fully qualified .NET array type name (namespace and array type name) or an instance of the NET.GenericClass class, in case of arrays of generic type. m,n,p,... are the number of elements in each dimension of the array.

array = NET.createArray(typeName, m,n,p,...) alternative syntax for creating an array.

You cannot specify the lower bound of an array or create a jagged array.

Examples

Create One-Dimensional Array Example

Create a single dimensional, zero-based array of strings:

```
strArray = NET.createArray('System.String', 3);
class(strArray)
```

MATLAB displays:

```
System.String[]
```

For information about accessing and setting values, see "Example — Accessing Elements of a .NET Array".

Create Two-Dimensional Array Example

Create a two dimensional array:

```
strArray = NET.createArray('System.String', [2,3]);
class(strArray)
```

MATLAB displays:

NET.createArray

```
System.String[,]

Alternatively, to create the same array type:

strArray2 = NET.createArray('System.String',2,3);

See Also

NET.convertArray, NET.createGeneric, NET.GenericClass
```

Purpose Create instance of specialized .NET generic type

Syntax genObj = createGeneric(className, paramTypes,

varargin ctorArgs)

Description genObj = createGeneric(className, paramTypes, varargin

ctorArgs) creates an instance genObj of generic type className.

Input Arguments

className Fully qualified string with the generic type

name.

paramTypes Allowed cell types are: strings with fully

qualified parameter type names and instances

of the NET.GenericClass class when

parameterization with another parameterized

type is needed.

ctorArgs Optional, variable length (0 to N) list

of constructor arguments matching the arguments of the .NET generic class constructor intended to be invoked.

Output Arguments

genObj Handle to the specialized generic class

instance.

Examples

Create an instance of System.Collections.Generic.List of System.Double values with initial storage capacity for 10 elements.

dblLst = NET.createGeneric('System.Collections.Generic.List', ...
{'System.Double'}, 10);

Create an instance of System.Collections.Generic.List of System.Collections.Generic.KeyValuePair generic associations where Key is of System.Int32 type and Value is a System.String class with initial storage capacity for 10 key-value pairs.

NET.createGeneric

```
kvpType = NET.GenericClass('System.Collections.Generic.KeyValuePair',.
    'System.Int32', 'System.String');
kvpList = NET.createGeneric('System.Collections.Generic.List',...
{ kvpType }, 10);
```

See Also

NET.GenericClass

NET.GenericClass class

Purpose Represent parameterized generic type definitions

Description Instances of this class are used by the NET.createGeneric function

when creation of generic specialization requires parameterization with

another parameterized type.

Construction NET.GenericClass Constructor for

NET.GenericClass class

Methods This class has no methods.

Properties This class has no properties.

See Also NET.createGeneric, NET.createArray, NET.invokeGenericMethod

NET.GenericClass

Purpose Constructor for

Constructor for NET.GenericClass class

Syntax

genType = NET.GenericClass (className, varargin paramTypes)

Description

genType = NET.GenericClass (className, varargin paramTypes) where className is a fully qualified string with the generic type name, and paramTypes is an optional, variable length (1 to N) list of types for the generic class parameterization. Allowed argument types are: strings with fully qualified parameter type name and instances of the NET.GenericClass class when deeper nested parameterization with another parameterized type is needed.

Examples

Create an instance of System.Collections.Generic.List of System.Collections.Generic.KeyValuePair generic associations where Key is of System.Int32 type and Value is a System.String class with initial storage capacity for 10 key-value pairs.

```
kvpType = NET.GenericClass('System.Collections.Generic.KeyValuePair',.
    'System.Int32', 'System.String');
kvpList = NET.createGeneric('System.Collections.Generic.List',...
    { kvpType }, 10);
```

See Also

NET.createGeneric, NET.createArray

NET.invokeGenericMethod

Purpose Invoke generic method of object

Syntax [varargout] = NET.invokeGenericMethod(obj,

'genericMethodName', paramTypes, args, ...)

Description [varargout] = NET.invokeGenericMethod(obj,

'genericMethodName', paramTypes, args, ...) calls instance or static generic method genericMethodName.

The NET.invokeGenericMethod function cannot invoke overloaded generic methods if they are overloaded on the argument data type.

Do not use $\ensuremath{\mathsf{NET.invokeGenericMethod}}$ for methods containing the C#

ref or out keywords.

Input Arguments

obj

Allowed argument types are:

- Instances of class containing the generic method
- Strings with fully qualified class name, if calling static generic methods
- Instances of NET.GenericClass definitions, if calling static generic methods of a generic class

genericMethodName

Generic method name to invoke

NET.invokeGenericMethod

		_	
na	ram	Tν	nes

Cell vector (1 to N) with the types for generic method parameterization, where allowed cell types are:

- Strings with fully qualified parameter type name.
- Instances of NET.GenericClass definitions, if using nested parameterization with another parameterized type

args

Optional, variable length (0 to N) list of method arguments

Output Arguments

varargout

Variable-length output argument list, varargout, from method *genericMethodName*

Examples

Use the following syntax to call a generic method that takes two parameterized types and returns a parameterized type:

```
a = NET.invokeGenericMethod(obj, ...
'myGenericSwapMethod', ...
{'System.Double', 'System.Double'}, ...
5, 6);
```

See Also

NET.GenericClass, NET.createGeneric, varargout

Purpose .NET exception

Description Construct a NET.NetException object to handle .NET errors.

Construction NE = NET.NetException(msgID, errMsg, netObj) constructs an

object NE of class NET.NetException and assigns to that object a message identifier msgID and error message string errMsg. The System.Exception object that caused the exception is netObj. Derived

from the MException class.

Properties In addition to the base class MException properties, NET. NetException

includes:

ExceptionObject

System. Exception class causing the error.

Methods Inherited Methods

See the methods of the base class MException.

Copy
Semantics

Handle. To learn how this affects your use of the class, see Copying Objects in the MATLAB Programming Fundamentals documentation.

Examples Display error information after trying to load an unknown assembly:

```
try
  NET.addAssembly('C:\Work\invalidfile.dll')
catch e
  e.message;
  if(isa(e, 'NET.NetException'))
    e0bj = e.ExceptionObject
  end
end
```

MATLAB displays:

NET.NetException class

```
ans =
Message: Could not load file or assembly
  'file:///C:\Work\invalidfile.dll' or
  one of its dependencies. The system cannot
  find the file specified.
Source: mscorlib
HelpLink:
e0bj =
  System.IO.FileNotFoundException handle
  Package: System.IO
  Properties:
           Message: [1x1 System.String]
          FileName: [1x1 System.String]
         FusionLog: [1x1 System.String]
              Data: [1x1 System.Collections.ListDictionaryInternal]
    InnerException: []
        TargetSite: [1x1 System.Reflection.RuntimeMethodInfo]
        StackTrace: [1x1 System.String]
          HelpLink: []
            Source: [1x1 System.String]
 Methods, Events, Superclasses
```

See Also MException

How To

- · Class Attributes
- Property Attributes

NET.setStaticProperty

Purpose Static property or field name

Syntax NET.setStaticProperty('propName', value)

Description NET.setStaticProperty('propName', value) sets the static property

or field name specified in the string propName to the given value.

Examples To set the myStaticProperty in the given class and namespace, use

the syntax:

NET.setStaticProperty('MyTestObject.MyClass.myStaticProperty', 5);

Summary of MATLAB Network Common Data Form (netCDF) capabilities

Description

MATLAB provides access to more than 30 functions in the Network Common Data Form (netCDF) interface. This interface provides an API that you can use to enable reading data from and writing data to netCDF files (known as *datasets* in netCDF terminology).

To use these functions, you should be familiar with the information about netCDF contained in the NetCDF C Interface Guide for version 3.6.2.

Note For information about MATLAB support for the Common Data Format (CDF), which is a completely separate, incompatible format, see "Importing Common Data File Format (CDF) Files" and "Exporting to Common Data File Format (CDF) Files".

In most cases, the syntax of the MATLAB function is similar to the syntax of the netCDF library function. The functions are implemented as a package called netcdf. To use these functions, prefix the function name with package name netcdf. For example, to call the netCDF library routine used to open existing netCDF files, use the following MATLAB syntax:

```
ncid = netcdf.open( ncfile, mode );
```

netCDF Library Functions

The following tables list all of the functions in the MATLAB netCDF package, grouped by category.

File Operations

netcdf Summary of MATLAB Network

Common Data Form (netCDF)

capabilities

netcdf.abort Revert recent netCDF file

definitions

netcdf.close Close netCDF file

netcdf.create Create new netCDF dataset
netcdf.endDef End netCDF file define mode
netcdf.getConstant Return numeric value of named

constant

netcdf.getConstantNames Return list of constants known to

netCDF library

netcdf.ing Return information about

netCDF file

netcdf.inqLibVers Return netCDF library version

information

netcdf.open Open netCDF file

netcdf.reDef Put open netCDF file into define

mode

netcdf.setDefaultFormat Change default netCDF file

format

netcdf.setFill Set netCDF fill mode

netcdf.sync Synchronize netCDF file to disk

Dimensions

netcdf.defDim Create netCDF dimension

netcdf.ingDim Return netCDF dimension name

and length

netcdf

netcdf.inqDimID Return dimension ID

netcdf.renameDim Change name of netCDF

dimension

Variables

netcdf.defVar Create netCDF variable netcdf.getVar Return data from netCDF

variable

netcdf.inqVar Return information about

variable

netcdf.inqVarID Return ID associated with

variable name

netcdf.putVar Write data to netCDF variable
netcdf.renameVar Change name of netCDF variable

Attributes

netcdf.copyAtt Copy attribute to new location

netcdf.delAtt Delete netCDF attribute
netcdf.getAtt Return netCDF attribute
netcdf.inqAtt Return information about

netCDF attribute

netcdf.inqAttID Return ID of netCDF attribute netcdf.inqAttName Return name of netCDF attribute

netcdf.putAtt Write netCDF attribute
netcdf.renameAtt Change name of attribute

Revert recent netCDF file definitions

Syntax

netcdf.abort(ncid)

Description

netcdf.abort(ncid) reverts a netCDF file to its previous state, backing out any definitions made since the file last entered define mode. A file enters define mode when you create it (using netcdf.create) or when you explicitly enter define mode (using netcdf.redef). Once you leave define mode (using netcdf.endDef), you cannot revert the definitions you made while in define mode. ncid is a netCDF file identifier returned by netcdf.create or netcdf.open. A call to netcdf.abort closes the file.

This function corresponds to the nc_abort function in the netCDF library C API. To use this function, you should be familiar with the information about netCDF contained in the NetCDF C Interface Guide for version 3.6.2.

Examples

This example creates a new file, performs an operation on the file, and then reverts the file back to its original state. To run this example, you must have write permission in your current directory.

```
% Create a netCDF file
ncid = netcdf.create('foo.nc','NC_NOCLOBBER');
% Perform an operation, such as defining a dimension.
dimid = netcdf.defDim(ncid, 'lat', 50);
% Revert the file back to its previous state.
netcdf.abort(ncid)
% Verify that the file is now closed.
dimid = netcdf.defDim(ncid, 'lat', 50); % should fail
??? Error using ==> netcdflib
NetCDF: Not a valid ID
Error in ==> defDim at 22
```

netcdf.abort

```
dimid = netcdflib('def_dim', ncid,dimname,dimlen);
```

See Also

netcdf.create, netcdf.endDef, netcdf.reDef

Purpose Close netCDF file

Syntax netcdf.close(ncid)

Description netcdf.close(ncid) terminates access to the netCDF file identified

by ncid.

ncid is a netCDF file identifier returned by netcdf.create or

netcdf.open.

This function corresponds to the nc_close function in the netCDF library C API. To use this function, you should be familiar with the information about netCDF contained in the NetCDF C Interface

Guide for version 3.6.2.

Examples This example creates a new netCDF file, and then closes the file. You

must have write permission in your current directory to run this

example.

ncid = netcdf.open('foo.nc','NC WRITE')

netcdf.close(ncid)

See Also netcdf.create, netCDF.open

Copy attribute to new location

Syntax

netcdf.copyAtt(ncid_in,varid_in,attname,ncid_out,varid_out)

Description

netcdf.copyAtt(ncid_in,varid_in,attname,ncid_out,varid_out) copies an attribute from one variable to another, possibly across files. ncid_in and ncid_out are netCDF file identifiers returned by netcdf.create or netcdf.open. varid_in identifies the variable with an attribute that you want to copy. varid_out identifies the variable to which you want to associate a copy of the attribute.

This function corresponds to the nc_copy_att function in the netCDF library C API. To use this function, you should be familiar with the information about netCDF contained in the NetCDF C Interface Guide for version 3.6.2.

Examples

This example makes a copy of the attribute associated with the first variable in the netCDF example file, example.nc, in a new file. To run this example, you must have write permission in your current directory.

```
% Open example file.
ncid = netcdf.open('example.nc','NC_NOWRITE');
% Get identifier for a variable in the file.
varid = netcdf.inqVarID(ncid,'avagadros_number');
% Create new netCDF file.
ncid2 = netcdf.create('foo.nc','NC_NOCLOBBER');
% Define a dimension in the new file.
dimid2 = netcdf.defDim(ncid2,'x',50);
% Define a variable in the new file.
varid2 = netcdf.defVar(ncid2,'myvar','double',dimid2);
% Copy the attribute named 'description' into the new file,
% associating the attribute with the new variable.
```

```
netcdf.copyAtt(ncid,varid,'description',ncid2,varid2);
%
% Check the name of the attribute in new file.
attname = netcdf.inqAttName(ncid2,varid2,0)
attname =
description
```

See Also

netcdf.inqAtt, netcdf.inqAttID, netcdf.inqAttName,
netcdf.putAtt, netcdf.renameAtt

netcdf.create

Purpose

Create new netCDF dataset

Syntax

Description

ncid = netcdf.create(filename, mode) creates a new netCDF file according to the file creation mode. The return value, ncid, is a file ID. The type of access is described by the mode parameter, which can have any of the following values.

Value	Description	
'NC_NOCLOBBER'	Prevent overwriting of existing file with the	
'NC_SHARE'	Allow synchronous file updates.	
'NC_64BIT_0FFSET'	Allow easier creation of files and variables which are larger than two gigabytes.	

Note You can specify the mode as a numeric value, retrieved using the netcdf.getConstant function. To specify more than one mode, use a bitwise-OR of the numeric values of the modes.

[chunksize out,

ncid]=netcdf.create(filename,mode,initsz,chunksize) creates a new netCDF file, but with additional performance tuning parameters. initsz sets the initial size of the file. chunksize can affect I/O performance. The actual value chosen by the netCDF library might not correspond to the input value.

This function corresponds to the nc_create and nc_create functions in the netCDF library C API. To use this function, you should be familiar with the information about netCDF contained in the NetCDF C Interface Guide for version 3.6.2.

Examples

This example creates a netCDF dataset named foo.nc, only if no other file with the same name exists in the current directory. To run this example, you must have write permission in your current directory.

ncid = netcdf.create('foo.nc','NC_NOCLOBBER');

See Also

netcdf.getConstant, netcdf.open

netcdf.defDim

Purpose

Create netCDF dimension

Syntax

dimid = netcdf.defDim(ncid,dimname,dimlen)

Description

dimid = netcdf.defDim(ncid,dimname,dimlen) creates a new dimension in the netCDF file specified by ncid, wheredimname is a character string that specifies the name of the dimension and dimlen is a numeric value that specifies its length. To define an unlimited dimension, specify the predefined constant 'NC_UNLIMITED' for dimlen, using netcdf.getConstant to retrieve the value.

netcdf.defDim returns dimid, a numeric ID corresponding to the new dimension.

This function corresponds to the nc_def_dim function in the netCDF library C API. To use this function, you should be familiar with the information about netCDF contained in the NetCDF C Interface Guide for version 3.6.2.

Examples

This example creates a new file and defines two dimensions in the file. One dimension is an unlimited dimension. To run this example, you must have write permission in your current directory.

```
% Create a netCDF file.
ncid = netcdf.create('foo.nc','NC_NOCLOBBER')
% Define a dimension.
latdimID = netcdf.defDim(ncid,'lat',50);
% Define an unlimited dimension.
londimID = netcdf.defDim(ncid,'lon',netcdf.getConstant('NC UNLIMITED'))
```

See Also

netcdf.getConstant

Create netCDF variable

Syntax

varid = netcdf.defVar(ncid, varname, xtype, dimids)

Description

varid = netcdf.defVar(ncid, varname, xtype, dimids) creates a new variable in the dataset identified by ncid.

varname is a character string that specifies the name of the variable. xtype can be either a character string specifying the data type of the variable, such as 'double', or it can be the numeric equivalent returned by the netcdf.getConstant function. dimids specifies a list of dimension IDs.

netcdf.defVar returns varid, a numeric identifier for the new variable.

This function corresponds to the nc_def_var function in the netCDF library C API. Because MATLAB uses FORTRAN-style ordering, the fastest-varying dimension comes first and the slowest comes last. Any unlimited dimension is therefore last in the list of dimension IDs. This ordering is the reverse of that found in the C API. To use this function, you should be familiar with the information about netCDF contained in the NetCDF C Interface Guide for version 3.6.2.

Examples

This example creates a new netCDF file, defines a dimension in the file, and then defines a variable on that dimension. (In netCDF files, you must create a dimension before you can create a variable.) To run this example, you must have write permission in your current directory.

```
% Create netCDF file.
ncid = netcdf.create('foo.nc','NC_NOCLOBBER');
%
% Define a dimension in the new file.
dimid = netcdf.defDim(ncid,'x',50);
% Define a variable in the new file.
varid = netcdf.defVar(ncid,'myvar','double',dimid)
```

See Also

netCDF.getConstant, netCDF.inqVar, netCDF.putVar

Delete netCDF attribute

Syntax

netcdf.delAtt(ncid,varid,attName)

Description

netcdf.delAtt(ncid,varid,attName) deletes the attribute identified by the text string attName.

ncid is a netCDF file identifier returned by netcdf.create or netcdf.open.

varid is a numeric value that identifies the variable. To delete a global attribute, use netcdf.getConstant('GLOBAL') for the varid. You must be in define mode to delete an attribute.

This function corresponds to the nc_del_att function in the netCDF library C API. To use this function, you should be familiar with the information about netCDF contained in the NetCDF C Interface Guide for version 3.6.2.

Examples

This example opens a local copy of the example netCDF file included with MATLAB, example.nc.

```
% Open a netCDF file.
ncid = netcdf.open('my_example.nc','NC_WRITE')
% Determine number of global attributes in file.
[numdims numvars numatts unlimdimID] = netcdf.inq(ncid);
numatts =

1
% Get name of attribute; it is needed for deletion.
attname = netcdf.inqAttName(ncid,netcdf.getConstant('NC_GLOBAL'),0)
% Put file in define mode to delete an attribute.
netcdf.reDef(ncid);
```

```
% Delete the global attribute in the netCDF file.
netcdf.delAtt(ncid,netcdf.getConstant('GLOBAL'),attname);
% Verify that the global attribute was deleted.
[numdims numvars numatts unlimdimID] = netcdf.inq(ncid);
numatts =
0
```

See Also

netcdf.getConstant, netcdf.inqAttName

End netCDF file define mode

Syntax

```
netcdf.endDef(ncid)
netcdf.endDef(ncid,h minfree,v align,v minfree,r align)
```

Description

netcdf.endDef(ncid) takes a netCDF file out of define mode and into data mode. ncid is a netCDF file identifier returned by netcdf.create or netcdf.open.

netcdf.endDef(ncid,h_minfree,v_align,v_minfree,r_align) takes a netCDF file out of define mode, specifying four additional performance tuning parameters. For example, one reason for using the performance parameters is to reserve extra space in the netCDF file header using the h minfree parameter:

```
ncid = netcdf.endDef(ncid,20000,4,0,4);
```

This reserves 20,000 bytes in the header, which can be used later when adding attributes. This can be extremely efficient when working with very large files. To understand how to use these performance tuning parameters, see the netCDF library documentation.

This function corresponds to the nc_enddef and nc_enddef functions in the netCDF library C API. To use this function, you should be familiar with the information about netCDF contained in the NetCDF C Interface Guide for version 3.6.2.

Examples

When you create a file using netcdf.create, the functions opens the file in define mode. This example uses netcdf.endDef to take the file out of define mode.

```
% Create a netCDF file.
ncid = netcdf.create('foo.c','NC_NOCLOBBER');
% Define a dimension.
dimid = netcdf.defDim(ncid, 'lat', 50);
% Leave define mode.
netcdf.endDef(ncid)
```

netcdf.endDef

```
% Test if still in define mode.
dimid = netcdf.defDim(ncid, 'lon', 50); % should fail
??? Error using ==> netcdflib
NetCDF: Operation not allowed in data mode

Error in ==> defDim at 22
dimid = netcdflib('def_dim', ncid,dimname,dimlen);

See Also
netcdf.create, netcdf.reDef
```

Return netCDF attribute

Syntax

```
attrvalue = netcdf.getAtt(ncid,varid,attname)
attrvalue = netcdf.getAtt(ncid,varid,attname,output_datatype)
```

Description

attrvalue = netcdf.getAtt(ncid,varid,attname) returns attrvalue, the value of the attribute specified by the text string attname. When it chooses the data type of attrvalue, MATLAB attempts to match the netCDF class of the attribute. For example, if the attribute has the netCDF data type NC_INT, MATLAB uses the int32 class for the output data. If an attribute has the netCDF data type NC_BYTE, the class of the output data is int8 value.

```
attrvalue =
```

netcdf.getAtt(ncid,varid,attname,output_datatype) returns attrvalue, the value of the attribute specified by the text string attname, using the output class specified by output_datatype. You can specify any of the following strings for the output data type.

'int'	'double'	'int16'
'short'	'single'	'int8'
'float'	'int32'	'uint8'

This function corresponds to several attribute I/O functions in the netCDF library C API. To use this function, you should be familiar with the information about netCDF contained in the NetCDF C Interface Guide for version 3.6.2.

Examples

This example opens the example netCDF file included with MATLAB, example.nc, and gets the value of the attribute associated with the first variable. The example also gets the value of the global variable in the file.

```
% Open a netCDF file.
ncid = netcdf.open('example.nc','NC NOWRITE');
```

```
% Get name of first variable.
[varname vartype vardimIDs varatts] = netcdf.inqVar(ncid,0);
% Get ID of variable, given its name.
varid = netcdf.inqVarID(ncid,varname);
% Get attribute name, given variable id.
attname = netcdf.inqAttName(ncid,varid,0);
% Get value of attribute.
attval = netcdf.getAtt(ncid,varid,attname);
% Get name of global attribute
gattname = netcdf.inqAttName(ncid,netcdf.getConstant('NC_GLOBAL'),0
% Get value of global attribute.
gattval = netcdf.getAtt(ncid,netcdf.getConstant('NC_GLOBAL'),gattna
gattval =
09-Jun-2008
```

See Also

netcdf.inqAtt,netcdf.putAtt

netcdf.getConstant

Purpose

Return numeric value of named constant

Syntax

val = netcdf.getConstant(param name)

Description

val = netcdf.getConstant(param_name) returns the numeric value
corresponding to the name of a constant defined by the netCDF library.
For example, netcdf.getConstant('NC_NOCLOBBER') returns the
numeric value corresponding to the netCDF constant NC_NOCLOBBER.

The value for param_name can be either upper- or lowercase, and does not need to include the leading three characters 'NC_'. To retrieve a list of all the names defined by the netCDF library, use the netCdf.getConstantNames function.

This function has no direct equivalent in the netCDF C interface. To learn about netCDF, see the information contained in the NetCDF C Interface Guide for version 3.6.2.

Examples

This example opens the example netCDF file included with MATLAB, example.nc.

```
% Open example file.
ncid = netcdf.open('example.nc','NC_NOWRITE');
% Determine contents of the file.
[ndims nvars natts dimm] = netcdf.inq(ncid);
% Get name of global attribute.
% Note: You must use netcdf.getConstant to specify NC_GLOBAL.
attname = netcdf.inqattname(ncid,netcdf.getConstant('NC_GLOBAL'),0)
attname =
creation date
```

See Also

netcdf.getConstantNames

netcdf.getConstantNames

Purpose Return list of constants known to netCDF library

Syntax val = netcdf.getConstantNames(param_name)

Description

val = netcdf.getConstantNames(param_name) returns a list of names of netCDF library constants, definitions, and enumerations. When these strings are supplied as actual parameters to MATLAB netCDF package functions, the functions automatically convert the constant to the appropriate numeric value.

This MATLAB function has no direct equivalent in the netCDF C interface. To learn about netCDF, see the information contained in the NetCDF C Interface Guide for version 3.6.2.

Examples

```
nc_constants = netcdf.getConstantNames
nc_constants =
   'NC2_ERR'
   'NC_64BIT_OFFSET'
   'NC_BYTE'
   'NC_CHAR'
   'NC_CLOBBER'
   'NC_DOUBLE'
   'NC_EBADDIM'
   'NC_EBADID'
   'NC_EBADNAME'
   'NC_EBADTYPE'
```

See Also

netCDF.getConstantNames

netcdf.getVar

Purpose

Return data from netCDF variable

Syntax

data = netcdf.getVar(ncid,varid)

data = netcdf.getVar(ncid,varid,start)

data = netcdf.getVar(ncid,varid,start,count)

data = netcdf.getVar(ncid,varid,start,count,stride)

data = netcdf.getVar(...,output type)

Description

data = netcdf.getVar(ncid,varid) returns data, the value of the variable specified by varid. MATLAB attempts to match the class of the output data to netCDF class of the variable.

ncid is a netCDF file identifier returned by netcdf.create or netcdf.open.

data = netcdf.getVar(ncid,varid,start) returns a single value starting at the specified index, start.

data = netcdf.getVar(ncid,varid,start,count) returns a contiguous section of a variable. start specifies the starting point and count specifies the amount of data to return.

data = netcdf.getVar(ncid,varid,start,count,stride) returns a subset of a section of a variable. start specifies the starting point, count specifies the extent of the section, and stride specifies which values to return.

data = netcdf.getVar(...,output_type) specifies the data type of the return value data. You can specify any of the following strings for the output data type.

'int8'
'uint8'
'int16'
'int32'
'single'
'double'

This function corresponds to several functions in the netCDF library C API. To use this function, you should be familiar with the information about netCDF contained in the NetCDF C Interface Guide for version 3.6.2.

Examples

Open the example netCDF file and get the value of a variable in the file.

```
% Open example file.
ncid = netcdf.open('example.nc', 'NC NOWRITE');
% Get the name of the first variable.
[varname, xtype, varDimIDs, varAtts] = netcdf.inqVar(ncid,0);
% Get variable ID of the first variable, given its name.
varid = netcdf.ingVarID(ncid, varname);
% Get the value of the first variable, given its ID.
data = netcdf.getVar(ncid,varid)
data =
  6.0221e+023
% Determine the data type of the output value
whos data
Name
           Size
                           Bytes Class
                                             Attributes
            1x1
                                8 double
  data
% Get the value again, this time specifying the output data type
data = netcdf.getVar(ncid,varid,'single');
% Determine the data type of the output value
whos data
  Name
            Size
                            Bytes Class
                                             Attributes
  data
            1x1
                                4 single
```

netcdf.getVar

See Also

netcdf.create ,netcdf.inqVarID, netcdf.open

Return information about netCDF file

Syntax

[ndims,nvars,ngatts,unlimdimid] = netcdf.inq(ncid)

Description

[ndims,nvars,ngatts,unlimdimid] = netcdf.inq(ncid) returns the number of dimensions, variables, and global attributes in a netCDF file. The function also returns the ID of the dimension defined with unlimited length, if one exists.

ncid is a netCDF file identifier returned by netcdf.create or netcdf.open. You can call netcdf.inq in either define mode or data mode.

This function corresponds to the nc_inq function in the netCDF library C API. To use this function, you should be familiar with the information about netCDF contained in the NetCDF C Interface Guide for version 3.6.2.

Examples

This example opens the example netCDF file included with MATLAB, example.nc, and uses the netcdf.inq function to get information about the contents of the file.

```
% Open netCDF example file.
ncid = netcdf.open('example.nc','NC_NOWRITE')
% Get information about the contents of the file.
[numdims, numvars, numglobalatts, unlimdimID] = netcdf.inq(ncid)
numdims =
     4
numvars =
```

netcdf.inq

```
numglobalatts =

1

unlimdimID =

3

See Also
netcdf.create, netcdf.open
```

Return information about netCDF attribute

Syntax

[xtype,attlen] = netcdf.inqAtt(ncid,varid,attname)

Description

[xtype,attlen] = netcdf.inqAtt(ncid,varid,attname) returns the data type, xtype, and length, attlen, of the attribute identified by the text string attname.

ncid is a netCDF file identifier returned by netcdf.create or netcdf.open.

varid identifies the variable that the attribute is associated with. To get information about a global attribute, specify netcdf.getConstant('NC_GLOBAL') in place of varid.

This function corresponds to the nc_inq_att function in the netCDF library C API. To use this function, you should be familiar with the information about netCDF contained in the NetCDF C Interface Guide for version 3.6.2.

Examples

This example opens the example netCDF file included with MATLAB, example.nc, and gets information about an attribute in the file.

```
% Open netCDF example file.
ncid = netcdf.open('example.nc','NOWRITE');
% Get identifier of a variable in the file, given its name.
varid = netcdf.inqVarID(ncid,'avagadros_number');
% Get attribute name, given variable id and attribute number.
attname = netcdf.inqAttName(ncid,varid,0);
% Get information about the attribute.
[xtype,attlen] = netcdf.inqAtt(ncid,varid,'description')
xtype =
```

```
attlen =
    31
% Get name of global attribute
gattname = netcdf.inqAttName(ncid,netcdf.getConstant('NC_GLOBAL'),0);
% Get information about global attribute.
[gxtype gattlen] = netcdf.inqAtt(ncid,netcdf.getConstant('NC_GLOBAL'),
gxtype =
    2
gattlen =
    11
```

See Also

netcdf.inqAttID netcdf.inqAttName

Purpose Return ID of netCDF attribute

Syntax attnum = netcdf.inqAttID(ncid, varid, attname)

Description

attnum = netcdf.inqAttID(ncid,varid,attname) retrieves attnum, the identifier of the attribute specified by the text string attname.

varid specifies the variable the attribute is associated with.

ncid is a netCDF file identifier returned by $\mathsf{netcdf.create}$ or

netcdf.open.

This function corresponds to the nc_inq_attid function in the netCDF library C API. To use this function, you should be familiar with the information about netCDF contained in the NetCDF C Interface Guide for version 3.6.2.

Examples

This example opens the netCDF example file included with MATLAB, example.nc.

```
% Open the netCDF example file.
ncid = netcdf.open('example.nc','NC_NOWRITE');
```

% Get the identifier of a variable in the file. varid = netcdf.inqVarID(ncid,'avagadros_number');

% Retrieve the identifier of the attribute associated with the vari attid = netcdf.inqAttID(ncid,varid,'description');

See Also

netcdf.ingAttnetcdf.ingAttName

netcdf.inqAttName

Purpose

Return name of netCDF attribute

Syntax

attname = netcdf.inqAttName(ncid,varid,attnum)

Description

attname = netcdf.inqAttName(ncid,varid,attnum) returns attname, a text string specifying the name of an attribute.

ncid is a netCDF file identifier returned by netcdf.create or netcdf.open.

varid is a numeric identifier of a variable in the file. If you want to get the name of a global attribute in the file, use netcdf.getConstant('NC_GLOBAL') in place of attnum is a zero-based numeric value specifying the attribute, with 0 indicating the first attribute, 1 the second attribute, and so on.

This function corresponds to the nc_inq_attname function in the netCDF library C API. To use this function, you should be familiar with the information about netCDF contained in the NetCDF C Interface Guide for version 3.6.2.

Examples

This example opens the example netCDF file included with MATLAB, example.nc.

```
% Open netCDF example file.
ncid = netcdf.open('example.nc','NC_NOWRITE');
% Get identifier of a variable in the file.
varid = netcdf.inqVarID(ncid,'avagadros_number')
% Get the name of the attribute associated with the variable.
attname = netcdf.inqAttName(ncid,varid,0)
attname =
description
% Get the name of the global attribute associated with the variable.
```

netcdf.inqAttName

```
gattname = netcdf.inqAttName(ncid,netcdf.getConstant('NC_GLOBAL'),0
gattname =
creation_date
```

See Also

netcdf.inqAtt netcdf.inqAttID

netcdf.inqDim

Purpose

Return netCDF dimension name and length

Syntax

[dimname, dimlen] = netcdf.inqDim(ncid,dimid)

Description

[dimname, dimlen] = netcdf.inqDim(ncid,dimid) returns the name, dimname, and length, dimlen, of the dimension specified by dimid. If ndims is the number of dimensions defined for a netCDF file, each dimension has an ID between 0 and ndims-1. For example, the dimension identifier of the first dimension is 0, the second dimension is 1, and so on.

ncid is a netCDF file identifier returned by netcdf.create or netcdf.open.

This function corresponds to the nc_inq_dim function in the netCDF library C API. To use this function, you should be familiar with the information about netCDF contained in the NetCDF C Interface Guide for version 3.6.2.

Examples

The example opens the example netCDF file include with MATLAB, example.nc.

```
ncid = netcdf.open('example.nc', 'NC_NOWRITE');
% Get name and length of first dimension
[dimname, dimlen] = netcdf.inqDim(ncid,0)
dimname =
x
dimlen =
50
```

See Also

netcdf.inqDimID

Return dimension ID

Syntax

dimid = netcdf.inqDimID(ncid,dimname)

Description

dimid = netcdf.inqDimID(ncid,dimname) returns dimid, the identifier of the dimension specified by the character string dimname. You can use the netcdf.inqDim function to retrieve the dimension name. ncid is a netCDF file identifier returned by netcdf.create or netcdf.open.

This function corresponds to the nc_inq_dimid function in the netCDF library C API. To use this function, you should be familiar with the information about netCDF contained in the NetCDF C Interface Guide for version 3.6.2.

Examples

This example opens the example netCDF file included with MATLAB, example.nc.

```
% Open netCDF example file.
ncid = netcdf.open('example.nc','NC_NOWRITE');
% Get name and length of first dimension
[dimname, dimlen] = netcdf.inqDim(ncid,0);
% Retrieve identifier of dimension.
dimid = netcdf.inqDimID(ncid,dimname)

dimid =
0
```

See Also

netcdf.inqDim

netcdf.inqLibVers

Purpose Return netCDF library version information

Syntax libvers = netcdf.inqLibVers

Description libvers = netcdf.inqLibVers returns a string identifying the version

of the netCDF library.

This function corresponds to the $nc_inq_libvers$ function in the netCDF library C API. To use this function, you should be familiar with the information about netCDF contained in the NetCDF C Interface

Guide for version 3.6.2.

Examples libvers = netcdf.inqLibVers

libvers =

3.6.2

Return information about variable

Syntax

[varname,xtype,dimids,natts] = netcdf.inqVar(ncid,varid)

Description

[varname,xtype,dimids,natts] = netcdf.inqVar(ncid,varid) returns the name, data type, dimensions IDs, and the number of attributes associated with the variable identified by varid. Dimension IDs are zero-based.

ncid is a netCDF file identifier returned by netcdf.create or netcdf.open.

This function corresponds to the nc_inq_var function in the netCDF library C API. Because MATLAB uses FORTRAN-style ordering, however, the order of the dimension IDs is reversed relative to what would be obtained from the C API. To use this function, you should be familiar with the information about netCDF contained in the NetCDF C Interface Guide for version 3.6.2.

Examples

This example opens the example netCDF file included with MATLAB, example.nc, and gets information about a variable in the file.

```
% Open the example netCDF file.
ncid = netcdf.open('example.nc','NC_NOWRITE');
% Get information about third variable in the file.
[varname, xtype, dimids, numatts] = netcdf.inqVar(ncid,2)
varname =
peaks
xtype =
```

netcdf.inqVar

```
dimids =
     0     1

numatts =
     1     1
```

See Also

netcdf.create ,netcdf.inqVarID, netcdf.open

Return ID associated with variable name

Syntax

varid = netcdf.inqVarID(ncid,varname)

Description

varid = netcdf.inqVarID(ncid, varname) returns varid, the ID of a netCDF variable specified by the text string, varname.

ncid is a netCDF file identifier returned by netcdf.create or netcdf.open.

This function corresponds to the nc_inq_varid function in the netCDF library C API. To use this function, you should be familiar with the information about netCDF contained in the NetCDF C Interface Guide for version 3.6.2.

Examples

This example opens the example netCDF file included with MATLAB, example.nc, and uses several inquiry functions to get the ID of the first variable.

See Also

netcdf.create, netcdf.ingVar, netcdf.open

netcdf.open

Purpose

Open netCDF file

Syntax

Description

 $\mbox{ncid} = \mbox{netcdf.open(filename, mode)}$ opens an existing \mbox{netCDF} file and returns a \mbox{netCDF} ID in \mbox{ncid} . mode describes the type of access to the file and can have any of the following values.

Value	Description
'NC_WRITE'	Read-write access
'NC_SHARE'	Synchronous file updates
'NC_NOWRITE'	Read-only access

You can also specify mode as a numeric value that can be retrieved using netcdf.getConstant. Use these numeric values when you want to specify a bitwise-OR of several mode.

[chosen_chunksize, ncid] = netcdf.open(filename, mode, chunksize) opens an existing netCDF file, specifying an additional I/O performance tuning parameter, chunksize. The actual value used by the netCDF library might not correspond to the input value you specify.

This function corresponds to the nc_open and nc_open functions in the netCDF library C API. To use this function, you should be familiar with the information about netCDF contained in the NetCDF C Interface Guide for version 3.6.2.

Examples

This example opens the example netCDF file included with MATLAB, example.nc.

```
ncid = netcdf.open('example.nc', 'NC NOWRITE');
```

See Also

netcdf.create,netcdf.getConstant

Write netCDF attribute

Syntax

netcdf.putAtt(ncid,varid,attrname,attrvalue)

Description

netcdf.putAtt(ncid,varid,attrname,attrvalue) writes the attribute named attrname with value attrvalue to the netCDF variable specified by varid. To specify a global attribute, use netcdf.getConstant('NC GLOBAL') for varid

ncid is a netCDF file identifier returned by netCDF.create or netCDF.open.

This function corresponds to several attribute I/O functions in the netCDF library C API. To use this function, you should be familiar with the information about netCDF contained in the NetCDF C Interface Guide for version 3.6.2.

Examples

This example creates a new netCDF file, defines a dimension and a variable, adds data to the variable, and then creates an attribute associated with the variable. To run this example, you must have writer permission in your current directory.

```
% Create a variable in the workspace.
my_vardata = linspace(0,50,50);

% Create a netCDF file.
ncid = netcdf.create('foo.nc','NC_WRITE');

% Define a dimension in the file.
dimid = netcdf.defDim(ncid,'my_dim',50);

% Define a new variable in the file.
varid = netcdf.defVar(ncid,'my_var','double',dimid);

% Leave define mode and enter data mode to write data.
netcdf.endDef(ncid);

% Write data to variable.
```

netcdf.putAtt

```
netcdf.putVar(ncid,varid,my_vardata);
% Re-enter define mode.
netcdf.reDef(ncid);
% Create an attribute associated with the variable.
netcdf.putAtt(ncid,0,'my_att',10);
% Verify that the attribute was created.
[xtype xlen] = netcdf.inqAtt(ncid,0,'my_att')
xtype =
6
xlen =
1
```

See Also

netcdf.getatt

Write data to netCDF variable

Syntax

netcdf.putVar(ncid,varid,data)
netcdf.putVar(ncid,varid,start,data)

netcdf.putVar(ncid,varid,start,count,data)

netcdf.putVar(ncid, varid, start, count, stride, data)

Description

netcdf.putVar(ncid,varid,data) writes data to a netCDF variable identified by varid.

ncid is a netCDF file identifier returned by netcdf.create or netcdf.open.

netcdf.putVar(ncid,varid,start,data) writes a single data value into the variable at the index specified by start.

netcdf.putVar(ncid,varid,start,count,data) writes a section of values into the netCDF variable at the index specified by the vector start to the extent specified by the vector count, along each dimension of the specified variable.

netcdf.putVar(ncid, varid, start, count, stride, data) writes the subsection specified by sampling interval, stride, of the values in the section of the variable beginning at the index start and to the extent specified by count.

This function corresponds to several variable I/O functions in the netCDF library C API. To use this function, you should be familiar with the information about netCDF contained in the NetCDF C Interface Guide for version 3.6.2.

Examples

This example creates a new netCDF file and writes a variable to the file.

```
% Create a 50 element vector for a variable.
my_vardata = linspace(0,50,50);
% Open netCDF file.
ncid = netcdf.create('foo.nc','NC_WRITE')
```

```
% Define the dimensions of the variable.
dimid = netcdf.defDim(ncid, 'my dim',50);
% Define a new variable in the file.
my_varID = netcdf.defVar(ncid,'my_var','double',dimid)
% Leave define mode and enter data mode to write data.
netcdf.endDef(ncid)
% Write data to variable.
netcdf.putVar(ncid,my_varID,my_vardata);
% Verify that the variable was created.
[varname xtype dimid natts ] = netcdf.inqVar(ncid,0)
varname =
my_var
xtype =
     6
dimid =
     0
natts =
     0
```

See Also

netcdf.getVar

Put open netCDF file into define mode

Syntax

netcdf.reDef(ncid)

Description

netcdf.reDef(ncid) puts an open netCDF file into define mode so that dimensions, variables, and attributes can be added or renamed. Attributes can also be deleted in define mode. ncid is a valid NetCDF file ID, returned from a previous call to netcdf.open or netcdf.create.

This function corresponds to the nc_redef function in the netCDF library C API. To use this function, you should be familiar with the information about netCDF contained in the NetCDF C Interface Guide for version 3.6.2.

Examples

This example opens a local copy of the example netCDF file included with MATLAB, example.nc.

```
% Open a netCDF file.
ncid = netcdf.open('my_example.nc','NC_WRITE')
% Try to define a dimension.
dimid = netcdf.defdim(ncid, 'lat', 50); % should fail.
??? Error using ==> netcdflib
NetCDF: Operation not allowed in data mode

Error in ==> defDim at 22
dimid = netcdflib('def_dim', ncid,dimname,dimlen);
% Put file in define mode.
netcdf.reDef(ncid);
% Try to define a dimension again. Should succeed.
dimid = netcdf.defDim(ncid, 'lat', 50);
```

See Also

netcdf.create, netcdf.endDef,netcdf.open

Change name of attribute

Syntax

netcdf.renameAtt(ncid,varid,oldName,newName)

Description

netcdf.renameAtt(ncid,varid,oldName,newName) changes the name of the attribute specified by the character string oldName.

newName is a character string that specifies the new name.

ncid is a netCDF file identifier returned by netcdf.create or netcdf.open.

varid identifies the variable to which the attribute is associated. To specify a global attribute, use $\mathsf{netcdf.getConstant('NC_GLOBAL')}$ for varid.

This function corresponds to the nc_rename_att function in the netCDF library C API. To use this function, you should be familiar with the information about netCDF contained in the NetCDF C Interface Guide for version 3.6.2.

Examples

This example modifies a local copy of the example netCDF file included with MATLAB, example.nc.

```
% Open netCDF file.
ncid = netcdf.open('my_example.nc','NC_WRITE')
% Get the ID of a variable the attribute is associated with.
varID = netcdf.inqVarID(ncid,'avagadros_number')
% Rename the attribute.
netcdf.renameAtt(ncid,varID,'description','Description');
% Verify that the name changed.
attname = netcdf.inqAttName(ncid,varID,0)
attname =
Description
```

netcdf.renameAtt

See Also netcdf.inqAttName

Change name of netCDF dimension

Syntax

netcdf.renameDim(ncid,dimid,newName)

Description

netcdf.renameDim(ncid,dimid,newName) renames the dimension identified by the dimension identifier, dimid.

 $\begin{tabular}{ll} \textbf{newName} is a character string specifying the new name. ncid is a \\ \textbf{netCDF} file identifier returned by netcdf.create or netcdf.open \\ \end{tabular}$

This function corresponds to the nc_rename_dim function in the netCDF library C API. To use this function, you should be familiar with the information about netCDF contained in the NetCDF C Interface Guide for version 3.6.2.

Examples

This examples modifies a local copy of the example netCDF file included with MATLAB, example.nc.

```
% Open netCDF file.
ncid = netcdf.open('my_example.nc','NC_WRITE')
% Put file is define mode.
netcdf.reDef(ncid)
% Get the identifer of a dimension to rename.
dimid = netcdf.inqDimID(ncid,'x');
% Rename the dimension.
netcdf.renameDim(ncid,dimid,'Xdim')
% Verify that the name changed.
data = netcdf.inqDim(ncid,dimid)
data =
Xdim
```

netcdf.renameDim

See Also

netcdf.defDim

Change name of netCDF variable

Syntax

netcdf.renameVar(ncid,varid,newName)

Description

netcdf.renameVar(ncid,varid,newName) renames the variable identified by varid in the netCDF file identified by ncid.newName is a character string specifying the new name.

This function corresponds to the nc_rename_var function in the netCDF library C API. To use this function, you should be familiar with the information about netCDF contained in the NetCDF C Interface Guide for version 3.6.2.

Examples

This example modifies a local copy of the example netCDF file included with MATLAB, example.nc.

```
% Open netCDF file.
ncid = netcdf.open('my_example.nc','NC_WRITE')

% Put file in define mode.
netcdf.redef(ncid)

% Get name of first variable
[varname, xtype, varDimIDs, varAtts] = netcdf.inqVar(ncid,0);

varname

varname =

avagadros_number

% Rename the variable, using a capital letter to start the name.
netcdf.renameVar(ncid,0,'Avagadros_number')

% Verify that the name of the variable changed.
[varname, xtype, varDimIDs, varAtts] = netcdf.inqVar(ncid,0);
```

netcdf.renameVar

varname

varname =

Avagadros_number

See Also netCDF.defVar, netCDF.inqVar, netCDF.putVar

netcdf.setDefaultFormat

Purpose Change default netCDF file format

Syntax oldFormat = netcdf.setDefaultFormat(newFormat)

Description

oldFormat = netcdf.setDefaultFormat(newFormat) changes the default format used by netCDF.create when creating new netCDF files, and returns the value of the old format. You can use this function to change the format used by a netCDF file without having to change the creation mode flag used in each call to netCDF.create.

newFormat can be either of the following values.

Value	Description
'NC_FORMAT_CLASSIC'	Original netCDF file format
'NC_FORMAT_64BIT'	64-bit offset format; relaxes limitations on creating very large files

You can also specify the numeric equivalent of these values, as retrieved by netcdf.getConstant.

This function corresponds to the nc_set_default_format function in the netCDF library C API. To use this function, you should be familiar with the information about netCDF contained in the NetCDF C Interface Guide for version 3.6.2.

Examples oldFormat = netcdf.setDefaultFormat('NC_FORMAT_64BIT');

See Also netcdf.create

Set netCDF fill mode

Syntax

old_mode = netcdf.setFill(ncid,new_mode)

Description

old_mode = netcdf.setFill(ncid,new_mode) sets the fill mode for a netCDF file identified by ncid.

new_mode can be either 'FILL' or 'NOFILL' or their numeric equivalents, as retrieved by netcdf.getConstant. The default mode is 'FILL'. netCDF pre-fills data with fill values. Specifying 'NOFILL' can be used to enhance performance, because it avoids the duplicate writes that occur when the netCDF writes fill values that are later overwritten with data.

This function corresponds to the nc_set_fill function in the netCDF library C API. To use this function, you should be familiar with the information about netCDF contained in the NetCDF C Interface Guide for version 3.6.2.

Examples

This example creates a new file and specifies the fill mode used by netCDF with the file.

```
ncid = netcdf.open('foo.nc','NC_WRITE');
% Set filling behavior
old mode = netcdf.setFill(ncid,'NC NOFILL');
```

See Also

netcdf.getConstant

netcdf.sync

Purpose

Synchronize netCDF file to disk

Syntax

netcdf.sync(ncid)

Description

netcdf.sync(ncid) synchronizes the state of a netCDF file to disk. The netCDF library normally buffers accesses to the underlying netCDF file, unless you specify the NC_SHARE mode when you opened the file with netcdf.open or netcdf.create. To call netcdf.sync, the netCDF file must be in data mode.

This function corresponds to the nc_sync function in the netCDF library C API. To use this function, you should be familiar with the information about netCDF contained in the NetCDF C Interface Guide for version 3.6.2.

Examples

This example creates a new netCDF file for write access, performs an operation on the file, takes the file out of define mode, and then synchronizes the file to disk.

```
% Create a netCDF file.
ncid = netcdf.create('foo.nc','NC_WRITE');
% Perform an operation.
dimid = netcdf.defDim(ncid,'Xdim',50);
% Take file out of define mode.
netcdf.endDef(ncid);
% Synchronize the file to disk.
netcdf.sync(ncid)
```

See Also

netcdf.close, netcdf.create, netcdf.open, netcdf.endDef

Determine where to draw graphics objects

Syntax

newplot

h = newplot

h = newplot(hsave)

Description

newplot prepares a figure and axes for subsequent graphics commands.

h = newplot prepares a figure and axes for subsequent graphics commands and returns a handle to the current axes.

h = newplot(hsave) prepares and returns an axes, but does not delete any objects whose handles you have assigned to the hsave argument, which can be a vector of handles. If hsave is not empty, the figure and axes containing hsave are prepared for plotting instead of the current axes of the current figure. If hsave is empty, newplot behaves as if it were called without any inputs.

Remarks

Use newplot at the beginning of high-level graphics code to determine which figure and axes to target for graphics output. Calling newplot can change the current figure and current axes. Basically, there are three options when you are drawing graphics in existing figures and axes:

- Add the new graphics without changing any properties or deleting any objects.
- Delete all existing objects whose handles are not hidden before drawing the new objects.
- Delete all existing objects regardless of whether or not their handles are hidden, and reset most properties to their defaults before drawing the new objects (refer to the following table for specific information).

The figure and axes NextPlot properties determine how newplot behaves. The following two tables describe this behavior with various property values.

First, newplot reads the current figure's NextPlot property and acts accordingly.

newplot

NextPlot	What Happens
new	Create a new figure and use it as the current figure.
add	Draw to the current figure without clearing any graphics objects already present.
replacechildren	Remove all child objects whose HandleVisibility property is set to on and reset figure NextPlot property to add.
	This clears the current figure and is equivalent to issuing the clf command.
replace	Remove all child objects (regardless of the setting of the HandleVisibility property) and reset figure properties to their defaults, except
	NextPlot is reset to add regardless of user-defined defaults.
	 Position, Units, PaperPosition, and PaperUnits are not reset.
	This clears and resets the current figure and is equivalent to issuing the clf reset command.

After newplot establishes which figure to draw in, it reads the current axes' NextPlot property and acts accordingly.

NextPlot	Description
add	Draw into the current axes, retaining all graphics objects already present.
replacechildren	Remove all child objects whose HandleVisibility property is set to on, but do not reset axes properties. This clears the current axes like the cla command.
replace	Remove all child objects (regardless of the setting of the HandleVisibility property) and reset axes properties to their defaults, except Position and Units.
	This clears and resets the current axes like the cla reset command.

See Also

axes, cla, clf, figure, hold, ishold, reset

The NextPlot property for figure and axes graphics objects

"Figure Windows" on page 1-105 for related functions

Controlling Graphics Output for more examples.

Tiff.nextDirectory

Purpose Make next IFD current IFD

Syntax tiffobj.nextDirectory()

Description tiffobj.nextDirectory() makes the next image file directory (IFD)

in the file the current IFD. Tiff object methods operate on the current IFD. Use this method to navigate among IFDs in a TIFF file containing

multiple images.

Examples Open a Tiff object and change the current IFD to the next IFD in the

file. Replace $\ensuremath{\mathsf{myfile.tif}}$ with the name of a TIFF file on your MATLAB

path. The TIFF file should contain multiple images.

```
t = Tiff('myfile.tif', 'r');
t.nextDirectory();
```

References This method corresponds to the TIFFReadDirectory function in the

LibTIFF C API. To use this method, you must be familiar with LibTIFF version 3.7.1, as well as the TIFF specification and technical notes. View this documentation at LibTIFF - TIFF Library and Utilities.

See Also Tiff.setDirectory

Tutorials • "Exporting Image Data and Metadata to TIFF Files"

· "Reading Image Data and Metadata from TIFF Files"

Purpose Next higher power of 2

Syntax p = nextpow2(A)

Description p = nextpow2(A) returns the smallest power of two that is greater

than or equal to the absolute value of A. (That is, p that satisfies 2^p

>= abs(A)).

This function is useful for optimizing FFT operations, which are most

efficient when sequence length is an exact power of two.

Examples For any integer n in the range from 513 to 1024, nextpow2(n) is 10.

For vector input, nextpow2(n) returns an element-by-element result:

A = [1 2 3 4 5 9 519] nextpow2(A) ans =

0 1 2 2 3 4 10

See Also fft, log2, pow2

nnz

Purpose Number of nonzero matrix elements

Syntax n = nnz(X)

Description n = nnz(X) returns the number of nonzero elements in matrix X.

The density of a sparse matrix is nnz(X)/prod(size(X)).

Examples The matrix

w = sparse(wilkinson(21));

is a tridiagonal matrix with 20 nonzeros on each of three diagonals,

so nnz(w) = 60.

See Also find, isa, nonzeros, nzmax, size, whos

Change EraseMode of all objects to normal

Note noanimate will be removed in a future release.

Syntax

noanimate(state,fig_handle)
noanimate(state)

Description

noanimate(state,fig_handle) sets the EraseMode of all image, line, patch, surface, and text graphics objects in the specified figure to normal. state can be the following strings:

- 'save' Set the values of the EraseMode properties to normal for all the appropriate objects in the designated figure.
- 'restore' Restore the EraseMode properties to the previous values (i.e., the values before calling noanimate with the 'save' argument).

noanimate(state) operates on the current figure.

noanimate is useful if you want to print the figure to a TIFF or JPEG format.

See Also

print

nonzeros

Purpose Nonzero matrix elements

Syntax s = nonzeros(A)

Description s = nonzeros(A) returns a full column vector of the nonzero elements

in A, ordered by columns.

This gives the s, but not the i and j, from [i,j,s] = find(A).

Generally,

 $length(s) = nnz(A) \le nzmax(A) \le prod(size(A))$

See Also find, isa, nnz, nzmax, size, whos

Vector and matrix norms

Syntax

n = norm(A)
n = norm(A,p)

Description

The *norm* of a matrix is a scalar that gives some measure of the magnitude of the elements of the matrix. The norm function calculates several different types of matrix norms:

n = norm(A) returns the largest singular value of A, max(svd(A)).

n = norm(A,p) returns a different kind of norm, depending on the value of p.

If p is	Then norm returns
1	The 1-norm, or largest column sum of A, max(sum(abs(A))).
2	The largest singular value (same as norm(A)).
inf	The infinity norm, or largest row sum of A, max(sum(abs(A'))).
'fro'	The Frobenius-norm of matrix A, sqrt(sum(diag(A'*A))).

When A is a vector:

norm(A,p)	Returns sum(abs(A).^p)^(1/p), for any $1 \le p \le \infty$.
norm(A)	Returns norm(A,2).
norm(A,inf)	Returns max(abs(A)).
norm(A,-inf)	Returns min(abs(A)).

Remarks

Note norm(x) is the Euclidean length of a vector x. On the other hand, MATLAB software uses "length" to denote the number of elements n in a vector. This example uses norm(x)/sqrt(n) to obtain the root-mean-square (RMS) value of an n-element vector x.

See Also

cond, condest, hypot, normest, rcond

Purpose 2-norm estimate

Syntax nrm = normest(S)

nrm = normest(S,tol)

[nrm,count] = normest(...)

Description

This function is intended primarily for sparse matrices, although it works correctly and may be useful for large, full matrices as well.

nrm = normest(S) returns an estimate of the 2-norm of the matrix S.

nrm = normest(S,tol) uses relative error tol instead of the default tolerance 1.e-6. The value of tol determines when the estimate is

considered acceptable.

[nrm,count] = normest(...) returns an estimate of the 2-norm and

also gives the number of power iterations used.

Algorithm

The power iteration involves repeated multiplication by the matrix S and its transpose, S'. The iteration is carried out until two successive

estimates agree to within the specified relative tolerance.

See Also

cond, condest, norm, rcond, svd

Find logical NOT of array or scalar input

Syntax

~A not(A)

Description

~A performs a logical NOT of input array A, and returns an array containing elements set to either logical 1 (true) or logical 0 (false). An element of the output array is set to 1 if the input array contains a zero value element at that same array location. Otherwise, that element is set to 0.

The input of the expression can be an array or can be a scalar value. If the input is an array, then the output is an array of the same dimensions. If the input is scalar, then the output is scalar.

not(A) is called for the syntax ~A when A is an object.

Example

If matrix A is

0	29	0	36	0
23	34	35	0	39
0	24	31	27	0
0	29	0	0	34

then

See Also

bitcmp, and, or, xor, any, all, "Logical Operators", "The Logical Class", "Bit-Wise Functions"

Purpose Open M-book in Microsoft Word software (on Microsoft Windows

platforms)

Syntax notebook

notebook('filename')
notebook('-setup')

Description

notebook starts Microsoft Word software and creates a new M-book titled Document 1.

notebook('filename') starts Microsoft Word and opens the M-book filename, where filename is either in the MATLAB current folder or is a full path. If filename does not exist, MATLAB creates a new M-book titled filename. If the file name extension is not specified, MATLAB assumes .doc.

notebook('-setup') runs an interactive setup function for Notebook. It copies the Notebook template, m-book.dot, to the Microsoft Word template folder, whose location MATLAB automatically determines from the Windows system registry. Upon completion, MATLAB displays a message indicating whether or not the setup was successful.

See Also

MATLAB Desktop Tools and Development Environment documentation

- Notebook for Publishing to Word
- "Overview of Publishing MATLAB Code"

notify (handle)

Purpose Notify listeners that event is occurring

Syntax notify(Hobj, 'EventName')

notify(Hobj,'EventName',data)

Description

notify(Hobj, 'EventName') notifies listeners that the specified event is taking place on the specified handle objects.

notify(Hobj, 'EventName', data) includes user-defined event data.

Input Arguments

Hobj

Array of handle objects triggering the specified event.

EventName

Name of the event.

data

An event.EventData object encapsulating information about the event. You can define custom event data by subclassing event.EventData and passing an instance of your subclass as the data argument. See "Defining Event-Specific Data" for information on defining event data.

See Also

See "Defining Events and Listeners — Syntax and Techniques"

handle, addlistener

Purpose Current date and time

Syntax t = now

Description t = now returns the current date and time as a serial date number. To

return the time only, use rem(now,1). To return the date only, use

floor(now).

Examples t1 = now, t2 = rem(now,1)

t1 =

7.2908e+05

t2 =

0.4013

See Also clock, date, datenum

nthroot

Purpose

Real nth root of real numbers

Syntax

y = nthroot(X, n)

Description

y = nthroot(X, n) returns the real nth root of the elements of X. Both X and n must be real and n must be a scalar. If X has negative entries, n must be an odd integer.

Example

nthroot(-2, 3)

returns the real cube root of -2.

ans =

-1.2599

By comparison,

 $(-2)^{(1/3)}$

returns a complex cube root of -2.

ans =

0.6300 + 1.0911i

See Also

power

Null space

Syntax

```
Z = null(A)
Z = null(A,'r')
```

Description

Z = null(A) is an orthonormal basis for the null space of A obtained from the singular value decomposition. That is, A*Z has negligible elements, size(Z,2) is the nullity of A, and Z'*Z = I.

Z = null(A,'r') is a "rational" basis for the null space obtained from the reduced row echelon form. A*Z is zero, size(Z,2) is an estimate for the nullity of A, and, if A is a small matrix with integer elements, the elements of the reduced row echelon form (as computed using rref) are ratios of small integers.

The orthonormal basis is preferable numerically, while the rational basis may be preferable pedagogically.

Example

Example 1

Compute the orthonormal basis for the null space of a matrix A.

```
A = [1]
            2
                   3
     1
            2
                   3
     1
                   3];
Z = null(A);
A*Z
ans =
  1.0e-015 *
     0.2220
                0.2220
     0.2220
                0.2220
     0.2220
                0.2220
Z'*Z
ans =
```

```
1.0000 -0.0000
-0.0000 1.0000
```

Example 2

Compute the 1-norm of the matrix A^*Z and determine that it is within a small tolerance.

```
norm(A*Z,1) < 1e-12
ans =
1
```

Example 3

Compute the rational basis for the null space of the same matrix A.

See Also

orth, rank, rref, svd

Convert numeric array to cell array

Syntax

```
C = num2cel1(A)
C = num2cel1(A, dim)
C = num2cel1(A, [dim1, dim2, ...])
```

Description

C = num2cell(A) converts numeric array A into cell array C by placing each element of A into a separate cell in C. The output array has the same size and dimensions as the input array, unless A is empty. If A is empty, all dimensions of C are zero.

C = num2cell(A, dim) converts numeric array A into a cell array of numeric vectors, the dimensions of which depend on the value of the dim argument. Return value C contains numel(A)/size(A,dim) vectors, each of length size(A, dim). (See Example 2, below). The dim input must be an integer with a value from ndims(A) to 1.

C = num2cell(A, [dim1, dim2, ...]) converts numeric array A into a cell array of numeric arrays, the dimensions of which depend on the values of arguments [dim1, dim2, ...]. Given the variables X and Y, where X=size(A,dim1) and Y=size(A,dim2), return value C contains numel(A)/prod(X,Y,...) arrays, each of size X-by-Y-by-.... All dimN inputs must be an integer with a value from ndims(A) to 1.

Remarks

num2cell works for all array types.

To convert the cell array back to a numeric array, use cell2mat or cat(dim, c{:}). See "Example 2 — Converting to Cell Array and Back to Numeric" on page 2-2780.

Examples

Example 1 — Converting to a Cell Array of the Same Dimensions

Create a 4x7x3 array of random numbers:

```
A = rand(4,7,3);
```

Convert the numeric array to a cell array of the same dimensions:

```
C = num2cell(A);
whos C
Name Size Bytes Class Attributes
C 4x7x3 5712 cell
```

Example 2 - Converting to Cell Array and Back to Numeric

Create a 3-by-4 numeric array A:

Convert A to a cell array C1 of the same size. Convert it back to a numeric array using the cell2mat function:

C1 = nur	m2cell(A	۹)		N1 = c	ell2ma	at (C1))
C1 =				N1 =			
[5]	[8]	[11]	[14]	5	8	11	14
[-9]	[-5]	[-1]	[3]	- 9	-5	- 1	3
[20]	[16]	[12]	[8]	20	16	12	8


Convert A to a cell array C2 of 1-by-4 arrays. Convert it back to a numeric array using the cat function:

Example 3 — Converting to a Cell Array of Different Dimensions


The following diagrams show the output of C=num2cell(A,dim), where A is a 4x7x3 numeric array, and dim is one dimension of the input array:

either 1, 2, or 3 in this case. The shaded segment of each diagram represents one cell of the output cell array. Each of these cells contains those elements of A that are positioned along the dimension specified by dim:


C = num2cell(A,1) yields a 21-element (1x7x3) cell array C, each cell containing a numeric vector of 4 elements along the 1st dimension of A.



C = num2cell(A,2) yields a 12-element (4x1x3) cell array C, each cell containing a numeric vector of 7 elements along the 2nd dimension of A.



C = num2cell(A,3) yields a 28-element (4x7x1) cell array C, each cell containing a numeric vector of 3 elements along the 3rd dimension of A.



Example 4 - Specifying More Than One Dimension for the Output

Given a 4x7x3 numeric array A

$$A = rand(4,7,3)$$

and the following two values X and Y

then the statement

$$C = num2cell(A, [1 3])$$

returns in C a cell array of numel(A)/prod(X,Y) numeric arrays, each having the dimensions X-by-Y.

See Also cat. mat

cat, mat2cell, cell2mat

num2hex

Purpose Convert singles and doubles to IEEE hexadecimal strings **Syntax** num2hex(X) **Description** If X is a single or double precision array with n elements, num2hex(X) is an n-by-8 or n-by-16 char array of the hexadecimal floating-point representation. The same representation is printed with format hex. **Examples** num2hex([1 0 0.1 -pi Inf NaN]) returns ans = 3ff00000000000000 0000000000000000 3fb99999999999a c00921fb54442d18 7ff00000000000000 fff8000000000000 num2hex(single([1 0 0.1 -pi Inf NaN])) returns ans = 3f800000 00000000 3dcccccd c0490fdb 7f800000 ffc00000 See Also hex2num, dec2hex, format

Convert number to string

Syntax

```
str = num2str(A)
str = num2str(A, precision)
str = num2str(A, format)
```

Description

The num2str function converts numbers to their string representations. This function is useful for labeling and titling plots with numeric values.

str = num2str(A) converts array A into a string representation str.
Converted floating-point values have a maximum of four digits of
precision, and an exponent if required. For integer values, num2str
returns the exact string representation of the value.

str = num2str(A, precision) converts the array A into a string representation str with the maximum number of digits specified by precision.

str = num2str(A, format) converts array A using the supplied format, as described on the fprintf function reference page. By default, num2str displays floating point values using the '%11.4g' format (four significant digits in exponential or fixed-point notation, whichever is shorter).

Remarks

Unlike fprintf, the num2str function trims any leading spaces from a string, even when used with the space character flag. For example, num2str(42.67, '% 10.2f') returns a 1-by-5 character array '42.67'.

Examples

```
num2str(pi) is 3.142.
```

num2str(eps) is 2.22e-16.

num2str(randn(2,2),3) produces the following string matrix:

```
num2str(randn(2,2),3)
ans =
0.538 -2.26
1.83 0.862
```

num2str

num2str with a format of %10.5e\n returns a matrix of strings in exponential format, having 5 decimal places, with each element separated by a newline character:

```
x = rand(2,3) * 9999; % Create a 2-by-3 matrix.

A = num2str(x, '%10.5e\n') % Convert to string array.
A =
6.87255e+003
1.55597e+003
8.55890e+003
3.46077e+003
1.91097e+003
4.90201e+003
```

See Also

mat2str, int2str, str2num, sprintf, fprintf

Total number of strips in image

Syntax

numStrips = tiffobj.numberOfStrips()

Description

numStrips = tiffobj.numberOfStrips() returns the total number of strips in the image.

Examples

Open a Tiff object and determine the number of strips in the image. Replace myfile.tif with the name of a TIFF file on your MATLAB path:

```
t = Tiff('myfile.tif', 'r');
%
% Check if image has a stripped organization
if ~t.isTiled()
   nStrips = t.numberOfStrips();
end
```

References

This method corresponds to the TIFFNumberOfStrips function in the LibTIFF C API. To use this method, you must be familiar with LibTIFF version 3.7.1, as well as the TIFF specification and technical notes. View this documentation at LibTIFF - TIFF Library and Utilities.

See Also

Tiff.numberOfTiles | Tiff.isTiled

Tutorials

- "Exporting Image Data and Metadata to TIFF Files"
- · "Reading Image Data and Metadata from TIFF Files"

Tiff.numberOfTiles

Purpose

Total number of tiles in image

Syntax

numTiles = tiffobj.numberOfTiles()

Description

numTiles = tiffobj.numberOfTiles() returns the total number of tiles in the image.

Examples

Open a Tiff object and determine the number of tiles in the image. Replace myfile.tif with the name of a TIFF file on your MATLAB path:

```
t = Tiff('myfile.tif', 'r');
%
% Check if image has a tiled organization
if t.isTiled()
   nTiles = t.numberOfTiles();
end
```

References

This method corresponds to the TIFFNumberOfTiles function in the LibTIFF C API. To use this method, you must be familiar with LibTIFF version 3.7.1, as well as the TIFF specification and technical notes. View this documentation at LibTIFF - TIFF Library and Utilities.

See Also

Tiff.numberOfStrips | Tiff.isTiled

Tutorials

- "Exporting Image Data and Metadata to TIFF Files" $\,$
- "Reading Image Data and Metadata from TIFF Files"

Number of elements in array or subscripted array expression

Syntax

```
n = numel(A)
```

n = numel(A, index1, index2, ... indexn)

Description

n = numel(A) returns the number of elements, n, in array A.

n = numel(A, index1, index2, ... indexn) returns the number of subscripted elements, n, in A(index1, index2, ..., indexn). To handle the variable number of arguments, numel is typically written with the header function n = numel(A, varargin), where varargin is a cell array with elements index1, index2, ... indexn.

The MATLAB software implicitly calls the numel built-in function whenever an expression generates a comma-separated list. This includes brace indexing (i.e., A{index1,index2,...,indexN}), and dot indexing (i.e., A.fieldname).

Remarks

It is important to note the significance of numel with regards to the overloaded subsref and subsasgn functions. In the case of the overloaded subsref function for brace and dot indexing (as described in the last paragraph), numel is used to compute the number of expected outputs (nargout) returned from subsref. For the overloaded subsasgn function, numel is used to compute the number of expected inputs (nargin) to be assigned using subsasgn. The nargin value for the overloaded subsasgn function is the value returned by numel plus 2 (one for the variable being assigned to, and one for the structure array of subscripts).

As a class designer, you must ensure that the value of n returned by the built-in numel function is consistent with the class design for that object. If n is different from either the nargout for the overloaded subsref function or the nargin for the overloaded subsasgn function, then you need to overload numel to return a value of n that is consistent with the class' subsref and subsasgn functions. Otherwise, MATLAB produces errors when calling these functions.

numel

Examples

Create a 4-by-4-by-2 matrix. numel counts 32 elements in the matrix.

See Also

nargin, nargout, prod, size, subsasgn, subsref

Purpose Amount of storage allocated for nonzero matrix elements

Syntax n = nzmax(S)

Description n = nzmax(S) returns the amount of storage allocated for nonzero elements.

If S is a sparse nzmax(S) is the number of storage locations matrix... allocated for the nonzero elements in S.

If S is a full matrix... nzmax(S) = prod(size(S)).

Often, nnz(S) and nzmax(S) are the same. But if S is created by an operation which produces fill-in matrix elements, such as sparse matrix multiplication or sparse LU factorization, more storage may be allocated than is actually required, and nzmax(S) reflects this. Alternatively, sparse(i,j,s,m,n,nzmax) or its simpler form, spalloc(m,n,nzmax), can set nzmax in anticipation of later fill-in.

See Also find, isa, nnz, nonzeros, size, whos

Solve fully implicit differential equations, variable order method

Syntax

[T,Y] = ode15i(odefun,tspan,y0,yp0)
[T,Y] = ode15i(odefun,tspan,y0,yp0,options)
[T,Y,TE,YE,IE] = ode15i(odefun,tspan,y0,yp0,options...)
sol = ode15i(odefun,[t0 tfinal],y0,yp0,...)

Arguments

The following table lists the input arguments for ode15i.

odefun A function handle that evaluates the left side of the differential equations, which are of the form f(t, y, y') = 0. See "Function Handles" in the MATLAB Programming documentation for more information.

A vector specifying the interval of integration, [t0,tf].

To obtain solutions at specific times (all increasing or all decreasing), use tspan = [t0,t1,...,tf].

y0, yp0 Vectors of initial conditions for y and y' respectively.

options Optional integration argument created using the odeset function. See odeset for details.

The following table lists the output arguments for ode15i.

T Column vector of time points

Y Solution array. Each row in y corresponds to the solution at a time returned in the corresponding row of t.

Description

[T,Y] = ode15i(odefun,tspan,y0,yp0) with tspan = [t0 tf] integrates the system of differential equations f(t,y,y') = 0 from time t0 to tf with initial conditions y0 and yp0. odefun is a function handle. Function ode15i solves ODEs and DAEs of index 1. The initial conditions must be consistent, meaning that f(t0,y0,yp0) = 0. You can use the function decic to compute consistent initial conditions

close to guessed values. Function odefun(t,y,yp), for a scalar t and column vectors y and yp, must return a column vector corresponding to f(t, y, y'). Each row in the solution array Y corresponds to a time returned in the column vector T. To obtain solutions at specific times t0,t1,...,tf (all increasing or all decreasing), use tspan = [t0,t1,...,tf].

"Parameterizing Functions", in the MATLAB Mathematics documentation, explains how to provide additional parameters to the function odefun, if necessary.

[T,Y] = ode15i(odefun,tspan,y0,yp0,options) solves as above with default integration parameters replaced by property values specified in options, an argument created with the odeset function. Commonly used options include a scalar relative error tolerance RelTol (1e-3 by default) and a vector of absolute error tolerances AbsTol (all components 1e-6 by default). See odeset for details.

[T,Y,TE,YE,IE] = ode15i(odefun,tspan,y0,yp0,options...) with the 'Events' property in options set to a function events, solves as above while also finding where functions of (t, y, y'), called event functions, are zero. The function events is of the form [value,isterminal,direction] = events(t,y,yp) and includes the necessary event functions. Code the function events so that the ith element of each output vector corresponds to the ith event. For the ith event function in events:

- value(i) is the value of the function.
- isterminal(i) = 1 if the integration is to terminate at a zero of this event function and 0 otherwise.
- direction(i) = 0 if all zeros are to be computed (the default), +1
 if only the zeros where the event function increases, and -1 if only
 the zeros where the event function decreases.

Output TE is a column vector of times at which events occur. Rows of YE are the corresponding solutions, and indices in vector IE specify which

event occurred. See "Integrator Options" in the MATLAB Mathematics documentation for more information.

sol = ode15i(odefun,[t0 tfinal],y0,yp0,...) returns a structure
that can be used with deval to evaluate the solution at any point
between t0 and tfinal. The structure sol always includes these fields:

sol.x	Steps chosen by the solver. If you specify the Events
	option and a terminal event is detected, sol.x(end)
	contains the end of the step at which the event
	occurred.

Each column sol.y(:,i) contains the solution at sol.x(i).

If you specify the Events option and events are detected, sol also includes these fields:

sol.xe	Points at which events, if any, occurred. sol.xe(end) contains the exact point of a terminal event, if any.
sol.ye	Solutions that correspond to events in sol.xe.
sol.ie	Indices into the vector returned by the function specified in the Events option. The values indicate which event the solver detected.

Options

ode15i accepts the following parameters in options. For more information, see odeset and Changing ODE Integration Properties in the MATLAB Mathematics documentation.

Error control	RelTol, AbsTol, NormControl
Solver output	OutputFcn, OutputSel, Refine, Stats
Event location	Events

Step size MaxStep, InitialStep

Jacobian Jacobian, JPattern, Vectorized

matrix

Solver Output

If you specify an output function as the value of the OutputFcn property, the solver calls it with the computed solution after each time step. Four output functions are provided: odeplot, odephas2, odephas3, odeprint. When you call the solver with no output arguments, it calls the default odeplot to plot the solution as it is computed. odephas2 and odephas3 produce two- and three-dimensional phase plane plots, respectively. odeprint displays the solution components on the screen. By default, the ODE solver passes all components of the solution to the output function. You can pass only specific components by providing a vector of indices as the value of the OutputSel property. For example, if you call the solver with no output arguments and set the value of OutputSel to [1,3], the solver plots solution components 1 and 3 as they are computed.

Jacobian Matrices

The Jacobian matrices $\partial f/\partial y$ and $\partial f/\partial y'$ are critical to reliability and efficiency. You can provide these matrices as one of the following:

- Function of the form [dfdy,dfdyp] = FJAC(t,y,yp) that computes the Jacobian matrices. If FJAC returns an empty matrix [] for either dfdy or dfdyp, then ode15i approximates that matrix by finite differences.
- Cell array of two constant matrices {dfdy,dfdyp}, either of which could be empty.

Use odeset to set the Jacobian option to the function or cell array. If you do not set the Jacobian option, ode15i approximates both Jacobian matrices by finite differences.

For ode15i, Vectorized is a two-element cell array. Set the first element to 'on' if odefun(t,[y1,y2,...],yp) returns

[odefun(t,y1,yp),odefun(t,y2,yp),...]. Set the second element to 'on' if odefun(t,y,[yp1,yp2,...]) returns [odefun(t,y,yp1),odefun(t,y,yp2),...]. The default value of Vectorized is $\{'off','off'\}$.

For ode15i, JPattern is also a two-element sparse matrix cell array. If $\partial f/\partial y$ or $\partial f/\partial y'$ is a sparse matrix, set JPattern to the sparsity patterns, {SPDY,SPDYP}. A sparsity pattern of $\partial f/\partial y$ is a sparse matrix SPDY with SPDY(i,j) = 1 if component i of f(t,y,yp) depends on component j of y, and 0 otherwise. Use SPDY = [] to indicate that $\partial f/\partial y$ is a full matrix. Similarly for $\partial f/\partial y'$ and SPDYP. The default value of JPattern is {[],[]}.


Example 1

This example uses a helper function decic to hold fixed the initial value for $\mathcal{Y}(t_0)$ and compute a consistent initial value for $\mathcal{Y}'(t_0)$ for the Weissinger implicit ODE. The Weissinger function evaluates the residual of the implicit ODE.

```
t0 = 1;
y0 = sqrt(3/2);
yp0 = 0;
[y0,yp0] = decic(@weissinger,t0,y0,1,yp0,0);
```

The example uses ode15i to solve the ODE, and then plots the numerical solution against the analytical solution.

```
[t,y] = ode15i(@weissinger,[1 10],y0,yp0);
ytrue = sqrt(t.^2 + 0.5);
plot(t,y,t,ytrue,'o');
```



Other Examples

These demos provide examples of implicit ODEs: ihb1dae, iburgersode. \\ \\

See Also

decic, deval, odeget, odeset, function_handle (@)

Other ODE initial value problem solvers: ode45, ode23, ode113, ode15s, ode23s, ode23t, ode23tb

ode23, ode45, ode113, ode15s, ode23s, ode23t, ode23tb

Purpose

Solve initial value problems for ordinary differential equations

Syntax

[T,Y] = solver(odefun,tspan,y0)

[T,Y] = solver(odefun,tspan,y0,options)

[T,Y,TE,YE,IE] = solver(odefun,tspan,y0,options)

sol = solver(odefun,[t0 tf],y0...)

where solver is one of ode45, ode23, ode113, ode15s, ode23s, ode23t, or ode23tb.

Arguments

The following table describes the input arguments to the solvers.

odefun

A function handle that evaluates the right side of the differential equations. See "Function Handles" in the MATLAB Programming documentation for more information. All solvers solve systems of equations in the form y' = f(t, y) or problems that involve a mass matrix, M(t, y)y' = f(t, y). The ode23s solver can solve only equations with constant mass matrices. ode15s and ode23t can solve problems with a mass matrix that is singular, i.e., differential-algebraic equations (DAEs).

tspan

A vector specifying the interval of integration, [t0,tf]. The solver imposes the initial conditions at tspan(1), and integrates from tspan(1) to tspan(end). To obtain solutions at specific times (all increasing or all decreasing), use tspan = [t0,t1,...,tf].

For tspan vectors with two elements [t0 tf], the solver returns the solution evaluated at every integration step. For tspan vectors with more than two elements, the solver returns solutions evaluated at the given time points.

ode23, ode45, ode113, ode15s, ode23s, ode23t, ode23tb

The time values must be in order, either increasing or decreasing.

Specifying tspan with more than two elements does not affect the internal time steps that the solver uses to traverse the interval from tspan(1) to tspan(end). All solvers in the ODE suite obtain output values by means of continuous extensions of the basic formulas. Although a solver does not necessarily step precisely to a time point specified in tspan, the solutions produced at the specified time points are of the same order of accuracy as the solutions computed at the internal time points.

Specifying tspan with more than two elements has little effect on the efficiency of computation, but for large systems, affects memory management.

y0

options

A vector of initial conditions.

Structure of optional parameters that change the default integration properties. This is the fourth input argument.

```
[t,y] =
solver(odefun, tspan, y0, options)
```

You can create options using the odeset function. See odeset for details.

The following table lists the output arguments for the solvers.

Τ Column vector of time points.

Υ Solution array. Each row in Y corresponds to the solution

at a time returned in the corresponding row of T.

ΤF The time at which an event occurs.

ode23, ode45, ode113, ode15s, ode23s, ode23t, ode23tb

YE The solution at the time of the event.

IE The index i of the event function that vanishes.

sol Structure to evaluate the solution.

Description

 $[\mathsf{T},\mathsf{Y}] = solver(\mathsf{odefun},\mathsf{tspan},\mathsf{y0})$ with $\mathsf{tspan} = [\mathsf{t0} \ \mathsf{tf}]$ integrates the system of differential equations y' = f(t,y) from time $\mathsf{t0}$ to tf with initial conditions $\mathsf{y0}$. odefun is a function handle. See Function Handles in the MATLAB Programming documentation for more information. Function $\mathsf{f} = \mathsf{odefun}(\mathsf{t},\mathsf{y})$, for a scalar t and a column vector y , must return a column vector f corresponding to f(t,y). Each row in the solution array Y corresponds to a time returned in column vector T . To obtain solutions at the specific times $\mathsf{t0}, \mathsf{t1}, \ldots, \mathsf{tf}$ (all increasing or all decreasing), use $\mathsf{tspan} = [\mathsf{t0}, \mathsf{t1}, \ldots, \mathsf{tf}]$.

"Parameterizing Functions", in the MATLAB Mathematics documentation, explains how to provide additional parameters to the function fun, if necessary.

[T,Y] = solver(odefun,tspan,y0,options) solves as above with default integration parameters replaced by property values specified in options, an argument created with the odeset function. Commonly used properties include a scalar relative error tolerance RelTol (1e-3 by default) and a vector of absolute error tolerances AbsTol (all components are 1e-6 by default). If certain components of the solution must be nonnegative, use the odeset function to set the NonNegative property to the indices of these components. See odeset for details.

[T,Y,TE,YE,IE] = solver(odefun,tspan,y0,options) solves as above while also finding where functions of (t,y), called event functions, are zero. For each event function, you specify whether the integration is to terminate at a zero and whether the direction of the zero crossing matters. Do this by setting the 'Events' property to a function, e.g., events or @events, and creating a function [value,isterminal,direction] = events(t,y). For the ith event function in events,

- value(i) is the value of the function.
- isterminal(i) = 1, if the integration is to terminate at a zero of this event function and 0 otherwise.
- direction(i) = 0 if all zeros are to be computed (the default), +1 if only the zeros where the event function increases, and -1 if only the zeros where the event function decreases.

Corresponding entries in TE, YE, and IE return, respectively, the time at which an event occurs, the solution at the time of the event, and the index i of the event function that vanishes.

sol = solver(odefun,[t0 tf],y0...) returns a structure that you
can use with deval to evaluate the solution at any point on the interval
[t0,tf]. You must pass odefun as a function handle. The structure
sol always includes these fields:

sol.x	Steps chosen by the solver.	
sol.y	Each column sol.y(:,i) contains the solution at sol.x(i).	
sol.solver	Solver name.	

If you specify the Events option and events are detected, sol also includes these fields:

sol.xe	Points at which events, if any, occurred. sol.xe(end) contains the exact point of a terminal event, if any.
sol.ye	Solutions that correspond to events in sol.xe.
sol.ie	Indices into the vector returned by the function specified in the Events option. The values indicate which event the solver detected.

If you specify an output function as the value of the OutputFcn property, the solver calls it with the computed solution after each time step. Four output functions are provided: odeplot, odephas2, odephas3,

odeprint. When you call the solver with no output arguments, it calls the default odeplot to plot the solution as it is computed. odephas2 and odephas3 produce two- and three-dimensional phase plane plots, respectively. odeprint displays the solution components on the screen. By default, the ODE solver passes all components of the solution to the output function. You can pass only specific components by providing a vector of indices as the value of the OutputSel property. For example, if you call the solver with no output arguments and set the value of OutputSel to [1,3], the solver plots solution components 1 and 3 as they are computed.

For the stiff solvers ode15s, ode23s, ode23t, and ode23tb, the Jacobian matrix $\partial f/\partial y$ is critical to reliability and efficiency. Use odeset to set Jacobian to @FJAC if FJAC(T,Y) returns the Jacobian $\partial f/\partial y$ or to the matrix $\partial f/\partial y$ if the Jacobian is constant. If the Jacobian property is not set (the default), $\partial f/\partial y$ is approximated by finite differences. Set the Vectorized property 'on' if the ODE function is coded so that odefun(T,[Y1,Y2...]) returns [odefun(T,Y1),odefun(T,Y2)...]. If $\partial f/\partial y$ is a sparse matrix, set the JPattern property to the sparsity pattern of $\partial f/\partial y$, i.e., a sparse matrix S with S(i,j) = 1 if the ith component of f(t,y) depends on the jth component of y, and 0 otherwise.

The solvers of the ODE suite can solve problems of the form M(t,y)y'=f(t,y), with time- and state-dependent mass matrix M. (The ode23s solver can solve only equations with constant mass matrices.) If a problem has a mass matrix, create a function M=MASS(t,y) that returns the value of the mass matrix, and use odeset to set the Mass property to QMASS. If the mass matrix is constant, the matrix should be used as the value of the Mass property. Problems with state-dependent mass matrices are more difficult:

 If the mass matrix does not depend on the state variable y and the function MASS is to be called with one input argument, t, set the MStateDependence property to 'none'.

• If the mass matrix depends weakly on y, set MStateDependence to 'weak' (the default); otherwise, set it to 'strong'. In either case, the function MASS is called with the two arguments (t,y).

If there are many differential equations, it is important to exploit sparsity:

- Return a sparse M(t, y).
- Supply the sparsity pattern of $\partial f/\partial y$ using the JPattern property or a sparse $\partial f/\partial y$ using the Jacobian property.
- For strongly state-dependent M(t, y), set MvPattern to a sparse matrix S with S(i,j) = 1 if for any k, the (i,k) component of M(t, y) depends on component j of y, and 0 otherwise.

If the mass matrix M is singular, then M(t,y)y'=f(t,y) is a system of differential algebraic equations. DAEs have solutions only when y_0 is consistent, that is, if there is a vector y_0 such that $M(t_0,y_0)y_0=f(t_0,y_0)$. The ode15s and ode23t solvers can solve DAEs of index 1 provided that y0 is sufficiently close to being consistent. If there is a mass matrix, you can use odeset to set the MassSingular property to 'yes', 'no', or 'maybe'. The default value of 'maybe' causes the solver to test whether the problem is a DAE. You can provide yp0 as the value of the InitialSlope property. The default is the zero vector. If a problem is a DAE, and y0 and yp0 are not consistent, the solver treats them as guesses, attempts to compute consistent values that are close to the guesses, and continues to solve the problem. When solving DAEs, it is very advantageous to formulate the problem so that M is a diagonal matrix (a semi-explicit DAE).

Solver	Problem Type	Order of Accuracy	When to Use
ode45	Nonstiff	Medium	Most of the time. This should be the first solver you try.
ode23	Nonstiff	Low	For problems with crude error tolerances or for solving moderately stiff problems.
ode113	Nonstiff	Low to high	For problems with stringent error tolerances or for solving computationally intensive problems.
ode15s	Stiff	Low to medium	If ode45 is slow because the problem is stiff.
ode23s	Stiff	Low	If using crude error tolerances to solve stiff systems and the mass matrix is constant.
ode23t	Moderately Stiff	Low	For moderately stiff problems if you need a solution without numerical damping.
ode23tb	Stiff	Low	If using crude error tolerances to solve stiff systems.

The algorithms used in the ODE solvers vary according to order of accuracy [6] and the type of systems (stiff or nonstiff) they are designed to solve. See "Algorithms" on page 2-2808 for more details.

Options

Different solvers accept different parameters in the options list. For more information, see odeset and "Integrator Options" in the MATLAB Mathematics documentation.

Parameters	ode45	ode23	ode113	ode15s	ode23s	ode23t	ode23tb
RelTol, AbsTol, NormControl	√	√	√	√	√	√	1
OutputFcn, OutputSel, Refine, Stats	√	√	√	√	√	√	√
NonNegative	\checkmark	√	√	√ *	_	√ *	√ *
Events	√	√	√	√	√	√	√
MaxStep, InitialStep	√	√	√	√	√	√	V
Jacobian, JPattern, Vectorized	_	_	_	√	√	√	√
Mass MStateDependence MvPattern MassSingular	\frac{}{}	\frac{}{}	\frac{}{}	\ \ \ \	√ _ _	\ \ \ \	\ \ \ -
InitialSlope	_	_	_	√	_	√	_
MaxOrder, BDF	_	_	_	V	_	_	_

Note You can use the NonNegative parameter with ode15s, ode23t, and ode23tb only for those problems for which there is no mass matrix.

Examples Example 1

An example of a nonstiff system is the system of equations describing the motion of a rigid body without external forces.

$$y'_1 = y_2 y_3$$
 $y_1(0) = 0$
 $y'_2 = -y_1 y_3$ $y_2(0) = 1$
 $y'_3 = -0.51 y_1 y_2$ $y_3(0) = 1$

To simulate this system, create a function rigid containing the equations

```
function dy = rigid(t,y)

dy = zeros(3,1); % a column vector

dy(1) = y(2) * y(3);

dy(2) = -y(1) * y(3);


dy(3) = -0.51 * y(1) * y(2);
```

In this example we change the error tolerances using the odeset command and solve on a time interval [0 12] with an initial condition vector [0 1 1] at time 0.

```
options = odeset('RelTol',1e-4,'AbsTol',[1e-4 1e-4 1e-5]);
[T,Y] = ode45(@rigid,[0 12],[0 1 1],options);
```

Plotting the columns of the returned array Y versus T shows the solution

```
\verb"plot(T,Y(:,1),'-',T,Y(:,2),'-.',T,Y(:,3),'.')"
```



Example 2

An example of a stiff system is provided by the van der Pol equations in relaxation oscillation. The limit cycle has portions where the solution components change slowly and the problem is quite stiff, alternating with regions of very sharp change where it is not stiff.

$$y'_1 = y_2$$
 $y_1(0) = 2$
 $y'_2 = 1000(1 - y_1^2)y_2 - y_1$ $y_2(0) = 0$

To simulate this system, create a function vdp1000 containing the equations


function dy = vdp1000(t,y)

```
dy = zeros(2,1); % a column vector dy(1) = y(2); dy(2) = 1000*(1 - y(1)^2)*y(2) - y(1);
```

For this problem, we will use the default relative and absolute tolerances (1e-3 and 1e-6, respectively) and solve on a time interval of [0 3000] with initial condition vector [2 0] at time 0.

```
[T,Y] = ode15s(@vdp1000,[0 3000],[2 0]);
```

Plotting the first column of the returned matrix \boldsymbol{Y} versus \boldsymbol{T} shows the solution



Example 3

This example solves an ordinary differential equation with time-dependent terms.

Consider the following ODE, with time-dependent parameters defined only through the set of data points given in two vectors:

```
y'(t) + f(t)y(t) = g(t)
```

The initial condition is y(0) = 0, where the function f(t) is defined through the n-by-1 vectors tf and f, and the function g(t) is defined through the m-by-1 vectors tg and g.

First, define the time-dependent parameters f(t) and g(t) as the following:

```
ft = linspace(0,5,25); % Generate t for f
f = ft.^2 - ft - 3; % Generate f(t)
gt = linspace(1,6,25); % Generate t for g
g = 3*sin(gt-0.25); % Generate g(t)
```

Write an M-file function to interpolate the data sets specified above to obtain the value of the time-dependent terms at the specified time:

```
function dydt = myode(t,y,ft,f,gt,g)
f = interp1(ft,f,t); % Interpolate the data set (ft,f) at time t
g = interp1(gt,g,t); % Interpolate the data set (gt,g) at time t
dydt = -f.*y + g; % Evalute ODE at time t
```


Call the derivative function myode.m within the MATLAB ode45 function specifying time as the first input argument:

```
Tspan = [1 5]; % Solve from t=1 to t=5 IC = 1; % y(t=0) = 1 [T Y] = ode45(@(t,y) myode(t,y,ft,f,gt,g),Tspan,IC); % Solve ODE
```

Plot the solution y(t) as a function of time:

```
plot(T, Y);
```

title('Plot of y as a function of time');
xlabel('Time'); ylabel('Y(t)');



Algorithms

ode45 is based on an explicit Runge-Kutta (4,5) formula, the Dormand-Prince pair. It is a *one-step* solver – in computing $y(t_n)$, it needs only the solution at the immediately preceding time point, $y(t_{n-1})$. In general, ode45 is the best function to apply as a *first try* for most problems. [3]

ode23 is an implementation of an explicit Runge-Kutta (2,3) pair of Bogacki and Shampine. It may be more efficient than ode45 at crude

tolerances and in the presence of moderate stiffness. Like ode45, ode23 is a one-step solver. [2]

ode113 is a variable order Adams-Bashforth-Moulton PECE solver. It may be more efficient than ode45 at stringent tolerances and when the ODE file function is particularly expensive to evaluate. ode113 is a *multistep* solver — it normally needs the solutions at several preceding time points to compute the current solution. [7]

The above algorithms are intended to solve nonstiff systems. If they appear to be unduly slow, try using one of the stiff solvers below.

ode15s is a variable order solver based on the numerical differentiation formulas (NDFs). Optionally, it uses the backward differentiation formulas (BDFs, also known as Gear's method) that are usually less efficient. Like ode113, ode15s is a multistep solver. Try ode15s when ode45 fails, or is very inefficient, and you suspect that the problem is stiff, or when solving a differential-algebraic problem. [9], [10]

ode23s is based on a modified Rosenbrock formula of order 2. Because it is a one-step solver, it may be more efficient than ode15s at crude tolerances. It can solve some kinds of stiff problems for which ode15s is not effective. [9]

ode23t is an implementation of the trapezoidal rule using a "free" interpolant. Use this solver if the problem is only moderately stiff and you need a solution without numerical damping. ode23t can solve DAEs. [10]

ode23tb is an implementation of TR-BDF2, an implicit Runge-Kutta formula with a first stage that is a trapezoidal rule step and a second stage that is a backward differentiation formula of order two. By construction, the same iteration matrix is used in evaluating both stages. Like ode23s, this solver may be more efficient than ode15s at crude tolerances. [8], [1]

See Also

deval, ode15i, odeget, odeset, function_handle (@)

References

- [1] Bank, R. E., W. C. Coughran, Jr., W. Fichtner, E. Grosse, D. Rose, and R. Smith, "Transient Simulation of Silicon Devices and Circuits," *IEEE Trans. CAD*, 4 (1985), pp 436-451.
- [2] Bogacki, P. and L. F. Shampine, "A 3(2) pair of Runge-Kutta formulas," *Appl. Math. Letters*, Vol. 2, 1989, pp 1-9.
- [3] Dormand, J. R. and P. J. Prince, "A family of embedded Runge-Kutta formulae," *J. Comp. Appl. Math.*, Vol. 6, 1980, pp 19-26.
- [4] Forsythe, G., M. Malcolm, and C. Moler, *Computer Methods for Mathematical Computations*, Prentice-Hall, New Jersey, 1977.
- [5] Kahaner, D., C. Moler, and S. Nash, *Numerical Methods and Software*, Prentice-Hall, New Jersey, 1989.
- [6] Shampine, L. F., Numerical Solution of Ordinary Differential Equations, Chapman & Hall, New York, 1994.
- [7] Shampine, L. F. and M. K. Gordon, Computer Solution of Ordinary Differential Equations: the Initial Value Problem, W. H. Freeman, San Francisco, 1975.
- [8] Shampine, L. F. and M. E. Hosea, "Analysis and Implementation of TR-BDF2," *Applied Numerical Mathematics 20*, 1996.
- [9] Shampine, L. F. and M. W. Reichelt, "The MATLAB ODE Suite," *SIAM Journal on Scientific Computing*, Vol. 18, 1997, pp 1-22.
- [10] Shampine, L. F., M. W. Reichelt, and J.A. Kierzenka, "Solving Index-1 DAEs in MATLAB and Simulink," *SIAM Review*, Vol. 41, 1999, pp 538-552.

Purpose

Define differential equation problem for ordinary differential equation solvers

Note This reference page describes the odefile and the syntax of the ODE solvers used in MATLAB, Version 5. MATLAB, Version 6, supports the odefile for backward compatibility, however the new solver syntax does not use an ODE file. New functionality is available only with the new syntax. For information about the new syntax, see odeset or any of the ODE solvers.

Description

odefile is not a command or function. It is a help entry that describes how to create an M-file defining the system of equations to be solved. This definition is the first step in using any of the MATLAB ODE solvers. In MATLAB documentation, this M-file is referred to as an odefile, although you can give your M-file any name you like.

You can use the odefile M-file to define a system of differential equations in one of these forms

$$y' = f(t, y)$$

or

$$M(t, y)y' = f(t, y)v$$

where:

- *t* is a scalar independent variable, typically representing time.
- y is a vector of dependent variables.
- f is a function of t and y returning a column vector the same length as y.
- M(t, y) is a time-and-state-dependent mass matrix.

The ODE file must accept the arguments t and y, although it does not have to use them. By default, the ODE file must return a column vector the same length as y.

All of the solvers of the ODE suite can solve M(t, y)y' = f(t, y), except ode23s, which can only solve problems with constant mass matrices. The ode15s and ode23t solvers can solve some differential-algebraic equations (DAEs) of the form M(t)y' = f(t, y).

Beyond defining a system of differential equations, you can specify an entire initial value problem (IVP) within the ODE M-file, eliminating the need to supply time and initial value vectors at the command line (see "Examples" on page 2-2814).

To Use the ODE File Template

- Enter the command help odefile to display the help entry.
- Cut and paste the ODE file text into a separate file.
- Edit the file to eliminate any cases not applicable to your IVP.
- Insert the appropriate information where indicated. The definition of the ODE system is required information.

```
switch flag
case '' % Return dy/dt = f(t,y).
  varargout{1} = f(t,y,p1,p2);
case 'init' % Return default [tspan,y0,options].
  [varargout{1:3}] = init(p1,p2);
case 'jacobian' % Return Jacobian matrix df/dy.
  varargout{1} = jacobian(t,y,p1,p2);
case 'jpattern' % Return sparsity pattern matrix S.
  varargout{1} = jpattern(t,y,p1,p2);
case 'mass' % Return mass matrix.
  varargout{1} = mass(t,y,p1,p2);
case 'events' % Return [value,isterminal,direction].
  [varargout{1:3}] = events(t,y,p1,p2);
otherwise
  error(['Unknown flag ''' flag '''.']);
```

```
end
% -----
function dvdt = f(t,v,p1,p2)
dydt = Insert a function of t and/or y, p1, and p2 here.>
% -----
function [tspan, y0, options] = init(p1, p2)
tspan = <Insert tspan here.>;
v0 = <Insert v0 here.>;
options = <Insert options = odeset(...) or [] here.>;
% -----
function dfdy = jacobian(t,y,p1,p2)
dfdv = <Insert Jacobian matrix here.>;
% -----
function S = jpattern(t,y,p1,p2)
S = <Insert Jacobian matrix sparsity pattern here.>;
% -----
function M = mass(t,v,p1,p2)
M = <Insert mass matrix here.>;
% -----
function [value,isterminal,direction] = events(t,y,p1,p2)
value = <Insert event function vector here.>
isterminal = <Insert logical ISTERMINAL vector here.>;
direction = <Insert DIRECTION vector here.>;
```

Notes

- 1 The ODE file must accept t and y vectors from the ODE solvers and must return a column vector the same length as y. The optional input argument flag determines the type of output (mass matrix, Jacobian, etc.) returned by the ODE file.
- **2** The solvers repeatedly call the ODE file to evaluate the system of differential equations at various times. *This is required information* you must define the ODE system to be solved.
- **3** The switch statement determines the type of output required, so that the ODE file can pass the appropriate information to the solver. (See notes 4 9.)

odefile

- **4** In the default *initial conditions* ('init') case, the ODE file returns basic information (time span, initial conditions, options) to the solver. If you omit this case, you must supply all the basic information on the command line.
- **5** In the 'jacobian' case, the ODE file returns a Jacobian matrix to the solver. You need only provide this case when you want to improve the performance of the stiff solvers ode15s, ode23s, ode23t, and ode23tb.
- **6** In the 'jpattern' case, the ODE file returns the Jacobian sparsity pattern matrix to the solver. You need to provide this case only when you want to generate sparse Jacobian matrices numerically for a stiff solver.
- **7** In the 'mass' case, the ODE file returns a mass matrix to the solver. You need to provide this case only when you want to solve a system in the form M(t, y)y' = f(t, y).
- 8 In the 'events' case, the ODE file returns to the solver the values that it needs to perform event location. When the Events property is set to on, the ODE solvers examine any elements of the event vector for transitions to, from, or through zero. If the corresponding element of the logical isterminal vector is set to 1, integration will halt when a zero-crossing is detected. The elements of the direction vector are -1, 1, or 0, specifying that the corresponding event must be decreasing, increasing, or that any crossing is to be detected.
- **9** An unrecognized flag generates an error.

Examples

The van der Pol equation, $y''_1 - \mu(1 - y_1^2)y' + y_1 = 0$, is equivalent to a system of coupled first-order differential equations.

$$y'_1 = y_2$$

 $y'_2 = \mu(1 - y_1^2)y_2 - y_1$


The M-file

```
function out1 = vdp1(t,y)
out1 = [y(2); (1-y(1)^2)*y(2) - y(1)];
```

defines this system of equations (with $\mu = 1$).

To solve the van der Pol system on the time interval $[0\ 20]$ with initial values (at time 0) of y(1) = 2 and y(2) = 0, use

```
[t,y] = ode45('vdp1',[0 20],[2; 0]);
plot(t,y(:,1),'-',t,y(:,2),'-.')
```



To specify the entire initial value problem (IVP) within the M-file, rewrite vdp1 as follows.

You can now solve the IVP without entering any arguments from the command line.

```
[t,Y] = ode23('vdp1')
```

In this example the ode23 function looks to the vdp1 M-file to supply the missing arguments. Note that, once you've called odeset to define options, the calling syntax

```
[t,Y] = ode23('vdp1',[],[],options)
```

also works, and that any options supplied via the command line override corresponding options specified in the M-file (see odeset).

See Also

The MATLAB Version 5 help entries for the ODE solvers and their associated functions: ode23, ode45, ode113, ode15s, ode23s, ode23t, ode23tb, odeget, odeset

Type at the MATLAB command line: more on, type function, more off. The Version 5 help follows the Version 6 help.

Purpose

Ordinary differential equation options parameters

Syntax

```
o = odeget(options, 'name')
o = odeget(options, 'name', default)
```

Description

o = odeget(options, 'name') extracts the value of the property specified by string 'name' from integrator options structure options, returning an empty matrix if the property value is not specified in options. It is only necessary to type the leading characters that uniquely identify the property name. Case is ignored for property names. The empty matrix [] is a valid options argument.

o = odeget(options, 'name', default) returns o = default if the named property is not specified in options.

Example

Having constructed an ODE options structure,

```
options = odeset('RelTol',1e-4,'AbsTol',[1e-3 2e-3 3e-3]);
```

you can view these property settings with odeget.

See Also

odeset

Purpose

Create or alter options structure for ordinary differential equation solvers

Syntax

```
options = odeset('name1',value1,'name2',value2,...)
options = odeset(oldopts,'name1',value1,...)
options = odeset(oldopts,newopts)
odeset
```

Description

The odeset function lets you adjust the integration parameters of the following ODE solvers.

For solving fully implicit differential equations:

ode15i

For solving initial value problems:

```
ode23, ode45, ode113, ode15s, ode23s, ode23t, ode23tb
```

See below for information about the integration parameters.

options = odeset('name1',value1,'name2',value2,...) creates an options structure that you can pass as an argument to any of the ODE solvers. In the resulting structure, options, the named properties have the specified values. For example, 'name1' has the value value1. Any unspecified properties have default values. It is sufficient to type only the leading characters that uniquely identify a property name. Case is ignored for property names.

options = odeset(oldopts, 'name1', value1,...) alters an existing options structure oldopts. This sets options equal to the existing structure oldopts, overwrites any values in oldopts that are respecified using name/value pairs, and adds any new pairs to the structure. The modified structure is returned as an output argument.

options = odeset(oldopts,newopts) alters an existing options structure oldopts by combining it with a new options structure newopts. Any new options not equal to the empty matrix overwrite corresponding options in oldopts.

odeset with no input arguments displays all property names as well as their possible and default values.

ODE Properties

The following sections describe the properties that you can set using odeset. The available properties depend on the ODE solver you are using. There are several categories of properties:

- "Error Control Properties" on page 2-2819
- "Solver Output Properties" on page 2-2821
- "Step-Size Properties" on page 2-2824
- "Event Location Property" on page 2-2826
- "Jacobian Matrix Properties" on page 2-2827
- "Mass Matrix and DAE Properties" on page 2-2831
- "ode15s and ode15i-Specific Properties" on page 2-2834

Note This reference page describes the ODE properties for MATLAB, Version 7. The Version 5 properties are supported only for backward compatibility. For information on the Version 5 properties, type at the MATLAB command line: more on, type odeset, more off.

Error Control Properties

At each step, the solver estimates the local error e in the ith component of the solution. This error must be less than or equal to the acceptable error, which is a function of the specified relative tolerance, RelTol, and the specified absolute tolerance, AbsTol.

```
|e(i)| \le \max(RelTol*abs(y(i)),AbsTol(i))
```

For routine problems, the ODE solvers deliver accuracy roughly equivalent to the accuracy you request. They deliver less accuracy for problems integrated over "long" intervals and problems that are moderately unstable. Difficult problems may require tighter tolerances than the default values. For relative accuracy, adjust RelTol. For

the absolute error tolerance, the scaling of the solution components is important: if |y| is somewhat smaller than AbsTo1, the solver is not constrained to obtain any correct digits in y. You might have to solve a problem more than once to discover the scale of solution components.

Roughly speaking, this means that you want RelTol correct digits in all solution components except those smaller than thresholds AbsTol(i). Even if you are not interested in a component y(i) when it is small, you may have to specify AbsTol(i) small enough to get some correct digits in y(i) so that you can accurately compute more interesting components.

The following table describes the error control properties. Further information on each property is given following the table.

Property	Value	Description
RelTol	Positive scalar {1e-3}	Relative error tolerance that applies to all components of the solution vector y.
AbsTol	Positive scalar or vector {1e-6}	Absolute error tolerances that apply to the individual components of the solution vector.
NormControl	on {off}	Control error relative to norm of solution.

Description of Error Control Properties

RelTol — This tolerance is a measure of the error relative to the size of each solution component. Roughly, it controls the number of correct digits in all solution components, except those smaller than thresholds AbsTol(i).

The default, 1e-3, corresponds to 0.1% accuracy.

AbsTo1 — AbsTo1(i) is a threshold below which the value of the ith solution component is unimportant. The absolute error tolerances determine the accuracy when the solution approaches zero.

If AbsTol is a vector, the length of AbsTol must be the same as the length of the solution vector y. If AbsTol is a scalar, the value applies to all components of y.

NormControl — Set this property on to request that the solvers control the error in each integration step with norm(e) <= max(RelTol*norm(y),AbsTol). By default the solvers use a more stringent componentwise error control.

Solver Output Properties

The following table lists the solver output properties that control the output that the solvers generate. Further information on each property is given following the table.

Property	Value	Description
NonNegative	Vector of integers	Specifies which components of the solution vector must be nonnegative. The default value is [].
OutputFcn	Function handle	A function for the solver to call after every successful integration step.
OutputSel	Vector of indices	Specifies which components of the solution vector are to be passed to the output function.
Refine	Positive integer	Increases the number of output points by a factor of Refine.
Stats	on {off}	Determines whether the solver should display statistics about its computations. By default, Stats is off.

Description of Solver Output Properties

NonNegative — The NonNegative property is not available in ode23s, ode15i. In ode15s, ode23t, and ode23tb, NonNegative is not available for problems where there is a mass matrix.

OutputFcn — To specify an output function, set 'OutputFcn' to a function handle. For example,

```
options = odeset('OutputFcn',@myfun)
```

sets 'OutputFcn' to @myfun, a handle to the function myfun. See "Function Handles" in the MATLAB Programming documentation for more information.

The output function must be of the form

```
status = myfun(t,y,flag)
```

"Parameterizing Functions", in the MATLAB Mathematics documentation, explains how to provide additional parameters to myfun, if necessary.

The solver calls the specified output function with the following flags. Note that the syntax of the call differs with the flag. The function must respond appropriately:

Flag	Description
init	The solver calls myfun(tspan,y0,'init') before beginning the integration to allow the output function to initialize. tspan and y0 are the input arguments to the ODE solver.
{[]}	The solver calls status = myfun(t,y,[]) after each integration step on which output is requested. t contains points where output was generated during the step, and y is the numerical solution at the points in t. If t is a vector, the ith column of y corresponds to the ith element of t.
	When length(tspan) > 2 the output is produced at every point in tspan. When length(tspan) = 2 the output is produced according to the Refine option.
	myfun must return a status output value of 0 or 1. If status = 1, the solver halts integration. You can use this mechanism, for instance, to implement a Stop button.

Flag	Description
done	The solver calls myfun([],[],'done') when integration is complete to allow the output function to perform any cleanup chores.

You can use these general purpose output functions or you can edit them to create your own. Type help function at the command line for more information.

- odeplot Time series plotting (default when you call the solver with no output arguments and you have not specified an output function)
- odephas2 Two-dimensional phase plane plotting
- odephas3 Three-dimensional phase plane plotting
- odeprint Print solution as it is computed

Note If you call the solver with no output arguments, the solver does not allocate storage to hold the entire solution history.

OutputSel — Use OutputSel to specify which components of the solution vector you want passed to the output function. For example, if you want to use the odeplot output function, but you want to plot only the first and third components of the solution, you can do this using

```
options = ...
odeset('OutputFcn',@odeplot,'OutputSel',[1 3]);
```

By default, the solver passes all components of the solution to the output function.

Refine — If Refine is 1, the solver returns solutions only at the end of each time step. If Refine is n > 1, the solver subdivides each time step into n smaller intervals and returns solutions at each time point. Refine does not apply when length(tspan)>2.

Note In all the solvers, the default value of Refine is 1. Within ode45, however, the default is 4 to compensate for the solver's large step sizes. To override this and see only the time steps chosen by ode45, set Refine to 1.

The extra values produced for Refine are computed by means of continuous extension formulas. These are specialized formulas used by the ODE solvers to obtain accurate solutions between computed time steps without significant increase in computation time.

Stats — By default, Stats is off. If it is on, after solving the problem the solver displays

- Number of successful steps
- Number of failed attempts
- Number of times the ODE function was called to evaluate f(t, y)

Solvers based on implicit methods, including ode23s, ode23t, ode23t, ode15s, and ode15i, also display

- Number of times that the partial derivatives matrix $\partial f/\partial x$ was formed
- Number of LU decompositions
- Number of solutions of linear systems

Step-Size Properties

The step-size properties specify the size of the first step the solver tries, potentially helping it to better recognize the scale of the problem. In addition, you can specify bounds on the sizes of subsequent time steps.

The following table describes the step-size properties. Further information on each property is given following the table.

Property	Value	Description
InitialStep	Positive scalar	Suggested initial step size.
MaxStep	Positive scalar {0.1*abs(t0-tf)}	Upper bound on solver step size.

Description of Step-Size Properties

InitialStep — InitialStep sets an upper bound on the magnitude of the first step size the solver tries. If you do not set InitialStep, the initial step size is based on the slope of the solution at the initial time tspan(1), and if the slope of all solution components is zero, the procedure might try a step size that is much too large. If you know this is happening or you want to be sure that the solver resolves important behavior at the start of the integration, help the code start by providing a suitable InitialStep.

MaxStep — If the differential equation has periodic coefficients or solutions, it might be a good idea to set MaxStep to some fraction (such as 1/4) of the period. This guarantees that the solver does not enlarge the time step too much and step over a period of interest. Do *not* reduce MaxStep for any of the following purposes:

- To produce more output points. This can significantly slow down solution time. Instead, use Refine to compute additional outputs by continuous extension at very low cost.
- When the solution does not appear to be accurate enough. Instead, reduce the relative error tolerance RelTol, and use the solution you just computed to determine appropriate values for the absolute error tolerance vector AbsTol. See "Error Control Properties" on page 2-2819 for a description of the error tolerance properties.
- To make sure that the solver doesn't step over some behavior that occurs only once during the simulation interval. If you know the time at which the change occurs, break the simulation interval into two pieces and call the solver twice. If you do not know the time at which the change occurs, try reducing the error tolerances RelTol and AbsTol. Use MaxStep as a last resort.

Event Location Property

In some ODE problems the times of specific events are important, such as the time at which a ball hits the ground, or the time at which a spaceship returns to the earth. While solving a problem, the ODE solvers can detect such events by locating transitions to, from, or through zeros of user-defined functions.

The following table describes the Events property. Further information on each property is given following the table.

ODE Events Property

String	Value	Description
Events		Handle to a function that includes one or more event functions.

Description of Event Location Properties

Events — The function is of the form

[value,isterminal,direction] = events(t,y)

value, isterminal, and direction are vectors for which the ith element corresponds to the ith event function:

- value(i) is the value of the ith event function.
- isterminal(i) = 1 if the integration is to terminate at a zero of this event function, otherwise, 0.
- direction(i) = 0 if all zeros are to be located (the default), +1 if only zeros where the event function is increasing, and -1 if only zeros where the event function is decreasing.

If you specify an events function and events are detected, the solver returns three additional outputs:

- · A column vector of times at which events occur
- Solution values corresponding to these times

• Indices into the vector returned by the events function. The values indicate which event the solver detected.

If you call the solver as

the solver returns these outputs as TE, YE, and IE respectively. If you call the solver as

the solver returns these outputs as sol.xe, sol.ye, and sol.ie, respectively.

For examples that use an event function, see "Event Location" and "Advanced Event Location" in the MATLAB Mathematics documentation.

Jacobian Matrix Properties

The stiff ODE solvers often execute faster if you provide additional information about the Jacobian matrix $\partial f / \partial y$, a matrix of partial derivatives of the function that defines the differential equations.

$$\frac{\partial f}{\partial y} = \begin{bmatrix} \frac{\partial f}{\partial y_1} & \frac{\partial f}{\partial y_2} & \cdots \\ \frac{\partial f}{\partial y_1} & \frac{\partial f}{\partial y_2} & \cdots \\ \vdots & \vdots & \vdots \end{bmatrix}$$

The Jacobian matrix properties pertain only to those solvers for stiff problems (ode15s, ode23s, ode23t, ode23tb, and ode15i) for which the Jacobian matrix $\partial f/\partial y$ can be critical to reliability and efficiency. If you do not provide a function to calculate the Jacobian, these solvers

approximate the Jacobian numerically using finite differences. In this case, you might want to use the Vectorized or JPattern properties.

The following table describes the Jacobian matrix properties for all implicit solvers except ode15i. Further information on each property is given following the table. See Jacobian Properties for ode15i on page 2-2830 for ode15i-specific information.

Jacobian Properties for All Implicit Solvers Except ode 15i

Property	Value	Description
Jacobian	Function handle constant matrix	Matrix or function that evaluates the Jacobian.
JPattern	Sparse matrix of {0,1}	Generates a sparse Jacobian matrix numerically.
Vectorized	on {off}	Allows the solver to reduce the number of function evaluations required.

Description of Jacobian Properties

Jacobian — Supplying an analytical Jacobian often increases the speed and reliability of the solution for stiff problems. Set this property to a function FJac, where FJac(t,y) computes $\partial f/\partial y$, or to the constant value of $\partial f/\partial y$.

The Jacobian for the "van der Pol Equation (Stiff)", described in the MATLAB Mathematics documentation, can be coded as

JPattern — JPattern is a sparsity pattern with 1s where there might be nonzero entries in the Jacobian.

Note If you specify Jacobian, the solver ignores any setting for JPattern.

Set this property to a sparse matrix S with S(i,j) = 1 if component i of f(t,y) depends on component j of y, and 0 otherwise. The solver uses this sparsity pattern to generate a sparse Jacobian matrix numerically. If the Jacobian matrix is large and sparse, this can greatly accelerate execution. For an example using the JPattern property, see Example: Large, Stiff, Sparse Problem in the MATLAB Mathematics documentation.

Vectorized — The Vectorized property allows the solver to reduce the number of function evaluations required to compute all the columns of the Jacobian matrix, and might significantly reduce solution time.

Set on to inform the solver that you have coded the ODE function F so that F(t,[y1 y2 ...]) returns [F(t,y1) F(t,y2) ...]. This allows the solver to reduce the number of function evaluations required to compute all the columns of the Jacobian matrix, and might significantly reduce solution time.

Note If you specify Jacobian, the solver ignores a setting of 'on' for 'Vectorized'.

With the MATLAB array notation, it is typically an easy matter to vectorize an ODE function. For example, you can vectorize the "van der Pol Equation (Stiff)", described in the MATLAB Mathematics documentation, by introducing colon notation into the subscripts and by using the array power (.^) and array multiplication (.*) operators.

```
function dydt = vdp1000(t,y)
dydt = [y(2,:); 1000*(1-y(1,:).^2).*y(2,:)-y(1,:)];
```

Note Vectorization of the ODE function used by the ODE solvers differs from the vectorization used by the boundary value problem (BVP) solver, bvp4c. For the ODE solvers, the ODE function is vectorized only with respect to the second argument, while bvp4c requires vectorization with respect to the first and second arguments.

The following table describes the Jacobian matrix properties for ode15i.

Jacobian Properties for ode 15i

Property	Value	Description
Jacobian	Function handle Cell array of constant values	Function that evaluates the Jacobian or a cell array of constant values.
JPattern	Sparse matrices of {0,1}	Generates a sparse Jacobian matrix numerically.
Vectorized	on {off}	Vectorized ODE function

Description of Jacobian Properties for ode 15i

Jacobian — Supplying an analytical Jacobian often increases the speed and reliability of the solution for stiff problems. Set this property to a function

$$[dFdy, dFdp] = Fjac(t,y,yp)$$

or to a cell array of constant values $\{\partial F/\partial y, (\partial F/\partial y)'\}$.

JPattern — JPattern is a sparsity pattern with 1's where there might be nonzero entries in the Jacobian.

Set this property to {dFdyPattern, dFdypPattern}, the sparsity patterns of $\partial F/\partial y$ and $\partial F/\partial y$, respectively.

Vectorized —

Set this property to {yVect, ypVect}. Setting yVect to 'on' indicates that

returns

Setting ypVect to 'on' indicates that

returns

$$[F(t,y,yp1) F(t,y,yp2) \dots]$$

Mass Matrix and DAE Properties

This section describes mass matrix and differential-algebraic equation (DAE) properties, which apply to all the solvers except ode15i. These properties are not applicable to ode15i and their settings do not affect its behavior.

The solvers of the ODE suite can solve ODEs of the form

$$M(t, y)y' = f(t, y)$$
(2-1)

with a mass matrix M(t, y) that can be sparse.

When M(t,y) is nonsingular, the equation above is equivalent to $y' = M^{-1}f(t,y)$ and the ODE has a solution for any initial values y_0 at t_0 . The more general form (Equation 2-1) is convenient when you express a model naturally in terms of a mass matrix. For large, sparse M(t,y), solving Equation 2-1 directly reduces the storage and run-time needed to solve the problem.

When M(t,y) is singular, then M(t,y) times M(t,y)y' = f(t,y) is a DAE. A DAE has a solution only when \mathcal{Y}_0 is consistent; that is, there

exists an initial slope yp_0 such that $M(t_0,y_0)yp_0=f(t_0,y_0)$. If y_0 and yp_0 are not consistent, the solver treats them as guesses, attempts to

 yp_0 are not consistent, the solver treats them as guesses, attempts to compute consistent values that are close to the guesses, and continues to solve the problem. For DAEs of index 1, solving an initial value problem with consistent initial conditions is much like solving an ODE.

The ode15s and ode23t solvers can solve DAEs of index 1. For examples of DAE problems, see Example: Differential-Algebraic Problem, in the MATLAB Mathematics documentation, and the examples amp1dae and hb1dae.

The following table describes the mass matrix and DAE properties. Further information on each property is given following the table.

Mass Matrix and DAE Properties (Solvers Other Than ode 15i)

Property	Value	Description
Mass	Matrix function handle	Mass matrix or a function that evaluates the mass matrix $M(t,y)$.
MStateDependencene {weak} strong		Dependence of the mass matrix on y .
MvPattern	Sparse matrix	$\partial (M(t,y)v)/\partial y$ sparsity pattern.
MassSingular	yes no {maybe}	Indicates whether the mass matrix is singular.
InitialSlope	Vector {zero vecto	rNector representing the consistent
		initial slope yp_0 .

Description of Mass Matrix and DAE Properties

Mass — For problems of the form M(t)y' = f(t,y), set 'Mass' to a mass matrix M. For problems of the form M(t)y' = f(t,y), set 'Mass' to a

function handle QMfun, where Mfun(t,y) evaluates the mass matrix

M(t,y). The ode23s solver can only solve problems with a constant mass matrix M. When solving DAEs, using ode15s or ode23t, it is advantageous to formulate the problem so that M is a diagonal matrix (a semiexplicit DAE).

For example problems, see "Finite Element Discretization" in the MATLAB Mathematics documentation, or the examples fem2ode or batonode.

MStateDependence — Set this property to none for problems

M(t)y' = f(t,y). Both weak and strong indicate M(t,y), but weak results in implicit solvers using approximations when solving algebraic equations.

MvPattern — Set this property to a sparse matrix S with S(i,j) = 1 if, for any k, the (i,k) component of M(t,y) depends on component j of y, and 0 otherwise. For use with the ode15s, ode23t, and ode23tb solvers when MStateDependence is strong. See burgersode as an example.

MassSingular — Set this property to no if the mass matrix is not singular and you are using either the ode15s or ode23t solver. The default value of maybe causes the solver to test whether the problem is a DAE, by testing whether $M(t_0, y_0)$ is singular.

InitialSlope — Vector representing the consistent initial slope yp_0 , where yp_0 satisfies $M(t_0,y_0)\cdot y_0'=f(t_0,y_0)$. The default is the zero vector.

This property is for use with the ode15s and ode23t solvers when solving DAEs.

ode 15s and **Properties**

ode15s is a variable-order solver for stiff problems. It is based on the numerical differentiation formulas (NDFs). The NDFs are ode 15i-Specific generally more efficient than the closely related family of backward differentiation formulas (BDFs), also known as Gear's methods. The ode15s properties let vou choose among these formulas, as well as specifying the maximum order for the formula used.

ode15i solves fully implicit differential equations of the form

$$f(t, y, y') = 0$$

using the variable order BDF method.

The following table describes the ode15s and ode15i-specific properties. Further information on each property is given following the table. Use odeset to set these properties.

ode 15s and ode 15i-Specific Properties

Property	Value	Description
MaxOrder	1 2 3 4 {5}	Maximum order formula used to compute the solution.
BDF (ode15s only)	on {off}	Specifies whether you want to use the BDFs instead of the default NDFs.

Description of ode 15s and ode 15i-Specific Properties

MaxOrder — Maximum order formula used to compute the solution.

BDF (ode15s only) — Set BDF on to have ode15s use the BDFs.

For both the NDFs and BDFs, the formulas of orders 1 and 2 are A-stable (the stability region includes the entire left half complex plane). The higher order formulas are not as stable, and the higher the order the worse the stability. There is a class of stiff problems (stiff oscillatory) that is solved more efficiently if MaxOrder is reduced (for example to 2) so that only the most stable formulas are used.

See Also

deval, odeget, ode45, ode23, ode23t, ode23tb, ode113, ode15s, ode23s, function_handle (@)

Extend solution of initial value problem for ordinary differential equation

Syntax

```
solext = odextend(sol, odefun, tfinal)
solext = odextend(sol, [], tfinal)
solext = odextend(sol, odefun, tfinal, yinit)
solext = odextend(sol, odefun, tfinal, [yinit, ypinit])
solext = odextend(sol, odefun, tfinal, yinit, options)
```

Description

solext = odextend(sol, odefun, tfinal) extends the solution stored in sol to an interval with upper bound tfinal for the independent variable. odefun is a function handle. See "Function Handles" in the MATLAB Programming documentation for more information. sol is an ODE solution structure created using an ODE solver. The lower bound for the independent variable in solext is the same as in sol. If you created sol with an ODE solver other than ode15i, the function odefun computes the right-hand side of the ODE equation, which is of the form y' = f(t, y). If you created sol using ode15i, the function odefun computes the left-hand side of the ODE equation, which is of the form f(t, y, y') = 0.

"Parameterizing Functions", in the MATLAB Mathematics documentation, explains how to provide additional parameters to the function odefun, if necessary.

odextend extends the solution by integrating odefun from the upper bound for the independent variable in sol to tfinal, using the same ODE solver that created sol. By default, odextend uses

- The initial conditions y = sol.y(:, end) for the subsequent integration
- The same integration properties and additional input arguments the ODE solver originally used to compute sol. This information is stored as part of the solution structure sol and is subsequently passed to solext. Unless you want to change these values, you do not need to pass them to odextend.

solext = odextend(sol, [], tfinal) uses the same ODE function that the ODE solver uses to compute sol to extend the solution. It is not necessary to pass in odefun explicitly unless it differs from the original ODE function.

solext = odextend(sol, odefun, tfinal, yinit) uses the column
vector yinit as new initial conditions for the subsequent integration,
instead of the vector sol.y(end).

Note To extend solutions obtained with ode15i, use the following syntax, in which the column vector ypinit is the initial derivative of the solution:

```
solext = odextend(sol, odefun, tfinal, [yinit, ypinit])
```

solext = odextend(sol, odefun, tfinal, yinit, options) uses
the integration properties specified in options instead of the options
the ODE solver originally used to compute sol. The new options are
then stored within the structure solext. See odeset for details on
setting options properties. Set yinit = [] as a placeholder to specify
the default initial conditions.

Example

The following command

```
sol=ode45(@vdp1,[0 10],[2 0]);
```

uses ode45 to solve the system y' = vdp1(t,y), where vdp1 is an example of an ODE function provided with MATLAB software, on the interval [0 10]. Then, the commands

```
sol=odextend(sol,@vdp1,20);
plot(sol.x,sol.y(1,:));
```

extend the solution to the interval [0 20] and plot the first component of the solution on [0 20].

odextend

See Also

deval, ode23, ode45, ode113, ode15s, ode23s, ode23t, ode23tb, ode15i, odeset, odeget, deval, function_handle (@)

Cleanup tasks at function completion

Syntax

C = onCleanup(S)

Description

C = onCleanup(S) when called in function F, specifies any cleanup tasks that need to be performed when F completes. S is a handle to a function that performs necessary cleanup work when F exits. (For example, closing files that have been opened by F). S is called whether F exits normally or because of an error.

onCleanup is a MATLAB class and C = onCleanup(S) constructs an instance C of that class. Whenever an object of this class is explicitly or implicitly cleared from the workspace, it runs the cleanup function, S. Objects that are local variables in a function are implicitly cleared at the termination of that function.

Examples

Use onCleanup to close a file in the first example, and to restore the current folder in the second:

```
function fileOpenSafely(fileName)
  fid = fopen(fileName, 'w');
  c = onCleanup(@()fclose(fid));

functionThatMayError(fid);
end % c executes fclose(fid) here
```

MATLAB closes fid whether functionThatMayError returns an error or not.

```
function changeFolderSafely(fileName)
   currentFolder = pwd;
   c = onCleanup(@()cd(currentFolder));
   functionThatMayError;
end % c executes cd(currentFolder) here
```

onCleanup

The current folder is preserved whether functionThatMayError returns an error or not.

See Also clear, clearvars

Create array of all ones

Syntax

```
Y = ones(n)
Y = ones(m,n)
Y = ones([m n])
Y = ones([m n p ...])
Y = ones([m n p ...])
Y = ones(size(A))
ones(m, n,...,classname)
ones([m,n,...],classname)
```

Description

Y = ones(n) returns an n-by-n matrix of 1s. An error message appears if n is not a scalar.

```
Y = ones(m,n) \text{ or } Y = ones([m n]) \text{ returns an m-by-n matrix of ones.}
```

Y = ones(m,n,p,...) or Y = ones([m n p ...]) returns an m-by-n-by-p-by-... array of 1s.

Note The size inputs m, n, p, ... should be nonnegative integers. Negative integers are treated as 0.

Y = ones(size(A)) returns an array of 1s that is the same size as A.

ones(m, n,...,classname) or ones([m,n,...],classname) is an m-by-n-by-... array of ones of data type classname. classname is a string specifying the data type of the output. classname can have the following values: 'double', 'single', 'int8', 'uint8', 'int16', 'uint16', 'int32', 'uint32', 'int64', or 'uint64'.

Example

```
x = ones(2,3,'int8');
```

See Also

eye, zeros, complex

Open file in appropriate application

Syntax

open(*name*)

output = open(name)

Description

open(name) opens the specified file or variable in the appropriate application.

output = open(name) returns an empty output ([]) for most cases. If
opening a MAT-file, output is a structure that contains the variables in
the file. If opening a figure, output is a handle to that figure.

Tips

The open function opens files based on their extension. You can extend the functionality of open by defining your own file handling function of the form openxxx, where xxx is a file extension. For example, if you create a function openlog, the open function calls openlog to process any files with the .log extension. The open function returns any single output defined by your function.

Input Arguments

name

Name of file or variable to open. If *name* does not include an extension, the open function:

- 1 Searches for a variable named *name*. If the variable exists, open opens it in the MATLAB Variable Editor.
- 2 Searches the MATLAB path for name.mdl or name.m. If name.mdl exists, then open opens the model in Simulink. If only name.m exists, open opens the file in the MATLAB Editor.

If more than one file named name exists on the MATLAB path, the open function opens the file returned by which (name).

The open function performs the following actions based on the file extension:

(Continued)

. m	Open in MATLAB Editor.
.mat	Return variables in structure st when called with the syntax:
	st = open(name)
.fig	Open figure in Handle Graphics.
.mdl	Open model in Simulink.
.prj	Open project in the MATLAB Compiler Deployment Tool.
.doc*	Open document in Microsoft Word.
.exe	Run executable file (only on Windows systems).
.pdf	Open document in Adobe® Acrobat®.
.ppt*	Open document in Microsoft PowerPoint.
.xls*	Start MATLAB Import Wizard.
.htm or .html	Open document in MATLAB browser.
.url	Open file in your default Web browser.

Examples

Open Contents.m in the MATLAB Editor by typing:

open Contents.m

Generally, MATLAB opens matlabroot\toolbox\matlab\general\Contents.m. However, if you have a file called Contents.m in a directory that is before toolbox\matlab\general on the MATLAB path, then open opens that file instead. To change the path, select File > Set Path.

Open a file not on the MATLAB path by including the complete file specification:

```
open('D:\temp\data.mat')
```

If the file does not exist, MATLAB displays an error message.

Create a function called opentxt to handle files with extension .txt:

```
function opentxt(filename)
   fprintf('You have requested file: %s\n', filename);
   wh = which(filename);
   if exist(filename, 'file') == 2
     fprintf('Opening in MATLAB Editor: %s\n', filename);
     edit(filename);
   elseif ~isempty(wh)
     fprintf('Opening in MATLAB Editor: %s\n', wh);
     edit(wh);
   else
     warning('MATLAB:fileNotFound', ...
             'File was not found: %s', filename);
   end
end
```

Open the file ngc6543a.txt (a description of ngc6543a.jpg, located in matlabroot\toolbox\matlab\demos):

```
photo text = 'ngc6543a.txt';
open(photo text)
```

open calls your function with the following syntax:

```
opentxt(photo text)
```

See Also

edit | fileformats | load | openfig | openvar | path | uiopen | which | winopen

Open new copy or raise existing copy of saved figure

Syntax

```
openfig('filename.fig')
openfig('filename.fig','new')
openfig('filename.fig','reuse')
openfig('filename.fig','new','invisible')
openfig('filename.fig','reuse','invisible')
openfig('filename.fig','new','visible')
openfig('filename.fig','reuse','visible')
figure_handle = openfig(...)
```

Description

openfig('filename.fig') and openfig('filename.fig', 'new') opens the figure contained in the FIG-file, filename.fig, and ensures it is visible and positioned completely on screen. You do not have to specify the full path to the FIG-file as long as it is on your MATLAB path. The .fig extension is optional.

openfig('filename.fig','reuse') opens the figure contained in the FIG-file only if a copy of the figure is not currently open. Otherwise, openfig brings the existing copy forward, making sure it is still visible and completely on screen.

openfig('filename.fig','new','invisible') or openfig('filename.fig','reuse','invisible') opens the figure as in the preceding example, while forcing the figure to be invisible.

```
openfig('filename.fig','new','visible') or openfig('filename.fig','reuse','visible') opens the figure, while forcing the figure to be visible.
```

figure_handle = openfig(...) returns the handle to the figure.

Remarks

openfig is designed for use with GUI figures. Use this function to:

• Open the FIG-file creating the GUI and ensure it is displayed on screen. This provides compatibility with different screen sizes and resolutions.

- Control whether the MATLAB software displays one or multiple instances of the GUI at any given time.
- Return the handle of the figure created, which is typically hidden for GUI figures.

If the FIG-file contains an invisible figure, openfig returns its handle and leaves it invisible. The caller should make the figure visible when appropriate.

Do not use openfig or double-click a FIG-file to open a GUI created with GUIDE. Instead open the GUI code file by typing its name in the command window or by right-clicking its name in the Current Folder Browser and selecting **Run File**. To open a GUIDE GUI, for example one called guifile.m, in an invisible state, specify the Visible property in your command:

```
guifile('Visible','off')
```

Your code should then make the figure visible at an appropriate time.

See Also

quide, quihandles, movegui, open, hgload, save

See Deploying User Interfaces in the MATLAB documentation for related functions

Control OpenGL rendering

Syntax

```
opengl info
s = opengl('data')
opengl software
opengl hardware
opengl verbose
opengl quiet
opengl DriverBugWorkaround
opengl('DriverBugWorkaround', WorkaroundState)
```

Description

The OpenGL autoselection mode applies when the RendererMode of the figure is auto. Possible values for selection_mode are

- autoselect allows OpenGL to be automatically selected if OpenGL is available and if there is graphics hardware on the host machine.
- neverselect disables autoselection of OpenGL.
- advise prints a message to the command window if OpenGL rendering is advised, but RenderMode is set to manual.

opengl, by itself, returns the current autoselection state.

Note that the autoselection state only specifies whether OpenGL should or should not be considered for rendering; it does not explicitly set the rendering to OpenGL. You can do this by setting the Renderer property of the figure to OpenGL. For example,

```
set(figure handle, 'Renderer', 'OpenGL')
```

opengl info prints information with the version and vendor of the OpenGL on your system. Also indicates wether your system is currently using hardware of software OpenGL and the state of various driver bug workarounds. Note that calling opengl info loads the OpenGL Library.

For example, the following output is generated on a Windows XP computer that uses ATI Technologies graphics hardware:

```
>> opengl info
Version
                = 1.3.4010 WinXP Release
Vendor
                = ATI Technologies Inc.
Renderer
                = RADEON 9600SE \times86/SSE2
MaxTextureSize = 2048
Visual
                = 05 (RGB 16 bits(05 06 05 00) zdepth 16, Hardware
Accelerated, Opengl, Double Buffered, Window)
Software
                = false
# of Extensions = 85
Driver Bug Workarounds:
OpenGLBitmapZbufferBug
                           = 0
OpenGLWobbleTesselatorBug = 0
OpenGLLineSmoothingBug
                           = 0
OpenGLDockingBug
                           = 0
OpenGLClippedImageBug
                           = 0
```

Note that different computer systems may not list all OpenGL bugs.

s = opengl('data') returns a structure containing the same data that is displayed when you call opengl info, with the exception of the driver bug workaround state.

opengl software forces the MATLAB software to use software OpenGL rendering instead of hardware OpenGL. Note that Macintosh systems do not support software OpenGL.

opengl hardware reverses the opengl software command and enables MATLAB to use hardware OpenGL rendering if it is available. If your computer does not have OpenGL hardware acceleration, MATLAB automatically switches to software OpenGL rendering (except on Macintosh systems, which do not support software OpenGL).

Note that on UNIX systems, the software or hardware options with the opengl command works only if MATLAB has not yet used the OpenGL renderer or you have not issued the opengl info command (which attempts to load the OpenGL Library).

opengl verbose displays verbose messages about OpenGL initialization (if OpenGL is not already loaded) and other runtime messages.

opengl quiet disables verbose message setting.

opengl *DriverBugWorkaround* queries the state of the specified driver bug workaround. Use the command opengl info to see a list of all driver bug workarounds. See "Driver Bug Workarounds" on page 2-2850 for more information.

opengl('*DriverBugWorkaround*', WorkaroundState) sets the state of the specified driver bug workaround. You can set WorkaroundState to one of three values:

- 0 Disable the specified *DriverBugWorkaround* (if enabled) and do not allow MATLAB to autoselect this workaround.
- 1 Enable the specified *DriverBugWorkaround*.
- -1 Set the specified *DriverBugWorkaround* to autoselection mode, which allows MATLAB to enable this workaround if the requisite conditions exist.

Driver Bug Workgrounds

The MATLAB software enables various OpenGL driver bug workarounds when it detects certain known problems with installed hardware. However, because there are many versions of graphics drivers, you might encounter situations when MATLAB does not enable a workaround that would solve a problem you are having with OpenGL rendering.

This section describes the symptoms that each workaround is designed to correct so you can decide if you want to try using one to fix an OpenGL rendering problem.

Use the opengl info command to see what driver bug workarounds are available on your computer.

Note These workarounds have not been tested under all driver combinations and therefore might produce undesirable results under certain conditions.

OpenGLBitmapZbufferBug

Symptom: text with background color (including data tips) and text displayed on image, patch, or surface objects is not visible when using OpenGL renderer.

Possible side effect: text is always on top of other objects.

Command to enable:

```
opengl('OpenGLBitmapZbufferBug',1)
```

OpenGLWobbleTesselatorBug

Symptom: Rendering complex patch object causes segmentation violation and returns a tesselator error message in the stack trace.

Command to enable:

```
opengl('OpenGLWobbleTesselatorBug',1)
```

OpenGLLineSmoothingBug

Symptom: Lines with a LineWidth greater than 3 look bad.

Command to enable:

```
opengl('OpenGLLineSmoothingBug',1)
```

OpenGLDockingBug

Symptom: MATLAB crashes when you dock a figure that has its Renderer property set to opengl.

Command to enable:

```
opengl('OpenGLDockingBug',1)
```

OpenGLClippedImageBug

Symptom: Images (as well as colorbar displays) do not display when the Renderer property set to opengl.

Command to enable:

```
opengl('OpenGLClippedImageBug',1)
```

OpenGLEraseModeBug

Symptom: Graphics objects with EraseMode property set to non-normal erase modes (xor, none, or background) do not draw when the figure Renderer property is set to opengl.

Command to enable:

```
opengl('OpenGLEraseModeBug',1)
```

See Also

Figure Renderer property for information on autoselection.

Open workspace variable in Variable Editor or other graphical editing tool

GUI Alternatives

As an alternative to the openvar function, double-click a variable in the Workspace browser.

Syntax

openvar('varname')


Description

openvar('varname') opens the workspace variable varname in the Variable Editor for graphical editing, where name is a one- or two-dimensional array, character string, cell array, structure, or an object and its properties. You also can view the contents of a multidimensional array. Changes that you make to variables in the Variable Editor occur in the workspace as soon as you enter them.

You need to enclose the variable's name in single quotation marks because the Variable Editor needs to know the name of the variable to be notified if the variable changes value is deleted or goes out of scope. Typing openvar(varname) instead of openvar('varname'), passes the Variable Editor the value of varname instead of its name, and generally results in an error. However, openvar varname and openvar 'varname' both work, because string arguments are assumed when using *command syntax*. See "Command vs. Function Syntax" in the MATLAB Programming Fundamentals documentation for more information.

The MATLAB software does not impose any limitation on the size of a variable that you can open in the Variable Editor. Your operating system or the amount of physical memory installed on your computer can impose such limits, however.

In some toolboxes, openvar opens a tool appropriate for viewing or editing objects they define instead of opening the Variable Editor.



Select a tab to view a variable that you have open in the Variable Editor.

Data Brushing in the Variable Editor The Data Brushing tool and the brush function let you manually highlight portions of graphs in the figure. You can also connect the data within graphs of numeric variables to their data sources (using the Linked Plot tool in the figure window or the linkdata function).

When you link graphs to source data and view the source data in the Variable Editor, observations that you highlight on graphs in Data Brushing mode also appear highlighted in the Variable Editor. Likewise, cells that you select in the Variable editor with its Data Brushing Tool appear highlighted in all linked figures which graph the variable.

Example - Identifying Outliers in a Linked Graph

Data Brushing helps to identify unusual observations in a data set that might warrant further analysis, for example extreme values. To explore this capability, follow these steps:


1 Make a scatter plot of data in MAT-file count.dat, and open the variable count in the Variable Editor. For example:


```
load count.dat
scatter(count(:,1),count(:,2))
openvar('count')
```

- **2** Open the Variable Editor, turn on its Data Brushing mode, and select the three highest values (rows 7, 8, and 20). (You select noncontiguous rows by holding down the **Ctrl** key and clicking them.)
- 3 Turn on Data Brushing mode and Data Linking mode for the figure with the scatter plot, or type the following commands:

brush on linkdata on

The data observations you brushed in the Variable Editor appear highlighted in the scatter plot, as the following figure shows.





openvar

Now brush other observations in the scatter plot and notice how the Variable Editor highlights these values, as long as the figure is in data linking mode. When a figure is not linked to its data sources, you can still brush its graphs and you can brush the same data in the Variable Editor, but only the display that you brush responds by highlighting.

You can turn data brushing on and off and perform a number of operations on brushed data from the **Brushing** item on the **Edit** menu. The operations include removing and replacing brushed observations, copying them to the clipboard or Command Window, and creating a new variable containing them. A **Brushing** context menu item also provides these options.

See Also

brush, linkdata, load, save, workspace

"Viewing and Editing Workspace Variables with the Variable Editor" in the MATLAB Desktop Tools and Development Environment Documentation.

"Making Graphs Responsive with Data Linking" in the MATLAB Data Analysis documentation.

Optimization options values

Syntax

```
val = optimget(options, 'param')
```

val = optimget(options, 'param', default)

Description

val = optimget(options, 'param') returns the value of the specified parameter in the optimization options structure options. You need to type only enough leading characters to define the parameter name uniquely. Case is ignored for parameter names.

val = optimget(options, 'param', default) returns default if the specified parameter is not defined in the optimization options structure options. Note that this form of the function is used primarily by other optimization functions.

Examples

This statement returns the value of the Display optimization options parameter in the structure called my options.

```
val = optimget(my_options, 'Display')
```

This statement returns the value of the Display optimization options parameter in the structure called my_options (as in the previous example) except that if the Display parameter is not defined, it returns the value 'final'.

```
optnew = optimget(my options, 'Display', 'final');
```

See Also

optimset, fminbnd, fminsearch, fzero, lsqnonneg

Create or edit optimization options structure

Syntax

```
options = optimset('param1',value1,'param2',value2,...)
optimset
options = optimset
options = optimset(optimfun)
options = optimset(oldopts,'param1',value1,...)
options = optimset(oldopts,newopts)
```

Description

The function optimset creates an options structure that you can pass as an input argument to the following four MATLAB optimization functions:

- fminbnd
- fminsearch
- fzero
- 1sqnonneg

You can use the options structure to change the default parameters for these functions.

Note If you have purchased the Optimization Toolbox, you can also use optimset to create an expanded options structure containing additional options specifically designed for the functions provided in that toolbox. See the reference page for the enhanced optimset function in the Optimization Toolbox for more information about these additional options.

options = optimset('param1',value1,'param2',value2,...) creates an optimization options structure called options, in which the specified parameters (param) have specified values. Any unspecified parameters are set to [] (parameters with value [] indicate to use the default value for that parameter when options is passed to the

optimization function). It is sufficient to type only enough leading characters to define the parameter name uniquely. Case is ignored for parameter names.

optimset with no input or output arguments displays a complete list of parameters with their valid values.

options = optimset (with no input arguments) creates an options structure options where all fields are set to [].

options = optimset(optimfun) creates an options structure options with all parameter names and default values relevant to the optimization function optimfun.

options = optimset(oldopts, 'param1', value1,...) creates a copy of oldopts, modifying the specified parameters with the specified values.

options = optimset(oldopts,newopts) combines an existing options structure oldopts with a new options structure newopts. Any parameters in newopts with nonempty values overwrite the corresponding old parameters in oldopts.

Options

The following table lists the available options for the MATLAB optimization functions.

Option	Value	Description
Display	'off' 'iter' {'final'} 'notify'	Level of display. 'off' displays no output; 'iter' displays output at each iteration; 'final' displays just the final output; 'notify' displays output only if the function does not converge.
FunValCheck	{'off'} 'on'	Check whether objective function values are valid. 'on' displays an error

Option	Value	Description
		when the objective function returns a value that is complex or NaN. 'off' displays no error.
MaxFunEvals	positive integer	Maximum number of function evaluations allowed.
MaxIter	positive integer	Maximum number of iterations allowed.
OutputFcn	function {[]}	User-defined function that an optimization function calls at each iteration.
PlotFcns	function {[]}	User-defined plot function that an optimization function calls at each iteration.
TolFun	positive scalar	Termination tolerance on the function value.
TolX	positive scalar	Termination tolerance on x .

Examples

This statement creates an optimization options structure called options in which the Display parameter is set to 'iter' and the TolFun parameter is set to 1e-8.

```
options = optimset('Display','iter','TolFun',1e-8)
```

This statement makes a copy of the options structure called options, changing the value of the TolX parameter and storing new values in optnew.

```
optnew = optimset(options, 'TolX',1e-4);
```

This statement returns an optimization options structure that contains all the parameter names and default values relevant to the function fminbnd.

optimset('fminbnd')

See Also

optimset (Optimization Toolbox version), optimget, fminbnd, fminsearch, fzero, lsqnonneg

Find logical OR of array or scalar inputs

Syntax

A | B | ... or(A, B)

Description

A | B | ... performs a logical OR of all input arrays A, B, etc., and returns an array containing elements set to either logical 1 (true) or logical 0 (false). An element of the output array is set to 1 if any input arrays contain a nonzero element at that same array location. Otherwise, that element is set to 0.

Each input of the expression can be an array or can be a scalar value. All nonscalar input arrays must have equal dimensions. If one or more inputs are an array, then the output is an array of the same dimensions. If all inputs are scalar, then the output is scalar.

If the expression contains both scalar and nonscalar inputs, then each scalar input is treated as if it were an array having the same dimensions as the other input arrays. In other words, if input A is a 3-by-5 matrix and input B is the number 1, then B is treated as if it were a 3-by-5 matrix of ones.

or (A, B) is called for the syntax A | B when either A or B is an object.

Note The symbols | and | | perform different operations in a MATLAB application. The element-wise OR operator described here is |. The short-circuit OR operator is ||.

Example

If matrix A is

0.4235	0.5798	0	0.7942	0
0.5155	0	0	0	0.8744
0	0	0	0.4451	0.0150
0.4329	0.6405	0.6808	0	0

and matrix B is

0	1	0	1	0
1	1	0	0	1
0	0	0	1	0
0	1	0	0	1

then

See Also

 $\mbox{\sc bitor},$ and, $\mbox{\sc xor},$ not, any, all, logical operators, logical types, bitwise functions

Eigenvalues of quasitriangular matrices

Syntax

```
E = ordeig(T)
E = ordeig(AA,BB)
```

Description

E = ordeig(T) takes a quasitriangular Schur matrix T, typically produced by schur, and returns the vector E of eigenvalues in their order of appearance down the diagonal of T.

E = ordeig(AA,BB) takes a quasitriangular matrix pair AA and BB, typically produced by qz, and returns the generalized eigenvalues in their order of appearance down the diagonal of AA-o*BB.

ordeig is an order-preserving version of eig for use with ordschur and ordqz. It is also faster than eig for quasitriangular matrices.

Examples

Example 1

```
T=diag([1 -1 3 -5 2]);
```

ordeig(T) returns the eigenvalues of T in the same order they appear on the diagonal.

```
ordeig(T)

ans =

1
-1
3
-5
2
```

eig(T), on the other hand, returns the eigenvalues in order of increasing magnitude.

```
eig(T)
ans =
```

```
3
Example 2
  A = rand(10);
  [U, T] = schur(A);
  abs(ordeig(T))
  ans =
      5.3786
      0.7564
      0.7564
      0.7802
      0.7080
      0.7080
      0.5855
      0.5855
      0.1445
      0.0812
  % Move eigenvalues with magnitude < 0.5 to the
  % upper-left corner of T.
  [U,T] = ordschur(U,T,abs(E)<0.5);
  abs(ordeig(T))
  ans =
      0.1445
      0.0812
      5.3786
      0.7564
      0.7564
      0.7802
```

-5 -1 1 2

ordeig

0.7080

0.7080

0.5855

0.5855

See Also

schur, qz, ordschur, ordqz, eig

Order fields of structure array

Syntax

```
s = orderfields(s1)
s = orderfields(s1, s2)
s = orderfields(s1, c)
s = orderfields(s1, perm)
[s, perm] = orderfields(...)
```

Description

- s = orderfields(s1) orders the fields in s1 so that the new structure array s has field names in ASCII dictionary order.
- s = orderfields(s1, s2) orders the fields in s1 so that the new structure array s has field names in the same order as those in s2. Structures s1 and s2 must have the same fields.
- s = orderfields(s1, c) orders the fields in s1 so that the new structure array s has field names in the same order as those in the cell array of field name strings c. Structure s1 and cell array c must contain the same field names.
- s = orderfields(s1, perm) orders the fields in s1 so that the new structure array s has fieldnames in the order specified by the indices in permutation vector perm.

If s1 has N fieldnames, the elements of perm must be an arrangement of the numbers from 1 to N. This is particularly useful if you have more than one structure array that you would like to reorder in the same way.

[s, perm] = orderfields(...) returns a permutation vector representing the change in order performed on the fields of the structure array that results in s.

Remarks

orderfields only orders top-level fields. It is not recursive.

Examples

Create a structure s. Then create a new structure from s, but with the fields ordered alphabetically:

```
s = struct('b', 2, 'c', 3, 'a', 1)
s =
```

```
b: 2
    c: 3
    a: 1

snew = orderfields(s)
snew =
    a: 1
    b: 2
    c: 3
```

Arrange the fields of s in the order specified by the second (cell array) argument of orderfields. Return the new structure in snew and the permutation vector used to create it in perm:

```
[snew, perm] = orderfields(s, {'b', 'a', 'c'})
snew =
    b: 2
    a: 1
    c: 3
perm =
    1
    3
    2
```

Now create a new structure, s2, having the same fieldnames as s. Reorder the fields using the permutation vector returned in the previous operation:

```
s2 = struct('b', 3, 'c', 7, 'a', 4)
s2 =
    b: 3
    c: 7
    a: 4

snew = orderfields(s2, perm)
snew =
    b: 3
    a: 4
```

c: 7

See Also

struct, fieldnames, setfield, getfield, isfield, rmfield, dynamic field names $\,$

Reorder eigenvalues in QZ factorization

Syntax

```
[AAS,BBS,QS,ZS] = ordqz(AA,BB,Q,Z,select)
[...] = ordqz(AA,BB,Q,Z,keyword)
[...] = ordqz(AA,BB,Q,Z,clusters)
```

Description

[AAS,BBS,QS,ZS] = ordqz(AA,BB,Q,Z,select) reorders the QZ factorizations Q*A*Z = AA and Q*B*Z = BB produced by the qz function for a matrix pair (A,B). It returns the reordered pair (AAS,BBS) and the cumulative orthogonal transformations QS and ZS such that QS*A*ZS = AAS and QS*B*ZS = BBS. In this reordering, the selected cluster of eigenvalues appears in the leading (upper left) diagonal blocks of the quasitriangular pair (AAS,BBS), and the corresponding invariant subspace is spanned by the leading columns of ZS. The logical vector select specifies the selected cluster as E(select) where E is the vector of eigenvalues as they appear along the diagonal of AA-2*BB.

Note To extract E from AA and BB, use ordeig(BB), instead of eig. This ensures that the eigenvalues in E occur in the same order as they appear on the diagonal of AA-9*BB.

[...] = ordqz(AA,BB,Q,Z,keyword) sets the selected cluster to include all eigenvalues in the region specified by keyword:

keyword	Selected Region
'lhp'	Left-half plane (real(E) < 0)
'rhp'	Right-half plane (real(E) > 0)
'udi'	Interior of unit disk (abs(E) < 1)
'udo'	Exterior of unit disk (abs(E) > 1)

[...] = ordqz(AA,BB,Q,Z,clusters) reorders multiple clusters at once. Given a vector clusters of cluster indices commensurate with E = ordeig(AA,BB), such that all eigenvalues with the same clusters

value form one cluster, ordqz sorts the specified clusters in descending order along the diagonal of (AAS,BBS). The cluster with highest index appears in the upper left corner.

Algorithm

For full matrices AA and BB, ${\tt qz}$ uses the LAPACK routines listed in the following table.

	AA and BB Real	AA or BB Complex
A and B double	DTGSEN	ZTGSEN
A or B single	STGSEN	CTGSEN

See Also

ordeig, ordschur, qz

Purpose

Reorder eigenvalues in Schur factorization

Syntax

[US,TS] = ordschur(U,T,select)
[US,TS] = ordschur(U,T,keyword)
[US,TS] = ordschur(U,T,clusters)

Description

[US,TS] = ordschur(U,T,select) reorders the Schur factorization X = U*T*U' produced by the schur function and returns the reordered Schur matrix TS and the cumulative orthogonal transformation US such that X = US*TS*US'. In this reordering, the selected cluster of eigenvalues appears in the leading (upper left) diagonal blocks of the quasitriangular Schur matrix TS, and the corresponding invariant subspace is spanned by the leading columns of US. The logical vector select specifies the selected cluster as E(select) where E is the vector of eigenvalues as they appear along T's diagonal.

Note To extract E from T, use E = ordeig(T), instead of eig. This ensures that the eigenvalues in E occur in the same order as they appear on the diagonal of TS.

[US,TS] = ordschur(U,T,keyword) sets the selected cluster to include all eigenvalues in one of the following regions:

keyword	Selected Region
'lhp'	Left-half plane (real(E) < 0)
'rhp'	Right-half plane (real(E) > 0)
'udi'	Interior of unit disk (abs(E) < 1)
'udo'	Exterior of unit disk (abs(E) > 1)

[US,TS] = ordschur(U,T,clusters) reorders multiple clusters
at once. Given a vector clusters of cluster indices, commensurate
with E = ordeig(T), and such that all eigenvalues with the same
clusters value form one cluster, ordschur sorts the specified clusters

in descending order along the diagonal of TS, the cluster with highest index appearing in the upper left corner.

Algorithm

Input of Type Double

If U and T have type double, ordschur uses the LAPACK routines listed in the following table to compute the Schur form of a matrix:

Matrix Type	Routine
Real	DTRSEN
Complex	ZTRSEN

Input of Type Single

If U and T have type single, ordschur uses the LAPACK routines listed in the following table to reorder the Schur form of a matrix:

Matrix Type	Routine
Real	STRSEN
Complex	CTRSEN

See Also

ordeig, ordqz, schur

Purpose

Hardcopy paper orientation

GUI Alternative

Use **File** —> **Print Preview** on the figure window menu to directly manipulate print layout, paper size, headers, fonts and other properties when printing figures. For details, see Using Print Preview in the MATLAB Graphics documentation.

Syntax

orient

orient landscape orient portrait orient tall

orient(fig_handle), orient(simulink_model)

orient(fig_handle,orientation), orient(simulink_model,

orientation)

Description

orient returns a string with the current paper orientation: portrait, landscape, or tall.

orient landscape sets the paper orientation of the current figure to full-page landscape, orienting the longest page dimension horizontally. The figure is centered on the page and scaled to fit the page with a 0.25 inch border.

orient portrait sets the paper orientation of the current figure to portrait, orienting the longest page dimension vertically. The portrait option returns the page orientation to the MATLAB default. (Note that the result of using the portrait option is affected by changes you make to figure properties. See the "Algorithm" section for more specific information.)

orient tall maps the current figure to the entire page in portrait orientation, leaving a 0.25 inch border.

orient(fig_handle), orient(simulink_model) returns the current orientation of the specified figure or Simulink model.

orient(fig_handle,orientation),
orient(simulink_model,orientation) sets the orientation for

the specified figure or Simulink model to the specified orientation (landscape, portrait, or tall).

Algorithm

orient sets the PaperOrientation, PaperPosition, and PaperUnits properties of the current figure. Subsequent print operations use these properties. The result of using the portrait option can be affected by default property values as follows:

- If the current figure PaperType is the same as the default figure PaperType and the default figure PaperOrientation has been set to landscape, then the orient portrait command uses the current values of PaperOrientation and PaperPosition to place the figure on the page.
- If the current figure PaperType is the same as the default figure PaperType and the default figure PaperOrientation has been set to landscape, then the orient portrait command uses the default figure PaperPosition with the x, y and width, height values reversed (i.e., [y,x,height,width]) to position the figure on the page.
- If the current figure PaperType is different from the default figure PaperType, then the orient portrait command uses the current figure PaperPosition with the x, y and width, height values reversed (i.e., [y,x,height,width]) to position the figure on the page.

See Also

print, printpreview, set

PaperOrientation, PaperPosition, PaperSize, PaperType, and PaperUnits properties of figure graphics objects

"Printing" on page 1-102 for related functions

orth

Purpose Range space of matrix

Syntax B = orth(A)

Description B = orth(A) returns an orthonormal basis for the range of A. The

columns of B span the same space as the columns of A, and the columns of B are orthogonal, so that B'*B = eye(rank(A)). The number of

columns of B is the rank of A.

See Also null, svd, rank

Purpose

Default part of switch statement

Syntax

```
switch switch_expr
case case_expr
statement, ..., statement
case {case_expr1, case_expr2, case_expr3, ...}
statement, ..., statement
otherwise
statement, ..., statement
end
```

Description

otherwise is part of the switch statement syntax, which allows for conditional execution. The statements following otherwise are executed only if none of the preceding case expressions (case_expr) matches the switch expression (sw expr).

Examples

The general form of the switch statement is

```
switch sw_expr
    case case_expr
        statement
        statement
    case {case_expr1,case_expr2,case_expr3}
        statement
        statement
        otherwise
            statement
            statement
            statement
            statement
            statement
            statement
            statement
            statement
```

See switch for more details.

See Also

switch, case, end, if, else, elseif, while

Symbols and Numerics	acot 2-86
, 2-44	acotd 2-88
& 2-56 2-63	acoth 2-89
* 2-44	acsc 2-91
+ 2-44	acscd 2-93
- 2-44	acsch 2-94
/ 2-44	activelegend 2-3028
: 2-70	actxcontrol 2-96
< 2-54	actxserver 2-107
> 2-54	Adams-Bashforth-Moulton ODE solver 2-2809
@ 2-1618	addCause, MException method 2-111
\ 2-44	addevent 2-114
^ 2-44	addframe
2-56 2-63	AVI files 2-116
~ 2-56 2-63	addition (arithmetic operator) 2-44
&& 2-63	addlistener 2-118
== 2.54	addOptional method
1) 2-68	of inputParser object 2-120
2-63	addParamValue method
~= 2-54	of inputParser object 2-123
1-norm 2-2769 2-3238	addpath $2 ext{-} 126$
2-norm (estimate of) 2-2771	addpref function 2-128
	addprop dynamicprops $\operatorname{method}\ 2 ext{-}129$
A	addRequired method
A	of inputParser object 2-132
abs 2-73	addressing selected array elements 2-70
absolute accuracy	addsample 2-135
BVP 2-473	addsampletocollection 2-137
DDE 2-1083	addtodate 2-139
ODE 2-2820	addts $2\text{-}141$
absolute value 2-73	adjacency graph 2-1189
Accelerator	airy $2-143$
Uimenu property 2-4164	Airy functions
accumarray 2-74	relationship to modified Bessel
accuracy	functions 2-143
of linear equation solution 2-869	align function 2-145
of matrix inversion 2-869	aligning scattered data
acos 2-81	multi-dimensional 2-2682
acosd 2-83	ALim, Axes property 2-293
acosh 2-84	all $2-151$

allchild function 2-153	stairseries property 2-3626
allocation of storage (automatic) 2-4520	stemseries property 2-3660
AlphaData	Surface property 2-3818
image property 2-1959	surfaceplot property 2-3840
surface property 2-3816	text property 2-3923
surfaceplot property 2-3839	annotation function 2-169
AlphaDataMapping	ans 2-211
image property 2-1960	anti-diagonal 2-1811
patch property 2-2921	any $2\text{-}212$
surface property 2-3817	arccosecant 2-91
surfaceplot property 2-3839	arccosine 2-81
AmbientLightColor, Axes property 2-294	arccotangent 2-86
AmbientStrength	arcsecant 2-244
Patch property 2-2922	arctangent 2-259
Surface property 2-3817	four-quadrant 2-261
surfaceplot property 2-3840	arguments
amd 2-161	checking number of inputs 2-2673
analytical partial derivatives (BVP) 2-474	checking number of outputs 2-2677
analyzer	number of output 2-2675
code 2-2604	passing variable numbers of 2-4362
and 2-166	arguments, function
and (function equivalent for &) 2-60	number of input 2-2675
AND, logical	arithmetic operations, matrix and array
bit-wise 2-419	distinguished 2-44
angle 2-168	arithmetic operators
annotating graphs	reference 2-44
in plot edit mode 2-3029	array
Annotation	addressing selected elements of 2-70
areaseries property 2-221	dimension
contourgroup property 2-894	rearrange 2-1527
errorbarseries property 2-1263	displaying 2-1166
hggroup property 2-1864	flip dimension of 2-1527
hgtransform property 2-1893	left division (arithmetic operator) 2-46
image property 2-1960	maximum elements of 2-2491
line property 2-352 2-2313	mean elements of 2-2497
lineseries property 2-2328	median elements of 2-2500
Patch property 2-2922	minimum elements of 2-2576
quivergroup property 2-3186	multiplication (arithmetic operator) 2-45
rectangle property 2-3264	of all ones 2-2841
scattergroup property 2-3429	of all zeros 2-4519

power (arithmetic operator) 2-46	assert 2-255
product of elements 2-3103	assignin $2\text{-}257$
rearrange	$atan^{-2}.259$
dimension 2-1527	atan2 2-261
removing first n singleton dimensions	atand $2\text{-}263$
of 2-3513	atanh $2\text{-}264$
removing singleton dimensions of 2-3613	.au files
reshaping 2-3339	reading 2-279
reverse dimension of 2-1527	writing 2-281
right division (arithmetic operator) 2-45	audio
shift circularly 2-774	saving in AVI format 2-282
shifting dimensions of 2-3513	signal conversion 2-2306 2-2656
size of 2-3527	audiodevinfo 2-266
sorting elements of 2-3548	audioplayer 2-268
structure 2-1724 2-3368 2-3496	audiorecorder 2-273
sum of elements 2-3795	aufinfo 2-278
swapping dimensions of 2-2117 2-2995	auread 2-279
transpose (arithmetic operator) 2-46	AutoScale
arrayfun 2-237	quivergroup property 2-3187
arrays	AutoScaleFactor
detecting empty 2-2133	quivergroup property 2-3187
maximum size of 2-867	autoselection of OpenGL 2-1441
arrays, structure	auwrite 2-281
field names of 2-1403	average of array elements 2-2497
arrowhead matrix 2-850	average,running 2-1490
ASCII	avi 2-282
delimited files	avifile 2-282
writing 2-1184	aviinfo 2-285
ASCII data	aviread 2-287
converting sparse matrix after loading	axes 2-288
from 2-3562	editing 2-3029
reading 2-1180	setting and querying data aspect ratio 2-998
reading from disk 2-2379	setting and querying limits 2-4490
saving to disk 2-3404	setting and querying plot box aspect
ascii function 2-243	ratio 2-2957
asec 2-244	Axes
asecd 2-246	creating 2-288
asech 2-247	defining default properties 2-289
$\operatorname{asinh}\ 2\text{-}253$	fixed-width font 2-310
aspect ratio of axes 2-998 2-2957	property descriptions 2-293

axis 2-331	contour property 2-895
axis crossing. See zero of a function	errorbar property 2-1264
azimuth (spherical coordinates) 2-3578	group property 2-1408 2-1961 2-3926
azimuth of viewpoint 2-4381	hggroup property 2-1865
	hgtransform property 2-1894
В	light property 2-2296
	line property 2-2314
BackFaceLighting	lineseries property 2-2329
Surface property 2-3819	quivergroup property 2-3187
surfaceplot property 2-3842	rectangle property 2-3265
BackFaceLightingpatch property 2-2924	scatter property 2-3430
BackgroundColor	stairseries property 2-3627
annotation textbox property 2-201	stem property 2-3661
Text property 2-3924	surface property 2-3819
Uitable property 2-4241	surfaceplot property 2-3842
BackGroundColor	transform property 2-2924
Uicontrol property 2-4116	Uipushtool property 2-4203
badly conditioned 2-3238	Uitable property 2-4242
balance 2-337	Uitoggletool property 2-4272
BarLayout	Uitoolbar property 2-4285
barseries property 2-353	bench 2-374
BarWidth	benchmark 2-374
barseries property 2-353	Bessel functions
base to decimal conversion 2-372	first kind 2-383
base two operations	modified, first kind 2-380
conversion from decimal to binary 2-1097	modified, second kind 2-386
logarithm 2-2400	second kind 2-389
next power of two 2-2765	Bessel functions, modified
base2dec 2-372	relationship to Airy functions 2-143
BaseLine	besseli 2-380
barseries property 2-353	besselj 2-383
stem property 2-3661	besselk 2-386
BaseValue	Bessel's equation
areaseries property 2-222	(defined) 2-383
barseries property 2-354	modified (defined) 2-380
stem property 2-3661	bessely 2-389
beep 2-373	beta 2-392
BeingDeleted	beta function
areaseries property 2-222	(defined) 2-392
barseries property 2-354	incomplete (defined) 2-394

natural logarithm 2-397	bold font
betainc 2-394	TeX characters 2-3949
betaln 2-397	boundary value problems 2-479
bicg 2-398	box 2-433
bicgstab 2-407	Box, Axes property 2-295
bicgstabl 2-413	braces, curly (special characters) 2-66
BiConjugate Gradients method 2-398	brackets (special characters) 2-66
BiConjugate Gradients Stabilized method 2-407	break $2-434$
2-413	breakpoints
bin2dec 2-416	listing 2-1054
binary data	removing 2-1040
reading from disk 2-2379	resuming execution from 2-1043
saving to disk 2-3404	setting in code files 2-1058
binary function 2-417	browser
binary to decimal conversion 2-416	for help 2-1850
bisection search 2-1642	brush $2\text{-}437$
bit depth	bsxfun $2\text{-}447$
querying 2-1983	bubble plot (scatter function) 2-3424
bit-wise operations	Buckminster Fuller 2-3893
AND 2-419	builtin $2\text{-}450$
get 2-422	BusyAction
OR 2-426	areaseries property 2-222
set bit 2-427	Axes property 2-295
shift 2-428	barseries property 2-354
XOR 2-430	contour property 2-895
bitand 2-419	errorbar property 2-1265
$\texttt{bitcmp}\ 2\text{-}420$	Figure property 2-1409
bitget 2-422	hggroup property 2-1866
bitmaps	hgtransform property 2-1895
writing 2-2012	Image property 2-1962
$\texttt{bitmax}\ 2\text{-}424$	Light property 2-2297
bitor 2-426	line property 2-2315
bitset 2-427	Line property 2-2329
bitshift $2-428$	patch property 2-2925
bitxor 2-430	quivergroup property 2-3188
blanks 2-431	rectangle property 2-3266
removing trailing 2-1094	Root property 2-3372
blkdiag 2-432	scatter property 2-3431
BMP files	stairseries property 2-3628
writing 2-2012	stem property 2-3662

Surface property 2-3819	singular BVPs 2-476
surfaceplot property 2-3842	solution statistics 2-477
Text property 2-3926	vectorization 2-473
Uicontextmenu property 2-4101	bvp4c 2-451
Uicontrol property 2-4117	bvp5c 2-462
Uimenu property 2-4165	bypget 2-467
Uipushtool property 2-4204	bvpinit 2-468
Uitable property 2-4242	bypset 2-471
Uitoggletool property 2-4273	bvpxtend 2-479
Uitoolbar property 2-4285	
ButtonDownFcn	C
area series property 2-223	
Axes property 2-296	calendar $2\text{-}480$
barseries property 2-355	call history 2-3110
contour property 2-896	CallBack
errorbar property 2-1265	Uicontextmenu property 2-4102
Figure property 2-1409	Uicontrol property 2-4119
hggroup property 2-1866	Uimenu property 2-4166
hgtransform property 2-1895	CallbackObject, Root property 2-3372
Image property 2-1962	calllib 2-481
Light property 2-2297	callSoapService 2-483
Line property 2-2315	camdolly 2-485
lineseries property 2-2330	camera
patch property 2-2925	dollying position 2-485
quivergroup property 2-3188	moving camera and target postions 2-485
rectangle property 2-3266	positioning to view objects 2-491
Root property 2-3372	rotating around camera target 2-493 2-495
scatter property 2-3431	rotating around viewing axis 2-501
stairseries property 2-3628	setting and querying position 2-497
stem property 2-3662	setting and querying projection type 2-499
Surface property 2-3820	setting and querying target 2-502
surfaceplot property 2-3843	setting and querying up vector 2-504
Text property 2-3927	setting and querying view angle 2-506
Uicontrol property 2-4118	CameraPosition, Axes property 2-297
Uitable property 2-4243	CameraPositionMode, Axes property 2-298
BVP solver properties	CameraTarget, Axes property 2-298
analytical partial derivatives 2-474	CameraTargetMode, Axes property 2-298
error tolerance 2-472	CameraUpVector, Axes property 2-298
Jacobian matrix 2-474	CameraUpVectorMode, Axes property 2-299
mesh 2-476	CameraViewAngle, Axes property 2-299

CameraViewAngleMode, Axes property 2-299	CDatapatch property 2-2926
camlookat 2-491	CDataSource
camorbit $2-493$	scatter property 2-3432
campan 2-495	surfaceplot property 2-3845
campos 2-497	cdf2rdf 2-535
camproj 2-499	cdfepoch 2-537
camroll 2-501	cdfinfo 2-539
camtarget 2-502	cdflib
$\mathtt{camup}\ 2\text{-}504$	summary of capabilities 2-543
camva 2-506	cdfread $2\text{-}715$
camzoom 2-508	cdfwrite 2-719
cart2pol 2-512	ceil 2-722
cart2sph 2-514	cell 2-723
Cartesian coordinates 2-512 2-514 2-3041 2-3578	cell array
case 2-515	conversion to from numeric array 2-2779
in switch statement (defined) 2-3880	creating 2-723
lower to upper 2-4325	structure of, displaying 2-743
upper to lower 2-2412	cell2mat 2-725
cast 2-517	cell2struct 2-727
cat 2-518	celldisp 2-736
catch 2-520	CellEditCallback
caxis 2-524	Uitable property 2-4244
Cayley-Hamilton theorem 2-3061	cellfun $2\text{-}737$
cd 2-529	cellplot 2-743
cd (ftp) function 2-534	CellSelectionCallback
CData	Uitable property 2-4246
Image property 2-1963	cgs 2-746
scatter property 2-3432	char 2-751
Surface property 2-3821	characters
surfaceplot property 2-3844	conversion, in serial format specification
Uicontrol property 2-4119	string 2-1575
Uipushtool property 2-4204	check boxes 2-4109
Uitoggletool property 2-4273	Checked, Uimenu property 2-4166
CDataMapping	checkerboard pattern (example) 2-3328
Image property 2-1965	checkin $2 ext{-} 752$
patch property 2-2927	examples 2-753
Surface property 2-3822	options 2-752
surfaceplot property 2-3844	checkout 2-755
CDataMode	examples 2-756
surfaceplot property 2-3845	options 2-755

child functions 2-3105	cla 2-778
Children	clabel 2-779
areaseries property 2-224	class, object. See object classes
Axes property 2-301	classes
barseries property 2-356	field names 2-1403
contour property 2-896	loaded 2-2044
errorbar property 2-1266	clc 2-789 2-799 2-3512
Figure property 2-1411	clear
hggroup property 2-1867	serial port I/O 2-798
hgtransform property 2-1896	clearing
Image property 2-1966	Command Window 2-789
Light property 2-2297	items from workspace 2-790
Line property 2-2316	Java import list 2-793
lineseries property 2-2330	clf 2-799
patch property 2-2928	ClickedCallback
quivergroup property 2-3189	Uipushtool property 2-4205
rectangle property 2-3267	Uitoggletool property 2-4274
Root property 2-3372	CLim, Axes property 2-301
scatter property 2-3433	CLimMode, Axes property 2-302
stairseries property 2-3629	clipboard 2-800
stem property 2-3663	Clipping
Surface property 2-3822	areaseries property 2-224
surfaceplot property 2-3846	Axes property 2-302
Text property 2-3928	barseries property 2-356
Uicontextmenu property 2-4102	contour property 2-897
Uicontrol property 2-4120	errrobar property 2-1266
Uimenu property 2-4167	Figure property 2-1411
Uitable property 2-4246	hggroup property 2-1867
Uitoolbar property 2-4286	hgtransform property 2-1896
chol 2-758	Image property 2-1966
Cholesky factorization 2-758	Light property 2-2297
(as algorithm for solving linear	Line property 2-2317
equations) 2-2600	lineseries property 2-2331
lower triangular factor 2-2900	quivergroup property 2-3189
preordering for 2-850	rectangle property 2-3267
cholinc 2-763	Root property 2-3373
cholupdate 2-771	scatter property 2-3433
circle	stairseries property 2-3629
rectangle function 2-3259	stem property 2-3663
circshift 2-774	Surface property 2-3823

surfaceplot property 2-3846	quivergroup property 2-3190
Text property 2-3928	stairseries property 2-3630
Uicontrol property 2-4120	stem property 2-3664
Uitable property 2-4246	Text property 2-3928
Clippingpatch property 2-2928	textarrow property 2-191
clock 2-801	color approximation
close 2-802	performed by rgb2ind 2-3356
AVI files 2-805	color of fonts, see also FontColor property 2-3949
close (ftp) function 2-806	colorbar 2-818
CloseRequestFcn, Figure property 2-1411	colormap $2\text{-}825$
closest point search 2-1205	editor 2-830
closest triangle search 2-4062	Colormap, Figure property 2-1414
closing	colormaps
MATLAB 2-3177	converting from RGB to HSV 2-3354
cmapeditor 2-830	plotting RGB components 2-3358
cmpermute 2-810	rearranging colors in 2-810
cmunique 2-811	removing duplicate entries in 2-811
code	ColorOrder, Axes property 2-302
analyzer 2-2604	ColorSpec 2-848
Code Analyzer	colperm 2-850
function 2-2604	ColumnEditable
function for entire folder 2-2614	Uitable property 2-4247
HTML report 2-2614	ColumnFormat
code files	Uitable property 2-4247
setting breakpoints 2-1058	ColumnName
colamd 2-814	Uitable property 2-4253
colon operator 2-70	ColumnWidth
color	Uitable property 2-4253
quantization performed by rgb2ind 2-3356	COM
Color	object methods
annotation arrow property 2-173	actxcontrol 2-96
annotation doublearrow property 2-177	actxserver 2-107
annotation line property 2-185	delete $2\text{-}1125$
annotation textbox property 2-201	events $2 ext{-} 1302$
Axes property 2-302	get 2-1696
errorbar property 2-1266	inspect 2-2060
Figure property 2-1414	load 2-2384
Light property 2-2297	move 2-2633
Line property 2-2317	propedit $2\text{-}3114$
lineseries property 2-2331	save 2-3411

$set\ 2\text{-}3475$	phase angle 2-168
server methods	See also imaginary
Execute 2-1304	complex conjugate 2-879
Feval 2-1374	sorting pairs of 2-954
combinations of n elements 2-2681	complex data
combs 2-2681	creating 2-862
comet 2-852	complex numbers, magnitude 2-73
comet3 2-854	complex Schur form 2-3448
comma (special characters) 2-67	compression
command syntax 2-3898	lossy 2-2017
Command Window	computer 2-867
clearing 2-789	computer MATLAB is running on 2-867
cursor position 2-1916	concatenation
get width 2-857	of arrays 2-518
commandhistory 2-856	cond 2-869
commands	condeig 2-870
help for 2-1846 2-1854	condest 2-871
system 2-3901	condition number of matrix 2-869 2-3238
UNIX 2-4301	improving 2-337
commandwindow 2-857	coneplot 2-873
comments	conj $2 ext{-}879$
block of 2-68	conjugate, complex 2-879
common elements. See set operations,	sorting pairs of 2-954
intersection	connecting to FTP server 2-1608
compan 2-858	containers
companion matrix 2-858	Map 2-2157 2-2237 2-2277 2-2450 2-3323
compass 2-859	$2 - 3530 \ 2 - 4355$
CompilerConfiguration 2-2561	context menu 2-4097
CompilerConfigurationDetails 2-2561	continuation (, special characters) 2-67
complementary error function	continue 2-880
(defined) 2-1252	continued fraction expansion 2-3232
scaled (defined) 2-1252	contour
complete elliptic integral	and mesh plot 2-1332
(defined) 2-1233	filled plot 2-1324
modulus of 2-1231 2-1233	functions 2-1320
complex $2-862$ $2-1950$	of mathematical expression 2-1321
exponential (defined) 2-1312	with surface plot 2-1353
logarithm 2-2397 to 2-2398	contour3 2-885
numbers 2-1925	contourc 2-889
numbers, sorting 2-3548 2-3552	contourf 2-891

ContourMatrix	multidimensional vizualization 2-930
contour property 2-897	two-dimensional visualization 2-928
contours	convhull 2-928
in slice planes 2-915	convhulln 2-930
contourslice 2-915	convn 2-932
contrast 2-919	convolution 2-920
conv 2-920	inverse. See deconvolution
conv2 2-922	two-dimensional 2-922
conversion	coordinate system and viewpoint 2-4382
base to decimal 2-372	coordinates
binary to decimal 2-416	Cartesian 2-512 2-514 2-3041 2-3578
Cartesian to cylindrical 2-512	cylindrical 2-512 2-514 2-3041
Cartesian to polar 2-512	polar 2-512 2-514 2-3041
complex diagonal to real block diagonal 2-535	spherical 2-3578
cylindrical to Cartesian 2-3041	coordinates. 2-512
decimal number to base 2-1091 2-1096	See also conversion
decimal to binary 2-1097	copyfile $2-933$
decimal to hexadecimal 2-1098	copying
full to sparse 2-3559	files and folders 2-933
hexadecimal to decimal 2-1858	copyobj $2-937$
integer to string 2-2074	corrcoef 2-939
lowercase to uppercase 2-4325	cosecant
matrix to string 2-2461	hyperbolic 2-970
numeric array to cell array 2-2779	inverse 2-91
numeric array to logical array 2-2401	inverse hyperbolic 2-94
numeric array to string 2-2783	$\cosh\ 2\text{-}945$
partial fraction expansion to	cosine
pole-residue 2-3341	hyperbolic 2-945
polar to Cartesian 2-3041	inverse 2-81
pole-residue to partial fraction	inverse hyperbolic 2-84
expansion 2-3341	cot 2-947
real to complex Schur form 2-3401	cotangent 2-947
spherical to Cartesian 2-3578	hyperbolic 2-950
string matrix to cell array 2-745	inverse 2-86
string to numeric array 2-3687	inverse hyperbolic 2-89
uppercase to lowercase 2-2412	$\verb"cotd" 2-949"$
vector to character string 2-751	$\verb"coth" 2-950"$
conversion characters in serial format	cov 2-952
specification string 2-1575	cplxpair $2 ext{-} 954$
convex hulls	cputime 2-955

create, RandStream method 2-956	csch 2-970
createCopy method	csvread 2-972
of inputParser object 2-960	csvwrite $2\text{-}975$
CreateFcn	ctranspose (function equivalent for \q) 2-50
areaseries property 2-224	ctranspose (timeseries) 2-977
Axes property 2-303	cubic interpolation 2-2090 2-2093 2-2096 2-2967
barseries property 2-356	piecewise Hermite 2-2080
contour property 2-898	cubic spline interpolation
errorbar property 2-1267	one-dimensional 2-2080 2-2090 2-2093
Figure property 2-1414	2-2096
group property 2-1896	cumprod 2-979
hggroup property 2-1867	cumsum 2-981
Image property 2-1966	cumtrapz 2-983
Light property 2-2298	cumulative
Line property 2-2317	product 2-979
lineseries property 2-2331	sum 2-981
patch property 2-2928	curl 2-985
quivergroup property 2-3190	curly braces (special characters) 2-66
rectangle property 2-3268	current folder 2-529
Root property 2-3373	changing 2-529
scatter property 2-3433	See also search path
stairseries property 2-3630	CurrentAxes 2-1415
stemseries property 2-3664	CurrentAxes, Figure property 2-1415
Surface property 2-3823	CurrentCharacter, Figure property 2-1416
surfaceplot property 2-3846	CurrentFigure, Root property 2-3373
Text property 2-3928	CurrentObject, Figure property 2-1416
Uicontextmenu property 2-4102	CurrentPoint
Uicontrol property 2-4120	Axes property 2-304
Uimenu property 2-4167	Figure property 2-1417
Uipushtool property 2-4205	cursor images
Uitable property 2-4254	reading 2-1998
Uitoggletool property 2-4274	cursor position 2-1916
Uitoolbar property 2-4286	Curvature, rectangle property 2-3269
createSoapMessage 2-964	curve fitting (polynomial) 2-3053
creating your own MATLAB functions 2-1615	customverctrl 2-989
cross 2-966	Cuthill-McKee ordering, reverse 2-3883 2-3893
cross product 2-966	cylinder 2-990
csc 2-967	cylindrical coordinates 2-512 2-514 2-3041
cscd 2-969	

D	datestr 2-1018
dagread 2-993	datevec 2-1036
daspect 2-998	dbclear 2-1040
data	dbcont $2\text{-}1043$
ASCII	dbdown $2\text{-}1044$
reading from disk 2-2379	dblquad $2\text{-}1045$
ASCII, saving to disk 2-3404	dbmex $2 ext{-} 1047$
binary, saving to disk 2-3404	dbquit $2\text{-}1049$
computing 2-D stream lines 2-3697	dbstack $2\text{-}1051$
computing 3-D stream lines 2-3699	dbstatus $2\text{-}1054$
formatted	dbstep $2\text{-}1056$
reading from files 2-1596	dbstop $2\text{-}1058$
isosurface from volume data 2-2181	dbtype 2-1068
reading binary from disk 2-2379	dbup 2-1069
reading from files 2-3954	DDE solver properties
reducing number of elements in 2-3284	error tolerance 2-1082
smoothing 3-D 2-3542	event location 2-1088
Data	solver output 2-1084
Uitable property 2-4255	step size 2-1086
data aspect ratio of axes 2-998	dde23 2-1070
data brushing	ddeget $2 ext{-} 1075$
different plot types 2-438	ddephas2 output function 2-1085
gestures for 2-443	ddephas3 output function 2-1085
restrictions on 2-440	ddeplot output function 2-1085
data types	ddeprint output function 2-1085
complex 2-862	ddesd 2-1076
data, aligning scattered	ddeset 2-1081
multi-dimensional 2-2682	deal 2-1091
data, ASCII	deblank $2 \text{-} 1094$
converting sparse matrix after loading	debugging
from 2-3562	changing workspace context 2-1044
DataAspectRatio, Axes property 2-306	changing workspace to calling file 2-1069
DataAspectRatioMode, Axes property 2-308	displaying function call stack 2-1051
datatipinfo 2-1012	files 2-3105
date 2-1013	function 2-2236
date and time functions 2-1245	MEX-files on UNIX 2-1047
date string	removing breakpoints 2-1040
format of 2-1018	resuming execution from breakpoint 2-1056
date vector 2-1038	setting breakpoints in 2-1058
datenum 2-1014	stepping through lines 2-1056

dec2base 2-1091 2-1096	quivergroup property 2-3190
dec2bin 2-1097	Root property 2-3373
dec2hex 2-1098	scatter property 2-3434
decic function 2-1100	stairseries property 2-3630
decimal number to base conversion 2-1091	stem property 2-3665
2-1096	Surface property 2-3823
decimal point (.)	surfaceplot property 2-3847
(special characters) 2-67	Text property 2-3929 2-3932
to distinguish matrix and array	Uicontextmenu property 2-4104 2-4121
operations 2-44	Uimenu property 2-4169
decomposition	Uipushtool property 2-4206
Dulmage-Mendelsohn 2-1188	Uitable property 2-4256
"economy-size" 2-3872	Uitoggletool property 2-4275
Schur 2-3448	Uitoolbar property 2-4288
singular value 2-3231 2-3872	DeleteFcn, line property 2-2318
deconv 2-1102	DeleteFcn, rectangle property 2-3269
deconvolution 2-1102	DeleteFcnpatch property 2-2929
definite integral 2-3152	deleting
del operator 2-1103	files 2-1123
del2 2-1103	items from workspace 2-790
Delaunay tessellation	delevent 2-1134
multidimensional vizualization 2-1118	delimiters in ASCII files 2-1180 2-1184
delaunayn 2-1118	delsample $2 ext{-} 1135$
delete 2-1123 2-1125	delsamplefromcollection 2-1136
serial port I/O 2-1129	demo $2\text{-}1137$
timer object 2-1131	demos
delete (ftp) function 2-1127	in Command Window 2-1209
delete handle method 2-1128	density
DeleteFcn	of sparse matrix 2-2766
areaseries property 2-225	depdir 2-1140
Axes property 2-309	dependence, linear 2-3787
barseries property 2-357	dependent functions 2-3105
contour property 2-898	depfun 2-1141
errorbar property 2-1267	derivative
Figure property 2-1418	approximate 2-1157
hggroup property 2-1868	polynomial 2-3050
hgtransform property 2-1897	desktop
Image property 2-1966	starting without 2-2477
Light property 2-2299	$det\ 2\text{-}1145$
lineseries property 2-2332	detecting

alphabetic characters 2-2161	extracting properties 2-467
empty arrays 2-2133	extracting properties of 2-1285 to 2-1286
global variables 2-2148	2-4027 to 2-4028
logical arrays 2-2162	forming initial guess 2-468
members of a set 2-2164	ODE initial value problems 2-2798
objects of a given class 2-2123	adjusting parameters of 2-2818
positive, negative, and zero array	extracting properties of 2-2817
elements 2-3520	parabolic-elliptic PDE problems 2-2976
sparse matrix 2-2199	diffuse 2-1159
determinant of a matrix 2-1145	DiffuseStrength
detrend 2-1146	Surface property 2-3824
detrend (timeseries) 2-1148	surfaceplot property 2-3847
deval 2-1149	DiffuseStrengthpatch property 2-2929
diag 2-1151	digamma function 2-3118
diagonal 2-1151	dimension statement (lack of in
anti- 2-1811	MATLAB) 2-4520
k-th (illustration) 2-4030	dimensions
main 2-1151	size of 2-3527
sparse 2-3564	Diophantine equations 2-1677
dialog 2-1153	dir 2-1160
dialog box	dir (ftp) function 2-1164
error 2-1281	direct term of a partial fraction expansion 2-3341
help 2-1852	directive
input 2-2049	%#eml $2\text{-}2606$
list 2-2374	%#ok 2-2607
message 2-2649	directories
print 2-3093	copying 2-933
question 2-3173	directory
warning 2-4418	changing on FTP server 2-534
diary 2-1155	listing for FTP server 2-1164
Diary, Root property 2-3374	making on FTP server 2-2590
DiaryFile, Root property 2-3374	directory, changing 2-529
$diff\ 2\text{-}1157$	disconnect 2-806
differences	discontinuities, eliminating (in arrays of phase
between adjacent array elements 2-1157	angles) 2-4321
between sets 2-3491	discontinuities, plotting functions with 2-1348
differential equation solvers	discontinuous problems 2-1542
defining an ODE problem 2-2811	disp 2-1166
ODE boundary value problems 2-451 2-462	memmapfile object 2-1168
adjusting parameters 2-471	serial port I/O 2-1171

timer object 2-1172	libfunctionsview 2-2282
disp, MException method 2-1169	libisloaded 2-2283
display 2-1174	libpointer 2-2285
display format 2-1554	libstruct 2-2287
displaying output in Command Window 2-2631	loadlibrary 2-2388
DisplayName	unloadlibrary 2-4304
areaseries property 2-225	dlmread 2-1180
barseries property 2-357	dlmwrite 2-1184
contourgroup property 2-899	dmperm 2-1188
errorbarseries property 2-1267	Dockable, Figure property 2-1419
hggroup property 2-1868	docsearch 2-1194
hgtransform property 2-1898	documentation
image property 2-1967	displaying online 2-1850
Line property 2-2319	dolly camera 2-485
lineseries property 2-2332	dos 2-1196
Patch property 2-2929	UNC pathname error 2-1197
quivergroup property 2-3191	dot 2-1198
rectangle property 2-3270	dot product 2-966 2-1198
scattergroup property 2-3434	dot-parentheses (special characters 2-67
stairseries property 2-3631	double 2-1199
stemseries property 2-3665	double click, detecting 2-1444
surface property 2-3825	double integral
surfaceplot property 2-3848	numerical evaluation 2-1045
text property 2-3930	DoubleBuffer, Figure property 2-1419
distribution	downloading files from FTP server 2-2575
Gaussian 2-1252	dragrect 2-1200
dither 2-1176	drawing shapes
division	circles and rectangles 2-3259
array, left (arithmetic operator) 2-46	DrawMode, Axes property 2-309
array, right (arithmetic operator) 2-45	drawnow 2-1202
by zero 2-2037	dsearchn 2-1205
matrix, left (arithmetic operator) 2-45	Dulmage-Mendelsohn decomposition 2-1188
matrix, right (arithmetic operator) 2-45	dynamic fields 2-67
of polynomials 2-1102	dynamicprops class 2-1206
divisor	dynamicprops.addprop 2-129
greatest common 2-1677	2) we she she wish she
dll libraries	F
MATLAB functions	E
calllib 2-481	echo 2-1207
libfunctions 2-2281	Echo, Root property 2-3374

echodemo $2 ext{-} 1209$	eigenvalues
echoing	effect of roundoff error 2-337
functions 2-1207	improving accuracy 2-337
edge finding, Sobel technique 2-924	eigenvector
EdgeAlpha	left 2-1218
patch property 2-2930	matrix, generalized 2-3208
surface property 2-3825	right 2-1218
surfaceplot property 2-3848	eigs 2-1221
EdgeColor	elevation (spherical coordinates) 2-3578
annotation ellipse property 2-182	elevation of viewpoint 2-4381
annotation rectangle property 2-188	ellipj $2-1231$
annotation textbox property 2-201	ellipke $2 ext{-} 1233$
areaseries property 2-226	ellipsoid 2-1235
barseries property 2-358	elliptic functions, Jacobian
patch property 2-2931	(defined) 2-1231
Surface property 2-3826	elliptic integral
surfaceplot property 2-3849	complete (defined) 2-1233
Text property 2-3931	modulus of 2-1231 2-1233
EdgeColor, rectangle property 2-3271	else 2-1237
EdgeLighting	elseif $2 ext{-} 1238$
patch property 2-2931	%#eml $2\text{-}2606$
Surface property 2-3827	Enable
surfaceplot property 2-3850	Uicontrol property 2-4122
editable text 2-4109	Uimenu property 2-4169
editing	Uipushtool property 2-4207
files 2-1214	Uitable property 2-4256
eig 2-1217	Uitogglehtool property 2-4276
eigensystem	end $2\text{-}1243$
transforming 2-535	end caps for isosurfaces 2-2171
eigenvalue	end of line, indicating 2-68
accuracy of 2-1217	eomday $2 ext{-} 1245$
complex 2-535	eq 2-1249
matrix logarithm and 2-2406	eq, MException method 2-1251
modern approach to computation of 2-3046	equal arrays
of companion matrix 2-858	detecting 2-2136 2-2140
problem 2-1218 2-3051	equal sign (special characters) 2-66
problem, generalized 2-1218 2-3051	equations, linear
problem, polynomial 2-3051	accuracy of solution 2-869
repeated 2-1219	EraseMode
Wilkinson test matrix and 2-4468	areaseries property 2-226

barseries property 2-358	disp 2-1169
contour property 2-900	eq 2-1251
errorbar property 2-1268	getReport 2-1741
hggroup property 2-1869	isequal 2-2139
hgtransform property 2-1898	last 2-2240
Image property 2-1968	ne 2-2689
Line property 2-2320	rethrow $2\text{-}3348$
lineseries property 2-2333	throw 2-3980
quivergroup property 2-3192	throwAsCaller 2-3984
rectangle property 2-3271	ErrorType, Root property 2-3375
scatter property 2-3435	etime $2 - 1284$
stairseries property 2-3632	etree 2-1285
stem property 2-3666	etreeplot 2-1286
Surface property 2-3827	eval 2-1287
surfaceplot property 2-3850	evalc 2-1290
Text property 2-3932	evalin 2-1291
EraseModepatch property 2-2932	event location (DDE) 2-1088
error 2-1254	event location (ODE) 2-2826
roundoff. See roundoff error	event.EventData 2-1293
error function	event.listener 2-1294
complementary 2-1252	event.PropertyEvent 2-1296
(defined) 2-1252	event.proplistener 2-1297
scaled complementary 2-1252	events 2-1302
error message	examples
displaying 2-1254	calculating isosurface normals 2-2178
Index into matrix is negative or zero 2-2402	contouring mathematical expressions 2-1321
retrieving last generated 2-2243 2-2251	isosurface end caps 2-2171
error messages	isosurfaces 2-2182
Out of memory $2\text{-}2878$	mesh plot of mathematical function 2-1330
error tolerance	mesh/contour plot 2-1334
BVP problems 2-472	plotting filled contours 2-1325
DDE problems 2-1082	plotting function of two variables 2-1338
ODE problems 2-2819	plotting parametric curves 2-1341
errorbars, confidence interval 2-1259	polar plot of function 2-1344
errordlg 2-1281	reducing number of patch faces 2-3281
ErrorMessage, Root property 2-3374	reducing volume data 2-3284
errors	subsampling volume data 2-3792
MException class 2-1251	surface plot of mathematical function 2-1348
addCause 2-111	surface/contour plot 2-1355
constructor 2-2567	Excel spreadsheets

loading 2-4495	ezsurf 2-1346
exclamation point (special characters) 2-68	ezsurfc 2-1353
Execute 2-1304	
executing statements repeatedly 2-1552 2-4455	F
executing statements repeatedly in	r
parallel 2-2894	F-norm 2-2769
execution	FaceAlpha
improving speed of by setting aside	annotation textbox property 2-202
storage 2-4520	FaceAlphapatch property 2-2933
pausing function 2-2955	FaceAlphasurface property 2-3828
resuming from breakpoint 2-1043	FaceAlphasurfaceplot property 2-3851
time for files 2-3105	FaceColor
exifread 2-1306	annotation ellipse property 2-182
exist 2-1307	annotation rectangle property 2-188
exit 2-1311	areaseries property 2-228
expint 2-1313	barseries property 2-360
expm 2-1314	Surface property 2-3829
expm1 2-1316	surfaceplot property 2-3852
exponential 2-1312	FaceColor, rectangle property 2-3272
complex (defined) 2-1312	FaceColorpatch property 2-2934
integral 2-1313	FaceLighting
matrix 2-1314	Surface property 2-3829
exponentiation	surfaceplot property 2-3853
array (arithmetic operator) 2-46	FaceLightingpatch property 2-2934
matrix (arithmetic operator) 2-46	faces, reducing number in patches 2-3280
export2wsdlg 2-1317	Faces, patch property 2-2935
extension, filename	FaceVertexAlphaData, patch property 2-2936
.m 2-1615	FaceVertexCData, patch property 2-2937
.mat $2\text{-}3404$	factor 2-1360
Extent	factorial 2-1361
Text property 2-3934	factorization
Uicontrol property 2-4123	LU 2-2430
Uitable property 2-4257	QZ 2-3052 2-3208
ezcontour 2-1320	factorization, Cholesky 2-758
ezcontourf 2-1324	(as algorithm for solving linear
ezmesh 2-1328	equations) 2-2600
ezmeshc 2-1332	preordering for 2-850
ezplot 2-1336	factors, prime 2-1360
ezplot3 2-1340	false 2-1362
ezpolar 2-1343	fclose

serial port I/O 2-1364	writing 2-2010
feather 2-1366	file name
feval 2-1372	building from parts 2-1611
Feval 2-1374	file size
fft 2-1379	querying 2-1983
FFT. See Fourier transform	fileattrib $2 ext{-} 1465$
fft2 2-1384	filebrowser 2-1472
fftn 2-1385	filemarker 2-1477
fftshift 2-1387	filename
fftw $2 - 1390$	parts 2-1479
FFTW 2-1382	temporary 2-3912
fgetl	filename extension
serial port I/O 2-1396	.m $2\text{-}1615$
fgets	.mat $2\text{-}3404$
serial port I/O 2-1400	fileparts 2-1479
field names of a structure, obtaining 2-1403	files
fieldnames 2-1403	ASCII delimited
fields, of structures	reading 2-1180
dynamic 2-67	writing 2-1184
figure 2-1405	checking existence of 2-1307
Figure	checking for problems 2-2604
creating 2-1405	contents, listing 2-4069
defining default properties 2-1407	copying 2-933
properties 2-1408	copying with copyfile 2-933
redrawing 2-3287	cyclomatic complexity of 2-2604
figure windows	debugging with profile 2-3105
moving in front of MATLAB® desktop 2-3512	deleting 2-1123
figure windows, displaying 2-1503	deleting on FTP server 2-1127
figurepalette 2-1463	editing 2-1214
figures	Excel spreadsheets
annotating 2-3029	loading 2-4495
saving 2-3415	fig 2-3415
Figures	figure, saving 2-3415
updating from file 2-1202	line numbers, listing 2-1068
file	lint tool 2-2604
extension, getting 2-1479	listing 2-1160
modification date 2-1160	in folder 2-4447
file formats	listing contents of 2-4069
getting list of supported formats 2-1985	locating 2-4452
reading 2-993 2-1996	McCabe complexity of 2-2604

$mdl\ 2\text{-}3415$	findfigs $2 ext{-} 1503$
model, saving 2-3415	finding 2-1497
opening	sign of array elements 2-3520
in Web browser 2-4440	zero of a function 2-1638
opening in Windows applications 2-4469	See also detecting
optimizing 2-3105	findobj $2\text{-}1504$
path, getting 2-1479	findobj handle method 2-1508
pathname for 2-4452	findprop handle method 2-1509
problems, checking for 2-2604	findstr 2-1511
reading	finish $2\text{-}1512$
data from 2-3954	finish.m $2\text{-}3177$
formatted 2-1596	FIR filter 2-1489
reading data from 2-993	FitBoxToText, annotation textbox
reading image data from 2-1996	property 2-202
size, determining 2-1162	FitHeightToText
sound	annotation textbox property 2-202
reading 2-279 2-4432	fitsinfo $2 ext{-} 1514$
writing 2-281 to 2-282 2-4438	fitsread 2-1523
startup 2-2469	fix 2-1526
.wav	fixed-width font
reading 2-4432	axes 2-310
writing 2-4438	text 2-3935
WK1	uicontrols 2-4124
loading 2-4474	uitables 2-4258
writing to 2-4477	FixedColors, Figure property 2-1420
writing image data to 2-2010	FixedWidthFontName, Root property 2-3374
filesep 2-1482	flints 2-2656
fill 2-1483	flip
Fill	array dimension 2-1527
contour property 2-901	flip array
fill3 2-1486	along dimension 2-1527
filter 2-1489	flip matrix
digital 2-1489	on horizontal axis 2-1529
finite impulse response (FIR) 2-1489	on vertical axis 2-1528
infinite impulse response (IIR) 2-1489	flipdim $2\text{-}1527$
two-dimensional 2-922	fliplr $2 ext{-} 1528$
filter (timeseries) 2-1492	flipud 2-1529
filter2 2-1495	floating-point
find 2-1497	integer, maximum 2-424
findall function 2-1502	floating-point arithmetic, IEEE

smallest postive number 2-3252	Uitable property 2-4258
floor 2-1531	FontName
flow control	annotation textbox property 2-204
break $2\text{-}434$	Axes property 2-310
case 2-515	Text property 2-3934
end $2\text{-}1243$	textarrow property 2-192
error $2 ext{-} 1256$	Uicontrol property 2-4124
for $2\text{-}1552$	Uitable property 2-4258
keyboard 2-2236	fonts
otherwise 2-2877	bold 2-192 2-205 2-3935
parfor 2-2894	italic 2-192 2-204 2-3934
return 2-3352	specifying size 2-3935
switch $2 - 3880$	TeX characters
while $2\text{-}4455$	bold 2-3949
fminbnd $2 ext{-} 1533$	italics 2-3949
fminsearch 2-1538	specifying family 2-3949
folder	specifying size 2-3949
listing MATLAB files in 2-4447	units 2-192 2-205 2-3935
root 2-2470	FontSize
temporary	annotation textbox property 2-205
system 2-3911	Axes property 2-311
folders	Text property 2-3935
adding to search path 2-126	textarrow property 2-192
checking existence of 2-1307	Uicontrol property 2-4125
copying 2-933	Uitable property 2-4259
creating 2-2587	FontUnits
listing 2-2414	Axes property 2-311
listing contents of 2-1160	Text property 2-3935
removing 2-3364	Uicontrol property 2-4125
removing from search path 2-3369	Uitable property 2-4259
font	FontWeight
fixed-width, axes 2-310	annotation textbox property 2-205
fixed-width, text 2-3935	Axes property 2-311
fixed-width, uicontrols 2-4124	Text property 2-3935
fixed-width, uitables 2-4258	textarrow property 2-192
FontAngle	Uicontrol property 2-4125
annotation textbox property 2-204	Uitable property 2-4259
Axes property 2-310	fopen
Text property 2-192 2-3934	serial port I/O 2-1550
Uicontrol property 2-4124	for $2\text{-}1552$

ForegroundColor	FTP
Uicontrol property 2-4126	connecting to server 2-1608
Uimenu property 2-4169	ftp function 2-1608
Uitable property 2-4260	full 2-1610
format 2-1554	fullfile 2-1611
Format 2-3375	func2str 2-1613
FormatSpacing, Root property 2-3376	function $2\text{-}1615$
formatted data	declaration 2-1615
reading from file 2-1596	echoing commands 2-1207
Fourier transform	naming conventions 2-1615
algorithm, optimal performance of 2-1382	function handle 2-1618
2-1936 2-1938 2-2765	function handles
as method of interpolation 2-2095	overview of 2-1618
discrete, n-dimensional 2-1385	function syntax 2-3898
discrete, one-dimensional 2-1379	functions 2-1621
discrete, two-dimensional 2-1384	call history 2-3110
fast 2-1379	call stack for 2-1051
inverse, n-dimensional 2-1940	checking existence of 2-1307
inverse, one-dimensional 2-1936	clearing from workspace 2-790
inverse, two-dimensional 2-1938	debugging 2-2236
shifting the zero-frequency component	finding using keywords 2-2410
of 2-1388	help for 2-1846 2-1854
fplot 2-1562 2-1579	in memory 2-2044
fprintf	locating 2-4452
serial port I/O 2-1575	locking (preventing clearing) 2-2617
fraction, continued 2-3232	pathname for 2-4452
fragmented memory 2-2878	pausing execution of 2-2955
$\texttt{frame2im} \ 2\text{-}1579$	programming 2-1615
frames 2-4109	that work down the first non-singleton
fread	dimension 2-3513
serial port I/O 2-1588	unlocking (allowing clearing) 2-2668
freqspace 2-1594	funm $2\text{-}1625$
frequency response	fwrite
desired response matrix	serial port I/O 2-1634
frequency spacing 2-1594	fzero 2-1638
frequency vector 2-2409	
fromName meta.class method 2-2531	G
fromName meta.package method 2-2542	_
fscanf	gallery 2-1644
serial port I/O 2-1601	gamma function

(defined) 2-1671	getdisp hgsetget class method 2-1722
incomplete 2-1671	getenv $2 ext{-} 1723$
logarithm of 2-1671	getframe 2-1729
logarithmic derivative 2-3118	image resolution and 2-1730
Gauss-Kronrod quadrature 2-3165	getinterpmethod $2 ext{-} 1735$
Gaussian distribution function 2-1252	getpixelposition 2-1736
Gaussian elimination	getpref function 2-1738
(as algorithm for solving linear	getqualitydesc 2-1740
equations) 2-2110 2-2601	getReport, MException method 2-1741
Gauss Jordan elimination with partial	getsampleusingtime (timeseries) 2-1744
pivoting 2-3399	getsampleusingtime (tscollection) 2-1745
LU factorization 2-2430	gettimeseriesnames 2-1748
gca 2-1674	gettsafteratevent 2-1749
gcbf function 2-1675	gettsafterevent 2-1750
gcbo function 2-1676	gettsatevent $2 ext{-} 1751$
gcd 2-1677	gettsbeforeatevent 2-1752
gcf 2-1679	gettsbeforeevent 2-1753
gco 2-1680	gettsbetweenevents $2 ext{-} 1754$
ge 2-1681	GIF files
generalized eigenvalue problem 2-1218 2-3051	writing 2-2012
generating a sequence of matrix names (M1	ginput function 2-1760
through M12) 2-1288	global 2-1763
genpath 2-1683	global variable
genvarname 2-1685	defining 2-1763
geodesic dome 2-3893	global variables, clearing from workspace 2-790
get 2-1689 2-1696	gmres 2-1765
memmapfile object 2-1699	golden section search 2-1536
serial port I/O 2-1705	Goup
timer object 2-1707	defining default properties 2-1892
get (timeseries) 2-1709	gplot $2-1771$
get (tscollection) 2-1710	grabcode function 2-1773
get hgsetget class method 2-1698	gradient $2\text{-}1775$
get, RandStream method 2-1704	gradient, numerical 2-1775
getabstime (timeseries) 2-1711	graph
getabstime (tscollection) $2 ext{-}1713$	adjacency 2-1189
getAllPackages meta.package method 2-2543	graph theory 2-4305
getappdata function 2-1715	graphics objects
getCompilerConfigurations $2 ext{-}2561$	Axes 2-288
getdatasamplesize 2-1720	Figure 2-1405
getDefaultStream, RandStream method 2-1721	getting properties 2-1689

Image 2-1951	П
Light 2-2294	hadamard 2-1806
Line 2-2307	Hadamard matrix 2-1806
Patch 2-2901	subspaces of 2-3787
resetting properties 2-3336	handle class 2-1807
Root 2-3371	handle graphics
setting properties 2-3467	hgtransform 2-1881
Surface 2-3811	handle graphicshggroup 2-1861
Text 2-3918	handle relational operators 2-3320
uicontextmenu 2-4097	handle.addlistener 2-118
Uicontrol 2-4108	handle.delete 2-1128
Uimenu 2-4161	handle.findobj 2-1508
graphics objects, deleting 2-1123	handle.findprop 2-1509
graphs	handle.isvalid 2-2209
editing 2-3029	handle.notify 2-2774
graymon 2-1778	HandleVisibility
greatest common divisor 2-1677	areaseries property 2-228
Greek letters and mathematical symbols 2-196	Axes property 2-312
2-207 2-3947	barseries property 2-360
grid 2-1779	contour property 2-901
grid arrays	errorbar property 2-1269
for volumetric plots 2-2525	Figure property 2-1421
multi-dimensional 2-2682	hggroup property 2-1871
griddatan 2-1786	hgtransform property 2-1900
GridLineStyle, Axes property 2-312	Image property 2-1969
group	Light property 2-2299
hggroup function 2-1861	Line property 2-2321
gsvd 2-1788	lineseries property 2-2334
gt 2-1794	patch property 2-2938
gtext 2-1796	quivergroup property 2-3193
guidata function 2-1797	rectangle property 2-3272
GUIDE	Root property 2-3376
object methods	stairseries property 2-3633
inspect 2-2060	stem property 2-3667
guihandles function 2-1802	Surface property 2-3830
GUIs, printing 2-3088	surfaceplot property 2-3853
gunzip 2-1803	Text property 2-3936
gzip 2-1805	Uicontextmenu property 2-410
	Uicontrol property 2-4126
	Uimenu property 2-4170

Uipushtool property 2-4207	textarrow property 2-193
Uitable property 2-4260	HeadStyle
Uitoggletool property 2-4277	annotation arrow property 2-173
Uitoolbar property 2-4288	textarrow property 2-193
hankel 2-1811	HeadWidth
Hankel matrix 2-1811	annotation arrow property 2-174
HDF	textarrow property 2-194
appending to when saving	Height
(WriteMode) 2-2016	annotation ellipse property 2-183
compression 2-2016	help $2\text{-}1846$
setting JPEG quality when writing 2-2016	keyword search in functions 2-2410
HDF files	online 2-1846
writing images 2-2012	Help browser 2-1850
HDF4	accessing from doc 2-1191
summary of capabilities 2-1812	Help Window 2-1854
HDF5	helpbrowser 2-1850
high-level access 2-1814	helpdesk $2\text{-}1851$
summary of capabilities 2-1814	helpdlg $2\text{-}1852$
HDF5 class	helpwin $2 ext{-} 1854$
low-level access 2-1814	Hermite transformations, elementary 2-1677
hdf5info 2-1817	hess $2\text{-}1855$
hdf5read 2-1819	Hessenberg form of a matrix 2-1855
hdf5write 2-1821	hex2dec 2-1858
hdfinfo $2\text{-}1825$	$hex2num\ 2-1859$
hdfread 2-1833	hgsetget class 2-1880
hdftool $2\text{-}1845$	hgsetget.get 2-1698
Head1Length	hgsetget.getdisp $2\text{-}1722$
annotation doublearrow property 2-177	hgsetget.set $2\text{-}3476$
Head1Style	hidden $2\text{-}1905$
annotation doublearrow property 2-178	Hierarchical Data Format (HDF) files
Head1Width	writing images 2-2012
annotation doublearrow property 2-179	hilb $2 ext{-} 1906$
Head2Length	Hilbert matrix 2-1906
annotation doublearrow property 2-177	inverse 2-2113
Head2Style	hist $2 ext{-} 1907$
annotation doublearrow property 2-178	histc 2-1911
Head2Width	HitTest
annotation doublearrow property 2-179	areaseries property 2-230
HeadLength	Axes property 2-313
annotation arrow property 2-173	barseries property 2-362

contour property 2-903	horzcat (function equivalent for $[,]$) 2-68
errorbar property 2-1271	horzcat (tscollection) 2-1919
Figure property 2-1422	hostid $2\text{-}1920$
hggroup property 2-1872	Householder reflections (as algorithm for solving
hgtransform property 2-1901	linear equations) 2-2602
Image property 2-1971	hsv2rgb 2-1921
Light property 2-2301	HTML
Line property 2-2322	in Command Window 2-2465
lineseries property 2-2336	HTML browser
Patch property 2-2939	in MATLAB 2-1850
quivergroup property 2-3195	HTML files
rectangle property 2-3274	opening 2-4440
Root property 2-3376	hyperbolic
scatter property 2-3438	cosecant 2-970
stairseries property 2-3635	cosecant, inverse 2-94
stem property 2-3669	cosine 2-945
Surface property 2-3831	cosine, inverse 2-84
surfaceplot property 2-3855	cotangent 2-950
Text property 2-3937	cotangent, inverse 2-89
Uicontrol property 2-4127	secant 2-3455
Uipushtool property 2-4208	secant, inverse 2-247
Uitable property 2-4261	sine 2-3525
Uitoggletool property 2-4277	sine, inverse 2-253
Uitoolbarl property 2-4289	tangent 2-3907
HitTestArea	tangent, inverse 2-264
areaseries property 2-230	hyperlink
barseries property 2-362	displaying in Command Window 2-1166
contour property 2-903	hyperlinks
errorbar property 2-1271	in Command Window 2-2465
quivergroup property 2-3195	hyperplanes, angle between 2-3787
scatter property 2-3438	hypot 2-1922
stairseries property 2-3635	
stem property 2-3669	1
hold 2-1914	. 0.100
home 2-1916	i 2-1925
HorizontalAlignment	icon images
Text property 2-3938	reading 2-1998
textbox property 2-194 2-205	idealfilter (timeseries) 2-1926
Uicontrol property 2-4127	identity matrix
horzcat 2-1917	sparse 2-3575

idivide 2-1930	incomplete beta function
IEEE floating-point arithmetic	(defined) 2-394
smallest positive number 2-3252	incomplete gamma function
if 2-1932	(defined) 2-1671
ifft 2-1936	ind2sub 2-2033
ifft2 2-1938	Index into matrix is negative or zero (error
ifftn 2-1940	message) 2-2402
ifftshift 2-1942	indexed images
IIR filter 2-1489	converting from RGB 2-3355
ilu 2-1943	indexing
im2java 2-1948	logical 2-2401
imag 2-1950	indices, array
image 2-1951	of sorted elements 2-3549
Image	Inf 2-2037
creating 2-1951	infinity 2-2037
properties 2-1959	norm 2-2769
image types	info $2\text{-}2040$
querying 2-1983	information
images	returning file information 2-1982
file formats 2-1996 2-2010	inline $2 ext{-} 2041$
reading data from files 2-1996	inmem $2\text{-}2044$
returning information about 2-1982	inpolygon $2\text{-}2046$
writing to files 2-2010	input $2\text{-}2048$
Images	checking number of arguments 2-2673
converting MATLAB image to Java	name of array passed as 2-2053
Image 2-1948	number of arguments 2-2675
imagesc 2-1976	prompting users for 2-2048
imaginary 2-1950	inputdlg $2\text{-}2049$
part of complex number 2-1950	inputname $2\text{-}2053$
unit (sqrt(\xd0 1)) 2-1925 2-2214	inputParser $2\text{-}2054$
See also complex	inspect 2-2060
imapprox 2-1980	installation, root folder 2-2470
imfinfo	instance properties 2-129
returning file information 2-1982	instrcallback 2-2068
imformats 2-1985	instrfind $2\text{-}2069$
import 2-1988	instrfindall $2\text{-}2071$
importing	example of 2-2072
Java class and package names 2-1988	int2str 2-2074
imread 2-1996	integer
imwrite $2-2010$	floating-point, maximum 2-424

IntegerHandle	Line property 2-2322
Figure property 2-1422	lineseries property 2-2336
integration	patch property 2-2940
polynomial 2-3057	quivergroup property 2-3195
quadrature 2-3152 2-3161	rectangle property 2-3274
interp1 2-2079	Root property 2-3376
interp1q 2-2087	scatter property 2-3439
interp2 2-2089	stairseries property 2-3635
interp3 2-2093	stem property 2-3670
interpft 2-2095	Surface property 2-3831 2-3855
interpn 2-2096	Text property 2-3940
interpolated shading and printing 2-3089	Uicontextmenu property 2-4105
interpolation	Uicontrol property 2-4128
cubic method 2-2079 2-2089 2-2093 2-2096	Uimenu property 2-4170
cubic spline method 2-2079 2-2089 2-2093	Uipushtool property 2-4208
2-2096	Uitable property 2-4261
FFT method 2-2095	Uitoggletool property 2-4278
linear method 2-2079 2-2089 2-2093 2-2096	Uitoolbar property 2-4289
multidimensional 2-2096	intersect 2-2103
nearest neighbor method 2-2079 2-2089	$\verb"intmax"\ 2-2104"$
2-2093 2-2096	intmin $2\text{-}2105$
one-dimensional 2-2079	intwarning 2-2106
three-dimensional 2-2093	$inv \ 2-2110$
two-dimensional 2-2089	inverse
Interpreter	cosecant 2-91
Text property 2-3939	cosine 2-81
textarrow property 2-194	cotangent 2-86
textbox property 2-205	Fourier transform 2-1936 2-1938 2-1940
interpstreamspeed 2-2099	Hilbert matrix 2-2113
Interruptible	hyperbolic cosecant 2-94
areaseries property 2-230	hyperbolic cosine 2-84
Axes property 2-313	hyperbolic cotangent 2-89
barseries property 2-362	hyperbolic secant 2-247
contour property 2-903	hyperbolic sine 2-253
errorbar property 2-1272	hyperbolic tangent 2-264
Figure property 2-1423	of a matrix 2-2110
hggroup property 2-1872	secant 2-244
hgtransform property 2-1901	tangent 2-259
Image property 2-1971	tangent, four-quadrant 2-261
Light property 2-2301	inversion, matrix

accuracy of 2-869	vertex normals 2-2178
InvertHardCopy, Figure property 2-1424	$ispc \ 2-2186$
invhilb $2-2113$	ispref function 2-2188
involutary matrix 2-2900	isprime 2-2189
ipermute 2-2117	isreal 2-2191
iqr (timeseries) 2-2118	isscalar 2-2194
is* 2-2120	issorted 2-2195
isa 2-2123	isspace 2-2198 2-2201
isappdata function 2-2125	issparse 2-2199
iscell 2-2126	isstr 2-2200
iscellstr 2-2127	isstruct $2\text{-}2205$
ischar 2-2128	isstudent 2-2206
isdir 2-2130	isunix 2-2208
isempty $2-2133$	isvalid 2-2210
isempty (timeseries) 2-2134	timer object 2-2211
isempty (tscollection) 2-2135	isvalid handle method 2-2209
isequal 2-2136	isvarname 2-2212
isequal, MException method 2-2139	isvector 2-2213
isequalwithequalnans 2-2140	italics font
isfield 2-2144	TeX characters 2-3949
isfinite 2-2146	
isfloat 2-2147	J
isglobal 2-2148	
ishandle 2-2150	j 2-2214
ishghandle 2-2151	Jacobi rotations 2-3598
isinf $2-2153$	Jacobian elliptic functions
isinteger 2-2154	(defined) 2-1231
isjava 2-2156	Jacobian matrix (BVP) 2-474
iskeyword 2-2159	Jacobian matrix (ODE) 2-2827
isletter 2-2161	generating sparse numerically 2-2828
islogical 2-2162	2-2830
ismac 2-2163	specifying 2-2828 2-2830
ismember $2 - 2164$	vectorizing ODE function 2-2828 to 2-2830
isnan 2-2167	Java
isnumeric 2-2168	class names 2-793 2-1988
isocap 2-2171	object methods
isonormals 2-2178	inspect 2-2060
isosurface 2-2181	objects 2-2156
calculate data from volume 2-2181	Java Image class
end caps 2-2171	creating instance of 2-1948

Java import list	version used by MATLAB 2-4372
adding to 2-1988	
clearing 2-793	K
Java version used by MATLAB 2-4372	
java_method 2-2219 2-2226	K>> prompt
java_object 2-2229	keyboard function 2-2236
javaaddath $2\text{-}2215$	keep
javachk 2-2220	some variables when clearing 2-796
javaclasspath 2-2221	keyboard 2-2236
javaMethod 2-2226	keyboard mode 2-2236
javaMethodEDT 2-2228	terminating 2-3352
javaObject 2-2229	KeyPressFcn
javaObjectEDT 2-2231	Uicontrol property 2-4129
javarmpath 2-2232	Uitable property 2-4262
joining arrays. See concatenation	KeyPressFcn, Figure property 2-1424
Joint Photographic Experts Group (JPEG)	KeyReleaseFcn, Figure property 2-1426
writing 2-2012	keyword search in functions 2-2410
JPEG	keywords
setting Bitdepth 2-2016	iskeyword function 2-2159
specifying mode 2-2017	kron 2-2238
JPEG 2000	Kronecker tensor product 2-2238
setting tile size 2-2018	Krylov subspaces 2-3977
JPEG 2000 comment	
setting when writing a JPEG 2000	L
image 2-2017	Label, Uimenu property 2-4172
specifying 2-2017	labeling
JPEG comment	axes 2-4488
setting when writing a JPEG image 2-2016	matrix columns 2-1166
JPEG files	plots (with numeric values) 2-2783
parameters that can be set when	LabelSpacing
writing 2-2016	contour property 2-904
writing 2-2012	Laplacian 2-1103
JPEG quality	Laplacian matrix 2-4305
setting when writing a JPEG image 2-2017	largest array elements 2-2491
to 2-2018 2-2022	last, MException method 2-2240
setting when writing an HDF image 2-2016	lasterr 2-2243
JPEG2000 files	lasterror 2-2246
parameters that can be set when	lastwarn 2-2251
writing 2-2017	LaTeX, see TeX 2-196 2-207 2-3947
jvm	20101, 500 1011 2 100 2 201 2 0011

Layer, Axes property 2-314	Light
Layout Editor	creating 2-2294
starting 2-1801	defining default properties 2-1957 2-2295
lcm 2-2253	properties 2-2296
LData	Light object
errorbar property 2-1272	positioning in spherical coordinates 2-2304
LDataSource	lightangle 2-2304
errorbar property 2-1272	lighting 2-2305
ldivide (function equivalent for .\) 2-49	limits of axes, setting and querying 2-4490
le 2-2261	line $2\text{-}2307$
least common multiple 2-2253	editing 2-3029
least squares	Line
polynomial curve fitting 2-3053	creating 2-2307
problem, overdetermined 2-3004	defining default properties 2-2312
legend 2-2263	properties 2-2313 2-2328
properties 2-2269	line numbers in files 2-1068
setting text properties 2-2269	linear audio signal 2-2306 2-2656
legendre 2-2272	linear dependence (of data) 2-3787
Legendre functions	linear equation systems
(defined) 2-2272	accuracy of solution 2-869
Schmidt semi-normalized 2-2272	linear equation systems, methods for solving
length	Cholesky factorization 2-2600
serial port I/O 2-2278	Gaussian elimination 2-2601
length (timeseries) 2-2279	Householder reflections 2-2602
length (tscollection) 2-2280	matrix inversion (inaccuracy of) 2-2110
LevelList	linear interpolation 2-2079 2-2089 2-2093 2-2096
contour property 2-904	linear regression 2-3053
LevelListMode	linearly spaced vectors, creating 2-2370
contour property 2-904	LineColor
LevelStep	contour property 2-905
contour property 2-905	lines
LevelStepMode	computing 2-D stream 2-3697
contour property 2-905	computing 3-D stream 2-3699
libfunctions 2-2281	drawing stream lines 2-3701
libfunctionsview 2-2282	LineSpec 2-2345
libisloaded 2-2283	LineStyle
libpointer 2-2285	annotation arrow property 2-174
libstruct 2-2287	annotation doublearrow property 2-179
license 2-2290	annotation ellipse property 2-183
light 2-2294	annotation line property 2-185

annotation rectangle property 2-189	surfaceplot property 2-3856
annotation textbox property 2-206	text object 2-3942
areaseries property 2-231	textarrow property 2-195
barseries property 2-363	linkaxes 2-2351
contour property 2-906	linkdata $2\text{-}2355$
errorbar property 2-1273	linkprop $2\text{-}2363$
Line property 2-2323	links
lineseries property 2-2337	in Command Window 2-2465
patch property 2-2940	linsolve 2-2367
quivergroup property 2-3196	linspace 2-2370
rectangle property 2-3274	lint tool for checking problems 2-2604
stairseries property 2-3636	list boxes 2-4110
stem property 2-3670	defining items 2-4135
surface object 2-3832	list, RandStream method 2-2371
surfaceplot object 2-3855	ListboxTop, Uicontrol property 2-4130
text object 2-3941	listdlg $2\text{-}2374$
textarrow property 2-195	listfonts 2-2377
LineStyleOrder	load 2-2379 2-2384
Axes property 2-314	serial port I/O 2-2386
LineWidth	loadlibrary 2-2388
annotation arrow property 2-175	Lobatto IIIa ODE solver 2-460 2-466
annotation doublearrow property 2-180	local variables 2-1615 2-1763
annotation ellipse property 2-183	locking functions 2-2617
annotation line property 2-186	log 2-2397
annotation rectangle property 2-189	saving session to file 2-1155
annotation textbox property 2-206	log10 [log010] 2-2398
areaseries property 2-231	log1p 2-2399
Axes property 2-315	log2 2-2400
barseries property 2-363	logarithm
contour property 2-906	base ten 2-2398
errorbar property 2-1273	base two 2-2400
Line property 2-2323	complex 2-2397 to 2-2398
lineseries property 2-2337	natural 2-2397
Patch property 2-2940	of beta function (natural) 2-397
quivergroup property 2-3196	of gamma function (natural) 2-1672
rectangle property 2-3274	of real numbers 2-3250
scatter property 2-3439	plotting 2-2403
stairseries property 2-3636	logarithmic derivative
stem property 2-3671	gamma function 2-3118
Surface property 2-3832	logarithmically spaced vectors, creating 2-2409

logical 2-2401	luinc 2-2438
logical array	
converting numeric array to 2-2401	M
detecting 2-2162	
logical indexing 2-2401	.m files
logical operations	checking existence of 2-1307
AND, bit-wise 2-419	M-file execution
OR, bit-wise 2-426	resuming after suspending 2-4221
XOR 2-4516	suspending from GUI 2-4292
XOR, bit-wise 2-430	M-files
logical operators 2-56 2-63	clearing from workspace 2-790
logical OR	deleting 2-1123
bit-wise 2-426	machine epsilon 2-4457
logical tests 2-2123	magic $2\text{-}2445$
all 2-151	magic squares 2-2445
any 2-212	Map containers
See also detecting	constructor 2-2450 2-3530
logical XOR 2-4516	methods 2-2277 2-3323 2-4355
bit-wise 2-430	Map methods
loglog 2-2403	constructor 2-2157 2-2237
logm 2-2406	Margin
logspace 2-2409	annotation textbox property 2-206
lookfor 2-2410	text object 2-3944
lossy compression	Marker
writing JPEG 2000 files with 2-2017	Line property 2-2323
writing JPEG files with 2-2017	lineseries property 2-2337
Lotus WK1 files	marker property 2-1274
loading 2-4474	Patch property 2-2941
writing 2-4477	quivergroup property 2-3197
lower 2-2412	scatter property 2-3440
lower triangular matrix 2-4030	stairseries property 2-3637
lowercase to uppercase 2-4325	stem property 2-3671
ls 2-2413	Surface property 2-3832
lscov 2-2415	surfaceplot property 2-3856
1sqnonneg 2-2420	MarkerEdgeColor
lsqr 2-2423	errorbar property 2-1274
lt 2-2428	Line property 2-2324
lu 2-2430	lineseries property 2-2338
LU factorization 2-2430	Patch property 2-2941
storage requirements of (sparse) 2-2789	quivergroup property 2-3197

scatter property 2-3440	MATLAB
stairseries property 2-3637	installation folder 2-2470
stem property 2-3672	quitting 2-3177
Surface property 2-3833	startup 2-2469
surfaceplot property 2-3857	version number, comparing 2-4370
MarkerFaceColor	version number, displaying 2-4364
errorbar property 2-1275	matlab : function 2-2465
Line property 2-2324	matlab (UNIX command) 2-2473
lineseries property 2-2338	matlab (Windows command) 2-2485
Patch property 2-2942	MATLAB files
quivergroup property 2-3198	listing names of in a folder 2-4447
scatter property 2-3441	matlab function for UNIX 2-2473
stairseries property 2-3638	matlab function for Windows 2-2485
stem property 2-3672	MATLAB startup file 2-3647
Surface property 2-3834	MATLAB® desktop
surfaceplot property 2-3857	moving figure windows in front of 2-3512
MarkerSize	${\tt matlab.mat}\ 2\text{-}3404$
errorbar property 2-1275	matlabcolon function 2-2465
Line property 2-2325	matlabrc 2-2469
lineseries property 2-2339	${\tt matlabroot}\ 2\text{-}2470$
Patch property 2-2942	matlabroot 2-2470
quivergroup property 2-3198	matrices
stairseries property 2-3638	preallocation 2-4520
stem property 2-3672	matrix 2-44
Surface property 2-3834	addressing selected rows and columns
surfaceplot property 2-3858	of 2-70
mass matrix (ODE) 2-2831	arrowhead 2-850
initial slope 2-2832 to 2-2833	columns
singular 2-2832	rearrange 2-1528
sparsity pattern 2-2832	companion 2-858
specifying 2-2832	condition number of 2-869 2-3238
state dependence 2-2832	condition number, improving 2-337
MAT-file 2-3404	converting to vector 2-71
converting sparse matrix after loading	defective (defined) 2-1219
from 2-3562	detecting sparse 2-2199
MAT-files	determinant of 2-1145
listing for folder 2-4447	diagonal of 2-1151
mat2cell 2-2458	Dulmage-Mendelsohn decomposition 2-1188
mat2str 2-2461	evaluating functions of 2-1625
material 2-2463	exponential 2-1314

transpose (arithmetic operator) 2-46
transposing 2-67
unimodular 2-1677
unitary 2-3872
upper triangular 2-4051
Vandermonde 2-3055
Wilkinson 2-3568 2-4468
writing formatted data to 2-1596
writing to ASCII delimited file 2-1184
writing to spreadsheet 2-4477
See also array
Matrix
hgtransform property 2-1902
matrix functions
evaluating 2-1625
matrix names, (M1 through M12) generating a
sequence of 2-1288
matrix power. See matrix, exponential
max 2-2491
max (timeseries) 2-2492
Max, Uicontrol property 2-4130
MaxHeadSize
quivergroup property 2-3198
maximum matching 2-1188
MDL-files
checking existence of 2-1307
mean 2-2497
mean (timeseries) 2-2498
median 2-2500
median (timeseries) 2-2501
median value of array elements 2-2500
memmapfile 2-2503
memory 2-2509
clearing 2-790
minimizing use of 2-2878
variables in 2-4461
menu (of user input choices) 2-2518
menu function 2-2518
MenuBar, Figure property 2-1428
Mersenne twister 2-3225 2-3229

mesh plot	-0 2-2557
tetrahedron 2-3913	-outdir dirname $2 \hbox{-} 2557$
mesh size (BVP) 2-476	-output resultname $2 \hbox{-} 2558$
meshc $2 - 2520$	<code>@rsp_file</code> $2\text{-}2554$
meshgrid $2 ext{-} 2525$	-setup $2\text{-}2558$
MeshStyle, Surface property 2-3834	-Uname 2-2558
MeshStyle, surfaceplot property 2-3858	-v 2-2558
meshz $2\text{-}2520$	mex.CompilerConfiguration $2\text{-}2561$
message	mex.CompilerConfigurationDetails $2-2561$
error See error message 2-4421	MEX-files
warning See warning message 2-4421	clearing from workspace 2-790
meta.class 2-2527	debugging on UNIX 2-1047
meta.DynamicProperty 2-2532	listing for folder 2-4447
meta.event 2-2536	mex.getCompilerConfigurations $2\text{-}2561$
meta.method 2-2538	MException
meta.package class 2-2541	constructor 2-1251 2-2567
meta.property 2-2544	methods
methods	addCause 2-111
locating 2-4452	disp 2-1169
mex 2-2553	eq $2\text{-}1251$
mex build script	getReport 2-1741
switches 2-2554	isequal 2-2139
-arch 2-2555	last 2-2240
-argcheck $2\text{-}2555$	ne 2-2689
-c 2-2555	rethrow $2\text{-}3348$
-compatibleArrayDims $2 \hbox{-} 2555$	throw 2-3980
-cxx 2-2555	throwAsCaller 2-3984
-Dname $2\text{-}2555$	mexext $2-2573$
-Dname=value $2\text{-}2556$	mfilename $2\text{-}2574$
-f optionsfile $2\text{-}2556$	mget function 2-2575
-fortran $2\text{-}2556$	Microsoft Excel files
-g 2-2556	loading 2-4495
-h[elp] 2-2556	$\min\ 2\text{-}2576$
-inline $2\text{-}2556$	min (timeseries) $2\text{-}2577$
-Ipathname $2 \hbox{-} 2556$	Min, Uicontrol property 2-4131
-largeArrayDims $2 ext{-} 2557$	MinColormap, Figure property 2-1429
-Lfolder $2\text{-}2557$	MinorGridLineStyle, Axes property 2-316
-lname $2\text{-}2557$	minres $2 ext{-} 2581$
-n 2-2557	minus (function equivalent for -) 2-49
name=value $2\text{-}2558$	mislocked $2\text{-}2586$

mkdir $2\text{-}2587$	mu-law encoded audio signals 2-2306 2-2656
mkdir (ftp) $2-2590$	multibandread 2-2657
mkpp 2-2591	multibandwrite 2-2662
mldivide (function equivalent for \) 2-49	multidimensional arrays
mlint 2-2604	concatenating 2-518
mlintrpt 2-2614	interpolation of 2-2096
suppressing messages 2-2616	number of dimensions of 2-2684
mlock 2-2617	rearranging dimensions of 2-2117 2-2995
mmfileinfo 2-2618	removing singleton dimensions of 2-3613
mod 2-2626	reshaping 2-3339
modal matrix 2-1217	size of 2-3527
mode 2-2628	sorting elements of 2-3548
mode objects	multiple
pan, using 2-2883	least common 2-2253
rotate3d, using 2-3392	multiplication
zoom, using 2-4525	array (arithmetic operator) 2-45
models	matrix (defined) 2-45
saving 2-3415	of polynomials 2-920
modification date	multistep ODE solver 2-2809
of a file 2-1160	munlock 2-2668
modified Bessel functions	
relationship to Airy functions 2-143	N
modulo arithmetic 2-2626	
MonitorPositions	Name, Figure property 2-1430
Root property 2-3376	namelengthmax 2-2670
Moore-Penrose pseudoinverse 2-3004	naming conventions
more 2-2631 2-2656	functions 2-1615
move 2-2633	NaN 2-2671
movefile $2\text{-}2635$	NaN (Not-a-Number) 2-2671
movegui function 2-2638	returned by rem 2-3322
movie 2-2641	nargchk 2-2673
movie2avi 2-2645	nargoutchk 2-2677
movies	native2unicode 2-2679
exporting in AVI format 2-282	ndgrid 2-2682
mpower (function equivalent for ^) 2-50	ndims 2-2684
mput function 2-2648	ne 2-2685
mrdivide (function equivalent for /) 2-49	ne, MException method 2-2689
msgbox 2-2649	nearest neighbor interpolation 2-2079 2-2089
$\texttt{mtimes}\ 2\text{-}2652$	2-2093 2-2096
mtimes (function equivalent for *) 2-49	NET

summary of functions 2-2692 return information about netCDF .NET dimension 2-2740 summary of functions 2-2692 netcdf.ingDimID netcdf return dimension ID for netCDF file 2-2741 summary of capabilities 2-2710 2-2743 netcdf.ingLibVers netcdf.abort return version of netCDF library 2-2742 revert recent netCDF file definitions 2-2713 netcdf.ingVarID netcdf.close return netCDF variable identifier 2-2745 close netCDF file 2-2715 netcdf.open open an existing netCDF file 2-2746 netcdf.copyAtt copy attribute to new location 2-2716 netcdf.putAtt write a netCDF attribute 2-2747 netcdf.create create netCDF file 2-2718 netcdf.putVar write data to netCDF variable 2-2749 netcdf.defDim create dimension in netCDF file 2-2720 netcdf.reDef netcdf.defVar put netCDF file into define mode 2-2751 define variable in netCDF dataset 2-2721 netcdf.renameAtt netcdf.delAtt netCDF function to change the name of an delete netCDF attribute 2-2722 attribute 2-2752 netcdf.endDef netcdf.renameDim takes a netCDF file out of define mode 2-2724 netCDF function to change the name of a netcdf.getAtt dimension 2-2754 return data from netCDF attribute 2-2726 netcdf.renameVar change the name of a netCDF netcdf.getConstant variable 2-2756 get numeric value of netCDF constant 2-2728 netcdf.getConstantNames netcdf.setDefaultFormatget list of netCDF constants 2-2729 change the default netCDF file format 2-2758 netcdf.getVar netcdf.setFill set netCDF fill behavior 2-2759 return data from netCDF variable 2-2730 netcdf.ing netcdf.sync return information about netCDF file 2-2733 synchronize netCDF dataset to disk 2-2760 netcdf.ingAtt newplot 2-2761return information about a netCDF NextPlot attribute 2-2735 Axes property 2-316 netcdf.ingAttID Figure property 2-1430 return identifier of netCDF attribute 2-2737 nextpow2 2-2765netcdf.ingAttName nnz 2-2766 return name of netCDF attribute 2-2738 no derivative method 2-1542 netcdf.ingDim nodesktop startup option 2-2477 nonzero entries

specifying maximum number of in sparse	real 2-3249
matrix 2-3559	smallest positive 2-3252
nonzero entries (in sparse matrix)	NumberTitle, Figure property 2-1430
allocated storage for 2-2789	numel 2-2787
number of 2-2766	numeric format 2-1554
replacing with ones 2-3590	numerical differentiation formula ODE
vector of 2-2768	solvers 2-2809
nonzeros 2-2768	numerical evaluation
norm 2-2769	double integral 2-1045
1-norm 2-2769 2-3238	triple integral 2-4033
2-norm (estimate of) 2-2771	nzmax 2-2789
F-norm 2-2769	
infinity 2-2769	0
matrix 2-2769	
pseudoinverse and 2-3004 2-3006	object
vector 2-2769	determining class of 2-2123
normal vectors, computing for volumes 2-2178	object classes, list of predefined 2-2123
NormalMode	objects
Patch property 2-2943	Java 2-2156
Surface property 2-3835	ODE file template 2-2812
surfaceplot property 2-3858	ODE solver properties
normest 2-2771	error tolerance 2-2819
not 2-2772	event location 2-2826
not (function equivalent for ~) 2-60	Jacobian matrix 2-2827
notebook 2-2773	mass matrix 2-2831
notify 2-2774	ode15s 2-2834
now 2-2775	solver output 2-2821
nthroot 2-2776	step size 2-2824
null 2-2777	ODE solvers
null space 2-2777	backward differentiation formulas 2-2834
num2cell 2-2779	numerical differentiation formulas 2-2834
$\verb num2hex 2-2782$	obtaining solutions at specific times 2-2797
num2str 2-2783	variable order solver 2-2834
number	ode15i function 2-2790
of array dimensions 2-2684	odefile 2-2811
numbers	odeget 2-2817
imaginary 2-1950	odephas2 output function 2-2823
NaN 2-2671	odephas3 output function 2-2823
plus infinity 2-2037	odeplot output function 2-2823
prime 2-3071	odeprint output function 2-2823

odeset 2-2818	ordqz $2 ext{-}2870$
odextend 2-2836	ordschur 2-2872
off-screen figures, displaying 2-1503	orient $2\text{-}2874$
OffCallback	orth 2-2876
Uitoggletool property 2-4279	orthographic projection, setting and
%#ok 2-2607	querying 2-499
OnCallback	otherwise 2-2877
Uitoggletool property 2-4279	Out of memory (error message) 2-2878
one-step ODE solver 2-2808	OuterPosition
ones 2-2841	Axes property 2-316
online documentation, displaying 2-1850	Figure property 2-1431
online help 2-1846	output
openfig 2-2846	checking number of arguments 2-2677
OpenGL 2-1437	controlling display format 2-1554
autoselection criteria 2-1441	in Command Window 2-2631
opening	number of arguments 2-2675
files in Windows applications 2-4469	output points (ODE)
openvar 2-2853	increasing number of 2-2821
operating system	output properties (DDE) 2-1084
MATLAB is running on 2-867	output properties (ODE) 2-2821
operating system command 2-3901	increasing number of output points 2-2821
operating system command, issuing 2-68	overflow 2-2037
operators	overloading
arithmetic 2-44	arithmetic operators 2-50
logical 2-56 2-63	relational operators 2-54
overloading arithmetic 2-50	special characters 2-69
overloading relational 2-54	
relational 2-54 2-2401	P
symbols 2-1846	-
optimget $2 ext{-} 2857$	P-files
optimization parameters structure 2-2857 to	checking existence of 2-1307
2-2858	pack 2-2878
optimizing file execution 2-3105	padecoef 2-2880
optimset $2 - 2858$	pagesetupdlg 2-2881
or 2-2862	paging
or (function equivalent for) 2-60	of screen 2-1848
ordeig 2-2864	paging in the Command Window 2-2631
orderfields 2-2867	pan mode objects 2-2883
ordering	PaperOrientation, Figure property 2-1432
reverse Cuthill-McKee 2-3883 2-3893	PaperPosition, Figure property 2-1432

PaperPositionMode, Figure property 2-1432	partial fraction expansion 2-3341
PaperSize, Figure property 2-1433	pascal 2-2900
PaperType, Figure property 2-1433	Pascal matrix 2-2900 2-3060
PaperUnits, Figure property 2-1434	patch 2-2901
parametric curve, plotting 2-1340	Patch
Parent	converting a surface to 2-3809
areaseries property 2-232	creating 2-2901
Axes property 2-318	properties 2-2921
barseries property 2-364	reducing number of faces 2-3280
contour property 2-906	reducing size of face 2-3516
errorbar property 2-1275	path 2-2948
Figure property 2-1435	building from parts 2-1611
hggroup property 2-1873	path2rc 2-2951
hgtransform property 2-1902	pathnames
Image property 2-1971	of functions or files 2-4452
Light property 2-2301	pathsep 2-2952
Line property 2-2325	pathtool 2-2953
lineseries property 2-2339	pause 2-2955
Patch property 2-2943	pauses, removing 2-1040
quivergroup property 2-3198	pausing function execution 2-2955
rectangle property 2-3275	pbaspect 2-2957
Root property 2-3377	PBM
scatter property 2-3441	parameters that can be set when
stairseries property 2-3638	writing 2-2018
stem property 2-3672	PBM files
Surface property 2-3835	writing 2-2013
surfaceplot property 2-3859	pcg 2-2963
Text property 2-3945	pchip 2-2967
Uicontextmenu property 2-4106	pcode 2-2970
Uicontrol property 2-4132	pcolor 2-2972
Uimenu property 2-4172	PCX files
Uipushtool property 2-4209	writing 2-2013
Uitable property 2-4263	PDE. See Partial Differential Equations
Uitoggletool property 2-4279	pdepe 2-2976
Uitoolbar property 2-4290	pdeval 2-2989
parentheses (special characters) 2-66	percent sign (special characters) 2-68
parfor 2-2893	percent-brace (special characters) 2-68
parse method	perfect matching 2-1188
of inputParser object 2-2895	performance 2-374
parseSoapResponse 2-2898	

period (.), to distinguish matrix and array	generating grid arrays for 2-2525
operations 2-44	slice plot 2-3536
period (special characters) 2-67	PlotBoxAspectRatio, Axes property 2-318
perl 2-2992	PlotBoxAspectRatioMode, Axes property 2-318
perl function 2-2992	plotedit 2-3029
Perl scripts in MATLAB 2-2992	plotting
perms 2-2994	3-D plot 2-3025
permutation	contours (a 2-1320
matrix 2-2430	contours (ez function) 2-1320
of array dimensions 2-2995	ez-function mesh plot 2-1328
random 2-3223	feather plots 2-1366
permutations of n elements 2-2994	filled contours 2-1324
permute 2-2995	function plots 2-1562
persistent 2-2996	functions with discontinuities 2-1348
persistent variable 2-2996	histogram plots 2-1907
perspective projection, setting and	in polar coordinates 2-1343
querying 2-499	isosurfaces 2-2181
PGM	loglog plot 2-2403
parameters that can be set when	mathematical function 2-1336
writing 2-2018	mesh contour plot 2-1332
PGM files	mesh plot 2-2520
writing 2-2013	parametric curve 2-1340
phase angle, complex 2-168	plot with two y-axes 2-3036
phase, complex	ribbon plot 2-3360
correcting angles 2-4318	rose plot 2-3384
pie 2-3000	scatter plot 2-3032
pie3 2-3002	scatter plot, 3-D 2-3426
pinv 2-3004	semilogarithmic plot 2-3458
planerot 2-3007	stem plot, 3-D 2-3658
platform MATLAB is running on 2-867	surface plot 2-3803
playshow function 2-3012	surfaces 2-1346
plot	velocity vectors 2-873
editing 2-3029	volumetric slice plot 2-3536
plot (timeseries) 2-3019	. See visualizing
plot box aspect ratio of axes 2-2957	plus (function equivalent for +) 2-49
plot editing mode	PNG
overview 2-3030	writing options for 2-2019
Plot Editor	alpha 2-2019
interface 2-3030 2-3113	background color 2-2019
plot, volumetric	chromaticities 2-2020

gamma 2-2020	eigenvalue problem 2-3051
interlace type 2-2020	evaluation 2-3058
resolution 2-2021	evaluation (matrix sense) 2-3060
significant bits 2-2020	make piecewise 2-2591
transparency 2-2021	multiplication 2-920
PNG files	polyval 2-3058
writing 2-2013	polyvalm 2-3060
PNM files	poorly conditioned
writing 2-2013	matrix 2-1906
Pointer, Figure property 2-1435	poorly conditioned eigenvalues 2-337
PointerLocation, Root property 2-3377	pop-up menus 2-4110
PointerShapeCData, Figure property 2-1435	defining choices 2-4135
PointerShapeHotSpot, Figure property 2-1436	Portable Anymap files
PointerWindow, Root property 2-3378	writing 2-2013
pol2cart 2-3041	Portable Bitmap (PBM) files
polar 2-3043	writing 2-2013
polar coordinates 2-3041	Portable Graymap files
computing the angle 2-168	writing 2-2013
converting from Cartesian 2-512	Portable Network Graphics files
converting to cylindrical or Cartesian 2-3041	writing 2-2013
plotting in 2-1343	Portable pixmap format
poles of transfer function 2-3341	writing 2-2013
poly 2-3045	Position
polyarea 2-3048	annotation ellipse property 2-183
polyder 2-3050	annotation line property 2-186
polyeig 2-3051	annotation rectangle property 2-190
polyfit 2-3053	arrow property 2-175
polygamma function 2-3118	Axes property 2-319
polygon	doubletarrow property 2-180
area of 2-3048	Figure property 2-1436
creating with patch 2-2901	Light property 2-2301
detecting points inside 2-2046	Text property 2-3945
polyint $2-3057$	textarrow property 2-195
polynomial	textbox property 2-206
analytic integration 2-3057	Uicontextmenu property 2-4106
characteristic 2-3045 to 2-3046 2-3382	Uicontrol property 2-4132
coefficients (transfer function) 2-3341	Uimenu property 2-4173
curve fitting with 2-3053	Uitable property 2-4263
derivative of 2-3050	position of camera
division 2-1102	dollying 2-485

position of camera, setting and querying 2-497	interpolated shading 2-3089
Position, rectangle property 2-3275	on MS-Windows 2-3087
PostScript	with a variable file name 2-3090
default printer 2-3079	with nodisplay 2-3082
levels 1 and 2 2-3079	with noFigureWindows 2-3082
printing interpolated shading 2-3089	with non-normal EraseMode 2-2321 2-2933
pow2 2-3062	2-3272 2-3828 2-3933
power 2-3063	printing figures
matrix. See matrix exponential	preview 2-3094
of real numbers 2-3253	printing tips 2-3087
of two, next 2-2765	printing, suppressing 2-67
power (function equivalent for .^) 2-50	printpreview $2 ext{-} 3094$
PPM	prod 2-3103
parameters that can be set when	product
writing 2-2018	cumulative 2-979
PPM files	Kronecker tensor 2-2238
writing 2-2013	of array elements 2-3103
ppval 2-3064	of vectors (cross) 2-966
preallocation	scalar (dot) 2-966
matrix 2-4520	profile $2\text{-}3105$
precision 2-1554	profsave 2-3112
prefdir 2-3066	projection type, setting and querying 2-499
preferences 2-3070	ProjectionType, Axes property 2-319
opening the dialog box 2-3070	prompting users for input 2-2048
present working directory 2-3136	prompting users to choose an item 2-2518
prime factors 2-1360	propedit 2-3113 to 2-3114
dependence of Fourier transform on 2-1382	proppanel $2\text{-}3117$
2-1384 to 2-1385	pseudoinverse 2-3004
prime numbers 2-3071	psi 2-3118
primes 2-3071	push buttons 2-4111
printdlg 2-3093	pwd $2\text{-}3136$
printdlg function 2-3093	
printer	Q
default for linux and unix 2-3079	
printer drivers	qmr 2-3137
GhostScript drivers 2-3074	QR decomposition
interploated shading 2-3089	deleting column from 2-3145
MATLAB printer drivers 2-3074	qrdelete 2-3145
printing	qrinsert 2-3147
GUIs 2-3088	qrupdate $2\text{-}3149$

quad 2-3152	randn $2 ext{-}3222$
quadgk 2-3161	setDefaultStream 2-3490
quadl 2-3167	range space 2-2876
quadrature 2-3152 2-3161	rank $2\text{-}3231$
quadv 2-3170	rank of a matrix 2-3231
quantization	RAS files
performed by rgb2ind 2-3356	parameters that can be set when
questdlg 2-3173	writing 2-2022
questdlg function 2-3173	writing 2-2014
quit 2-3177	RAS image format
quitting MATLAB 2-3177	specifying color order 2-2022
quiver 2-3180	writing alpha data 2-2022
quiver3 2-3183	Raster image files
qz 2-3208	writing 2-2014
QZ factorization 2-3052 2-3208	rational fraction approximation 2-3232
	rbbox 2-3236 2-3287
R	rcond 2-3238
	rdivide (function equivalent for ./) 2-49
radio buttons 2-4111	readasync 2-3243
rand, RandStream method 2-3212	reading
randi, RandStream method 2-3217	data from files 2-3954
randn, RandStream method 2-3222	formatted data from file 2-1596
random	readme files, displaying 2-2130 2-4451
permutation 2-3223	real 2-3249
sparse matrix 2-3596 to 2-3597	real numbers 2-3249
symmetric sparse matrix 2-3598	reallog $2\text{-}3250$
random number generators 2-2371 2-3212	realmax $2 ext{-} 3251$
2-3217 2-3222 2-3225 2-3229	realmin $2 ext{-} 3252$
randperm 2-3223	realpow $2 ext{-} 3253$
randStream	realsqrt $2 ext{-} 3254$
constructor 2-3229	rearrange array
RandStream 2-3225 2-3229	flip along dimension 2-1527
constructor 2-3225	reverse along dimension 2-1527
methods	rearrange matrix
create 2-956	flip left-right 2-1528
get 2-1704	flip up-down 2-1529
getDefaultStream 2-1721	reverse column order 2-1528
list 2-2371	reverse row order 2-1529
rand 2-3212	RearrangeableColumn
randi 2-3217	Uitable property 2-4264

rearranging arrays	removets $2 ext{-} 3325$
converting to vector 2-71	rename function 2-3327
removing first n singleton dimensions 2-3513	renaming
removing singleton dimensions 2-3613	using copyfile 2-933
reshaping 2-3339	renderer
shifting dimensions 2-3513	OpenGL 2-1437
swapping dimensions 2-2117 2-2995	painters 2-1437
rearranging matrices	zbuffer 2-1437
converting to vector 2-71	Renderer, Figure property 2-1437
rotating 90\xfb 2-3388	RendererMode, Figure property 2-1441
transposing 2-67	repeatedly executing statements 2-1552 2-4455
record 2-3255	repeatedly executing statements in
rectangle	parallel 2-2894
properties 2-3264	replicating a matrix 2-3328
rectangle function 2-3259	repmat 2-3328
rectint 2-3277	resample (timeseries) 2-3330
RecursionLimit	resample (tscollection) 2-3333
Root property 2-3378	reset 2-3336
recycle 2-3278	reshape 2-3339
reduced row echelon form 2-3399	residue $2 ext{-} 3341$
reducepatch 2-3280	residues of transfer function 2-3341
reducevolume 2-3284	Resize, Figure property 2-1442
reference page	ResizeFcn, Figure property 2-1442
accessing from doc 2-1191	restoredefaultpath $2\text{-}3345$
refresh 2-3287	$rethrow\ 2\text{-}3346$
regexprep 2-3307	rethrow, MException method 2-3348
regexptranslate 2-3311	return 2-3352
regression	reverse
linear 2-3053	array along dimension 2-1527
regularly spaced vectors, creating 2-70 2-2370	array dimension 2-1527
rehash 2-3316	matrix column order 2-1528
relational operators 2-54 2-2401	matrix row order 2-1529
relational operators for handle objects 2-3320	reverse Cuthill-McKee ordering 2-3883 2-3893
relative accuracy	RGB images
BVP 2-472	converting to indexed 2-3355
DDE 2-1083	RGB, converting to HSV 2-3354
norm of DDE solution 2-1083	rgb2hsv $2\text{-}3354$
norm of ODE solution 2-2820	rgb2ind $2\text{-}3355$
ODE 2-2820	rgbplot 2-3358
rem 2-3322	ribbon 2-3360

right-click and context menus 2-4097	in inverse Hilbert matrix 2-2113
rmappdata function 2-3363	partial fraction expansion and 2-3342
rmdir 2-3364	polynomial roots and 2-3382
rmdir (ftp) function 2-3367	sparse matrix conversion and 2-3563
rmfield 2-3368	RowName
rmpath 2-3369	Uitable property 2-4264
rmpref function 2-3370	RowStriping
RMS. See root-mean-square	Uitable property 2-4265
rolling camera 2-501	rref 2-3399
root folder 2-2470	rrefmovie 2-3399
Root graphics object 2-3371	rsf2csf 2-3401
root object 2-3371	rubberband box 2-3236
root, see rootobject 2-3371	$\operatorname{run}\ 2\text{-}3403$
root-mean-square	Runge-Kutta ODE solvers 2-2808
of vector 2-2769	running average 2-1490
roots 2-3382	
roots of a polynomial 2-3045 to 2-3046 2-3382	S
rose 2-3384	_
Rosenbrock	save 2-3404 2-3411
banana function 2-1540	serial port I/O 2-3413
ODE solver 2-2809	saveas 2-3415
rosser 2-3387	savepath 2-3421
rot90 2-3388	saving
rotate 2-3389	ASCII data 2-3404
rotate3d 2-3392	session to a file 2-1155
rotate3d mode objects 2-3392	workspace variables 2-3404
rotating camera 2-493	scalar product (of vectors) 2-966
rotating camera target 2-495	scaled complementary error function
Rotation, Text property 2-3946	(defined) 2-1252
rotations	scatter 2-3423
Jacobi 2-3598	scatter3 2-3426
round 2-3398	scattered data, aligning
to nearest integer 2-3398	multi-dimensional 2-2682
towards infinity 2-722	scattergroup
towards minus infinity 2-1531	properties 2-3429
towards zero 2-1526	Schmidt semi-normalized Legendre
roundoff error	functions 2-2272
characteristic polynomial and 2-3046	schur 2-3448
effect on eigenvalues 2-337	Schur decomposition 2-3448
evaluating matrix functions 2-1628	Schur form of matrix 2-3401 2-3448

screen, paging 2-1848	scatter property 2-3441
ScreenDepth, Root property 2-3378	stairseries property 2-3638
ScreenPixelsPerInch, Root property 2-3379	stem property 2-3673
ScreenSize, Root property 2-3379	Surface property 2-3835
script 2-3451	surfaceplot property 2-3859
declaration 2-1615	Text property 2-3946
scrolling screen 2-1848	Uicontrol property 2-4133
search path	Uitable property 2-4265
adding folders to 2-126	selecting areas 2-3236
MATLAB 2-2948	SelectionHighlight
modifying 2-2953	areaseries property 2-232
removing folders from 2-3369	Axes property 2-320
toolbox folder 2-4021	barseries property 2-364
user folder 2-4331	contour property 2-907
viewing 2-2953	errorbar property 2-1276
search, string 2-1511	Figure property 2-1444
sec 2-3452	hggroup property 2-1873
secant 2-3452	hgtransform property 2-1902
hyperbolic 2-3455	Image property 2-1972
inverse 2-244	Light property 2-2302
inverse hyperbolic 2-247	Line property 2-2325
secd 2-3454	lineseries property 2-2339
$\mathrm{sech}\ 2\text{-}3455$	Patch property 2-2943
Selected	quivergroup property 2-3199
areaseries property 2-232	rectangle property 2-3275
Axes property 2-320	scatter property 2-3441
barseries property 2-364	stairseries property 2-3639
contour property 2-906	stem property 2-3673
errorbar property 2-1275	Surface property 2-3835
Figure property 2-1444	surfaceplot property 2-3859
hggroup property 2-1873	Text property 2-3946
hgtransform property 2-1902	Uicontrol property 2-4133
Image property 2-1972	Uitable property 2-4265
Light property 2-2302	SelectionType, Figure property 2-144
Line property 2-2325	selectmoveresize $2\text{-}3457$
lineseries property 2-2339	semicolon (special characters) 2-67
Patch property 2-2943	sendmail $2\text{-}3461$
quivergroup property 2-3199	Separator
rectangle property 2-3275	Uipushtool property 2-4210
Root property 2-3379	Uitoggletool property 2-4279

Separator, Uimenu property 2-4173	calllib 2-481
sequence of matrix names (M1 through M12)	libfunctions $2\text{-}2281$
generating 2-1288	libfunctionsview 2-2282
serial 2-3463	libisloaded 2-2283
serialbreak 2-3466	libpointer 2-2285
server (FTP)	libstruct 2-2287
connecting to 2-1608	loadlibrary 2-2388
server variable 2-1374	unloadlibrary $2\text{-}4304$
session	shell script 2-3901 2-4301
saving 2-1155	shiftdim $2\text{-}3513$
set 2-3467 2-3475	shifting array
serial port I/O 2-3480	circular 2-774
timer object 2-3482	ShowArrowHead
set (timeseries) $2-3485$	quivergroup property 2-3199
set (tscollection) 2-3486	ShowBaseLine
set hgsetget class method 2-3476	barseries property 2-364
set operations	ShowHiddenHandles, Root property 2-3380
difference 2-3491	showplottool $2\text{-}3514$
exclusive or 2-3509	ShowText
intersection 2-2103	contour property 2-907
membership 2-2164	shrinkfaces 2-3516
union 2-4296	shutdown 2-3177
unique 2-4298	$\operatorname{sign}\ 2\text{-}3520$
setabstime (timeseries) 2-3487	signum function 2-3520
setabstime (tscollection) 2-3488	simplex search 2-1542
setappdata 2-3489	Simpson's rule, adaptive recursive 2-3154
setDefaultStream, RandStream method 2-3490	Simulink
setdiff 2-3491	version number, comparing 2-4370
setdisp hgsetget class method 2-3493	version number, displaying 2-4364
setenv 2-3494	sine
setinterpmethod 2-3498	hyperbolic 2-3525
setpixelposition 2-3500	inverse hyperbolic 2-253
setpref function 2-3503	single $2\text{-}3524$
setstr 2-3504	single quote (special characters) 2-67
settimeseriesnames 2-3508	singular value
setxor 2-3509	decomposition 2-3231 2-3872
shading $2-3510$	largest 2-2769
shading colors in surface plots 2-3510	rank and 2-3231
shared libraries	$\sinh~2 ext{-}3525$
MATLAB functions	size

array dimesions 2-3527	undo checkout 2-4294
serial port I/O 2-3532	spalloc 2-3558
size (timeseries) 2-3533	sparse 2-3559
size (tscollection) 2-3535	sparse matrix
size of array dimensions 2-3527	allocating space for 2-3558
size of fonts, see also FontSize property 2-3949	applying function only to nonzero elements
size vector 2-3339	of 2-3576
SizeData	density of 2-2766
scatter property 2-3442	detecting 2-2199
SizeDataSource	diagonal 2-3564
scatter property 2-3442	finding indices of nonzero elements of 2-1497
slice 2-3536	identity 2-3575
slice planes, contouring 2-915	number of nonzero elements in 2-2766
sliders 2-4111	permuting columns of 2-850
SliderStep, Uicontrol property 2-4133	random 2-3596 to 2-3597
smallest array elements 2-2576	random symmetric 2-3598
smooth3 2-3542	replacing nonzero elements of with
smoothing 3-D data 2-3542	ones 2-3590
soccer ball (example) 2-3893	results of mixed operations on 2-3560
solution statistics (BVP) 2-477	specifying maximum number of nonzero
sort 2-3548	elements 2-3559
sorting	vector of nonzero elements 2-2768
array elements 2-3548	visualizing sparsity pattern of 2-3607
complex conjugate pairs 2-954	sparse storage
matrix rows 2-3552	criterion for using 2-1610
sortrows 2-3552	spaugment $2\text{-}3561$
sound 2-3555 2-3557	spconvert 2-3562
converting vector into 2-3555 2-3557	spdiags $2 ext{-} 3564$
files	special characters
reading 2-279 2-4432	descriptions 2-1846
writing 2-281 2-4438	overloading 2-69
playing 2-4430	specular $2 ext{-} 3574$
recording 2-4436	SpecularColorReflectance
resampling 2-4430	Patch property 2-2944
sampling 2-4436	Surface property 2-3835
source control on UNIX platforms	surfaceplot property 2-3859
checking out files	SpecularExponent
function 2-755	Patch property 2-2944
source control systems	Surface property 2-3836
checking in files 2-752	surfaceplot property 2-3860

SpecularStrength	startat
Patch property 2-2944	timer object 2-3645
Surface property 2-3836	startup $2 ext{-} 3647$
surfaceplot property 2-3860	folder and path 2-4331
speye 2-3575	startup file 2-3647
spfun 2-3576	startup files 2-2469
sph2cart 2-3578	State
sphere 2-3579	Uitoggletool property 2-4280
sphereical coordinates	static text 2-4111
defining a Light position in 2-2304	$\operatorname{std}\ 2\text{-}3648$
spherical coordinates 2-3578	std (timeseries) 2-3650
spinmap 2-3582	stem 2-3652
spline 2-3583	$stem3\ 2-3658$
spline interpolation (cubic)	step size (DDE)
one-dimensional 2-2080 2-2090 2-2093	initial step size 2-1087
2-2096	upper bound 2-1087
Spline Toolbox 2-2085	step size (ODE) 2-1086 2-2824
spones 2-3590	initial step size 2-2825
spparms 2-3591	upper bound 2-2825
sprand 2-3596	stop
sprandn 2-3597	timer object 2-3679
sprandsym 2-3598	stopasync 2-3680
sprank 2-3599	stopwatch timer 2-3987
spreadsheets	storage
loading WK1 files 2-4474	allocated for nonzero entries (sparse) 2-2789
loading XLS files 2-4495	sparse 2-3559
reading into a matrix 2-1180	storage allocation 2-4520
writing from matrix 2-4477	$str2cell\ 2\text{-}745$
writing matrices into 2-1184	str2double 2-3681
sqrt 2-3609	$str2func\ 2\text{-}3682$
sqrtm 2-3610	str2mat 2-3686
square root	$\operatorname{str2num}\ 2\text{-}3687$
of a matrix 2-3610	strcat 2-3691
of array elements 2-3609	stream lines
of real numbers 2-3254	computing 2-D 2-3697
squeeze 2-3613	computing 3-D 2-3699
stack, displaying 2-1051	drawing 2-3701
standard deviation 2-3648	stream2 2-3697
start	stream3 2-3699
timer object 2-3644	stretch-to-fill 2-289

$\operatorname{strfind} 2-3730$	sub2ind $2\text{-}3767$
string	subfunction 2-1615
comparing one to another 2-3693 2-3736	$subplot\ 2\text{-}3770$
converting from vector to 2-751	subplots
converting matrix into 2-2461 2-2783	assymetrical 2-3775
converting to lowercase 2-2412	suppressing ticks in 2-3778
converting to numeric array 2-3687	subscripts
converting to uppercase 2-4325	in axis title 2-4017
dictionary sort of 2-3552	in text strings 2-3950
finding first token in 2-3751	subspace 2-3787
searching and replacing 2-3748	subsref (function equivalent for
searching for 2-1511	A(i,j,k)) 2-68
String	subtraction (arithmetic operator) 2-44
Text property 2-3946	subvolume 2-3792
textarrow property 2-195	$sum\ 2\text{-}3795$
textbox property 2-207	cumulative 2-981
Uicontrol property 2-4134	of array elements 2-3795
string matrix to cell array conversion 2-745	sum (timeseries) $2 ext{-} 3798$
strings 2-3732	superscripts
strjust 2-3734	in axis title 2-4017
strmatch 2-3735	in text strings 2-3950
strread 2-3739	support 2-3802
strrep 2-3748	surf2patch 2-3809
strtok 2-3751	surface 2-3811
$\operatorname{strtrim}\ 2\text{-}3755$	Surface
struct 2-3756	and contour plotter 2-1353
struct2cell 2-3761	converting to a patch 2-3809
structfun $2 - 3762$	creating 2-3811
structure array	defining default properties 2-3262 2-3815
getting contents of field of 2-1724	plotting mathematical functions 2-1346
remove field from 2-3368	properties 2-3816 2-3839
setting contents of a field of 2-3496	surface normals, computing for volumes 2-2178
structure arrays	surfl 2-3866
field names of 2-1403	surfnorm $2\text{-}3870$
structures	$\operatorname{svd}\ 2\text{-}3872$
dynamic fields 2-67	svds $2\text{-}3875$
strvcat 2-3765	swapbytes 2-3878
Style	switch $2\text{-}3880$
Light property 2-2302	symamd 2-3882
Uicontrol property 2-4137	symbfact 2-3886

symbols	Text property 2-3951
operators 2-1846	Uicontextmenu property 2-4107
symbols in text 2-196 2-207 2-3947	Uicontrol property 2-4137
symmlq 2-3888	Uimenu property 2-4173
symrcm 2-3893	Uipushtool property 2-4210
synchronize 2-3896	Uitable property 2-4265
syntax, command 2-3898	Uitoggletool property 2-4280
syntax, function 2-3898	Uitoolbar property 2-4290
syntaxes	Tagged Image File Format (TIFF)
function, defining 2-1615	writing 2-2014
system 2-3901	tan $2\text{-}3904$
UNC pathname error 2-3902	tand $2\text{-}3906$
system folder	tangent 2-3904
temporary 2-3911	four-quadrant, inverse 2-261
	hyperbolic 2-3907
т	inverse 2-259
1	inverse hyperbolic 2-264
table lookup. See interpolation	tanh 2-3907
Tag	tar 2-3909
areaseries property 2-232	target, of camera 2-502
Axes property 2-320	tempdir 2-3911
barseries property 2-365	tempname 2-3912
contour property 2-907	temporary
errorbar property 2-1276	files 2-3912
Figure property 2-1445	system folder 2-3911
hggroup property 2-1873	tensor, Kronecker product 2-2238
hgtransform property 2-1903	terminating MATLAB 2-3177
Image property 2-1972	test matrices 2-1644
Light property 2-2302	
Line property 2-2326	test, logical. See logical tests and detecting
lineseries property 2-2340	tetrahedron
Patch property 2-2944	mesh plot 2-3913
quivergroup property 2-3199	tetramesh 2-3913
rectangle property 2-3275	TeX commands in text 2-196 2-207 2-3947
Root property 2-3380	text 2-3918
	editing 2-3029
scatter property 2-3443	subscripts 2-3950
stairseries property 2-3639	superscripts 2-3950
stem property 2-3673	Text
Surface property 2-3836	creating 2-3918
surfaceplot property 2-3860	defining default properties 2-3921

fixed-width font 2-3935	TIFF image format
properties 2-3923	specifying color space 2-2022
TextBackgroundColor	tiling (copies of a matrix) 2-3328
textarrow property 2-198	time
TextColor	CPU 2-955
textarrow property 2-198	elapsed (stopwatch timer) 2-3987
TextEdgeColor	required to execute commands 2-128-
textarrow property 2-198	time and date functions 2-1245
TextLineWidth	timer
textarrow property 2-198	properties 2-4002
TextList	timer object 2-4002
contour property 2-908	timerfind
TextListMode	timer object 2-4009
contour property 2-908	timerfindall
TextMargin	timer object 2-4011
textarrow property 2-198	times (function equivalent for .*) 2-49
textread 2-3954	timeseries $2 ext{-} 4013$
TextRotation, textarrow property 2-199	timestamp 2-1160
textscan 2-3960	title 2-4016
TextStep	with superscript 2-4017
contour property 2-909	Title, Axes property 2-322
TextStepMode	todatenum 2-4019
contour property 2-909	toeplitz 2-4020
textwrap 2-3974	Toeplitz matrix 2-4020
tfqmr 2-3977	toggle buttons 2-4111
throw, MException method 2-3980	token 2-3751
throwAsCaller, MException method 2-3984	See also string
TickDir, Axes property 2-321	Toolbar
TickDirMode, Axes property 2-321	Figure property 2-1446
TickLength, Axes property 2-321	Toolbox
TIFF	Spline 2-2085
compression 2-2023	toolbox folder, path 2-4021
encoding 2-2018	toolboxdir $2\text{-}4021$
ImageDescription field 2-2023	TooltipString
maxvalue 2-2018	Uicontrol property 2-4137
parameters that can be set when	Uipushtool property 2-4210
writing 2-2022	Uitable property 2-4266
resolution 2-2023	Uitoggletool property 2-4280
writemode 2-2023	trace $2-4022$
writing 2-2014	trace of a matrix 2-1151 2-4022

trailing blanks	tsdata.event $2 ext{-}4060$
removing 2-1094	tsearchn 2-4062
transform	tsprops $2-4063$
hgtransform function 2-1881	tstool 2-4068
transform, Fourier	type $2-4069$
discrete, n-dimensional 2-1385	Туре
discrete, one-dimensional 2-1379	areaseries property 2-233
discrete, two-dimensional 2-1384	Axes property 2-322
inverse, n-dimensional 2-1940	barseries property 2-365
inverse, one-dimensional 2-1936	contour property 2-909
inverse, two-dimensional 2-1938	errorbar property 2-1276
shifting the zero-frequency component	Figure property 2-1446
of 2-1388	hggroup property 2-1874
transformation	hgtransform property 2-1903
See also conversion 2-535	Image property 2-1973
transformations	Light property 2-2302
elementary Hermite 2-1677	Line property 2-2326
transmitting file to FTP server 2-2648	lineseries property 2-2340
transpose	Patch property 2-2945
array (arithmetic operator) 2-46	quivergroup property 2-3200
matrix (arithmetic operator) 2-46	rectangle property 2-3276
transpose (function equivalent for .\q) $2-50$	Root property 2-3380
transpose (timeseries) $2\text{-}4023$	scatter property 2-3443
trapz $2\text{-}4025$	stairseries property 2-3640
treelayout 2-4027	stem property 2-3674
treeplot 2-4028	Surface property 2-3836
triangulation	surfaceplot property 2-3861
2-D plot 2-4035	Text property 2-3951
tril 2-4030	Uicontextmenu property 2-4107
$trimesh\ 2\text{-}4031$	Uicontrol property 2-4138
triple integral	Uimenu property 2-4173
numerical evaluation 2-4033	Uipushtool property 2-4211
triplequad 2-4033	Uitable property 2-4266
triplot $2-4035$	Uitoggletool property 2-4281
trisurf $2-4049$	Uitoolbar property 2-4291
triu $2\text{-}4051$	typecast $2\text{-}4070$
true $2-4052$	
truth tables (for logical operations) 2-56	U
try 2-4053	
tscollection 2-4057	UData

errorbar property 2-1277	Uicontrol
quivergroup property 2-3201	defining default properties 2-4114
UDataSource	fixed-width font 2-4124
errorbar property 2-1277	types of 2-4108
quivergroup property 2-3201	Uicontrol Properties 2-4114
Uibuttongroup	uicontrols
defining default properties 2-4079	printing 2-3088
uibuttongroup function 2-4074	uigetdir $2\text{-}4141$
Uibuttongroup Properties 2-4079	uigetfile $2\text{-}4145$
uicontextmenu 2-4097	uigetpref function 2-4156
UiContextMenu	uiimport $2\text{-}4160$
Uicontrol property 2-4138	uimenu $2\text{-}4161$
Uipushtool property 2-4211	Uimenu
Uitoggletool property 2-4281	creating 2-4161
Uitoolbar property 2-4291	defining default properties 2-4163
UIContextMenu	Properties 2-4163
areaseries property 2-233	Uimenu Properties 2-4163
Axes property 2-323	uint16 $2\text{-}4175$
barseries property 2-365	uint 32 $2-4175$
contour property 2-910	uint64 $2\text{-}4175$
errorbar property 2-1277	uint8 2-2075 2-4175
Figure property 2-1447	uiopen $2\text{-}4177$
hggroup property 2-1874	Uipanel
hgtransform property 2-1903	defining default properties 2-4182
Image property 2-1973	uipanel function 2-4179
Light property 2-2303	Uipanel Properties 2-4182
Line property 2-2326	uipushtool $2\text{-}4199$
lineseries property 2-2340	Uipushtool
Patch property 2-2945	defining default properties 2-4202
quivergroup property 2-3200	Uipushtool Properties 2-4202
rectangle property 2-3276	uiputfile $2\text{-}4212$
scatter property 2-3443	uiresume $2\text{-}4221$
stairseries property 2-3640	uisave $2-4223$
stem property 2-3674	uisetcolor function 2-4226
Surface property 2-3837	uisetfont $2\text{-}4227$
surfaceplot property 2-3861	uisetpref function 2-4229
Text property 2-3951	uistack 2-4230
Uitable property 2-4266	Uitable
Uicontextmenu Properties 2-4100	defining default properties 2-4239
uicontrol 2-4108	fixed-width font 2-4258

uitable function 2-4231	untar 2-4316
Uitable Properties 2-4239	unwrap 2-4318
uitoggletool 2-4268	unzip $2-4323$
Uitoggletool	up vector, of camera 2-504
defining default properties 2-4271	updating figure during file execution 2-1202
Uitoggletool Properties 2-4271	uplus (function equivalent for unary +) 2-49
uitoolbar 2-4282	upper 2-4325
Uitoolbar	upper triangular matrix 2-4051
defining default properties 2-4284	uppercase to lowercase 2-2412
Uitoolbar Properties 2-4284	url
uiwait 2-4292	opening in Web browser 2-4440
uminus (function equivalent for unary \xd0	usejava 2-4329
) 2-49	user input
UNC pathname error and dos 2-1197	from a button menu 2-2518
UNC pathname error and system 2-3902	UserData
unconstrained minimization 2-1538	areaseries property 2-233
undefined numerical results 2-2671	Axes property 2-324
undocheckout 2-4294	barseries property 2-366
unicode2native 2-4295	contour property 2-910
unimodular matrix 2-1677	errorbar property 2-1278
union $2\text{-}4296$	Figure property 2-1448
unique 2-4298	hggroup property 2-1874
Units	hgtransform property 2-1904
annotation ellipse property 2-183	Image property 2-1973
annotation rectangle property 2-190	Light property 2-2303
arrow property 2-175	Line property 2-2326
Axes property 2-323	lineseries property 2-2341
doublearrow property 2-180	Patch property 2-2945
Figure property 2-1447	quivergroup property 2-3200
line property 2-186	rectangle property 2-3276
Root property 2-3380	Root property 2-3381
Text property 2-3951	scatter property 2-3444
textarrow property 2-199	stairseries property 2-3640
textbox property 2-209	stem property 2-3674
Uicontrol property 2-4138	Surface property 2-3837
Uitable property 2-4266	surfaceplot property 2-3861
unix $2-4301$	Text property 2-3952
unloadlibrary $2\text{-}4304$	Uicontextmenu property 2-4107
unlocking functions 2-2668	Uicontrol property 2-4139
$\operatorname{unmkpp}\ 2\text{-}4309$	Uimenu property 2-4173

Uipushtool property 2-4211	product (cross) 2-966
Uitable property 2-4267	vector field, plotting 2-873
Uitoggletool property 2-4281	vectorize $2-4363$
Uitoolbar property 2-4291	vectorizing ODE function (BVP) 2-474
userpath 2-4331	vectors, creating
	logarithmically spaced 2-2409
v	regularly spaced 2-70 2-2370
	velocity vectors, plotting 2-873
validateattributes 2-4340	ver 2-4364
validatestring $2\text{-}4349$	verctrl function (Windows) 2-4366
Value, Uicontrol property 2-4139	verLessThan 2-4370
vander $2\text{-}4356$	version $2\text{-}4372$
Vandermonde matrix 2-3055	version numbers
var 2-4357	comparing 2-4370
var (timeseries) $2\text{-}4358$	displaying 2-4364
varargin $2\text{-}4360$	vertcat $2-4374$
varargout 2-4362	vertcat (function equivalent for [2-68
variable numbers of arguments 2-4362	vertcat (timeseries) 2-4376
variable-order solver (ODE) 2-2834	vertcat (tscollection) 2-4377
variables	VertexNormals
checking existence of 2-1307	Patch property 2-2945
clearing from workspace 2-790	Surface property 2-3837
global 2-1763	surfaceplot property 2-3861
in workspace 2-4479	VerticalAlignment, Text property 2-3952
keeping some when clearing 2-796	VerticalAlignment, textbox property 2-199
linking to graphs with linkdata 2-2355	2-209
listing 2-4461	Vertices, Patch property 2-2946
local 2-1615 2-1763	video
name of passed 2-2053	saving in AVI format 2-282
opening 2-2853	view 2-4381
persistent 2-2996	azimuth of viewpoint 2-4381
saving 2-3404	coordinate system defining 2-4382
sizes of 2-4461	elevation of viewpoint 2-4381
VData	view angle, of camera 2-506
quivergroup property 2-3202	View, Axes property (obsolete) 2-324
VDataSource	viewing
quivergroup property 2-3202	a group of object 2-491
vector	a specific object in a scene 2-491
dot product 2-1198	viewmtx $2-4384$
frequency 2-2409	Visible

areaseries property 2-234	reducing face size in isosurfaces 2-3516
Axes property 2-324	reducing number of elements in 2-3284
barseries property 2-366	voronoi $2\text{-}4397$
contour property 2-910	Voronoi diagrams
errorbar property 2-1278	multidimensional vizualization 2-4404
Figure property 2-1448	two-dimensional vizualization 2-4397
hggroup property 2-1875	voronoin $2\text{-}4404$
hgtransform property 2-1904	
Image property 2-1973	W
Light property 2-2303	
Line property 2-2326	wait
lineseries property 2-2341	timer object 2-4408
Patch property 2-2946	waitbar $2\text{-}4409$
quivergroup property 2-3201	waitfor $2\text{-}4413$
rectangle property 2-3276	waitforbuttonpress 2-4417
Root property 2-3381	warndlg $2\text{-}4418$
scatter property 2-3444	warning $2\text{-}4421$
stairseries property 2-3640	warning message (enabling, suppressing, and
stem property 2-3674	displaying) 2-4421
Surface property 2-3837	waterfall $2\text{-}4425$
surfaceplot property 2-3862	.wav files
Text property 2-3953	reading 2-4432
Uicontextmenu property 2-4107	writing 2-4438
Uicontrol property 2-4140	waverecord 2-4436
Uimenu property 2-4174	wavfinfo $2-4429$
Uipushtool property 2-4211	wavplay $2-4430$
Uitable property 2-4267	wavread 2-4429 2-4432
Uitoggletool property 2-4281	wavrecord 2-4436
Uitoolbar property 2-4291	wavwrite 2-4438
visualizing	WData
	quivergroup property 2-3203
cell array structure 2-743	WDataSource
sparse matrices 2-3607 volumes	quivergroup property 2-3203
	web 2-4440
calculating isosurface data 2-2181	Web browser
computing 2-D stream lines 2-3697	displaying help in 2-1850
computing 3-D stream lines 2-3699	pointing to file or url 2-4440
computing isosurface normals 2-2178	weekday 2-4445
contouring slice planes 2-915	well conditioned 2-3238
drawing stream lines 2-3701	
end caps 2-2171	what $2\text{-}4447$

whatsnew $2\text{-}4451$	X
which $2\text{-}4452$	X
while $2\text{-}4455$	annotation arrow property 2-176 2-180
white space characters, ASCII 2-2198 2-3751	annotation line property 2-187
whitebg $2\text{-}4459$	textarrow property 2-200
who, whos	X Windows Dump files
who 2-4461	writing 2-2014
wilkinson 2-4468	x-axis limits, setting and querying 2-4490
Wilkinson matrix 2-3568 2-4468	XAxisLocation, Axes property 2-324
WindowButtonDownFcn, Figure property 2-1448	XColor, Axes property 2-325
WindowButtonMotionFcn, Figure	XData
property 2-1449	areaseries property 2-234
WindowButtonUpFcn, Figure property 2-1450	barseries property 2-366
WindowKeyPressFcn , Figure property $2-1450$	contour property 2-910
${\tt WindowKeyReleaseFcn}\ , Figure\ property\ 2\text{-}1452$	errorbar property 2-1278
Windows Paintbrush files	Image property 2-1974
writing 2-2013	Line property 2-2327
WindowScrollWheelFcn, Figure property 2-1452	lineseries property 2-2341
WindowStyle, Figure property 2-1455	Patch property 2-2946
winopen $2-4469$	quivergroup property 2-3204
winqueryreg $2-4471$	scatter property 2-3444
WK1 files	stairseries property 2-3640
loading 2-4474	stem property 2-3675
writing from matrix 2-4477	Surface property 2-3837
wk1finfo $2\text{-}4473$	surfaceplot property 2-3862
wk1read 2-4474	XDataMode
wk1write 2-4477	areaseries property 2-234
workspace 2-4479	barseries property 2-366
changing context while debugging 2-1044	contour property 2-911
2-1069	errorbar property 2-1278
clearing items from 2-790	lineseries property 2-2341
consolidating memory 2-2878	quivergroup property 2-3204
predefining variables 2-3647	stairseries property 2-3641
saving 2-3404	stem property 2-3675
variables in 2-4461	surfaceplot property 2-3862
viewing contents of 2-4479	XDataSource
workspace variables	areaseries property 2-235
reading from disk 2-2379	barseries property 2-367
WVisual, Figure property 2-1457	contour property 2-911
WVisualMode, Figure property 2-1459	errorbar property 2-1279

lineseries property 2-2342	Y
quivergroup property 2-3204	Υ
scatter property 2-3444	annotation arrow property 2-176 2-181 2-187
stairseries property 2-3641	textarrow property 2-200
stem property 2-3675	y-axis limits, setting and querying 2-4490
surfaceplot property 2-3862	YAxisLocation, Axes property 2-324
XDir, Axes property 2-325	YColor, Axes property 2-325
XDisplay, Figure property 2-1460	YData
XGrid, Axes property 2-326	areaseries property 2-235
xlabel 2-4488	barseries property 2-367
XLabel, Axes property 2-326	contour property 2-912
xlim 2-4490	errorbar property 2-1279
XLim, Axes property 2-327	Image property 2-1974
XLimMode, Axes property 2-327	Line property 2-2327
XLS files	lineseries property 2-2342
loading 2-4495	Patch property 2-2946
xlsfinfo $2-4493$	quivergroup property 2-3205
xlsread 2-4495	scatter property 2-3445
xlswrite $2-4505$	stairseries property 2-3642
XMinorGrid, Axes property 2-328	stem property 2-3676
xmlread 2-4510	Surface property 2-3838
xmlwrite $2-4515$	surfaceplot property 2-3863
xor 2-4516	YDataMode
XOR, printing 2-227 2-359 2-901 2-1269 2-1899	contour property 2-912
$2 - 1969 \ 2 - 2321 \ 2 - 2334 \ 2 - 2933 \ 2 - 3193 \ 2 - 3272$	quivergroup property 2-3205
$2 - 3436 \ 2 - 3633 \ 2 - 3667 \ 2 - 3828 \ 2 - 3851 \ 2 - 3933$	surfaceplot property 2-3863
XScale, Axes property 2-328	YDataSource
xslt 2-4517	areaseries property 2-236
XTick, Axes property 2-328	barseries property 2-368
XTickLabel, Axes property 2-329	contour property 2-912
XTickLabelMode, Axes property 2-330	errorbar property 2-1280
XTickMode, Axes property 2-329	lineseries property 2-2343
XVisual, Figure property 2-1460	quivergroup property 2-3206
XVisualMode, Figure property 2-1462	scatter property 2-3445
XWD files	stairseries property 2-3642
writing 2-2014	stem property 2-3676
xyz coordinates . See Cartesian coordinates	surfaceplot property 2-3863
	YDir, Axes property 2-325
	YGrid, Axes property 2-326
	ylabel 2-4488

YLabel, Axes property 2-326 ylim 2-4490 YLim, Axes property 2-327 YLimMode, Axes property 2-327 YMinorGrid, Axes property 2-328 YScale, Axes property 2-328 YTick, Axes property 2-328 YTickLabel, Axes property 2-329 YTickLabelMode, Axes property 2-330 YTickMode, Axes property 2-329

Z

z-axis limits, setting and querying 2-4490 ZColor, Axes property 2-325 ZData

contour property 2-913 Line property 2-2327 lineseries property 2-2343 Patch property 2-2946 quivergroup property 2-3206 scatter property 2-3446 stemseries property 2-3677 Surface property 2-3838 surfaceplot property 2-3864

ZDataSource

contour property 2-913 lineseries property 2-2343 2-3677 scatter property 2-3446 surfaceplot property 2-3864 ZDir, Axes property 2-325 zero of a function, finding 2-1638 zeros 2-4519 ZGrid, Axes property 2-326 Ziggurat 2-3225 2-3229 zip 2-4521zlabel 2-4488 zlim 2-4490 ZLim, Axes property 2-327 ZLimMode, Axes property 2-327 ZMinorGrid, Axes property 2-328 zoom 2-4524zoom mode objects 2-4525 ZScale, Axes property 2-328 ZTick, Axes property 2-328 ZTickLabel, Axes property 2-329 ZTickLabelMode, Axes property 2-330 ZTickMode, Axes property 2-329