



# Simulink® Design Verifier™

## User's Guide

R2014b



# MATLAB® & SIMULINK®



## How to Contact MathWorks



Latest news: [www.mathworks.com](http://www.mathworks.com)  
Sales and services: [www.mathworks.com/sales\\_and\\_services](http://www.mathworks.com/sales_and_services)  
User community: [www.mathworks.com/matlabcentral](http://www.mathworks.com/matlabcentral)  
Technical support: [www.mathworks.com/support/contact\\_us](http://www.mathworks.com/support/contact_us)



Phone: 508-647-7000



The MathWorks, Inc.  
3 Apple Hill Drive  
Natick, MA 01760-2098

*Simulink<sup>®</sup> Design Verifier<sup>™</sup> User's Guide*

© COPYRIGHT 2007–2014 by The MathWorks, Inc.

The software described in this document is furnished under a license agreement. The software may be used or copied only under the terms of the license agreement. No part of this manual may be photocopied or reproduced in any form without prior written consent from The MathWorks, Inc.

**FEDERAL ACQUISITION:** This provision applies to all acquisitions of the Program and Documentation by, for, or through the federal government of the United States. By accepting delivery of the Program or Documentation, the government hereby agrees that this software or documentation qualifies as commercial computer software or commercial computer software documentation as such terms are used or defined in FAR 12.212, DFARS Part 227.72, and DFARS 252.227-7014. Accordingly, the terms and conditions of this Agreement and only those rights specified in this Agreement, shall pertain to and govern the use, modification, reproduction, release, performance, display, and disclosure of the Program and Documentation by the federal government (or other entity acquiring for or through the federal government) and shall supersede any conflicting contractual terms or conditions. If this License fails to meet the government's needs or is inconsistent in any respect with federal procurement law, the government agrees to return the Program and Documentation, unused, to The MathWorks, Inc.

### Trademarks

Prover, Prover Technology, Prover Plug-In and the Prover logo are trademarks or registered trademarks of Prover Technology AB in Sweden, the United States and in other countries. MATLAB and Simulink are registered trademarks of The MathWorks, Inc. See [www.mathworks.com/trademarks](http://www.mathworks.com/trademarks) for a list of additional trademarks. Other product or brand names may be trademarks or registered trademarks of their respective holders.

### Patents

MathWorks products are protected by one or more U.S. patents. Please see [www.mathworks.com/patents](http://www.mathworks.com/patents) for more information.

### **Revision History**

May 2007	Online only	New for Version 1.0 (Release 2007a+)
September 2007	Online only	Revised for Version 1.1 (Release 2007b)
March 2008	Online only	Revised for Version 1.2 (Release 2008a)
October 2008	Online only	Revised for Version 1.3 (Release 2008b)
March 2009	Online only	Revised for Version 1.4 (Release 2009a)
September 2009	Online only	Revised for Version 1.5 (Release 2009b)
March 2010	Online only	Revised for Version 1.6 (Release 2010a)
September 2010	Online only	Revised for Version 1.7 (Release 2010b)
April 2011	Online only	Revised for Version 2.0 (Release 2011a)
September 2011	Online only	Revised for Version 2.1 (Release 2011b)
March 2012	Online only	Revised for Version 2.2 (Release 2012a)
September 2012	Online only	Revised for Version 2.3 (Release 2012b)
March 2013	Online only	Revised for Version 2.4 (Release 2013a)
September 2013	Online only	Revised for Version 2.5 (Release 2013b)
March 2014	Online only	Revised for Version 2.6 (Release 2014a)
October 2014	Online only	Revised for Version 2.7 (Release 2014b)



## Acknowledgments

---

## Getting Started

---

**1**

<b>Simulink Design Verifier Product Description</b> .....	<b>1-2</b>
Key Features .....	<b>1-2</b>
<b>Simulink Design Verifier Block Library</b> .....	<b>1-3</b>
<b>Analyze a Model</b> .....	<b>1-4</b>
About This Example .....	<b>1-4</b>
Open the Model .....	<b>1-4</b>
Generate Test Cases .....	<b>1-5</b>
Combine Test Cases .....	<b>1-24</b>
<b>Analyze a Subsystem</b> .....	<b>1-26</b>
<b>Analyze a Stateflow Atomic Subchart</b> .....	<b>1-28</b>
Analyze an Atomic Subchart Using the Simulink Design Verifier Software .....	<b>1-28</b>
<b>Basic Workflow for Simulink Design Verifier</b> .....	<b>1-31</b>

## How the Simulink Design Verifier Software Works

---

**2**

<b>Analyze a Simple Model</b> .....	<b>2-2</b>
-------------------------------------	------------

<b>Model Blocks</b> .....	2-4
<b>Block Reduction</b> .....	2-5
<b>Inline Parameters</b> .....	2-6
<b>Large Models</b> .....	2-7
<b>Handle Incompatibilities with Automatic Stubbing</b> .....	2-8
What Is Automatic Stubbing? .....	2-8
How Automatic Stubbing Works .....	2-8
Analyze a Model Using Automatic Stubbing .....	2-10
<b>Nonfinite Data</b> .....	2-15
<b>Approximations</b> .....	2-16
Approximations During Model Analysis .....	2-16
Types of Approximations .....	2-16
Floating-Point to Rational Number Conversion .....	2-17
Linearization of Two-Dimensional Lookup Tables .....	2-17
While Loops .....	2-17
<b>Logic Operations Short-Circuiting</b> .....	2-19

## Checking Compatibility with the Simulink Design Verifier Software

### 3

<b>Check Model Compatibility</b> .....	3-2
Compatibility with Simulink Design Verifier .....	3-2
Run Compatibility Check .....	3-2
Compatibility Check Results .....	3-3
<b>Supported and Unsupported Simulink Blocks</b> .....	3-9
<b>Support Limitations for Simulink Software Features</b> .....	3-21
<b>Support Limitations for Model Blocks</b> .....	3-24

<b>Support Limitations for Stateflow Software Features . . . .</b>	<b>3-26</b>
ml Namespace Operator, ml Function, ml Expressions . . . .	3-26
C Math Functions . . . . .	3-26
Atomic Subcharts That Call Exported Graphical Functions Outside a Subchart . . . . .	3-27
Recursion and Cyclic Behavior . . . . .	3-27
Custom C or C++ Code . . . . .	3-29
Machine-Parented Data . . . . .	3-29
Textual Functions with Literal String Arguments . . . . .	3-29
<b>Support Limitations for MATLAB for Code Generation . . .</b>	<b>3-30</b>
Unsupported MATLAB for Code Generation Features . . . .	3-30
Support Limitations for MATLAB for Code Generation Library Functions . . . . .	3-30

## Working with Block Replacements

# 4

<b>What Is Block Replacement? . . . . .</b>	<b>4-2</b>
<b>Built-In Block Replacements . . . . .</b>	<b>4-3</b>
<b>Template for Block Replacement Rules . . . . .</b>	<b>4-5</b>
<b>Define Custom Block Replacements . . . . .</b>	<b>4-6</b>
Basic Workflow for Defining Custom Block Replacements . . .	4-6
Specify Replacement Blocks . . . . .	4-6
Write Block Replacement Rules . . . . .	4-7
Replace Multiport Switch Blocks . . . . .	4-7
<b>Execute Block Replacements . . . . .</b>	<b>4-14</b>
Configure Block Replacements . . . . .	4-14
Replace Blocks in a Model . . . . .	4-15

## Specifying Parameter Configurations

### 5

<b>Parameter Constraint Values</b> .....	5-2
Parameter Configuration for Analysis .....	5-2
Data Types in Parameter Configurations .....	5-3
<b>Define Constraint Values for Parameters</b> .....	5-4
Find Parameters and Autogenerate Constraints .....	5-5
Edit Parameter Constraints .....	5-8
Highlight Constrained Parameters in Model .....	5-9
<b>Specify Parameter Constraint Values for Full Coverage</b> ..	5-10
About This Example .....	5-10
Construct Example Model .....	5-11
Parameterize Constant Block .....	5-12
Preload Workspace Variable .....	5-12
Autogenerate Parameter Constraint .....	5-13
Analyze Example Model .....	5-14
Simulate Test Cases .....	5-17
<b>Store Parameter Constraints in MATLAB Code Files</b> .....	5-21
Export Parameter Constraints to File .....	5-21
Import Parameter Constraints from File .....	5-23
<b>Define Constraint Values for Parameters in MATLAB Code Files</b> .....	5-24
Template Parameter Configuration File .....	5-24
Syntax in Parameter Configuration Files .....	5-24

## Detecting Design Errors

### 6

<b>What Is Design Error Detection?</b> .....	6-2
<b>Derived Ranges in Design Error Detection</b> .....	6-3
<b>Run a Design Error Detection Analysis</b> .....	6-4
Workflow for Detecting Design Errors .....	6-4



Understand the Analysis Results .....	6-4
Review the Latest Analysis Results in the Model Explorer ..	6-6
<b>Dead Logic Detection .....</b>	<b>6-8</b>
Detect Dead Logic Only .....	6-8
Detect Dead and Active Logic .....	6-9
<b>Detect Dead Logic in Example Model .....</b>	<b>6-10</b>
Overview of Dead Logic Detection .....	6-10
Detect Dead Logic in Example Model .....	6-10
Review Analysis Results for Example Model .....	6-11
Review Analysis Report for Example Model .....	6-12
<b>Model Objects That Receive Dead Logic Detection .....</b>	<b>6-14</b>
Abs .....	6-15
Dead Zone .....	6-15
Discrete-Time Integrator .....	6-16
Enabled Subsystem .....	6-16
Enabled and Triggered Subsystem .....	6-17
Fcn .....	6-17
For Iterator, For Iterator Subsystem .....	6-17
If, If Action Subsystem .....	6-18
Library-Linked Objects .....	6-18
Logical Operator .....	6-18
MATLAB Function .....	6-18
MinMax .....	6-19
Model .....	6-19
Multiport Switch .....	6-19
Rate Limiter .....	6-19
Relay .....	6-20
Saturation .....	6-20
Stateflow Charts .....	6-21
Switch .....	6-21
SwitchCase, SwitchCase Action Subsystem .....	6-21
Triggered Models .....	6-21
Triggered Subsystem .....	6-22
While Iterator, While Iterator Subsystem .....	6-22
<b>Detect Integer Overflow and Division-by-Zero Errors .....</b>	<b>6-23</b>
About This Example .....	6-23
Analyze the Model .....	6-23
Review the Analysis Results .....	6-24
Limitation of Integer Overflow Detection .....	6-27

<b>Check for Specified Intermediate Minimum and Maximum Signal Values</b> .....	<b>6-28</b>
Overview of Specified Minimum and Maximum Signal Values .....	6-28
About This Example .....	6-29
Create the Example Model .....	6-29
Analyze the Model .....	6-30
Review the Analysis Results .....	6-31
<b>Detect Out of Bound Array Access Errors</b> .....	<b>6-35</b>
Design Error Detection for Out of Bound Array Access .....	6-35
Detect Out of Bound Array Access in Example Model .....	6-35
Limitations of Support for Out of Bound Array Access Design Error Detection .....	6-41

## Generating Test Cases

# 7

<b>What Is Test Case Generation?</b> .....	<b>7-2</b>
Test Case Blocks .....	7-2
Test Case Functions .....	7-2
<b>Workflow for Test Case Generation</b> .....	<b>7-4</b>
<b>Generate Test Cases for Model Decision Coverage</b> .....	<b>7-5</b>
Construct the Example Model .....	7-5
Check Compatibility of the Example Model .....	7-6
Configure Test Generation Options .....	7-7
Analyze the Example Model .....	7-8
Review Analysis Results .....	7-8
Customize Test Generation .....	7-17
Reanalyze the Example Model .....	7-19
Analyze Contradictory Models .....	7-20
<b>Generate Test Cases for a Subsystem</b> .....	<b>7-21</b>
<b>Select Components for Test Case Generation</b> .....	<b>7-22</b>
Test Generation Advisor .....	7-22
Test Generation Advisor Requirements .....	7-24
Identify Analyzable Components .....	7-24

Analyze and Generate Tests for Model Components . . . . .	7-24
<b>Model Coverage Objectives for Test Generation . . . . .</b>	<b>7-28</b>
Decision . . . . .	7-28
Condition . . . . .	7-28
MCDC . . . . .	7-29
Relational Boundary . . . . .	7-29

## Extending Existing Test Cases

# 8

<b>When to Extend Existing Test Cases . . . . .</b>	<b>8-2</b>
<b>Common Workflow for Extending Existing Test Cases . . . . .</b>	<b>8-4</b>
<b>Extend Test Cases for Model with Temporal Logic . . . . .</b>	<b>8-5</b>
Create Starting Test Case . . . . .	8-5
Log Starting Test Case . . . . .	8-8
Extend Existing Test Cases . . . . .	8-9
Verify Analysis Results . . . . .	8-11
<b>Extend Test Cases for Closed-Loop System . . . . .</b>	<b>8-12</b>
Log Starting Test Case . . . . .	8-12
Extend Existing Test Cases . . . . .	8-15
<b>Extend Test Cases for Modified Model . . . . .</b>	<b>8-19</b>
Create Starting Test Cases . . . . .	8-19
Extend Existing Test Cases . . . . .	8-20

## Achieving Test Cases for Missing Model Coverage

# 9

<b>Generate Test Cases for Missing Coverage Data . . . . .</b>	<b>9-2</b>
<b>Achieve Missing Coverage in Referenced Model . . . . .</b>	<b>9-3</b>
Record Coverage Data for Example Model . . . . .	9-3
Find Test Cases for the Missing Coverage . . . . .	9-5

Achieve Missing Coverage .....	9-5
Verify 100% Model Coverage .....	9-6
<b>Missing Coverage in Subsystems and Model Blocks .....</b>	<b>9-7</b>
<b>Achieve Missing Coverage in Closed-Loop Simulation</b>	
<b>Model .....</b>	<b>9-8</b>
Record Coverage Data for the Model .....	9-8
Find Test Cases for Missing Coverage .....	9-9
<b>Modified Condition and Decision Coverage in Simulink</b>	
<b>Design Verifier .....</b>	<b>9-12</b>

## Verifying Model Components

# 10

<b>What Is Component Verification? .....</b>	<b>10-2</b>
Component Verification Approaches .....	10-2
Simulink Design Verifier Tools for Component Verification ..	10-2
<b>Functions for Component Verification .....</b>	<b>10-4</b>
<b>Verify a Component for Code Generation .....</b>	<b>10-6</b>
About the Example Model .....	10-6
Prepare the Component for Verification .....	10-8
Record Coverage for the Component .....	10-9
Use Simulink Design Verifier Software to Record Additional Coverage .....	10-10
Combine the Harness Models .....	10-12
Execute the Component in Simulation Mode .....	10-13
Execute the Component in Software-in-the-Loop (SIL) Mode .....	10-13

## Considering Specified Minimum and Maximum Values for Inputs During Analysis

### 11

<b>Minimum and Maximum Input Constraints</b> .....	11-2
Simulink Design Verifier Support for Specified Input Minimum and Maximum Values .....	11-2
Limitations of Simulink Design Verifier Support for Specified Minimum and Maximum Values .....	11-3
<b>Specify Input Range for Inport Blocks</b> .....	11-4
<b>Specified Input Ranges in sldvData Fields</b> .....	11-5
<b>Specify Input Range for Simulink.Signal Objects</b> .....	11-6
<b>Specify Input Range for Stateflow Data Objects</b> .....	11-7
<b>Specify Input Range for Subsystems</b> .....	11-9
<b>Specify Input Range for Global Data Stores</b> .....	11-11

## Proving Properties of a Model

### 12

<b>What Is Property Proving?</b> .....	12-2
Proof Blocks .....	12-2
Proof Functions .....	12-2
<b>Workflow for Proving Model Properties</b> .....	12-4
<b>Prove Properties in a Model</b> .....	12-5
About This Example .....	12-5
Construct Example Model .....	12-6
Check Compatibility of Example Model .....	12-7
Instrument Example Model .....	12-8
Configure Property-Proving Options .....	12-9
Analyze Example Model .....	12-10
Review Analysis Results .....	12-10

Customize Example Proof . . . . .	12-19
Reanalyze Example Model . . . . .	12-20
Review Results of Second Analysis . . . . .	12-20
Analyze Contradictory Models . . . . .	12-23
Prove Properties in a Large Model . . . . .	12-24
<b>Prove System-Level Properties Using Verification Model</b> . . . . .	<b>12-25</b>
When to Use a Verification Model for Property Proving . . . . .	12-25
About this Example . . . . .	12-25
Understand the Verification Model . . . . .	12-25
Prove the Properties of the Design Model . . . . .	12-26
Fix the Verification Model . . . . .	12-27
<b>Prove Properties in a Subsystem</b> . . . . .	<b>12-29</b>
<b>Model Requirements</b> . . . . .	<b>12-30</b>
Basic Properties . . . . .	12-30
Temporal Properties . . . . .	12-34

## Reviewing the Results

# 13

<b>Highlighted Results on the Model</b> . . . . .	<b>13-2</b>
Results Review with Model Highlighting . . . . .	13-2
Simulink Design Verifier Results Inspector . . . . .	13-2
Enable Highlighted Results on a Model . . . . .	13-3
Green Highlighting on Model . . . . .	13-5
Red Highlighting on Model . . . . .	13-6
Orange Highlighting on Model . . . . .	13-6
Gray Highlighting on Model . . . . .	13-8
<b>Simulink Design Verifier Data Files</b> . . . . .	<b>13-9</b>
Data File Generation . . . . .	13-9
Contents of sldvData Structure . . . . .	13-9
Model Information Fields in sldvData . . . . .	13-10
Simulate Models with Data Files . . . . .	13-15
Load Results from Data Files . . . . .	13-15
<b>Simulink Design Verifier Harness Models</b> . . . . .	<b>13-16</b>
Harness Model Generation . . . . .	13-16

Create a Harness Model . . . . .	13-16
Anatomy of a Harness Model . . . . .	13-17
Configuration of the Harness Model . . . . .	13-21
Simulate the Harness Model . . . . .	13-21
<b>Export Test Cases to SystemTest . . . . .</b>	<b>13-24</b>
<b>Simulink Design Verifier Reports . . . . .</b>	<b>13-27</b>
Simulink Design Verifier Report Generation . . . . .	13-27
Create Analysis Reports . . . . .	13-27
Front Matter . . . . .	13-28
Summary Chapter . . . . .	13-28
Analysis Information Chapter . . . . .	13-28
Derived Ranges Chapter . . . . .	13-33
Objectives Status Chapters . . . . .	13-34
Model Items Chapter . . . . .	13-41
Design Errors Chapter . . . . .	13-42
Test Cases Chapter . . . . .	13-43
Properties Chapter . . . . .	13-48
<b>Simulink Design Verifier Log Files . . . . .</b>	<b>13-50</b>
<b>Review Analysis Results . . . . .</b>	<b>13-52</b>
View Active Results . . . . .	13-52
Load Previous Results . . . . .	13-52
Explore Results . . . . .	13-52

## Analyzing Large Models and Improving Performance

# 14

<b>Sources of Model Complexity . . . . .</b>	<b>14-2</b>
<b>Analyze a Large Model . . . . .</b>	<b>14-3</b>
Types of Large Model Problems . . . . .	14-3
Summarize Model Hierarchy and Compatibility . . . . .	14-4
Use the Default Parameter Values . . . . .	14-4
Modify the Analysis Parameters . . . . .	14-6
Use the Large Model Optimization . . . . .	14-6
Stop the Analysis Before Completion . . . . .	14-6

<b>Increase Allocated Memory for Analysis Report Generation</b> .....	<b>14-8</b>
<b>Manage Model Data to Simplify the Analysis</b> .....	<b>14-9</b>
Simplify Data Types .....	<b>14-9</b>
Constrain Data .....	<b>14-9</b>
<b>Partition Model Inputs for Incremental Test Generation</b> .	<b>14-13</b>
<b>Bottom-Up Approach to Model Analysis</b> .....	<b>14-15</b>
<b>Extract Subsystems for Analysis</b> .....	<b>14-16</b>
Overview of Subsystem Extraction .....	<b>14-16</b>
sldvextract Function .....	<b>14-16</b>
Structure of the Extracted Model .....	<b>14-17</b>
Analyze Subsystems That Read from Global Data Storage .	<b>14-17</b>
Analyze Function-Call Subsystems .....	<b>14-20</b>
<b>Logical Operations</b> .....	<b>14-23</b>
<b>Models with Large Verification State Space</b> .....	<b>14-24</b>
<b>Counters and Timers</b> .....	<b>14-25</b>
<b>Prove Properties in Large Models</b> .....	<b>14-27</b>
Find Property Violations While Designing Your Model . . .	<b>14-27</b>
Combine Proving Properties and Finding Proof Violations .	<b>14-28</b>

## **15** Simulink Design Verifier Configuration Parameters

<b>Simulink Design Verifier Options</b> .....	<b>15-2</b>
Options in Configuration Parameters Dialog Box .....	<b>15-2</b>
Design Verification Options Objects .....	<b>15-2</b>
Command-Line Parameters for Design Verification Options	<b>15-2</b>
<b>Design Verifier Pane</b> .....	<b>15-11</b>
Design Verifier Pane Overview .....	<b>15-11</b>
Mode .....	<b>15-11</b>
Maximum analysis time .....	<b>15-13</b>



Display unsatisfiable test objectives . . . . .	15-13
Automatic stubbing of unsupported blocks and functions . .	15-14
Use specified input minimum and maximum values . . . . .	15-14
Output folder . . . . .	15-15
Make output file names unique by adding a suffix . . . . .	15-16
<b>Design Verifier Pane: Block Replacements . . . . .</b>	<b>15-18</b>
Block Replacements Pane Overview . . . . .	15-18
Apply block replacements . . . . .	15-18
List of block replacement rules . . . . .	15-19
File path of the output model . . . . .	15-20
<b>Design Verifier Pane: Parameters . . . . .</b>	<b>15-21</b>
Parameters Pane Overview . . . . .	15-22
Enable parameter configuration . . . . .	15-22
Use parameter configuration table . . . . .	15-23
Parameter configuration file . . . . .	15-24
Use . . . . .	15-25
Name . . . . .	15-26
Constraint . . . . .	15-26
Value . . . . .	15-27
Min . . . . .	15-28
Max . . . . .	15-28
Model Element . . . . .	15-29
<b>Design Verifier Pane: Test Generation . . . . .</b>	<b>15-30</b>
Test Generation Pane Overview . . . . .	15-31
Model coverage objectives . . . . .	15-31
Test conditions . . . . .	15-32
Test objectives . . . . .	15-33
Maximum test case steps . . . . .	15-33
Test suite optimization . . . . .	15-34
Extend existing test cases . . . . .	15-36
Data file . . . . .	15-37
Ignore objectives satisfied by existing test cases . . . . .	15-38
Ignore objectives satisfied in existing coverage data . . . . .	15-38
Coverage data file . . . . .	15-39
Ignore objectives based on filter . . . . .	15-40
Coverage filter file . . . . .	15-40
Include relational boundary objectives . . . . .	15-41
Floating point absolute tolerance . . . . .	15-42
Floating point relative tolerance . . . . .	15-43

<b>Design Verifier Pane: Design Error Detection</b> .....	<b>15-45</b>
Design Error Detection Pane Overview .....	15-45
Dead logic .....	15-45
Identify active logic .....	15-46
Integer overflow .....	15-47
Division by zero .....	15-48
Check specified intermediate minimum and maximum values .....	15-48
Out of bound array access .....	15-49
<b>Design Verifier Pane: Property Proving</b> .....	<b>15-51</b>
Property Proving Pane Overview .....	15-51
Assertion blocks .....	15-51
Proof assumptions .....	15-52
Strategy .....	15-53
Maximum violation steps .....	15-54
<b>Design Verifier Pane: Results</b> .....	<b>15-56</b>
Results Pane Overview .....	15-57
Save test data to file .....	15-57
Data file name .....	15-57
Include expected output values .....	15-58
Randomize data that do not affect the outcome .....	15-59
Display results of the analysis on the model .....	15-61
Save test harness as model .....	15-61
Harness model file name .....	15-62
Reference input model in generated harness .....	15-63
Save test harness as SystemTest TEST-file (will reference saved data file) .....	15-64
SystemTest file name .....	15-65
<b>Design Verifier Pane: Report</b> .....	<b>15-67</b>
Report Pane Overview .....	15-67
Generate report of the results .....	15-67
Report file name .....	15-68
Include screen shots of properties .....	15-69
Display report .....	15-70

## Glossary

---

# Acknowledgments

The Simulink<sup>®</sup> Design Verifier<sup>™</sup> software uses Prover Plug-In<sup>®</sup> products from Prover<sup>®</sup> Technology to generate test cases and prove model properties.





# Getting Started

---

- “Simulink Design Verifier Product Description” on page 1-2
- “Simulink Design Verifier Block Library” on page 1-3
- “Analyze a Model” on page 1-4
- “Analyze a Subsystem” on page 1-26
- “Analyze a Stateflow Atomic Subchart” on page 1-28
- “Basic Workflow for Simulink Design Verifier” on page 1-31

## Simulink Design Verifier Product Description

**Identify design errors, generate test vectors, and verify designs against requirements**

Simulink Design Verifier uses formal methods to identify hard-to-find design errors in models without requiring extensive tests or simulation runs. Design errors detected include dead logic, integer overflow, division by zero, and violations of design properties and assertions.

Simulink Design Verifier highlights blocks in the model containing these errors and blocks proven to be without them. For each block with an error, it calculates signal-range boundaries and generates a test vector that reproduces the error in simulation.

The generated test vectors provide simulation inputs that exercise functionality captured in the model structure and specified by the test objectives. The test vectors, together with the design properties and test objectives, can be used to verify code running in software-in-the-loop (SIL) and processor-in-the-loop (PIL) test configurations.


Learn more about verification, validation, and test in Model-Based Design and support for certification standards in automotive, aerospace, and industrial automation applications.

### Key Features

- Polyspace<sup>®</sup> and Prover Plug-In formal analysis engines
- Detection of dead logic, integer and fixed-point overflows, division by zero, and violations of design properties
- Blocks and functions for modeling functional and safety requirements
- Test vector generation from functional requirements and model coverage objectives, including condition, decision, and modified condition/decision (MCDC)
- Property proving, with generation of violation examples for analysis and debugging
- Fixed-point and floating-point model support

## Simulink Design Verifier Block Library

To open the Simulink Design Verifier block library, at the MATLAB® command prompt, type `sldvlib`.



The Simulink Design Verifier block library has three categories of blocks:

- Objectives and Constraints — Blocks that define custom objectives and constraints
- Temporal Operators — Blocks that define temporal properties on Boolean signals
- Verification Utilities — Miscellaneous verification utilities

The block library also has a sublibrary, Example Properties, that includes examples of how to specify common properties in your model. You can easily adapt these examples for use in your models.

## Analyze a Model

In this section...
“About This Example” on page 1-4
“Open the Model” on page 1-4
“Generate Test Cases” on page 1-5
“Combine Test Cases” on page 1-24

### About This Example

The following sections describe an example model, Cruise Control Test Generation. This example illustrates how to use the Simulink Design Verifier software to generate test cases that achieve complete model coverage. Through this example, you learn how to analyze models with the Simulink Design Verifier software and interpret the results.


### Open the Model

To open the Cruise Control Test Generation model, at the MATLAB prompt, enter:

```
sldvdemo_cruise_control
```



## Simulink Design Verifier Cruise Control Test Generation



This example shows how to generate test cases that achieve complete model coverage. By default, Simulink Design Verifier generates test cases that satisfy objectives in the fewest steps. One of the test objectives forces the discrete integrator in the PI controller to exceed its upper limit. When you run Simulink Design Verifier without constraints, the limit is exceeded in a single step by forcing speed to be 500. The constraint on speed limits the values in test cases between 0 and 100. This forces the test cases to take several samples to exceed the integrator limit.

**Run**  
(double-click)

Run Simulink Design Verifier

**Toggle Speed  
Constraint**  
(double-click)

Toggle Constraint

**View Options**  
(double-click)

View Simulink Design Verifier Options

## Generate Test Cases


- “Run Analysis” on page 1-6

- “Generate Analysis Results” on page 1-8
- “Highlight Analysis Results on Model” on page 1-9
- “Generate Detailed Analysis Report” on page 1-12
- “Create Harness Model” on page 1-19
- “Simulate Tests and Produce Model Coverage Report” on page 1-23

## **Run Analysis**

To generate test cases for the Cruise Control Test Generation model, open the model window and double-click the block labeled **Run**.

Simulink Design Verifier begins analyzing the model to generate test cases, and the Simulink Design Verifier Results Summary window opens. The Results Summary window displays a running log showing the progress of the analysis.



If you need to terminate an analysis while it is running, click **Stop**. The software asks if you want to produce results. If you click **Yes**, the software creates a data file based on the results achieved so far. The path name of the data file appears in the Results Summary window.

The data file is a MAT-file that contains a structure named `sldvData`. This structure stores the data that the software gathers and produces during the analysis.

For more information, see “Simulink Design Verifier Data Files” on page 13-9.

## **Generate Analysis Results**


When the Simulink Design Verifier software completes its analysis of the `sldvdemo_cruise_control` model, the Results Summary window displays several options:

- **Highlight analysis results on model**
- **Generate detailed analysis report**
- **Create harness model**
- **Simulate tests and produce a model coverage report**

---

**Note:** When you analyze other models, depending on the results of the analysis, you may see a subset of these four options.

---



The sections that follow describe these options in detail.

### Highlight Analysis Results on Model

In the Simulink Design Verifier Results Summary window, if you click **Highlight analysis results on model**, the software highlights objects in the model in three different colors, depending on the analysis results:

- “Green: Objectives Satisfied” on page 1-10



- “Orange: Objectives Undecided” on page 1-10
- “Red: Objectives Unsatisfiable” on page 1-11

When you highlight the analysis results on a model, the Simulink Design Verifier Results Inspector opens. When you click an object in the model that has analysis results, the Results Inspector displays the results summary for that object.

### Green: Objectives Satisfied

Green outline indicates that the analysis generated test cases for all the objectives for that block. If the block is a subsystem or Stateflow<sup>®</sup> atomic subchart, the green outline indicates that the analysis generated test cases for all objectives associated with the child objects.

For example, in the `sldvdemo_cruise_control` model, the green outline shows that the PI controller subsystem satisfied all test objectives. The Results Inspector lists the two satisfied test objectives for the PI controller subsystem.




### Orange: Objectives Undecided

Orange outline indicates that the analysis was not able to determine if an objective was satisfiable or not. This situation might occur when:

- The analysis times out
- The software satisfies test objectives without generating test cases due to:
  - Automatic stubbing errors
  - Limitations of the analysis engine



In the following example, the analysis timed out before it could determine if one of the objectives for the Discrete-Time Integrator block was satisfiable.



### Red: Objectives Unsatisfiable

Red outline indicates that the analysis found some objectives for which it could not generate test cases, most likely due to unreachable design elements in your model.

In the following example, input 2 always satisfies the criterion for the Switch block, so the Switch block never passes through the value of input 3.



## Generate Detailed Analysis Report

In the Simulink Design Verifier Results Summary window, if you click **Generate detailed analysis report**, the software saves and then opens a detailed report of the analysis. The path to the report is:

```
<current_folder>/sldv_output/...  
sldvdemo_cruise_control/sldvdemo_cruise_control_report.html
```

The HTML report includes the following chapters.



## Table of Contents

- [1. Summary](#)
- [2. Analysis Information](#)
- [3. Test Objectives Status](#)
- [4. Model Items](#)
- [5. Test Cases](#)

For a description of each report chapter, see:

- “Summary” on page 1-13
- “Analysis Information” on page 1-14
- “Test Objectives Status” on page 1-15
- “Model Items” on page 1-17
- “Test Cases” on page 1-18

### Summary

In the **Table of Contents**, click **Summary** to display the Summary chapter, which includes the following information:

- Name of the model
- Mode of the analysis (test generation, property proving, design error detection)
- Status of the analysis
- Length of the analysis in seconds
- Number of objectives satisfied

## Chapter 1. Summary

### Analysis Information

Model:	sldvdemo_cruise_control
Mode:	TestGeneration
Status:	Completed normally
Analysis Time:	7s

### Objectives Status

Number of Objectives:	34
Objectives Satisfied:	34

### Analysis Information

In the **Table of Contents**, click **Analysis Information** to display information about the analyzed model and the analysis options.

## Chapter 2. Analysis Information

### Table of Contents

[Model Information](#)

[Analysis Options](#)

[Constraints](#)

[Approximations](#)

### Model Information

File:	sldvdemo_cruise_control
Version:	1.56
Time Stamp:	Wed Jul 18 10:45:08 2012
Author:	The MathWorks Inc.

### Analysis Options

Mode:	TestGeneration
Test Suite Optimization:	CombinedObjectives
Maximum Testcase Steps:	500 time steps
Test Conditions:	UseLocalSettings
Test Objectives:	UseLocalSettings
Model Coverage Objectives:	MCDC
Maximum Analysis Time:	60s
Block Replacement:	off
Parameters Analysis:	on
Parameters Configuration File:	sldv_params_template.m
Save Data:	on
Save Harness:	off
Save Report:	off

### Test Objectives Status

In the **Table of Contents**, click **Test Objectives Status** to display a table of satisfied objectives. The following figure shows a partial list of the objectives satisfied in the Cruise Control Test Generation model.

## Chapter 3. Test Objectives Status

### Table of Contents

[Objectives Satisfied](#)

### Objectives Satisfied

Simulink Design Verifier found test cases that exercise these test objectives.

#	Type	Model Item	Description	Test Case
1	Decision	<a href="#">Controller/Switch3</a>	logical trigger input false (output is from 3rd input port)	<a href="#">8</a>
2	Decision	<a href="#">Controller/Switch3</a>	logical trigger input true (output is from 1st input port)	<a href="#">4</a>
3	Decision	<a href="#">Controller/Switch2</a>	logical trigger input false (output is from 3rd input port)	<a href="#">1</a>
4	Decision	<a href="#">Controller/Switch2</a>	logical trigger input true (output is from 1st input port)	<a href="#">8</a>
5	Decision	<a href="#">Controller/Switch1</a>	logical trigger input false (output is from 3rd input port)	<a href="#">5</a>
6	Decision	<a href="#">Controller/Switch1</a>	logical trigger input true (output is from 1st input port)	<a href="#">8</a>
7	Condition	<a href="#">Controller/Logical Operator1</a>	Logic: input port 1 T	<a href="#">3</a>
8	Condition	<a href="#">Controller/Logical Operator1</a>	Logic: input port 1 F	<a href="#">8</a>
9	Condition	<a href="#">Controller/Logical Operator2</a>	Logic: input port 1 T	<a href="#">8</a>
10	Condition	<a href="#">Controller/Logical Operator2</a>	Logic: input port 1 F	<a href="#">5</a>
11	Condition	<a href="#">Controller/Logical Operator2</a>	Logic: input port 2 T	<a href="#">6</a>
12	Condition	<a href="#">Controller/Logical Operator2</a>	Logic: input port 2 F	<a href="#">5</a>
13	MCDC	<a href="#">Controller/Logical Operator2</a>	Logic: MCDC expression for output with input port 1 T	<a href="#">8</a>

The **Objectives Satisfied** table lists the following information for the model:

- **#** — Objective number
- **Type** — Objective type
- **Model Item** — Element in the model for which the objective was tested. Click this link to display the model with this element highlighted.
- **Description** — Description of the objective
- **Test Case** — Test case that achieves the objective. Click this link for more information about that test case.

In the row for objective 34, click the test case number (7) to display more information about Test Case 7 in the report's **Test Cases** chapter.

## Test Case 7

### Summary

Length: 0.06 second (7 sample periods)  
 Objectives Satisfied: 1

### Objectives

Step	Time	Model Item	Objectives
7	0.06	<a href="#">Controller/PI Controller/Discrete-Time Integrator</a>	integration result >= upper limit T

### Generated Input Data

Time	0	0.01-0.05	0.06
Step	1	2-6	7
enable	1	1	1
brake	0	0	0
set	1	0	1
inc	1	1	-
dec	0	0	-
speed	97	0	0

In this example, Test Case 7 satisfies one objective, that the integration result be greater than or equal to the upper limit T in the Discrete-Time Integrator block. The table lists the values of the six signals from time 0 through time 0.06.

### Model Items

In the **Table of Contents**, click **Model Items** to see detailed information about each item in the model that defines coverage objectives. This table includes the status of the objective at the end of the analysis. Click the links in the table for detailed information about the satisfied objectives.

## Chapter 4. Model Items

### Table of Contents

[Controller/Switch3](#)  
[Controller/Switch2](#)  
[Controller/Switch1](#)  
[Controller/Logical Operator1](#)  
[Controller/Logical Operator2](#)  
[Controller/Logical Operator](#)  
[Controller/PI Controller](#)  
[Controller/PI Controller/Discrete-Time Integrator](#)

This section presents, for each object in the model defining coverage objectives, the list of objectives and their individual status at the end of the analysis. It should match the coverage report obtained from running the generated test suite on the model, either from the harness model or by using the `slvrtruntests` command.

### Controller/Switch3

[View](#)

#:	Type	Description	Status	Test Case
1	Decision	logical trigger input false (output is from 3rd input port)	Satisfied	<a href="#">8</a>
2	Decision	logical trigger input true (output is from 1st input port)	Satisfied	<a href="#">4</a>

### Controller/Switch2

[View](#)

#:	Type	Description	Status	Test Case
3	Decision	logical trigger input false (output is from 3rd input port)	Satisfied	<a href="#">1</a>
4	Decision	logical trigger input true (output is from 1st input port)	Satisfied	<a href="#">8</a>

### Test Cases


In the **Table of Contents**, click **Test Cases** to display detailed information about each generated test case, including:

- Length of time to execute the test case
- Number of objectives satisfied
- Detailed information about the satisfied objectives
- Input data

For an example, see the section for Test Case 7 in “Test Objectives Status” on page 1-15.


### Create Harness Model

In the Simulink Design Verifier Results Summary window, if you click **Create harness model**, the software creates and opens a harness model named `sldvdemo_cruise_control_harness`.



The harness model contains the following blocks:

- The Test Case Explanation block is a DocBlock block that documents the generated test cases. Double-click the Test Case Explanation block to view a description of each test case for the objectives that the test case satisfies.



```
Editor - S:\sca_sldv\sldvdemo_cruise_control_harness_testcases.txt
EDITOR VIEW close/clear all
New Open Save Find Files Insert fx
Compare Comment % Indent Go To Breakpoints
Print Find
FILE EDIT NAVIGATE BREAKPOINTS
sldvdemo_cruise_control_harness_test... x
1 Test Case 1 (1 Objectives)
2 Parameter values:
3
4 1. Controller/Switch2 - logical trigger input false (output is from 3rd input port) @ T=0.00
5
6 Test Case 2 (3 Objectives)
7 Parameter values:
8
9 1. Controller/Logical Operator - Logic: input port 1 F @ T=0.00
10 2. Controller/Logical Operator - Logic: MCDC expression for output with input port 1 F @ T=0.00
11 3. Controller/PI Controller - enable logical value F @ T=0.00
12
13 Test Case 3 (3 Objectives)
14 Parameter values:
15
16 1. Controller/Logical Operator1 - Logic: input port 1 T @ T=0.00
17 2. Controller/Logical Operator - Logic: input port 2 F @ T=0.00
18 3. Controller/Logical Operator - Logic: MCDC expression for output with input port 2 F @ T=0.00
19
20 Test Case 4 (1 Objectives)
21 Parameter values:
22
23 1. Controller/Switch3 - logical trigger input true (output is from 1st input port) @ T=0.00
24
25 Test Case 5 (7 Objectives)|
26 Parameter values:
27
28 1. Controller/Switch1 - logical trigger input false (output is from 3rd input port) @ T=0.00
29 2. Controller/Logical Operator2 - Logic: input port 1 F @ T=0.00
30 3. Controller/Logical Operator2 - Logic: input port 2 F @ T=0.00
31 4. Controller/Logical Operator2 - Logic: MCDC expression for output with input port 1 F @ T=0.00
32 5. Controller/Logical Operator2 - Logic: MCDC expression for output with input port 2 F @ T=0.00
33 6. Controller/Logical Operator - Logic: input port 3 F @ T=0.00
34 7. Controller/Logical Operator - Logic: MCDC expression for output with input port 3 F @ T=0.00
35
36 Test Case 6 (2 Objectives)
37 Parameter values:
38
39 1. Controller/Logical Operator2 - Logic: input port 2 T @ T=0.01
40 2. Controller/Logical Operator2 - Logic: MCDC expression for output with input port 2 T @ T=0.01
41
42 Test Case 7 (1 Objectives)
43 Parameter values:
44
Click and drag to move the document bar... |plain text file Ln 25 Col 27 OVR
```

- The Test Unit block is a Subsystem block that contains a copy of the original model that the software analyzed. Double-click the Test Unit block to view its contents and confirm that it is a copy of the Cruise Control Test Generation model.



**Note:** You can configure the harness model to reference the model that you are analyzing using a Model block instead of using a subsystem. In the Configuration Parameters dialog box, on the **Design Verifier > Results** pane, select **Save test harness as model** and **Reference input model in generated harness**.


- The Inputs block is a Signal Builder block that contains the generated test case signals. Double-click the Inputs block to open the Signal Builder dialog box and view the eight test case signals.
- The Size-Type block is a subsystem that transmits signals from the Inputs block to the Test Unit block. This block verifies that the size and data type of the signals are consistent with the Test Unit block.

The Signal Builder dialog box contains eight test cases.


- 1 To view Test Case 7, from the **Active Group** list, select **Test Case 7**.

In Test Case 7 at 0.01 seconds:

- The enable and inc signals remain 1.
- The brake and dec signals remain 0.
- The set signal transitions from 1 to 0.
- The speed signal transitions from 100 to 0.













In the Signal Builder block, the signal group satisfies the test objectives described in the Test Case Explanation block.

- 2 To confirm that the Simulink Design Verifier software achieved complete model coverage, simulate the harness model using all the test cases. In the Signal Builder dialog box, click the **Run all and produce coverage** button .

The Simulink software simulates all the test cases. The Simulink Verification and Validation™ software collects coverage data for the harness model and displays a coverage report. The report summary shows that the `sldvdemo_cruise_control_harness` model achieves 100% coverage.

## Summary

### Model Hierarchy/Complexity:

		D1	C1	MCDC
1. <a href="#">sldvdemo_cruise_control_harness</a>	8	100% 	100% 	100% 
2. ... <a href="#">Test Unit (copied from sldvdemo_cruise_control)</a>	7	100% 	100% 	100% 
3. .... <a href="#">Controller</a>	7	100% 	100% 	100% 
4. .... <a href="#">PI Controller</a>	4	100% 	NA	NA

### Simulate Tests and Produce Model Coverage Report

In the Simulink Design Verifier Results Summary window, if you click **Simulate tests and produce a model coverage report**, the software simulates the model and produces a coverage report for the `sldvdemo_cruise_control` model. The software stores the report with the following name:

```
<current_folder>/sldv_output/sldvdemo_cruise_control/...
  sldvdemo_cruise_control_report.html
```

When you click **Run all and produce coverage** to simulate tests in the harness model, you may see the following differences between this coverage report and the report you generated for the model itself:

- The harness model coverage report might contain additional time steps. When you collect coverage for the harness model, the model stop time equals the stop time for the longest test case. As a result, you might achieve additional coverage when you simulate the shorter test cases.
- The cyclomatic complexity coverage for the Test Unit subsystem in the harness model might be different than the coverage for the model itself due to the structure of the harness model.

## Combine Test Cases

If you prefer to review results that are combined into a smaller number of test cases, set the **Test suite optimization** parameter to **LongTestcases**. When you use the **LongTestcases** optimization, the analysis generates fewer, but longer, test cases that each satisfy multiple test objectives. This optimization creates a more efficient analysis and results that are easier to review.

Open the `sldvdemo_cruise_control` model and rerun the analysis with the **LongTestcases** optimization:

- 1 Select **Analysis > Design Verifier > Options**.
- 2 In the Configuration Parameters dialog box, in the **Select** tree on the left side, under the **Design Verifier** category, select **Test Generation**.
- 3 Set the **Test suite optimization** parameter to **LongTestcases**.
- 4 Click **Apply** and **OK** to close the Configuration Parameters dialog box.
- 5 In the `sldvdemo_cruise_control` model, double-click the block labeled **Run**.
- 6 In the Results Summary window, click **Create harness model**.

In the harness model, the Signal Builder block and the Test Case Explanation block now contain one longer test case instead of the eight shorter test cases created earlier in “Generate Test Cases”.

The screenshot shows an IDE window titled "Editor - S:\sca\_sldv\slvdemo\_cruise\_control\_harness\_testcase\_long.txt". The window contains a list of 34 test objectives, each with a unique identifier and a description of the test condition. The objectives are as follows:

```

1 Test Case 1 (34 Objectives)
2 Parameter values:
3
4 1. Controller/Switch3 - logical trigger input false (output is from 3rd input port) @ T=0.00
5 2. Controller/Switch3 - logical trigger input true (output is from 1st input port) @ T=0.02
6 3. Controller/Switch2 - logical trigger input false (output is from 3rd input port) @ T=0.03
7 4. Controller/Switch2 - logical trigger input true (output is from 1st input port) @ T=0.00
8 5. Controller/Switch1 - logical trigger input false (output is from 3rd input port) @ T=0.04
9 6. Controller/Switch1 - logical trigger input true (output is from 1st input port) @ T=0.00
10 7. Controller/Logical Operator1 - Logic: input port 1 T @ T=0.02
11 8. Controller/Logical Operator1 - Logic: input port 1 F @ T=0.00
12 9. Controller/Logical Operator2 - Logic: input port 1 T @ T=0.00
13 10. Controller/Logical Operator2 - Logic: input port 1 F @ T=0.04
14 11. Controller/Logical Operator2 - Logic: input port 2 T @ T=0.07
15 12. Controller/Logical Operator2 - Logic: input port 2 F @ T=0.04
16 13. Controller/Logical Operator2 - Logic: MCDC expression for output with input port 1 T @ T=0.00
17 14. Controller/Logical Operator2 - Logic: MCDC expression for output with input port 2 T @ T=0.07
18 15. Controller/Logical Operator2 - Logic: MCDC expression for output with input port 1 F @ T=0.04
19 16. Controller/Logical Operator2 - Logic: MCDC expression for output with input port 2 F @ T=0.04
20 17. Controller/Logical Operator - Logic: input port 1 T @ T=0.00
21 18. Controller/Logical Operator - Logic: input port 1 F @ T=0.01
22 19. Controller/Logical Operator - Logic: input port 2 T @ T=0.00
23 20. Controller/Logical Operator - Logic: input port 2 F @ T=0.02
24 21. Controller/Logical Operator - Logic: input port 3 T @ T=0.00
25 22. Controller/Logical Operator - Logic: input port 3 F @ T=0.05
26 23. Controller/Logical Operator - Logic: MCDC expression for output with input port 1 T @ T=0.00
27 24. Controller/Logical Operator - Logic: MCDC expression for output with input port 2 T @ T=0.00
28 25. Controller/Logical Operator - Logic: MCDC expression for output with input port 3 T @ T=0.00
29 26. Controller/Logical Operator - Logic: MCDC expression for output with input port 1 F @ T=0.01
30 27. Controller/Logical Operator - Logic: MCDC expression for output with input port 2 F @ T=0.02
31 28. Controller/Logical Operator - Logic: MCDC expression for output with input port 3 F @ T=0.05
32 29. Controller/PI Controller - enable logical value F @ T=0.01
33 30. Controller/PI Controller - enable logical value T @ T=0.00
34 31. Controller/PI Controller/Discrete-Time Integrator - integration result <= lower limit F @ T=0.00
35 32. Controller/PI Controller/Discrete-Time Integrator - integration result <= lower limit T @ T=0.14
36 33. Controller/PI Controller/Discrete-Time Integrator - integration result >= upper limit F @ T=0.00
37 34. Controller/PI Controller/Discrete-Time Integrator - integration result >= upper limit T @ T=0.26

```

The status bar at the bottom of the window indicates "plain text file", "Ln 1", "Col 1", and "OVR".

7 Click **Run all and produce coverage** to collect coverage.

The analysis still satisfies all 34 objectives.

## Analyze a Subsystem

In addition to analyzing a model, you can analyze a subsystem within a model. This technique is good for large models, where you want to review the analysis in smaller, manageable reports.

This example analyzes the Controller subsystem in the `sldvdemo_cruise_control` model.

- 1 Open the example model:

`sldvdemo_cruise_control`

- 2 Right-click the Controller subsystem, and select **Design Verifier > Enable ‘Treat as Atomic Unit’ to Analyze**.

The Function Block Parameters dialog box for the Controller subsystem opens.

- 3 Select **Treat as atomic unit**.

An *atomic subsystem* executes as a unit relative to the parent model; subsystem block execution does not interleave with parent block execution. You can extract atomic subsystems for use as standalone models.

You must set the **Treat as atomic unit** parameter to analyze a subsystem with the Simulink Design Verifier software.

After you set the parameter, other parameters become available, but you can ignore them.

- 4 Click **OK** to close the dialog box.
- 5 Select **File > Save As** and save the Cruise Control Test Generation model under a new name.
- 6 To start the subsystem analysis and generate test cases, right-click the Controller subsystem, and select **Design Verifier > Generate Tests for Subsystem**.
- 7 The Simulink Design Verifier software analyzes the subsystem. When the analysis is complete, view the analysis results for the Controller subsystem by clicking one of the following options:

- **Highlight analysis results on model**
- **Generate detailed analysis report**
- **Create harness model**

- **Simulate tests and produce a model coverage report**
- 8** Review the results of the subsystem analysis and compare them to the results of the full-model analysis described in “Analyze a Model” on page 1-4:
- The subsystem analysis analyzes the Controller as a standalone model.
  - The Controller subsystem contains all the test objectives in the Cruise Control Test Generation model, so both analyses generate the same test cases.

## Analyze a Stateflow Atomic Subchart

In a Stateflow chart, an *atomic subchart* is a graphical object that allows you to reuse the same state or subchart across multiple charts and models. You can use the Simulink Design Verifier software to analyze atomic subcharts individually. You do not have to analyze the chart that contains the atomic subchart, or the model that contains the chart.

If you are having problems analyzing a large model, analyzing an atomic subchart in a controlled environment is helpful. As described in “Bottom-Up Approach to Model Analysis” on page 14-15, by analyzing atomic subcharts or other components in the model hierarchy individually, you can analyze a model to:

- Solve problems that slow down or prevent test generation, property proving, or design error detection.
- Analyze model components that are unreachable in the context of the container model or chart.

---

**Note:** For more information about atomic subcharts, see “What Is an Atomic Subchart?” in the Stateflow documentation.

---

## Analyze an Atomic Subchart Using the Simulink Design Verifier Software

The `sf_atomic_sensor_pair` example model models a redundant sensor pair using atomic subcharts. This example analyzes the `Sensor1` subchart in the `RedundantSensors` chart.


- 1 Open the `sf_atomic_sensor_pair` example model:

```
sf_atomic_sensor_pair
```

This model demonstrates how to model a simple redundant sensor pair using atomic subcharts.

- 2 Double-click the `RedundantSensors` chart to open it.






This Stateflow chart has two atomic subcharts:

- Sensor1
  - Sensor2
- 3** To analyze the **Sensor1** subchart using the Simulink Design Verifier software, right-click the subchart and select **Design Verifier > Generate Tests for Subchart**.

During the analysis, the software creates a Simulink model named **Sensor1** that contains the **Sensor1** subchart. The new model contains Inport and Outport blocks that respectively correspond to the data objects **u** and **y** in the subchart.



The software saves the new model and other files generated by the analysis in:

`<current_folder>/sldv_output/Sensor1`

- 4 When the analysis is complete, view the analysis results for the **Sensor1** subchart by clicking one of the following options:
  - **Highlight analysis results on model**
  - **Generate detailed analysis report**
  - **Create harness model**
  - **Simulate tests and produce a model coverage report**

## Basic Workflow for Simulink Design Verifier

The basic workflow for analyzing your model is described in the following steps, with links to related documentation.

Step	Action	See...
1	Check the compatibility of your model.	“Check Model Compatibility”
2	If you want to work around compatibility limitations in your model or customize model elements for analysis, you can use Simulink Design Verifier block replacement rules. If you want to generate additional values for parameters in your model during analysis, use Simulink Design Verifier parameter configurations.	<ul style="list-style-type: none"> <li>• “What Is Block Replacement?”</li> <li>• “Parameter Constraint Values”</li> </ul>
3	Set Simulink Design Verifier options.	“Simulink Design Verifier Options”
4	If you plan to generate test cases or prove properties in your model, first run design error detection for integer overflow and division by zero.	<ul style="list-style-type: none"> <li>• “What Is Design Error Detection?”</li> <li>• “Detect Integer Overflow and Division-by-Zero Errors”</li> </ul>
5	Analyze your model to: <ul style="list-style-type: none"> <li>• Detect design errors</li> <li>• Generate test cases</li> <li>• Prove properties</li> </ul>	<ul style="list-style-type: none"> <li>• “Run a Design Error Detection Analysis”</li> <li>• “Workflow for Test Case Generation”</li> <li>• “Workflow for Proving Model Properties”</li> </ul>
6	Generate the results.	“Generate Analysis Results” on page 1-8
7	Interpret the results.	“Results Interpretation and Use”




# How the Simulink Design Verifier Software Works

---

- “Analyze a Simple Model” on page 2-2
- “Model Blocks” on page 2-4
- “Block Reduction” on page 2-5
- “Inline Parameters” on page 2-6
- “Large Models” on page 2-7
- “Handle Incompatibilities with Automatic Stubbing” on page 2-8
- “Nonfinite Data” on page 2-15
- “Approximations” on page 2-16
- “Logic Operations Short-Circuiting” on page 2-19

## Analyze a Simple Model

This simple Simulink model includes two Logical Operator blocks and a Memory block.



The persistent information in this model is limited to the Boolean value of the Memory block. The input to the model is a single Boolean value. The following table describes the complete behavior of the model, including the behavior that would result from an arbitrarily long sequence of inputs.

#	Input	Memory Value	Output of XOR Block = Next Memory Value	Output of AND Block
1	false	false	false	false
2	true	false	true	false
3	false	true	true	false
4	true	true	false	true

Suppose you want to generate test cases that result in a true output; this goal is your *test objective*. If you run the Simulink Design Verifier software to generate test cases that result in a true output, the software searches this table to see if such a scenario is possible.

After the Simulink Design Verifier software discovers a configuration that satisfies the test objective (in this case, when both the input and the Memory block output are true), it needs to find a path to reach this configuration from the initial conditions. If the initial memory value is true, the test case only needs to be a single time step (row 4) where the input was true.

If the initial memory value is false (the default), the test case must force the memory value to be true. In this example, the path requires two steps:

- 1 The input value is true and the memory value is false (row 2). Thus, the output of the XOR block is true, making the memory value true.
- 2 Now that the input value and memory value are both true (row 4), the output is true, so the analysis achieves the specified test objective.

An infinite number of test cases can cause the output to be true, and regardless of the state value, the output can be held false for an arbitrary time before making it true. When the Simulink Design Verifier software searches, it returns the first test case it encounters that satisfies the objective. This case is invariably the simulation with the fewest time steps. Sometimes you may find this result undesirable because it is unrealistic or does not satisfy some other test requirement.

The same basic principles from this example apply to property proving and test case generation. During test case generation, option parameters explicitly specify the search criteria. For example, you can specify that the Simulink Design Verifier software find paths for all block outputs or find only those paths that cause the block output to be true.

During a property proving analysis, you specify a functional requirement, or property, that you want the Simulink Design Verifier software to prove, for example, that the output is always true. If the search completes without finding a path that violates the property, the property is proven. If the software finds a path where the output is false, it creates a counterexample that causes the output to be false.

During an error detection analysis, the Simulink Design Verifier software identifies objectives where data overflow or division-by-zero errors can and cannot occur. The analysis creates test cases that demonstrate how the errors can occur.

### Model Blocks

If your model contains Model blocks that reference external models, the Simulink Design Verifier software creates test cases for the top-level model, considering each referenced model in its execution context.

If you have multiple Model blocks that reference the same model, the software analyzes each instance of the referenced model in the context from which it is referenced. The software attempts to satisfy test objectives for each instance within its execution context in the top-level model. If you have three Model blocks that reference a certain model, the analysis produces results for all three instances.

If you simulate the model using the test cases that the analysis generates, and collect coverage, the Simulink Verification and Validation software combines the coverage data for multiple instances of the same referenced model. The simulation produces one set of coverage results for each referenced model; if you have three Model blocks that reference a certain model, the simulation produces one set of results for that referenced model.

For example, suppose you have three Model blocks that reference the same model. Suppose also that referenced model has three test objectives. When you run a Simulink Design Verifier analysis for the top-level model, the total number of test objectives for the three Model blocks is nine. If you then simulate the model with the test cases generated by the analysis, the coverage results for that referenced model specify three test objectives.




## Block Reduction

Block reduction is a Simulink feature that lets you achieve faster execution during model simulation and in generated code. When block reduction is enabled, the Simulink software collapses certain groups of blocks into a single, more efficient block, or removes them entirely.

When the Simulink Design Verifier software translates a model, block reduction happens automatically, and blocks in unused code paths are eliminated from the model. The Simulink Design Verifier results do not include test objectives for blocks that have been reduced.

Consider the Switch block in the following model.



For this Switch block, the control input is always 0. If the **Criteria for passing first input** block parameter is `u2 ~= 0`, the Switch block always passes the third input through to the output port. When you analyze this model, the Simulink Design Verifier software removes the Switch block from the model and does not report any test objectives for the Switch block.

For more information about block reduction, see the description of the “Block reduction” parameter.

### Inline Parameters

The **Inline parameters** parameter is a Simulink optimization that transforms tunable parameters into constant values. For example, suppose you have a Gain block whose **Gain** parameter is **a**, where **a** is defined in the model workspace. During simulation, Simulink converts that **Gain** parameter to a constant value, as defined in the workspace.

When the Simulink Design Verifier software translates a model, it transforms all tunable parameters in the model into constant values, even if the **Inline parameters** option is off.

To tune parameters for an analysis, define parameter values in a parameter configuration file and specify that file in the **Configuration Parameters > Design Verifier > Parameters** pane to apply those parameter values during the analysis. For example, to constrain the values of a **Gain** parameter **a** to integer values from 4 to 10, in the parameter configuration file, specify the following:

```
params.a = int8([4 10]);
```

The analysis generates the specified values and returns results for those values.

For detailed information about how to specify parameters during a Simulink Design Verifier analysis, see “Define Constraint Values for Parameters”.

## Large Models

In larger, more complicated models, the Simulink Design Verifier software uses mathematical techniques to simplify the analysis:

- It identifies portions of the model that do not affect the desired objectives.
- It discovers relationships within the model that reduce the complexity of the search.
- It reuses intermediate results from one objective to another.

In this way, the problem is reduced to a search through the logical values that describe your model.

For detailed information about analyzing large models, see “Analyze a Large Model”.

## Handle Incompatibilities with Automatic Stubbing

### In this section...

“What Is Automatic Stubbing?” on page 2-8

“How Automatic Stubbing Works” on page 2-8

“Analyze a Model Using Automatic Stubbing” on page 2-10

### What Is Automatic Stubbing?

Automatic stubbing lets you analyze a model that contains objects that the Simulink Design Verifier software does not support.

When you enable the automatic stubbing option (it is enabled by default), the software considers only the interface of the unsupported objects, not their actual behavior. This technique allows the software to complete the analysis. However, the analysis may achieve only partial results if any unsupported model element affects the simulation outcome.

### How Automatic Stubbing Works

If you enable automatic stubbing, when the Simulink Design Verifier analysis comes to an unsupported block, the software “stubs” that block. The analysis ignores the behavior of the block, and as a result, the block output can take any value.

#### Stub Trigonometric Function Block

The Simulink Design Verifier software does not support Trigonometric Function blocks when the **Function** parameter is set to **acos**, such as the one in the following graphic.




When stubbing this block during analysis, `out_signal` can take any value, with the following results.

Analysis Model	Result of Stubbing <code>out_signal</code>
Design error detection	<ul style="list-style-type: none"> <li>• If a design-error objective that depends on <code>out_signal</code> is proven valid, that objective is valid for all simulations. In this case, the stubbing did not affect the results of the analysis.</li> <li>• If a design-error objective that depends on <code>out_signal</code> is falsified, the analysis cannot create a test case. The analysis cannot determine which input to the stubbed block produces the output that falsifies the objective.</li> </ul>
Test case generation	<ul style="list-style-type: none"> <li>• If a test objective that depends on the value of <code>out_signal</code> is satisfied, the analysis cannot create a test case. The analysis cannot determine which input to the stubbed block produces the output that satisfies the objective.</li> <li>• If a test objective that depends on the value of <code>out_signal</code> is unsatisfiable, there is no simulation that can satisfy that objective. In this case, the stubbing did not affect the results of the analysis.</li> </ul>
Property proving	<ul style="list-style-type: none"> <li>• If a proof objective that depends on <code>out_signal</code> is proven valid, that objective is valid for all simulations. In this case, the stubbing did not affect the results of the analysis.</li> <li>• If a proof objective that depends on <code>out_signal</code> is falsified, the analysis cannot create a counterexample. The analysis cannot determine which input to the stubbed block produces the output that falsifies the objective.</li> </ul>

### Stub S-Function Block Containing Function-Call Triggers

The Simulink example model `sfcdemo_sfncall` has an S-Function block. The S-function `sfncall` triggers the execution of the function-call subsystems `f1` `subsys1` and `f2` `subsys2` on the first and second elements of the first output port.



The Simulink Design Verifier software does not support the S-Function block, so if automatic stubbing is enabled, the analysis ignores the behavior of the S-function. As a result, the code that triggers the two function-call subsystems is ignored, resulting in two unsatisfiable objectives. Since the function calls are ignored, the contents of those subsystems are effectively eliminated from the analysis.

### Analyze a Model Using Automatic Stubbing

This section describes a workflow for using automatic stubbing, with a simple Simulink model as an example.

- “Check Model Compatibility” on page 2-11
- “Turn On Automatic Stubbing” on page 2-13
- “Review Results” on page 2-14
- “Achieve Complete Results” on page 2-14


The following model contains a Discrete State-Space block, which is not compatible with the Simulink Design Verifier software.



### Check Model Compatibility

From the Simulink Editor, there are two ways to check whether a model is compatible with the Simulink Design Verifier software:

- Run the Simulink Design Verifier compatibility check by selecting **Analysis > Design Verifier > Check Compatibility > Model**.




- Select the analysis that you want:
  - **Analysis > Design Verifier > Detect Design Errors > Model**
  - **Analysis > Design Verifier > Generate Tests > Model**
  - **Analysis > Design Verifier > Prove Properties > Model**



The software first checks the compatibility of the model. If the model itself is incompatible, for example, if it uses a variable-step solver, the analysis cannot continue.

If it finds incompatible elements in the model, the software analyzes the model and, by default, stubs out the incompatible elements. The Diagnostic Viewer also opens, listing the incompatibilities.



---

**Note:** For more information, see “Manage Errors and Warnings” in the Simulink documentation.

---

### Turn On Automatic Stubbing

Automatic stubbing is enabled by default. To change the automatic stubbing setting, in the Configuration Parameters dialog box, on the main **Design Verifier** pane, select **Automatic stubbing of unsupported block and functions**. When you run the analysis, the software tells you that stubbing is turned on and the analysis continues.

### Review Results

If you run an analysis with automatic stubbing enabled, make sure to review the results. In this report, generated after a test case generation analysis, you see a table of unsupported blocks that the software encountered.

### Unsupported Blocks

The following blocks are not supported by Simulink Design Verifier. They were abstracted during the analysis. This can lead Simulink Design Verifier to produce only partial results for parts of the model that depends on the output values of these blocks.

Block	Type
<a href="#">Discrete State-Space</a>	DiscreteStateSpace

The generated analysis report for the example model shows that the objectives are undecided because of stubbing. The software cannot generate test cases because it does not understand the operation of the Discrete State-Space block.

### Objectives Undecided Due to Stubbing

Simulink Design Verifier was not able to decide these objectives due to stubbing.

#	Type	Model Item	Description	Analysis Time (sec)
2	Decision	<a href="#">Saturation</a>	input > lower limit F	12
3	Decision	<a href="#">Saturation</a>	input > lower limit T	12
4	Decision	<a href="#">Saturation</a>	input >= upper limit F	12
5	Decision	<a href="#">Saturation</a>	input >= upper limit T	12

### Achieve Complete Results

If your analysis does not achieve complete results because of the stubbing, you can define custom block replacements to give a more precise definition of the unsupported blocks. For more information, see “Define Custom Block Replacements” on page 4-6 or enter `echodemo sldvdemo_blockreplacement_unsupportedblocks` at the MATLAB command line to step through the Block Replacements for Unsupported Blocks example.

## Nonfinite Data

The Simulink Design Verifier software does not support nonfinite data (for example, NaN and Inf) and related operations.

During an analysis, the software handles nonfinite operations as follows:

- In the Relational Operator block:
  - If the **Relational operator** parameter is `isFinite`, the output is always 1.
  - If the **Relational operator** parameter is `isNan` or `isInf`, the output is always 0.
- In the MATLAB Function block:
  - For the `isFinite` function, the output is always 1.
  - For the `isNan` and `isInf` functions, the output is always 0.

## Approximations

In this section...
“Approximations During Model Analysis” on page 2-16
“Types of Approximations” on page 2-16
“Floating-Point to Rational Number Conversion” on page 2-17
“Linearization of Two-Dimensional Lookup Tables” on page 2-17
“While Loops” on page 2-17

### Approximations During Model Analysis

The Simulink Design Verifier software attempts to generate inputs and parameters to achieve objectives. However, there could be an infinite number of values for the software to search. To create reasonable limits on the analysis, the software performs approximations to simplify the analysis. The software records any approximations it performed in the Analysis Information chapter of the Simulink Design Verifier HTML report. For a description of this chapter, see “Analysis Information Chapter” on page 13-28.

Review the analysis results carefully when the software uses approximations. Evaluate your model to identify which blocks or subsystems caused the software to perform the approximations.

Rarely, an approximation can result in test cases that fail to achieve test objectives or demonstrate a design error, or counterexamples that fail to falsify proof objectives. For example, suppose the software generates a test case signal that should achieve an objective by exceeding a threshold; a floating-point round-off error might prevent that signal from attaining the threshold value.

### Types of Approximations

The Simulink Design Verifier software performs three types of approximations when it analyzes a model:

- “Floating-Point to Rational Number Conversion” on page 2-17
- “Linearization of Two-Dimensional Lookup Tables” on page 2-17
- “While Loops” on page 2-17

## Floating-Point to Rational Number Conversion

The Simulink Design Verifier software simplifies the linear arithmetic of floating-point numbers by approximating them with infinite-precision rational numbers. The software discovers how the logical relationships between these values affects the objectives. This analysis enables the software to support supervisory logic that is commonly found in embedded controls designs.

If your model contains floating-point values in the signals, input values, or block parameters, the Simulink Design Verifier software converts those values to rational numbers before performing its analysis.

---

**Note:** As a result of these approximations, Simulink Design Verifier software does not consider the effect of round-off error, or the upper and lower bounds of floating-point numbers.

---

## Linearization of Two-Dimensional Lookup Tables

The Simulink Design Verifier software does not support nonlinear arithmetic. If your model contains any 2-D Lookup Table blocks, or n-D Lookup Table blocks where  $n = 2$ , with all of the following characteristics, the software approximates nonlinear two-dimensional interpolation with linear interpolation by fitting planes to each interpolation interval.

Block	Characteristics
n-D Lookup Table block, $n = 2$ :	<ul style="list-style-type: none"> <li>• <b>Interpolation method</b> parameter is <code>Linear</code>.</li> <li>• <b>Extrapolation method</b> parameter is <code>Clip</code> or <code>Linear</code>.</li> <li>• The input and output signals both have the floating-point data type.</li> </ul>

## While Loops

If your model or a Stateflow chart in your model contains a `while` loop, Simulink Design Verifier tries to detect a conservative constant bound that allows the `while` loop to exit. If the software cannot find a constant bound, it performs a `while` loop approximation. With this approximation, the analysis does not prove objectives to be

valid or unsatisfiable and it does not prove dead logic. The generated analysis report notes this approximation.


The behavior of the `while` loop approximation is consistent in all modes of analysis, as described in the following table.

<b>Analysis Mode</b>	<b>While Loop Approximation</b>
Design Error Detection	Sets number of <code>while</code> loop iterations to 3. Does not report dead logic or valid objectives.
Test Case Generation	Sets number of <code>while</code> loop iterations to 3. Does not report unsatisfiable objectives.
Property Proving	Sets number of <code>while</code> loop iterations to 3. Does not report valid objectives.

## Logic Operations Short-Circuiting

When the Simulink Design Verifier software performs an analysis, if possible, the software short-circuits logic blocks. When the previous inputs alone determine the block output, the analysis ignores any remaining block inputs. For example, if the first input to a Logical Operator block whose **Operator** parameter specifies **AND** is false, the analysis ignores the values of the other inputs.

Consider the following example model, with the **Model coverage objectives** parameter set to **Condition Decision**.



When the Simulink Design Verifier software analyzes this model for Condition Decision coverage, the analysis can only satisfy five of six objectives for the Logical Operator block inputs. The software cannot generate a test case when the third input to the Logical Operator block is false. If the second input is false, the third input is false, but the software ignores the third input due to the short-circuiting. If the second input is true, the third input is never false.





# Checking Compatibility with the Simulink Design Verifier Software

---

- “Check Model Compatibility” on page 3-2
- “Supported and Unsupported Simulink Blocks” on page 3-9
- “Support Limitations for Simulink Software Features” on page 3-21
- “Support Limitations for Model Blocks” on page 3-24
- “Support Limitations for Stateflow Software Features” on page 3-26
- “Support Limitations for MATLAB for Code Generation” on page 3-30

# Check Model Compatibility

<b>In this section...</b>
“Compatibility with Simulink Design Verifier” on page 3-2
“Run Compatibility Check” on page 3-2
“Compatibility Check Results” on page 3-3

## Compatibility with Simulink Design Verifier

The Simulink Design Verifier software analyzes Simulink models in order to:

- Detect design errors that may occur at runtime
- Generate test cases that achieve model coverage
- Prove properties and identify property violations

For these analyses, the models must:

- Compile into an executable form
- Be compatible with code generation
- Perform a zero-second simulation with no errors, where the simulation start time and stop time are both 0.

The software supports a broad range of Simulink and Stateflow software features in your models. However, there are features that the product does not support, described in “Support Limitations for Simulink Software Features” on page 3-21 and “Support Limitations for Stateflow Software Features” on page 3-26. Avoid using unsupported features in models that you plan to analyze with the Simulink Design Verifier software.

## Run Compatibility Check

The software automatically checks the compatibility of your model before it begins an analysis.

You can also run a compatibility check on your model before you start an analysis. To run a compatibility check on your model, do one of the following:

- From the Simulink Editor, select **Analysis > Design Verifier > Check Compatibility > Model**.
- In the Model Advisor, select either **By Product > Simulink Design Verifier > Check compatibility with Simulink Design Verifier** or **By Task > Simulink Design Verifier Compatibility Check > Check compatibility with Simulink Design Verifier**. Click **Run This Check**.

For more information, see “Simulink Design Verifier Checks”.

- Use the `sldvcompat` function to run the compatibility checker programmatically at the command line or in a MATLAB program. For more information, see the `sldvcompat` reference page.


## Compatibility Check Results

There are three outcomes of a compatibility check:

- “Model Is Compatible” on page 3-3
- “Model Is Incompatible” on page 3-4
- “Model Is Partially Compatible” on page 3-7

### Model Is Compatible


In the Results Summary window, you see if your model is compatible with the software.



#### **Model Is Incompatible**

If the model itself is incompatible with the software, two dialog boxes appear:


- Simulink Design Verifier Results Summary




- Diagnostic Viewer. Use the information in this dialog box to identify and fix the incompatibility.
- If your model uses a variable-step solver, configure the solver options to a fixed-step.

### 3 Checking Compatibility with the Simulink Design Verifier Software

---



- If your model has nonfinite data, change the value of the data or configure the model so that the data is treated as a variable during Simulink Design Verifier analysis.




---

**Note:** For more information about the Diagnostic Viewer, see “Manage Errors and Warnings” in the Simulink documentation.


---

### Model Is Partially Compatible

A model is partially compatible if at least one object in the model is incompatible. Automatic stubbing is enabled by default, so if you start an analysis that determines that the model is partially incompatible, it gives the following message, but the analysis proceeds.

The model can be analyzed by Simulink Design Verifier. It contains unsupported elements that will be stubbed out during analysis. The results of the analysis might be incomplete.

If you have disabled automatic stubbing, the analysis stops. The Results Summary window appears as follows.



To turn on automatic stubbing:

- 1 In the Simulink Editor, select **Analysis > Design Verifier > Options**.
- 2 Under **Analysis options**, select **Automatic stubbing of unsupported blocks and functions**.

For more information on automatic stubbing, see “Handle Incompatibilities with Automatic Stubbing”.



## Supported and Unsupported Simulink Blocks

The software provides various levels of support for Simulink blocks:

- Fully supported
- Partially supported
- Not supported

If your model contains unsupported blocks, you can enable automatic stubbing. Automatic stubbing considers the interface of the unsupported blocks, but not their behavior. If any of the unsupported blocks affect the simulation outcome, however, the analysis may achieve only partial results. For details about automatic stubbing, see “Handle Incompatibilities with Automatic Stubbing”.

To achieve 100% coverage, avoid using unsupported blocks in models that you analyze. Similarly, for partially supported blocks, specify only the block parameters that the software recognizes.

The following tables summarize the analysis support for Simulink blocks. Each table lists the blocks in a Simulink library and describes support information for that particular block.

### Additional Math and Discrete Library

The software supports all blocks in the Additional Math and Discrete library.

### Commonly Used Blocks Library

The Commonly Used Blocks library includes blocks from other libraries. Those blocks are listed under their respective libraries.

### Continuous Library

Block	Support Notes
Derivative	Not supported
Integrator	Not supported and not stubbable

<b>Block</b>	<b>Support Notes</b>
“Integrator Limited”	Not supported and not stubbable
PID Controller	Not supported
PID Controller (2 DOF)	Not supported
“Second Order Integrator”	Not supported and not stubbable
Second Order Integrator Limited	Not supported and not stubbable
State-Space	Not supported and not stubbable
Transfer Fcn	Not supported and not stubbable
Transport Delay	Not supported
Variable Time Delay	Not supported
Variable Transport Delay	Not supported
Zero-Pole	Not supported and not stubbable

## Discontinuities Library

The software supports all blocks in the Discontinuities library.

## Discrete Library

<b>Block</b>	<b>Support Notes</b>
Delay	Supported
Difference	Supported
Discrete Derivative	Supported
Discrete Filter	Supported
Discrete FIR Filter	Supported
“Discrete PID Controller”	Supported
“Discrete PID Controller (2 DOF)”	Supported
Discrete State-Space	Not supported
Discrete Transfer Fcn	Supported
Discrete Zero-Pole	Not supported

Block	Support Notes
Discrete-Time Integrator	Supported
First-Order Hold	Supported
Memory	Supported
Tapped Delay	Supported
Transfer Fcn First Order	Supported
Transfer Fcn Lead or Lag	Supported
Transfer Fcn Real Zero	Supported
Unit Delay	Supported
Zero-Order Hold	Supported

## Logic and Bit Operations Library

The software supports all blocks in the Logic and Bit Operations library.

## Lookup Tables Library

Block	Support Notes
Cosine	Supported
Direct Lookup Table (n-D)	Supported
Interpolation Using Prelookup	Not supported when: <ul style="list-style-type: none"> <li>The <b>Interpolation method</b> parameter is <b>Linear</b> and the <b>Number of table dimensions</b> parameter is greater than 4.</li> </ul> or <ul style="list-style-type: none"> <li>The <b>Interpolation method</b> parameter is <b>Linear</b> and the <b>Number of sub-table selection dimensions</b> parameter is not 0.</li> </ul>
1-D Lookup Table	Not supported when the <b>Interpolation method</b> or the <b>Extrapolation method</b> parameter is <b>Cubic Spline</b> .

Block	Support Notes
2-D Lookup Table	Not supported when the <b>Interpolation method</b> or the <b>Extrapolation method</b> parameter is <b>Cubic Spline</b> .
n-D Lookup Table	Not supported when: <ul style="list-style-type: none"> <li>• The <b>Interpolation method</b> or the <b>Extrapolation method</b> parameter is <b>Cubic Spline</b>.</li> </ul> or <ul style="list-style-type: none"> <li>• The <b>Interpolation method</b> parameter is <b>Linear</b> and the <b>Number of table dimensions</b> parameter is greater than 5.</li> </ul>
Lookup Table Dynamic	Supported
Prelookup	Supported
“Sine”	Supported

## Math Operations Library

Block	Support Notes
Abs	Supported
Add	Supported
Algebraic Constraint	Supported
Assignment	Supported
Bias	Supported
Complex to Magnitude-Angle	Not supported
Complex to Real-Imag	Not supported
Divide	Supported
Dot Product	Supported
“Find Nonzero Elements”	Supported
Gain	Supported
Magnitude-Angle to Complex	Not supported

Block	Support Notes								
Math Function	All signal types support the following <b>Function</b> parameter settings.								
	<table border="1"> <tr> <td data-bbox="601 390 734 434">conj</td> <td data-bbox="734 390 905 434">hermitian</td> <td data-bbox="905 390 1113 434">magnitude<sup>2</sup></td> <td data-bbox="1113 390 1337 434">mod</td> </tr> <tr> <td data-bbox="601 434 734 477">rem</td> <td data-bbox="734 434 905 477">reciprocal</td> <td data-bbox="905 434 1113 477">square</td> <td data-bbox="1113 434 1337 477">transpose</td> </tr> </table>	conj	hermitian	magnitude <sup>2</sup>	mod	rem	reciprocal	square	transpose
	conj	hermitian	magnitude <sup>2</sup>	mod					
	rem	reciprocal	square	transpose					
The software does not support the following <b>Function</b> parameter settings.									
<table border="1"> <tr> <td data-bbox="601 598 845 642">10<sup>u</sup></td> <td data-bbox="845 598 1083 642">exp</td> <td data-bbox="1083 598 1337 642">hypot</td> </tr> <tr> <td data-bbox="601 642 845 690">log</td> <td data-bbox="845 642 1083 690">log10</td> <td data-bbox="1083 642 1337 690">pow</td> </tr> </table>	10 <sup>u</sup>	exp	hypot	log	log10	pow			
10 <sup>u</sup>	exp	hypot							
log	log10	pow							
“Matrix Concatenate”	Supported								
MinMax	Supported								
MinMax Running Resettable	Supported								
Permute Dimensions	Supported								
Polynomial	Supported								
Product	Supported								
Product of Elements	Supported								
Real-Imag to Complex	Not supported								
Reciprocal Sqrt	Not supported								
Reshape	Supported								
Rounding Function	Supported								
Sign	Supported								
Signed Sqrt	Not supported								
Sine Wave Function	Not supported								
Slider Gain	Supported								
Sqrt	Not supported								
Squeeze	Supported								
Subtract	Supported								
Sum	Supported								

Block	Support Notes
Sum of Elements	Supported
Trigonometric Function	Supported if <b>Function</b> is <code>sin</code> , <code>cos</code> , or <code>sincos</code> , and <b>Approximation method</b> is <code>CORDIC</code> .
Unary Minus	Supported
“Vector Concatenate”	Supported
Weighted Sample Time Math	Supported

## Model Verification Library

The software supports all blocks in the Model Verification library.

## Model-Wide Utilities Library

Block	Support Notes
Block Support Table	Supported
DocBlock	Supported
Model Info	Supported
Timed-Based Linearization	Not supported
Trigger-Based Linearization	Not supported

## Ports & Subsystems Library

Block	Support Notes
Atomic Subsystem	Supported
Code Reuse Subsystem	Supported
Configurable Subsystem	Supported
Enable	Supported
Enabled Subsystem	Design range checks do not consider specified minimum and maximum values for blocks connected to the output

Block	Support Notes
	of the subsystem. For more information on design range checks, see “Check for Specified Intermediate Minimum and Maximum Signal Values”.
Enabled and Triggered Subsystem	<p>Not supported when the trigger control signal specifies a fixed-point data type.</p> <p>Design range checks do not consider specified minimum and maximum values for blocks connected to the output of the subsystem. For more information on design range checks, see “Check for Specified Intermediate Minimum and Maximum Signal Values”.</p>
For Each	<p>Supported with the following limitations:</p> <ul style="list-style-type: none"> <li>• When For Each Subsystem contains another For Each Subsystem, not supported.</li> <li>• When For Each Subsystem contains one or more Simulink Design Verifier Test Condition, Test Objective, Proof Assumption, or Proof Objective blocks, not supported.</li> <li>• When the mask parameters of the For Each Subsystem are partitioned, not supported.</li> </ul>
For Each Subsystem	<p>Supported with the following limitations:</p> <ul style="list-style-type: none"> <li>• When For Each Subsystem contains another For Each Subsystem, not supported.</li> <li>• When For Each Subsystem contains one or more Simulink Design Verifier Test Condition, Test Objective, Proof Assumption, or Proof Objective blocks, not supported.</li> <li>• When the mask parameters of the For Each Subsystem are partitioned, not supported.</li> </ul>
For Iterator Subsystem	Supported
Function-Call Feedback Latch	Supported
Function-Call Generator	Supported
Function-Call Split	Supported

Block	Support Notes
Function-Call Subsystem	Design range checks do not consider specified minimum and maximum values for blocks connected to the output of the subsystem. For more information on design range checks, see “Check for Specified Intermediate Minimum and Maximum Signal Values”.
If	<p>When running test case generation for coverage, the If block records condition, decision, and MCDC coverage. However, the Simulink Design Verifier software generates test cases only for condition and decision coverage.</p> <p>Parameter configurations are not supported. The analysis ignores parameter configurations that you specify for an If block.</p>
If Action Subsystem	Supported
Inport	Supported
Model	Supported except for the limitations described in “Support Limitations for Model Blocks”.
Model Variants	Supported except for the limitations described in “Support Limitations for Model Blocks”.
Outport	Supported
Subsystem	Supported
Switch Case	Supported
Switch Case Action Subsystem	Supported
Trigger	Supported
Triggered Subsystem	<p>Not supported when the trigger control signal specifies a fixed-point data type.</p> <p>Design range checks do not consider specified minimum and maximum values for blocks connected to the output of the subsystem. For more information on design range checks, see “Check for Specified Intermediate Minimum and Maximum Signal Values”.</p>
Variant Subsystem	Not supported when the <b>Generate preprocessor conditionals</b> parameter is enabled.



Block	Support Notes
While Iterator Subsystem	Supported

## Signal Attributes Library

The software supports all blocks in the Signal Attributes library.

## Signal Routing Library

Block	Support Notes
Bus Assignment	Supported
Bus Creator	Supported
Bus Selector	Supported
Data Store Memory	Supported
Data Store Read	Supported
Data Store Write	Supported
Demux	Supported
Environment Controller	Supported
From	Supported
Goto	Supported
Goto Tag Visibility	Supported
Index Vector	Supported
Manual Switch	<p>The Manual Switch block is compatible with the software, but the analysis ignores this block in a model. The analysis does not flag the coverage objectives for this block as satisfiable or unsatisfiable.</p> <p>Model coverage data is collected for the Manual Switch block.</p>
Merge	Supported
Multiport Switch	Supported

Block	Support Notes
Mux	Supported
Selector	Supported
Switch	Supported
Vector Concatenate	Supported

## Sinks Library

Block	Support Notes
Display	Supported
Floating Scope	Supported
Outport (Out1)	Supported
Scope	Supported
Stop Simulation	Not supported and not stubbable
Terminator	Supported
To File	Supported
To Workspace	Supported
XY Graph	Supported

## Sources Library

Block	Support Notes
Band-Limited White Noise	Not supported
Chirp Signal	Not supported
Clock	Supported
Constant	Supported unless <b>Constant value</b> is <code>inf</code> .
Counter Free-Running	Supported
Counter Limited	Supported
Digital Clock	Supported

Block	Support Notes
Enumerated Constant	Supported
From File	Not supported. When MAT-file data is stored in MATLAB <code>timeseries</code> format, not stubbable.
From Workspace	Not supported
Ground	Supported
Inport (In1)	Supported
Pulse Generator	Supported
Ramp	Supported
Random Number	Not supported and not stubbable
Repeating Sequence	Not supported
Repeating Sequence Interpolated	Not supported
Repeating Sequence Stair	Supported
Signal Builder	Not supported
Signal Generator	Not supported
Sine Wave	Not supported
Step	Supported
Uniform Random Number	Not supported and not stubbable

## User-Defined Functions Library

Block	Support Notes
Fcn	<p>Supports all operators except <math>\wedge</math>, and supports only the mathematical functions <code>abs</code>, <code>ceil</code>, <code>fabs</code>, <code>floor</code>, <code>rem</code>, and <code>sgn</code>.</p> <p>Parameter configurations are not supported. The analysis ignores parameter configurations that you specify for these blocks.</p>
Interpreted MATLAB Function	Not supported
Level-2 MATLAB S-Function	Not supported

<b>Block</b>	<b>Support Notes</b>
MATLAB Function	For limitations, see “Support Limitations for MATLAB for Code Generation” on page 3-30.
S-Function	Not supported
S-Function Builder	Not supported

## Support Limitations for Simulink Software Features

The software does not support the following Simulink software features. Avoid using these unsupported features.

Not Supported	Description
Variable-step solvers	<p>The software supports only fixed-step solvers.</p> <p>For more information, see “Choosing a Fixed-Step Solver” in the Simulink documentation.</p>
Callback functions	<p>The software does not execute model callback functions during the analysis. The results that the analysis generates, such as the harness model, may behave inconsistently with the expected behavior.</p> <ul style="list-style-type: none"> <li>• If a model or any referenced model calls a callback function that changes any block parameters, model parameters, or workspace variables, the analysis does not reflect those changes.</li> <li>• Changing the storage class of base workspace variables on model callback functions or mask initializations is not supported.</li> <li>• Callback functions called prior to analysis, such as the <code>PreLoadFcn</code> or <code>PostLoadFcn</code> model callbacks, are fully supported.</li> </ul>
Model callback functions	<p>The software only supports model callback functions if the <code>InitFcn</code> callback of the model is empty.</p>
Algebraic loops	<p>The software does not support models that contain algebraic loops.</p> <p>For more information, see “Algebraic Loops” in the Simulink documentation.</p>
Masked subsystem initialization functions	<p>The software does not support models whose masked subsystem initialization modifies any attribute of any workspace parameter.</p>
Complex signals	<p>The software supports only real signals.</p>

Not Supported	Description
	For more information, see “Complex Signals” in the Simulink documentation.
Variable-size signals	<p>The software does not support variable-size signals. A variable-size signal is a signal whose size (number of elements in a dimension), in addition to its values, can change during model execution.</p> <p>For more information, see “Variable-Size Signal Basics” in the Simulink documentation.</p>
Multiword fixed-point data types	The software does not support multiword fixed-point data types.
Nonzero start times	<p>Although Simulink allows you to specify a nonzero simulation start time, the analysis generates signal data that begins only at zero. If your model specifies a nonzero start time:</p> <ul style="list-style-type: none"><li>• If you do not select the <b>Reference input model in generated harness</b> parameter (the default), the harness model is a subsystem. The analysis sets the start time of the harness model to 1 and continues the analysis.</li><li>• If you select the <b>Reference input model in generated harness</b> parameter, a Model block references the harness model. The software cannot change the start time of the harness model, so the analysis stops and you see a recommendation to set the <b>Start time</b> parameter to 0.</li></ul>

Not Supported	Description
Nonfinite data	<p>The software does not support nonfinite data (for example, NaN and Inf) and related operations.</p> <p>In the Relational Operator block, the software assigns the output as follows:</p> <ul style="list-style-type: none"> <li>• If the <b>Relational operator</b> parameter is <code>isFinite</code>, the output is always 1.</li> <li>• If the <b>Relational operator</b> parameter is <code>isNan</code> or <code>isInf</code>, the output is always 0.</li> </ul> <p>In the MATLAB Function block, the software assigns the return value as follows:</p> <ul style="list-style-type: none"> <li>• For the <code>isFinite</code> function, the output is always 1.</li> <li>• For the <code>isNan</code> and <code>isInf</code> functions, the output is always 0.</li> </ul>
Concurrent execution	The software does not support models that are configured for concurrent execution.
Signals with nonzero sample time offset	The software does not support models with signals that have nonzero sample time offsets.
Models with no output ports	The software only supports models that have one or more output ports.
Large floating-point constants outside the range $[-\text{realmax}/2, \text{realmax}/2]$	The use of large floating-point constants can cause out of memory errors or substantial loss of precision. Avoid using such constants if possible.

## Support Limitations for Model Blocks

The software supports the Model block with the following limitations. The software cannot analyze a model containing one or more Model blocks if:

- The referenced model is protected. Protected referenced models are encoded to obscure their contents. This allows third parties to use the referenced model without being able to view the intellectual property that makes up the model.

For more information, see “Protected Model”.

- The parent model or any of the referenced models returns an error when you set the **Configuration Parameters > Diagnostics > Connectivity > Element name mismatch** parameter to `error`.

You can use the **Element name mismatch** diagnostic along with bus objects so that your model meets the bus element naming requirements imposed by some blocks.

- The Model block uses asynchronous function-call inputs.
- Any of the Model blocks in the model reference hierarchy creates an artificial algebraic loop. If this occurs, take the following steps:
  - 1 On the **Diagnostics** pane of the Configuration Parameters dialog box, set the **Minimize algebraic loop** parameter to `error` so that Simulink reports an algebraic loop error.
  - 2 On the **Model Referencing** Pane of the Configuration Parameters dialog box, select the Minimize algebraic loop occurrences parameter.

Simulink tries to eliminate the artificial algebraic loop during simulation.

- 3 Simulate the model.
- 4 If Simulink cannot eliminate the artificial algebraic loop, highlight the location of the algebraic loop by selecting **Simulation > Update Diagram**.
- 5 Eliminate the artificial algebraic loop so that the software can analyze the model. Break the loop with Unit Delay blocks so that the execution order is predictable.

---

**Note:** For more information, see “Algebraic Loops”.

---

- The parent model uses the base workspace and the referenced model uses a data dictionary.



- The parent model and the referenced model have mismatched data type override settings. The data type override setting of the parent model and its referenced models must be the same, unless the data type override setting of the parent model is **Use local settings**. You can select the data type override settings for your model in the **Analysis** menu, in the Fixed Point Tool dialog box under the **Settings for selected system** pane.

## Support Limitations for Stateflow Software Features

The software does not support the following Stateflow software features. Avoid using these unsupported features in models that you analyze.

### In this section...

“ml Namespace Operator, ml Function, ml Expressions” on page 3-26

“C Math Functions” on page 3-26

“Atomic Subcharts That Call Exported Graphical Functions Outside a Subchart” on page 3-27

“Recursion and Cyclic Behavior” on page 3-27

“Custom C or C++ Code” on page 3-29

“Machine-Parented Data” on page 3-29

“Textual Functions with Literal String Arguments” on page 3-29

### ml Namespace Operator, ml Function, ml Expressions

The software does not support calls to MATLAB functions or access to MATLAB workspace variables, which the Stateflow software allows. (See “Access Built-In MATLAB Functions and Workspace Data” in the Stateflow documentation.)

### C Math Functions

The software supports calls to the following C math functions:

- `abs`
- `ceil`
- `fabs`
- `floor`
- `fmod`
- `labs`
- `ldexp`
- `pow` (only for integer exponents)

The software does not support calls to other C math functions, which the Stateflow software allows. If automatic stubbing is enabled, which it is by default, the software eliminates these unsupported functions during the analysis.

For information about C math functions in Stateflow, see “Call C Functions in C Charts” in the Stateflow documentation.

---

**Note:** For details about automatic stubbing, see “Handle Incompatibilities with Automatic Stubbing”.

---

## Atomic Subcharts That Call Exported Graphical Functions Outside a Subchart

The software does not support atomic subcharts that call exported graphical functions, which the Stateflow software allows.

---

**Note:** For information about exported functions, see “Export Stateflow Functions for Reuse” in the Stateflow documentation.

---

## Recursion and Cyclic Behavior

Simulink Design Verifier software does not support recursive functions, which occur when a function calls itself directly or indirectly through another function call. Stateflow software allows you to implement recursion using graphical functions.

In addition, the software does not support recursion that the Stateflow software allows you to implement using a combination of event broadcasts and function calls.

---

**Note:** For information about avoiding recursion in Stateflow charts, see “Guidelines for Avoiding Unwanted Recursion in a Chart” in the Stateflow documentation.

---


Stateflow software also allows you to create *cyclic behavior*, where a sequence of steps is repeated indefinitely. If your model has a chart with cyclic behavior, the Simulink Design Verifier software cannot analyze it.

**Note:** For information about cyclic behavior in Stateflow charts, see “Cyclic Behavior in a Chart” in the Stateflow documentation.


---

However, you can modify a chart with cyclic behavior so that it is compatible, as in the following example.

The following chart creates cyclic behavior. State A calls state A1, which broadcasts a **Clear** event to state B, which calls state B2, which broadcasts a **Set** event back to state A, causing the cyclic behavior.



If you change the `send` function calls to use directed event broadcasts so that the `Set` and `Clear` events are broadcast directly to the states B1 and A1, respectively, the cyclic behavior disappears and the Simulink Design Verifier software can analyze the model.




---

**Note:** For information about the benefits of directed event broadcasts, see “Broadcast Events to Synchronize States” in the Stateflow documentation.

---

## Custom C or C++ Code

The software does not support custom C or C++ code, which the Stateflow software allows.

## Machine-Parented Data

The software does not support machine-parented data (i.e., defined at the level of the Stateflow machine), which the Stateflow software allows.

For more information, see “Best Practices for Using Data in Charts” in the Stateflow documentation.

## Textual Functions with Literal String Arguments

The software does not support literal string arguments to textual functions in a Stateflow chart.

## Support Limitations for MATLAB for Code Generation

**In this section...**

“Unsupported MATLAB for Code Generation Features” on page 3-30

“Support Limitations for MATLAB for Code Generation Library Functions” on page 3-30

### Unsupported MATLAB for Code Generation Features

The software does not support the following features of the MATLAB Function block in the Simulink software and MATLAB functions in the Stateflow software. Avoid using these unsupported features in models that you analyze with the Simulink Design Verifier software.

Not Supported	Description
Complex numbers	The software supports only real numbers and cannot analyze MATLAB for code generation functions that use complex numbers.
Characters	The software does not support characters, which MATLAB for code generation allows.
C functions	The software does not support calls to external C functions, which MATLAB for code generation allows.
Extrinsic functions	The software supports extrinsic functions only when they do not affect the output of a MATLAB function.
Handle classes	The software does not support handle classes in the MATLAB Function block. The software does support value classes.

### Support Limitations for MATLAB for Code Generation Library Functions

The software provides various levels of support for MATLAB for code generation library functions. The software either fully or partially supports particular functions. It does not support other functions.

If your model contains unsupported functions, you can turn on automatic stubbing, which considers the interface of the unsupported functions, but not their behavior. However, if any of the unsupported functions affect the simulation outcome, the analysis may achieve

only partial results. For details about automatic stubbing, see “Handle Incompatibilities with Automatic Stubbing”.

To achieve 100% coverage, avoid using unsupported MATLAB library functions in models that you analyze.

The following table lists Simulink Design Verifier support for categories of library functions in code generation from MATLAB:

- Software supports functions in that category, indicated by a dash (—).
- Software does not support functions in that category.
- Software supports the function in that category with limitations as specified.

For the complete listing of available functions, see “Functions and Objects Supported for C and C++ Code Generation — Alphabetical List”.

Function Category	Support Notes	
Aerospace Toolbox functions	Not supported.	
Arithmetic operator functions	Supported with the following limitations:	
	<code>mldivide (\)</code>	Supports only scalar arguments.
	<code>mpower (^)</code>	Supports only integer exponents.
	<code>mrdivide (/)</code>	Supports only scalar arguments.
	<code>power (.^)</code>	Supports only integer exponents.
Bit-wise operation functions	—	
Casting functions	Supported with the following limitations:	
	<code>char</code>	Not supported.
	<code>typecast</code>	Not supported.
Communications System Toolbox™ functions	Not supported.	
Complex number functions	Not supported.	
Computer Vision System Toolbox™ functions	Not supported.	
Data type functions	—	
Derivative and Integral functions	Not supported.	
Discrete math functions	—	
Error handling functions	Supported with the following limitations:	

Function Category	Support Notes	
	assert	Supported, but does not behave like a Proof Objective block.
Exponential functions	Supported with the following limitations:	
	exp	Not supported.
	expm	Not supported.
	expm1	Not supported.
	log	Not supported.
	log2	Not supported.
	log10	Not supported.
	log1p	Not supported.
	nextpow2	Not supported.
	nthroot	Not supported.
	reallog	Not supported.
	realpow	Not supported.
	realsqrt	Not supported.
	sqrt	Not supported.
Filtering and convolution functions	Supported with the following limitations:	
	detrend	Not supported.
Fixed-Point Designer™ functions	Supported with the following limitations:	
	complex	Not supported.
Histogram functions	Not supported.	
Image Processing Toolbox™ functions	Not supported.	
Input and output functions	—	
Interpolation and computation geometry	Supported with the following limitations:	
	cart2pol	Not supported.
	cart2sph	Not supported.
	pol2cart	Not supported.
	sph2cart	Not supported.



Function Category	Support Notes	
Linear algebra	Not supported.	
Logical operator functions	—	
MATLAB Compiler™ functions	Not supported.	
Matrix and array functions	Supported with the following limitations:	
	<code>angle</code>	Not supported.
	<code>cond</code>	Not supported.
	<code>det</code>	Not supported.
	<code>eig</code>	Not supported.
	<code>inv</code>	Not supported.
	<code>invhilb</code>	Not supported.
	<code>logspace</code>	Not supported.
	<code>lu</code>	Not supported.
	<code>norm</code>	Supported only when invoked using the syntax <code>norm(A,p)</code> where <code>p</code> is either 1 or <code>inf</code> .
	<code>normest</code>	Not supported.
	<code>pinv</code>	Not supported.
	<code>planerot</code>	Not supported.
	<code>qr</code>	Not supported.
	<code>rank</code>	Not supported.
	<code>rcond</code>	Not supported.
	<code>subspace</code>	Not supported.
Nonlinear numerical methods	Not supported.	
Polynomial functions	Not supported.	
Relational operations functions	—	
Rounding and remainder functions	—	

<b>Function Category</b>	<b>Support Notes</b>	
Set functions	—	
Signal Processing functions in MATLAB	Not supported.	
Signal Processing Toolbox™ functions	Not supported.	
Special values	Supported with the following limitations:	
	rand	Not supported.
	randn	Not supported.
Specialized math	Not supported.	
Statistical functions	—	
String functions	Supported with the following limitations:	
	char	Not supported.
	ischar	Not supported.
Trigonometric functions	Not supported.	

# Working with Block Replacements

---

- “What Is Block Replacement?” on page 4-2
- “Built-In Block Replacements” on page 4-3
- “Template for Block Replacement Rules” on page 4-5
- “Define Custom Block Replacements” on page 4-6
- “Execute Block Replacements” on page 4-14

# What Is Block Replacement?

Using the Simulink Design Verifier software, you can define rules to replace blocks automatically in your model. For example, you can work around a block that is incompatible with the software by creating a rule that replaces an unsupported Simulink block in your model with a supported block that is functionally equivalent. Or, you can customize blocks for analysis by creating a rule that adds constraints or objectives to particular blocks in your model.

When performing block replacements, the software makes a copy of your model and replaces blocks in the copy, without altering your original model. In this way, you can easily customize a model for analysis.

The Simulink Design Verifier software replaces blocks automatically in a model using:

- Libraries of replacement blocks
- Rules that define which blocks to replace and under what conditions

You replace any block with any built-in block, library block, or subsystem.

Block replacements are extensible, allowing you to define your own libraries of replacement blocks and custom block replacement rules. Use this capability if you need to:

- Work around an incompatibility, such as the presence of unsupported blocks in your model.
- Customize a block for analysis, such as:
  - Adding constraints to its input signals
  - Adding objectives to its output signals
  - Eliminating the contents of a subsystem or Model block to simplify your analysis

---

**Note:** You can use automatic stubbing as an alternative to block replacements in order to resolve incompatibilities. Automatic stubbing replaces unsupported blocks with elements that have the same interface. For more information, see “Handle Incompatibilities with Automatic Stubbing” on page 2-8.

---

## Built-In Block Replacements

The Simulink Design Verifier software provides a set of block replacement rules and a corresponding library of replacement blocks. Use these built-in block replacements when analyzing models. They serve as examples that you can examine to learn how to create your own block replacements.

The following table lists the factory default block replacement rules, available in the `matlabroot\toolbox\slsv\slsv\private` folder. There are two implementations of each factory-default block replacement rule. Rules whose file names end with `_normal.m` replace blocks with Subsystem blocks. Rules whose file names end with `_configss.m` replace blocks with Configurable Subsystem blocks.

File Name	Description
blkrep_rule_lookup_normal.m blkrep_rule_lookup_configss.m	A rule that replaces 1-D Lookup Table blocks with an implementation that includes test objectives for each breakpoint and interval specified by the <b>Breakpoints</b> parameter.
blkrep_rule_lookup2D_normal.m blkrep_rule_lookup2D_configss.m	A rule that adds Test Condition/Proof Assumption blocks to the input ports of 2-D Lookup Table blocks. Each Test Condition/Proof Assumption block constrains signal values to the interval specified by the corresponding breakpoint vector.
blkrep_rule_mpswitch2_normal.m blkrep_rule_mpswitch2_configss.m	A rule that adds a Test Condition/Proof Assumption block to the control input port of Multiport Switch blocks whose <b>Number of data ports</b> parameter is 2. The Test Condition/Proof Assumption block constrains signal values to the interval [1, 2] (or [0, 1] if the block uses zero-based indexing).
blkrep_rule_mpswitch3_normal.m blkrep_rule_mpswitch3_configss.m	A rule that adds a Test Condition/Proof Assumption block to the control input port of Multiport Switch blocks whose <b>Number of data ports</b> parameter is 3. The Test Condition/Proof Assumption block constrains signal values to the interval [1, 3] (or [0, 2] if the block uses zero-based indexing).
blkrep_rule_mpswitch4_normal.m blkrep_rule_mpswitch4_configss.m	A rule that adds a Test Condition/Proof Assumption block to the control input port of Multiport Switch blocks whose <b>Number of data ports</b> parameter

File Name	Description
	is 4. The Test Condition/Proof Assumption block constrains signal values to the interval [1, 4] (or [0, 3] if the block uses zero-based indexing).
blkrep_rule_mpswitch5_normal.m blkrep_rule_mpswitch5_configss.m	A rule that adds a Test Condition/Proof Assumption block to the control input port of Multiport Switch blocks whose <b>Number of data ports</b> parameter is 5. The Test Condition/Proof Assumption block constrains signal values to the interval [1, 5] (or [0, 4] if the block uses zero-based indexing).
blkrep_rule_switch_normal.m blkrep_rule_switch_configss.m	A rule that replaces Switch blocks with an implementation that includes test objectives, requiring that each switch position be exercised when the values of the first and third input ports are different.
blkrep_rule_selector IndexVecPort_normal.m blkrep_rule_selector IndexVecPort_configss.m	A rule that adds a Test Condition/Proof Assumption block to the index port of Selector blocks whose <b>Index Option</b> parameter is <b>Index vector (port)</b> . The Test Condition/Proof Assumption block constrains signal values to an interval whose endpoints are derived from the values of the Selector block's <b>Input port size</b> and <b>Index mode</b> parameters.
blkrep_rule_selector StartingIdxPort_normal.m blkrep_rule_selector StartingIdxPort_configss.m	A rule that adds a Test Condition/Proof Assumption block to the index port of Selector blocks whose <b>Index Option</b> parameter is <b>Starting index (port)</b> . The Test Condition/Proof Assumption block constrains signal values to an interval whose endpoints are derived from the values of the Selector block's <b>Input port size</b> , <b>Output size</b> , and <b>Index mode</b> parameters.

The library of replacement blocks that corresponds to the factory default rules is  
`matlabroot/toolbox/sldv/sldv/sldvblockreplacementlib`

## Template for Block Replacement Rules

To help you create block replacement rules, the Simulink Design Verifier software provides an annotated template that contains a skeleton implementation of the requisite callbacks:

```
matlabroot/toolbox/sldv/sldv/sldvblockreplacemtemplate.m
```

To create a block replacement rule, make a copy of the template and edit the copy to implement the desired behavior for the rule you are creating. The comments in the template provide hints about how to use each section. For a tutorial on using the template to write custom block replacements rules, see “Write Block Replacement Rules” on page 4-7.

# Define Custom Block Replacements

### In this section...

“Basic Workflow for Defining Custom Block Replacements” on page 4-6

“Specify Replacement Blocks” on page 4-6

“Write Block Replacement Rules” on page 4-7

“Replace Multiport Switch Blocks” on page 4-7

## Basic Workflow for Defining Custom Block Replacements

To replace certain blocks in your model in a way that the factory-default block replacement rules do not handle, create custom block replacement rules by completing the following tasks:

- “Specify Replacement Blocks” on page 4-6
- “Write Block Replacement Rules” on page 4-7

## Specify Replacement Blocks

A replacement block can be one of the built-in blocks in the Simulink model library or a block in a user-created library.

In the Simulink Design Verifier software, replacement blocks have the following restrictions:

- They must be built-in blocks or subsystems.
- They cannot be Model blocks, nor can they include any Model blocks.

---

**Note:** A Model block cannot be a replacement block, but you can replace Model blocks with built-in blocks or subsystems.

---

- They must reside in a block library that is available on your MATLAB search path.
- If the replacement block is a subsystem, any Inport and Outport blocks *must* have the default names (In1 and Out1).

After constructing your replacement block, write a custom block replacement rule.



## Write Block Replacement Rules

Block replacement rules have the following restrictions:


- The function that represents a block replacement rule must include particular callbacks. Use the block replacement rule template as a starting point for writing a custom rule. (See “Template for Block Replacement Rules” on page 4-5.)
- The function that represents a block replacement rule must be on the MATLAB search path.

## Replace Multiport Switch Blocks

- “Why Replace Multiport Switch Blocks?” on page 4-7
- “Create the Library and Replacement Block” on page 4-8
- “Write the Rule for the Replacement Block” on page 4-10

### Why Replace Multiport Switch Blocks?

A Multiport Switch block has one control input port and one or more data input ports; the default number of data inputs is 3.




A model may have test objectives on some blocks whose output is directly or indirectly connected to the Multiport Switch block. For example, a Saturation block may send data to the control input port. In this case, the analysis may create test cases that satisfy those objectives. However, those test cases may create values that are out of range for the control input port, regardless of whether the Multiport Switch block uses zero-based indexing or one-based indexing. This causes the simulation to fail.

In this example, you create a rule to replace all Multiport Switch blocks that have two data inputs and do not use zero-based indexing. The replacement block is a subsystem that has a Test Condition block that constrains the value of the control input to 1 or 2, so that the analysis does not create out-of-range data input values. This allows the analysis to satisfy the objectives on blocks that are connected to the control input port of the Multiport Switch block.

### Create the Library and Replacement Block


Create a user library and specify the replacement block as a masked subsystem:

- 1 In the Simulink Library Browser, select **File > New > Library**.
- 2 In your library, create a subsystem named `myReplacementBlock` to represent your replacement block.
- 3 Inside `myReplacementBlock`, add two Inport blocks so that the subsystem has three input ports and one output port. In your top-level model, the subsystem should look like the following graphic.



- 4 Add a Multiport Switch block and a Test Condition block to the subsystem. Set the block parameters as follows.
  - In the Multiport Switch block, set the **Number of data ports** parameter to 2.
  - In the Test Condition block, set the **Values** parameter to `{[1, 2]}`.

After you set these parameters, the contents of your subsystem `myReplacementBlock` should look like the following graphic.




- 5 To create a mask for your subsystem, from the top-level model, right-click `myReplacementBlock`. From the context menu, select **Mask > Create Mask**.

6 In the Mask Editor, specify the following information:

- In the **Parameters** pane, define a mask parameter named `InputSameDT` as shown.

This parameter replicates the behavior of the **Require all data port inputs to have the same data type** parameter of the underlying Multiport Switch block.



- In the **Initialization** pane, in the **Initialization commands** field, enter commands to specify that the subsystem inherit the `InputSameDT` parameter value of the top-level model:

```
maskInputSameDT = get_param(gcb, 'InputSameDT');
blkName = sprintf('/Multiport\nSwitch');
targetBlock = [gcb, blkName];
```

```
set_param(targetBlock, 'InputSameDT', maskInputSameDT);
```

- 7 Save your block library as a model file called `custom_rule` in a folder on your MATLAB search path.

### Write the Rule for the Replacement Block

To write a rule for the replacement block:

- 1 Open the block replacement rule template

```
matlabroot/toolbox/sldv/sldv/sldvblockreplacetemplate.m
```

- 2 Make a copy of the file and save it as `custom_rule_switch.m` in a folder on your MATLAB search path.

---

**Note:** Execute steps 3 through 11 for the copy of the template that you saved.

---

- 3 To declare a function `custom_rule_switch` and modify its help, modify the first few lines of the template:

```
function rule = custom_rule_switch
%CUSTOM_RULE_SWITCH Custom block replacement rule for
%the Simulink Design Verifier software
%
% This block replacement rule identifies Multiport
% Switch blocks whose "Number of inputs" parameter
% specifies '2' and "Use zero-based indexing" parameter
% specifies 'off'. It replaces such blocks with an
% implementation that includes a Test Condition block
% on the control input signal.
```

The function name must match its file name, without the `.m` extension. The comments that follow the function declaration create help for this rule.

- 4 Specify the type of block that you want to replace in your model by specifying its `BlockType` parameter as the `rule.blockType` object. For this example, change the `rule.blockType` object to `'MultiPortSwitch'`:

```
%% Target Block Type
%
rule.BlockType = 'MultiPortSwitch';
```

---

**Note:** You can use the `get_param` function to obtain the value of the `BlockType` parameter for the block that you want to replace.

---

- 5 Specify the full block path name for the replacement block as the `rule.ReplacementPath` object. For this example, to replace Multiport Switch blocks with the replacement block developed in “Specify Replacement Blocks” on page 4-6, modify the `rule.ReplacementPath` object using the full block path name:

```
%% Replacement Library
%
rule.ReplacementPath = sprintf('custom_rule/myReplacementBlock');
```

---

**Note:** To get the full block path name, use the `gcb` function.

---

- 6 To specify the type of subsystem that the software uses when replacing blocks, specify a value for the `rule.ReplacementMode` object. Valid values are:
- **Normal** — The software replaces blocks with a copy of the subsystem specified by the `rule.ReplacementPath` object. This is the default.
  - **ConfigurableSubSystem** — The software replaces blocks with a Configurable Subsystem block. With the Configurable Subsystem block, you can choose whether it represents the subsystem specified by the `rule.ReplacementPath` object, or the original block before its replacement.

For this example, set `rule.ReplacementMode` to **Normal**:

```
%% Replacement Mode
%
rule.ReplacementMode = 'Normal';
```

- 7 Specify parameter values that the replacement blocks inherit from the blocks being replaced. You achieve inheritance by mapping the parameter names in a structure. Each field of the structure represents a parameter that the replacement block inherits. Specify the value of each field using the token `$original.parameter$.parameter`. `parameter` is the name of the parameter that belongs to the original block.

To define a structure named `parameter` that maps the `InputSameDT` parameter from the original Multiport Switch blocks to their replacement blocks, change the content of the **Parameter Handling** section as follows:

```
%% Parameter Handling
%
parameter.InputSameDT = '$original.InputSameDT$';

% Register the parameter mapping for the rule
rule.ParameterMap = parameter;
```

---

**Note:** To determine block parameter names, refer to “Block Libraries” in the Simulink documentation.

---

- 8 To define the callback functions, keep the following lines in the file:

```
%% Replacement Test Callback
% Customize the local function 'replacementTestFunction' to specify the
% conditions under which Simulink Design Verifier replaces blocks when
% using this rule. Simulink Design Verifier replaces blocks only when this
% local function returns true.
%
rule.IsReplaceableCallBack = @replacementTestFunction;

%% Post Replacement Callback
% Customize the local function 'postReplacementFunction' to specify actions
% that will be performed after a block is replaced.
%
% The usage of this callback in replacement rules is optional. Simulink
% Design Verifier does not enforce its existence in the rule definition.
%
rule.PostReplacementCallBack = @postReplacementFunction;
```

- 9 Customize `replacementTestFunction` by specifying conditions under which the Simulink Design Verifier software replaces blocks in your model.

To instruct the software to replace only the Multiport Switch blocks whose `NumInputPorts` parameter is 2 and whose `zeroIdx` parameter is off, replace the existing `replacementTestFunction` with the following:

```
function out = replacementTestFunction(blockH)
% Specify the logic that determines when the Simulink Design
% Verifier software replaces a block in your model. For example,
% restrict replacements to only the blocks whose parameters
% specify particular values.
%
out = false;
numInputPorts = eval(get_param(blockH,'NumInputPorts'));
zeroIdx = get_param(blockH,'zeroIdx');
if numInputPorts==2 && strcmp(zeroIdx,'off')
    out = true;
```

end

Because `replacementTestFunction` executes after the model has been compiled, you can access parameters such as `CompiledPortDataTypes` or `CompiledPortDimensions` from `replacementTestFunction`.

For an example of a `replacementTestFunction` that accesses these parameters, open the following file:

*matlabroot/toolbox/sldv/sldv/private/blkrep\_rule\_switch\_normal.m*

- 10** Optionally, you can customize `postReplacementFunction` to specify the actions the software performs after a block has been replaced.

For an example of a `postReplacementFunction`, open the following file:

*matlabroot/toolbox/sldv/sldv/private/blkrep\_rule\_selectorIndexVecPort\_normal.m*

- 11** Save the edited file and continue to the next section, “Execute Block Replacements” on page 4-14, to execute your replacement rule.

# Execute Block Replacements

### In this section...

“Configure Block Replacements” on page 4-14

“Replace Blocks in a Model” on page 4-15

## Configure Block Replacements

You must configure block replacement options before executing block replacements in your model. To specify block replacement options from the model window:

- 1 Open the `sldvdemo_param_identification` model.
- 2 Rename this model to `my_sldvdemo_param_identification`, and save it in a folder on your MATLAB search path.
- 3 In the Model Editor, select **Analysis > Design Verifier > Options**.

The Configuration Parameters dialog box displays the main pane of the **Design Verifier** category.

- 4 In the Configuration Parameters dialog box, select **Design Verifier > Block Replacements**.
- 5 On the **Block Replacements** pane, select **Apply block replacements** to enable block replacements.

Selecting this check box provides access to the **List of block replacement rules (in order of priority)** and **File path of the output model** options.

- 6 To execute your custom block replacement rule, follow these steps:
  - a In the **List of block replacement rules (in order of priority)** box, delete:  
`<FactoryDefaultRules>`
  - b Enter:  
`custom_rule_switch`

The Simulink Design Verifier software replaces a block in your model only once. If multiple rules apply to the same block, the software replaces the block using the rule with the highest priority.



- 7 In the **File path of the output model** field, accept the default to create a model named `my_sldvdemo_param_identification_replacement`. This model is a copy of the original model and includes the block replacements.

By default, this software creates a model named `$ModelName$_replacement`, where `$ModelName$` is the name of the model it is analyzing. To use a different name for the model with the block replacements, enter the name in this field. You do not need to include a file extension.

- 8 Click **Apply**.
- 9 Save the `my_sldvdemo_param_identification` model.

## Replace Blocks in a Model

- “Replace Blocks and Analyze Model with the Block Replacements” on page 4-15
- “Perform the Block Replacements Only” on page 4-16

### Replace Blocks and Analyze Model with the Block Replacements

After enabling the **Apply block replacements** option, you can start a Simulink Design Verifier analysis that analyzes the model after executing the block replacements. To trigger block replacements and start the analysis, do one of the following:

- Select **Analysis > Design Verifier > Options**, and on the **Design Verifier** pane, click **Generate Tests**.
- In the Model Editor, select **Analysis > Design Verifier > Generate Tests > Model**.

---

**Note:** If your model has unsaved changes, the Simulink Design Verifier software asks if you want to save the model before executing the block replacements.

---

The Simulink Design Verifier software copies your model, replaces blocks in the copy, without altering the original model, and analyzes the model with the replacements.

Upon completing its analysis, you can generate a detailed analysis report that includes information about the block replacements it executed. For each block replacement, you can follow a link from the report to the block replacement in the model copy, saved using the name you specified on the **Design Verifier > Block Replacements** pane of the Configuration Parameters dialog box.

### Perform the Block Replacements Only

Replacing the blocks in a model *before* running the analysis can help you debug the custom block replacement rules. Once the block replacement rules are working as you want, analyze the model that contains the block replacements.

To perform only the block replacements, without analyzing the model with the block replacements, at the command line or from a program, use the `sldvblockreplacement` function. Set two parameters of the `sldvoptions` structure related to replacing blocks, and call `sldvblockreplacement` as follows:

```
opts = sldvoptions;
opts.BlockReplacement = 'on'
opts.BlockReplacementRulesList = ...
    'custom_rule_switch, <FactoryDefaultRules>';
[status, newmodelH] = sldvblockreplacement(...
    'my_sldvdemo_param_identification', opts);
```

If you execute block replacements programmatically, in the MATLAB Command Window, the Simulink Design Verifier software displays a table that lists available block replacement rules and opens the copy of the model that contains the block replacements (\$modelName\$\_replacement).

The table lists all built-in rules and any custom rules that you specified using the **List of block replacement rules (in order of priority)** option (see “Configure Block Replacements” on page 4-14). The table includes the following information:

- **Type**  
Type of rule, either built-in or custom
- **Registration MATLAB File name**  
Name of the file that expresses the rule
- **Block types**  
BlockType parameter value of the block that the rule replaces
- **Priority**  
Priority of execution when multiple rules target the same type of block for replacement
- **Active**  
Flag that indicates whether the rule is active (1) or ignored (0)

The output also displays information about the block replacements. For example, the output for this example indicates that the software used the `custom_rule_switch.m` rule to replace a Multiport Switch block (of the same name) at the top level of the model.

# Specifying Parameter Configurations

---

- “Parameter Constraint Values” on page 5-2
- “Define Constraint Values for Parameters” on page 5-4
- “Specify Parameter Constraint Values for Full Coverage” on page 5-10
- “Store Parameter Constraints in MATLAB Code Files” on page 5-21
- “Define Constraint Values for Parameters in MATLAB Code Files” on page 5-24

# Parameter Constraint Values

<b>In this section...</b>
“Parameter Configuration for Analysis” on page 5-2
“Data Types in Parameter Configurations” on page 5-3

## Parameter Configuration for Analysis

Simulink Design Verifier software can treat parameters in your model as variables during its analysis. For example, suppose you specify a variable that is defined in the MATLAB workspace as the value of a block parameter in your model. You can instruct the Simulink Design Verifier software to use additional values for that parameter in its analysis.

This allows you to, for example:

- Extend the results of a error detection analysis property proof to consider the impact of additional parameter values.
- Generate comprehensive test cases for situations in which parameter values must vary to achieve more complete coverage results. For more information, see “Specify Parameter Constraint Values for Full Coverage” on page 5-10.

If you place a constraint on a parameter in your model, during analysis that parameter takes only your specified constraint value or values. A group of constraints on parameters in the same model is also called a *parameter configuration*.

Use the Parameter Configuration Table to manage constraints on your model parameters for analysis. In the Parameter Configuration Table, you can:

- Autogenerate value ranges for parameters in your model. See “Autogenerate Parameter Constraint”.
- Enter your own value ranges for parameters in your model. See “Define Constraint Values for Parameters”.
- Highlight objects in your model that have parameters configured to act as variables during analysis. See “Highlight Constrained Parameters in Model” on page 5-9.
- Import and export parameter configurations from MATLAB code files. See “Store Parameter Constraints in MATLAB Code Files”.

**Note:** When you configure Simulink Design Verifier to treat parameters as variables in its analysis, you cannot also use the analysis to extend existing test cases. In **Analysis > Design Verifier > Options**, if you specify your model to extend existing test cases with a **Data file** and apply parameter configurations with a **Parameter configuration file** or the Parameter Configuration Table, when you attempt to perform Simulink Design Verifier analysis, the software reports that your model is incompatible. This occurs because the existing test cases do not include corresponding parameter values.

---

## Data Types in Parameter Configurations

Consider the following issues related to data types when constraining parameter values:

- “Parameters Cannot Be Structures” on page 5-3
- “Parameters Converted to Fixed Point in the Model” on page 5-3
- “Parameters Defined as Simulink.Parameter and Referenced by Multiple Locations” on page 5-3

### Parameters Cannot Be Structures

If the data type of a parameter in the MATLAB workspace is `struct`, Simulink Design Verifier cannot generate values for that parameter during the analysis.

### Parameters Converted to Fixed Point in the Model

If your model references a base workspace parameter whose data type is `auto`, `single`, or `double`, and the model converts that parameter to a fixed-point data type, you must define the constraints for that parameter according to its fixed-point type.

### Parameters Defined as Simulink.Parameter and Referenced by Multiple Locations

For a parameter defined as `Simulink.Parameter` or an inherited class of `Simulink.Parameter` whose data type is `auto`, if the parameter is referenced by multiple locations with different data types, Simulink Design Verifier cannot generate values for that parameter during the analysis.

## Define Constraint Values for Parameters

This example shows how to specify values or ranges of values used for model parameters during Simulink Design Verifier analysis.


### In this section...

“Find Parameters and Autogenerate Constraints” on page 5-5

“Edit Parameter Constraints” on page 5-8


“Highlight Constrained Parameters in Model” on page 5-9

Using the Parameter Configuration Table, you can find and autogenerate constraints for parameters in your model. This example uses the following model, which contains **Gain** and **Constant** parameters defined as **m** and **b**, respectively.



Variables **m** and **b** are defined in the MATLAB workspace.

The model callback function `PreLoadFcn` defines **m** and **b** in the MATLAB workspace.



When the model opens:

- `m` is set to 5.
- `b` is a `Simulink.Parameter` object of type `int8` whose value is set to 5.

## Find Parameters and Autogenerate Constraints

- 1 Open the Parameter Configuration Table.

In the Simulink Editor, select **Analysis > Design Verifier > Options**. In the **Select** tree, choose **Design Verifier > Parameters**.

- 2 Enable the Parameter Configuration Table.

In the **Parameters** pane, select **Enable parameter configuration** and **Use parameter configuration table**.

- 3 Find parameters that can be constrained for analysis.

At the bottom of the Parameter Configuration Table, click **Find in Model**. The Parameter Configuration Table searches your model for parameters that can be configured and loads them in the table.

When possible, the Parameter Configuration Table autogenerates constraint values for parameters. You can use these autogenerated values or specify your own constraint.

In this example, in the Parameter Configuration Table, rows for model parameters **m** and **b** appear.

Use	Name	Constraint	Value	Min	Max	Model Element
<input checked="" type="checkbox"/>	b		5			ex_defining_param_configurations_errwarn/Constant
<input checked="" type="checkbox"/>	m		5			ex_defining_param_configurations_errwarn/Gain

Each row represents a parameter configuration. You can edit the parameter's constraint value(s) in the field under **Constraint**. To use your specified parameter configuration in analysis, select the check box in the field under **Use**. The following table provides more details about these and other columns in the Parameter Configuration Table.

For parameter in row, the column...	Shows...
<b>Use</b>	Whether specified constraint for parameter is used in analysis.  To include parameter configuration in analysis, select the check box. To exclude parameter configuration from analysis, clear the selection.



For parameter in row, the column...	Shows...
<b>Name</b>	Name of parameter.
<b>Constraint</b>	Autogenerated or user-specified constraint value(s) for parameter.  To change the specified constraint value(s), double-click in this field and enter new constraint value(s).
<b>Value</b>	Value of parameter. If the parameter is defined in a Simulink data dictionary that is linked to the model, the column shows the value of the parameter in the data dictionary. Otherwise, it shows the value of the parameter in the base workspace.
<b>Min</b>	Specified minimum value for parameter, if parameter is of type <code>Simulink.Parameter</code> and has a specified minimum value.
<b>Max</b>	Specified maximum value for parameter, if parameter is of type <code>Simulink.Parameter</code> and has a specified maximum value.
<b>Model Element</b>	Path to model component(s) where parameter is used.

**Note:** If you use a MATLAB variable from a data dictionary as a model parameter, SLDV analysis does not consider the parameter as tunable. If you want the parameter to be tunable for the analysis, use a `Simulink.Parameter` object for the parameter. To create a `Simulink.Parameter` object in the data dictionary:

- 1 In the Model Explorer, on the **Model Hierarchy** pane, select the workspace under the data dictionary that contains your MATLAB variable.
- 2 Select **Add > Simulink Parameter**. You see a new variable titled **Param** in the workspace.

- 3 Rename the variable. Assign the same data type as the original MATLAB variable.
- 4 In your model, use the variable that you just created as your parameter.

### Edit Parameter Constraints

For each parameter you want to treat as a variable during analysis, specify constraint values.

- 1 In the Parameter Configuration Table, in the **Constraint** column, double-click the field for the parameter you want to constrain. Enter your constraint values.

For this example:

- For parameter **b**, specify the value range [4, 10].
- For parameter **m**, specify the value 3.

Use	Name	Constraint	Value	Min	Max	Model Element
<input checked="" type="checkbox"/>	b	[4,10]	5			ex_defining_param_configurations_errwarn/Constant
<input checked="" type="checkbox"/>	m	3	5			ex_defining_param_configurations_errwarn/Gain

- 2 To enable a parameter configuration for analysis, click to select the row that corresponds to the configured parameter. Click **Enable**.

To enable multiple parameter configurations at once, shift-click to select multiple rows, and click **Enable**.

- 3 To exclude parameter configurations from analysis, click to select the row that corresponds to the configured parameter. Click **Disable**.

When you disable a parameter configuration, the specified constraint for this parameter is not used in analysis.

To disable multiple parameter configurations at once, shift-click to select multiple rows, and click **Disable**.

- 4 To exclude a parameter configuration from analysis and delete its specified constraint, click to select the row that corresponds to the configured parameter. Click **Clear**.

The Parameter Configuration Table clears the specified constraint for the parameter, and the parameter configuration is excluded from analysis.

To clear multiple parameter configurations at once, shift-click to select multiple rows, and click **Clear**.

## Highlight Constrained Parameters in Model

Highlight model components that use the parameters for which you have specified constraints.

- 1 Select the parameter(s) you want to highlight in the model.

To select a parameter, click anywhere inside the **Name** or **Constraint** columns for either parameter. Shift-click to select multiple parameters.


Parameter Configuration Table

Enable Disable Clear Highlight in Model

Use	Name	Constraint	Value	Min	Max	Model Element
<input checked="" type="checkbox"/>	b	[4,10]	5			ex_defining_param_configurations_errwarn/Constant
<input checked="" type="checkbox"/>	m	3	5			ex_defining_param_configurations_errwarn/Gain

- 2 Click **Highlight in Model**.

In the Simulink Editor, model components that use the selected parameters are highlighted.



Variables m and b are defined in the MATLAB workspace.

## Specify Parameter Constraint Values for Full Coverage

### In this section...

“About This Example” on page 5-10

“Construct Example Model” on page 5-11

“Parameterize Constant Block” on page 5-12

“Preload Workspace Variable” on page 5-12

“Autogenerate Parameter Constraint” on page 5-13

“Analyze Example Model” on page 5-14

“Simulate Test Cases” on page 5-17

### About This Example

This example describes how to create and analyze a simple Simulink model, for which you generate test cases that achieve decision coverage. However, in this example, achieving complete decision coverage is possible only when the Simulink Design Verifier software treats a particular block parameter as a variable during its analysis. This example explains how to specify parameter configurations for use with the analysis.


The following workflow guides you through the process of completing this example.

Task	Description	See...
1	Construct the example model.	“Construct Example Model” on page 5-11
2	Specify a variable as the value of a Constant block parameter.	“Parameterize Constant Block” on page 5-12
3	Constrain the value of the variable that the Constant block specifies.	“Autogenerate Parameter Constraint” on page 5-13
4	Generate test cases for your model and interpret the results.	“Analyze Example Model” on page 5-14
5	Simulate the test cases and measure the resulting decision coverage.	“Simulate Test Cases” on page 5-17

## Construct Example Model

Construct a simple Simulink model to use in this example:

- 1 Create an empty Simulink model.
- 2 Copy the following blocks into the empty Simulink Editor:
  - From the Sources library:
    - Two Inport blocks to initiate the input signals
    - A Constant block to control the switch
  - From the Signal Routing library: A Multiport Switch block to provide simple logic
  - From the Sinks library: An Outport block to receive the output signal
- 3 Double-click the Multiport Switch block to access its dialog box and specify its **Number of data ports** option as 2.
- 4 Connect the blocks so that your model looks like the following.



- 5 Select **Simulation > Model Configuration Parameters**.
- 6 In the **Select** tree on the left side of the Configuration Parameters dialog box, select the **Solver** node. Under **Solver options**, set the **Type** option to **Fixed-step**, and then set the **Solver** option to **discrete (no continuous states)**.
- 7 In the **Select** tree, select the **Diagnostics** node. Set **Automatic solver parameter selection** to **none**.
- 8 Click **OK** to apply your changes and close the Configuration Parameters dialog box.
- 9 Save your model as `ex_defining_params_example` for use in the next procedure.

## Parameterize Constant Block

Parameterize the Constant block in your model by specifying a variable as the value of the Constant block's **Constant value** parameter:

- 1 Double-click the Constant block.
- 2 In the **Constant value** box, enter A.
- 3 Click **OK** to apply your change and close the Constant block parameter dialog box.
- 4 Save your model.

## Preload Workspace Variable


Preload the value of the MATLAB workspace variable A referenced by the Constant block:

- 1 Select **File > Model Properties > Model Properties**.
- 2 Click the **Callbacks** tab.
- 3 In the **PreLoadFcn**, enter:

```
A = int8(1);
```

- 4 Click **OK** to close the Model Properties dialog box and save your changes.
- 5 Close your model.
- 6 Open your model.

When you open the model, the **PreLoadFcn** defines a variable A of type **int8** whose value is 1.



## Autogenerate Parameter Constraint


Use the Parameter Configuration Table to constrain the variable **A** to specified values.

- 1** In the Simulink Editor, select **Analysis > Design Verifier > Options**.
- 2** In Configuration Parameters dialog box, from the **Select** tree under **Design Verifier**, select **Parameters**.
- 3** Select **Enable parameter configuration**.
- 4** Select **Use parameter configuration table**.
- 5** At the bottom of the Parameter Configuration Table, click **Find in Model**.

The Parameter Configuration Table is populated with parameters from your model. When possible, it autogenerates constraint values for each parameter, depending on the data type and location of the parameter in the model.

In this case, a row appears for the parameter **A** that you defined. The table row for **A** displays the following information:

- In the **Name** column, the parameter name (**A**).
- In the **Constraint** column, the constraint specified on parameter **A**. The Parameter Configuration Table autogenerates the constraint values {**1**, **2**}.
- In the **Value** column, the value of **A** in the base workspace. This value is **1**.
- In the **Model Element** column, the model component in which **A** resides (ex\_defining\_params\_example/Constant).
- In the **Use** column, a check box indicating whether the specified constraint values in the table are configured for analysis.



- 6 In the Parameter Configuration Table, in the row for parameter **A**, make sure that you select the **Use** check box.

When you enable this parameter configuration, during Simulink Design Verifier analysis, the parameter **A** takes only the `int8` values 1 and 2.

- 7 In the Configuration Parameters dialog box, click **OK**.
- 8 Save your model.

### Analyze Example Model

Analyze the model using the parameter configuration you just created, and generate the analysis report:



- 1 In the Simulink Editor, select **Analysis > Design Verifier > Generate Tests > Model**.

Simulink Design Verifier begins analyzing your model to generate test cases.

- 2 When the software completes its analysis, in the Simulink Design Verifier Results Summary window, select **Generate detailed analysis report**.

The software displays an HTML report named `ex_defining_params_example_report.html`.

Keep the Results Summary window open for the next procedure.

- 3 In the Simulink Design Verifier report **Table of Contents**, click **Test Cases**.
- 4 Click **Test Case 1** to display the subsection for that test case.

## Test Case 1

### Summary

Length: 0 second (1 sample period)  
 Objectives 1  
 Satisfied:

### Objectives

Step	Time	Model Item	Objectives
1	0	<a href="#">Multiport Switch</a>	integer input value = 1 (output is from input port 1)

### Generated Parameter Values

Parameter	Value
A	1

### Generated Input Data

<b>Time</b>	<b>0</b>
<b>Step</b>	<b>1</b>
In1	-
In2	-

This section provides details about Test Case 1 that the Simulink Design Verifier software generated to satisfy a coverage objective in the model. In this test case, a value of 1 for parameter A satisfies the objective.

- 5 Scroll down to the Test Case 2 section in the **Test Cases** chapter.

### Test Case 2

#### Summary

Length: 0 second (1 sample period)  
Objectives Satisfied: 1

#### Objectives

Step	Time	Model Item	Objectives
1	0	<a href="#">Multiport Switch</a>	integer input value = *,2 (output is from input port 2)

#### Generated Parameter Values

Parameter	Value
A	2

#### Generated Input Data

Time	0
Step	1
In1	-
In2	-

This section provides details about Test Case 2, which satisfies another coverage objective in the model. In this test case, a value of 2 for parameter A satisfies the objective.


## Simulate Test Cases


Simulate the generated test cases and review the coverage report that results from the simulation:

- 1 In the Simulink Design Verifier Results Summary window, select **Create harness model**.

The software creates and opens a harness model named `ex_defining_params_example_harness`.

- 2 The block labeled Inputs in the harness model is a Signal Builder block that contains the test case signals. Double-click the Inputs block to view the test case signals in the Signal Builder block.





- 3 In the Signal Builder dialog box, click the **Run all** button .

The Simulink software simulates each of the test cases in succession, collects coverage data for each simulation, and displays an HTML report of the combined coverage results at the end of the last simulation.

- 4 In the model coverage report, review the **Summary** section:

## Summary

### Model Hierarchy/Complexity:

		D1
1. <a href="#">ex_defining_params_example_harness</a>	2	100% 
2. . . . <a href="#">Test Unit (copied from ex_defining_params_example)</a>	1	100% 

This section summarizes the coverage results for the harness model and its Test Unit subsystem. Observe that the subsystem achieves 100% decision coverage.

- 5** In the **Summary** section, click the Test Unit subsystem.

The report displays detailed coverage results for the Test Unit subsystem.

**2. SubSystem block "[Test Unit \(copied from ex\\_defining\\_param...](#)"****Parent:** [/ex\\_defining\\_params\\_example\\_harness](#)

<b>Metric</b>	<b>Coverage (this object)</b>	<b>Coverage (inc. descendants)</b>
Cyclomatic Complexity	0	1
Decision (D1)	NA	100% (2/2) decision outcomes

**MultiPortSwitch block "[Multiport Switch](#)"****Parent:** [ex\\_defining\\_params\\_example\\_harness/Test Unit \(copied from ex\\_defining\\_params\\_example\)](#)

<b>Metric</b>	<b>Coverage</b>
Cyclomatic Complexity	1
Decision (D1)	100% (2/2) decision outcomes

**Decisions analyzed:**

integer input value	100%
= 1 (output is from input port 1)	2/4
= *,2 (output is from input port 2)	2/4

This section reveals that the Multiport Switch block achieves 100% decision coverage because the test cases exercise each of the switch pathways.

## Store Parameter Constraints in MATLAB Code Files

### In this section...

“Export Parameter Constraints to File” on page 5-21

“Import Parameter Constraints from File” on page 5-23

You can use the Parameter Configuration Table to manage constraints on your model parameters for analysis. If you place a constraint on a parameter in your model, during analysis that parameter takes only your specified constraint value or values. A group of constraints on parameters in the same model is also called a *parameter configuration*. You can store groups of parameter constraints in a MATLAB code file called a parameter configuration file. For more information on configuring parameters for Simulink Design Verifier, see “Define Constraint Values for Parameters” on page 5-4.

To enable parameter configuration, in the Simulink Editor, select **Analysis > Design Verifier > Parameters**. In the **Parameters** pane, select **Enable parameter configuration**.


### Export Parameter Constraints to File

Using the Parameter Configuration Table, you can export parameter constraint values to a MATLAB code file. If you later want to use the same parameter configuration in a different analysis, you can import your previously specified parameter constraint values from the MATLAB code file.

To export parameter constraint values to a file:

- 1 Open the Parameter Configuration Table. In the Simulink Editor, select **Analysis > Design Verifier > Options**. In the **Select** tree, choose **Design Verifier > Parameters**.

The Parameter Configuration Table shows specified constraint values for parameters in your model, as in the following example screen shot.



### 2 Click **Export to File**.

The Parameter Configuration File saves the current parameter configurations to a .m file with the name you specify. Parameters that do not have the **Use** check box enabled appear as commented lines in the parameter configuration file.

In the example shown in the previous step, the parameter configuration file contains the following code:

```
function params = ex_many_params_config
params.param_01 = {0, 1};
% params.param_02 = {0, 01};
params.param_03 = {0, 1};
% params.param_04 = {0, 1};
```



## Import Parameter Constraints from File

If you defined parameter configurations for analysis in a release prior to R2014a, you can import corresponding MATLAB files and manage these parameters in the Parameter Configuration Table.

To import parameter constraints from a MATLAB code file:

- 1 Open the Parameter Configuration Table. In the Simulink Editor, select **Analysis > Design Verifier > Options**. In the **Select** tree, choose **Design Verifier > Parameters**.
- 2 Click **Add from File**. Choose a parameter configuration file.

The Parameter Configuration Table loads specified parameter constraints from the code, excluding code comments, from the file. If you specify a constraint for a parameter and then load a parameter configuration file containing constraint specification for the same parameter, the constraint specified in the file overwrites the preexisting constraint in the table.

Simulink Design Verifier provides an example parameter configuration file for the example model `sldvdemo_param_identification`:

```
matlabroot/toolbox/sldv/sldvdemos/sldvdemo_param_ident_config.m
```

# Define Constraint Values for Parameters in MATLAB Code Files

### In this section...

“Template Parameter Configuration File” on page 5-24

“Syntax in Parameter Configuration Files” on page 5-24

To specify parameters as variables for analysis, you can use the Parameter Configuration Table or define parameter configurations in a MATLAB code file. You can also export parameter configuration files from the Parameter Configuration Table. For more information, see “Store Parameter Constraints in MATLAB Code Files”.

This example shows how to define parameter configurations in a MATLAB code file. For an example that shows how to define these parameter configurations using the Parameter Configuration Table, see “Define Constraint Values for Parameters” on page 5-4.

## Template Parameter Configuration File

The Simulink Design Verifier software provides an annotated template that you can use as a starting point:

```
matlabroot/toolbox/sldv/sldv/sldv_params_template.m
```


To create a parameter configuration file, make a copy of the template and edit the copy. The comments in the template explain the syntax for defining parameter configurations.

To associate the parameter configuration file with your model before analyzing the model, in the Configuration Parameters dialog box, on the **Design Verifier > Parameters** pane, enter the file name in the **Parameter configuration file** field.

## Syntax in Parameter Configuration Files

Specify parameter configurations using a structure whose fields share the same names as the parameters that you treat as input variables.


For example, suppose you want to constrain the **Gain** and **Constant value** parameters, **m** and **b**, which appear in the following model:



Variables `m` and `b` are defined in the MATLAB workspace.

The `PreLoadFcn` callback function defines `m` and `b` in the MATLAB workspace when you open the model:

- `m` is set to 5.
- `b` is a `Simulink.Parameter` object of type `int8` whose value is set to 5.



In your parameter configuration file, specify constraints for `m` and `b`:

```
params.b = int8([4 10]);
params.m = {};
```

This file specifies:

- `b` is an 8-bit signed integer from 4 to 10. The constraint type must match the type of the parameter `b` in the MATLAB workspace, `int8`, in this example.

- `m` is not constrained to any values.

Specify points using the `Sldv.Point` constructor, which accepts a single value as its argument. Specify intervals using the `Sldv.Interval` constructor, which requires two input arguments, i.e., a lower bound and an upper bound for the interval. Optionally, you can provide one of the following strings as a third input argument that specifies inclusion or exclusion of the interval endpoints:

- `' () '` — Defines an open interval.
- `' [] '` — Defines a closed interval.
- `' (] '` — Defines a left-open interval.
- `' [) '` — Defines a right-open interval.

---

**Note:** By default, the Simulink Design Verifier software considers an interval to be closed if you omit its two-character string.

---

The following example constrains `m` to 3 and `b` to any value in the closed interval `[0, 10]`:

```
params.m = Sldv.Point(3);  
params.b = Sldv.Interval(0, 10);
```

If the parameters are scalar, you can omit the constructors and instead specify single values or two-element vectors. For example, you can alternatively specify the previous example as:

```
params.m = 3;  
params.b = [0 10];
```

---

**Note:** To indicate no constraint for an input parameter, specify `params.m = {}` or `params.m = []`. The analysis treats this parameter as free input.

---

You can specify multiple constraints for a single parameter using a cell array. In this case, the analysis combines the constraints using a logical OR operation.

The following example constrains `m` to either 3 or 5 and constrains `b` to any value in the closed interval `[0, 10]`:

```
params.m = {3, 5};
```

```
params.b = [0 10];
```

You can specify several sets of parameters by expanding the size of your structure. For example, the following example uses a 1-by-2 structure to define two sets of parameters:

```
params(1).m = {3, 5};  
params(1).b = [0 10];
```

```
params(2).m = {12, 15, Sldv.Interval(50, 60, '()')};  
params(2).b = 5;
```

The first parameter set constrains **m** to either 3 or 5 and constrains **b** to any value in the closed interval [0, 10]. The second parameter set constrains **m** to either 12, 15, or any value in the open interval (50, 60), and constrains **b** to 5.

# Detecting Design Errors

---

- “What Is Design Error Detection?” on page 6-2
- “Derived Ranges in Design Error Detection” on page 6-3
- “Run a Design Error Detection Analysis” on page 6-4
- “Dead Logic Detection” on page 6-8
- “Detect Dead Logic in Example Model” on page 6-10
- “Model Objects That Receive Dead Logic Detection” on page 6-14
- “Detect Integer Overflow and Division-by-Zero Errors” on page 6-23
- “Check for Specified Intermediate Minimum and Maximum Signal Values” on page 6-28
- “Detect Out of Bound Array Access Errors” on page 6-35

## What Is Design Error Detection?

Design error detection is a Simulink Design Verifier analysis mode that detects the following types of errors:

- Dead logic
- Integer or fixed-point data overflow
- Division by zero
- Intermediate signal values that are outside the specified minimum and maximum values
- Out of bound array access

Before you simulate your model, analyze your model in design error detection mode to find and diagnose these errors. Design error detection analysis determines the conditions that cause the error, helping you identify possible design flaws. Design error detection analysis also computes a range of signal values that can occur for block outports and Stateflow local data in your model.

After the analysis, you can:

- Click individual blocks to view the analysis results for that block.
- Create a harness model containing test cases that demonstrate the errors.
- Create an analysis report that contains detailed results for the entire model.



## Derived Ranges in Design Error Detection

When you specify minimum and maximum values for a signal or data in a model, these values define a *design range*.

During design error detection, the software analyzes the model behavior and computes the values that can occur during simulation for:

- Block Outputs
- Stateflow local data

The range of these values is called a *derived range*.

The **Use specified input minimum and maximum values** parameter in the Configuration Parameters dialog box, on the **Design Verifier** pane, if enabled, tells the analysis to consider the design ranges on the model input ports as constraints when calculating the derived ranges. By default, the **Use specified input minimum and maximum values** parameter is enabled.

If **Use specified input minimum and maximum values** is disabled, the software does not restrict the signals when computing the derived ranges.

To see how this process works, consider the following model.



In this model, the design ranges are:

- Inport block:  $[-25..25]$
- Abs block output:  $[10..30]$

Given the design range on the Inport block, the only possible values for the Abs block output are values from 0 to 25. Therefore, the derived range for the Abs block is  $[0..25]$ .

However, if you disable the **Use specified input minimum and maximum values** parameter, the analysis calculates the derived ranges based on unrestricted values of the input ports of the model. In the preceding model, the only valid outputs of the Abs block are nonnegative numbers. Consequently, the derived range for the Abs block is  $[0..Inf]$ .

## Run a Design Error Detection Analysis

### In this section...

“Workflow for Detecting Design Errors” on page 6-4

“Understand the Analysis Results” on page 6-4

“Review the Latest Analysis Results in the Model Explorer” on page 6-6

### Workflow for Detecting Design Errors

To analyze your model for design errors, use the following workflow:

- 1 Verify that your model is compatible with Simulink Design Verifier software.
- 2 If you have Stateflow objects in your model, in the Configuration Parameters dialog box, on the **Diagnostics > Stateflow** pane, set **Transition shadowing** to **error**.
- 3 Specify options that control how Simulink Design Verifier detects design errors in your model.
- 4 Execute the Simulink Design Verifier analysis.
- 5 Review the analysis results.

---

**Note:** If you select design error detection for dead logic, you cannot select any other type of design error detection. For dead logic detection, Simulink Design Verifier performs an independent analysis. If you want to detect design errors for dead logic and any of the other types of design errors, you must perform design error detection analysis twice.

---


### Understand the Analysis Results

When you run a design error detection analysis, by default, the software highlights model objects in one of four colors so that the analysis results are easy to review.

Model Object Highlighting Color	Analysis Results
Green	One of the following: <ul style="list-style-type: none"> <li>• The analysis did not find overflow or division-by-zero errors.</li> </ul>


Model Object Highlighting Color	Analysis Results
	<ul style="list-style-type: none"> <li>• The analysis did not find dead logic.</li> <li>• The analysis did not find intermediate or output signals outside the range of user-specified minimum and maximum constraints.</li> <li>• The analysis did not find out of bound array access errors.</li> </ul>
Red	<p>One of the following:</p> <ul style="list-style-type: none"> <li>• The analysis found at least one test case that causes overflow or division-by-zero errors.</li> <li>• The analysis found dead logic.</li> <li>• The analysis found intermediate or output signals outside the range of user-specified minimum and maximum constraints.</li> <li>• The analysis found at least one test case that causes an out of bound array access error.</li> </ul>
Orange	<p>For at least one objective, the analysis could not determine if the model has dead logic, overflow errors, division-by-zero errors, signals outside the user-specified range, or out of bound array access errors. This situation can occur when:</p> <ul style="list-style-type: none"> <li>• The analysis times out.</li> <li>• The software cannot determine if an error occurred or not. This result is due to: <ul style="list-style-type: none"> <li>• Automatic stubbing errors; for more information, see “Handle Incompatibilities with Automatic Stubbing”.</li> <li>• Limitations of the analysis engine.</li> </ul> </li> </ul>
Gray	The model object was not part of the analysis.

The Simulink Design Verifier Results window initially displays a summary of the analysis results, as in the following example.



When you click an object in the model, additional details about the results for that object are displayed in the Simulink Design Verifier Results window.

---

**Tip** By default, the Simulink Design Verifier Results window is always the topmost visible window. To change that setting, click the  icon and on the context menu, clear the check mark next to **Always on top**.

---

### Review the Latest Analysis Results in the Model Explorer

If you close the analysis results to fix the cause of the errors in your model, you might need to rereview the analysis results. As long as your model remains open, you can view the results of your most recent analysis results in the Model Explorer.

After you close your model, you can no longer view any analysis results.

To view the latest results, in the model window, select **Analysis > Design Verifier > Latest Results**. The Model Explorer opens with the results displayed on the right-hand pane.

For any Simulink Design Verifier analysis, from the Model Explorer, you can perform the following tasks:

- Highlight the analysis results on the model.
- Generate a detailed analysis report.
- Create the harness model, or if the harness model already exists, open it.

---

**Note:** If no objectives are falsified, you cannot create the harness model.

---

- View the data file.
- View the log file.

## Dead Logic Detection

<b>In this section...</b>
“Detect Dead Logic Only” on page 6-8
“Detect Dead and Active Logic” on page 6-9

Design error detection for dead logic in Simulink Design Verifier consists of two analysis options:

- Detection of dead logic only. If you select this option, the software does not report active logic or undecided objectives. This option is available in:
  - Model Advisor.
  - The Configuration Parameters dialog box.
- Detection of active logic. Active logic detection runs concurrently with dead logic detection. In rare cases, active logic detection can also find additional dead logic. This option is available in the Configuration Parameters dialog box.

### Detect Dead Logic Only

To detect dead logic using the Model Advisor:

- 1 Select **Analysis > Model Advisor**.
- 2 Select the model component where you want to detect dead logic.
- 3 In the Model Advisor window, do one of the following:
  - Expand the node **Model Advisor > By Product > Simulink Design Verifier > Design Error Detection**. Select **Detect Dead Logic**.
  - Expand the node **Model Advisor > By Task > Simulink Design Verifier Design Error Checks**. Select **Detect Dead Logic**.
- 4 Click the **Run This Check** button.

To detect dead logic if you are not using the Model Advisor:

- 1 In the Simulink Editor, select **Analysis > Design Verifier > Options**
- 2 In the Configuration Parameters dialog box, in the **Select** tree, under **Design Verifier**, select **Design Error Detection**

- 3 In the **Design Error Detection** pane, select **Dead logic**.

Clear **Identify active logic** if it is selected.

- 4 Click **OK** to apply these settings and close the Configuration Parameters dialog box.
- 5 In the Simulink Editor, select **Analysis > Design Verifier > Detect Design Errors**.

## **Detect Dead and Active Logic**

- 1 In the Simulink Editor, select **Analysis > Design Verifier > Options**
- 2 In the Configuration Parameters dialog box, in the **Select** tree, under **Design Verifier**, select **Design Error Detection**
- 3 In the **Design Error Detection** pane, select **Dead logic** and then **Identify active logic**.
- 4 Click **OK** to apply these settings and close the Configuration Parameters dialog box.
- 5 In the Simulink Editor, select **Analysis > Design Verifier > Detect Design Errors**.

## **More About**

- “Design Verifier Pane: Design Error Detection”

## Detect Dead Logic in Example Model

In this section...
“Overview of Dead Logic Detection” on page 6-10
“Detect Dead Logic in Example Model” on page 6-10
“Review Analysis Results for Example Model” on page 6-11
“Review Analysis Report for Example Model” on page 6-12

### Overview of Dead Logic Detection

During a design error detection analysis, Simulink Design Verifier can detect dead logic in your model. Logic is considered dead if it is proven through analysis to stay inactive during execution. Dead logic might be caused by a design or a requirement error.

- 1 In the Configuration Parameters dialog box, on the **Design Verifier > Design Error Detection** pane:
  - To detect dead logic, select **Dead Logic**.
  - To detect active logic, select **Identify active logic**.
- 2 Select **Analysis > Design Verifier > Detect Design Errors**.

For information on more detailed analysis that identifies both dead logic and active logic, see “Dead Logic Detection” on page 6-8.

### Detect Dead Logic in Example Model

This example shows how to analyze the `sldvdemo_fuelsys_logic_simple` model for dead logic.

- 1 To open the example model, at the MATLAB command prompt, type:

```
sldvdemo_fuelsys_logic_simple
```
- 2 Select **Analysis > Design Verifier > Options**.
- 3 In the Configuration Parameters dialog box, select **Design Verifier > Design Error Detection**.



- 4 On the **Design Error Detection** pane, select **Dead Logic** and **Identify active logic**.

When you select **Dead Logic**, the other **Design Error Detection** analysis options are inactive.

- 5 Close the Configuration Parameters dialog box.
- 6 Select **Analysis > Design Verifier > Detect Design Errors > Model**.


After the analysis:

- The software highlights the model with the analysis results.
- The Simulink Design Verifier Results dialog box opens and displays a summary of the analysis.


## Review Analysis Results for Example Model

This example shows how to review the analysis results when you detect dead logic in the `sldvdemo_fuelsys_logic_simple` model.

- 1 To review the model analysis results, at the top level of the `sldvdemo_fuelsys_logic_simple` model, open the `control logic` Stateflow chart.
  - Model objects with active logic are highlighted in green.
  - Model objects with dead logic are highlighted in red.
- 2 In the `sldvdemo_fuelsys_logic_simple/control logic` window, click the `Sens_Failure_Counter.INC` transition in the `Speed_Sensor_Mode` state.



The Simulink Design Verifier Results dialog box displays a summary of the active and dead logic for the transition.



## Review Analysis Report for Example Model

This example shows how to generate an analysis report after you detect dead logic in the `sldvdemo_fuelsys_logic_simple` model. The analysis report is an HTML file that provides detailed information about the analysis.

- 1 In the Simulink Design Verifier Results window, click **Back to summary**.

**2** Click **Generate detailed analysis report**.

The software generates a detailed analysis report that opens in a browser.

**3** In the analysis report, click **Design Error Detection Objectives Status**.

For `sldvdemo_fuelsys_logic_simple` model, the **Design Error Detection Objectives Status** chapter of the report provides detailed results in two categories:

- **Dead Logic** — Simulink Design Verifier proved the decision and condition outcomes listed in the table that cannot occur and are dead logic.
- **Active Logic** — Simulink Design Verifier found the decision and condition outcomes listed in the table that can occur and are active logic.

**4** Investigate the analysis results for `Sens_Failure_Counter.INC`:

- In the analysis report, in the **Analysis Information** chapter, the **Constraints** section lists the constraints for `control logic/Input Data "press"`. The value of `press` is constrained to values between 0 and 2.
- In the Model Explorer window, select **Base Workspace > zero\_thresh**. The value of `zero_thresh` is 250.
- With the design constraints, `press` is always less than `zero_thresh`. The logic `press < zero_thresh` is never false. The false condition for the transition is never exercised. Therefore, it is dead logic.

**5** Close `sldvdemo_fuelsys_logic_simple`.

## Model Objects That Receive Dead Logic Detection

Model objects that have decision or condition outcomes receive dead logic detection, as the following table shows. Click a link in the first column to get more detailed information about the outcomes for specific model objects.

Model Object Receiving Dead Logic Detection	Decision Outcomes	Condition Outcomes
<a href="#">“Abs” on page 6-15</a>	●	
<a href="#">“Dead Zone” on page 6-15</a>	●	
<a href="#">“Discrete-Time Integrator” on page 6-16</a>	●	
<a href="#">“Enabled Subsystem” on page 6-16</a>	●	●
<a href="#">“Enabled and Triggered Subsystem” on page 6-17</a>	●	●
<a href="#">“Fcn” on page 6-17</a>		●
<a href="#">“For Iterator, For Iterator Subsystem” on page 6-17</a>	●	
<a href="#">“If, If Action Subsystem” on page 6-18</a>	●	●
<a href="#">“Library-Linked Objects” on page 6-18</a>	●	●
<a href="#">“Logical Operator” on page 6-18</a>		●
<a href="#">“MATLAB Function” on page 6-18</a>	●	●
<a href="#">“MinMax” on page 6-19</a>	●	
<a href="#">“Model” on page 6-19</a>	●	●
<a href="#">“Multiport Switch” on page 6-19</a>	●	
<a href="#">“Rate Limiter” on page 6-19</a>	●	
<a href="#">“Relay” on page 6-20</a>	●	
<a href="#">“Saturation” on page 6-20</a>	●	
<a href="#">“Stateflow Charts” on page 6-21</a>	●	●
<a href="#">“Switch” on page 6-21</a>	●	

Model Object Receiving Dead Logic Detection	Decision Outcomes	Condition Outcomes
“SwitchCase, SwitchCase Action Subsystem” on page 6-21	•	
“Triggered Models” on page 6-21	•	•
“Triggered Subsystem” on page 6-22	•	•
“While Iterator, While Iterator Subsystem” on page 6-22	•	

## Abs

The Abs block has decision outcomes based on:

- Input to the block being less than zero.
- Data type of the input signal.

For input to the block being less than zero, there are two decision outcomes:

- Block input is less than zero, indicating a true decision.
- Block input is not less than zero, indicating a false decision.

If the input data type to the Abs block is `uint8`, `uint16`, or `uint32`, the software sets the block output equal to the block input without making a decision. If the input data type to the Abs block is `Boolean`, an error occurs.

## Dead Zone

The Dead Zone block has decision outcomes based on these parameters:

- **Start of dead zone**
- **End of dead zone**

The **Start of dead zone** parameter specifies the lower limit of the dead zone. For the **Start of dead zone** parameter, there are two decision outcomes:

- Block input is greater than or equal to the lower limit, indicating a true decision.
- Block input is less than the lower limit, indicating a false decision.

The **End of dead zone** parameter specifies the upper limit of the dead zone. For the **End of dead zone** parameter, there are two decision outcomes:

- Block input is greater than the upper limit, indicating a true decision.
- Block input is less than or equal to the upper limit, indicating a false decision.

### Discrete-Time Integrator

The Discrete-Time Integrator block has decision outcomes based on these parameters:

- **External reset**
- **Limit output**

If you set **External reset** to **none**, the software does not report decision outcomes. Otherwise, there are two decision outcomes:

- Block output is reset, indicating a true decision.
- Block output is not reset, indicating a false decision.

If you do not select **Limit output**, the software does not report decision outcomes. Otherwise, the software reports decision outcomes for the **Lower saturation limit** and the **Upper saturation limit**.

For the **Upper saturation limit**, there are two decision outcomes:

- Integration result is greater than or equal to the upper limit, indicating a true decision.
- Integration result is less than the upper limit, indicating a false decision.

For the **Lower saturation limit**, there are two decision outcomes:

- Integration result is less than or equal to the lower limit, indicating a true decision.
- Integration result is greater than the lower limit, indicating a false decision.

### Enabled Subsystem

The Enabled Subsystem block has two decision outcomes:

- Block is enabled, indicating a true decision.
- Block is disabled, indicating a false decision.

The Enabled Subsystem block has two condition outcomes only if the enable input is a vector:

- Element of the enable input is true, indicating a true condition.
- Element of the enable input is false, indicating a false condition.

## Enabled and Triggered Subsystem

The Enabled and Triggered Subsystem block has two decision outcomes:

- Trigger edge occurs while the block is enabled, indicating a true decision.
- Trigger edge does not occur while the block is enabled, or the block is disabled, indicating a false decision.

The software determines condition outcomes for the enable input and the trigger input separately.

- For the enable input:
  - Input is true, indicating a true condition.
  - Input is false, indicating a false condition.
- For the trigger input:
  - Trigger edge occurs, indicating a true condition.
  - Trigger edge does not occur, indicating a false condition.

## Fcn

The Fcn block has two condition outcomes based on input values or arithmetic expressions that are inputs to Boolean operators in the block:

- Input to a Boolean operator is true, indicating a true condition.
- Input to a Boolean operator is false, indicating a false condition.

## For Iterator, For Iterator Subsystem

The For Iterator block and For Iterator Subsystem have two decision outcomes:

- Iteration value being at or below the iteration limit, indicated as true.

- Iteration value being above the iteration limit, indicated as false.

### If, If Action Subsystem

The If blocks that causes an If Action Subsystem to execute has:

- Decision outcomes for the `if` condition and all `elseif` conditions defined in the If block.
- Condition outcomes if the `if` condition or any of the `elseif` conditions contains a logical expression with multiple conditions.

### Library-Linked Objects

Simulink blocks and Stateflow charts that are linked to library objects receive the same dead logic detection that they would receive if they were not linked to library objects.

### Logical Operator

The Logical Operator block has two condition outcomes:

- Input is true, indicating a true condition.
- Input is false, indicating a false condition.

### MATLAB Function

The following MATLAB Function block statements have decision outcomes:

- Function header - Function or sub-function that is executed.
- `if` - Expression evaluates to true, indicating a true decision. Expression evaluates to false, indicating a false decision.
- `switch` - Decision outcomes corresponding to every switch case path, including the fall-through case.
- `for` - Loop condition evaluates to true, indicating a true decision. Loop condition evaluates to false, indicating a false decision.
- `while` - Loop condition evaluates to true, indicating a true decision. Loop condition evaluates to false, indicating a false decision.

The following logical conditions have condition outcomes:



- `if` statement conditions
- `while` statement conditions

## MinMax

The MinMax block has decision outcomes based on passing each input to the output of the block.

For passing each input to the output of the block, there are two decision outcomes:

- Input passed to block output, indicating a true decision.
- Input not passed to block output, indicating a false decision.

## Model

The Model block itself does not have decision or condition outcomes. The model that the block references receive the decision or condition outcomes.

## Multiport Switch

The Multiport Switch block has decision outcomes based on passing each input, excluding the first control input, to the output of the block.

For passing each input, excluding the first control input, to the output of the block, there are two decision outcomes:

- Input passed to block output, indicating a true decision.
- Input not passed to block output, indicating a false decision.

## Rate Limiter

The Rate Limiter block has decision outcomes based on the **Rising slew rate** and **Falling slew rate** parameters.

For the **Rising slew rate**, there are two decision outcomes:

- Block input changes more than or equal to the rising rate, indicating a true decision.
- Block input changes less than the rising rate, indicating a false decision.

For the **Falling slew rate**, there are two decision outcomes:

- Block input changes less than or equal to the falling rate, indicating a true decision.
- Block input changes more than the falling rate, indicating a false decision.

The software does not have **Falling slew rate** outcomes for a time step when the **Rising slew rate** is true.

### Relay

The Relay block has decision outcomes based on the **Switch on point** and the **Switch off point** parameters.

For the **Switch on point**, there are two decision outcomes:

- Block input is greater than or equal to the **Switch on point**, indicating a true decision.
- Block input is less than the **Switch on point**, indicating a false decision.

For the **Switch off point**, there are two decision outcomes:

- Block input is less than or equal to the **Switch off point**, indicating a true decision.
- Block input is greater than the **Switch off point**, indicating a false decision.

The software does not have **Switch off point** decision outcomes for a time step when the switch on threshold is true.

### Saturation

The Saturation block has decision outcomes based on the **Lower limit** and **Upper limit** parameters.

For the **Upper limit**, there are two decision outcomes:

- Block input is greater than or equal to the upper limit, indicating a true decision.
- Block input is less than the upper limit, indicating a false decision.

For the **Lower limit**, there are two decision outcomes:

- Block input is greater than the lower limit, indicating a true decision.

- Block input is less than or equal to the lower limit, indicating a false decision.

The software does not have **Lower limit** decision outcomes for a time step when the upper limit is true.

## Stateflow Charts

The Stateflow Chart block has decision outcomes:

- Transition decision is evaluated as true, indicating a true decision.
- Transition decision is evaluated as false, indicating a false decision.

The Stateflow Chart block has condition outcomes:

- Condition is evaluated as true, indicating a true condition.
- Condition is evaluated as false, indicating a false condition.

## Switch

The Switch block has decision outcomes based on the control input to the block.

For the control input to the block, there are two decision outcomes:

- Control input evaluates to true, indicating a true decision.
- Control input evaluates to false, indicating a false decision.

## SwitchCase, SwitchCase Action Subsystem

The SwitchCase block and SwitchCase Action Subsystem have two decision outcomes:

- Block evaluates to true, indicating a true decision.
- Block does not evaluate to true, indicating a false decision.

## Triggered Models

The Triggered Models block has two decision outcomes:

- Referenced model is triggered, indicating a true decision.
- Referenced model is not triggered, indicating a false decision.

If the trigger input is a vector, then there are two condition outcomes:

- Element of the trigger port is true, indicating a true condition.
- Element of the trigger port is false, indicating a false condition.

### **Triggered Subsystem**

The Triggered Subsystem block has two decision outcomes:

- Block is triggered, indicating a true decision.
- Block is not triggered, indicating a false decision.

If the trigger input is a vector, then there are two condition outcomes:

- Element of the trigger edge is true, indicating a true condition.
- Element of the trigger edged is false, indicating a false condition.

### **While Iterator, While Iterator Subsystem**

The While Iterator block and While Iterator Subsystem have two decision outcomes:

- `while` condition is satisfied, indicating a true decision.
- `while` condition is not satisfied, indicating a false decision.

# Detect Integer Overflow and Division-by-Zero Errors

## In this section...

“About This Example” on page 6-23

“Analyze the Model” on page 6-23

“Review the Analysis Results” on page 6-24

“Limitation of Integer Overflow Detection” on page 6-27

## About This Example

The following sections describe how to analyze the `sldvdemo_cruise_control_fxp_fixed` model for integer overflow and division-by-zero errors.

## Analyze the Model

Open and check model for integer overflow and division-by-zero errors:

- 1 Open the `sldvdemo_cruise_control_fxp_fixed` model.
- 2 Select **Analysis > Design Verifier > Options**.
- 3 In the Configuration Parameters dialog box, in the **Select** tree under **Design Verifier**, select the **Design Error Detection** node.
- 4 On the **Design Error Detection** pane, select:
  - **Integer overflow**
  - **Division by zero**
- 5 In the Configuration Parameters dialog box, on the **Diagnostics > Data Validity** pane, set **Signals > Wrap on overflow**, **Signals > Saturate on overflow** and **Parameters > Detect overflow** to error.
- 6 Click **OK** to save these settings and close the Configuration Parameters dialog box.
- 7 Select **Analysis > Design Verifier > Detect Design Errors > Model**.

When the analysis is complete:

- The software highlights the model with the analysis results.

- The Simulink Design Verifier Results dialog box opens and displays a summary of the analysis.

### Review the Analysis Results

- “Review the Results on the Model” on page 6-24
- “Review the Harness Model” on page 6-26
- “Review the Analysis Report” on page 6-27


### Review the Results on the Model

The derived ranges can help you understand the source of an error by identifying the possible signal values, as you can see by taking the following steps:

- 1 At the top level of the `sldvdemo_cruise_control_fxp_fixed` model, click the Fixed-Point Controller subsystem.

The Simulink Design Verifier Results window displays the derived range of possible signal values for the Outports, as calculated by the analysis:


- The values of Output 1 (throt) range from  $-2.6101$  to  $2.6096$ .
- The values of Output 2 (target) range from  $0$  to  $256$ .




- 2 Click the Output blocks of the `sldvdemo_cruise_control_fxp_fixed` model to see the same signal bound values.
- 3 Open the Fixed-Point Controller subsystem.

Two objects in this subsystem are outlined in red. The PI Controller subsystem is outlined in green.

- 4 Click the Sum block, outlined in red, that provides the error input to the PI Controller subsystem.



This Sum block can produce an overflow error. The analysis found a test case that can result in a computation where the output of the Sum block exceeds the range  $[-128..128]$ .



- 5 To more fully understand this error, click the two blocks that provide the inputs to the Sum block. In the Simulink Design Verifier Results window, view their derived ranges:
  - The third Outputport from the Bus block has a range of  $[0..256]$ .
  - The Output from the Switch block has a range of  $[0..256]$ .

You can see that the sum operation for these signal ranges can compute a value that exceeds the range  $[-128..128]$  for the Output of the Sum block.

The analysis reports the overflow error on the Sum block. The analysis does not propagate this error and assumes that the Sum block output is within the valid range for any subsequent computations.

- 6 Click the PI Controller subsystem, outlined in green. None of the blocks in the PI Controller subsystem can produce overflow or division-by-zero errors. When the software analyzes the PI Controller subsystem, it ignores the overflow error from the Sum block and assumes that the inputs to the subsystem are valid.

Keep the `sldvdemo_cruise_control_fxp_fixed` model open. In the next section, you create the harness model to see the test case that generates the Sum block overflow error.

### Review the Harness Model

To see the test cases that demonstrate the errors, generate the harness model from the Simulink Design Verifier Results window:

- 1 In the `sldvdemo_cruise_control_fxp_fixed` model, open the Fixed-Point Controller subsystem.
- 2 Click the Sum block, outlined in red, that provides the error input to the PI Controller subsystem.

The Simulink Design Verifier Results window displays information that an overflow error occurred.

- 3 In the Simulink Design Verifier Results window, click **View test case**.

The software creates a harness model containing the test case with the signal values that cause this overflow error.

In the harness model, the Signal Builder dialog box opens, with Test Case 2 displayed.

- 4 Click the Start simulation button to simulate the model with this test case.

As expected, the simulation fails due to an overflow error at the Sum block in the Fixed-Point Controller subsystem.

For more information, see “Simulink Design Verifier Harness Models”.



## Review the Analysis Report

To view an HTML report containing detailed information about the analysis report for the `sldvdemo_cruise_control_fxp_fixed` model:

- 1 In the Simulink Design Verifier Results window, to redisplay the results summary, click **Back to summary**.
- 2 Click **Generate detailed analysis report**.

The software generates a detailed analysis report that opens in a browser.

For the `sldvdemo_cruise_control_fxp_fixed` model, the **Design Error Detection Objectives Status** chapter of the report provides detailed results in two categories:

- **Objectives Proven Valid** — Model objects that did not produce errors
- **Objectives Falsified with Test Cases** — Model objects for which test cases generated errors

For more information, see “Simulink Design Verifier Reports”.

## Limitation of Integer Overflow Detection

Design error detection for integer overflow does not detect overflow for fixed-point types with nonstandard word length, i.e. a word length that is not 8-bit, 16-bit, or 32-bit.

## Check for Specified Intermediate Minimum and Maximum Signal Values

### In this section...

“Overview of Specified Minimum and Maximum Signal Values” on page 6-28

“About This Example” on page 6-29

“Create the Example Model” on page 6-29

“Analyze the Model” on page 6-30

“Review the Analysis Results” on page 6-31

### Overview of Specified Minimum and Maximum Signal Values

During a design error detection analysis, the software checks the specified minimum and maximum values on intermediate signals throughout the model and on the output ports. These values define the *design ranges*.

The analysis checks for specified minimum and maximum values on:

- Simulink block outputs, with the exception of the limitations described in the next section
- `Simulink.Signal` objects
- Stateflow data objects
- MATLAB for code generation data objects
- Global data store writes

If the analysis detects that a signal exceeds the design range, the results identify where in the model the errors occurred. In addition, you can generate a harness model that contains test cases that demonstrate how the error occurred.

### Limitations of Checking Specified Minimum and Maximum Signal Values

If you analyze a model checking if specified minimum and maximum values are exceeded, the software cannot check minimum and maximum values specified on:

- `Simulink.BusElement` objects.
- Any Mux block with an output connected to a Selector block
- Merge block inputs

To work around this limitation, use a `Simulink.Signal` object on the Merge block output and specify the range on the `Simulink.Signal` object.

---

**Note:** For information about how a Simulink Design Verifier analysis handles specified minimum and maximum values on input ports, see “Minimum and Maximum Input Constraints”.

---

## About This Example

In this section, you create and analyze a model that has specified design minimum and maximum values on:

- The input ports
- The output ports of two of the intermediate blocks

The design error detection analysis identifies blocks where the output values exceed the design range. If the analysis detects this error, this example demonstrates how the analysis uses the specified minimum and maximum values when continuing the analysis.

## Create the Example Model

Create the model for this example:

- 1 In the model window, select **File > New > Model**.
- 2 From the Simulink Commonly Used Blocks library, add the following blocks to the model and assign the indicated parameter values.

Block	Tab	Parameter	Value
Inport	Signal Attributes	Minimum	0
Inport	Signal Attributes	Maximum	5
Gain	Main	Gain	5
Gain	Signal Attributes	Output minimum	0
Gain	Signal Attributes	Output maximum	20
Gain	Signal Attributes	Output data type	int16
Saturation	Main	Upper limit	25

Block	Tab	Parameter	Value
Saturation	Main	Lower limit	-25
Saturation	Signal Attributes	Output minimum	-25
Saturation	Signal Attributes	Output maximum	25
Outport	No changes		

- 3 Connect the four blocks as shown.



- 4 To display the specified minimum and maximum values in the model window, select **Display > Signals & Ports > Design Ranges**.
- 5 Select **Analysis > Design Verifier > Options**.
- 6 In the Configuration Parameters dialog box, on the **Solver** pane, under **Solver options**:
- a Set **Type** to Fixed-step.  
The Simulink Design Verifier software does not support variable-step solvers.
  - b Set **Solver** to discrete (no continuous states).
- 7 On the **Design Verifier** pane, set **Mode** to Design error detection.
- 8 On the **Design Verifier > Design Error Detection** pane:
- a Select **Check specified intermediate minimum and maximum values**.
  - b Clear the **Integer overflow** and **Division by zero** parameters.
- In this example, you check only for intermediate minimum and maximum violations.
- 9 To save these settings and exit the Configuration Parameters dialog box, click **OK**.
- 10 Save the model and name it `ex_interim_minmax`.

## Analyze the Model


To analyze the example model to identify any intermediate signals that violate the specified minimum and maximum values, select **Analysis > Design Verifier > Detect Design Errors > Model**.

After the analysis is complete:

- The software highlights the model with the analysis results.



- The Simulink Design Verifier Results dialog box opens and displays a summary of the analysis.



## Review the Analysis Results

- “Review Results on the Model” on page 6-31
- “Review the Harness Model” on page 6-33
- “Review the Analysis Report” on page 6-34

### Review Results on the Model

In the model window, the Gain block is colored red and the Saturation block is colored green. This indicates that:


- At least one objective associated with the Gain block was falsified. For this example, the analysis falsified exactly one objective.
- All objectives associated with the Saturation block were satisfied. For this example, the analysis satisfied exactly one objective.

To understand these results:

- 1 Click the Gain block.

The Simulink Design Verifier Results window shows that the design range for the output was [0..20], but the analysis detected an error and generated a test case that demonstrates that error. Because the design range for the input block is [0..5], when the input to the Gain block is 5, the output is 25, which exceeds the specified maximum value on that port.


The analysis computes and displays the derived range to help you understand how the design range was exceeded.



When the software detects an error, the analysis proceeds, but constrains the signal to the tightest intersection of the design range and the derived range, which for the Gain block output in this example is [0..20].

- 2 Click the Saturation block.

The Simulink Design Verifier Results window shows that the output of the Saturation block never exceeded the design range [-25..25]. The input to the Saturation block never exceeded [0..20], which is the derived range that the analysis propagated from the Gain block.



### Review the Harness Model

When the analysis completes, you can create a harness model contains the test cases that result in errors.

For the example model, view the test case that caused the design range error in the Gain block:

- 1 After the analysis completes and the model is highlighted, click the Gain block.
- 2 In the Simulink Design Verifier Results window, click **View test case**.

The software creates a harness model named `ex_interim_minmax_harness` and opens the Signal Builder block in the harness model that contains the test case.

In the Signal Builder block, one test case, whose signal value is 5, caused the output of the Gain block to be 25, which exceeds the specified maximum of 20.

- 3 Before you simulate this test case, in the Configuration Parameters dialog box, on the **Diagnostics > Data Validity** pane, set **Simulation range checking** to warning or error.

Setting this parameter specifies the diagnostic action to take if Simulink detects signals that exceed specified minimum or maximum values during simulation.

- If you specify **warning**, the simulation displays a warning message and continues.

- If you specify **error**, the simulation displays an error message and stops.
- 4 Click **OK** to save your change and close the Configuration Parameters dialog box.
  - 5 In the Signal Builder block window, click **Start simulation** to simulate the model with this test case.

As expected, in the MATLAB window, the simulation displays a warning or error that the output value of the Gain block exceeds the specified maximum.

### Review the Analysis Report

You can also generate an HTML report containing detailed information about the analysis report for the `ex_interim_minmax` model. To create this report, in the Simulink Design Verifier Results window, click **Generate detailed analysis report**. The analysis report opens in a browser.

In the analysis report, the **Design Error Detection Objectives Status** chapter of the report provides detailed results in two categories:

- **Objectives Proven Valid** — The output values for the Saturation block are always within the design range.
- **Objectives Falsified with Test Cases** — The output values for the Gain block violated the design range.



## Detect Out of Bound Array Access Errors

### In this section...

“Design Error Detection for Out of Bound Array Access” on page 6-35

“Detect Out of Bound Array Access in Example Model” on page 6-35

“Limitations of Support for Out of Bound Array Access Design Error Detection” on page 6-41

### Design Error Detection for Out of Bound Array Access

Simulink Design Verifier design error detection analysis detects out of bound array access errors in your model. In simulation, when your model attempts to access an array element using an invalid index, an out of bound array access error occurs.

To detect out of bound array access errors in your model:

- 1 In the Simulink Editor, select **Analysis > Design Verifier > Options**.  
The Configuration Parameters dialog box opens to the **Design Verifier** pane.
- 2 Under **Analysis options**, from the **Mode** list, select **Design error detection**.
- 3 In the **Select** tree, under **Design Verifier**, select **Design Error Detection**.
- 4 Select **Out of bound array access**.
- 5 Click **OK**.
- 6 In the Simulink Editor, select **Analysis > Design Verifier > Detect Design Errors > Model**.

The Simulink Design Verifier log window opens, showing the progress of the analysis.

When the analysis is complete:

- The software highlights the model with the analysis results.
- The Simulink Design Verifier Results dialog box opens and displays an analysis summary.


### Detect Out of Bound Array Access in Example Model

This example shows how to detect out of bound array access errors in the `sldvdemo_array_bounds` example model.

- 1 At the MATLAB command prompt, type:

```
sldvdemo_array_bounds
```

The example model opens.



This example shows you how to statically detect out of bound array errors using Simulink Design Verifier. This model contains errors that result from using 1-based indices in a 0-based Stateflow array.

<b>Run</b> (double-click)	<b>View Options</b> (double-click)	<b>More Information</b> (double-click)
Run Simulink Design Verifier	View Simulink Design Verifier Options	View Documentation


Using input signal values, the ComputeIndex MATLAB Function block determines a range of indices with minimum `minIdx` and maximum `maxIdx`. The `ArrayOp_Matlab`, `ArrayOp_MAL`, and `ArrayOp_SF` blocks use the set of integer indices between `minIdx` and `maxIdx` to access array elements and perform array operations.

In this example model, the analysis options are configured for out of bound array access error detection. To view these options, double-click the **View Simulink Design Verifier Options** button.


- 2 Start the design error detection analysis by double-clicking the **Run Simulink Design Verifier** button.

The Simulink Design Verifier log window opens, displaying the progress of the analysis.


When the analysis is complete, the example model is highlighted with the analysis results.



- 3 View the analysis results inside the chart by double-clicking the ArrayOp\_SF Chart block, highlighted in red.



- 4 See detailed analysis results for the Diff state in the Simulink Design Verifier Results window by selecting the Diff state. That state is highlighted in red.



Simulink Design Verifier detected index out of bound errors for array `u` in state `Diff`.

- 5 Click the first **View test case** link.

Simulink Design Verifier creates and opens a harness model that contains test cases, or input signal groups, that demonstrate out of bound array access errors.


- 6 In the Signal Builder dialog box, click **Start simulation** to simulate the harness model with Test Case 1.

The simulation stops just before entering the state `Diff`. The Stateflow Debugger opens. The following error is shown:

```
Runtime error: Index into array out of range
Model Name: sldvdemo_array_bounds_harness
Block Name: sldvdemo_array_bounds_harness/...
  Test Unit (copied from sldvdemo_array_bounds)/ArrayOp_SF
  Attempted to access 4 element of data u(#188 (0:3:0))...
  The valid index range is 0 to 3
```

Keep the Stateflow Debugger open at this breakpoint.

- 7 In the `sldvdemo_array_bounds_harness` model, hold your cursor over the Diff state to see the data values at this simulation breakpoint.



Using Test Case 1 input signal values, the ComputeIndex MATLAB Function block determines the range of array indices to be 1:4. One-based indexing is consistent with MATLAB syntax, so these indices are valid for the ArrayOp\_Matlab MATLAB Function block and the ArrayOp\_MAL Stateflow chart.

The ArrayOp\_SF Stateflow chart uses C as the action language, which does not support one-based indexing. `1:4` is not a valid index range for array access in that chart. The valid index range for array access in that chart is `0:3`, as the error message reported. When either `maxIdx` or `minIdx` evaluates to 4, an out of bound array access error occurs in the ArrayOp\_SF Chart block.

For more information on zero-based indexing support, see “Differences Between MATLAB and C as Action Language Syntax”.

## **Limitations of Support for Out of Bound Array Access Design Error Detection**

### **Inf Index Values**

Design error detection does not support indexing by `Inf`. If your model attempts to access an array using an index value that evaluates to `Inf`, design error detection does not report an out of bound array access error, but in simulation, an out of bound array access error occurs.

### **Index Vector Block with Scalar Data Input**

Out of bound array access design error detection does not support Index Vector blocks with scalar data inputs. If your model includes an Index Vector block that specifies a scalar data input instead of a vector data input and the control input causes an out of bounds array access, design error detection does not report an error, but an error occurs in simulation.





# Generating Test Cases

---

- “What Is Test Case Generation?” on page 7-2
- “Workflow for Test Case Generation” on page 7-4
- “Generate Test Cases for Model Decision Coverage” on page 7-5
- “Generate Test Cases for a Subsystem” on page 7-21
- “Select Components for Test Case Generation” on page 7-22
- “Model Coverage Objectives for Test Generation” on page 7-28

## What Is Test Case Generation?

The Simulink Design Verifier software can generate test cases that satisfy coverage objectives for your model, including:

- “Decision”
- “Condition”
- “MCDC”

Test cases help you confirm model performance by demonstrating how the blocks in the model execute in different modes. When generating test cases, the software performs a formal analysis of your model. After completing the analysis, the software provides several ways for you to review the results.

### Test Case Blocks

For customizing test cases for your Simulink models, the Simulink Design Verifier software provides two blocks:

- The Test Objective block defines the values of a signal that a test case must satisfy.
- The Test Condition block constrains the values of a signal during analysis.

### Test Case Functions

To customize test cases for a Simulink model or Stateflow chart, the Simulink Design Verifier software provides two MATLAB functions. You can use these functions in a MATLAB Function block. Both functions are active in generated code and in Simulink Design Verifier.

- `sldv.test` — Specifies a test objective.
- `sldv.condition` — Specifies a test condition.

These functions:

- Identify mathematical relationships for testing in a form that can be more natural than using block parameters.
- Support specifying multiple objectives, assumptions, or conditions without complicating the model.

- Provide access to the power of MATLAB.
- Support separation of verification and model design.

For an example of how to use these functions, see the `sldv.test` or `sldv.condition` reference page.

---

**Note:** Simulink Design Verifier blocks and functions are saved with a model. If you open the model on a MATLAB installation that does not have a Simulink Design Verifier license, you can see the blocks and functions, but they do not produce results.

---

## Workflow for Test Case Generation

To generate test cases for your model, use the following workflow.

Task	Description	For an example, see
1	Verify that your model is compatible for use with the Simulink Design Verifier software.	“Check Compatibility of the Example Model”
2	If you have Stateflow objects in your model, in the Configuration Parameters dialog box, on the <b>Diagnostics &gt; Stateflow</b> pane, set <b>Transition shadowing</b> to <b>error</b> .	
3	Optionally, instrument your model with blocks or MATLAB functions that specify test objectives and test conditions.	“Customize Test Generation”
4	Specify options that control how Simulink Design Verifier generates test cases for your model.	“Configure Test Generation Options”
5	Execute the Simulink Design Verifier analysis.	“Analyze the Example Model” and “Reanalyze the Example Model”
6	Review the analysis results.	“Review Analysis Results”

## Generate Test Cases for Model Decision Coverage


### In this section...

- “Construct the Example Model” on page 7-5
- “Check Compatibility of the Example Model” on page 7-6
- “Configure Test Generation Options” on page 7-7
- “Analyze the Example Model” on page 7-8
- “Review Analysis Results” on page 7-8
- “Customize Test Generation” on page 7-17
- “Reanalyze the Example Model” on page 7-19
- “Analyze Contradictory Models” on page 7-20

### Construct the Example Model

Construct a model for this example:

- 1 Create a Simulink model.
- 2 Copy the following blocks into your empty model window:
  - From the Sources library, an Inport block to initiate the input signal whose value the Simulink Design Verifier software controls.
  - From the Sources library, two Constant blocks to serve as Switch block data inputs.
  - From the Signal Routing library, a Switch block to provide simple logic.
  - From the Sinks library, an Outport block to receive the output signal.
- 3 In your model, double-click one of the Constant blocks and specify its **Constant value** parameter as 2.
- 4 Connect the blocks so that your model appears similar to the following diagram.



- 5 In the model window, select **Simulation > Model Configuration Parameters**.
- 6 On the left side of the Configuration Parameters dialog box, in the **Select** tree, click the **Solver** category. On the right side, under **Solver options**:
  - Set the **Type** option to **Fixed-step**.
  - Set the **Solver** option to **Discrete (no continuous states)**.

Simulink Design Verifier analyzes only models that use a fixed-step solver.

- 7 Click **OK** to save your changes and close the Configuration Parameters dialog box.
- 8 Save your model with the name `ex_generate_test_cases_example`.

## Check Compatibility of the Example Model


Every time Simulink Design Verifier analyzes a model, before the analysis begins, the software performs a compatibility check. If your model is not compatible, the software cannot analyze it.

Before you start the analysis, you can also make sure that your model is compatible with Simulink Design Verifier software:

- 1 Open the `ex_generate_test_cases_example` model.
- 2 In the model window, select **Analysis > Design Verifier > Check Compatibility > Model**.

The software displays the log window, which states whether or not your model is compatible for analysis.

The model you just created is compatible.



### What If a Model Is Partially Compatible?

If the compatibility check indicates that your model is partially compatible, your model contains at least one object that Simulink Design Verifier does not support. You can analyze a partially compatible model, but, by default, the unsupported objects are stubbed out. The results of the analysis can be incomplete.

For detailed information about automatic stubbing, see “Handle Incompatibilities with Automatic Stubbing” on page 2-8.

### Configure Test Generation Options

Configure the Simulink Design Verifier software to generate test cases that achieve 100% decision coverage for the `ex_generate_test_cases_example` model:

- 1 Open the `ex_generate_test_cases_example` model.
- 2 In the model window, select **Analysis > Design Verifier > Options**.
- 3 On the left side of the Configuration Parameters dialog box, in the **Select** tree, click the **Design Verifier** category. Under **Analysis options**, set the **Mode** option to **Test generation**.
- 4 On the left side of the Configuration Parameters dialog box, in the **Select** tree, click the **Test Generation** category.
- 5 On the **Test Generation** pane, set the **Model coverage objectives** parameter to **Decision**.

For this example, the analysis generates test cases that record only decision coverage.

The **Test suite optimization** parameter is set by default to **CombinedObjectives**. If you want to generate fewer but longer test cases, select **LongTestcases** for the **Test suite optimization** parameter.

- 6 Click **OK** to save your changes and close the Configuration Parameters dialog box.
- 7 Save the `ex_generate_test_cases_example` model.

### Analyze the Example Model


To analyze the `ex_generate_test_cases_example` model, in the model window, select **Analysis > Design Verifier > Generate Tests > Model**. The Simulink Design Verifier software begins analyzing your model to generate test cases.

During the analysis, the log window shows the progress of the analysis. It displays information such as the number of test objectives processed and which objectives are satisfied.

### Review Analysis Results

When the software completes its analysis, the log window displays the following options for reviewing the results.





The following sections describe how you can review the analysis results:


- “Review Analysis Results on the Model” on page 7-10
- “Review Detailed Analysis Report” on page 7-12
- “Review Harness Model” on page 7-13
- “Simulate Tests and Produce a Model Coverage Report” on page 7-14
- “View sldvData File” on page 7-16

- “Review Analysis Results in the Model Explorer” on page 7-16


### Review Analysis Results on the Model


Highlight the analysis results on the example model:

- 1 In the log window for the `ex_generate_test_cases_example` analysis, click **Highlight analysis results on model**.



The Switch block is outlined in green, which indicates that the Switch block has test cases that satisfy its test objectives.


The Simulink Design Verifier Results window opens. As you click objects in the model, this window changes to display detailed analysis results for that object. By default, the Simulink Design Verifier Results window is always the topmost visible window. To allow the window to move behind other window, click  and clear Always on top.



- 2 Click the highlighted Switch block.

The Simulink Design Verifier Results window indicates that the analysis generated test cases for both test objectives:

- `trigger >= threshold`
- `trigger < threshold`



For more information about highlighted analysis results on a model, see “Highlighted Results on the Model” on page 13-2.

## Review Detailed Analysis Report

Create a detailed HTML analysis report:

- 1 In the Simulink Design Verifier log window, click **Generate detailed analysis report**.

The HTML report opens in a browser window.

- 2 The report includes the following **Table of Contents**. Click a hyperlink to navigate to a section in the report.

<b>Table of Contents</b>
<a href="#">1. Summary</a>
<a href="#">2. Analysis Information</a>
<a href="#">3. Test Objectives Status</a>
<a href="#">4. Model Items</a>
<a href="#">5. Test Cases</a>

- 3 In the **Table of Contents**, click **Summary** to display the report's Summary chapter.

The Summary chapter lists information about the model and the status of the objectives—satisfied or not.

- 4 In the **Table of Contents**, click **Analysis Information** to display the Analysis Information chapter.

The Analysis Information chapter provides information about:

- The model that you analyzed.
- The options that you specified for the analysis.
- Approximations the software performed during the analysis.

- 5 In the **Table of Contents**, click **Test Objectives Status** to display the report's Test Objectives Status chapter.

This table indicates that the analysis satisfied both test objectives associated with the Switch block in the `ex_generate_test_cases_example` model, for which it generated two test cases.

- 6 Under the table **Test Case** column, click **2** to display the Test Case 2 section.


This section provides details about a test case that the analysis generated to achieve an objective in your model. This test case achieves test objective 1, when the Switch block passes its third input to its output port. Specifically, the software determines that a value of  $-1$  for the Switch block control signal causes the block to pass its third input as the block output.

For more information about the HTML reports, see “Simulink Design Verifier Reports” on page 13-27.

### Review Harness Model

To create a harness model with test cases that satisfy the test objectives in your model, in the Simulink Design Verifier log window, click **Create harness model**.

The software creates a harness model named `ex_generate_test_cases_example_harness`.



The Signal Builder block named Inputs contains the test cases. Double-click the Inputs block to see the test cases. From the Signal Builder block, you can simulate the model using the test cases and produce a model coverage report, as described in “Simulate Tests and Produce a Model Coverage Report”.

For more information about the harness model, see “Simulink Design Verifier Harness Models” on page 13-16.

### If Analysis Generates Many Test Cases

If you have a large model, the analysis might produce a harness model that contains a large number of test cases.

To perform a more efficient analysis and create easier-to-review results:


- 1 Set the **Test suite optimization** parameter to `LongTestcases`.
- 2 Rerun the analysis.

In the `LongTestcases` optimization, the analysis generates fewer but longer test cases that each satisfy multiple test objectives.

### **Simulate Tests and Produce a Model Coverage Report**

To simulate the harness model using the generated test cases in the harness model:

- 1 In the harness model, double-click the Inputs block to open the Signal Builder dialog box.



2

In the Signal Builder dialog box, click **Run all** .

The software simulates the harness model using both test cases, collects model coverage information, and displays a coverage report. The coverage report indicates that the test cases record 100% decision coverage for the `ex_generate_test_cases_example` model.

You can also simulate the model without creating a harness model. In the Simulink Design Verifier log window, click **Simulate tests and produce a model coverage report**.

For more information about model coverage, see “Top-Level Model Coverage Report” in the Simulink Verification and Validation documentation.

### View sldvData File

The Simulink Design Verifier data file is a MAT-file that contains a structure named `sldvData`. This structure stores all the data that the analysis gathers and produces during the analysis. You can use the data file to conduct your own analysis or to generate a custom report.

To view the data file, click the data file name in the log window, in this example, `ex_generate_test_cases_example_sldvdata.mat`. When you click the file name, a copy of the `sldvData` object is instantiated in the MATLAB workspace so that you can review and manipulate the data.

For more information about Simulink Design Verifier data files, see “Simulink Design Verifier Data Files” on page 13-9.

### Review Analysis Results in the Model Explorer

As long as your model remains open, you can view the results of your most recent Simulink Design Verifier analysis in the Model Explorer.

In the Simulink Editor, select **Analysis > Design Verifier > Results > Active**. The Model Explorer opens. The results of the latest Simulink Design Verifier analysis appear in the right-hand pane.

For any Simulink Design Verifier analysis, from the Model Explorer, you can perform the following tasks.

Task	For more information
Highlight the analysis results on the model.	“Highlighted Results on the Model” on page 13-2
Generate a detailed analysis report.	“Simulink Design Verifier Reports” on page 13-27
Create the harness model, or if the harness model already exists, open it.	“Simulink Design Verifier Harness Models” on page 13-16




Task	For more information
If no test cases were generated during the analysis, this option is not available.	
View the data file.	“Simulink Design Verifier Data Files” on page 13-9
View the log file.	“Simulink Design Verifier Log Files” on page 13-50

After you close your model, you can no longer view analysis results.

## Customize Test Generation

You can use the Test Condition block to constrain signals in your model to certain values during the analysis.


- 1 At the MATLAB command prompt, enter `sldvlib` to display the Simulink Design Verifier library.
- 2 Open the Objectives and Constraints sublibrary.
- 3 Copy the Test Condition block to your model by dragging it from the Simulink Design Verifier library to your model window.
- 4 In the model window, insert the Test Condition block between the Inport and Switch blocks.



- 5 Double-click the Test Condition block to access its attributes.

The Test Condition block parameters dialog box opens.

- 6 In the **Values** box, enter `[-0.1, 0.1]`. When generating test cases for this model, the analysis constrains the signal values, entering the Switch block control port to the specified range.



- 7 Click **OK** to save your changes and close the Test Condition block parameters dialog box.
- 8 Save your model as `ex_generate_test_cases_with_tc_block` and keep it open.

## Reanalyze the Example Model

Analyze the `ex_generate_test_cases_with_tc_block` model with the Test Condition block. To observe how the Test Condition block affects test generation, compare the result of this analysis to the result that you obtained in “Analyze Example Model”.

- 1 In the model window, select **Analysis > Design Verifier > Generate Tests > Model**.

The Simulink Design Verifier software displays a log window and begins analyzing your model to generate test cases. When the software completes the analysis, the log window displays the options for reviewing the results.

- 2 In the Simulink Design Verifier log window, click **Generate detailed analysis report**.
- 3 To begin reviewing the report, in the **Table of Contents**, click **Summary**.

The Summary chapter indicates that the Simulink Design Verifier software satisfied two test objectives in the model.

- 4 In the **Table of Contents**, click **Analysis Information**. Scroll to the bottom of this chapter, to the Constraints section.

This section lists the Test Condition block that you added to constrain the value of the Switch block control signal to the interval  $[-0.1, 0.1]$ .

- 5 In the **Table of Contents**, click **Test Objectives Status**.

This table indicates that the Simulink Design Verifier software satisfied both test objectives for the Switch block through the two test cases generated.

- 6 Under the table **Test Case** column, click 1.

This section provides details about a test case that the software generated to achieve an objective in your model. This test case achieves test objective 1, when the Switch block passes its third input to its output port. Although the Test Condition block restricts the domain of input signals to the interval  $[-0.1, 0.1]$ , the software determines that a value of  $-0.1$  for the Switch block control signal satisfies this objective.

- 7 To confirm that the test case achieves 100% decision coverage, open the harness model.
- 8 Double-click the Inputs block to open the Signal Builder dialog box.

9

In the Signal Builder dialog box, click **Run all** .

The Simulink software simulates the harness model using both test cases, collects model coverage information, and displays a coverage report. The Summary section of the report indicates that the Simulink Design Verifier software generated test cases that achieve complete decision coverage for your example model.

### Analyze Contradictory Models

If the analysis produces the error `The model is contradictory in its current configuration`, the software detected a contradiction in your model and cannot analyze the model.

You can have a contradiction if your model has Test Objective blocks with incorrect parameters. For example, a contradiction can be an objective that states that a signal must be between 0 and 5 when the signal is the constant 10.

If the software detects a contradiction, all previous results are invalidated and the software reports that some of the objectives cannot be satisfied.

## Generate Test Cases for a Subsystem

If you have a large model, to review the analysis in smaller, manageable reports, you can generate test cases for subsystems in the model.

- 1 Open the model that contains the subsystem.
- 2 Make the subsystem atomic.
- 3 Run the Simulink Design Verifier software using the **Generate Tests for Subsystem** option.
- 4 Review the results.

The tutorial in “Analyze a Subsystem” describes how to analyze the Controller subsystem in the Cruise Control Test Generation model.

## Select Components for Test Case Generation


In this section...
“Test Generation Advisor” on page 7-22
“Test Generation Advisor Requirements” on page 7-24
“Identify Analyzable Components” on page 7-24
“Analyze and Generate Tests for Model Components” on page 7-24

### Test Generation Advisor

You can use the Test Generation Advisor to select model components (atomic subsystems and model blocks) for test generation. The Test Generation Advisor summarizes test generation compatibility, condition and decision objectives, and dead logic for the model and model components.

The Test Generation Advisor performs a high-level analysis and fast dead logic detection. You can use the results to better understand your model before test generation, particularly for large models, complex models, or models for which you are uncertain of the test generation compatibility. For example, you can:

- Identify components that are incompatible with test case generation.
- Identify complex components that may be time-consuming to analyze.
- Determine instances of dead logic.
- Get a snapshot of the component hierarchy.
- Get recommended test generation parameters.



The Test Generation Advisor classifies components as analyzable, complex, or incompatible.

- *Analyzable* components are compatible with Simulink Design Verifier. The preliminary analysis indicates that Simulink Design Verifier might achieve high component coverage.
- *Complex* components are also compatible with Simulink Design Verifier. However, the preliminary analysis indicates that Simulink Design Verifier might require more time and resources to achieve high component coverage due to component complexity or other factors. For more information, see “Sources of Model Complexity”.
- You cannot generate tests for *incompatible* components. For more information, see “Check Model Compatibility”.

The results summary displays specific information about the model and each component:

- **Status:** The compatibility or complexity
- **Objectives:** The number of condition and decision objectives
- **Dead Logic Detected:** The number of instances of dead logic detected during the analysis. This might not include every instance of dead logic.
- **Objectives Decided:** The percentage of condition and decision objectives determined by test cases and dead logic.

### Test Generation Advisor Requirements

For analysis, your model must compile. Also, if you change the model name, you must reload the model and reopen the Test Generation Advisor.

### Identify Analyzable Components

To analyze your model using the Test Generation Advisor, follow this high-level workflow:


- 1 Open your model.
- 2 From the menu bar, click **Analysis > Design Verifier > Generate Tests > Advisor**.
- 3 Your model compiles, and the Test Generation Advisor opens. It displays the model hierarchy and summary table.
- 4 Enter a time value for **Seconds per component**, which limits the analysis time per component. This value does not include time for other operations such as compilation.
- 5 Run the analysis by clicking **Play**. Track the analysis using the progress indicator.
- 6 Determine incompatibilities, complexities and characteristics from the component hierarchy tree and the results summary.
- 7 Trace from the summary to the model using the component hyperlinks.

### Analyze and Generate Tests for Model Components


This example demonstrates analysis and test generation using the Test Generation Advisor. The example model has analyzable and incompatible subsystems.

- 1 At the command line, enter `fuelsys` to open the `fuelsys` model.
- 2 Save a copy of the model in a writable location on the MATLAB path.
- 3 Click **Analysis > Design Verifier > Generate Tests > Advisor** to open the Test Generation Advisor.






- 4 In the **Seconds per component** text box, enter 25.
- 5 Click **Play** to begin the model analysis.
- 6 After the analysis is complete, the component tree displays results for the overall model and each component.






- Highlight the control logic subsystem in the component hierarchy. The analysis was partial, in that it determined 87% of the objectives for control logic by test cases and dead logic. To load the test generation summary, click the **Show test generation results summary** link.

At the bottom of the summary, the table lists recommended test generation parameters.


**Component Name: control logic**

Overall progress 

Components processed 7/7

 Incompatible: 2       Analyzable: 5       Complex: 0

*Summary of subcomponents in 'control logic'*

Component Name	Status	Objectives (Condition Decision)	Dead Logic Detected	Objectives Decided (%)
<a href="#">fuelsys/fuel rate controller/control logic</a>		109	0	87.156%

---

*Preliminary Test Generation Results*

Preliminary analysis result for control logic: 95 out of 109 objectives decided.  
[Show test generation results summary \(Partial\)](#)

---

*Preliminary Dead Logic Detection*

No **dead logic** found in 'control logic'.

---

*Recommendations*

SLDV Option	Recommendation
Maximum analysis time(seconds)	300
Automatic stubbing of unsupported atomic blocks	on
Testsuite generation strategy	CombinedObjectives (Nonlinear Extended)

---

- 8 Click the **Component name** hyperlink. Simulink traces to the control logic Stateflow chart.
- 9 Generate the full set of tests for the subsystem. In the Test Generation Advisor summary for control logic, click **Extract this component and generate tests**.

## Model Coverage Objectives for Test Generation

In this section...
“Decision” on page 7-28
“Condition” on page 7-28
“MCDC” on page 7-29
“Relational Boundary” on page 7-29

### Decision

Decision coverage examines blocks and Stateflow states that represent decision points in a model. For instance, the Switch block involves the decision about whether the control input is greater than a threshold value. For more information, see “Model Objects That Receive Coverage” in Simulink Verification and Validation documentation.

To enable decision coverage, under **Design Verifier > Test Generation**, for **Model coverage objectives**, select one of the following:

- Decision
- Condition Decision
- MCDC

For each decision in your model, Simulink Design Verifier generates test cases that satisfy the coverage objective. For more information, see “Decision Coverage (DC)” in Simulink Verification and Validation documentation.

### Condition

Condition coverage examines blocks that output the logical combination of their inputs and Stateflow transitions. For more information, see “Model Objects That Receive Coverage” in Simulink Verification and Validation documentation.

To enable condition coverage, under **Design Verifier > Test Generation**, for **Model coverage objectives**, select one of the following:

- Condition Decision
- MCDC

For each input to a logical block and each condition in a transition, Simulink Design Verifier generates test cases that satisfy the coverage objective. For more information, see “Condition Coverage (CC)” in Simulink Verification and Validation documentation. .

## MCDC

Modifier condition/decision coverage examines blocks that output the logical combination of their inputs and Stateflow transitions. For more information, see “Model Objects That Receive Coverage” in Simulink Verification and Validation documentation.

To enable condition MCDC coverage, under **Design Verifier > Test Generation**, for **Model coverage objectives**, select MCDC.

For each input to a logical block and each condition in a transition, Simulink Design Verifier generates test cases that satisfy the coverage objective. For more information, see “MCDC Coverage” in Simulink Verification and Validation documentation.

For information on how MCDC test generation deviates from strict MCDC coverage, see “Modified Condition and Decision Coverage in Simulink Design Verifier”.

## Relational Boundary

Relational boundary coverage examines blocks that have an explicit or implicit relational operation and Stateflow transitions. For more information, see “Model Objects That Receive Coverage” in Simulink Verification and Validation documentation. Test generation for relational boundary coverage is not supported for If and Fcn blocks.

To enable relational boundary coverage, under **Design Verifier > Test Generation**, select **Include relational boundary objectives**.

For each relational operation in the model, Simulink Design Verifier generates test cases that satisfy the coverage objective. For more information, see “Relational Boundary Coverage” in Simulink Verification and Validation documentation.



# Extending Existing Test Cases

---

- “When to Extend Existing Test Cases” on page 8-2
- “Common Workflow for Extending Existing Test Cases” on page 8-4
- “Extend Test Cases for Model with Temporal Logic” on page 8-5
- “Extend Test Cases for Closed-Loop System” on page 8-12
- “Extend Test Cases for Modified Model” on page 8-19

## When to Extend Existing Test Cases

The Simulink Design Verifier software can analyze your model using previously generated test cases that you specify. You can use this feature in the following situations:

- You encounter delays trying to analyze your model, or you see incomplete results. This can happen if your model has any of the following characteristics:
  - Temporal logic
  - Large counters
  - Model objects that are difficult to test due to complex or nonlinear logic

Analyzing the model and considering the existing test cases allows you to focus the analysis on those parts of the model that are difficult to analyze. You can combine the generated test cases to create a complete test suite for the full model.

For an example of extending existing test cases for a model that uses temporal logic, see “Extend Test Cases for Model with Temporal Logic” on page 8-5.

- You have a closed-loop simulation model that uses a Model block to include the controller. First, log the data from the Model block and then analyze the model referenced by the Model block. Using this technique, the test cases for the controller can realistically reflect the continuous time behavior expected in the closed-loop system.

For an example of extending existing test cases for a closed-loop system, see “Extend Test Cases for Closed-Loop System” on page 8-12.

- You change an existing model for which you have already generated test cases. In this situation, you can reanalyze the model, omitting the analysis results from the original version of the model. The combined test cases give you a complete test suite for the new model.

For an example of extending existing test cases for modified models, see “Extend Test Cases for Modified Model” on page 8-19.

---

**Note:** When you configure Simulink Design Verifier to treat parameters as variables in its analysis, you cannot also use the analysis to extend existing test cases. In **Analysis > Design Verifier > Options**, if you specify your model to extend existing test cases with a **Data file** and apply parameter configurations with a **Parameter configuration file**, when you attempt to perform Simulink Design Verifier analysis, the software



reports that your model is incompatible. This occurs because the existing test cases do not include corresponding parameter values.

---

## Common Workflow for Extending Existing Test Cases

Use the following workflow for extending existing test cases during a test-generation analysis:

- Create the starting test cases.
- Log the starting test cases.
- Extend the existing test cases during test-generation analysis.
- Verify that you have created a complete test suite.

The examples in this category use some or all of these tasks when extending existing test cases during analysis.

## Extend Test Cases for Model with Temporal Logic

### In this section...

- “Create Starting Test Case” on page 8-5
- “Log Starting Test Case” on page 8-8
- “Extend Existing Test Cases” on page 8-9
- “Verify Analysis Results” on page 8-11

### Create Starting Test Case


This example uses the `sldvdemo_sbr_extend_design` model. This model includes a Stateflow chart SBR that uses temporal logic. The transition from the `KEY_OFF` state to the `KEY_ON` state occurs after the Stateflow chart has been simulated 500 times. To test this transition requires a test case with 500 time steps.

In this example, you create a test case that forces the transition to `KEY_ON` by setting the `KEY` input to 1 for the duration of the test case. You simulate the model using this test case, satisfying the objectives for the `KEY_OFF/KEY_ON` transition. Then you analyze the model, ignoring the objectives already satisfied by the test case you create.

- 1 Open the example model:

```
sldvdemo_sbr_extend_design
```

- 2 Open the SBR Stateflow chart to see the `KEY_OFF/KEY_ON` transition.




- 3 Create a model reference harness model:


```
[-, harnessModelFilePath] = ...
sldvmakeharness('sldvdemo_sbr_extend_design', [], [], true);
```

The harness model, `sldvdemo_sbr_extend_design_harness`, includes:

- A Model block named Test Unit that references the original model, `sldvdemo_sbr_extend_design`.




- A Signal Builder block named Inputs that contains the test-case inputs to the model referenced in the Model block.



Initially, the Signal Builder block contains only the default test case, with all three inputs set to 0.

- A DocBlock block named Test Case Explanation that documents the test case.




Initially, the Test Case Explanation block does not have any content for the default test case.

- 4 `sldvmakeharness` returns the path to the harness model file in `harnessModelFilePath`. Extract the name of the harness model file into `harnessModel`, for later use:


```
[~, harnessModel] = fileparts(harnessModelFilePath);
```

In order to analyze the KEY\_OFF to KEY\_ON state transition, create a test case that makes the transition to the KEY\_ON state in 500 time steps:

- 1 Open the Signal Builder dialog box for the harness model.
- 2 Select **Axes > Change Time Range**.
- 3 The Signal Builder's time range determines the span of time over which its output is explicitly defined. In the Set the total time range dialog box, set the **Max time** field to 5 seconds, creating 500 time steps of 0.01 seconds duration each.
- 4 Set the KEY input to 1 for the duration of this starting test case, forcing the transition to the KEY\_ON state. Selecting the **Inputs.KEY** signal requires two clicks. First, click the signal so that dots appear at both ends of the signal.




- 5 Click the **Inputs.KEY** signal again. The Signal Builder thickens the signal to indicate that it is selected.



- 6 At the bottom of the Signal Builder dialog box, under **Left Point**, enter 1 for **Y**.
- 7 Press **Enter** to apply the change.

The **Inputs.KEY** signal is set to 1 for the duration of the test case.



- 8 Close the Signal Builder dialog box.

## Log Starting Test Case

The next step is to log the starting test case that you created. You can then specify that the Simulink Design Verifier software ignore the objectives satisfied by that test case when performing an analysis.

The `sldvlogsignals` function records the test case data in a MAT-file that contains an `sldvData` structure. This structure stores all the data that the software gathers and produces during the analysis.

To log the starting test cases:

- 1 Save the name of the Model block in the harness model that references the `sldvdemo_sbr_extend_design` model:
- 2 Simulate the model referenced by the Model block using the new test case, and log the input signals in the workspace variable `loggeddata`:

```
loggeddata = sldvlogsignals(modelBlock{1});
```

- 3 Save the logged data in a MAT-file named `existingtestcase.mat`:

```
save('existingtestcase.mat', 'loggeddata');
```

You will specify this file when you analyze the `sldvdemo_sbr_extend_design` model.

## Extend Existing Test Cases

You can now analyze the `sldvdemo_sbr_extend_design` model and specify that the analysis extend the test cases already satisfied. The analysis uses the existing test-case data as a starting point, and does not try to generate test cases for the `KEY_OFF` to `KEY_ON` transition in the SBR Stateflow chart.


Specify the starting test case and analyze the model:

- 1 In the model window for `sldvdemo_sbr_extend_design`, select **Analysis > Design Verifier > Options**.
- 2 In the Configuration Parameters dialog box, in the **Select** tree, under **Design Verifier**, select **Test Generation**.
- 3 On the **Test Generation** pane, under **Existing test cases**, select **Extend existing test cases**.
- 4 In the **Data file** field, enter the name of the MAT-file that contains the logged data:  
`existingtestcase.mat`
- 5 Clear **Ignore objectives satisfied by existing test cases**.

When you clear this option, the software includes the starting test case in the final test suite. You will see that the complete test suite achieves 100% model coverage.

- 6 To close the Configuration Parameters dialog box, click **OK**.
- 7 Save the `sldvdemo_sbr_extend_design` model on the MATLAB path with the name `sldvdemo_sbr_extend_design_test`.
- 8 In the Model Editor, select **Analysis > Design Verifier > Generate Tests > Model**.

The log window first lists the objectives that the starting test case satisfied.




The log window then lists the objectives generated beyond the starting test case.




## Verify Analysis Results

To make sure that this analysis creates a complete test suite, generate the harness model so you can simulate the model with the generated test cases:

- 1 In the log window, click **Create harness model**.
- 2 In the harness model `sldvdemo_sbr_extend_design_test_harness`, open the Signal Builder block named Inputs.
- 3 To simulate the model using all the test cases, click the **Run all and produce coverage** button .

When the simulation is complete, the model coverage report is displayed.

- 4 View the coverage information for the `sldvdemo_sbr_extend_design_test` model to see that the complete test suite achieves 100% coverage.



## Extend Test Cases for Closed-Loop System

<b>In this section...</b>
“Log Starting Test Case” on page 8-12
“Extend Existing Test Cases” on page 8-15

Suppose that you have a model with a closed-loop controller in a model referenced by a Model block. You do not record 100% coverage for the referenced model. Extending existing test cases can help you achieve 100% coverage. The Simulink Design Verifier software adds time steps to the existing test cases when analyzing the controller implemented by the referenced model. The test cases that result from the analysis realistically reflect the continuous time behavior expected in the closed-loop controller.

A *closed-loop controller* passes instructions to the controlled system and receives information from the environment as the control instructions execute. The controller can adapt and change its instructions as it receives this information.

### Log Starting Test Case

This example uses the `sldemo_mdhref_basic` model. The CounterA Model block references the model `sldemo_mdhref_counter`. When you simulate the parent model, `sldemo_mdhref_basic`, and collect coverage, you record only 75% coverage for `sldemo_mdhref_counter`. Log the data from the simulation and extend those test cases to achieve 100% coverage for the referenced model.

- 1 Open the example model:

`sldemo_mdhref_basic`

- 2 In the Simulink Editor, select **Analysis > Coverage > Settings**.

The Coverage Settings dialog box opens.

- 3 In the Coverage Settings dialog box, select **Coverage for referenced models**.

Note that the analysis records coverage only for referenced models with **Simulation mode** set to Normal. In `sldemo_mdhref_basic`, the CounterC Model block has **Simulation mode** set to Accelerator, so you cannot record coverage for it.


- 4 Under **Coverage metrics**, select **Decision**, **Condition**, and **MCDC** to record decision, condition, and modified condition/decision coverage.

- 5 Click **OK**.
- 6 Simulate the model.

When the simulation completes, the generated coverage report opens in a browser window. The report shows the following coverage results for the referenced model:

- Condition: 50% (2/4) condition outcomes
- Decision: 25% (1/4) decision outcomes
- MCDC: 0% (0/2) conditions reversed the outcome

The coverage results are also highlighted in the referenced model, `sldemo_md1ref_counter`. You can select individual model objects to view specific coverage results in the Coverage dialog box, as shown in the following screenshot.



- 7 To log the input signals for the CounterA Model block in sldemo\_mdref\_basic during simulation, at the MATLAB command prompt, enter the following code:

```
logged_data = sldvlogs('sldemo_mdref_basic/CounterA');
```

- 8 Save the logged data in a MAT-file named `existingtestcase.mat`:

```
save('existingtestcase.mat', 'logged_data');
```

When you analyze the model referenced in CounterA (`sldemo_mdref_counter`) to extend existing test cases, you specify this MAT-file.

## Extend Existing Test Cases

Analyze the `sldemo_mdref_counter` model, specifying that the analysis extend the test cases already satisfied:

- 1 To open the `sldemo_mdref_counter` model, in the `sldemo_mdref_basic` model, double-click the CounterA Model block.
- 2 In the Simulink Editor, select **Analysis > Design Verifier > Options**.
- 3 In the Configuration Parameters dialog box, on the **Select** pane, under **Design Verifier**, select **Test Generation**.
- 4 On the **Test Generation** pane, in the **Model coverage objectives** box, select **MCDC**.
- 5 Under **Existing test cases**, select **Extend existing test cases**.
- 6 In the **Data file** field, specify the name of the MAT-file that contains the logged data, in this case, `existingtestcase.mat`.
- 7 Clear **Ignore objectives satisfied by existing test cases**.

When you clear this option, the software includes the test cases recorded in the file `existingtestcase.mat` in the final test suite.

- 8 Click **OK**.
- 9 In the Simulink Editor, select **Analysis > Design Verifier > Generate Tests > Model**.

The analysis first loads the objectives satisfied by the logged test cases. Then it adds extra time steps to those test cases and tries to satisfy any missing objectives. When the analysis completes, the Simulink Design Verifier log window opens and indicates that all 12 objectives are satisfied.

- 10 To view the analysis results on the model, in the Simulink Design Verifier log window, select **Highlight analysis results on model**.

The Simulink Design Verifier results are highlighted in the referenced model, `sldemo_md1ref_counter`. You can select individual model objects to view specific analysis results in the Simulink Design Verifier Results dialog box, as shown in the following screenshot.

The image displays the Simulink environment for a model named 'sldemo\_mdref\_counter'. The main workspace shows a block diagram of a closed-loop control system. The system has three input ports: 'upper' (value 1), 'lower' (value 3), and 'input' (value 2). The 'input' signal is summed and compared against the 'upper' and 'lower' limits using '>=' blocks. The results of these comparisons are combined in an 'AND' block. This 'AND' block's output is used to control a 'Switch' block, which selects between the 'previous\_output' (from a 'z' block) and the current sum. The 'Switch' block's output is limited by a 'limit' block and then fed back to the 'z' block. A 'ScopeA' block is used for monitoring. The status bar at the bottom left indicates 'Ready'.

In the bottom right corner, the 'Simulink Design Verifier Results' window is open, showing the following test results for the 'sldemo\_mdref\_counter/Switch' block:

- [Back to summary](#) - [Close results](#)
- sldemo\_mdref\_counter/Switch**
- logical trigger input false (output is from 3rd input port) **SATISFIED** - [View test case](#)
- logical trigger input true (output is from 1st input port) **SATISFIED** - [View test case](#)

- 11 To verify the results of the analysis and review the generated test cases, in the Simulink Design Verifier log window, select **Generate detailed analysis report**.
- 12 To collect model coverage using the extended test suite, in the Simulink Design Verifier log window, select **Simulate tests and produce a model coverage report**.

When the simulation completes, the generated coverage report opens in a browser window. The report now shows the following coverage results for the referenced model `sldemo_md1ref_counter`:

- Condition: 100% (4/4) condition outcomes
- Decision: 100% (4/4) decision outcomes
- MCDC: 100% (2/2) conditions reversed the outcome



## Extend Test Cases for Modified Model

### In this section...

“Create Starting Test Cases” on page 8-19

“Extend Existing Test Cases” on page 8-20


Suppose that you have a model that you have already analyzed using the Simulink Design Verifier software, and you modify the model. The original test suite may not record 100% coverage for the modified model. Reanalyze the modified model to make sure that it satisfies all the new test objectives. Instead of reanalyzing the entire model, you focus the new analysis on just the modified part of the model. In this way, you leverage the test cases created for the original model, extending them to satisfy any new objectives.

This example uses the `sldvdemo_cruise_control` model. You analyze the model and generate test cases. Then you analyze a modified version of that model, `sldvdemo_cruise_control_mod`, extending the test cases from the original analysis. The analysis returns a complete test suite for the new model.

### Create Starting Test Cases

Analyze the `sldvdemo_cruise_control` model and generate test cases that achieve 100% coverage.

- 1 Open the example model:  
`sldvdemo_cruise_control`
- 2 To start a Simulink Design Verifier analysis for the `sldvdemo_cruise_control` model, double-click the Run Simulink Design Verifier block:



Run Simulink Design Verifier

The analysis satisfies 34 test objectives for the `sldvdemo_cruise_control` model. The software stores the resulting data file in a subfolder of the MATLAB Current Folder:

```
sldv_output\sldvdemo_cruise_control\sldvdemo_cruise_control_sldvdata.mat
```

In the next section, when you analyze the modified model, this data file specifies the starting test cases that you extend.

- 3 Close the `sldvdemo_cruise_control` model and all the files created by the analysis. If asked, do not save any changes you made to the model.

## Extend Existing Test Cases


The `sldvdemo_cruise_control_mod` model is a modified version of `sldvdemo_cruise_control`. The Controller subsystem contains a Saturation block that specifies that the target speed cannot exceed 70.

Open the modified model and analyze it, extending the test cases that you generated when analyzing the `sldvdemo_cruise_control` model:

- 1 Open the example model, the modified version of `sldvdemo_cruise_control`:

```
sldvdemo_cruise_control_mod
```

- 2 Double-click the Controller subsystem to see the change to the original model, a Saturation block that specifies the maximum speed:



- 3 Close the Controller subsystem.
- 4 Select **Analysis > Design Verifier > Options**.
- 5 In the Configuration Parameters dialog box, on the **Select** pane, under **Design Verifier**, select **Test Generation**.
- 6 On the **Test Generation** pane, under **Existing test cases**, select **Extend existing test cases**.
- 7 In the **Data file** field, click **Browse** and navigate to the MAT-file created in the MATLAB Current Folder when analyzing the original model:

sldv\_output\sldvdemo\_cruise\_control\sldvdemo\_cruise\_control\_sldvdata.mat

- 8** Clear **Ignore objectives satisfied by existing test cases**.

When you clear this option, the analysis includes the test cases recorded in the file `sldvdemo_cruise_control_sldvdata.mat` in the final test suite.

- 9** Click **Apply** to save these settings.
- 10** To open the main **Design Verifier** pane, in the **Select** tree, click **Design Verifier**.
- 11** To start the analysis, click **Generate Tests**.

The analysis first loads the 34 objectives satisfied by the initial test cases. Then it adds extra time steps to those test cases and tries to satisfy any missing objectives.

- 12** In the log window, click **Generate detailed analysis report**.

The analysis satisfied a total of 38 satisfied objectives for the `sldvdemo_cruise_control_mod` model. The analysis satisfied four additional objectives that correspond to the Saturation block.

<b>Objectives Satisfied</b>				
Simulink Design Verifier found test cases that exercise these test objectives.				
#	Type	Model Item	Description	Test Case
1	Decision	<a href="#">Controller/Switch1</a>	logical trigger input false (output is from 3rd input port)	<a href="#">3</a>
2	Decision	<a href="#">Controller/Switch1</a>	logical trigger input true (output is from 1st input port)	<a href="#">1</a>
3	Decision	<a href="#">Controller/Saturation</a>	input > lower limit F	<a href="#">1</a>
4	Decision	<a href="#">Controller/Saturation</a>	input > lower limit T	<a href="#">3</a>
5	Decision	<a href="#">Controller/Saturation</a>	input >= upper limit F	<a href="#">1</a>
6	Decision	<a href="#">Controller/Saturation</a>	input >= upper limit T	<a href="#">10</a>



# Achieving Test Cases for Missing Model Coverage

---

- “Generate Test Cases for Missing Coverage Data” on page 9-2
- “Achieve Missing Coverage in Referenced Model” on page 9-3
- “Missing Coverage in Subsystems and Model Blocks” on page 9-7
- “Achieve Missing Coverage in Closed-Loop Simulation Model” on page 9-8
- “Modified Condition and Decision Coverage in Simulink Design Verifier” on page 9-12

## Generate Test Cases for Missing Coverage Data

If you simulate your model and record coverage data, but your model does not achieve 100% coverage, the Simulink Design Verifier software can find test cases that achieve the missing coverage. The software targets the test-generation analysis for the part of the model that is missing coverage, ignoring the model coverage data that was recorded during simulation.

The following examples describe how to focus the test-generation analysis on a part of the model that did not achieve 100% coverage:

- “Achieve Missing Coverage in Referenced Model” on page 9-3
- “Achieve Missing Coverage in Closed-Loop Simulation Model” on page 9-8

## Achieve Missing Coverage in Referenced Model

### In this section...

“Record Coverage Data for Example Model” on page 9-3

“Find Test Cases for the Missing Coverage” on page 9-5

“Achieve Missing Coverage” on page 9-5

“Verify 100% Model Coverage” on page 9-6

This example model uses a referenced model that does not achieve full coverage. When you run a test-generation analysis on the referenced model and combine it with previously recorded coverage data, you can achieve 100% coverage for the referenced model.

### Record Coverage Data for Example Model

Simulate the example model, recording Condition, Decision, and MCDC coverage.

- 1 Open the example model:

`sldemo_mdhref_basic`

The Model blocks CounterA, CounterB, and CounterC reference the model `sldemo_mdhref_counter`.

- 2 In the Simulink Editor, select **Analysis > Coverage > Settings**.

The Coverage Settings dialog box opens to the Coverage tab.

- 3 On the **Coverage** tab, set the following options:

- Select **Coverage for referenced models**.
- Click **Select Models**. In the Select Models for Coverage Analysis dialog box, select the check boxes for the referenced model, `sldemo_mdhref_counter`. Click **OK**.

Check boxes for `sldemo_mdhref_counter` appear twice, corresponding to CounterA and CounterB. Coverage cannot be enabled for CounterC since it specifies the `Accelerator` simulation mode in its model reference parameters.

- Specify which types of coverage to record during simulation. Under **Coverage metrics**, select:

- **Decision**
- **Condition**
- **MCDC**

- 4 Click the **Results** tab. Set the following options:
  - Select **Save last run in workspace variable** to save the collected coverage data from the most recent simulation run in a variable in the MATLAB workspace.
  - In the **cvdata object name** field, enter `covdata_original` to specify a unique name for the coverage data workspace variable.
- 5 Click the **Reporting** tab. Set the following options:
  - Select **Generate HTML report** to specify that the simulation create a coverage report.
  - Select **Last run** to specify that the coverage report show data from the most recent simulation run.
- 6 Click **OK**.
- 7 Start the simulation of the `sldemo_md1ref_basic` model to record the coverage data.

After the simulation, the coverage report opens. The report indicates that the following coverage is achieved for the referenced model `sldemo_md1ref_counter`:

- Decision: 25%
- Condition: 50%
- MCDC: 0%

The simulation saves the coverage data in the MATLAB workspace variable `covdata_original`, a `cvdata` object that contains the coverage data.

- 8 Save the coverage data in a file on the MATLAB path:

```
cvsave('existingcov',covdata_original);
```

Keep the model open as you continue through this example.



## Find Test Cases for the Missing Coverage

To achieve 100% coverage for the `sldemo_md1ref_counter` model, run a test-generation analysis that uses the existing coverage data.

- 1 Open the referenced model using the following command:

```
open_system('sldemo_md1ref_counter');
```

- 2 Create an `sldvoptions` object:

```
opts = sldvoptions;
```

When you create the `sldvoptions` object, you need to specify:

- That the analysis ignore satisfied coverage data.
- The file name containing the satisfied coverage data (`existingcov.cvt`)

Enter the following commands to specify these options:

```
opts.IgnoreCovSatisfied = 'on';  
opts.CoverageDataFile = 'existingcov.cvt';
```

- 3 Analyze the referenced model, `sldemo_md1ref_counter`, using the specified options:

```
[status, fileNames] = sldvrun('sldemo_md1ref_counter',opts,true);
```

The Simulink Design Verifier analysis satisfies five objectives and creates one test case for the referenced model.

The next section simulates the referenced model, `sldemo_md1ref_counter`, using the test case that the analysis created.

## Achieve Missing Coverage

To achieve the missing coverage for the referenced model, `sldemo_md1ref_counter`, simulate the model using the test case from the Simulink Design Verifier analysis.

- 1 Open the referenced model using the following command:

```
open_system('sldemo_md1ref_counter');
```

- 2 Create a `cvttest` object for the simulation and specify to record Decision, Condition, and MCDC coverage.

```

cvt = cvtest('sldemo_mdhref_counter');
cvt.settings.decision = 1;
cvt.settings.condition = 1;
cvt.settings.mcDC = 1;

```

- 3 Specify to record coverage and set the name of the `cvtest` object.

```

runOpts = sldvruntestopts;
runOpts.coverageEnabled = true;
runOpts.coverageSetting = cvt;

```

- 4 Simulate the model using the `cvtest` object, `cvt`, and the test case, as defined in `fileNames.DataFile`. Save the recorded coverage data in the workspace variable `covdata_missing`.

```

[-, covdata_missing] = sldvruntest('sldemo_mdhref_counter', fileNames.DataFile, runOpts);

```

## Verify 100% Model Coverage

You saved the coverage data from the simulation of the top-level model, `sldemo_mdhref_basic` in the workspace variable `covdata_original`. To create a report that combines the coverage data from the top-level model with the missing coverage data from the referenced model, `sldemo_mdhref_counter`, enter the following command:

```

cvhtml('Coverage Summary', covdata_original, covdata_missing);

```

The report shows that by analyzing the referenced model and using those results to record coverage, you can achieve 100% decision, condition, and MCDC coverage.

### Summary

Model Hierarchy/Complexity:	Test 1			Test 2			Total		
	D1	C1	MCDC	D1	C1	MCDC	D1	C1	MCDC
1. <a href="#">sldemo_mdhref_counter</a>	3 25%	50%	0%	75%	100%	0%	100%	100%	100%

## Missing Coverage in Subsystems and Model Blocks

If your model has a Subsystem block that does not achieve full coverage, you can convert it to model referenced in a Model block. “Convert a Subsystem to a Referenced Model” describes how to convert a subsystem to a referenced model. You can then follow the steps described in “Achieve Missing Coverage in Referenced Model” on page 9-3.

However, some subsystems cannot be converted to Model blocks. To test a subsystem to see if it can be converted to a Model block, use the `Simulink.SubSystem.convertToModelReference` function. If that function cannot convert the subsystem, an error message explains why the conversion failed.

In addition, you may have a Stateflow chart or a MATLAB Function block that does not achieve full coverage. Stateflow charts and MATLAB Function blocks cannot be converted to referenced models.

For situations when you cannot use a Model block, follow steps similar to the steps described in the following section, “Achieve Missing Coverage in Closed-Loop Simulation Model” on page 9-8.

## Achieve Missing Coverage in Closed-Loop Simulation Model

### In this section...

“Record Coverage Data for the Model” on page 9-8

“Find Test Cases for Missing Coverage” on page 9-9

If you have a subsystem or a Stateflow chart that does not achieve 100% coverage, and you do not want to convert the subsystem or chart to a Model block, this example can help you achieve full coverage.

The example uses a closed-loop controller model. A *closed-loop controller* passes instructions to the controlled system and receives information from the environment as the control instructions are executed. The controller can adapt and change its instructions as it receives this information.

The `sldvdemo_autotrans` model is a closed-loop simulation model. The ShiftLogic Stateflow chart represents the controller part of this model. Test cases designed in the ManeuversGUI Signal Builder block drive the closed-loop simulation.

### Record Coverage Data for the Model

To simulate the model, recording Condition, Decision, and MCDC coverage for the ShiftLogic controller:

- 1 Open the example model:  
`sldvdemo_autotrans`
- 2 In the Simulink Editor, select **Analysis > Coverage > Settings**.  
  
The Coverage Settings dialog box opens to the **Coverage** tab.
- 3 Select **Coverage for this model: sldvdemo\_autotrans**.
- 4 Click **Select Subsystem**.
- 5 In the Subsystem Selection dialog box, select ShiftLogic and click **OK**.
- 6 Under **Coverage metrics**, select the types of coverage that you want the simulation to record:
  - **Decision**

- **Condition**
  - **MCDC**
- 7** Clear the other coverage metrics if they are checked.
  - 8** Click the Results tab.
  - 9** In the **covdata object name** field, enter `covdata_original_controller` to specify a unique name for the coverage data workspace variable.
  - 10** Click the **Reporting** tab.
  - 11** Select **Generate HTML report**.
  - 12** Click **OK**.
  - 13** Start the simulation of the `sldvdemo_autotrans` model to record the coverage data.

After the simulation, the coverage report opens. The report indicates that the following coverage is achieved for the ShiftLogic Stateflow chart:

- Decision: 87% (27/31) decision outcomes
- Condition: 67% (8/12) condition outcomes
- MCDC: 33% (2/6) conditions reversed the outcome

The simulation saves the coverage data in the MATLAB workspace variable `covdata_original_controller`, a `cvtest` object that contains the coverage data.

- 14** Save the coverage data in a file on the MATLAB path:

```
cvsave('existingcov',covdata_original_controller);
```

## Find Test Cases for Missing Coverage

To find the missing coverage for the ShiftLogic chart, run a subsystem analysis on that block. Use this technique to focus your analysis on an individual part of the model.

To achieve 100% coverage for the ShiftLogic controller, run a test-generation analysis that uses the existing coverage data.

- 1** Right-click the ShiftLogic block and select **Design Verifier > Options**.
- 2** In the Configuration Parameters dialog box, under the **Select** tree, choose the **Design Verifier** node. Under **Analysis options** in the **Mode** field, select **Test generation**.

- 3 Under the **Design Verifier** node, select **Test Generation**. Under **Existing coverage data**, select **Ignore objectives satisfied in existing coverage data**.
- 4 In the **Coverage data file** field, enter the name of the file containing the coverage data that you recorded during simulation:  
`existingcov.cvt`
- 5 Click **Apply** to save these settings.
- 6 Under the **Select** tree, click **Design Verifier**.
- 7 On the main **Design Verifier** pane, click **Generate Tests**.

The analysis extracts the Stateflow chart into a new model named `ShiftLogic0`. The analysis analyzes the new model, ignoring the coverage objectives previously satisfied and recorded in the `existingcov.cvt` file.

- 8 When the test-generation analysis is complete, in the Simulink Design Verifier log window, select **Simulate tests and produce a model coverage report**.

The report indicates that the following coverage is achieved for the ShiftLogic chart in simulation with the test cases generated by Simulink Design Verifier:

- Decision: 84% (26/31) decision outcomes
- Condition: 83% (10/12) condition outcomes
- MCDC: 67% (4/6) conditions reversed the outcome

The Simulink Design Verifier report lists six test cases for the extracted model that satisfy the objectives not covered in the `existingcov.cvt` file.

---

**Note:** The Simulink Design Verifier report indicates that two coverage objectives in the Stateflow chart ShiftLogic are proven unsatisfiable. Since the ShiftLogic chart updates at every time step, the implicit event `tick` is never `false`. The analysis cannot satisfy condition or MCDC coverage for either instance of the temporal event `after(TWAIT, tick)`.

`after(TWAIT, tick)` is semantically equivalent to

```
Event == tick && temporalCount(tick) >= TWAIT
```

If you move `after(TWAIT, tick)` into the condition, as in


```
[after(TWAIT, tick) && speed < down_th]
```

the Simulink Design Verifier software determines that `tick` is always `true`, so it only tests the `temporalCount(tick) >= TWAIT` part of `after(TWAIT, tick)`. The analysis is able to find test objectives that satisfy Condition and MCDC coverage for `after(TWAIT, tick)`.

---

## Modified Condition and Decision Coverage in Simulink Design Verifier

There is a difference between the definition of modified condition and decision coverage (MCDC) for model coverage analysis in Simulink Verification and Validation and for test case generation analysis in Simulink Design Verifier. This difference can be seen in analysis results for logical expressions containing a mixture of AND and OR operators, as in the Stateflow transition shown below.



Given that A, B, and C are each separate inputs, there are five possible ways to evaluate the condition on the Stateflow transition, shown in the following table.


	A	B	C	(A && B)    C
1	F	x	F	F
2	F	x	T	T
3	T	F	F	F
4	T	F	T	T
5	T	T	x	T

Satisfying MCDC for a Boolean variable requires a pair of condition evaluations, showing that a change in that variable alone changes the evaluation of the entire expression. In this example, MCDC can be satisfied for C with either the pair 1, 2 or the pair 3, 4. In both of those cases, the value of the expression changed because the value of C changed, while all other variable values stayed the same.



Each pair has a different set of values for A and B which are held constant, but each pair contains one evaluation where C and out are true and one evaluation where C and out are false. To satisfy MCDC for C, Simulink Design Verifier test generation analysis accepts any pair containing one evaluation of true values and one evaluation of false values for C and out; in this example, it accepts not only pair 1, 2 and pair 3, 4 but also pair 1, 4 and pair 2, 3. Simulink Verification and Validation model coverage analysis uses a strict form of MCDC that is only satisfied by pair 1, 2 or by pair 3, 4.

The above example assumes that A, B, and C are all separate inputs. When input A is constrained to be the same value as C, as in the model below, only a subset of condition evaluations are possible.



This subset of condition evaluations for the Stateflow transition is shown in the following table.

	A	B	C	(A && B)    C
1	F	x	F	F
4	T	F	T	T
5	T	T	x	T

Evaluations 2 and 3 are no longer possible, so neither pair 1, 2 nor pair 3, 4 is possible. As a result, MCDC for C can no longer be satisfied in Simulink Verification and Validation model coverage analysis. Since pair 1, 4 is still possible, however, Simulink Design Verifier test generation analysis reports that MCDC for C is satisfiable.

The complexity of MCDC analysis for logical expressions with a mixture of AND and OR operators causes this difference between results from Simulink Verification and

Validation and Simulink Design Verifier. Using the `IndividualObjectives` strategy for test generation analysis in Simulink Design Verifier can minimize this effect.

### **More About**

- “MCDC”

# Verifying Model Components

---

- “What Is Component Verification?” on page 10-2
- “Functions for Component Verification” on page 10-4
- “Verify a Component for Code Generation” on page 10-6

## What Is Component Verification?

<b>In this section...</b>
“Component Verification Approaches” on page 10-2
“Simulink Design Verifier Tools for Component Verification” on page 10-2

### Component Verification Approaches

Component verification lets you test a design component in your model using either of the following approaches:

- **Within the context of the model that contains the component** — Using systematic simulation of closed-loop controllers requires that you verify components within a control system model. Doing so lets you test the control algorithms with your model. This approach is called *system analysis*.
- **As standalone components** — For a high level of confidence in the component algorithm, verify the component in isolation from the rest of the system. This approach is called *component analysis*.

Verifying standalone components provides three advantages:

- You can use analysis to focus on portions of the design that you cannot test because of the physical limitations of the system being controlled.
- You can use this approach for open-loop simulations to test the plant model without feedback control.
- You can use this approach when the model is unavailable or when you need to simulate a control system model in accelerated mode for performance reasons.

### Simulink Design Verifier Tools for Component Verification

By isolating the component to verify, and using tools that the Simulink Design Verifier software provides, you create test cases that let you expand the scope of the testing for large models. This expanded testing helps you accomplish the following:

- **Achieve 100% model coverage** — If certain model components do not record 100% coverage, the top-level model cannot achieve 100% coverage. By verifying these components individually, you can create test cases that fully specify the component interface, allowing the component to record 100% coverage.

- Debug the component — To verify that each model component satisfies the specified design requirements, you can create test cases that verify that specific components perform as designed.
- Test the robustness of the component — To verify that a component handles unexpected inputs and calculations properly, you can create test cases that generate data. Then, test the error-handling capabilities in the component.

## Functions for Component Verification

The Simulink Design Verifier software provides several functions that facilitate the tasks associated with component verification.

Function	Task
<code>sldvlogsignals</code>	Simulate a Simulink model and log input signals to a Model block in the model. If you modify the test cases in the Signal Builder harness model, use this approach for logging input signals to the harness model itself.
<code>sldvmakeharness</code>	Create a harness model for a component, using logged input signals if specified, or using the default signals.  For more information about harness models, see “Simulink Design Verifier Harness Models”.
<code>sldvmergeharness</code>	Merge test cases from several harness models into a single harness model.
<code>sldvextract</code>	Extract an atomic subsystem or atomic subchart into a new model.
<code>sldvruntest</code>	Simulate a model, executing the specified test cases to record model coverage and output values.
<code>sldvruncgvtest</code>	Invoke the Code Generation Verification (CGV) API, and execute the specified test cases on the generated code for the model.  <b>Note:</b> To execute a model in different modes of execution, use the CGV API to verify the numerical equivalence of results. For more information about the CGV API, see “Programmatic Code Generation Verification”.

Component verification functions do not support the following Simulink features:

- Variable-step solvers for `sldvruntest`
- Component interfaces that contain:
  - Complex signals
  - Variable-size signals

- Array of buses
- Multiword fixed-point data types

## Verify a Component for Code Generation

### In this section...

“About the Example Model” on page 10-6

“Prepare the Component for Verification” on page 10-8

“Record Coverage for the Component” on page 10-9

“Use Simulink Design Verifier Software to Record Additional Coverage” on page 10-10

“Combine the Harness Models” on page 10-12

“Execute the Component in Simulation Mode” on page 10-13

“Execute the Component in Software-in-the-Loop (SIL) Mode” on page 10-13

### About the Example Model

This example uses the `slvndemo_powerwindow` model to show how to verify a component in the context of the model that contains that component. As you work through this example, you use the Simulink Design Verifier component verification functions to create test cases and measure coverage for a referenced model. In addition, you can execute the referenced model in both simulation mode and Software-in-the-Loop (SIL) mode using the Code Generation Verification (CGV) API.


---

**Note:** You must have the following product licenses to run this example:

- Stateflow
  - Embedded Coder<sup>®</sup>
  - Simulink Coder<sup>™</sup>
- 


The component that you verify is a Model block named `control`. This component resides inside the `power_window_control_system` subsystem in the top level of the `slvndemo_powerwindow` model. The `power_window_control_system` subsystem is shown below.






The control Model block references the slvndemo\_powerwindow\_controller model.

### Simulink Verification and Validation Power Window Controller



The referenced model contains a Stateflow chart control, which implements the logic for the power window controller.



## Prepare the Component for Verification

To verify the referenced model `slvndemo_powerwindow_controller`, create a harness model that contains the input signals that simulate the controller in the plant model:

- 1 Open the `slvndemo_powerwindow` example model and the referenced model:

```
open_system('slvndemo_powerwindow');
open_system('slvndemo_powerwindow_controller');
```

- 2 Open the `power_window_control_system` subsystem in the example model.

The Model block named `control` in the `power_window_control_system` subsystem references the component that you verify during this example, `slvndemo_powerwindow_controller`.

- 3 Simulate the Model block that references the `slvndemo_powerwindow_controller` model and log the input signals to the Model block:

```
loggedSignalsPlant = sldvlogsignals( ...
```

```
'slvndemo_powerwindow/power_window_control_system/control');
```

`sldvlogsignals` stores the logged signals in `loggedSignalsPlant`.

- 4 Generate a harness model with the logged signals:

```
harnessModelFilePath = sldvmakeharness( ...
    'slvndemo_powerwindow_controller', loggedSignalsPlant);
```

`sldvmakeharness` creates and opens a harness model named `slvndemo_powerwindow_controller_harness`. The Signal Builder block contains one test case containing the logged signals.

For more information about harness models, see “Simulink Design Verifier Harness Models”.

- 5 For use later in this example, save the name of the harness model:

```
[~, harnessModel] = fileparts(harnessModelFilePath);
```

- 6 Leave all windows open for the next part of this example.

Next, you will record coverage for the `slvndemo_powerwindow_controller` model.

## Record Coverage for the Component

Model coverage is a measure of how thoroughly a test case tests a model, and the percentage of pathways that a test case exercises. To record coverage for the `slvndemo_powerwindow_controller` model:

- 1 Create a default options object, required by the `sldvruntime` function:

```
runOpts = sldvruntimeopts;
```

- 2 Specify to simulate the model, and record coverage:

```
runOpts.coverageEnabled = true;
```

- 3 Simulate the referenced model and record coverage:

```
[~, covDataFromLoggedSignals] = sldvruntime( ...
    'slvndemo_powerwindow_controller', loggedSignalsPlant, runOpts);
```

- 4 Display the HTML coverage report:

```
cvhtml('Coverage with Test Cases', covDataFromLoggedSignals);
```

The `slvndemo_powerwindow_controller` model achieved:

- Decision coverage: 40%
- Condition coverage: 35%
- MCDC coverage: 10%

For more information about decision coverage, condition coverage, and MCDC coverage, see “Types of Model Coverage” in the Simulink Verification and Validation documentation.

Because you did not achieve 100% coverage for the `slvndemo_powerwindow_controller` model, next, you will analyze the model to record additional coverage and create additional test cases.

## Use Simulink Design Verifier Software to Record Additional Coverage

You can use the Simulink Design Verifier software to analyze the `slvndemo_powerwindow_controller` model and collect coverage. You can specify that the analysis ignore any previously satisfied objectives and record additional coverage.

To record additional coverage for the model:

- 1 Save the coverage data that you recorded for the logged signals in a file:  

```
cvsave('existingCovFromLoggedSignal', covDataFromLoggedSignals);
```
- 2 Create a default options object for the analysis:  

```
opts = sldvoptions;
```
- 3 Specify that the analysis generate test cases to record decision, condition, and modified condition/decision coverage:  

```
opts.ModelCoverageObjectives = 'MCDC';
```
- 4 Specify that the analysis ignore objectives that you satisfied when you logged the signals to the Model block:  

```
opts.IgnoreCovSatisfied = 'on';
```
- 5 Specify the name of the file that contains the satisfied objectives data:  

```
opts.CoverageDataFile = 'existingCovFromLoggedSignal.cvt';
```

- 6** Specify that the analysis not display unsatisfiable objectives in the Diagnostic Viewer:

```
opts.DisplayUnsatisfiableObjectives = 'off';
```

For this example, the focus is on satisfying as many objectives as possible.

- 7** Specify that the analysis create long test cases that satisfy several objectives:

```
opts.TestSuiteOptimization = 'LongTestcases';
```

Creating a smaller number of test cases each of which satisfies multiple test objectives saves time when you execute the generated code in the next section.

- 8** Specify to create a harness model that references the component using a Model block:

```
opts.saveHarnessModel = 'on';
opts.ModelReferenceHarness = 'on';
```

The harness model that you created from the logged signals in “Prepare the Component for Verification” on page 10-8 uses a Model block that references the `slvndemo_powerwindow_controller` model. The harness model that the analysis creates must also use a Model block that references `slvndemo_powerwindow_controller`. You can append the test case data to the first harness model, creating a single test suite.

- 9** Analyze the model using the Simulink Design Verifier software:

```
[status, fileNames] = sldvrun('slvndemo_powerwindow_controller', ...
    opts, true);
```

The analysis creates and opens a harness model `slvndemo_powerwindow_controller_harness`. The Signal Builder block contains one long test case that satisfies 74 test objectives.

You can combine this test case with the test case that you created in “Prepare the Component for Verification” on page 10-8, to record additional coverage for the `slvndemo_powerwindow_controller` model.

- 10** Save the name of the new harness model and open it:

```
[~, newHarnessModel] = fileparts(fileNames.HarnessModel);
open_system(newHarnessModel);
```

Next, you will combine the two harness models to create a single test suite.

## Combine the Harness Models

You created two harness models when you:

- Logged the signals to the control Model block that references the `slvndemo_powerwindow_controller` model.
- Analyzed the `slvndemo_powerwindow_controller` model.

If you combine the test cases in both harness models, you can record coverage that gets you closer to achieving 100% coverage:

- 1 Combine the harness models by appending the most recent test cases to the test cases for the logged signals:

```
sldvmergeharness(harnessModel, newHarnessModel);
```

The Signal Builder block in the `slvndemo_powerwindow_controller_harness` model now contains both test cases.

- 2 Log the signals to the harness model:

```
loggedSignalsMergedHarness = sldvlogsignals(harnessModel);
```

- 3 Use the combined test cases to record coverage for the `slvndemo_powerwindow_controller_harness` model. First, configure the options object for `sldvruntest`:

```
runOpts = sldvruntestopts;  
runOpts.coverageEnabled = true;
```

- 4 Simulate the model and record and display the coverage data:

```
[~, covDataFromMergedSignals] = sldvruntest( ...  
    'slvndemo_powerwindow_controller', loggedSignalsMergedHarness, ...  
    runOpts);  
cvhtml('Coverage with Merged Test Cases', covDataFromMergedSignals);
```

The `slvndemo_powerwindow_controller` model now achieves:

- Decision coverage: 100%
- Condition coverage: 80%
- MCDC coverage: 60%

## Execute the Component in Simulation Mode

To verify that the generated code for the model produces the same results as simulating the model, use the Code Generation Verification (CGV) API methods.

---

**Note:** To execute a model in different modes of execution, use the CGV API to verify the numerical equivalence of results. For more information about the CGV API, see “Programmatic Code Generation Verification” in the Embedded Coder documentation.

---

When you perform this procedure, the simulation compiles and executes the model code using both test cases.

- 1 Create a default options object for `sldvruncgvtest`:

```
runcgvopts = sldvruntestopts('cgv');
```

- 2 Specify to execute the model in simulation mode:

```
runcgvopts.cgvConn = 'sim';
```

- 3 Execute the `slvndemo_powerwindow_controller` model using the two test cases and the `runcgvopts` object:

```
cgvSim = sldvruncgvtest('slvndemo_powerwindow_controller', ...  
    loggedSignalsMergedHarness, runcgvopts);
```

These steps save the results in the workspace variable `cgvSim`.

Next, you will execute the same model with the same test cases in Software-in-the-Loop (SIL) mode and compare the results from both simulations.

For more information about Normal simulation mode, see “Execute the Model” in the Embedded Coder documentation.

## Execute the Component in Software-in-the-Loop (SIL) Mode

When you execute a model in Software-in-the-Loop (SIL) mode, the simulation compiles and executes the generated code on your host computer.

In this section, you execute the `slvndemo_powerwindow_controller` model in SIL mode and compare the results to the previous section, when you executed the model in simulation mode.

- 1 Specify to execute the model in SIL mode:

```
runcgvopts.cgvConn = 'sil';
```

- 2 Execute the `slvrv_powerwindow_controller` model using the two test cases and the `runcgvopts` object:

```
cgvSil = sldvruncgvtest('slvrvdemo_powerwindow_controller', ...  
    loggedSignalsMergedHarness, runcgvopts);
```

The workspace variable `cgvSil` contains the results of the SIL mode execution.

- 3 Compare the results in `cgvSil` to the results in `cgvSim`, created from the simulation mode execution. Use the “compare (`cgv.CGV`)” method to compare the results from the two simulations:

```
for i=1:length(loggedSignalsMergedHarness.TestCases)  
    simout = cgvSim.getOutputData(i);  
    silout = cgvSil.getOutputData(i);  
    [matchNames, ~, mismatchNames, ~] = ...  
    cgv.CGV.compare(simout, silout);  
end
```

- 4 Display the results of the comparison in the MATLAB Command Window:

```
fprintf(['\nTest Case(%d):%d Signals match, %d Signals mismatch\r'], ...  
    i, length(matchNames), length(mismatchNames));
```

As expected, the results of the two simulations match.

For more information about Software-in-the-Loop (SIL) simulations, see “What are SIL and PIL Simulations?” in the Embedded Coder documentation.



# Considering Specified Minimum and Maximum Values for Inputs During Analysis

---

- “Minimum and Maximum Input Constraints” on page 11-2
- “Specify Input Range for Inport Blocks” on page 11-4
- “Specified Input Ranges in sldvData Fields” on page 11-5
- “Specify Input Range for Simulink.Signal Objects” on page 11-6
- “Specify Input Range for Stateflow Data Objects” on page 11-7
- “Specify Input Range for Subsystems” on page 11-9
- “Specify Input Range for Global Data Stores” on page 11-11

## Minimum and Maximum Input Constraints

### In this section...

“Simulink Design Verifier Support for Specified Input Minimum and Maximum Values” on page 11-2

“Limitations of Simulink Design Verifier Support for Specified Minimum and Maximum Values” on page 11-3

When creating a model, you can specify minimum and maximum values on input ports to mimic environmental constraints as part of your design. The Simulink Design Verifier analysis can automatically consider these values as constraints for:

- Design error detection
- Test case generation
- Property proving

Specifying minimum and maximum input values is similar to the way you use the Test Condition block or the `sldv.condition` function to constrain signals during test case generation or the Proof Assumption block or the `sldv.assume` function to constrain signals during property proving. The Test Condition and Proof Assumption blocks capture the analysis constraints. The Simulink Design Verifier software can also consider the design constraints captured in the Inport block minimum and maximum parameters as constraints for analysis.

---

**Note:** For more information about signal values, see “Signal Values” in the Simulink documentation.

---

### Simulink Design Verifier Support for Specified Input Minimum and Maximum Values

By default, the Simulink Design Verifier software considers any minimum and maximum input values specified for Inport blocks in your model. To enable this capability:

- 1 In the model window, select **Analysis > Design Verifier > Options**.
- 2 On the **Design Verifier** pane, select the **Use specified input minimum and maximum values** parameter.

- 3 After the analysis completes, to view the design minimum and maximum constraints for your model, click **Generate detailed analysis reports**.

The constraints are listed in the **Analysis Information** chapter of the Simulink Design Verifier report.

## **Limitations of Simulink Design Verifier Support for Specified Minimum and Maximum Values**

Simulink Design Verifier support for specified minimum and maximum values has the following limitations:

- The analysis considers specified minimum and maximum values on root-level Inport blocks only. The analysis ignores any minimum and maximum values specified on other Simulink blocks.
- The analysis does not consider specified minimum and maximum values on bus objects. The analysis ignores any minimum and maximum values specified on Simulink bus objects.


## Specify Input Range for Inport Blocks

You can specify the output minimum and maximum values on Inport blocks in the Block Parameter dialog box, on the **Signal Attributes** tab. Set the following parameters:

- **Minimum**
- **Maximum**

The following example model restricts the signals from two Inport blocks:

- Input1 block: Minimum: 1, Maximum: 5
- Input2 block: Minimum: -1, Maximum: 1



When you analyze this model using the Simulink Design Verifier software, the analysis uses the minimum and maximum values as constraints. The analysis produces the following results:

- The output from Input1 is never less than 0, so the first input to the Logical Operator block is never **false**. The objective that the first input to the Logical Operator equals **false** is therefore unsatisfiable.
- The Logical Operator block cannot achieve 100% MCDC coverage because the condition where the first input is **false** never occurs.

The detailed analysis report indicates the values it used as constraints for Input1 and Input2.

## Specified Input Ranges in sldvData Fields

When you analyze a model, the Simulink Design Verifier software generates a data file when it completes its analysis. The data file is a MAT-file that contains an `sldvData` structure. The `sldvData` structure stores all the data that the software gathers and produces during the analysis. You can use the data file to customize your own analysis or to generate a custom report.

If your model contains specified minimum and maximum values on the input ports, the `sldvData` structure contains information about those values. For example, after analyzing the `ex_minmax_on_inports` model in “Specify Input Range for Inport Blocks” on page 11-4, the data file contains the following values:

- For the Input1 block:

```
sldvData.Constraints.DesignMinMax(1).value{1}.low
```

```
ans =
```

```
1
```

```
sldvData.Constraints.DesignMinMax(1).value{1}.high
```

```
ans =
```

```
5
```

- For the Input2 block:

```
sldvData.Constraints.DesignMinMax(2).value{1}.low
```

```
ans =
```

```
-1
```

```
sldvData.Constraints.DesignMinMax(2).value{1}.high
```

```
ans =
```


```
1
```

## Specify Input Range for Simulink.Signal Objects

Using the Model Explorer, in the model workspace, you can specify minimum and maximum values on `Simulink.Signal` objects associated with input signals.

The following example model uses the `Simulink.Signal` objects associated with the input signals `a` and `b` to restrict the signal values:

- Signal `a`: Minimum: 1, Maximum: 5
- Signal `b`: Minimum: -1, Maximum: 1



When you analyze this model, the results are the same as if you specified the minimum and maximum values on the input ports.

---



**Specifying Signal Ranges on Inport Blocks and Signals** If you specify ranges on the Inport blocks *and* on the signals, the analysis considers the tightest range. For example, if you specify a range of 4..12 on an input port and a range of 1..8 on the signal from the input port, the analysis considers the range 4..8.

---

## Specify Input Range for Stateflow Data Objects

Using the Model Explorer, you can specify ranges on data objects that are directly connected to the root-level input ports for a Stateflow chart.

In the following example model, the Stateflow chart named Chart has a data object  $x$  whose range you specified as  $0 < x < 10$ . In this chart,  $x$  must be greater than 15 to trigger the transition from **low** to **high**.



The value of  $x$  must fall between 0 and 10, so the transition condition  $[x > 15]$  is never true. The transition from **low** to **high** never occurs. Because the **high** state is never entered, the transition condition  $[x < 15]$  is never tested, and the transition from **high** to **low** never occurs; the chart is always in the **low** state.

When you analyze this model, the following objectives are proven unsatisfiable:

- The **high** state is never entered.
- The transition condition  $[x > 15]$  is always **false**, never **true**.
- The condition  $[x < 15]$  is never tested, so it is never **true** or **false**.

The analysis report indicates the values it used as constraints for  $x$ :  $[0, 10]$ .




## Specify Input Range for Subsystems


The Simulink Design Verifier software considers specified input minimum and maximum values as constraints only at the top level of a model. You can specify minimum and maximum values on Input ports on subsystems, but when you analyze the top-level model, the software ignores those values.

However, when you perform the subsystem analysis, the software considers specified minimum and maximum values on the input ports of the subsystem.

For example, consider the following model, and its subsystem.



In Subsystem, the specified minimum and maximum values for input port SSIn are  $-10$  and  $10$ , respectively. The lower and upper limits for the Saturation block are  $-15$  and  $15$ , respectively.



If you right-click Subsystem in the top-level model and select **Generate Tests for Subsystem**, the analysis considers the specified minimum and maximum values as constraints on the SSIn port.

## Constraints

### Design Min Max Constraints

Name	Design Min Max Constraint
<a href="#">SSIn</a>	[-10, 10]

The analysis identifies two unsatisfiable objectives:

- $\text{input} > \text{lower limit F}$ : The input is always greater than the lower limit on the Saturation block (-15).
- $\text{input} \geq \text{upper limit T}$ : The input is never greater than or equal to the upper limit (15).

If you analyze the model that contains Subsystem, the analysis does not consider the values specified on the input port SSIn in the subsystem. The analysis considers only the root-level input ports at the respective level of the hierarchy for analysis.

## Specify Input Range for Global Data Stores


A *data store* is a repository to which you can write data and from which you can read data, without having to connect an input or output signal directly to the data store. You create a data store using a Data Store Memory block or a `Simulink.Signal` object. You can specify minimum and maximum values for any data store.

As described in “Extract Subsystems for Analysis” on page 14-16, during subsystem analysis, the Simulink Design Verifier software creates a new input port to mimic the execution context for a global data store. If the data store has specified minimum and maximum values, those values are assigned as minimum and maximum values on the new input port. The input minimum and maximum values are used as subsystem-level analysis constraints.

In the following example model, data store A has a minimum value of 0 and a maximum value of 10.



The atomic subsystem reads from the data store and checks to see if the input is less than 0. The Compare To Zero block outputs 1 if the input is less than 0, and outputs 0 if the input is greater than or equal to 0. The Test Objective block checks to see if the output is ever 1.



If you right-click Subsystem in the top-level model and select **Generate Tests for Subsystem**, the analysis considers the constraints for data store A to be [0, 10].

The analysis does not satisfy the objective specified in the Test Objective block. The input is always greater than or equal to 0, so the output from the Compare To Zero block is always 0.



# Proving Properties of a Model

---

- “What Is Property Proving?” on page 12-2
- “Workflow for Proving Model Properties” on page 12-4
- “Prove Properties in a Model” on page 12-5
- “Prove System-Level Properties Using Verification Model” on page 12-25
- “Prove Properties in a Subsystem” on page 12-29
- “Model Requirements” on page 12-30

## What Is Property Proving?

A *property* is a requirement that you model in Simulink or Stateflow, or using MATLAB Function blocks. A property can be a simple requirement, such as a signal in your model that must attain a particular value or range of values during simulation.

A property can also be a requirement on the model that involves a number of input and output signals modeled as a logical expression that needs to be proved.

The Simulink Design Verifier software performs a formal analysis of your model to prove or disprove the specified properties. After completing the analysis, the software offers several ways for you to review the results:

- Highlighted on the model
- A harness model with test cases
- A detailed HTML report

### Proof Blocks

The Simulink Design Verifier software provides two blocks so you can specify property proofs in your Simulink models:

- Proof Objective — Define the values of a signal to prove
- Proof Assumption — Constrain the values of a signal during a proof

---

**Note:** Blocks from the Model Verification library in the Simulink software behave like Proof Objective blocks during Simulink Design Verifier proofs. You can use Assertion blocks and other Model Verification blocks to specify properties of your model. For more information about these blocks, see “Model Verification” in the Simulink documentation.

---

### Proof Functions

The Simulink Design Verifier software provides two Stateflow and MATLAB for code generation functions to specify property proving for a Simulink model or Stateflow chart:

- `sldv.prove` — Specifies a proof objective
- `sldv.assume` — Specifies a proof assumption

These functions:

- Identify mathematical relationships for proving properties in a form that can be more natural than using block parameters
- Support specifying multiple objectives, assumptions, or conditions without complicating the model.
- Provide access to the power of MATLAB.
- Support separation of verification and model design.

For an example of how to use these proof functions, see the `sldv.prove` reference page.

---

**Note:** Simulink Design Verifier blocks and functions are saved with a model. If you open the model on a MATLAB installation that does not have a Simulink Design Verifier license, you can see the blocks and functions, but they do not produce results.

---

### Workflow for Proving Model Properties

To prove properties of your design model, use the following workflow:

- 1 Determine the verification objectives for your design model, e.g., based on your requirements specifications.
- 2 Instrument your design model to specify proof objectives and proof assumptions.
  - For simple properties, instrument your model with blocks or MATLAB functions that specify the proof objectives.
  - For system-level properties, construct a verification model that contains a Model block that references the design model and define the properties on the design model interface using the same inputs and outputs.
- 3 Define analysis constraints using the Proof Assumption block or `sldv.assume`. These constraints apply to all enabled proof objectives.

---

**Note:** The proof assumptions are applied to all enabled proof objectives. Make sure that you do not specify any contradictory assumptions because that might invalidate the entire analysis.

---

- 4 Specify options that control how Simulink Design Verifier proves the properties of your model.
- 5 Execute the Simulink Design Verifier analysis and review the results.

For an exercise that demonstrates this workflow, see “Prove Properties in a Model” on page 12-5.



## Prove Properties in a Model

### In this section...

- “About This Example” on page 12-5
- “Construct Example Model” on page 12-6
- “Check Compatibility of Example Model” on page 12-7
- “Instrument Example Model” on page 12-8
- “Configure Property-Proving Options” on page 12-9
- “Analyze Example Model” on page 12-10
- “Review Analysis Results” on page 12-10
- “Customize Example Proof” on page 12-19
- “Reanalyze Example Model” on page 12-20
- “Review Results of Second Analysis” on page 12-20
- “Analyze Contradictory Models” on page 12-23
- “Prove Properties in a Large Model” on page 12-24

### About This Example

The following sections describe a Simulink model, for which you prove a property that you specify using a Proof Objective block. This example demonstrates the property-proving capabilities of the Simulink Design Verifier software.

In this example, you perform the following tasks.


Task	Description	See...
1	Construct the example model.	“Construct Example Model” on page 12-6
2	Verify that your model is compatible with the Simulink Design Verifier software.	“Check Compatibility of Example Model” on page 12-7
3	Add a Proof Objective block to your model to prepare for its proof.	“Instrument Example Model” on page 12-8

Task	Description	See...
4	Configure the Simulink Design Verifier software to prove properties.	“Configure Property-Proving Options” on page 12-9
5	Prove a property of your model.	“Analyze Example Model” on page 12-10
6	Review the analysis results.	“Review Analysis Results” on page 12-10
7	Add proof assumptions to specify analysis constraints.	“Customize Example Proof” on page 12-19
8	Prove a property of the customized model and interpret the results.	“Reanalyze Example Model” on page 12-20

## Construct Example Model

Construct a Simulink model to use in this example:

- 1 Create an empty Simulink model.
- 2 Copy the following blocks into your empty model window:
  - From the Sources library, an Inport block to initiate the input signal whose value the Simulink Design Verifier software controls
  - From the Logic and Bit Operations library, a Compare To Zero block to provide simple logic
  - From the Sinks library, an Outport block to receive the output signal
- 3 Connect these blocks such so your model appears similar to the following model:



- 4 In the model window, select **Simulation > Model Configuration Parameters**.
- 5 On the left side of the Configuration Parameters dialog box, in the **Select** tree, click the **Solver** category. On the right side, under **Solver options**:
  - Set the **Type** option to **Fixed-step**.

- Set the **Solver** option to **Discrete** (no continuous states).

The Simulink Design Verifier can analyze only models that use a fixed-step solver.

- 6 Click **OK** to save your changes and close the Configuration Parameters dialog box.
- 7 Save your model with the name `ex_property_proving_example_basic`.

## Check Compatibility of Example Model


Every time Simulink Design Verifier software analyzes a model, before the analysis begins, the software performs a compatibility check. If your model is not compatible, the software cannot analyze it.

You can also make sure your model is compatible with the Simulink Design Verifier software before you start the analysis:

- 1 Open the `ex_property_proving_example_basic` model.
- 2 In the model window, select **Analysis > Design Verifier > Check Compatibility > Model**.

The Simulink Design Verifier software displays the log window, which states whether or not your model is compatible.

The model you just created is compatible.



### What If a Model Is Partially Compatible?

If the compatibility check indicates that your model is partially compatible, your model contains at least one object that the Simulink Design Verifier software does not support. You can analyze a partially compatible model, but, by default, unsupported objects are stubbed out. The results of the analysis may be incomplete. For detailed information about automatic stubbing, see “Handle Incompatibilities with Automatic Stubbing”.

### Instrument Example Model

Prepare your example model so that you can prove its properties with the Simulink Design Verifier software. Specifically, instrument the model by adding and configuring a Proof Objective block:

- 1 In the MATLAB Command Window, enter `sldvlib`.

The Simulink Design Verifier library appears.


- 2 Open the Objectives and Constraints sublibrary.
- 3 Copy the Proof Objective block to your model and insert it between the Compare To Zero and Output blocks.
- 4 In your model, double-click the Proof Objective block.

The Proof Objective block parameters dialog box opens.

- 5 In the **Values** box, enter 1.

The Simulink Design Verifier software will attempt to prove that the signal output by the Compare To Zero block always attains this value for any signals that it receives.

- 6 Click **OK** to apply your changes and close the Proof Objective block parameters dialog box.



- 7 Save your model and keep it open.

## Configure Property-Proving Options

Configure the Simulink Design Verifier software to prove properties of the `ex_property_proving_example_basic` model that you instrumented:

- 1 Open the `ex_property_proving_example_basic` model.
- 2 In your Simulink model window, select **Analysis > Design Verifier > Options**.
- 3 On the left side of the Configuration Parameters dialog box, in the **Select** tree, select the **Design Verifier** category. Under **Analysis options** on the right side, set the **Mode** parameter to **Property proving**.
- 4 Click **OK** to apply your changes and close the Configuration Parameters dialog box.

---

**Note:** On the **Property Proving** pane, you can optionally specify values for other parameters that control how the Simulink Design Verifier software proves properties of your model. For more information, see “Design Verifier Pane: Property Proving” on page 15-51.

---

- 5 Save the `ex_property_proving_example_basic` model.

### Analyze Example Model

To analyze the `ex_property_proving_example_basic` model, in the model window, select **Analysis > Design Verifier > Prove Properties > Model**. The Simulink Design Verifier software begins a property-proving analysis.

During the analysis, the log window shows the progress of the analysis. It displays information such as the number of objectives processed and which objectives were satisfied or falsified.

To terminate the analysis at any time, in the log window, click **Stop**.

### Review Analysis Results

When the analysis is complete, the log window displays the following options for reviewing the results:

- Highlight the analysis results on the model
- Generate a detailed HTML analysis report
- Create a harness model with test cases
- Simulate the test cases created by the model and produce a model coverage report

You can also view the Simulink Design Verifier data file. For detailed information about the data file, see “Simulink Design Verifier Data Files” on page 13-9.

The following sections describe how you can review the analysis results:

- “Review Results on Model” on page 12-11
- “Review Detailed Analysis Report” on page 12-13
- “Review Harness Model” on page 12-15
- “Simulate Model with Counterexample” on page 12-16
- “Review Analysis Results in the Model Explorer” on page 12-18


## Review Results on Model

You can review the analysis results at a glance by viewing the blocks that are highlighted in the model window. The highlighting can have four colors:

- Green — The analysis proved all the proof objectives valid.
- Red — The analysis disproved a proof objective and generated a counterexample that falsified that objective.
- Orange — The analysis disproved a proof objective, but it could not generate a counterexample or the proof objective remained undecided. This result occurs due to:
  - A proof objective on a signal whose value the software cannot control, for example, a Constant block
  - A proof objective that depends on nonlinear computation
  - A proof objective that creates an arithmetic error, such as division by zero
  - Automatic stubbing being enabled, and the analysis encountering an unsupported block whose operation it does not understand but that the analysis requires to generate the counterexample
  - The analysis timing out
  - Limitations of the analysis engine
- Gray — The model object was not part of the analysis.


Highlight the analysis results on the example model:

- 1 In the log window for the `ex_property_proving_example_basic` analysis, click **Highlight analysis results on model**.



The Proof Objective block is highlighted in red, which indicates that a proof objective was falsified with a counterexample.


The Simulink Design Verifier Results window appears.



As you click objects in the model, this window changes to display detailed analysis results for that object.



---

**Tip** By default, the Simulink Design Verifier Results window is always the topmost visible window. To allow the window to move behind other window, click  and clear Always on top.

---

- 2 Click the highlighted Proof Objective block.



The Simulink Design Verifier Results window indicates that the proof objective that the output signal from the Compare to Zero was not 1 was disproved with a counterexample.

### Review Detailed Analysis Report

To create a detailed HTML analysis report:

- 1 In the Simulink Design Verifier log window, click **Generate detailed analysis report**.

The HTML report opens in a browser window.

- 2 The report includes the following **Table of Contents**. Click a hyperlink to navigate to particular section in the report.

Table of Contents	
1.	<a href="#">Summary</a>
2.	<a href="#">Analysis Information</a>
3.	<a href="#">Proof Objectives Status</a>
4.	<a href="#">Properties</a>

- 3 In the **Table of Contents**, click Summary.

Chapter 1. Summary	
<b>Analysis Information</b>	
Model:	ex_property_proving_example
Mode:	PropertyProving
Status:	Completed normally
Analysis Time:	0s
<b>Objectives Status</b>	
<b>Number of Objectives:</b>	<b>1</b>
Objectives Falsified with Counterexamples:	1

The Summary provides an overview of the analysis results, and it indicates that the Simulink Design Verifier software identified a counterexample that falsifies an objective in your model.

- 4 Scroll back to the top of the browser window. In the **Table of Contents**, click **Proof Objectives Status**.

Objectives Falsified with Counterexamples				
#:	Type	Model Item	Description	Counterexample
1	Custom Proof Objective	<a href="#">Proof Objective</a>	Objective: 1	<a href="#">1</a>

The Objectives Falsified with Counterexamples table lists the proof objectives that the Simulink Design Verifier software disproved using a counterexample that it generated. You can locate the objective in your model window by clicking **Proof Objective**; the software highlights the corresponding Proof Objective block in your model window.

- 5 In the Objectives Falsified with Counterexamples table, under the **Counterexample** column, click **1**.

Proof Objective	
<b>Summary</b>	
Model Item:	<a href="#">Proof Objective</a>
Property:	Objective: 1
Status:	Falsified
<b>Counter Example</b>	
<b>Time 0</b>	
<b>Step 1</b>	
In1	1


This section displays information about proof objective 1 and provides details about the counterexample that the Simulink Design Verifier software generated to disprove that objective. In this counterexample, a signal value of 99 falsifies the objective that you specified using the Proof Objective block. That is, 99 is not less than or equal to 0, which causes the Compare To Zero block to return 0 (false) instead of 1 (true).

### Review Harness Model

Create a harness model with counterexamples that falsify the proof objectives in your model:


- 1 In the Simulink Design Verifier log window, click **Create harness model**.

The software creates a harness model named `ex_property_proving_example_basic_harness`.



The harness model contains the following items:

- Signal Builder block named **Inputs** — A group of signals that falsify proof objectives.
  - Subsystem block named **Test Unit** — A copy of your model.
  - DocBlock named **Test Case Explanation** — A textual description of the counterexamples that the analysis generates.
  - A **Size-Type** block — A subsystem that transmits signals from the **Inputs** block to the **Test Unit** block. This block verifies that the size and data type of the signals are consistent with the **Test Unit** block.
- 2 Double-click the **Inputs** block.




The input signal 1 causes the output of the Compare to Zero block to be 0. This counterexample violates the proof objective that specifies that the output of the Compare to Zero block be 1.


### Simulate Model with Counterexample

Simulate the harness model to observe the counterexample that falsifies the proof objective in your model:

- 1 In the `ex_property_proving_example_basic` model window, select **View > Library Browser**
- 2 From the Sinks library, copy a Scope block into your harness model window. The Scope block allows you to see the value of the signal output by the Compare To Zero block in your model.
- 3 In your harness model window, connect the output signal of the Test Unit subsystem to the Scope block.



- 4 In your harness model window, select **Simulation > Run** to begin the simulation.  
The Simulink software simulates the harness model.
- 5 In your harness model window, double-click the Scope block to open its display window.



The Scope block displays the value of the signal output by the Compare To Zero block in your model. In this example, the Compare To Zero block returns 0 (false) throughout the simulation, which falsifies the proof objective that the output of the Compare to Zero block be 1 (true). The counterexample that the Signal Builder block supplies falsifies the proof objective.

### Review Analysis Results in the Model Explorer

As long as your model remains open, you can view the results of your most recent Simulink Design Verifier analysis results in the Model Explorer.

In the Simulink Editor, select **Analysis > Design Verifier > Latest Results**. The Model Explorer opens, and the results of the latest Simulink Design Verifier analysis appear in the right-hand pane.

For any Simulink Design Verifier analysis, from the Model Explorer, you can perform the following tasks.

Task	For more information
Highlight the analysis results on the model.	“Highlighted Results on the Model” on page 13-2
Generate a detailed analysis report.	“Simulink Design Verifier Reports” on page 13-27
Create the harness model, or if the harness model already exists, open it.  If no counterexamples were created during the analysis, this option is not available.	“Simulink Design Verifier Harness Models” on page 13-16
View the data file.	“Simulink Design Verifier Data Files” on page 13-9
View the log file.	“Simulink Design Verifier Log Files” on page 13-50

After you close your model, you can no longer view the analysis results.

## Customize Example Proof

Modify the simple Simulink model whose proof objective the Simulink Design Verifier software disproved in the previous task. Specifically, customize the proof by adding and configuring a Proof Assumption block:

- 1 In the MATLAB Command Window, type `sldvlib`.

The Simulink Design Verifier library opens.


- 2 Open the Objectives and Constraints sublibrary.
- 3 Copy the Proof Assumption block to your model.
- 4 In your model window, insert the Proof Assumption block between the Inport and Compare To Zero blocks.
- 5 In your model, double-click the Proof Assumption block to access its attributes.

The Proof Assumption block parameter dialog box opens.

- 6 In the **Values** box, enter `[-1, 0]`. When proving properties of this model, the Simulink Design Verifier software constrains the signal values entering the Compare To Zero block to the specified range. If the input to the Compare to Zero

block is always within this range, the output of the Compare to Zero block will always be 1.

- Click **Apply** and then **OK** to apply your changes and close the Proof Assumption block parameter dialog box.



- Save the `ex_property_proving_example_basic` model and keep it open.

## Reanalyze Example Model

Analyze the model that you modified to see how the Proof Assumption block affects the property-proving analysis.

In the `ex_property_proving_example_basic` model window, select **Analysis > Design Verifier > Prove Properties > Model**.

When the analysis is complete, the log window displays the options. There is no option to create a harness model, because the analysis satisfied all proof objectives in your model, so there are no counterexamples.

## Review Results of Second Analysis

Review the results of the second analysis:

- “Review Results on the Model” on page 12-20
- “Review Analysis Report” on page 12-21


### Review Results on the Model

Highlight the model to see the analysis results:

- Click **Highlight analysis results on model**.


The Proof Objective is now highlighted in green.





- 2 Click the Proof Objective block.

The Simulink Design Verifier Results window shows that the proof objective that states that the signal be 1 is valid.



### Review Analysis Report

Review the analysis results in the detailed report:

- 1 Click **Generate detailed analysis report**.
- 2 In the **Table of Contents**, click **Summary**.

**Chapter 1. Summary**

**Analysis Information**

Model: ex\_property\_proving\_example\_basic  
 Mode: PropertyProving  
 Status: Completed normally  
 Analysis Time: 0s

**Objectives Status**

**Number of Objectives: 1**  
 Objectives Proven Valid: 1

The Summary chapter indicates that the Simulink Design Verifier software proved a proof objective in the model.

- 3 The Constraints section lists the analysis constraint you specified in the Proof Assumption block.

**Constraints**

**Analysis Constraints**

Name	Analysis Constraint
<a href="#">Assumption</a>	[-1, 0]

- 4 Scroll back to the top of the browser window. In the **Table of Contents**, click Proof Objectives Status.

Objectives Proven Valid				
#	Type	Model Item	Description	Counterexample
1	Proof objective	<a href="#">Proof Objective</a>	Objective: 1	n/a

The Objectives Proven Valid table lists the proof objectives that the Simulink Design Verifier software proved to be valid.

- 5 Scroll down to view the Properties chapter or go to the top of the browser window and in the **Table of Contents**, click **Properties**.

Proof Objective	
<b>Summary</b>	
Model Item:	<a href="#">Proof Objective</a>
Property:	Objective: 1
Status:	Proven valid

The Proof Objective summary indicates that the Simulink Design Verifier software proved an objective that you specified in your model. The Proof Assumption block restricts the domain of the input signals to the interval  $[-1, 0]$ . Therefore, the software proves that this interval does not contain values that are greater than zero, thereby satisfying the proof objective.

## Analyze Contradictory Models

If the analysis produces the error **The model is contradictory in its current configuration**, the software detected a contradiction in your model and it cannot analyze the model. You can have a contradiction if your model has Proof Assumption blocks with incorrect parameters. For example, an assumption could state that a signal must be between 0 and 5 when the signal is constant 10.

If the software detects a contradiction, all previous results are invalidated and the software reports that all the properties are falsified.

### **Prove Properties in a Large Model**

A thorough proof of your model requires that the Simulink Design Verifier software search through all reachable configurations of your model—even the ones that are reached only after long time delays. The computation time and memory required to search a model completely often make an exhaustive proof impractical.

“Prove Properties in Large Models” on page 14-27 gives detailed information about strategies you can use to improve the performance of a property-proving analysis of a large model.

# Prove System-Level Properties Using Verification Model

## In this section...

“When to Use a Verification Model for Property Proving” on page 12-25

“About this Example” on page 12-25

“Understand the Verification Model” on page 12-25

“Prove the Properties of the Design Model” on page 12-26

“Fix the Verification Model” on page 12-27

## When to Use a Verification Model for Property Proving

If your model has system-wide properties that affect the behavior of the model, you might want to prove the properties without changing the design model. To do this, you create a *verification model* that includes:

- Model block that references the design model
- One or more verification subsystems that define the properties and any required constraints

## About this Example

The design model `sldvdemo_sbr_design` models the logic for a seat belt reminder light. If the ignition is turned on, the seat belts are unfastened, and the car exceeds a certain speed, the seat belt reminder light turns on.

The `sldvdemo_sbr_verification` model is a verification model that defines some constraints and verifies the properties in the `sldvdemo_sbr_design` model. The Model block in the verification model references the design model, so that the verification logic exists only in the verification model.

The `sldvdemo_sbr_verification` model contains a property that is falsified, because a constraint is disabled. In the `sldvdemo_sbr_verification_fixed` model, the constraint is enabled and all the properties are proven valid.

## Understand the Verification Model

Take these steps to understand how the verification model works:

- 1 Open the verification model:

`sldvdemo_sbr_verification`

The Design Model block is a Model block that references `sldvdemo_sbr_design`. The SBR Stateflow chart in the design model assumes that the KEY input is initially 0.

- 2 Open the Safety Properties subsystem that specifies the properties of the design model that you want to prove.

This subsystem contains a MATLAB Function block called **MATLAB Property**. The code in this block specifies the property that the seat belt reminder should be on when the ignition is on, the seat belt is not fastened, and the speed is less than 15:

- 3 Close the Safety Properties subsystem.
- 4 Open the Input Constraints subsystem.

This subsystem defines the following constraints:

- The key can have three positions: 0, 1, 2
- The speed is constrained to fall between 10 and 30.
- The key must start at 0 and can only change by one increment at a time. For example, the key can change from 0 to 1 or 1 to 2, but not from 0 to 2. In this verification model, this constraint is not enabled.

- 5 Close the Input Constraints subsystem, but keep the `sldvdemo_sbr_verification` model open.

### Prove the Properties of the Design Model

Analyze the `sldvdemo_sbr_verification` model to prove the properties:

- 1 In the `sldvdemo_sbr_verification` model window, to start the analysis, double-click the **Run** button to start the analysis.


When the analysis completes, the Simulink Design Verifier log window indicates that one objective was falsified.

- 2 To see which objective was falsified, click **Highlight analysis results on model**.

The Safety Properties subsystem is highlighted in red.

- 3 Open the Safety Properties subsystem and click the MATLAB Property block.

The Simulink Design Verifier Results window indicates that the statement `sldv.prove(implies(activeCond,SeatBeltIcon))` was false during at least one time step.




- 4 Click **View counterexample** to see the signal values that violated this property.

The Signal Builder block opens with the counterexample. The KEY input was initially 2, which is invalid.

To validate the property specified in the Safety Properties subsystem, you have to make sure that the initial value of KEY is 0.

## Fix the Verification Model

The Input Constraints subsystem in the verification model contained three constraints. The third constraint, which requires that the initial value of KEY be 0, and that KEY can only change in increments of 1, is disabled.



To see how this property is validated when you enable the third constraint:

- 1 In the `sldvdemo_sbr_verification` model, click **Open Fixed Model**.

The `sldvdemo_sbr_verification_fixed` verification model opens.

- 2 Open the Input Constraints subsystem.

This third constraint is now enabled so that `KEY` has an initial value of 0 and changes in increments of 1.

- 3 Close the Input Constraints subsystem.
- 4 In the `sldvdemo_sbr_verification_fixed` model, to start the analysis, double-click the **Run** block.

The analysis proves the validity of the property.



## Prove Properties in a Subsystem

If you have a large model, you can prove the properties of a subsystem in the model and review the analyses in smaller, manageable reports. The workflow for proving properties in a subsystem is:

- 1 Open the model that contains the subsystem.
- 2 Make the subsystem atomic.
- 3 Run the Simulink Design Verifier software using the **Prove Properties of Subsystem** option.
- 4 Review the results.

The tutorial in “Analyze a Subsystem” explains how to generate test cases for the Controller subsystem in the Cruise Control Test Generation model. The steps for proving properties are similar to those for generating test cases, except that you select the **Prove Properties of Subsystem** option instead of the **Generate Tests for Subsystem** option.

## Model Requirements

The Simulink Design Verifier block library includes a sublibrary Example Properties. The Example Properties sublibrary includes:

- “Basic Properties” on page 12-30 — Four examples that demonstrate how to prove basic properties.
- “Temporal Properties” on page 12-34 — Four examples that demonstrate how to define temporal properties on Boolean signals

The workflow for using these examples in your model is:

- 1 Copy these examples into your Verification Subsystem block.
- 2 Adapt them, if required, for the specific properties that you want to prove.
- 3 Run the Simulink Design Verifier analysis to prove that the assertions in these examples never fail.
- 4 If the assertion fails, the software creates a counterexample that causes the assertion to fail and then generates a harness model.
- 5 On the harness model, execute the counterexample to confirm that the assertion fails with that counterexample.

### Basic Properties


To view the Basic Properties examples:

- 1 Open the Simulink Design Verifier block library. Type:  
`sldvlib`
- 2 Double-click the Examples sublibrary.
- 3 Double-click the **Basic Properties** block that contains the examples.

The sections that follow describe each example in the Block Properties sublibrary in detail.

#### Conditions that Trigger a Result

The Simulink Design Verifier Implies block allows you to test for conditions that trigger a result. This example specifies that if condition **A** is true, result **B** must always be true.





Implies operation describes conditions that should trigger a result.

### Increasing or Decreasing Signals

The two examples in this section specify that a signal is either:


- Always increasing or staying constant
- Always decreasing or staying constant



Increasing and decreasing operations describe signals that should increase or decrease.

### Exclusivity Operation


This example describes four conditions that should not be true at the same time.



Exclusivity operation describes conditions that should never be true at same time.

#### Conditions with One True Element

This example specifies that only one of the four input signals can be true.



Mutual exclusivity operation describes conditions that should have exactly one true element.

## Temporal Properties


To view the Temporal Properties examples:

- 1 Open the Simulink Design Verifier block library. Type:  
sldvlib
- 2 Double-click the Temporal Properties sublibrary.
- 3 Double-click the **Temporal Properties** block that contains the examples.

The sections that follow describe each example in the Temporal Properties sublibrary in detail.


### Synchronize the Output with the Input

When the input In1 equals ACTIVE, the input In2 is set to INACTIVE after five time steps.




### Make a Signal Inactive After a Delay

In this example, after five consecutive time steps where the SENSOR\_HIGH input is true, the CMD signal becomes true. CMD is true as long as SENSOR\_HIGH is true, unless the block is reset by the MANUAL\_RESET signal.




### Extend a True Signal

In this example, after the input becomes true, the output becomes true for the number of time steps specified in the Detector block, in this case, 5. The input remains true for 5 time steps as well.



### Test the Input Against a Specified Threshold

When the input In3 equals ON and the input In4 is less than the constant THRESHOLD, In3 is set to OFF within five time steps.





# Reviewing the Results

---

- “Highlighted Results on the Model” on page 13-2
- “Simulink Design Verifier Data Files” on page 13-9
- “Simulink Design Verifier Harness Models” on page 13-16
- “Export Test Cases to SystemTest” on page 13-24
- “Simulink Design Verifier Reports” on page 13-27
- “Simulink Design Verifier Log Files” on page 13-50
- “Review Analysis Results” on page 13-52

## Highlighted Results on the Model

In this section...
“Results Review with Model Highlighting” on page 13-2
“Simulink Design Verifier Results Inspector” on page 13-2
“Enable Highlighted Results on a Model” on page 13-3
“Green Highlighting on Model” on page 13-5
“Red Highlighting on Model” on page 13-6
“Orange Highlighting on Model” on page 13-6
“Gray Highlighting on Model” on page 13-8

### Results Review with Model Highlighting

When you analyze a model using the Simulink Design Verifier software, you can highlight the analyzed model objects in one of four colors:

- Green
- Red
- Orange
- Gray

Model highlighting allows you to review the analysis results at a glance by viewing the objects that are highlighted in the Simulink Editor.

### Simulink Design Verifier Results Inspector

When a model is highlighted, you can click an object for which the analysis recorded results. When you click the object, the Simulink Design Verifier Results Inspector displays the detailed analysis results for that object.

The Results Inspector does not display detailed results for Stateflow state transition tables, but analysis data for state transition tables is included in Simulink Design Verifier reports, data files, and log files.


## Enable Highlighted Results on a Model

For test case generation or property proving analysis, to enable results highlighting on the model after analysis is complete, do one of the following:

- Before the analysis, in the Configuration Parameters dialog box, on the **Design Verifier > Results** pane, select **Display the results of the analysis on the model**.
- After the analysis, in the Simulink Design Verifier log window, select **Highlight analysis results on model**.


For design error detection analysis, results highlighting on the model after analysis is complete is enabled by default.

For all analysis types, you can also highlight results on the model during analysis. To do this, in the Results Summary window, click **Highlight**.



In the Simulink Editor, results highlighting appears on the model. Model objects that the analysis has not yet processed display in orange.

The Results Inspector also opens, displaying the elapsed time of the analysis and a summary of status for analysis objectives.



## Green Highlighting on Model

Objects that are highlighted in green have the following meaning for each type of analysis.

Analysis mode	Green highlighting means...
Design error detection	One of the following: <ul style="list-style-type: none"> <li>• The analysis did not find overflow or division-by-zero errors.</li> <li>• The analysis did not find dead logic</li> <li>• The analysis did not find intermediate or output signals outside the range of user-specified minimum and maximum constraints.</li> <li>• The analysis did not find out of bound array access errors.</li> </ul>
Test generation	The analysis found test cases that satisfy the test objectives.
Property proving	The analysis proved all the proof objectives valid.

## Red Highlighting on Model

Objects that are highlighted in red have the following meaning, depending on the analysis type.

Analysis mode	Red highlighting means...
Design error detection	<p>One of the following:</p> <ul style="list-style-type: none"> <li>• The analysis found at least one test case that causes overflow or division-by-zero errors.</li> <li>• The analysis found dead logic.</li> <li>• The analysis found intermediate or output signals outside the range of user-specified minimum and maximum constraints.</li> <li>• The analysis found at least one test case that causes an out of bound array access error.</li> </ul>
Test generation	The analysis could not satisfy certain test objectives.
Property proving	The analysis disproved a proof objective and generated a counterexample that falsified that objective.

## Orange Highlighting on Model

Objects that are highlighted in orange have the following meaning, depending on the analysis type.

Analysis mode	Orange highlighting means...
Design error detection	<p>For the highlighted model object, the analysis did not decide at least one design error detection objective. This situation can occur when:</p> <ul style="list-style-type: none"> <li>• The analysis is still in progress.</li> <li>• The analysis times out.</li> <li>• The analysis cannot decide a design error detection objective because of division by zero or nonlinear arithmetic.</li> <li>• The software cannot decide a design error detection objective because of stubbing. For more information, see</li> </ul>

Analysis mode	Orange highlighting means...
	<p data-bbox="590 302 1277 361">“Handle Incompatibilities with Automatic Stubbing” on page 2-8.</p> <ul data-bbox="555 371 1311 534" style="list-style-type: none"><li data-bbox="555 371 1311 534">• The software cannot decide a design error detection objective because of limitations of the analysis engine. For example, if the analysis encounters an unbounded while loop, it performs an approximation. For information about this approximation, see “While Loops”.</li></ul>
Test generation	<p data-bbox="550 539 1329 598">For the highlighted model object, the analysis did not decide at least one test objective. This situation can occur when:</p> <ul data-bbox="555 631 1285 1062" style="list-style-type: none"><li data-bbox="555 631 980 661">• The analysis is still in progress.</li><li data-bbox="555 673 877 703">• The analysis times out.</li><li data-bbox="555 715 1252 774">• The analysis cannot decide a test objective because of division by zero or nonlinear arithmetic.</li><li data-bbox="555 786 1285 881">• The software cannot decide a test objective because of stubbing. For more information, see “Handle Incompatibilities with Automatic Stubbing” on page 2-8.</li><li data-bbox="555 894 1270 1062">• The software cannot decide a test objective because of limitations of the analysis engine. For example, if the analysis encounters an unbounded while loop, it performs an approximation. For information about this approximation, see “While Loops”.</li></ul>

Analysis mode	Orange highlighting means...
Property proving	<p>For the highlighted model object, the analysis did not decide at least one proof objective. This situation can occur when:</p> <ul style="list-style-type: none"> <li>• The analysis is still in progress.</li> <li>• The analysis times out.</li> <li>• A proof objective exists on a signal whose value the software cannot control, for example, a Constant block.</li> <li>• The analysis cannot decide a proof objective because of division by zero or nonlinear arithmetic.</li> <li>• The software cannot decide a proof objective because of stubbing. For more information, see “Handle Incompatibilities with Automatic Stubbing” on page 2-8.</li> <li>• The software cannot decide a proof objective because of limitations of the analysis engine. For example, if the analysis encounters an unbounded while loop, it performs an approximation. For information about this approximation, see “While Loops”.</li> </ul>

## Gray Highlighting on Model

Objects that are highlighted in gray have the following meaning.

Analysis mode	Gray highlighting means...
<ul style="list-style-type: none"> <li>• Design error detection</li> <li>• Test generation</li> <li>• Property proving</li> </ul>	The model object was not part of the analysis.



# Simulink Design Verifier Data Files

## In this section...

“Data File Generation” on page 13-9

“Contents of `sldvData` Structure” on page 13-9

“Model Information Fields in `sldvData`” on page 13-10

“Simulate Models with Data Files” on page 13-15

“Load Results from Data Files” on page 13-15

## Data File Generation

When you enable the **Save test data to file** parameter (see “Design Verifier Pane: Results” on page 15-56), the Simulink Design Verifier software generates a data file when it completes its analysis. The data file is a MAT-file that contains a structure named `sldvData`. This structure stores all the data the software gathers and produces during the analysis. Although the software displays the same data graphically in the harness model and report, you can use the data file to conduct your own analysis or to generate a custom report.

By default, the **Save test data to file** parameter is enabled.

## Contents of `sldvData` Structure

When the Simulink Design Verifier software completes its analysis, it produces a MAT-file that contains a structure named `sldvData`. To explore the contents of the `sldvData` structure:

- 1 Generate test cases for the `sldvdemo_flipflop` model:

```
sldvdemo_flipflop;  
sldvrun('sldvdemo_flipflop');
```

- 2 To load the data file, at the MATLAB prompt, enter the following command:

```
load('sldv_output\sldvdemo_flipflop\sldvdemo_flipflop_sldvdata.mat')
```

The MATLAB software loads the `sldvData` structure into its workspace. This structure contains the Simulink Design Verifier analysis results of the `sldvdemo_flipflop` model.

- 3 Enter `sldvData` at the MATLAB command line to display the field names that constitute the structure:

```
sldvData =
    ModelInformation: [1x1 struct]
  AnalysisInformation: [1x1 struct]
    ModelObjects: [1x2 struct]
    Constraints: []
    Objectives: [1x12 struct]
    TestCases: [1x4 struct]
    Version: '2.1'
```

## Model Information Fields in `sldvData`

The following sections describe the fields in the `sldvData` structure:

- “ModelInformation Field” on page 13-10
- “AnalysisInformation Field” on page 13-11
- “ModelObjects Field” on page 13-11
- “Constraints Field” on page 13-12
- “Objectives Field” on page 13-12
- “TestCases Field / CounterExamples Field” on page 13-13
- “Version Field” on page 13-14

### ModelInformation Field

In the `sldvData` structure, the `ModelInformation` field contains information about the model you analyzed. The following table describes each subfield of the `ModelInformation` field.

Subfield Name	Description
Name	String that specifies the model name.
Version	String that specifies the model number.
Author	String that specifies the user name.
TimeStamp	String that specifies the last date and time the model was updated.
SubsystemPath	String that represents the full path name of the subsystem (if any) that was analyzed.

Subfield Name	Description
ExtractedModel	String that represents the name of the model extracted (if any) to analyze the subsystem (if any) specified in <code>SubsystemPath</code> .
ReplacementModel	String that specifies the name of the model (if any) that contains the block replacements.

### AnalysisInformation Field

In the `sldvData` structure, the `AnalysisInformation` field lists settings of particular analysis options and related information. The following table describes each subfield of the `AnalysisInformation` field.

Subfield Name	Description
Status	String that specifies the completion status of the Simulink Design Verifier analysis.
AnalysisTime	Double that specifies the length of the analysis in seconds.
Options	Deep copy of the Simulink Design Verifier options object used during the analysis.
InputPortInfo	Cell array of structures that specifies information about each Inport block in the top-level system.
OutputPortInfo	Cell array of structures that specifies information about each Outport block in the top-level system.
SampleTimes	For internal use only.
Parameters	For internal use only.
AbstractedBlocks	For internal use only.
Approximations	A structure that describes the approximations performed during the analysis. For more information about approximations, see “Approximations” on page 2-16.
ReplacementInfo	For internal use only.

### ModelObjects Field

In the `sldvData` structure, the `ModelObjects` field lists the model items and their associated objectives. The following table describes each subfield of the `ModelObjects` field.

Subfield Name	Description
descr	String that specifies the full path to a model object, including objects in a Stateflow chart.
typeDesc	String that specifies the block type of the model object.
slPath	String that specifies the full path to a Simulink model object.
sfObjType	String that specifies the type of a Stateflow object, e.g., S for state and T for transition.
sfObjNum	Integer that represents the unique identifier of a Stateflow object.
sid	For internal use only.
designSid	For internal use only.
replacementSid	For internal use only.
objectives	Vector of integers that represents the indices of objectives associated with a model object.

**Constraints Field**

In the `sldvData` structure, the **Constraints** field lists information about specified minimum and maximum values (if any) on input ports in your model. The following table describes the subfield of the **Constraints** field.

Subfield Name	Description
DesignMinMax	Cell array of structures that include the name and minimum and maximum values for each input port for which values are specified.

**Objectives Field**

In the `sldvData` structure, the **Objectives** field lists information about each objective, such as its type, status, and description. The following table describes each subfield of the **Objectives** field.

Subfield Name	Description
type	String that specifies the type of an objective.

Subfield Name	Description
status	String that specifies the status of an objective.
descr	String that specifies the description of an objective.
label	String that specifies the label of an objective.
outcomeValue	Integer that specifies an objective's outcome.
coveragePointIdx	Integer that represents the index of a coverage point with which an objective is associated.
linkInfo	For internal use only.
range	For internal use only.
modelObjectIdx	Integer that represents the index of a model object with which an objective is associated.
analysisTime	Integer that represents the analysis time for an object.
testCaseIdx	Integer that represents the index of a test case or counterexample that addresses an objective.

### TestCases Field / CounterExamples Field

In the `sldvData` structure, this field can have two names, depending on the type of check:

- If you set the **Mode** parameter to **Design error detection**, the **CounterExamples** field lists information about each test case that results in an integer overflow or division-by-zero error.
- If you set the **Mode** parameter to **Test generation**, the **TestCases** field lists information about each test case, such as its signal values and the test objectives it achieves.
- If you set the **Mode** parameter to **Property proving**, the **CounterExamples** field lists information about each counterexample and the proof objective it falsifies.

The following table describes each subfield of the **TestCases / CounterExamples** field.

Subfield Name	Description
timeValues	Vector that specifies the time values associated with signals in a test case or counterexample.

Subfield Name	Description
dataValues	Cell array that specifies the data values associated with signals in a test case or counterexample.
paramValues	Structure that specifies the parameter values associated with a test case or counterexample. Its fields include:  <b>name</b> — String that specifies the name of a parameter.  <b>value</b> — Number that specifies the value of a parameter.  <b>noEffect</b> — Logical value that specifies whether a parameter's value affects an objective.
stepValues	Vector that specifies the number of time steps that comprise signals in a test case or counterexample.
objectives	Structure that specifies objectives that a test case or a counterexample addresses. Its fields include:  <b>objectiveIdx</b> — Integer that represents the index of an objective that a test case achieves or a counterexample falsifies.  <b>atTime</b> — Time value at which either a test case achieves an objective or a counterexample falsifies an objective.  <b>atStep</b> — Time step at which either a test case achieves an objective or a counterexample falsifies an objective.
dataNoEffect	Cell array of logical vectors that specifies whether a signal's data values affect an objective. The vector uses 1 to indicate that a signal's data value does not affect an objective; otherwise, it uses 0.
expectedOutput	Cell array of vectors that specifies the output values that result from simulating the model using the test case signals. Each cell represents the output values associated with a different Output block in the top-level system. This subfield is populated if you select <b>Include expected output values</b> .

### Version Field

In the `sldvData` structure, the `Version` field is a string that specifies the version of the Simulink Design Verifier software that analyzed the model.

## Simulate Models with Data Files

The `sldvrntest` function simulates a model using test cases or counterexamples that reside in a Simulink Design Verifier data file:

- 1 Simulate the `sldvdemo_flipflop` model and generate test cases:

```
sldvdemo_flipflop
```

- 2 Save the location of the data file generated after analyzing the model:

```
sldvDataFile = 'sldv_output\sldvdemo_flipflop\sldvdemo_flipflop_sldvdata.mat'
```

- 3 Use the `sldvrntest` function to simulate the `sldvdemo_flipflop` model using test case 2 in the data file:

```
[ outdata ] = sldvrntest('sldvdemo_flipflop', sldvDataFile, 2)
```

The output from `sldvrntest` is an array of “`Simulink.SimulationOutput` class” objects.

- 4 Examine the output data from the first test case using the methods of the `Simulink.SimulationOutput` object:

```
tout_sldvrntest = outData(1).find('tout_sldvrntest');  
xout_sldvrntest = outData(1).find('xout_sldvrntest');  
yout_sldvrntest = outData(1).find('yout_sldvrntest');  
logsout_sldvrntest = outData(1).find('logsout_sldvrntest');
```

## Load Results from Data Files

You can load previous analysis results for a model from a data file. For more information, see “Load Previous Results” and `sldvloadresults`.

## Simulink Design Verifier Harness Models

### In this section...

- “Harness Model Generation” on page 13-16
- “Create a Harness Model” on page 13-16
- “Anatomy of a Harness Model” on page 13-17
- “Configuration of the Harness Model” on page 13-21
- “Simulate the Harness Model” on page 13-21

### Harness Model Generation

During or after a Simulink Design Verifier analysis, you can create a harness model.

The contents of the harness model depend on the value of the **Mode** parameter, set in the Configuration Parameters dialog box on the **Design Verifier** pane:

- **Design error detection** — The harness model contains test cases that result in errors during simulation.
- **Test generation** — The harness model contains test cases that achieve test objectives.
- **Property proving** — The harness model contains counterexamples that falsify proof objectives.

By default, the **Save test harness as model** parameter is disabled.

---

**Note:** The Simulink Design Verifier software can generate a harness model only when the top level of the system you are analyzing contains an Inport block.

---

### Create a Harness Model

To create a harness model before or after the analysis, do one of the following:


- Before the analysis, in the Configuration Parameters dialog box, on the **Design Verifier > Results** pane, select **Save test harness as model**.



- After the analysis, in the Simulink Design Verifier log window, select **Create harness model**.

## Anatomy of a Harness Model

The Simulink Design Verifier software produces a harness model that looks like this:




The harness model contains the following items:


- **Inputs** — This Signal Builder block contains signals that comprise the test cases or counterexamples that the Simulink Design Verifier software generated. The Signal Builder block contains signals only for input signals that are used in the model. If an input signal has no effect on the output of the model, that signal is not included in the Signal Builder block.

Double-click the Inputs block to open the Signal Builder dialog box and view its signals. Each signal group represents a unique test case or counterexample. In the Signal Builder dialog box, select a tab to view the signals associated with a particular test case or counterexample.

The following Signal Builder block shows the signals for Test Case 7 after Simulink Design Verifier performs test generation analysis on the `sldvdemo_cruise_control` model with the default options.



If you select the `LongTestcases` option of the **Test suite optimization** parameter, the analysis creates fewer, longer test cases. For example, if you select the `LongTestcases` option for the `sldvdemo_cruise_control` model, the analysis produces one long test case instead of nine shorter test cases. The following Signal Builder dialog box shows the signals for the long test case.



**Note:** For more information about the Signal Builder dialog box, see “Signal Groups” in the Simulink documentation.

- **Size-Type** — This Subsystem block transmits signals from the Inputs block to the Test Unit block. It verifies that the size and data type of the of the signals are consistent with the Test Unit block.

- **Test Unit** — This Subsystem block contains a copy of the original model that the Simulink Design Verifier software analyzed.

If you select the **Reference input model in generated harness** on the **Design Verifier > Results** pane, the Test Unit is a Model block that references the model you are analyzing, not a subsystem.

- **Test Case Explanation** — This DocBlock block documents the test cases or counterexamples that the Simulink Design Verifier software generates. Double-click the Test Case Explanation block to view a description of each test case or counterexample. The block lists either the test objectives that each test case achieves (as in the next graphic) or the proof objectives that each counterexample falsifies.

```

1 Test Case 1 (1 Objectives)
2   Parameter values:
3
4   1. Controller/Switch2 - logical trigger input false (output is from 3rd input port) @ T=0.00
5
6 Test Case 2 (3 Objectives)
7   Parameter values:
8
9   1. Controller/Logical Operator - Logic: input port 1 F @ T=0.00
10  2. Controller/Logical Operator - Logic: MCDC expression for output with input port 1 F @ T=0.00
11  3. Controller/PI Controller - enable logical value F @ T=0.00
12
13 Test Case 3 (3 Objectives)
14   Parameter values:
15
16  1. Controller/Logical Operator1 - Logic: input port 1 T @ T=0.00
17  2. Controller/Logical Operator - Logic: input port 2 F @ T=0.00
18  3. Controller/Logical Operator - Logic: MCDC expression for output with input port 2 F @ T=0.00
19
20 Test Case 4 (1 Objectives)
21   Parameter values:
22
23  1. Controller/Switch3 - logical trigger input true (output is from 1st input port) @ T=0.00
24
25 Test Case 5 (7 Objectives)
26   Parameter values:
27
28  1. Controller/Switch1 - logical trigger input false (output is from 3rd input port) @ T=0.00
29  2. Controller/Logical Operator2 - Logic: input port 1 F @ T=0.00
30  3. Controller/Logical Operator2 - Logic: input port 2 F @ T=0.00
31  4. Controller/Logical Operator2 - Logic: MCDC expression for output with input port 1 F @ T=0.00
32  5. Controller/Logical Operator2 - Logic: MCDC expression for output with input port 2 F @ T=0.00
33  6. Controller/Logical Operator - Logic: input port 3 F @ T=0.00
34  7. Controller/Logical Operator - Logic: MCDC expression for output with input port 3 F @ T=0.00
35
36 Test Case 6 (2 Objectives)
37   Parameter values:
38
39  1. Controller/Logical Operator2 - Logic: input port 2 T @ T=0.01
40  2. Controller/Logical Operator2 - Logic: MCDC expression for output with input port 2 T @ T=0.01
41
42 Test Case 7 (1 Objectives)
43   Parameter values:
44

```

## Configuration of the Harness Model

After the Simulink Design Verifier software generates the harness model, it has the following settings:

- The harness model start time is always 0. If the original model uses a nonzero start time, the software ignores this and uses 0 for the simulation start time for test cases and counterexamples.
- The harness model stop time always equals the stop time of the longest test case in the Signal Builder dialog box.
- By default, the software enables coverage reporting for harness models that contain test cases. Although it enables coverage reporting with particular options selected, you can customize the settings to meet your needs. For more information, see “Customize Requirements Report” in the Simulink Verification and Validation documentation.
- By default, if you select **Ignore objective based on filter** and provide a coverage filter file for the Test Unit, the coverage filter file also applies to the harness model. The coverage objective filter parameters are in the Configuration Parameters dialog box, on the **Test Generation** pane.

## Simulate the Harness Model

The harness model enables you to simulate a copy of your original model using the test cases or counterexamples that the Simulink Design Verifier software generates. Using the harness model, you can simulate:

- A counterexample
- A single test case, for which the Simulink Verification and Validation software collects and displays model coverage information
- All test cases, for which the Simulink Verification and Validation software collects and displays cumulative model coverage information

---

**Note:** If you analyze a model that simulates with sample time warnings, when you simulate the harness model, the warnings may be reported as errors, causing the simulation to fail.

---


To simulate a single test case or counterexample:

- 1 In the harness model, double-click the Inputs block.

The Signal Builder dialog box appears.

- 2 In the Signal Builder dialog box, select the tab associated with a particular test case or counterexample.

The Signal Builder dialog box displays the signals that comprise the selected test case or counterexample.


- 3 In the Signal Builder dialog box, click the **Start simulation** button .

The Simulink software simulates the harness model using the signals associated with the selected test case or counterexample. When simulating a test case, the Simulink Verification and Validation software collects model coverage information and displays a coverage report.

To simulate all test cases and measure their combined model coverage:

- 1 In the harness model, double-click the Inputs block.

The Signal Builder dialog box appears.

- 2 In the Signal Builder dialog box, click the **Run all** button .

The Simulink software simulates the harness model using all test cases, while the Simulink Verification and Validation software collects model coverage information and displays a coverage report.

When you click **Run all**, the software simulates all the test cases using the stop time for the harness model. The stop time equals the stop time for the longest test case, so you may accumulate additional coverage when you simulate the shorter test cases.

If the Test Unit in the harness model is a subsystem, the values of the Simulink simulation optimization parameters on the Configuration Parameters dialog box may impact your coverage results.

---

**Note:** The simulation optimization parameters are on the following Configuration Parameters dialog box panes:

- **Optimization** pane

- **Optimization > Signals and Parameters** pane
  - **Optimization > Stateflow** pane
- 

See “Simulating with Signal Groups” in the Simulink documentation for more information about simulating models containing Signal Builder blocks.

## Export Test Cases to SystemTest

If you have installed the SystemTest software with your MATLAB application, you can specify that the Simulink Design Verifier software create a SystemTest TEST-file when it analyzes a model. Creating a TEST-file allows you to configure and collect model coverage results and run the test cases from inside the SystemTest environment.

---


**Note:** The option to create a SystemTest TEST-file is only available in test-generation mode; you cannot create this file when running a property-proving analysis.

---

In addition, if you have a model with a large number of inputs, this feature eliminates the overhead of creating the harness model. However, you can create both a harness model and a TEST-file in the same analysis.


To create a TEST-file for the `sldvdemo_cruise_control` model, perform these steps:

- 1 Type `sldvdemo_cruise_control` at the MATLAB command prompt to open the Cruise Control Test Generation model.
- 2 Select **Analysis > Design Verifier > Options** to open the Configuration Parameters dialog box.
- 3 In the **Select** pane, under **Design Verifier**, select **Results**.
- 4 On the **Results** pane, under **SystemTest options**, select **Save test harness as SystemTest TEST-file (will reference saved data file)**.




- 5 If you prefer a file name other than the default, specify the **SystemTest file name**.
- 6 Under **Data File options**, verify that **Save test data to file** is selected. You must select this option to generate a TEST-file.






- 7 If you do not need the Simulink Design Verifier harness model in addition to the TEST-file, under **Harness model options**, clear **Save text harness as model**.



- 8 Click **Apply** and **OK** to save the changes and exit the Configuration Parameters dialog box.
- 9 Double-click the Run block in the `sldvdemo_cruise_control` model to start the analysis.

When the analysis completes, the SystemTest desktop opens the TEST-file, which, for this example, is saved as

```
matlabroot\sldvdemo_output\sldv_cruise_control\sldvdemo_cruise_control_harness.test
```



In the **Test Browser** pane, the 8 iterations in **Main Test (8 Iterations)** correspond to the 8 test cases that the Simulink Design Verifier software generates and describes in the Test Case Explanation block of the harness model.

For information about running Simulink Design Verifier test cases using the SystemTest software, see “Create a Simulink Design Verifier Test Vector” in the SystemTest documentation.

# Simulink Design Verifier Reports

## In this section...

“Simulink Design Verifier Report Generation” on page 13-27

“Create Analysis Reports” on page 13-27

“Front Matter” on page 13-28

“Summary Chapter” on page 13-28

“Analysis Information Chapter” on page 13-28

“Derived Ranges Chapter” on page 13-33

“Objectives Status Chapters” on page 13-34

“Model Items Chapter” on page 13-41

“Design Errors Chapter” on page 13-42

“Test Cases Chapter” on page 13-43

“Properties Chapter” on page 13-48

## Simulink Design Verifier Report Generation

After an analysis, the Simulink Design Verifier software can generate an HTML report that contains detailed information about the analysis results.

In addition, the analysis report contains hyperlinks that allow you to:

- Navigate to a specific part of the report
- Navigate to the object in your Simulink model for which the analysis recorded results

## Create Analysis Reports

To create a detailed analysis report before or after the analysis, do one of the following:

- Before the analysis, in the Configuration Parameters dialog box, on the **Design Verifier > Report** pane, select **Generate report of the results**.
- After the analysis, in the Simulink Design Verifier log window, select **Generate detailed analysis results**.

### Front Matter

The report begins with two sections:

- “Title” on page 13-28
- “Table of Contents” on page 13-28

#### Title

The title section lists the following information:

- Model or subsystem name the Simulink Design Verifier software analyzed
- User name associated with the current MATLAB session
- Date and time that the Simulink Design Verifier software generated the report

#### Table of Contents

The table of contents follows the title section. Clicking items in the table of contents allows you to navigate quickly to particular chapters in the report.

### Summary Chapter

The **Summary** chapter of the HTML report lists the following information:

- Name of the model
- Analysis mode
- Analysis status
- Status of objectives analyzed

### Analysis Information Chapter

The **Analysis Information** chapter of the HTML report includes the following sections:

- “Model Information” on page 13-29
- “Analysis Options” on page 13-29
- “Unsupported Blocks” on page 13-30

- “Constraints” on page 13-31
- “Block Replacements Summary” on page 13-31
- “Approximations” on page 13-32

### **Model Information**

The Model Information section provides the following information about the current version of the model:

- Path and file name of the model that the Simulink Design Verifier software analyzed
- Model version
- Date and time that the model was last saved
- Name of the person who last saved the model

### **Analysis Options**

The Analysis Options section provides information about the Simulink Design Verifier analysis settings.

The Analysis Options section lists the parameters that affected the Simulink Design Verifier analysis. If you enabled coverage filtering, the name of the filter file is included in this section.

## Analysis Options

Mode:	TestGeneration
Test Suite Optimization:	CombinedObjectives
Maximum Testcase Steps:	500 time steps
Test Conditions:	UseLocalSettings
Test Objectives:	UseLocalSettings
Model Coverage Objectives:	MCDC
Maximum Analysis Time:	60s
Block Replacement:	on
Block Replacement Rules:	<FactoryDefaultRules>
Parameters Analysis:	on
Parameters Configuration File:	sldv_params_template.m
Save Data:	on
Save Harness:	on
Save Report:	on

---

**Note:** For more information about these parameters, see “Simulink Design Verifier Options”.

---

### Unsupported Blocks

If your model includes unsupported blocks, by default, automatic stubbing is enabled to allow the analysis to proceed. With automatic stubbing enabled, the software considers only the interface of the unsupported blocks, not their actual behavior. This technique

allows the software to complete the analysis. However, the analysis may achieve only partial results if any of the unsupported model blocks affect the simulation outcome.

The Unsupported Blocks section appears only if the analysis stubbed unsupported blocks; it lists the unsupported block in a table, with a hyperlink to the block in the model.

## Unsupported Blocks

The following blocks are not supported by Simulink Design Verifier. They were abstracted during the analysis. This can lead Simulink Design Verifier to produce only partial results for parts of the model that depends on the output values of these blocks.

Block	Type
<a href="#">Discrete State-Space</a>	DiscreteStateSpace

For more information about automatic stubbing, see “Handle Incompatibilities with Automatic Stubbing” on page 2-8.

## Constraints

The Constraints section provides information about test conditions that the Simulink Design Verifier software applied when it analyzed a model.

## Constraints

### Analysis Constraints

Name	Analysis Constraint
<a href="#">constraint</a>	[0, 100]

You can navigate to the constraint in your model by clicking the hyperlink in the Constraints table. The software highlights the corresponding Test Condition block in your model window and opens a new window showing the block in detail.

## Block Replacements Summary

The Block Replacements Summary provides an overview of the block replacements that the Simulink Design Verifier software executed. It appears only if the Simulink Design Verifier software replaced blocks in a model.

Each row of the table corresponds to a particular block replacement rule that the Simulink Design Verifier software applied to the model. The table lists the following:

- Name of the file that contains the block replacement rule and the value of the `BlockType` parameter the rule specifies
- Description of the rule that the `MaskDescription` parameter of the replacement block specifies
- Names of blocks that the Simulink Design Verifier software replaced in the model

To locate a particular block replacement in your model, click on the name for that replacement in the Replaced Blocks column of the table; the software highlights the affected block in your model window and opens a new window that displays the block in detail.

## Block Replacements Summary

**Table 2.1. Block Replacements**

#:	Replacement Rule / Block Type	Rule Description	Replaced Blocks
1	blkrep_rule_switch_normal /Switch	Inserts test objectives for switch blocks that require each switch position be demonstrated when the values of input ports 1 and 3 differ.	<a href="#">Switch1</a> <a href="#">Switch2</a> <a href="#">Switch3</a>

## Approximations

Each row of the Approximations table describes a specific type of approximation that the Simulink Design Verifier software used during its analysis of the model.

## Approximations

Simulink Design Verifier performed the following approximations during analysis. These can impact the precision of the results generated by Simulink Design Verifier. Please see the product documentation for further details.

#	Type	Description
1	Rational approximation	The model includes floating-point arithmetic. Simulink Design Verifier approximates floating-point arithmetic with rational number arithmetic.



---

**Note:** Review the analysis results carefully when the software uses approximations. In rare cases, an approximation may result in test cases that fail to achieve test objectives or counterexamples that fail to falsify proof objectives. For example, a floating-point round-off error might prevent a signal from exceeding a designated threshold value.

---

## Derived Ranges Chapter

In a design error detection analysis, the analysis calculates the derived ranges of the signal values for the Outports for each block in the model. This information can help you identify the source of data overflow or division-by-zero errors.

The table in the **Derived Ranges** chapter of the analysis report lists these bounds.

### Chapter 3. Derived Ranges

Signal	Derived Ranges
<a href="#">Controller/Constant1- output 1</a>	1
<a href="#">Controller/Unit Delay- output 1</a>	[-Inf..Inf]
<a href="#">Controller/Sum- output 1</a>	[-Inf..Inf]
<a href="#">Controller/Constant3- output 1</a>	1
<a href="#">Controller/Sum2- output 1</a>	[-Inf..Inf]
<a href="#">Controller/Switch3/Switch. Defined by block replacement rule 'blkrep rule switch normal'.- output 1</a>	[-Inf..Inf]
<a href="#">Controller/Switch2/Switch. Defined by block replacement rule 'blkrep rule switch normal'.- output 1</a>	[-Inf..Inf]
<a href="#">Controller/Switch1/Switch. Defined by block replacement rule 'blkrep rule switch normal'.- output 1</a>	[-Inf..Inf]
<a href="#">Controller/Sum1- output 1</a>	[-Inf..Inf]
<a href="#">Controller/Logical Operator1- output 1</a>	[F..T]
<a href="#">Controller/Unit Delay1- output 1</a>	[F..T]
<a href="#">Controller/Logical Operator2- output 1</a>	[F..T]
<a href="#">Controller/Logical Operator- output 1</a>	[F..T]
<a href="#">throt- output 1</a>	[-3.5954e+306..3.5954e+306]
<a href="#">target- output 1</a>	[-Inf..Inf]

## Objectives Status Chapters

This section of the report provides information about all objectives in a model, including an objective's type, the model item to which it corresponds, and its description.

- “Design Error Detection Objectives Status” on page 13-34
- “Test Objectives Status” on page 13-36
- “Proof Objectives Status” on page 13-38
- “Objectives Undecided” on page 13-39
- “Objectives Undecided Due to Division by Zero” on page 13-40
- “Objectives Undecided Due to Nonlinearities” on page 13-40
- “Objectives Undecided Due to Stubbing” on page 13-40

### Design Error Detection Objectives Status

If you run a design error detection analysis, the **Design Error Detection Objectives Status** section can include the following tables:

- “Active Logic” on page 13-34
- “Dead Logic” on page 13-35
- “Objectives Proven Valid” on page 13-36
- “Objectives Falsified with Test Cases” on page 13-36

### Active Logic

The **Active Logic** section lists the model items for which the analysis found active logic. The following image shows a portion of the Active Logic section of the generated analysis report for the `sldvdemo_fuelsys_logic_simple` example model.

## Active Logic

Simulink Design Verifier found that these decision and condition outcomes can occur and are active logic in the model.

#	Type	Model Item	Description	Analysis Time (sec)
5	Decision	<a href="#">control logic.Oxygen Sensor Mode</a>	State: Substate executed State "O2_fail"	52
6	Decision	<a href="#">control logic.Oxygen Sensor Mode</a>	State: Substate executed State "O2_normal"	52
7	Decision	<a href="#">control logic.Oxygen Sensor Mode</a>	State: Substate executed State "O2_warmup"	52
8	Decision	<a href="#">control logic.Oxygen Sensor Mode."[Ego &lt; max_ego]/ Sens Fail..."</a>	Transition: Transition trigger expression F	52
9	Decision	<a href="#">control logic.Oxygen Sensor Mode."[Ego &lt; max_ego]/ Sens Fail..."</a>	Transition: Transition trigger expression T	52
10	Decision	<a href="#">control logic.Oxygen Sensor Mode."[Ego &gt; max_ego]/ Sens Failu..."</a>	Transition: Transition trigger expression F	52
11	Decision	<a href="#">control logic.Oxygen Sensor Mode."[Ego &gt; max_ego]/ Sens Failu..."</a>	Transition: Transition trigger expression T	52
12	Decision	<a href="#">control logic.Oxygen Sensor Mode."[after (5,tick)]"</a>	Transition: Transition trigger expression F	52
13	Decision	<a href="#">control logic.Oxygen Sensor Mode."[after (5,tick)]"</a>	Transition: Transition trigger expression T	52

## Dead Logic

The **Dead Logic** section lists the model items for which the analysis found dead logic. The following image shows the Dead Logic section of the generated analysis report for the `sldvdemo_fuelsys_logic_simple` example model.

## Dead Logic

Simulink Design Verifier proved that these decision and condition outcomes cannot occur and are dead-logic in the model. Dead-logic in the model can also be a side-effect of parameter configurations, input specified minimum maximum constraints, or in rare cases, the approximations performed by Simulink Design Verifier.

#	Type	Model Item	Description	Analysis Time (sec)
49	Condition	<a href="#">control logic.Speed_Sensor_Mode."[speed==0 &amp; press &lt; zero th..."</a>	Transition: Condition 2, "press < zero_thresh" F	20
86	Decision	<a href="#">control logic.Fueling_Mode.Fuel_Disabled."[in (Sens Failure Counter.Mu..."</a>	Transition: Transition trigger expression F	20

## Objectives Proven Valid

The **Objectives Proven Valid** section lists the design error detection objectives that the analysis proved valid. For these objectives, the analysis determined that the described design errors cannot occur.

## Objectives Proven Valid

#	Type	Model Item	Description	Analysis Time (sec)	Test Case
20	Overflow	<a href="#">debounce/ SFunction</a>	Overflow	5	n/a

## Objectives Falsified with Test Cases

The **Objectives Falsified with Test Cases** section lists the objectives for which the analysis found test cases that demonstrate design errors.

## Objectives Falsified with Test Cases

#	Type	Model Item	Description	Analysis Time (sec)	Test Case
12	Overflow	<a href="#">Verify True Output/Sum</a>	Overflow	13	<a href="#">1</a>

## Test Objectives Status

If you run a test case generation analysis, the **Test Objectives Status** section can include the following tables:

- “Objectives Satisfied” on page 13-37
- “Objectives Proven Unsatisfiable” on page 13-37

## Objectives Satisfied

The **Objectives Satisfied** section lists test objectives that the analysis satisfied.

### Objectives Satisfied

Simulink Design Verifier found test cases that exercise these test objectives.

#	Type	Model Item	Description	Analysis Time (sec)	Test Case
1	Condition	<a href="#">Controller/Logical Operator1</a>	Logic: input port 1 T	0	<a href="#">3</a>
2	Condition	<a href="#">Controller/Logical Operator1</a>	Logic: input port 1 F	0	<a href="#">8</a>
3	Condition	<a href="#">Controller/Logical Operator2</a>	Logic: input port 1 T	0	<a href="#">8</a>
4	Condition	<a href="#">Controller/Logical Operator2</a>	Logic: input port 1 F	0	<a href="#">5</a>
5	Condition	<a href="#">Controller/Logical Operator2</a>	Logic: input port 2 T	1	<a href="#">6</a>
6	Condition	<a href="#">Controller/Logical Operator2</a>	Logic: input port 2 F	0	<a href="#">5</a>
7	MCDC	<a href="#">Controller/Logical Operator2</a>	Logic: MCDC expression for output with input port 1 T	0	<a href="#">8</a>
8	MCDC	<a href="#">Controller/Logical Operator2</a>	Logic: MCDC expression for output with input port 2 T	1	<a href="#">6</a>
9	MCDC	<a href="#">Controller/Logical Operator2</a>	Logic: MCDC expression for output with input port 1 F	0	<a href="#">5</a>

## Objectives Proven Unsatisfiable

The **Objectives Proven Unsatisfiable** section lists the test objectives that the analysis determined could not be satisfied.

In the following example, the Stateflow chart Mode Logic updates at every time step, so the implicit event `tick` is never false. The analysis cannot satisfy condition coverage for the temporal event `after(4, tick)`. For this and other unsatisfiable objectives in the model, the report lists the type, model item, and description.

## Objectives Proven Unsatisfiable

Simulink Design Verifier proved that there does not exist any test case exercising these test objectives. This often indicates the presence of dead-logic in the model. Other possible reasons can be inactive blocks in the model due to parameter configuration or test constraints such as given using Test Condition blocks. In rare cases, the approximations performed by Simulink Design Verifier can make objectives impossible to achieve.

#	Type	Model Item	Description	Analysis Time (sec)	Test Case
4	Decision	<a href="#">Switchable config</a>	enable logical value T	1	n/a
5	Condition	<a href="#">Logical Operator</a>	Logic: input port 1 T	1	n/a
7	Decision	<a href="#">Normal config (feedthrough)</a>	enable logical value F	1	n/a
9	Decision	<a href="#">Switchable config/Multiport Switch</a>	integer input value = 0 (output is from input port 0)	0	n/a
10	Decision	<a href="#">Switchable config/Multiport Switch</a>	integer input value = 1 (output is from input port 1)	0	n/a
11	Decision	<a href="#">Switchable config/Multiport Switch</a>	integer input value = 2 (output is from input port 2)	0	n/a
12	Decision	<a href="#">Switchable config/Multiport Switch</a>	integer input value = *,3 (output is from input port 3)	0	n/a
22	Condition	<a href="#">Mode Logic."after(4, tick)"</a>	Transition: Condition 1, "tick" F	1	n/a
37	Decision	<a href="#">protected division1/Switch</a>	logical trigger input false (output is from 3rd input port)	1	n/a
41	Decision	<a href="#">protected division/Switch</a>	logical trigger input false (output is from 3rd input port)	1	n/a
45	Decision	<a href="#">Mode Logic.Clipped."[!on]"</a>	Transition: Transition trigger expression F	1	n/a

## Proof Objectives Status

If you run a property-proving analysis, the **Proof Objectives Status** section can include:

- “Objectives Proven Valid” on page 13-38
- “Objectives Falsified with Counterexamples” on page 13-39

## Objectives Proven Valid

The **Objectives Proven Valid** section lists the proof objectives that the analysis proved valid.

## Objectives Proven Valid

#	Type	Model Item	Description	Analysis Time (sec)	Counterexample
1	Proof objective	<a href="#">Verify Output/FoutCorrect</a>	Objective: T	1	n/a
2	Proof objective	<a href="#">Verify Output/ToutCorrect</a>	Objective: T	1	n/a

## Objectives Falsified with Counterexamples

The **Objectives Falsified with Counterexamples** section lists the proof objectives that the analysis disproved. In this example, the software generated at least one counterexample that falsifies the specified objective.

## Objectives Falsified with Counterexamples

#	Type	Model Item	Description	Analysis Time (sec)	Counterexample
1	Assert	<a href="#">Verify True Output/Assertion</a>	Assert	1	<a href="#">1</a>

## Objectives Undecided

For all types of objectives, the **Objectives Undecided** section lists the objectives for which the analysis was unable to determine an outcome in the allotted time.

In the following property-proving example, either the software exceeded its analysis time limit (which the **Maximum analysis time** parameter specifies), or you aborted the analysis before it completed processing these objectives.

## Objectives Undecided

Simulink Design Verifier was not able to process these objectives with the current options.

#	Type	Model Item	Description	Analysis Time (sec)	Counterexample
1	Proof objective	<a href="#">Verify Output/FoutCorrect</a>	Objective: T	-1	n/a
2	Proof objective	<a href="#">Verify Output/ToutCorrect</a>	Objective: T	-1	n/a

### Objectives Undecided Due to Division by Zero

For all types of objectives, the **Objectives Undecided Due to Division by Zero** section lists objectives that the analysis was unable to decide because of division by zero errors in the associated model items. To detect division by zero errors before running further analysis on your model, follow the procedure in “Detect Integer Overflow and Division-by-Zero Errors”.

### Objectives Undecided Due to Division by Zero

Simulink Design Verifier was not able to decide these objectives due to division by zero errors in the model.

#	Type	Model Item	Description	Analysis Time (sec)	Test Case
1	Decision	<a href="#">Saturation</a>	input > lower limit F	0	n/a
2	Decision	<a href="#">Saturation</a>	input > lower limit T	0	n/a
3	Decision	<a href="#">Saturation</a>	input >= upper limit F	0	n/a
4	Decision	<a href="#">Saturation</a>	input >= upper limit T	0	n/a

### Objectives Undecided Due to Nonlinearities

For all types of objectives, the **Objectives Undecided Due to Nonlinearities** section lists the objectives that the analysis was unable to decide because they require computation of nonlinear arithmetic. Simulink Design Verifier does not support nonlinear arithmetic or nonlinear logic.

### Objectives Undecided Due to Nonlinearities

Simulink Design Verifier was not able to decide these objectives due to the presence of nonlinear arithmetic in the model.

#	Type	Model Item	Description	Analysis Time (sec)	Test Case
30	Decision	<a href="#">BasicRollMode/Integrator</a>	integration result <= lower limit T	2	n/a
32	Decision	<a href="#">BasicRollMode/Integrator</a>	integration result >= upper limit T	2	n/a

### Objectives Undecided Due to Stubbing

For all types of objectives, the **Objectives Undecided Due to Stubbing** section lists model items with objectives that the analysis was unable to decide because of stubbing. These can include objectives that, in releases prior to R2013b, were



marked as **Objectives Satisfied – No Test Case** or **Objectives Falsified – No Counterexample**.

### Objectives Undecided Due to Stubbing

Simulink Design Verifier was not able to decide these objectives due to stubbing.

#	Type	Model Item	Description	Analysis Time (sec)
2	Decision	<a href="#">Saturation</a>	input > lower limit F	12
3	Decision	<a href="#">Saturation</a>	input > lower limit T	12
4	Decision	<a href="#">Saturation</a>	input >= upper limit F	12
5	Decision	<a href="#">Saturation</a>	input >= upper limit T	12

## Model Items Chapter

The **Model Items** chapter of the HTML report includes a table for each object in the model that defines coverage objectives. The table for a particular object lists all of the associated objectives, the objective types, objective descriptions, and the status of each objective at the end of the analysis.

The table for an individual object in the model will look similar to this one for the Discrete-Time Integrator in the PI Controller subsystem of the `sldvdemo_cruise_control` example model.

### Controller/PI Controller/Discrete-Time Integrator

[View](#)

#:	Type	Description	Status	Test Case
31	Decision	integration result <= lower limit F	Satisfied	<a href="#">3</a>
32	Decision	integration result <= lower limit T	Satisfied	<a href="#">8</a>
33	Decision	integration result >= upper limit F	Satisfied	<a href="#">3</a>
34	Decision	integration result >= upper limit T	Satisfied	<a href="#">9</a>

To highlight a given object in your model, click **View** at the upper-left corner of the table; the software opens a new window that displays the object in detail. To view the details of the test case that was applied to a specific objective, click the test case number in the last column of the table.

## Design Errors Chapter

If you run a design error detection analysis, the report includes a **Design Errors** chapter. This chapter includes sections that summarize the design errors the analysis validated or falsified:

- “Table of Contents” on page 13-42
- “Summary” on page 13-42
- “Test Case” on page 13-43

### Table of Contents

Each Design Errors chapter contains a table of contents. Each item in the table of contents is a hyperlink to results about a specific design error.

### Summary

The Summary section lists:

- The model item
- The type of design error that was detected (overflow or division by zero)
- The status of the analysis (Falsified or Proven Valid)

In the following example, the software analyzed the `sldvdemo_debounce_falseprop` model to detect design errors. The analysis detected an overflow error in the Sum block in the Verification Subsystem named Verify True Output.

### Summary

Model Item:	<a href="#">Verify True Output/Sum</a>
Type:	Overflow
Status:	Falsified

## Test Case

The Test Case section lists the time step and corresponding time at which the test case falsified the design error objective. The Inport block raw had a value of 255, which caused the overflow error.

### Test Case

<b>Time</b>	<b>0- 0.01</b>
<b>Step</b>	<b>1-2</b>
<b>raw</b>	<b>255</b>

## Test Cases Chapter

If you run a test generation analysis, the report includes a **Test Cases** chapter. This chapter includes sections that summarize the test cases the analysis generated:

- “Table of Contents” on page 13-43
- “Summary” on page 13-43
- “Objectives” on page 13-44
- “Generated Input Data” on page 13-44
- “Expected Output” on page 13-45
- “Combined Objectives” on page 13-46
- “Long Test Cases” on page 13-47

### Table of Contents

Each Test Cases chapter contains a table of contents. Each item in the table of contents is a hyperlink to information about a specific test case.

### Summary

The Summary section lists:

- Length of the signals that comprise the test case
- Total number of test objectives that the test case achieves

## Summary

Length: 0.06 second (7 sample periods)  
 Objectives Satisfied: 1

## Objectives

The Objectives section lists:

- The time step at which the test case achieves that objective.
- The time at which the test case achieves that objective.
- A link to the model item associated with that objective. Clicking the link highlights the model item in the Simulink Editor.
- The objective that was achieved.

## Objectives

Step	Time	Model Item	Objectives
7	0.06	<a href="#">Controller/PI Controller/Discrete-Time Integrator</a>	integration result >= upper limit T

## Generated Input Data

For each input signal associated with the model item, the Generated Input Data section lists the time step and corresponding time at which the test case achieves particular test objectives. If the signal value does not change over those time steps, the table lists the time step and time as ranges.

## Generated Input Data

<b>Time</b>	<b>0</b>	<b>0.01- 0.05</b>	<b>0.06</b>
<b>Step</b>	<b>1</b>	<b>2-6</b>	<b>7</b>
enable	1	1	1
brake	0	0	0
set	1	0	1
inc	1	1	-
dec	1	0	-
speed	97	0	0

---

**Note:** The Generated Input Data table displays a dash (–) instead of a number as a signal value when the value of the signal at that time step does not affect the test objective. In the harness model, the Inputs block represents these values with zeros unless you enable the **Randomize data that does not affect outcome** parameter (see “Randomize data that do not affect the outcome” on page 15-59).

---

## Expected Output

If you select the **Include expected output values** on the **Design Verifier > Results** pane of the Configuration Parameters dialog box, the report includes the Expected Output section for each test case. For each output signal associated with the model item, this table lists the expected output value at each time step.

**Expected Output** These output values are expected assuming that inputs that do not affect the test objectives (- in the table above) are given a default value - 0 for numeric types, and default value for enumerated types.

<b>Time</b>	<b>0</b>	<b>0.01</b>	<b>0.02</b>	<b>0.03</b>	<b>0.04</b>	<b>0.05</b>	<b>0.06</b>
<b>Step</b>	<b>1</b>	<b>2</b>	<b>3</b>	<b>4</b>	<b>5</b>	<b>6</b>	<b>7</b>
throt	0	1.96	1.9898	2.0197	2.0497	2.0798	0.05
target	97	98	99	100	101	102	0

### **Combined Objectives**

If you set the **Test suite optimization** option to **CombinedObjectives** (the default), the Test Cases chapter may include individual information about many test cases.

# Chapter 5. Test Cases

## Table of Contents

[Test Case 1](#)

[Test Case 2](#)

[Test Case 3](#)

[Test Case 4](#)

[Test Case 5](#)

[Test Case 6](#)

[Test Case 7](#)

[Test Case 8](#)

[Test Case 9](#)

This section contains detailed information about each generated test case.

## Test Case 1

### Summary

Length: 0 second (1 sample period)

Objectives 12

Satisfied:

### Long Test Cases

If you set the **Test suite optimization** option to LongTestcases, the Test Cases chapter in the report includes fewer sections about longer test cases.

## Chapter 5. Test Cases

### Table of Contents

#### [Test Case 1](#)

This section contains detailed information about each generated test case.

### Test Case 1

#### Summary

Length:	0.26 second (27 sample periods)
Objectives Satisfied:	259

### Properties Chapter

If you run a property-proving analysis, the report includes a **Properties** chapter. This chapter includes sections that summarize the proof objectives and any counterexamples the software generated:

- “Table of Contents” on page 13-48
- “Summary” on page 13-48
- “Counterexample” on page 13-49

#### Table of Contents

Each Properties chapter contains a table of contents. Each item in the table of contents is a hyperlink to information about a specific property that was falsified.

#### Summary

The Summary section lists:



- The model item that the software analyzed
- The type of property that was evaluated
- The status of the analysis

In the following example, the software analyzed the `sldvdemo_cruise_control_verification` model for property proving. The analysis proved that the input to the Assertion block named `BrakeAssertion` was nonzero.

## Summary

Model Item: [Safety Properties/BrakeAssertion](#)  
 Property: Assert  
 Status: Falsified

## Counterexample

The Counterexample section lists the time step and corresponding time at which the counterexample falsified the property. This section also lists the values of the signals at that time step.

## Counterexample

Time	0	0.01	0.02-0.04
Step	1	2	3-5
InputData.Actual_speed	0	0	0
InputData.Switches.enable	1	1	0
InputData.Switches.brake	0	0	1
InputData.Switches.set	1	0	0
InputData.Switches.setIncDec.inc	1	1	0
InputData.Switches.setIncDec.dec	0	0	0

### Simulink Design Verifier Log Files

Every time you analyze a model, the Simulink Design Verifier software creates a log file. To view the log file, click **View Log** in the Simulink Design Verifier log window.

The log file contains a list of the analysis results for each object in the model. The content of the log file corresponds to the analysis results displayed in the log window during the analysis.

```
1
2 12-Jun-2013 11:24:50
3 Starting test generation for model 'sldvdemo_cruise_control'
4 Compiling model... done
5 Translating model... done
6 'sldvdemo_cruise_control' is compatible with Simulink Design Verifier.
7
8 Generating tests...
9
10 SATISFIED
11 Controller/Logical Operator
12 Logic: MCDC expression for output with input port 3 T
13 Analysis Time = 00:00:01
14
15 SATISFIED
16 Controller/Logical Operator
17 Logic: MCDC expression for output with input port 2 T
18 Analysis Time = 00:00:01
19
20 SATISFIED
21 Controller/Logical Operator
22 Logic: MCDC expression for output with input port 1 T
23 Analysis Time = 00:00:01
24
25 SATISFIED
26 Controller/Logical Operator2
27 Logic: MCDC expression for output with input port 1 T
28 Analysis Time = 00:00:01
29
30 SATISFIED
31 Controller/PI Controller
32 enable logical value T
33 Analysis Time = 00:00:01
```

## Review Analysis Results

### In this section...

“View Active Results” on page 13-52

“Load Previous Results” on page 13-52

“Explore Results” on page 13-52

### View Active Results

After analysis is complete, the Simulink Design Verifier Results Summary window opens, showing different ways you can use the results. See “Explore Results” on page 13-52.

If you close the Results Summary window so you can fix the cause of any analysis errors in your model, you might need to review the analysis results again. If you have not closed your model since you ran the analysis, you can reopen the latest analysis results for your model. In the Simulink Editor, select **Analysis > Design Verifier > Results > Active**. The Results Summary window reopens with the latest analysis results for your model.

You can also view Simulink Design Verifier analysis results in the Model Explorer.

### Load Previous Results

If you want to review results of a previous analysis on a model, you can load these results from the analysis data file. In the Simulink Editor, select **Analysis > Design Verifier > Results > Load**. Browse and select the data file that corresponds to the analysis you want to review.

For more information on analysis data files, see “Simulink Design Verifier Data Files”.

If you load analysis results for a model from a data file that was generated with a previous version of that model, you might see unexpected effects. To avoid inconsistencies between your model and analysis results data, when you load results for a model, choose a data file that contains results from the same version of that model.

### Explore Results

With active or previous analysis results loaded in the Model Explorer or Results Summary window, you can perform the following tasks.

<b>Task</b>	<b>For more information</b>
Highlight the analysis results on the model.	“Highlighted Results on the Model” on page 13-2
Generate a detailed analysis report.	“Simulink Design Verifier Reports” on page 13-27
Create the harness model, or if the harness model already exists, open it.  You will not be able to create the harness model if: <ul style="list-style-type: none"><li>• No design error objectives were falsified</li><li>• No test cases were generated</li><li>• No counterexamples were created</li></ul>	“Simulink Design Verifier Harness Models” on page 13-16
View the data file.	“Simulink Design Verifier Data Files” on page 13-9
View the log file.	“Simulink Design Verifier Log Files” on page 13-50



# Analyzing Large Models and Improving Performance

---

- “Sources of Model Complexity” on page 14-2
- “Analyze a Large Model” on page 14-3
- “Increase Allocated Memory for Analysis Report Generation” on page 14-8
- “Manage Model Data to Simplify the Analysis” on page 14-9
- “Partition Model Inputs for Incremental Test Generation” on page 14-13
- “Bottom-Up Approach to Model Analysis” on page 14-15
- “Extract Subsystems for Analysis” on page 14-16
- “Logical Operations” on page 14-23
- “Models with Large Verification State Space” on page 14-24
- “Counters and Timers” on page 14-25
- “Prove Properties in Large Models” on page 14-27

## Sources of Model Complexity

Some characteristics of Simulink models can cause problems during a Simulink Design Verifier analysis in the following ways:

- Complexity of model inputs due to:
  - Large number of inputs (The number of inputs can vary, depending on the individual model.)
  - Types of inputs (floating-point values, for example)
  - The way the inputs affect the model state and the objectives of the analysis
- Number of possible simulation paths through a model
- Portions of the model that cannot be reached
- Large counters in the model

The topics in “Complexity Reduction” describe techniques designed to reduce the impact of this complexity and achieve the best performance from the Simulink Design Verifier software.

Most of these techniques focus on test generation for large models. However, you can use many of them to detect design errors or prove the properties of a large model and generate counterexamples when a property is disproved. In addition, “Prove Properties in Large Models” on page 14-27 describes specific techniques for proving properties in a large model.



# Analyze a Large Model

## In this section...

- “Types of Large Model Problems” on page 14-3
- “Summarize Model Hierarchy and Compatibility” on page 14-4
- “Use the Default Parameter Values” on page 14-4
- “Modify the Analysis Parameters” on page 14-6
- “Use the Large Model Optimization” on page 14-6
- “Stop the Analysis Before Completion” on page 14-6

## Types of Large Model Problems

The Simulink Design Verifier software may encounter some of these problems when analyzing a large model:

- Unsatisfiable objectives — The software proved there are no test cases that exercise these test objectives, and did not generate any test cases.
- Undecided objectives — The software was not able to satisfy or falsify these objectives.
- Objectives with errors — This problem usually occurs when a model component uses nonlinear arithmetic, which can affect a test objective.
- Cannot complete the analysis in the time allotted — This problem may indicate an area of your model where the software encountered problems, or you may need to increase value of the **Maximum analysis time** parameter.
- Analysis hangs — If the number of objectives processed remains constant for a considerable length of time, the software has likely encountered complexity between the model and its objectives.
- Does not achieve a high percentage of model coverage — When you run the test cases on the harness model, the percentage of model coverage is insufficient for your design.

The next few sections describe the initial steps to take when analyzing a large model. Although these steps address test generation, you can use a similar approach when detecting design errors or proving properties in a model.

## Summarize Model Hierarchy and Compatibility

You can use the Test Generation Advisor to summarize test generation compatibility, condition and decision objectives, and dead logic for the model and model components.

The Test Generation Advisor performs a high-level analysis and fast dead logic detection. You can use the results to better understand your model, particularly large models, complex models, or models for which you are uncertain of their compatibility with Simulink Design Verifier. For example, you can:

- Identify incompatibilities with test case generation.
- Identify complex components that might be time-consuming to analyze.
- Determine instances of dead logic.
- Get a summary of the component hierarchy.
- Get recommended test generation parameters.

You can access the Test Generation Advisor from the menu bar by clicking **Analysis > Design Verifier > Generate Tests > Advisor**. For more information see “Select Components for Test Case Generation”.

## Use the Default Parameter Values

When you generate test cases, you should generally begin by analyzing the model using the Simulink Design Verifier default parameter values:

- 1 Check to see if your model is compatible with the Simulink Design Verifier software, as described in “Check Model Compatibility”.
- 2 Using the default parameter values, analyze the model. The following table lists the default values for parameters in the Configuration Parameters dialog box that you might change when analyzing large models.

Parameter	Default Value	Description
<b>Maximum analysis time (s)</b>	300 (seconds)	If the analysis does not finish within the specified time, the analysis times out and terminates.
<b>Test suite optimization</b>	CombinedObjective (Nonlinear extended)	Generates test cases that address more than one test objective, as with the CombinedObjectives option, but

Parameter	Default Value	Description
		with improved support for nonlinear arithmetic. Each test case tends to include many time steps.
<b>Model coverage objectives</b>	Condition Decision	Generates test cases that achieve condition and decision coverage.

- 3 Review the following information in the Simulink Design Verifier log window while the analysis runs:
  - Number of objectives processed — How many objectives were processed? Did the analysis hang after processing a certain number of objectives? The answers to these questions might give you a clue about where a problem might lie.
  - Number of objectives satisfied/Number of objectives falsified — Which objectives were falsified?
  - Time elapsed — Did the analysis time out, or did it finish within the specified maximum analysis time?
- 4 When the analysis completes, you can highlight the results in the model and individually review the analysis of each model object, as described in “Highlighted Results on the Model”. You can also generate and review the Simulink Design Verifier HTML report. This report contains links to the model elements for satisfied and falsified objectives so you can see what portions of the model might have problems. For more information, see “Simulink Design Verifier Reports”.
- 5 For a test-generation analysis, if all the test objectives have been satisfied, run the test cases on the harness model to determine model coverage.

If model coverage is enough for your design, you do not need to do anything else. If the coverage is insufficient, take additional steps to improve the analysis performance, as described in the following sections.

---

**Note:** A large percentage of falsified objectives and poor model coverage often indicate that you need to change model parameter values to get complete coverage. This can occur when you have tunable parameters in Constant blocks that are connected to enabled subsystems or to the trigger inputs of Switch blocks. In these situations, configure Simulink Design Verifier parameter support as described in the example “Specify Parameter Constraint Values for Full Coverage”.

---

### Modify the Analysis Parameters

If the analysis satisfied most but not all of the objectives, try the following steps:

- 1 Increase the **Maximum analysis time** parameter. This gives the analysis more time to satisfy all the objectives.
- 2 Set the **Model coverage objectives** parameter to **Decision**. Selecting this option generates only test cases that achieve decision coverage. These test cases are a subset of the **MCDC** option.
- 3 Rerun the analysis and review the report.

If the results are still not satisfactory, try the techniques described in the following sections.

### Use the Large Model Optimization

Set the **Test suite optimization** parameter to **LargeModel** or **LargeModel (Nonlinear Extended)**, and rerun the Simulink Design Verifier analysis.

The large model optimization strategies are designed for large, complex models. The **LargeModel (Nonlinear Extended)** strategy includes improved support for nonlinear arithmetic. These two strategies may or may not improve the results of your analysis enough to fully test your design.

If you have outstanding objectives you want the software to generate, continue with the following techniques.

### Stop the Analysis Before Completion

Watch the **Objectives processed** value in the log window. If about 50 percent of the **Maximum analysis time** parameter has elapsed and this value does not increase, the model analysis may have trouble processing certain objectives. If the analysis does not progress, take the following steps:

- 1 Click **Stop** in the log window.

A dialog box appears, informing you that the analysis was aborted and asking you if you still want to produce results.

- 2 Click **Yes** to save the results of the analysis so far.

The log window lists the following options, depending on which analysis mode you ran:

- **Highlight analysis results on model**
  - **Generate detailed analysis report**
  - **Create harness model**
  - **Simulate tests and produce a model coverage report**
- 3** Click **Generate detailed analysis report**.
  - 4** In the HTML report, review the following sections to identify the model elements that are causing problems:
    - **Objectives Undecided when the Analysis was Stopped**
    - **Objectives Producing Errors**
  - 5** Review the model elements that have undecided objectives or objectives with errors to see if any of the following problems are present. Consult the respective documentation for specific techniques to improve the analysis.

<b>Problem in your model</b>	<b>More information</b>
Floating-point inputs	“Manage Model Data to Simplify the Analysis” on page 14-9
Nonlinear operations	<ul style="list-style-type: none"> <li>• “Bottom-Up Approach to Model Analysis” on page 14-15</li> <li>• “Logical Operations” on page 14-23</li> </ul>
Large state spaces	“Models with Large Verification State Space” on page 14-24
Large timers and time delays	“Counters and Timers” on page 14-25

### **Increase Allocated Memory for Analysis Report Generation**

When you analyze a model with a large root-level input signal count, you may encounter an insufficient memory error when the Simulink Design Verifier software is generating the report.

When this occurs, you need to increase the amount of memory the Sun™ Java® Virtual Machine (JVM™) software can allocate. For steps on how to increase this memory, see “Increase the MATLAB JVM Memory Allocation Limit” in the MATLAB Report Generator™ documentation.

## Manage Model Data to Simplify the Analysis

### In this section...

“Simplify Data Types” on page 14-9

“Constrain Data” on page 14-9

### Simplify Data Types

One way to simplify your model is to use for the designated signal data type a data type requiring the least amount of space for the expected data. For example, do not use an `int` data type for Boolean data, because only one bit is required for Boolean data.


In another example, suppose you have a Sum block with two inputs that are always integers between  $-10$  and  $10$ . Set the **Output data type** parameter to `int8`, rather than `int32` or `double`.

To display the signal data types in the model window, select **Display > Signals & Ports > Port Data Types**.

### Constrain Data

Another effective technique for reducing complexity is to restrict the inputs to a set of representative values or, ideally, a single constant value. This process, called *discretization*, treats the input as if it were an enumeration. Discretization allows you to handle nonlinear arithmetic from multiplication and division in the simplest way possible.

The following model has a Product block feeding a Saturation block.



The Simulink Design Verifier software generates errors when attempting to satisfy the upper and lower limits of the Saturation block, because the software does not support nonlinear arithmetic. To work around these errors, restrict one of the inputs to a set of discrete values.


Identify discrete values that are required to satisfy your testing needs. For example, you may have an input for model speed, and your design contains paths of execution that are conditioned on speed above or below thresholds of 80, 150, 600, and 8000 RPM. For an effective analysis, constrain speed values to be 50, 100, 200, 1000, 5000, or 10000 RPM so that every threshold can be either active or inactive.

If you need to use more than two or three values, consider specifying the constrained values using an expression like

```
num2cell(minval:increment:maxval)
```

Using the previous example model, restrict the second input ( $y$ ) to be either 1, 2, 5, or 10 using the Test Condition block as shown in the following model. The Simulink Design Verifier software produces test cases for all inputs.





You can also constrain signals that are intermediate or output values of the model. Constraining such signals makes it easier to work around multiplication or division inside lower level subsystems that do not depend on model inputs.

---


**Note:** Discretization is best limited to a small number of inputs (less than 10). If your model requires discretization of many inputs, try to achieve model coverage through successive simulations, as described in “Partition Model Inputs for Incremental Test Generation” on page 14-13.

---

Test Condition blocks do not need to be placed exactly on the inputs. In deciding where to place the constraints in your model, consider the following guidelines:

- Favor constraints on the input values because the software can process inputs easier.
- If you need to place constraints on both the input and the output, for example, to avoid nonlinear arithmetic, one of the constraints should be a range such as [minval maxval]. The software first tests the values at both ends of the range and can return a test case, even if the underlying calculations are nonlinear.
- Make sure that constraints at corresponding input and output points are not contradictory. Do not constrain the output signals to values that are not achievable because of the constraints on the input values.
- Avoid creating constraints that contradict the model. Such contradictions occur when a constraint can never be satisfied because it contradicts some aspect of the model or another constraint. Analyzing contradictory models can cause the Simulink Design Verifier software to hang.

The next model is a simple example of a contradictory model. The second input to the Multiply block is the constant 1, but the Test Condition block constrains it to a value of 2, 5, or 10. The analysis cannot achieve all the test objectives in this model.



- When you work with large models that have many multiplication and division operations, you may find it easier to add constraints to all of the floating-point inputs rather than to identify the precise set of inputs that require constraints.

## Partition Model Inputs for Incremental Test Generation

As described in “Constrain Data” on page 14-9, you can constrain the values of model inputs using the Simulink Design Verifier Test Condition block.

Like other Simulink parameters, constraint values can be shared across several blocks by referencing a common workspace variable; you can initialize constraint values using MATLAB commands. If you have several inputs related to speed, such as desired speed, measured speed, and average speed, you might choose to constrain all of them to the same set of values.

As an advanced technique for experienced MATLAB programmers, you can use parameterized constraints and successive runs of the Simulink Design Verifier software to implement an incremental test-generation technique:

- 1 Partition model inputs so that some are held constant, some are constrained to sets of constants using the Test Condition block, and some can have any value.
- 2 Generate test cases and run those test cases to collect model coverage.
- 3 Choose new values and partition the inputs with these new values.
- 4 Generate test cases for missing coverage using the `sldvgencov` function and the current test coverage.

---

**Note:** To view an example of extending an existing test suite to achieve missing model coverage, enter the following at the command prompt in the MATLAB Command Window:


```
showdemo('sldvdemo_incremental_test_generation')
```

---

- 5 Repeat steps 3 and 4 until you have achieved the desired coverage.

Partition the model inputs that enable further simplification when an analysis runs. Consider the following model, which has three mutually independent enabled subsystems:

- Normal Mode
- Shutdown Mode
- Failure Mode



You can incrementally generate test cases for each subsystem by constraining the first input to a constant value before running an analysis. In this way, as you create test cases for each subsystem, the software ignores the complexity of the other two subsystems.

## Bottom-Up Approach to Model Analysis

Simulink Design Verifier software works most effectively at analyzing large models using a bottom-up approach. In this approach, the software analyzes smaller model components first, which can be faster than using the `Large model` test suite optimization.

The bottom-up approach offers several advantages:

- It allows you to solve the problems that slow down error detection, test generation, or property proving in a controlled environment.
- Solving problems with small model components before analyzing the model as a whole is more efficient, especially if you have unreachable components in your model that you can only discover in the context of the model.
- You can iterate more quickly—find a problem and fix it, find another problem and fix it, and so on.
- If one model component has a problem—for example, a component is unreachable in simulation—that can prevent the software from generating tests for *all* the objectives in a large model.

Try this workflow with your large model:

- 1** Break down the model into components of 100–1000 objectives each. Use the `sldvextract` function to extract components into a new model for analysis purposes.
- 2** Analyze the individual components, starting with the lowest level subsystems.
- 3** Fix any problems by adding constraints or specifying block replacements.
- 4** After you analyze the smaller components, reapply the required constraints and substitutions to the original model and analyze the full model.

When you finish a bottom-up analysis, you should have a top-level model that the Simulink Design Verifier software can analyze quickly.

## Extract Subsystems for Analysis

In this section...
“Overview of Subsystem Extraction” on page 14-16
“sldvextract Function” on page 14-16
“Structure of the Extracted Model” on page 14-17
“Analyze Subsystems That Read from Global Data Storage” on page 14-17
“Analyze Function-Call Subsystems” on page 14-20

### Overview of Subsystem Extraction

If you have a large model that slows down your analysis or has unreachable objectives, you may want to analyze atomic subsystems or Stateflow atomic subcharts using the Simulink Design Verifier software. This technique allows you to implement a bottom-up approach to analyzing a large model, as described in “Bottom-Up Approach to Model Analysis” on page 14-15.

When you analyze a subsystem or atomic subchart, the software:

- Extracts the subsystem or subchart into a new model.
- If required, adds blocks to the newly created model that replicate the execution context of the subsystem or subchart within its parent model.
- Analyzes the extracted model and produces results.

---

**Note:** The Simulink Design Verifier software can only analyze atomic subsystems and atomic subcharts.

For more information about analyzing subsystems, see “Analyze a Subsystem” on page 1-26.

For more information about analyzing atomic subcharts, see “Analyze a Stateflow Atomic Subchart” on page 1-28.

---

### sldvextract Function

The `sldvextract` function allows you to extract subsystems and atomic subcharts for component verification. By extracting the subsystem or atomic subchart, you can

verify the component in isolation from the rest of the system, allowing you to test the component algorithm. For more information, see “What Is Component Verification?” and “Functions for Component Verification”.

## Structure of the Extracted Model

When you analyze a subsystem or atomic subchart, the Simulink Design Verifier software creates a new model that contains the subsystem or atomic subchart, and any input and output ports that correspond to the ports connected to the original subsystem. The software assigns the following properties to the ports in the new model, as determined by compiling the original model:

- Data types
- Sample rates
- Signal dimensions

The software names the new model *subsystem\_name*, where *subsystem\_name* is the name of the subsystem.

The next sections provide examples of how the Simulink Design Verifier software extracts and analyzes subsystems.

## Analyze Subsystems That Read from Global Data Storage

A *data store* is a repository to which you can write data, and from which you can read data, without having to connect an input or output signal directly to the data store.

You create a data store using a Data Store Memory block or a `Simulink.Signal` object. The Data Store Memory block or `Simulink.Signal` object represents the data store and specifies its properties. Every data store must have a unique name.

When you analyze a subsystem that reads data from a data store that is accessed outside the subsystem, the analysis:

- Adds a Data Store Memory block to the new model.
- Adds an input port that writes to the data store. Since the input writes to the data store, the data can have any values (within the specified data type) for the purpose of the Simulink Design Verifier analysis.

If the data store specifies minimum and maximum values, those values are assigned to the new input port.

The following example analyzes a subsystem in the `sl_subsys_fcncall8` example model:

- 1 Open the `sl_subsys_fcncall8` example model:

```
sl_subsys_fcncall8
```


This model defines a data store A, from which the atomic subsystem Reader reads data using a Data Store Read block.

- 2 Right-click the Reader subsystem and select **Design Verifier > Generate Tests for Subsystem**.

The Simulink Design Verifier log window shows that the software extracts the subsystem into a new model named `Reader`, analyzes the extracted model, and offers you the choice of which results to produce.

- 3 Open the new `Reader` model that the software created in `<current_folder>\sldv_output\Reader`.





The new Inport block A writes into the data store, which is used by the subsystem Reader in the new model.

### Analyze Function-Call Subsystems

A *function-call subsystem* is a triggered subsystem whose execution is determined by logic internal to a C MEX S-function instead of by the value of a signal. Function-call subsystems are always atomic.

---

**Note:** For more information, see “Function-Call Subsystems and S-Functions” in the Simulink documentation.

---

When you analyze a model with a function-call subsystem, the Simulink Design Verifier software creates a new model with an Inport block that mimics the trigger and a copy of the subsystem. The software then analyzes the new model.

The following example analyzes a function-call subsystem in the `s1_subsys_fcncall2` model:


- 1 Open the `s1_subsys_fcncall2` example model:

`s1_subsys_fcncall2`

This model contains a Stateflow chart named Chart that triggers the function-call subsystem `f`.


- 2 Right-click the `f` subsystem and select **Design Verifier > Generate Tests for Subsystem**.

The software extracts the subsystem into a new model named `f`, analyzes the extracted model, and produces results.



- 3 Open the `f` model that the software created in `<current_folder>\sldv_output\f`.

The Inport block and the new subsystem block mimic the trigger for the function-call subsystem `f` in the new `f` model.



## Logical Operations

If you have a Simulink model with both logical and arithmetic operations, consider analyzing only the logical operations.

The Simulink Design Verifier software does not support nonlinear arithmetic of floating-point numbers, as occurs with multiplication or division, unless one of the multiply operands or the divisor is a constant.

To simplify models that contain integers or floating-point numbers, the software maps the model computations into expressions of Boolean variables. For example, the software might represent an eight-bit number as a set of eight Boolean values, with one for each digit. It might represent a bit-wise **OR** operation of two eight-bit integers as eight separate logical **OR** operations.

Mapping problems of one data type into Boolean variables is complex, and this complexity increases when the software performs such mapping. The software handles models with predominantly logical signals more efficiently than it does those with large integer or floating-point signals.

---

**Note:** Simulink Design Verifier software can handle floating-point inputs when their values impact the design through linear inequalities such as  $x < y$  or  $a > 0$ .

In addition, input complexity can result from certain cast operations. For example, casting a `double` to an `int8` can introduce a nonlinearity in certain situations.

---

## Models with Large Verification State Space

Persistent design variables (variables that are assigned in one time step and used in a later time step during simulation) affect the complexity of analysis in much the same way as input complexity. You can use one or more of the following techniques to simplify the complexity of the state space you want to search:

- Apply constraints to input signals that are delayed.
- Constrain the inputs to states that are contained within conditionally executed subsystems.
- Limit the number of test case steps by setting the **Maximum test case step** parameter to 20.
- Increase the sample time for part or all of the model. (This procedure is similar to reducing timer thresholds, as described in “Counters and Timers” on page 14-25.) A test case that you generate at a lower sample rate often has similarities to the test case with a high sample rate that you need to achieve an objective.
- Use tight variable types where ever possible. For example, if a flag with values of 0 or 1 only is defined as a `double`, restrict the type to `Boolean`.

States that are computed from previous state values present a special challenge. For example, if you want to restrict the integrator value in a PID controller, you can only use a set of values that includes all reachable values from the initial value. Otherwise, the input must be forced to 0. Neither of these limitations is practical and would probably make the analysis less complete.

Alternatively, you can use existing simulation data to help satisfy your testing needs. If you have existing test data, run it on your model and collect model coverage. For an example of extending an existing test suite to achieve missing model coverage, see [Extending an Existing Test Suite](#).

## Counters and Timers

Simulink Design Verifier analysis searches through sequences of states to find input values that drive the analysis to reach a state that satisfies an objective. Each counter value or timer step corresponds to a different state, so the presence of long timers or counters can dramatically increase the size of the state representation. Since analysis complexity depends on the size of the state representation, you must give special consideration to counters and timers in your model to avoid overcomplicating Simulink Design Verifier analysis.

---

**Note:** For the purposes of Simulink Design Verifier analysis, the term *configuration* refers to a set of values for all the persistent information in your model.

---

The search process investigates all configurations that can be reached in a single timer step before considering any of the configurations that can be reached in two timer steps. Likewise, the search investigates all configurations that can be reached in two timer steps before it considers any configuration that requires three or more timer steps, and so on. The number of timer steps required to exhaust the counter directly affects the number of states that the analysis needs to search. Models that contain time delays, such as countdown timers, complicate the analysis by forcing the search to span a large number of states.

You may see similar effects when systems use extensive averaging and filtering to delay the response to a change in inputs. Any aspect of the design that delays the response causes the test sequences to contain more timer steps, resulting in longer test cases that are more difficult to identify.

Some basic techniques you can use to improve analysis performance in models with counters or timers include the following:

- Choose very small values for time delays. A system with a logical error when a time delay is set to 2000 steps usually demonstrates that error if the time delay is changed to 2 steps. If your system has several delays, choose small but unique values for each of them so that your delays are progressively satisfied.
- Make the initial values of counters and timers parameter values that the Simulink Design Verifier software can modify. The software finds initial values that allow shorter test cases to exceed thresholds. For more information, see “Parameter Constraint Values”.

- Choose higher frequency cutoffs for filters and fewer samples to average to minimize filtering delays.

Some more advanced techniques you can use to improve analysis performance in models with counters or timers include the following:

- Use `sldvtimer` to identify timer patterns that can be optimized for Simulink Design Verifier test generation.
- Use an existing test case or set of test cases that exhausts the counter or timer, and extend those test cases to create a full test suite. For more information, see [Defining and Extending Existing Test Cases](#).



## Prove Properties in Large Models

Property proving uses the same underlying techniques as design error detection and test generation and suffers from the same performance limitations. However, unlike design error detection or test generation, you often cannot simplify the problem without compromising the validity of the results.

You can quickly prove simple proof objectives that are not affected by model dynamics. However, a thorough proof requires that the Simulink Design Verifier software search through all reachable configurations of your model—even the ones that are reached only after long time delays. The computation time and memory required to search a model completely often make an exhaustive proof impractical.

There are two techniques you can use to improve the performance of property proving in a large model:

### In this section...

“Find Property Violations While Designing Your Model” on page 14-27

“Combine Proving Properties and Finding Proof Violations” on page 14-28

## Find Property Violations While Designing Your Model

Simulink Design Verifier software offers a strategy that quickly identifies property violations in larger, more complicated models. While designing your model, analyze your model using this strategy so that you can fix any property violations before finalizing your design.

To identify property violations of a model, on the **Design Verifier > Property Proving** pane of the Configuration Parameters dialog box, specify the value of the **Strategy** parameter as **FindViolation**. When you use this strategy, the **Maximum violation steps** parameter becomes active so that you can specify an upper bound for the number of time steps in the search.

When analyze the model, the software searches only for property violations within the specified number of time steps. By identifying and fixing the property violations first, you improve the performance of a property-proving analysis that uses the **Prove** strategy.

If a violation is not detected, it is impossible to violate the property with any input sequence having fewer time steps than the specified limit. However, you cannot prove

that the property is true because there might be a counterexample within more time steps than the specified limit.

## Combine Proving Properties and Finding Proof Violations

Use the following technique for proving properties in large model. This technique combines proving and searching for violations:

- 1** On the **Design Verifier > Property Proving** pane, set the **Strategy** parameter to **Prove**.
- 2** On the **Design Verifier** pane, use a relatively short value for the **Maximum analysis time** parameter, such as 5–10 minutes. If trivial counterexamples exist — or if your properties do not depend on model dynamics—the analysis should complete in that amount of time.
- 3** Change the **Strategy** parameter to **FindViolation**, and choose a small bound for the **Maximum violation steps** parameter, such as 4, 5, or 6. If your properties have simple counterexamples, the software should discover them.
- 4** If you do not find any violations with a small bound, increase the bound and look for longer counterexamples.
  - a** Increase the bound in several increments, and observe the processing time and memory consumption. System resources might limit the length of violation that can be searched.
  - b** In addition, consider the dynamics of your model and the number of time steps required to transition between an arbitrary pair of configurations. If you choose too large a bound, the violation search can be more complex than the unbounded proof.
- 5** If you can run violation searches with relatively large bounds, e.g., 30–50 time steps, switch back to the **Prove** strategy, and use a longer time limit, such as several hours.

# Simulink Design Verifier Configuration Parameters

---

- “Simulink Design Verifier Options” on page 15-2
- “Design Verifier Pane” on page 15-11
- “Design Verifier Pane: Block Replacements” on page 15-18
- “Design Verifier Pane: Parameters” on page 15-21
- “Design Verifier Pane: Test Generation” on page 15-30
- “Design Verifier Pane: Design Error Detection” on page 15-45
- “Design Verifier Pane: Property Proving” on page 15-51
- “Design Verifier Pane: Results” on page 15-56
- “Design Verifier Pane: Report” on page 15-67

## Simulink Design Verifier Options

### In this section...

“Options in Configuration Parameters Dialog Box” on page 15-2

“Design Verification Options Objects” on page 15-2

“Command-Line Parameters for Design Verification Options” on page 15-2

### Options in Configuration Parameters Dialog Box

The Simulink Design Verifier software provides numerous options in the Configuration Parameters dialog box that control its behavior when analyzing models. To view the options related to Simulink Design Verifier, in the model window, select **Analysis > Design Verifier > Options**. The Configuration Parameters dialog box opens; the **Design Verifier** panes are listed in the **Select** tree on the left-hand side.

By default, Simulink Design Verifier options do not appear in a model's Configuration Parameters dialog box. In the Simulink Editor, when you select **Analysis > Design Verifier > Options**, Simulink Design Verifier initially associates its default options with that model. After you save the model, you can access Simulink Design Verifier options directly from the Configuration Parameters dialog box or from the Model Explorer.

See “Configuration Parameters Dialog Box Overview” for more information about working with this interface.

### Design Verification Options Objects

You can use the `sldvoptions` function to specify Simulink Design Verifier options at the command line.

To view in the MATLAB Command Window the design verification options associated with a Simulink model, use the following syntax:

```
opts = sldvoptions('model_name');  
get(opts)
```

### Command-Line Parameters for Design Verification Options

The following table lists parameters that you can use to configure the behavior of the Simulink Design Verifier software. Use the `get_param` and `set_param` functions to retrieve and specify values for these parameters programmatically.

For each parameter listed in the table, the **Location** column indicates where you can set its value in the Configuration Parameters dialog box. The **Values** column shows the type of value required, the possible values (separated with a vertical line), and the default value (enclosed in braces).

Parameter	Location	Values
DVAbsoluteTolerance	Set by the <b>Floating point absolute tolerance</b> parameter on the <b>Design Verifier &gt; Test Generation</b> pane.	double { '1.0e-05' }
DVAssertions	Set by the <b>Assertion blocks</b> parameter on the <b>Design Verifier &gt; Property Proving</b> pane.	'EnableAll'   'DisableAll'   {'UseLocalSettings'}
DVAutomaticStubbing	Set by the <b>Automatic stubbing of unsupported blocks and functions</b> parameter on the <b>Design Verifier</b> pane.	{'on'}   'off'
DVBlockReplacement	Set by the <b>Apply block replacements</b> parameter on the <b>Design Verifier &gt; Block Replacements</b> pane.	'on'   {'off'}
DVBlockReplacement-ModelFileName	Set by the <b>File path of the output model</b> parameter on the <b>Design Verifier &gt; Block Replacements</b> pane.	string { '\$modelName\$_replacement' }
DVBlockReplacement-RulesList	Set by the <b>List of block replacement rules</b> parameter on the <b>Design Verifier &gt; Block Replacements</b> pane.	string { '<FactoryDefaultRules>' }
DVCoverageDataFile	Set by the <b>Coverage data file</b> parameter on the <b>Design Verifier &gt; Test Generation</b> pane.	string { '' }

Parameter	Location	Values
DVCovFilter	Set by the <b>Ignore objectives based on filter</b> parameter on the <b>Design Verifier &gt; Test Generation</b> pane.	'on'   {'off'}
DVCovFilterFileName	Set by the <b>Coverage filter file</b> parameter on the <b>Design Verifier &gt; Test Generation</b> pane.	string { '' }
DVDataFileName	Set by the <b>Data file name</b> parameter on the <b>Design Verifier &gt; Results</b> pane.	string { '\$modelName \$_sldvdata' }
DVDesignMinMaxCheck	Set by the <b>Check specified intermediate minimum and maximum values</b> parameter on the <b>Design Verifier &gt; Design Error Detection</b> pane.	'on'   {'off'}
DVDesignMinMax-Constraints	Set by the <b>Use specified input minimum and maximum values</b> parameter on the <b>Design Verifier</b> pane.	{ 'on' }   'off'
DVDetectDeadLogic	Set by <b>Dead logic</b> on the <b>Design Verifier &gt; Design Error Detection</b> pane.	'on'   {'off'}
DVDetectDivisionByZero	Set by the <b>Division by zero</b> parameter on the <b>Design Verifier &gt; Design Error Detection</b> pane.	{ 'on' }   'off'
DVDetectIntegerOverflow	Set by the <b>Integer overflow</b> parameter on the <b>Design Verifier &gt; Design Error Detection</b> pane.	{ 'on' }   'off'

Parameter	Location	Values
DVDetectOutOfBounds	Set by the <b>Out of bound array access</b> parameter on the <b>Design Verifier &gt; Design Error Detection</b> pane.	'on'   {'off'}
DVDisplayReport	Set by the <b>Display report</b> parameter on the <b>Design Verifier &gt; Report</b> pane.	{'on'}   'off'
DVDisplayResultsOnModel	Set by the <b>Display results of the analysis on the model</b> parameter on the <b>Design Verifier &gt; Results</b> pane.	'on'   {'off'}
DVDisplayUnsatisfiable-Objectives	Set by the <b>Display unsatisfiable test objectives</b> parameter on the <b>Design Verifier</b> pane.	'on'   {'off'}
DVExtendExistingTests	Set by the <b>Extend existing test cases</b> parameter on the <b>Design Verifier &gt; Test Generation</b> pane.	'on'   {'off'}
DVExistingTestFile	Set by the <b>Data file</b> parameter on the <b>Design Verifier &gt; Test Generation</b> pane.	string { '' }
DVHarnessModelFileName	Set by the <b>Harness model file name</b> parameter on the <b>Design Verifier &gt; Results</b> pane.	string { '\$modelName \$ _harness' }
DVIgnoreCovSatisfied	Set by the <b>Ignore objectives satisfied in existing coverage data</b> parameter on the <b>Design Verifier &gt; Test Generation</b> pane.	'on'   {'off'}

Parameter	Location	Values
DVIgnoreExistTest-Satisfied	Set by the <b>Ignore objectives satisfied by existing test cases</b> parameter on the <b>Design Verifier &gt; Test Generation</b> pane.	{'on'}   'off'
DVIncludeRelationalBound	Set by the <b>Include relational boundary objectives</b> parameter on the <b>Design Verifier &gt; Test Generation</b> pane.	{'on'}   'off'
DVMakeOutputFilesUnique	Set by the <b>Make output file names unique by adding a suffix</b> check box on the <b>Design Verifier</b> pane.	{'on'}   'off'
DVMaxProcessTime	Set by the <b>Maximum analysis time</b> parameter on the <b>Design Verifier</b> pane.	double {'300'}
DVMaxTestCaseSteps	Set by the <b>Maximum test case steps</b> parameter on the <b>Design Verifier &gt; Test Generation</b> pane.	int32 {'500'}
DVMaxViolationSteps	Set by the <b>Maximum violation steps</b> parameter on the <b>Design Verifier &gt; Property Proving</b> pane.	int32 {'20'}
DVMode	Set by the <b>Mode</b> parameter on the <b>Design Verifier</b> pane.	{'TestGeneration'}   'DesignErrorDetection'   'PropertyProving'
DVModelCoverage-Objectives	Set by the <b>Model coverage objectives</b> parameter on the <b>Design Verifier &gt; Test Generation</b> pane.	'None'   'Decision'   {'ConditionDecision'}   'MCDC'



Parameter	Location	Values
DVModelReferenceHarness	Set by the <b>Reference input model in generated harness</b> parameter on the <b>Design Verifier &gt; Results</b> pane of the Configuration Parameters dialog box.	'on'   {'off'}
DVOutputDir	Set by <b>Output directory</b> on the <b>Design Verifier</b> pane.	string {'sldv_output/ \$ModelName\$'}
DVParameterConstraints	Set by <b>Constraint</b> column in Parameter Configuration Table on the <b>Design Verifier &gt; Parameters</b> pane.	double array {[ ]}
DVParameterNames	Set by <b>Name</b> column in Parameter Configuration Table on the <b>Design Verifier &gt; Parameters</b> pane.	double array {[ ]}
DVParameterUseInAnalysis	Set by <b>Use</b> column in Parameter Configuration Table on the <b>Design Verifier &gt; Parameters</b> pane.	cell array {[ ]}
DVParameters	Set by <b>Enable parameter configuration</b> on the <b>Design Verifier &gt; Parameters</b> pane.	'on'   {'off'}
DVParametersConfigFileName	Set by <b>Parameter configuration file</b> on the <b>Design Verifier &gt; Parameters</b> pane.  This parameter is disabled when DVParametersUseConfig is set to 'on'.	string { 'sldv_params_template.m' }

Parameter	Location	Values
DVParametersUseConfig	Set by <b>Use parameter configuration table</b> on the <b>Design Verifier &gt; Parameters</b> pane.  When set to 'on', this parameter disables DVParametersConfigFileNa	'on'   {'off'}
DVProofAssumptions	Set by the <b>Proof assumptions</b> parameter on the <b>Design Verifier &gt; Property Proving</b> pane.	'EnableAll'   'DisableAll'   {'UseLocalSettings'}
DVProvingStrategy	Set by the <b>Strategy</b> parameter on the <b>Design Verifier &gt; Property Proving</b> pane.	'FindViolation'   {'Prove'}   'ProveWithViolationDetection'
DVRandomizeNoEffectData	Set by the <b>Randomize data that do not affect the outcome</b> parameter on the <b>Design Verifier &gt; Results</b> pane.	'on'   {'off'}
DVRelativeTolerance	Set by the <b>Floating point relative tolerance</b> parameter on the <b>Design Verifier &gt; Test Generation</b> pane.	double {'0.01'}
DVReportFileName	Set by the <b>Report file name</b> parameter on the <b>Design Verifier &gt; Report</b> pane.	string {'\$modelName\$_report'}
DVReportIncludeGraphics	Set by the <b>Include screen shots of properties</b> parameter on the <b>Design Verifier &gt; Report</b> pane.	'on'   {'off'}

Parameter	Location	Values
DVSaveDataFile	Set by the <b>Save test data to file</b> parameter on the <b>Design Verifier &gt; Results</b> pane.	{'on'}   'off'
DVSaveExpectedOutput	Set by the <b>Include expected output values</b> parameter on the <b>Design Verifier &gt; Results</b> pane.	'on'   {'off'}
DVSaveHarnessModel	Set by the <b>Save test harness as model</b> parameter on the <b>Design Verifier &gt; Results</b> pane.	'on'   {'off'}
DVSaveReport	Set by the <b>Generate report of the results</b> parameter on the <b>Design Verifier &gt; Report</b> pane.	'on'   {'off'}
DVSaveSystemTestHarness	Set by the <b>Save test harness as SystemTest TEST-file (will reference saved data file)</b> parameter on the <b>Design Verifier &gt; Results</b> pane.	'on'   {'off'}
DVSystemTestFileName	Set by the <b>SystemTest file name</b> parameter on the <b>Design Verifier &gt; Results</b> pane.	string {'\$ModelName \$_harness'}
DVTestConditions	Set by the <b>Test conditions</b> parameter on the <b>Design Verifier &gt; Test Generation</b> pane.	'EnableAll'   'DisableAll'   {'UseLocalSettings'}
DVTestObjectives	Set by the <b>Test objectives</b> parameter on the <b>Design Verifier &gt; Test Generation</b> pane.	'EnableAll'   'DisableAll'   {'UseLocalSettings'}

Parameter	Location	Values
DVTestSuiteOptimization	Set by the <b>Test suite optimization</b> parameter on the <b>Design Verifier &gt; Test Generation</b> pane.	<pre>{'CombinedObjectives'}   'IndividualObjectives'   'LargeModel'   'LongTestcases'   'CombinedObjectives (Nonlinear Extended)'   'LargeModel (Nonlinear Extended)'</pre>

## Design Verifier Pane

The screenshot shows the Design Verifier Pane interface. It is divided into two main sections: "Analysis options" and "Output".

**Analysis options:**

- Mode: Test generation (selected in a dropdown menu)
- Maximum analysis time (s): 300 (text input field)
- Display unsatisfiable test objectives
- Automatic stubbing of unsupported blocks and functions
- Use specified input minimum and maximum values

**Output:**

- Output folder: sldv\_output/\$ModelName\$ (text input field)
- Make output file names unique by adding a suffix

At the bottom right, there are two buttons: "Check Model Compatibility" and "Generate Tests".

### In this section...

“Design Verifier Pane Overview” on page 15-11

“Mode” on page 15-11

“Maximum analysis time” on page 15-13

“Display unsatisfiable test objectives” on page 15-13

“Automatic stubbing of unsupported blocks and functions” on page 15-14

“Use specified input minimum and maximum values” on page 15-14

“Output folder” on page 15-15

“Make output file names unique by adding a suffix” on page 15-16

## Design Verifier Pane Overview

Specify analysis options and configure Simulink Design Verifier output.

### Mode

Specify the analysis mode for the Simulink Design Verifier software.

### Settings

**Default:** Test generation

Design error detection

Detects integer and fixed-point overflow errors and division-by-zero errors in a model

Test generation

Generates test cases for a model.

Property proving

Proves properties of a model.

### Tip

The Simulink Design Verifier software specifies the value of this option automatically when you select one of the following menu options:

- **Analysis > Design Verifier > Generate Tests**
- **Analysis > Design Verifier > Detect Design Errors**
- **Analysis > Design Verifier > Prove Properties**

### Dependency

Selecting **Test generation** enables the **Display unsatisfiable test objectives** parameter.

When you set the **Mode** parameter, the button below **Check Model Compatibility** changes as follows:

- **Mode:** Test generation, button reads: **Generate Tests**
- **Mode:** Design error detection, button reads: **Detect Errors**
- **Mode:** Property proving, button reads: **Prove Properties**

### Command-Line Information

**Parameter:** DVMode

**Type:** string

**Value:** 'TestGeneration' | 'DesignErrorDetection' | 'PropertyProving'

**Default:** 'TestGeneration'

### See Also

- Basic Workflow for Simulink Design Verifier

- What Is Design Error Detection?
- What Is Test Case Generation?
- What Is Property Proving?

## Maximum analysis time

Specify the maximum time (in seconds) that the Simulink Design Verifier software spends analyzing a model.

### Settings

**Default:** 300

The value that you enter represents the maximum number of seconds the Simulink Design Verifier software analyzes your model.

### Command-Line Information

**Parameter:** DVMaxProcessTime

**Type:** double

**Value:** any valid value

**Default:** 300

## Display unsatisfiable test objectives

Specify whether to display warnings if the analysis detects unsatisfiable test objectives.

### Settings

**Default:** Off

On

Displays a warning in the Simulation Diagnostics Viewer when the Simulink Design Verifier software is unable to satisfy a test objective.

Off

Does not display a warning when the Simulink Design Verifier software is unable to satisfy a test objective.

---

**Tip** If you select **Display unsatisfiable test objectives**, on the **Test Generation** pane, set **Test suite optimization** to **CombinedObjectives**. If you perform test-

generation analysis on your model and the returned test objectives do not have outcomes, set **Test suite optimization** to **IndividualObjectives** and reanalyze the model. The **IndividualObjectives** strategy analyzes each objective independently and identifies unsatisfiable objectives.

---

### Command-Line Information

**Parameter:** DVDisplayUnsatisfiableObjectives

**Type:** string

**Value:** 'on' | 'off'

**Default:** 'off'

## Automatic stubbing of unsupported blocks and functions

Specify whether or not Simulink Design Verifier software should ignore unsupported blocks and functions and proceed with the analysis.

### Settings

**Default:** On

On

Ignores unsupported blocks and functions and proceeds with the analysis.

Off

Displays a warning when the Simulink Design Verifier software encounters an unsupported block or function and asks if you want to continue the analysis.

### Command-Line Information

**Parameter:** DVAutomaticStubbing

**Type:** string

**Value:** 'on' | 'off'

**Default:** 'on'

### See Also

Handle Incompatibilities with Automatic Stubbing

## Use specified input minimum and maximum values



Specify whether or not Simulink Design Verifier software should generate test cases that consider specified minimum and maximum values as constraints for all input signals in your model.

### Settings

**Default:** On

On

Considers specified minimum and maximum values as constraints for all input signals.

Off

Ignores any specified minimum and maximum values.

### Command-Line Information

**Parameter:** DVDesignMinMaxConstraints

**Type:** string

**Value:** 'on' | 'off'

**Default:** 'on'

### See Also

Minimum and Maximum Input Constraints

## Output folder

Specify a path name to which the Simulink Design Verifier software writes its output.

### Settings

**Default:** sldv\_output/\$modelName\$

- Enter a path that is either absolute or relative to the current folder.
- \$modelName\$ is a token that represents the model name.

### Tip

You can use the following parameters to customize the names and locations of Simulink Design Verifier output:

- On the **Results** pane:

- **Data file name**
- **Harness model file name**
- **SystemTest file name**
- On the **Report** pane:
  - **Report file name**
  - **File path of the output model**
- On the **Block Replacements** pane:
  - **File path of the output model**

### Command-Line Information

**Parameter:** DVOutputDir

**Type:** string

**Value:** any valid path

**Default:** 'sldv\_output/\$ModelName\$'

### See Also

Results Interpretation and Use

## Make output file names unique by adding a suffix

Specify whether the Simulink Design Verifier software makes its output file names unique by appending a numeric suffix.

### Settings

**Default:** On

On

Appends an incremental numeric suffix to Simulink Design Verifier output file names. Selecting this option prevents the software from overwriting existing files that have the same name.

Off

Does not append a suffix to Simulink Design Verifier output file names. In this case, the software might overwrite existing files that have the same name.

**Command-Line Information**

**Parameter:** DVMakeOutputFilesUnique

**Type:** string


**Value:** 'on' | 'off'

**Default:** 'on'

**See Also**

Results Interpretation and Use

## Design Verifier Pane: Block Replacements



Block replacements

Apply block replacements

List of block replacement rules (in order of priority):

Output model

File path of the output model:

### In this section...

“Block Replacements Pane Overview” on page 15-18

“Apply block replacements” on page 15-18

“List of block replacement rules” on page 15-19

“File path of the output model” on page 15-20

## Block Replacements Pane Overview

Specify options that control how the Simulink Design Verifier software preprocesses the models it analyzes.

### See Also

Block Replacement

## Apply block replacements

Specify whether the Simulink Design Verifier software replaces blocks in a model before its analysis.

## Settings

**Default:** Off

On

Replaces blocks in a model before the Simulink Design Verifier software analyzes it.

Off

Does not replace blocks in a model before the Simulink Design Verifier software analyzes it.

## Dependencies

This parameter enables **List of block replacement rules** and **File path of the output model**.

## Command-Line Information

**Parameter:** DVBlockReplacement

**Type:** string

**Value:** 'on' | 'off'

**Default:** 'off'

## See Also

Block Replacement

## List of block replacement rules

Specify a list of block replacement rules that the Simulink Design Verifier software executes before its analysis.

## Settings

**Default:** <FactoryDefaultRules>

- Specify block replacement rules as a list delimited by spaces, commas, or carriage returns.
- The Simulink Design Verifier software processes block replacement rules in the order that you list them.
- If you specify the default value, the Simulink Design Verifier software uses its factory default block replacement rules.

### Dependency

This parameter is enabled when you select **Apply block replacements**.

### Command-Line Information

**Parameter:** DVBlockReplacementRulesList

**Type:** string

**Value:** any valid rules

**Default:** '<FactoryDefaultRules>'

### See Also

Block Replacement

## File path of the output model

Specify a folder and file name for the model that results after applying block replacement rules.

### Settings

**Default:** \$modelName\$\_replacement

- Optionally, enter a path that is either absolute or relative to the path name specified in **Output directory**.
- Enter a file name for the model that results after applying block replacement rules.
- \$modelName\$ is a token that represents the model name.

### Dependency

This parameter is enabled when you select **Apply block replacements**.

### Command-Line Information

**Parameter:** DVBlockReplacementModelFileName

**Type:** string

**Value:** any valid path and file name

**Default:** '\$modelName\$\_replacement'

### See Also

Block Replacement

## Design Verifier Pane: Parameters

**Parameters**

Enable parameter configuration  Use parameter configuration table

Parameter configuration file:   

**Parameter Configuration Table**

Use	Name	Constraint	Value	Min	Max	Model Element
-----	------	------------	-------	-----	-----	---------------

### In this section...

- “Parameters Pane Overview” on page 15-22
- “Enable parameter configuration” on page 15-22
- “Use parameter configuration table” on page 15-23
- “Parameter configuration file” on page 15-24
- “Use” on page 15-25

### In this section...

“Name” on page 15-26

“Constraint” on page 15-26

“Value” on page 15-27

“Min” on page 15-28

“Max” on page 15-28

“Model Element” on page 15-29

## Parameters Pane Overview

Specify options that control how the Simulink Design Verifier software uses parameter configurations when analyzing models.

### Enable parameter configuration

Specify whether the software uses parameter configurations when analyzing a model. Select this option to treat parameters as variables in Simulink Design Verifier analysis.

To specify value ranges or constraints for parameters:

- Use a parameter configuration file. Enter the file name in **Parameter configuration file**.
- Use the Parameter Configuration Table. Select **Use parameter configuration table**.

### Settings

**Default:** Off

On

The Simulink Design Verifier software uses specified parameter configurations when analyzing a model.

Off

The Simulink Design Verifier software does not use parameter configurations when analyzing a model.



## Tips

When you configure Simulink Design Verifier to treat parameters as variables in its analysis, you cannot also use the analysis to extend existing test cases. In **Analysis > Design Verifier > Options**, if you specify your model to extend existing test cases with a **Data file** and apply parameter configurations with a **Parameter configuration file** or the Parameter Configuration Table, when you attempt to perform Simulink Design Verifier analysis, the software reports that your model is incompatible. This occurs because the existing test cases do not include corresponding parameter values.

## Dependency

This parameter enables **Parameter configuration file**.

## Command-Line Information

**Parameter:** DVParameters

**Type:** string

**Value:** 'on' | 'off'

**Default:** 'off'

## See Also

“Define Constraint Values for Parameters”

## Use parameter configuration table

Enable the Parameter Configuration Table to specify value ranges or constraints for parameters.

## Settings

**Default:** Off

On

Use the Parameter Configuration Table to define parameters as variables for Simulink Design Verifier analysis.

Off

Do not use the Parameter Configuration Table to define parameters as variables for Simulink Design Verifier analysis.

### Tips

When you configure Simulink Design Verifier to treat parameters as variables in its analysis, you cannot also use the analysis to extend existing test cases. In **Analysis > Design Verifier > Options**, if you specify your model to extend existing test cases with a **Data file** and apply parameter configurations with a **Parameter configuration file** or the Parameter Configuration Table, when you attempt to perform Simulink Design Verifier analysis, the software reports that your model is incompatible. This occurs because the existing test cases do not include corresponding parameter values.

### Dependency

When **Enable parameter configuration** is also selected, this parameter enables the Parameter Configuration Table.

This parameter disables **Parameter configuration file**.

### Command-Line Information

**Parameter:** DVParametersUseConfig

**Type:** string

**Value:** 'on' | 'off'

**Default:** 'off'

### See Also

“Define Constraint Values for Parameters”

## Parameter configuration file

Specify a MATLAB function that defines parameter configurations for a model.

### Settings

**Default:** sldv\_params\_template.m

- The default file, `sldv_params_template.m`, is a template that you can edit and save. The comments in the template explain the syntax you use to specify parameter configurations.
- Click the **Browse** button to select an existing MATLAB file.
- Click the **Edit** button to open the specified MATLAB file in an editor.

## Tips

When you configure Simulink Design Verifier to treat parameters as variables in its analysis, you cannot also use the analysis to extend existing test cases. In **Analysis > Design Verifier > Options**, if you specify your model to extend existing test cases with a **Data file** and apply parameter configurations with a **Parameter configuration file** or the Parameter Configuration Table, when you attempt to perform Simulink Design Verifier analysis, the software reports that your model is incompatible. This occurs because the existing test cases do not include corresponding parameter values.

## Dependency

This parameter is enabled by **Enable parameter configuration**. This parameter is disabled by **Use parameter configuration table**.

## Command-Line Information

**Parameter:** DVParametersConfigFileName

**Type:** string

**Value:** any valid MATLAB file

**Default:** 'sldv\_params\_template.m'

## See Also

“Define Constraint Values for Parameters”

## Use

In the Parameter Configuration Table, each row represents a parameter that can be constrained to specified values during Simulink Design Verifier analysis.

The **Use** column specifies whether to use this row's named parameter and specified constraint in the current parameter configuration.

## Settings

**Default:** Off

On

Use this parameter and its specified constraint in the current parameter configuration.

Off

Do not use this parameter and its specified constraint in the current parameter configuration.

### Dependency

When **Enable parameter configuration** and **Use parameter configuration table** are selected, this column is enabled.

### See Also

“Define Constraint Values for Parameters”

## Name

In the Parameter Configuration Table, each row represents a parameter that can be constrained to specified values during Simulink Design Verifier analysis.

The **Name** column displays the name of the parameter.

### Settings

**Default:** empty

### Tips

To load your model’s parameters into the Parameter Configuration Table, at the bottom of the table, click **Find in Model**. When possible, the software automatically generates constraint values for each parameter.

### Dependency

When **Enable parameter configuration** and **Use parameter configuration table** are selected, this column is enabled.

### See Also

“Define Constraint Values for Parameters”

## Constraint

In the Parameter Configuration Table, each row represents a parameter that can be constrained to specified values during Simulink Design Verifier analysis.

The **Constraint** column contains the specified value range for the parameter.

### Settings

**Default:** empty

### Tips

To autogenerate parameter constraints, at the bottom of the Parameter Configuration Table, click **Find in Model**.

### Dependency

When **Enable parameter configuration** and **Use parameter configuration table** are selected, this column is enabled.

### See Also

“Define Constraint Values for Parameters”

## Value

In the Parameter Configuration Table, each row represents a parameter that can be constrained to specified values during Simulink Design Verifier analysis.

The **Value** column contains the value of the parameter in the base workspace. If the parameter is defined in a Simulink data dictionary that is linked to the model, the **Value** column contains the value of the parameter in the data dictionary.

### Settings

**Default:** empty

### Dependency

When **Enable parameter configuration** and **Use parameter configuration table** are selected, this column is enabled.

### See Also

“Define Constraint Values for Parameters”

## Min

In the Parameter Configuration Table, each row represents a parameter that can be constrained to specified values during Simulink Design Verifier analysis.

For parameters of type `Simulink.Parameter` with a specified minimum value, the **Min** column contains the specified minimum value for the parameter.

### Settings

**Default:** empty

### Dependency

When **Enable parameter configuration** and **Use parameter configuration table** are selected, this column is enabled.

### See Also

- “Define Constraint Values for Parameters”
- `Simulink.Parameter`

## Max

In the Parameter Configuration Table, each row represents a parameter that can be constrained to specified values during Simulink Design Verifier analysis.

For parameters of type `Simulink.Parameter` with a specified maximum value, the **Max** column contains the specified maximum value for the parameter.

### Settings

**Default:** empty

### Dependency

When **Enable parameter configuration** and **Use parameter configuration table** are selected, this column is enabled.

### See Also

- “Define Constraint Values for Parameters”

- Simulink.Parameter

## Model Element

In the Parameter Configuration Table, each row represents a parameter that can be constrained to specified values during Simulink Design Verifier analysis.

The **Model Element** column displays the path to the model element(s) where the parameter is used.

### Settings

**Default:** empty

### Dependency

When **Enable parameter configuration** and **Use parameter configuration table** are selected, this column is enabled.

### See Also

“Define Constraint Values for Parameters”

## Design Verifier Pane: Test Generation

Test generation

Model coverage objectives:

Test conditions:

Test objectives:

Maximum test case steps:

Test suite optimization:

Existing test cases

Extend existing test cases:

Data file:

Ignore objectives satisfied by existing test cases

Existing coverage data

Ignore objectives satisfied in existing coverage data:

Coverage data file:

Coverage objective filter

Ignore objective based on filter:

Coverage filter file:

Relational Boundary Objectives

Include relational boundary objectives

Floating point absolute tolerance:  Floating point relative tolerance:

### In this section...

“Test Generation Pane Overview” on page 15-31

“Model coverage objectives” on page 15-31

“Test conditions” on page 15-32

“Test objectives” on page 15-33

“Maximum test case steps” on page 15-33

“Test suite optimization” on page 15-34

“Extend existing test cases” on page 15-36

“Data file” on page 15-37

“Ignore objectives satisfied by existing test cases” on page 15-38



**In this section...**

“Ignore objectives satisfied in existing coverage data” on page 15-38

“Coverage data file” on page 15-39

“Ignore objectives based on filter” on page 15-40

“Coverage filter file” on page 15-40

“Include relational boundary objectives” on page 15-41

“Floating point absolute tolerance” on page 15-42

“Floating point relative tolerance” on page 15-43

## Test Generation Pane Overview

Specify options that control how the Simulink Design Verifier software generates tests for the models it analyzes.

### See Also

Workflow for Test Case Generation

## Model coverage objectives

Specify the type of model coverage that the Simulink Design Verifier software attempts to achieve.

### Settings

**Default:** Condition Decision

None

Generates test cases that achieve only the custom objectives that you specified in your model using, for example, Test Objective blocks.

Decision

Generates test cases that achieve decision coverage. For more information, see “Decision”.

Condition Decision

Generates test cases that achieve condition and decision coverage. For more information, see “Condition”.

### MCDC

Generates test cases that achieve modified condition/decision coverage (MCDC). For more information, see “MCDC”.

When you set **Model coverage objectives** to MCDC, the Simulink Design Verifier software automatically enables every coverage objective for decision coverage and condition coverage as well. Similarly, enabling coverage for condition coverage causes every decision and condition coverage outcome to be enabled.

#### Command-Line Information

**Parameter:** DVModelCoverageObjectives

**Type:** string

**Value:** 'None' | 'Decision' | 'ConditionDecision' | 'MCDC'

**Default:** 'ConditionDecision'

#### See Also

Workflow for Test Case Generation

## Test conditions

Specify whether Test Condition blocks in your model are enabled or disabled.

### Settings

**Default:** Use local settings

Use local settings

Enables or disables Test Condition blocks based on the value of the **Enable** parameter of each block. If a block's **Enable** parameter is selected, the block is enabled; otherwise, the block is disabled.

Enable all

Enables all Test Condition blocks in the model regardless of the settings of their **Enable** parameters.

Disable all

Disables all Test Condition blocks in the model regardless of the settings of their **Enable** parameters.

#### Command-Line Information

**Parameter:** DVTestConditions

**Type:** string

**Value:** 'UseLocalSettings' | 'EnableAll' | 'DisableAll'

**Default:** 'UseLocalSettings'

### See Also

- Test Condition
- Workflow for Test Case Generation

## Test objectives

Specify whether Test Objective blocks in your model are enabled or disabled.

### Settings

**Default:** Use local settings

Use local settings

Enables or disables Test Objective blocks based on the value of the **Enable** parameter of each block. If a block's **Enable** parameter is selected, the block is enabled; otherwise, the block is disabled.

Enable all

Enables all Test Objective blocks in the model regardless of the settings of their **Enable** parameters.

Disable all

Disables all Test Objective blocks in the model regardless of the settings of their **Enable** parameters.

### Command-Line Information

**Parameter:** DVTestObjectives

**Type:** string

**Value:** 'UseLocalSettings' | 'EnableAll' | 'DisableAll'

**Default:** 'UseLocalSettings'

### See Also

- Test Objective
- Workflow for Test Case Generation

## Maximum test case steps

Specify the maximum number of simulation steps the Simulink Design Verifier software takes when attempting to satisfy a test objective.

The analysis uses the **Maximum test case steps** parameter during certain parts of the test-generation analysis to bound the number of steps that test generation uses. When you set a small value for this parameter, the parts of the analysis that are bounded complete in less time. When you set a larger value, the bounded parts of the analysis take longer, but it is possible for these parts of the analysis to generate longer test cases.

To achieve the best performance, set the **Maximum test case steps** parameter to a value just large enough to bound the longest required test case, even if the test cases that are ultimately generated are longer than this value.

When you also specify **LongTestcases** for the **Test suite optimization** parameter, the analysis uses successive passes of test generation to extend a potential test case so that it satisfies more objectives. When this happens, the analysis applies the **Maximum test case steps** parameter to each individual iteration of test generation.

### Settings

**Default:** 500

You can specify a value that represents the maximum number of simulation steps the Simulink Design Verifier software takes when attempting to satisfy a test objective.

### Command-Line Information

**Parameter:** DVMaxTestCaseSteps

**Type:** int32

**Value:** any valid value

**Default:** 500

### See Also

Workflow for Test Case Generation

## Test suite optimization

Specify the optimization strategy to use when generating test cases.

### Settings

**Default:** CombinedObjectives (Nonlinear Extended)

**CombinedObjectives (Nonlinear Extended)**

Analyzes the model using a variation of the **CombinedObjectives** optimization. This optimization includes improved support for nonlinear arithmetic.

**LargeModel (Nonlinear Extended)**

Analyzes the model using a variation of the **LargeModel** optimization. This optimization includes improved support for nonlinear arithmetic.

**IndividualObjectives**

Maximizes the number of test cases in a suite by generating cases that each address only one test objective. Each test case tends to be short, i.e., it includes only a few time steps.

**LongTestcases**

Combines test cases to create a smaller number of test cases. This strategy generates fewer, but longer, test cases that each satisfy multiple test objectives and creates a more efficient analysis and easier-to-review results.

**CombinedObjectives**

Minimizes the number of test cases in a suite by generating cases that address more than one test objective. Each test case tends to be long, i.e., it includes many time steps.

**LargeModel**

Minimizes the number of test cases in a suite by generating cases that address more than one test objective. This strategy is tailored for large, complex models; consequently, it tends to use all the time that the **Maximum analysis time** option allots.

**Tip**

If you want to identify unsatisfiable objectives, set this option to **IndividualObjectives**. The **IndividualObjectives** strategy analyzes each objective independently, so it has a better chance of identifying unsatisfiable objectives.

If you have a large number of test objectives or you want to create a smaller number of test cases, select **LongTestcases** for a more efficient analysis and an easy-to-review report.

If your model has both of the following characteristics:

- Nonlinearities, such as those that result from multiplying or dividing the model's input signals

- Numerous test objectives, such as those that result when using blocks that receive model coverage

set this option to `LargeModel (Nonlinear Extended)`. The `LargeModel` and `LargeModel (Nonlinear Extended)` strategies perform an analysis that is tailored to large, complex models. However, these strategies tend to use all the time that the **Maximum analysis time** option allots.

#### Command-Line Information

**Parameter:** `DVTestSuiteOptimization`

**Type:** string

**Value:** `'CombinedObjectives (Nonlinear Extended)'` | `'LargeModel (Nonlinear Extended)'` | `'IndividualObjectives'` | `'LongTestcases'` | `'CombinedObjectives'` | `'LargeModel'` |

**Default:** `'CombinedObjectives (Nonlinear Extended)'`

#### See Also

Workflow for Test Case Generation

## Extend existing test cases

Extend the Simulink Design Verifier analysis by importing test cases logged from a harness model or a closed-loop simulation model.

#### Settings

**Default:** Off

On

Extends the analysis by using the logged test cases specified in **Data file**.

Off

Does not extend the analysis.

#### Tips

When Simulink Design Verifier is configured to apply parameters specified in **Parameter configuration file**, you cannot use the **Extend existing test cases** option. If you specify your model to extend existing test cases with a **Data file** and apply parameter configurations with a **Parameter configuration file**, when you attempt

to perform Simulink Design Verifier analysis, the software reports that your model is incompatible. This occurs because the existing test cases do not include corresponding parameter values.

## Dependency

This parameter enables **Data file** and **Ignore objectives satisfied by existing test cases**.

## Command-Line Information

**Parameter:** DVExtendExistingTests

**Type:** string

**Value:** 'on' | 'off'

**Default:** 'off'

## See Also

- When to Extend Existing Test Cases
- Common Workflow for Extending Existing Test Cases

## Data file

Specify a folder and file name for the MAT-file that contains the logged test case data.

## Settings

**Default:** ''

- Specify a folder and file name for the MAT-file that contains the logged test case data in an `sldvData` object.
- Click the **Browse** button to navigate to and select an existing file.

## Tips

When you configure Simulink Design Verifier to treat parameters as variables in its analysis, you cannot also use the analysis to extend existing test cases. In **Analysis > Design Verifier > Options**, if you specify your model to extend existing test cases with a **Data file** and apply parameter configurations with a **Parameter configuration file** or the Parameter Configuration Table, when you attempt to perform Simulink Design Verifier analysis, the software reports that your model is incompatible. This occurs because the existing test cases do not include corresponding parameter values.

### Command-Line Information

**Parameter:** DVExistingTestFile

**Type:** string

**Value:** any valid path and file name

**Default:** ' '

### See Also

Simulink Design Verifier Data Files

## Ignore objectives satisfied by existing test cases

Ignore the coverage objectives satisfied by the logged test cases in **Data file**.

### Settings

**Default:** On



On

Generates results, but excludes coverage objectives satisfied by logged test cases in **Data file** from the analysis.



Off

Generates results for the full test suite, including coverage objectives satisfied by the logged test cases in **Data file**.

### Command-Line Information

**Parameter:** DVIgnoreExistTestSatisfied

**Type:** string

**Value:** 'on' | 'off'

**Default:** 'on'

### See Also

- “Extend Test Cases for Closed-Loop System”
- Simulink Design Verifier Data Files

## Ignore objectives satisfied in existing coverage data

Specify to analyze the model, ignoring satisfied coverage objectives, as specified in **Coverage data file**.



## Settings

**Default:** Off

On

Ignores satisfied coverage objectives in **Coverage data file** during the analysis.

Off

Generates results for all coverage objectives, including those in **Coverage data file**.

## Dependency

This parameter enables **Coverage data file**.

## Command-Line Information

**Parameter:** DVIgnoreCovSatisfied

**Type:** string

**Value:** 'on' | 'off'

**Default:** 'off'

## See Also

- “Achieve Missing Coverage in Closed-Loop Simulation Model”
- Test Case Extension

## Coverage data file

Specify a folder and file name for the file that contains data about satisfied coverage objectives.

## Settings

**Default:** ''

- Specify the name of the folder and file name that contains the satisfied coverage objectives data

Click the **Browse** button to select an existing MATLAB file.

## Command-Line Information

**Parameter:** DVCoverageDataFile

**Type:** string

**Value:** any valid path and file name

**Default:** ''

### See Also

- “Achieve Missing Coverage in Closed-Loop Simulation Model”
- Test Case Extension

## Ignore objectives based on filter

Specify to analyze the model, ignoring the coverage objectives in the **Coverage filter file**.

### Settings

**Default:** Off

On

Ignores coverage objectives in the **Coverage filter file** during the analysis.

Off

Generates results for all coverage objectives, including those in **Coverage filter file**.

### Dependency

This parameter enables **Coverage filter file**.

### Command-Line Information

**Parameter:** DVCovFilter

**Type:** string

**Value:** 'on' | 'off'

**Default:** 'off'

### See Also

“Coverage Filtering” in the Simulink Verification and Validation documentation

## Coverage filter file

Specify a folder and file name for the file that contains the coverage objectives you want to ignore. The **Coverage filter file** specifies model objects to exclude from model coverage during test case generation.

### Settings

**Default:** ' '

- Specify the name of the folder and file name that contains the coverage objectives you want to ignore.

Click the **Browse** button to select an existing MATLAB file.

### Command-Line Information

**Parameter:** DVCovFilterFileName

**Type:** string

**Value:** any valid path and file name

**Default:** ' '

### See Also

“Coverage Filter Rules and Files” in the Simulink Verification and Validation documentation

## Include relational boundary objectives

Specify generation of test cases that satisfy relational boundary objectives. The objective applies to blocks such as Relational Operator that have an explicit or implicit relational operation. The tests check the relational operations in these blocks with:

- Equal operand values for integer and fixed-point operands.
- Operand values within a certain tolerance for all operands. For integer and fixed-point operands, the tolerance is fixed. For floating-point operands, the tolerance is computed using the inputs and a tolerance value that you specify. If you do not specify a tolerance value, the default values are used.

### Settings

**Default:** Off

On

For supported blocks, generated test cases satisfy relational boundary objectives.

Off

Generated test cases do not satisfy relational boundary objectives.

### Dependencies

If you select this option, you can use default values or specify values for:

- “Floating point absolute tolerance” on page 15-42
- “Floating point relative tolerance” on page 15-43

### Command-Line Information

**Parameter:** DVIncludeRelationalBoundary

**Type:** string

**Value:** 'on' | 'off'

**Default:** 'off'

### See Also

- “Relational Boundary”
- “Model Objects That Receive Coverage” in the Simulink Verification and Validation documentation

## Floating point absolute tolerance

Specify a value for absolute tolerance used in relational boundary tests. The relational boundary objectives apply to blocks such as Relational Operator that have an explicit or implicit relational operation. The tolerance value applies only if the relational operations in those blocks use floating point operands.

- For integer operands, the tolerance value is fixed at 1.
- For fixed-point operands, the tolerance value is the least significant bit.

### Settings

**Default:** 1.0000e-05

For supported blocks, the relational boundary tests check the relational operations in the block with operand values that differ by a certain tolerance. The software calculates the tolerance value using the following formula

$\max(\text{absTol}, \text{relTol} * \max(|\text{lhs}|, |\text{rhs}|))$ , where:

- `absTol` is the absolute tolerance value that you specify.
- `relTol` is a relative tolerance value that you can specify.
- `lhs` is the left operand and `rhs` the right operand.
- `max(x,y)` returns `x` or `y`, whichever is greater.

### Dependencies

To enter a value for this option, you must select “Include relational boundary objectives” on page 15-41.

### Command-Line Information

**Parameter:** DVAbsoluteTolerance

**Type:** double

**Value:** Any valid value

**Default:** 1.0000e-05

### See Also

- “Relational Boundary”
- “Model Objects That Receive Coverage” in the Simulink Verification and Validation documentation

## Floating point relative tolerance

Specify a value for relative tolerance used in relational boundary tests. The relational boundary objectives apply to blocks such as Relational Operator that have an explicit or implicit relational operation. The tolerance value applies only if the relational operations in those blocks use floating point operands.

- For integer operands, the tolerance value is fixed at 1.
- For fixed-point operands, the tolerance value is the least significant bit.

### Settings

**Default:** 0.01

For supported blocks, the relational boundary tests check the relational operations in the block with operand values that differ by a certain tolerance. The software calculates the tolerance value using the following formula

$\max(\text{absTol}, \text{relTol} * \max(|\text{lhs}|, |\text{rhs}|))$ , where:

- `absTol` is an absolute tolerance value that you can specify.
- `relTol` is the relative tolerance value that you specify.
- `lhs` is the left operand and `rhs` the right operand.
- `max(x, y)` returns `x` or `y`, whichever is greater.

### Dependencies

To enter a value for this option, you must select “Include relational boundary objectives” on page 15-41.

### Command-Line Information

**Parameter:** `DVRelativeTolerance`

**Type:** `double`


**Value:** Any valid value

**Default:** `0.01`

### See Also

- “Relational Boundary”
- “Model Objects That Receive Coverage” in the Simulink Verification and Validation documentation

## Design Verifier Pane: Design Error Detection



Design Error Detection

- Dead logic
  - Identify active logic
- Integer overflow
- Division by zero
- Check specified intermediate minimum and maximum values
- Out of bound array access

### In this section...

“Design Error Detection Pane Overview” on page 15-45

“Dead logic” on page 15-45

“Identify active logic” on page 15-46

“Integer overflow” on page 15-47

“Division by zero” on page 15-48

“Check specified intermediate minimum and maximum values” on page 15-48

“Out of bound array access” on page 15-49

## Design Error Detection Pane Overview

Specify options that control how the Simulink Design Verifier software detects runtime errors in the models it analyzes.

### Dead logic

Specify whether to analyze your model for dead logic.

### Settings

**Default:** Off

On

Reports dead logic in your model.

Off

Does not report dead logic in your model.

### Dependency

Design error detection for dead logic is standalone analysis. When you enable **Dead logic**, **Active logic** is enabled and other design error detection options are disabled.

### Command-Line Information

**Parameter:** DVDetectDeadLogic

**Type:** string

**Value:** 'on' | 'off'

**Default:** 'off'

### See Also

Dead Logic Detection

## Identify active logic

Specify whether to analyze your model for active logic, in addition to dead logic.

### Settings

**Default:** Off

On

Reports active logic in your model.

Off

Does not report active logic in your model.



## Dependency

To enable **Identify active logic**, select **Dead logic**.

Design error detection for dead logic is standalone analysis. When you enable **Dead logic**, **Identify active logic** is enabled and other design error detection options are disabled.

## Command-Line Information

**Parameter:** DVDetectActiveLogic

**Type:** string

**Value:** 'on' | 'off'

**Default:** 'off'

## See Also

Dead Logic Detection

## Integer overflow

Specify whether to analyze your model for integer and fixed-point data overflow errors.

## Settings

**Default:** On

On

Reports integer or fixed-point data overflow errors in your model.

Off

Does not report integer or fixed-point data overflow errors in your model.

## Dependency

This parameter is disabled by **Dead logic**.

## Command-Line Information

**Parameter:** DVDetectIntegerOverflow

**Type:** string

**Value:** 'on' | 'off'

**Default:** 'on'

### See Also

Static Run-Time Error Detection

## Division by zero

Specify whether to analyze your model for division-by-zero errors.

### Settings

**Default:** On

On

Reports division-by-zero errors in your model.

Off

Does not report division-by-zero errors in your model.

### Dependency

This parameter is disabled by **Dead logic**.

### Command-Line Information

**Parameter:** DVDetectDivisionByZero

**Type:** string

**Value:** 'on' | 'off'

**Default:** 'on'

### See Also

Static Run-Time Error Detection

## Check specified intermediate minimum and maximum values

Specify whether to check that the intermediate and output signals in your model are within the range of user-specified minimum and maximum constraints.

### Settings

**Default:** Off

On

Checks that intermediate and output signals are within the range of user-specified minimum and maximum constraints.

Off

Does not check that intermediate and output signals are within the range of user-specified minimum and maximum constraints.

### Dependency

This parameter is disabled by **Dead logic**.

### Command-Line Information

**Parameter:** DVDesignMinMaxCheck

**Type:** string

**Value:** 'on' | 'off'

**Default:** 'off'

### See Also

Design Range Checks

## Out of bound array access

Specify whether to analyze your model for out of bound array access errors.

### Settings

**Default:** Off

On

Reports out of bound array access errors in your model.

Off

Does not report out of bound array access errors in your model.

### Dependency

This parameter is disabled by **Dead logic**.

### **Command-Line Information**

**Parameter:** DVDetectOutOfBounds

**Type:** string


**Value:** 'on' | 'off'

**Default:** 'off'

### **See Also**

- Detect Out of Bound Array Access in Example Model
- Static Run-Time Error Detection

## Design Verifier Pane: Property Proving



Property proving

Assertion blocks: Use local settings

Proof assumptions: Use local settings

Strategy: Prove

Maximum violation steps:

### In this section...

“Property Proving Pane Overview” on page 15-51

“Assertion blocks” on page 15-51

“Proof assumptions” on page 15-52

“Strategy” on page 15-53

“Maximum violation steps” on page 15-54

## Property Proving Pane Overview

Specify options that control how the Simulink Design Verifier software proves properties for the models it analyzes.

### See Also

- “What Is Property Proving?”
- “Workflow for Proving Model Properties”
- “Prove Properties in a Model”

## Assertion blocks

Specify whether Assertion blocks in your model are enabled or disabled.

### Settings

**Default:** Use local settings

Use local settings

Enables or disables Assertion blocks based on the value of the **Enable** parameter of each block. If a block's **Enable** parameter is selected, the block is enabled; otherwise, the block is disabled.

### Enable all

Enables all Assertion blocks in the model regardless of the settings of their **Enable** parameters.

### Disable all

Disables all Assertion blocks in the model regardless of the settings of their **Enable** parameters.

### Command-Line Information

**Parameter:** DVAssertions

**Type:** string

**Value:** 'UseLocalSettings' | 'EnableAll' | 'DisableAll'

**Default:** 'UseLocalSettings'

### See Also

- Assertion
- “Workflow for Proving Model Properties”
- “Prove Properties in a Model”

## Proof assumptions

Specify whether Proof Assumption blocks in your model are enabled or disabled.

### Settings

**Default:** Use local settings

### Use local settings

Enables or disables Proof Assumption blocks based on the value of the **Enable** parameter of each block. If a block's **Enable** parameter is selected, the block is enabled; otherwise, the block is disabled.

### Enable all

Enables all Proof Assumption blocks in the model regardless of the settings of their **Enable** parameters.

### Disable all

Disables all Proof Assumption blocks in the model regardless of the settings of their **Enable** parameters.

### Command-Line Information

**Parameter:** DVProofAssumptions

**Type:** string

**Value:** 'UseLocalSettings' | 'EnableAll' | 'DisableAll'

**Default:** 'UseLocalSettings'

### See Also

- Proof Assumption
- “Workflow for Proving Model Properties”
- “Prove Properties in a Model”

## Strategy

Specify the strategy that the Simulink Design Verifier software uses when proving properties.

### Settings

**Default:** Prove

Prove

Performs property proofs.

FindViolation

Searches only for property violations within the number of simulation steps specified by the **Maximum violation steps** option.

ProveWithViolationDetection

Searches first for property violations within the number of simulation steps specified by the **Maximum violation steps** option; then it attempts to prove properties for which it failed to detect a violation. This strategy is a combination of the **Prove** and **FindViolation** strategies.

### Dependency

Selecting **FindViolation** or **ProveWithViolationDetection** enables the **Maximum violation steps** parameter.

### Command-Line Information

**Parameter:** DVProvingStrategy

**Type:** string

**Value:** 'Prove' | 'FindViolation' | 'ProveWithViolationDetection'

**Default:** 'Prove'

### See Also

- “What Is Property Proving?”
- “Workflow for Proving Model Properties”
- “Prove Properties in a Model”

### Maximum violation steps

Specify the maximum number of simulation steps over which the Simulink Design Verifier software searches for property violations.

### Settings

**Default:** 20

The Simulink Design Verifier software does not search beyond the maximum number of simulation steps that you specify. Therefore, it cannot identify violations that might occur later in a simulation.

### Dependency

This parameter is enabled when you set **Strategy** to `FindViolation` or `ProveWithViolationDetection`.

### Command-Line Information

**Parameter:** DVMaxViolationSteps

**Type:** int32

**Value:** any valid value

**Default:** 20

### See Also

- “What Is Property Proving?”
- “Workflow for Proving Model Properties”



- “Prove Properties in a Model”

## Design Verifier Pane: Results

The screenshot shows the 'Results' section of the Design Verifier Configuration Parameters pane. It is organized into four distinct sections, each with a title and a set of options:

- Data file options:** Includes a checked checkbox for 'Save test data to file', a text field for 'Data file name' containing '\$ModelName\$\_slvdvdata', and two unchecked checkboxes for 'Include expected output values' and 'Randomize data that do not affect the outcome'.
- Display results on model:** Includes one unchecked checkbox for 'Display results of the analysis on the model'.
- Harness model options:** Includes one unchecked checkbox for 'Save test harness as model', a text field for 'Harness model file name', and one unchecked checkbox for 'Reference input model in generated harness'.
- SystemTest options:** Includes one unchecked checkbox for 'Save test harness as SystemTest TEST-file (will reference saved data file)' and a text field for 'SystemTest file name'.

### In this section...

“Results Pane Overview” on page 15-57

“Save test data to file” on page 15-57

“Data file name” on page 15-57

“Include expected output values” on page 15-58

“Randomize data that do not affect the outcome” on page 15-59

“Display results of the analysis on the model” on page 15-61

“Save test harness as model” on page 15-61

“Harness model file name” on page 15-62

“Reference input model in generated harness” on page 15-63

“Save test harness as SystemTest TEST-file (will reference saved data file)” on page 15-64

“SystemTest file name” on page 15-65

## Results Pane Overview

Specify options that control how the Simulink Design Verifier software handles the results that it generates.

### See Also

Results Interpretation and Use

## Save test data to file

Save the test data that the Simulink Design Verifier analysis generates to a MAT-file.

### Settings

**Default:** On

On

Saves the test data that the analysis generates to a MAT-file.

Off

Does not save the test data that the analysis generates.

### Dependency

This parameter enables **Data file name**.

### Command-Line Information

**Parameter:** DVSaveDataFile

**Type:** string

**Value:** 'on' | 'off'

**Default:** 'on'

### See Also

- Simulink Design Verifier Data Files
- Results Interpretation and Use

## Data file name

Specify a folder and file name for the MAT-file that contains the data generated during the analysis, stored in an `sldvData` structure.

### Settings

**Default:** `$modelName$_sldvdata`

- Optionally, enter a path that is either absolute or relative to the path name specified in **Output directory**.
- Enter a file name for the MAT-file.
- `$modelName$` is a token that represents the model name.

### Dependency

This parameter is enabled by **Save test data to file**.

### Command-Line Information

**Parameter:** `DVDataFileName`

**Type:** string

**Value:** any valid path and file name

**Default:** `'$modelName$_sldvdata'`

### See Also

- Simulink Design Verifier Data Files
- Results Interpretation and Use

## Include expected output values

Simulate the model using test case signals and include the output values in the Simulink Design Verifier data file.

### Settings

**Default:** Off

On

Simulates the model using the test case signals that the analysis produces. For each test case, the software collects the simulation output values associated with

Output blocks in the top-level system and includes those values in the MAT-file that it generates.

Off

Does not simulate the model and collect output values for inclusion in the MAT-file that the analysis generates.

### Tips

- The `TestCases.expectedOutput` subfield of the MAT-file contains the output values. For more information, see “Contents of sldvData Structure”.
- When **Include expected output values** is enabled, the Simulink Design Verifier software successively simulates the model using each test case that it generates. Enabling this option requires more time for the Simulink Design Verifier software to complete its analysis.

### Dependency

This parameter is enabled by **Save test data to file**.

### Command-Line Information

**Parameter:** DVSaveExpectedOutput

**Type:** string

**Value:** 'on' | 'off'

**Default:** 'off'

### See Also

- Simulink Design Verifier Data Files
- Results Interpretation and Use

## Randomize data that do not affect the outcome

Specify whether to use random values instead of zeros for input signals that have no impact on test or proof objectives.

### Settings

**Default:** Off

On


Assigns random values to test case or counterexample signals that do not affect the outcome of test or proof objectives in a model. This option can enhance traceability and improve your regression tests.

Off

Assigns zeros to test case or counterexample signals that do not affect the outcome of test or proof objectives in a model.

### Tips

- This option replaces default data values with random values when the Simulink Design Verifier internal analysis engine does not specify a value. When a value does not influence the satisfaction of a test or proof objective, the generated analysis report indicates that value with a dash (–).
- Simulink Design Verifier generated analysis reports show the setting of this option.
- Enable this option to enhance traceability when simulating test cases or counterexamples. For instance, consider the following model:



Only the signal entering the Switch block's control port impacts its decision coverage. If the **Randomize data that does not affect outcome** parameter is off, the Simulink Design Verifier software uses zeros to represent the signals from In1 and In3. When inspecting the results from test case or counterexample simulations, it is unclear which of these signals passes through the Switch block because they have the same value. But if the **Randomize data that does not affect outcome** parameter is on, the software uses unique values to represent each of those signals. In this case, it is easier to determine which signal passes through the Switch block.

### Dependency

This parameter is enabled by **Save test data to file**.

**Command-Line Information****Parameter:** DVRandomizeNoEffectData**Type:** string**Value:** 'on' | 'off'**Default:** 'off'**See Also**

- Simulink Design Verifier Data Files
- Results Interpretation and Use

**Display results of the analysis on the model**

Specify whether to display analysis results by highlighting the model and providing context-sensitive details about the results.

**Settings****Default:** Off On

Highlight the model with the analysis results and provide context-sensitive details about the results.

 Off

Do not display analysis results on the model.

**Command-Line Information****Parameter:** DVDisplayResultsOnModel**Type:** string**Value:** 'on' | 'off'**Default:** 'off'**See Also**

- “Highlighted Results on the Model”
- Results Interpretation and Use

**Save test harness as model**

Create a harness model generated by the Simulink Design Verifier analysis.

### Settings

**Default:** Off

On

Saves the harness model that the Simulink Design Verifier software generates as a model file.

Off

Does not save the harness model that the Simulink Design Verifier software generates.

### Dependency

This parameter enables **Harness model file name**.

### Command-Line Information

**Parameter:** DVSaveHarnessModel

**Type:** string

**Value:** 'on' | 'off'

**Default:** 'off'

### See Also

- “Simulink Design Verifier Harness Models”
- Results Interpretation and Use

## Harness model file name

Specify a folder and file name for the harness model.

### Settings

**Default:** \$modelName\$\_harness

- Optionally, enter a path that is either absolute or relative to the path name specified in **Output directory**.
- Enter a file name for the harness model.



- `$modelName$` is a token that represents the model name.

### Dependency

This parameter is enabled by **Save test harness as model**.

### Command-Line Information

**Parameter:** DVHarnessModelFileName

**Type:** string

**Value:** any valid path and file name

**Default:** '\$modelName\$\_harness'

### See Also

- “Simulink Design Verifier Harness Models”
- Results Interpretation and Use

## Reference input model in generated harness

Use a Model block to reference the model to run in the harness model.

### Settings

**Default:** Off

On

Uses a Model block to reference the model to run in the harness model.

Off

Uses a copy of the model in the harness model.

### Tips

- If the Test Unit in the harness model is a subsystem, the values of the Simulink simulation optimization parameters on the Configuration Parameters dialog box may impact your coverage results.

---

**Note:** The simulation optimization parameters are on the following Configuration Parameters dialog box panes:

- **Optimization** pane
  - **Optimization > Signals and Parameters** pane
  - **Optimization > Stateflow** pane
- 
- If your model contains bus objects and you select **Reference input model in generated harness**, in the **Configuration Parameters > Diagnostics > Connectivity** pane, you must set the **Mux blocks used to create bus signals** parameter to **error**. For more information, see “Prevent Bus and Mux Mixtures”.
  - On the **Design Verifier > Parameters** pane, if you select the **Apply parameters** parameter, the Simulink Design Verifier software uses a subsystem that contains a copy of the original model in the harness model, even if you select **Reference input model in generated harness**.

#### Command-Line Information

**Parameter:** DVModelReferenceHarness

**Type:** string

**Value:** 'on' | 'off'

**Default:** 'off'

#### See Also

- “Simulink Design Verifier Harness Models”
- Results Interpretation and Use

### Save test harness as SystemTest TEST-file (will reference saved data file)

Save the analysis results as a SystemTest TEST-file so you can run test cases using the SystemTest capabilities.

---

**Note:** The option to create a SystemTest TEST-file is only available in test-generation mode; you cannot create this file when running a property-proving analysis.

---

#### Settings

**Default:** Off

On

Saves the analysis results as a SystemTest TEST-file.

Off

Does not save the analysis results as a SystemTest TEST-file.

### Dependency

This parameter enables **SystemTest file name**.

### Command-Line Information

**Parameter:** DVSaveSystemTestHarness

**Type:** string

**Value:** 'on' | 'off'

**Default:** 'off'

### See Also

- “Export Test Cases to SystemTest”
- Results Interpretation and Use

## SystemTest file name

Specify a folder and file name for the SystemTest TEST-file.

### Settings

**Default:** \$ModelName\$\_harness

- Optionally, enter a path that is either absolute or relative to the path name specified in **Output directory**.
- Enter a file name for the SystemTest TEST-file.
- \$ModelName\$ is a token that represents the model name.

### Dependency

This parameter is enabled by **Save test harness as SystemTest TEST-file (will reference saved data file)**.

### Command-Line Information

**Parameter:** DVMSystemTestFileName

**Type:** string

**Value:** any valid path and file name

**Default:** '\$modelName\$\_harness'

### **See Also**

- “Export Test Cases to SystemTest”
- Results Interpretation and Use

## Design Verifier Pane: Report

Report

Generate report of the results

Report file name:

Include screen shots of properties

Display report

### In this section...

“Report Pane Overview” on page 15-67

“Generate report of the results” on page 15-67

“Report file name” on page 15-68

“Include screen shots of properties” on page 15-69

“Display report” on page 15-70

## Report Pane Overview

Specify options that control how the Simulink Design Verifier software reports its results.

### See Also

- “Simulink Design Verifier Reports”
- Results Interpretation and Use

## Generate report of the results

Generate and save a Simulink Design Verifier report.

### Settings

Default: Off

On

Saves the HTML report that the Simulink Design Verifier software generates.

Off

Does not generate a Simulink Design Verifier report.

### Dependencies

When this parameter is enabled, you must enable **Save test harness as model**.

This parameter enables the following parameters:

- **Report file name**
- **Include screen shots of properties**
- **Display report**

### Command-Line Information

**Parameter:** DVSaveReport

**Type:** string

**Value:** 'on' | 'off'

**Default:** 'off'

### See Also

- “Simulink Design Verifier Reports”
- Results Interpretation and Use

## Report file name

Specify a folder and file name for the report that Simulink Design Verifier analysis generates.

### Settings

**Default:** \$ModelName\$\_report

- Optionally, enter a path that is either absolute or relative to the path name specified in **Output directory**.
- Enter a file name for the report that the analysis generates.
- \$ModelName\$ is a token that represents the model name.

## Dependency

This parameter is enabled by **Generate report of the results**.

### Command-Line Information

**Parameter:** DVReportFileName

**Type:** string

**Value:** any valid path and file name

**Default:** '\$modelName\$\_report'

### See Also

- “Simulink Design Verifier Reports”
- Results Interpretation and Use

## Include screen shots of properties

Includes screen shots of properties in the Simulink Design Verifier report. Only valid in property-proving mode.

### Settings

**Default:** Off

On

Includes screen shots of properties in the Simulink Design Verifier report. Only valid in property-proving mode.

Off

Does not include screen shots of properties in the Simulink Design Verifier report.

## Dependency

This parameter is enabled by **Generate report of the results**.

### Command-Line Information

**Parameter:** DVReportIncludeGraphics

**Type:** string

**Value:** 'on' | 'off'

**Default:** 'off'

### See Also

- “Simulink Design Verifier Reports”
- Results Interpretation and Use

### Display report

Display the report that the Simulink Design Verifier analysis generates after completing its analysis.

#### Settings

**Default:** On

On

Displays the report that the analysis generates after completing its analysis.

Off

Does not display the report that the analysis generates after completing its analysis.

#### Dependency

This parameter is enabled by **Generate report of the results**.

#### Command-Line Information

**Parameter:** DVDisplayReport

**Type:** string

**Value:** 'on' | 'off'

**Default:** 'on'

### See Also

- “Simulink Design Verifier Reports”
- Results Interpretation and Use



<b>abstraction</b>	The process of ignoring certain aspects of model behavior that do not affect the test objective or property under investigation.
<b>analysis model</b>	The target model for a Simulink Design Verifier analysis. If you select an atomic subsystem for analysis, the analysis model is generated by extracting the subsystem to a new model.
<b>assumption</b>	A property that is assumed to be true during a property proof. The proof result holds only when the assumption is true.
<b>block replacement rule</b>	A rule that is registered with the Simulink Design Verifier software and defines how instances of specific blocks are replaced by an alternate implementation. The software uses MATLAB commands to define when and how to apply a block replacement rule (see “Define Custom Block Replacements”).
<b>component verification</b>	The process of verifying an individual components in a model. You can verify a component within the execution context of the model, or independently of its parent model.
<b>condition coverage</b>	Measures the percentage of the total number of logic conditions associated with logical model objects that the simulation actually exercised. Enabling condition coverage causes every decision and condition coverage outcome to be enabled. See “Types of Model Coverage” in the Simulink Verification and Validation documentation.
<b>constraint</b>	A property that is forced to be true during test case generation.
<b>counterexample</b>	A test case that demonstrates a property violation.
<b>coverage objective</b>	A test objective that defines when a coverage point results in a particular outcome.
<b>coverage point</b>	A decision, condition, or MCDC expression associated with a model object. Each coverage point has a fixed number of mutually exclusive outcomes.

<b>decision coverage</b>	Measures the percentage of the total number of simulation paths through model objects that the simulation actually traversed. Decision coverage is a subset of modified decision/condition coverage. See “Types of Model Coverage” in the Simulink Verification and Validation documentation.
<b>floating-point approximation</b>	The process of approximating floating-point numbers using rational numbers (i.e., fractions whose numerator and denominator are small integers). The Simulink Design Verifier software performs floating-point approximations during its analysis. It can generate invalid test cases that result from numerical differences. For example, given a large enough floating-point number $x$ , the expression $x == (x+1)$ can be true; however, this expression never holds if $x$ is a rational number.
<b>invalid test case</b>	A test case that does not satisfy its objectives.
<b>modified condition/decision coverage (MCDC)</b>	<p>Measures the independence of logical block inputs and transition conditions associated with logical model objects during the simulation. When you set the coverage objective to MCDC, Simulink Design Verifier automatically enables every coverage objective for decision coverage and condition coverage as well.</p> <p>Note that MCDC test cases are not generated for XOR configured logic operators. You can achieve MCDC by using the same tests that would be generated from AND configured blocks or OR configured blocks.</p> <p>See “Types of Model Coverage” in the Simulink Verification and Validation documentation.</p>
<b>nonlinear arithmetic</b>	A computation in the model that cannot be expressed as a combination of mutually exclusive linear expressions. Nonlinear arithmetic can affect a property or test objective, and it can cause the analysis to return an error. In this case, you should apply simplifying approximations and abstractions.

---

<b>property</b>	A logical expression of the signals and data values, within a model, that is intended to be proven true during simulation. Properties evaluate at specific points in the model.
<b>property violation</b>	The condition during a simulation when a property is false.
<b>test case</b>	A sequence of numeric values and input data time that you input to a model during its simulation.
<b>test harness</b>	A model that runs test cases on an analysis model.
<b>test objective</b>	A logical expression of the signals and data values, within a model, that is intended to be true at least once in the resulting test case during simulation. Test objectives evaluate at specific points in the model.
<b>Test Objective block</b>	The block that you add to a model to define test objectives. In the block mask, define test objectives as values or ranges that an input signal must satisfy during a test case.
<b>unsatisfiable test objective</b>	The status of a test objective that indicates a test case cannot be generated for the specified approximations. This includes floating-point approximations and maximum-step limitations specified in the <b>Design Verifier &gt; Test Generation</b> pane of the Configuration Parameters dialog box.
<b>validated property</b>	The status of a property that indicates no counterexample exists, subject to floating-point approximations and the settings specified in the <b>Property Proving</b> pane of the Configuration Parameters dialog box.

