


MATLAB[®]

External Interfaces



MATLAB[®]

R2015a



How to Contact MathWorks



Latest news: www.mathworks.com
Sales and services: www.mathworks.com/sales_and_services
User community: www.mathworks.com/matlabcentral
Technical support: www.mathworks.com/support/contact_us



Phone: 508-647-7000



The MathWorks, Inc.
3 Apple Hill Drive
Natick, MA 01760-2098

MATLAB® External Interfaces

© COPYRIGHT 1984–2015 by The MathWorks, Inc.

The software described in this document is furnished under a license agreement. The software may be used or copied only under the terms of the license agreement. No part of this manual may be photocopied or reproduced in any form without prior written consent from The MathWorks, Inc.

FEDERAL ACQUISITION: This provision applies to all acquisitions of the Program and Documentation by, for, or through the federal government of the United States. By accepting delivery of the Program or Documentation, the government hereby agrees that this software or documentation qualifies as commercial computer software or commercial computer software documentation as such terms are used or defined in FAR 12.212, DFARS Part 227.72, and DFARS 252.227-7014. Accordingly, the terms and conditions of this Agreement and only those rights specified in this Agreement, shall pertain to and govern the use, modification, reproduction, release, performance, display, and disclosure of the Program and Documentation by the federal government (or other entity acquiring for or through the federal government) and shall supersede any conflicting contractual terms or conditions. If this License fails to meet the government's needs or is inconsistent in any respect with federal procurement law, the government agrees to return the Program and Documentation, unused, to The MathWorks, Inc.

Trademarks

MATLAB and Simulink are registered trademarks of The MathWorks, Inc. See www.mathworks.com/trademarks for a list of additional trademarks. Other product or brand names may be trademarks or registered trademarks of their respective holders.

Patents

MathWorks products are protected by one or more U.S. patents. Please see www.mathworks.com/patents for more information.

Revision History

December 1996	First printing	New for MATLAB 5 (release 8)
July 1997	Online only	Revised for MATLAB 5.1 (Release 9)
January 1998	Second printing	Revised for MATLAB 5.2 (Release 10)
October 1998	Third printing	Revised for MATLAB 5.3 (Release 11)
November 2000	Fourth printing	Revised and renamed for MATLAB 6.0 (Release 12)
June 2001	Online only	Revised for MATLAB 6.1 (Release 12.1)
July 2002	Online only	Revised for MATLAB 6.5 (Release 13)
January 2003	Online only	Revised for MATLAB 6.5.1 (Release 13SP1)
June 2004	Online only	Revised for MATLAB 7.0 (Release 14)
October 2004	Online only	Revised for MATLAB 7.0.1 (Release 14SP1)
September 2005	Online only	Revised for MATLAB 7.1 (Release 14SP3)
March 2006	Online only	Revised for MATLAB 7.2 (Release 2006a)
September 2006	Online only	Revised for MATLAB 7.3 (Release 2006b)
March 2007	Online only	Revised for MATLAB 7.4 (Release 2007a)
September 2007	Online only	Revised for MATLAB 7.5 (Release 2007b)
March 2008	Online only	Revised for MATLAB 7.6 (Release 2008a)
October 2008	Online only	Revised for MATLAB 7.7 (Release 2008b)
March 2009	Online only	Revised for MATLAB 7.8 (Release 2009a)
September 2009	Online only	Revised for MATLAB 7.9 (Release 2009b)
March 2010	Online only	Revised for MATLAB 7.10 (Release 2010a)
September 2010	Online only	Revised for MATLAB 7.11 (Release 2010b)
April 2011	Online only	Revised for MATLAB 7.12 (Release 2011a)
September 2011	Online only	Revised for MATLAB 7.13 (Release 2011b)
March 2012	Online only	Revised for MATLAB 7.14 (Release 2012a)
September 2012	Online only	Revised for MATLAB 8.0 (Release 2012b)
March 2013	Online only	Revised for MATLAB 8.1 (Release 2013a)
September 2013	Online only	Revised for MATLAB 8.2 (Release 2013b)
March 2014	Online only	Revised for MATLAB 8.3 (Release 2014a)
October 2014	Online only	Revised for MATLAB 8.4 (Release 2014b)
March 2015	Online only	Revised for MATLAB 8.5 (Release 2015a)

Python Interface Topics

Install Supported Python Implementation	1-3
Install Python Version 2.7	1-3
Install Python Version 3.3 or 3.4	1-3
Call Python from MATLAB	1-4
Call User-Defined Custom Module	1-10
Use Python Numeric Types in MATLAB	1-12
Call Python Methods with Numeric Arguments	1-13
Default Numeric Types	1-14
Use Python array Types in MATLAB	1-15
Pass MATLAB String to Python Method	1-16
Use Python str Type in MATLAB	1-17
Pass MATLAB Backslash Control Character	1-18
Create Python list Variable	1-19
Use Python list Type in MATLAB	1-20
Use Python list of Numeric Types in MATLAB	1-22
Pass Cell Array as Python Sequence Type	1-23
Read Element of Nested list Type	1-25

Use Python tuple Type in MATLAB	1-26
Create Python tuple Variable	1-27
Create Singleton Python tuple Variable	1-28
Create Python dict Variable	1-29
Pass dict Argument to Python Method	1-30
Use Python dict Type in MATLAB	1-31
Convert Python dict Type to MATLAB Structure	1-33
Pass Keyword Arguments	1-34
Index into Python String	1-35
Index into Python list	1-36
Index into Python tuple	1-38
Index into Python dict	1-39
Use Python List as Values in for Loop	1-40
Display Stepped Range of Elements	1-41
Accessing Elements in Python Container Types	1-42
Sequence Types	1-42
Mapping Types	1-43
Size and Dimensions	1-43
Array Support	1-44
Use Zero-Based Indexing for Python Functions	1-44
Viewing Python Numeric Values	1-45
Why Do I See Properties When I Display a Number?	1-45
What Is the L Character Attached to a Number?	1-45
Call Methods on Python Variables	1-47

System and Configuration Requirements	1-49
Python Version Support	1-49
Set Python Version on Windows Platform	1-49
Set Python Version on Mac and Linux Platforms	1-50
64-bit/32-bit Versions of Python on Windows Platforms	1-50
Requirements for Building Python Executable	1-50
Creating a Python Object	1-51
Passing Data to Python	1-54
MATLAB Type to Python Type Mapping	1-54
MATLAB Vector to Python Mapping	1-55
Unsupported MATLAB Types	1-55
Handling Data Returned from Python	1-57
Automatic Python Type to MATLAB Type Mapping	1-57
Explicit Type Conversions	1-57
How MATLAB Represents Python Operators	1-59
Execute Callable Python Object	1-61
Python import and MATLAB import Commands	1-62
Do Not Type “import <i>pythonmodule</i> ”	1-62
Use MATLAB import to Shorten Class or Function Names .	1-62
List, Tuple, and Dictionary Types	1-64
Limitations to Python Support	1-65
Limitations to Indexing into Python Objects	1-66
Undefined variable "py" or function "py.command"	1-67
Python Not Installed	1-67
64-bit/32-bit Versions of Python on Windows Platforms	1-67
MATLAB Cannot Find Python	1-68
Error in User-Defined Python Module	1-68
Python Module Not on Python Search Path	1-68
Module Name Conflicts	1-69
Python Tries to Execute command in Wrong Module	1-69
Help for Python Functions	1-70

Handle Python Exceptions	1-72
Troubleshooting Error Messages	1-73
Python Error: message	1-73
Python Module Errors	1-73
Errors Converting Python Data	1-74
Using Python Data in MATLAB	1-75
Call Python eval Function	1-76
Precedence Order of Methods and Functions	1-78

Read and Write MATLAB MAT-Files in C/C++ and Fortran

2

Writing Custom Applications to Access MAT-Files	2-2
Why Write Custom Applications?	2-2
MAT-File Interface Library	2-3
Exchanging Data Files Between Platforms	2-4
MAT-File Library and Include Files	2-5
MAT-Function Include Files	2-5
MAT-Function Libraries	2-5
Example Files	2-6
What You Need to Build Custom Applications	2-7
Copy External Data into MAT-File Format with Standalone Programs	2-8
Overview of matimport.c Example	2-8
Declare Variables for External Data	2-9
Create mxArray Variables	2-9
Create MATLAB Variable Names	2-10
Read External Data into mxArray Data	2-10
Create and Open MAT-File	2-11
Write mxArray Data to File	2-11
Clean Up	2-11
Build the Application	2-11

Create the MAT-File	2-11
Import Data into MATLAB	2-12
Create MAT-File in C or C++	2-13
Create MAT-File in C	2-13
Create MAT-File in C++	2-13
Read MAT-File in C/C++	2-14
Create MAT-File in Fortran	2-15
Read MAT-File in Fortran	2-16
Work with mxArray	2-17
Read Structures from a MAT-File	2-17
Read Cell Arrays from a MAT-File	2-18
Table of MAT-File Source Code Files	2-19
Building on Mac and Linux Operating Systems	2-21
Setting Run-Time Library Path	2-21
Building the Application	2-22
Building on Windows Operating Systems	2-23
Sharing MAT-File Applications	2-24

Calling C Shared Library Functions from MATLAB

3

Calling Functions in Shared Libraries	3-2
What Is a Shared Library?	3-2
Loading and Unloading the Library	3-3
Viewing Library Functions	3-4
Invoking Library Functions	3-6
Limitations to Shared Library Support	3-8
MATLAB Supports C Library Routines	3-8
Workarounds for Loading C++ Libraries	3-8
Using Bit Fields	3-9

Using Enum Declarations	3-10
Unions Not Supported	3-10
Compiler Dependencies	3-11
Limitations Using Structures	3-11
Limitations Using Pointers	3-11
Functions with Variable Number of Input Arguments Not Supported	3-11
Module Not Found Error	3-13
No Matching Signature Error	3-14
MATLAB Crashes Calling Function in Shared Library	3-15
Passing Arguments to Shared Library Functions	3-16
C and MATLAB Equivalent Types	3-16
Passing Arguments	3-18
Passing a NULL Pointer	3-18
Manually Converting Data Passed to Functions	3-19
Shared Library shrlibsample.c	3-20
Pass String Arguments	3-21
Pass Structures	3-23
Add Values of Fields in Structure	3-23
Preconvert MATLAB Structure Before Adding Values	3-24
Display Structure Field Names	3-25
Pass Enumerated Types	3-26
Call Function with Enumeration String	3-26
Call Function with Integer Equivalent of Enumeration	3-26
Pass Pointers	3-28
Pass Primitive MATLAB Type	3-28
Pass Arrays	3-29
Two Dimensional MATLAB Arrays	3-29
More than Two Dimensional MATLAB Arrays	3-30
Iterate Through an Array	3-32
Create Cell Array from lib.pointer Object	3-32
Perform Pointer Arithmetic on Structure Array	3-33

Working with Pointer Arguments	3-34
Pointer Arguments in C Functions	3-34
Creating a Pointer to a Primitive Type	3-34
Creating a Pointer to a Structure	3-37
Passing a Pointer to the First Element of an Array	3-39
Putting a String into a Void Pointer	3-40
Passing an Array of Strings	3-40
Memory Allocation for an External Library	3-42
Multilevel Pointers	3-43
Working with Structure Arguments	3-45
Structure Argument Requirements	3-45
Finding Structure Field Names	3-45
Strategies for Passing Structures	3-45
Work with libstruct Objects	3-47
MATLAB Prototype Files	3-49
When to Use a Prototype File	3-49
How to Create a Prototype File	3-49
How to Specify a Thunk file	3-50
Deploy Applications That Use loadlibrary	3-50
Use loadlibrary in a Parallel Computing Environment	3-50
Change Function Signature	3-50
Rename Library Function	3-50
Load Subset of Functions in Library	3-50
Call Function with Variable Number of Arguments	3-51

Intro to MEX-Files

4

Introducing MEX-Files	4-3
Using MEX-Files	4-4
MEX-File Placement	4-5
Use Help Files with MEX-Files	4-6

MATLAB Data	4-7
The MATLAB Array	4-7
Lifecycle of mxArray	4-7
Data Storage	4-8
MATLAB Types	4-10
Sparse Matrices	4-11
Using Data Types	4-12
Testing for Most-Derived Class	4-15
Testing for a Category of Types	4-15
Another Test for Built-In Types	4-16
Build MEX-File	4-17
Linking Multiple Files	4-18
What You Need to Build MEX-Files	4-19
Changing Default Compiler	4-20
Windows Systems	4-20
Mac and Linux Systems	4-21
Do Not Use mex -f optionsfile Syntax	4-21
Using MEX Script Options to Custom Build	4-23
Include Files	4-23
Compiling MEX-Files with the Microsoft Visual C++ IDE ..	4-24
Call LAPACK and BLAS Functions	4-26
What You Need to Know	4-26
Creating a MEX-File Using LAPACK and BLAS Functions .	4-26
Preserving Input Values from Modification	4-28
Passing Arguments to Fortran Functions from C/C++	
Programs	4-29
Passing Arguments to Fortran Functions from Fortran	
Programs	4-30
Handling Complex Numbers in LAPACK and BLAS	
Functions	4-31
Modifying the Function Name on UNIX Systems	4-34
Running MEX-Files with .DLL File Extensions on Windows	
32-bit Platforms	4-35

Upgrade MEX-Files to Use 64-Bit API	4-36
MATLAB Support for 64-Bit Indexing	4-36
MEX Uses 32-Bit API by Default	4-36
What If I Do Not Upgrade?	4-38
How to Upgrade MEX-Files to Use the 64-Bit API	4-38
Upgrade MEX-Files to Use Graphics Objects	4-47
Replace mexGet and mexSet Functions	4-47
mex Automatically Converts Handle Type	4-50
I Want to Rebuild MEX Source Code Files	4-50
I Do Not Have MEX Source Code File	4-50
Platform Compatibility	4-52
Verify the MEX-File Is Built For Your Platform	4-52
Verify Your Architecture on Windows Platforms	4-52
Invalid MEX-File Error	4-53
Run MEX-File You Receive from Someone Else	4-54
MEX-File Dependent Libraries	4-55
Document Build Information in the MEX-File	4-56
Version Compatibility	4-58
Getting Help When MEX Fails	4-59
Errors Finding Supported Compiler	4-59
Errors Building MEX Function	4-59
Preview mex Build Commands	4-60
Understanding MEX-File Problems	4-61
Problem 1 — Compiling a Source MEX-File Fails	4-63
Problem 2 — Compiling Your Own Program Fails	4-63
Problem 3 — Binary MEX-File Load Errors	4-64
Problem 4 — Segmentation Fault	4-65
Problem 5 — Program Generates Incorrect Results	4-65
Compiler- and Platform-Specific Issues	4-66
Linux gcc Compiler Version Error	4-66
Linux gcc -fPIC Errors	4-66

Memory Management Issues	4-67
Overview	4-67
Improperly Destroying an mxArray	4-68
Incorrectly Constructing a Cell or Structure mxArray	4-68
Creating a Temporary mxArray with Improper Data	4-69
Creating Potential Memory Leaks	4-70
Improperly Destroying a Structure	4-70
Destroying Memory in a C++ Class Destructor	4-71
 Compiler Errors in Fortran MEX-Files	 4-72

C/C++ MEX-Files

5

Components of MEX-File	5-3
mexFunction Gateway Routine	5-3
Naming the MEX-File	5-3
Required Parameters	5-3
Managing Input and Output Parameters	5-4
Validating Inputs	5-4
Computational Routine	5-5
 MATLAB API Libraries	 5-6
Matrix Library	5-6
MEX Library	5-6
Preprocessor Macros	5-6
 User Messages	 5-8
 Error Handling	 5-9
 Data Flow in MEX-Files	 5-10
Showing Data Input and Output	5-10
Gateway Routine Data Flow Diagram	5-11
 Creating C++ MEX-Files	 5-13
Creating Your C++ Source File	5-13
Compiling and Linking	5-13
Memory Considerations For Class Destructors	5-13
Use mexPrintf to Print to the MATLAB Command Window .	5-14

C++ Class in MEX-Files	5-15
Handle Files with C++	5-16
C++ Example	5-16
C Example	5-16
Create C Source MEX-File	5-18
Table of MEX-File Source Code Files	5-24
Choose a C++ Compiler	5-28
Set Up C/C++ Examples	5-29
Pass Scalar Values	5-30
Pass Scalar as Matrix	5-30
Pass Scalar by Value	5-31
Pass Strings	5-33
Handling Strings in C/C++	5-35
How MATLAB Represents Strings in MEX-Files	5-35
Character Encoding and Multibyte Encoding Schemes	5-35
Converting MATLAB String to C-Style String	5-36
Converting C-Style String to MATLAB String	5-36
Returning Modified Input String	5-36
Memory Management	5-36
Pass Multiple Inputs or Outputs	5-38
Pass Structures and Cell Arrays	5-40
Create 2-D Cell Array	5-41
Fill mxArray	5-42
Options	5-42
Copying Data Directly into an mxArray	5-42
Pointing to Data	5-42
Prompt User for Input	5-44
Handle Complex Data	5-45

Handle 8-, 16-, and 32-Bit Data	5-46
Manipulate Multidimensional Numerical Arrays	5-47
Handle Sparse Arrays	5-49
Call MATLAB Functions from C/C++ MEX-Files	5-50
Debugging on Microsoft Windows Platforms	5-51
Notes on Debugging	5-52
Debugging on Linux Platforms	5-53
Debugging on Mac Platforms	5-55
Using Xcode	5-55
Using LLDB	5-57
Handling Large mxArray Arrays	5-60
Using the 64-Bit API	5-60
Building the Binary MEX-File	5-62
Example	5-62
Caution Using Negative Values	5-62
Building Cross-Platform Applications	5-63
Memory Management	5-64
Automatic Cleanup of Temporary Arrays	5-64
Example	5-65
Persistent Arrays	5-65
Handling Large File I/O	5-67
Prerequisites to Using 64-Bit I/O	5-67
Specifying Constant Literal Values	5-69
Opening a File	5-69
Printing Formatted Messages	5-70
Replacing fseek and ftell with 64-Bit Functions	5-70
Determining the Size of an Open File	5-71
Determining the Size of a Closed File	5-72

Components of Fortran MEX-File	6-2
mexFunction Gateway Routine	6-2
Naming the MEX-File	6-2
Difference Between .f and .F Files	6-2
Required Parameters	6-3
Managing Input and Output Parameters	6-3
Validating Inputs	6-4
Computational Routine	6-4
MATLAB Fortran API Libraries	6-5
Matrix Library	6-5
MEX Library	6-5
Preprocessor Macros	6-5
Using the Fortran %val Construct	6-6
Data Flow in Fortran MEX-Files	6-8
Showing Data Input and Output	6-8
Gateway Routine Data Flow Diagram	6-9
User Messages	6-11
Error Handling	6-12
Build Fortran MEX-File	6-13
Create Fortran Source MEX-File	6-14
Set Up Fortran Examples	6-19
Pass Scalar Values	6-20
Pass Strings	6-21
Pass Arrays of Strings	6-22
Pass Matrices	6-23
Pass Integers	6-24

Pass Multiple Inputs or Outputs	6-25
Handle Complex Data	6-26
Dynamically Allocate Memory	6-27
Handle Sparse Matrices	6-28
Call MATLAB Functions from Fortran MEX-Files	6-29
Debug Fortran Source MEX-Files	6-31
Notes on Debugging	6-31
Debugging on Microsoft Windows Platforms	6-31
Debugging on Linux Platforms	6-31
Handling Large mxArray	6-34
Using the 64-Bit API	6-34
Building the Binary MEX-File	6-36
Caution Using Negative Values	6-36
Building Cross-Platform Applications	6-36
Memory Management	6-37
MATLAB Supports Fortran 77	6-38

Calling MATLAB Engine from C/C++ and Fortran Programs

7

Introducing MATLAB Engine	7-2
Communicating with MATLAB Software	7-3
Callbacks in Applications	7-4
Call MATLAB Functions from C/C++ Applications	7-5
Call MATLAB Functions from Fortran Applications	7-7
Attach to Existing MATLAB Sessions	7-9

Build Windows Engine Application	7-11
Run Windows Engine Application	7-12
Setting Run-Time Library Path on Windows Systems	7-13
Change Path Each Time You Run the Application	7-13
Permanently Change Path	7-13
Troubleshooting	7-14
Registering MATLAB as a COM Server	7-15
Build Linux Engine Application	7-16
Run Linux Engine Application	7-17
Setting Run-Time Library Path on Mac and Linux Systems	7-18
C Shell	7-18
Bourne Shell	7-18
Building Engine Applications with IDE	7-20
Configuring the IDE	7-20
Engine Include Files	7-20
Engine Libraries	7-20
Library Files Required by libeng	7-21
Can't Start MATLAB Engine	7-23
Debugging MATLAB Functions Used in Engine Applications	7-24
Multithreaded Applications	7-25
Getting Started	7-26

MATLAB Engine for Python Topics

8

Get Started with MATLAB Engine for Python	8-2
--	------------

Install MATLAB Engine for Python	8-5
Install MATLAB Engine for Python Without Administrator Privileges	8-5
Start and Stop MATLAB Engine for Python	8-7
Start MATLAB Engine for Python	8-7
Run Multiple Engines	8-7
Stop MATLAB Engine	8-7
Start Engine with Startup Options	8-8
Call MATLAB Functions from Python	8-9
Return Output Argument from MATLAB Function	8-9
Return Multiple Output Arguments from MATLAB Function	8-9
Return No Output Arguments from MATLAB Function	8-9
Stop Execution of Function	8-10
Call MATLAB Functions Asynchronously from Python ...	8-11
Call User Script and Function from Python	8-12
Redirect Standard Output and Error to Python	8-14
Use MATLAB Handle Objects in Python	8-15
Use MATLAB Engine Workspace in Python	8-17
Pass Data to MATLAB from Python	8-18
Python Type to MATLAB Scalar Type Mapping	8-18
Python Container to MATLAB Array Type Mapping	8-18
Unsupported Python Types	8-19
Handle Data Returned from MATLAB to Python	8-20
MATLAB Scalar Type to Python Type Mapping	8-20
MATLAB Array Type to Python Type Mapping	8-21
Unsupported MATLAB Types	8-21
MATLAB Arrays as Python Variables	8-23
Create MATLAB Arrays in Python	8-23
MATLAB Array Attributes and Methods in Python	8-25
Multidimensional MATLAB Arrays in Python	8-25
Index Into MATLAB Arrays in Python	8-25
Slice MATLAB Arrays in Python	8-26
Reshape MATLAB Arrays in Python	8-27

Use MATLAB Arrays in Python	8-28
Sort and Plot MATLAB Data from Python	8-30
Get Help for MATLAB Functions from Python	8-34
How to Find MATLAB Help	8-34
Open MATLAB Help Browser from Python	8-34
Display MATLAB Help at Python Prompt	8-35
Default Numeric Types in MATLAB and Python	8-36
System Requirements for MATLAB Engine for Python ...	8-38
Python Version Support	8-38
64-bit or 32-bit Versions of Python and MATLAB	8-38
Requirements for Building Python from Source	8-39
Limitations to MATLAB Engine for Python	8-40
Troubleshoot MATLAB Errors in Python	8-41
MATLAB Errors in Python	8-41
MatlabExecutionError: Undefined Function	8-41
SyntaxError: Expression Not Valid Target	8-42
SyntaxError: Invalid Syntax	8-42

Using Java Libraries from MATLAB

9

Using Java Libraries	9-2
Java Software Is Integral to MATLAB	9-2
When to Use Java Libraries in MATLAB	9-2
To Learn More About Java Programming Language	9-3
Platform Support for JVM Software	9-3
Bringing Java Classes into MATLAB Workspace	9-4
Introduction	9-4
Sources of Java Classes	9-4
Defining New Java Classes	9-5
Java Class Path	9-5
Making Java Classes Available in MATLAB Workspace	9-6
Loading Java Class Definitions	9-8

Simplifying Java Class Names	9-9
Locating Native Method Libraries	9-10
Java Classes Contained in a JAR File	9-10
Creating and Using Java Objects	9-12
Overview	9-12
Constructing Java Objects	9-12
Concatenating Java Objects	9-14
Saving and Loading Java Objects to MAT-Files	9-15
Finding the Public Data Fields of an Object	9-16
Accessing Private and Public Data	9-17
Determining the Class of an Object	9-18
Invoking Methods on Java Objects	9-20
Calling Syntax	9-20
Obtaining Method Information	9-22
Java Methods That Affect MATLAB Commands	9-25
How MATLAB Handles Undefined Methods	9-26
Handling Java Exceptions	9-27
Method Execution in MATLAB	9-27
Working with Java Arrays	9-28
Introduction	9-28
How MATLAB Represents the Java Array	9-28
Creating an Array of Objects in MATLAB	9-32
Accessing Elements of a Java Array	9-35
Assigning to a Java Array	9-38
Concatenating Java Arrays	9-41
Creating a New Array Reference	9-42
Creating a Copy of a Java Array	9-43
Passing Data to Java Methods	9-45
Introduction	9-45
Conversion of MATLAB Argument Data	9-45
Passing Built-In Types	9-47
Converting Numbers to Integer Arguments	9-48
Passing String Arguments	9-49
Passing Java Objects	9-49
Other Data Conversion Topics	9-52
Passing Data to Overloaded Methods	9-53
Handling Data Returned from Java Methods	9-55
Introduction	9-55

Conversion of Java Return Types	9-55
Conversion of Java Object Return Types	9-56
Built-In Types	9-56
Converting Objects to MATLAB Types	9-57
Read URL	9-61
Overview	9-61
Description of URLdemo	9-61
Running the Example	9-62
Find Internet Protocol Address	9-63
Overview	9-63
Description of resolveip	9-63
Running the Example	9-64
Create and Use Phone Book	9-65
Overview	9-65
Description of Function phonebook	9-66
Description of Function pb_lookup	9-70
Description of Function pb_add	9-70
Description of Function pb_remove	9-71
Description of Function pb_change	9-72
Description of Function pb_listall	9-73
Description of Function pb_display	9-74
Description of Function pb_keyfilter	9-74
Running the phonebook Program	9-75
Java Heap Memory Preferences	9-77

Using .NET Libraries from MATLAB

10

Access a Simple .NET Class	10-4
System.DateTime Example	10-4
Create .NET Object From Constructor	10-5
View Information About .NET Object	10-5
Introduction to .NET Data Types	10-7
Load a Global .NET Assembly	10-9

Work with Microsoft Excel Spreadsheets Using .NET	10-10
Work with Microsoft Word Documents Using .NET	10-12
Assembly is Library of .NET Classes	10-13
Limitations to .NET Support	10-14
System Requirements for Using MATLAB Interface to .NET	10-16
MATLAB Configuration File	10-16
Using .NET from MATLAB	10-17
Benefits of the MATLAB .NET Interface	10-17
Why Use the MATLAB .NET Interface?	10-17
NET Assembly Integration Using MATLAB Compiler SDK	10-18
To Learn More About the .NET Framework	10-18
Using a .NET Object	10-19
Creating a .NET Object	10-19
What Classes Are in a .NET Assembly?	10-19
Using the delete Function on a .NET Object	10-20
Build a .NET Application for MATLAB Examples	10-21
Troubleshooting Security Policy Settings From Network Drives	10-22
.NET Terminology	10-23
.NET Framework System Namespace	10-23
Reference Type Versus Value Type	10-23
Simplify .NET Class Names	10-24
Use import in MATLAB Functions	10-25
Nested Classes	10-26
Handle .NET Exceptions	10-27
Pass Numeric Arguments	10-28
Call .NET Methods with Numeric Arguments	10-28
Use .NET Numeric Types in MATLAB	10-28

Pass System.String Arguments	10-29
Call .NET Methods with System.String Arguments	10-29
Use System.String in MATLAB	10-29
Pass System.Enum Arguments	10-31
Call .NET Methods with System.Enum Arguments	10-31
Use System.Enum in MATLAB	10-32
Pass System.Nullable Arguments	10-33
Pass Cell Arrays of .NET Data	10-37
Example of Cell Arrays of .NET Data	10-37
Create a Cell Array for Each System.Object	10-38
Create MATLAB Variables from the .NET Data	10-38
Call MATLAB Functions with MATLAB Variables	10-38
Pass Jagged Arrays	10-40
Create System.Double .NET Jagged Array	10-40
Call .NET Method with System.String Jagged Array Arguments	10-40
Call .NET Method with Multidimensional Jagged Array Arguments	10-41
Convert Nested System.Object Arrays	10-43
Passing Data to .NET Objects	10-44
Pass Primitive .NET Types	10-44
Pass Cell Arrays	10-45
Pass Nonprimitive .NET Objects	10-46
Pass MATLAB Strings	10-46
Pass System.Nullable Type	10-46
Pass NULL Values	10-47
Unsupported MATLAB Types	10-47
Choosing Method Signatures	10-47
Example — Choosing a Method Signature	10-48
Pass Arrays	10-49
Pass MATLAB Arrays as Jagged Arrays	10-50
Handling Data Returned from .NET Objects	10-51
.NET Type to MATLAB Type Mapping	10-51
How MATLAB Handles System.String	10-52
How MATLAB Handles System.__ComObject	10-53
How MATLAB Handles System.Nullable	10-54

How MATLAB Handles dynamic Type	10-55
How MATLAB Handles Jagged Arrays	10-55
Using Arrays with .NET Applications	10-56
Passing MATLAB Arrays to .NET	10-56
Accessing .NET Array Elements in MATLAB	10-56
Converting .NET Arrays to Cell Arrays	10-57
Converting .NET Jagged Arrays to MATLAB Arrays	10-59
Limitations to Support of .NET Arrays	10-59
Set Static .NET Properties	10-60
System.Environment.CurrentDirectory Example	10-60
Do Not Use ClassName.PropertyName Syntax for Static Properties	10-60
Using .NET Properties	10-62
How MATLAB Represents .NET Properties	10-62
How MATLAB Maps C# Property and Field Access Modifiers	10-62
MATLAB Does Not Display Protected Properties	10-64
Work with .NET Methods Having Multiple Signatures ...	10-65
Display Function Signature Example	10-66
SampleMethods Class	10-67
Call .NET Methods With out Keyword	10-69
Call .NET Methods With ref Keyword	10-70
Call .NET Methods With params Keyword	10-71
Call .NET Methods with Optional Arguments	10-72
Setting Up the Examples	10-72
Skip Optional Arguments	10-72
Call Overloaded Methods	10-73
Calling .NET Methods	10-75
Calling Object Methods	10-75
Getting Method Information	10-75
C# Method Access Modifiers	10-75
VB.NET Method Access Modifiers	10-76

Reading Method Signatures	10-76
Calling .NET Generic Methods	10-77
Calling .NET Methods with Optional Arguments	10-78
Skipping Optional Arguments	10-78
Determining Which Overloaded Method Is Invoked	10-78
Support for ByRef Attribute in VB.NET	10-78
Calling .NET Extension Methods	10-79
Call .NET Properties That Take an Argument	10-80
How MATLAB Represents .NET Operators	10-82
Limitations to Support of .NET Methods	10-83
Overloading MATLAB Functions	10-83
Use .NET Events in MATLAB	10-84
Monitor Changes to .TXT File	10-84
Monitor Changes to Windows Form ComboBox	10-84
Call .NET Delegates in MATLAB	10-86
Declare a Delegate in a C# Assembly	10-86
Load the Assembly Containing the Delegate into MATLAB	10-86
Select a MATLAB Function	10-86
Create an Instance of the Delegate in MATLAB	10-87
Invoke the Delegate Instance in MATLAB	10-87
Create Delegates from .NET Object Methods	10-88
Create Delegate Instances Bound to .NET Methods	10-89
Example — Create a Delegate Instance Associated with a .NET Object Instance Method	10-89
Example — Create a Delegate Instance Associated with a Static .NET Method	10-90
Call Delegates With out and ref Type Arguments	10-91
Combine and Remove .NET Delegates	10-92
.NET Delegates	10-94

Calling .NET Methods Asynchronously	10-95
How MATLAB Handles Asynchronous Method Calls in .NET	10-95
Calling a Method Asynchronously Using a Callback When an Asynchronous Call Finishes	10-95
Calling a Method Asynchronously Without a Callback	10-97
Using EndInvoke With out and ref Type Arguments	10-98
Using Polling to Detect When Asynchronous Call Finishes	10-98
Limitations to Support of .NET Events	10-99
MATLAB Support of Standard Signature of an Event Handler Delegate	10-99
Limitations to Support of .NET Delegates	10-100
Use Bit Flags with .NET Enumerations	10-101
How MATLAB Supports Bit-Wise Operations on System.Enum	10-101
Creating .NET Enumeration Bit Flags	10-101
Removing a Flag from a Variable	10-102
Replacing a Flag in a Variable	10-102
Testing for Membership	10-103
Read Special System Folder Path	10-105
.NET Enumerations in MATLAB	10-106
Default Methods for an Enumeration	10-107
NetDocEnum Example Assembly	10-109
Work with Members of a .NET Enumeration	10-110
Refer to a .NET Enumeration Member	10-112
Using the Implicit Constructor	10-112
Display .NET Enumeration Members as Character Strings	10-114
Convert .NET Enumeration Values to Type Double	10-115
Iterate Through a .NET Enumeration	10-116
Information About System.Enum Methods	10-116

Display Enumeration Member Names	10-117
Use .NET Enumerations to Test for Conditions	10-118
Using Switch Statements	10-118
Using Relational Operations	10-118
Underlying Enumeration Values	10-120
Limitations to Support of .NET Enumerations	10-121
Create .NET Collections	10-122
Convert .NET Collections to MATLAB Arrays	10-124
Create .NET Arrays of Generic Type	10-125
Display .NET Generic Methods Using Reflection	10-126
showGenericMethods Function	10-126
Display Generic Methods in a Class	10-127
Display Generic Methods in a Generic Class	10-128
.NET Generic Classes	10-129
Accessing Items in .NET Collections	10-130
Call .NET Generic Methods	10-131
Using the NetDocGeneric Example	10-131
Invoke Generic Class Member Function	10-132
Invoke Static Generic Functions	10-132
Invoke Static Generic Functions of a Generic Class	10-132
Invoke Generic Functions of a Generic Class	10-133

Using COM Objects from MATLAB

11

MATLAB COM Integration	11-2
What Is COM?	11-2
Concepts and Terminology	11-2
The MATLAB COM Client	11-4
The MATLAB COM Automation Server	11-4

Registering Controls and Servers	11-5
Getting Started with COM	11-7
Introduction to COM	11-7
Basic COM Functions	11-7
Use Internet Explorer in MATLAB Figure	11-10
Techniques Demonstrated	11-10
Using the Figure to Access Properties	11-10
Complete Code Listing	11-11
Creating the Figure	11-12
Calculating the ActiveX Object Container Size	11-12
Automatic Resize	11-13
Selecting Graphics Objects	11-13
Add Grid ActiveX Control in a Figure	11-15
Techniques Demonstrated	11-15
Using the Control	11-15
Complete Code Listing	11-16
Preparing to Use the Control	11-17
Creating a Figure to Contain the Control	11-18
Creating an Instance of the Control	11-19
Using Mouse-Click Event to Plot Data	11-20
Managing Figure Resize	11-21
Closing the Figure	11-22
Read Excel Spreadsheet Data	11-23
Techniques Demonstrated	11-23
Using the UI	11-23
Complete Code Listing	11-24
Excel Spreadsheet Format	11-24
Excel Automation Server	11-25
Manipulating the Data in the MATLAB Workspace	11-26
The Plotter UI	11-26
Inserting MATLAB Graphs Into Excel Spreadsheets	11-28
Supported Client/Server Configurations	11-30
Introduction	11-30
MATLAB Client and In-Process Server	11-30
MATLAB Client and Out-of-Process Server	11-31
COM Implementations Supported by MATLAB Software ..	11-32
Client Application and MATLAB Automation Server	11-32
Client Application and MATLAB Engine Server	11-33

Creating COM Objects	12-2
Creating the Server Process — An Overview	12-2
Creating an ActiveX Control	12-3
Creating a COM Server	12-9
Explore COM Objects	12-11
About Your Object	12-11
Exploring Properties	12-11
Exploring Methods	12-12
Exploring Events	12-13
Exploring Interfaces	12-14
Identifying Objects and Interfaces	12-15
Use Object Properties	12-17
About Object Properties	12-17
Working with Multiple Objects	12-17
Using Enumerated Values for Properties	12-18
Using the Property Inspector	12-20
Custom Properties	12-21
Properties That Take Arguments	12-22
Use Methods	12-26
About Methods	12-26
Getting Method Information	12-26
Invoking Methods on an Object	12-31
Exceptions to Using Implicit Syntax	12-32
Specifying Enumerated Parameters	12-34
Optional Input Arguments	12-35
Returning Multiple Output Arguments	12-36
Argument Callouts in Error Messages	12-36
Use Events	12-38
About Events	12-38
Functions for Working with Events	12-39
Examples of Event Handlers	12-39
Responding to Events — an Overview	12-39
Responding to Events — Examples	12-41
Writing Event Handlers	12-49
Sample Event Handlers	12-51
Writing Event Handlers as MATLAB Local Functions	12-52

Getting Interfaces to COM Object	12-54
IUnknown and IDispatch Interfaces	12-54
Custom Interfaces	12-55
Save COM Objects	12-57
Functions for Saving and Restoring COM Objects	12-57
Releasing COM Interfaces and Objects	12-58
Handling COM Data in MATLAB Software	12-59
Passing Data to COM Objects	12-59
Handling Data from COM Objects	12-61
Unsupported Types	12-62
Passing MATLAB Data to ActiveX Objects	12-62
Passing MATLAB SAFEARRAY to COM Object	12-62
Reading SAFEARRAY from COM Objects in MATLAB Applications	12-64
Displaying MATLAB Syntax for COM Objects	12-65
Use MATLAB Application as Automation Client	12-68
MATLAB Sample Control	12-68
Using a MATLAB Application as an Automation Client	12-68
Connecting to an Existing Excel Application	12-69
Running a Macro in an Excel Server Application	12-70
MATLAB COM Client Example	12-71
Deploy ActiveX Controls Requiring Run-Time Licenses ..	12-72
Create a Function to Build the Control	12-72
Build the Control and the License File	12-72
Build the Executable	12-73
Deploy the Files	12-73
Use Microsoft Forms 2.0 Controls	12-74
Affected Controls	12-74
Replacement Controls	12-74
Use COM Collections	12-76
Use MATLAB Application as DCOM Client	12-77
MATLAB COM Support Limitations	12-78

Register MATLAB as Automation Server	13-2
When to Register MATLAB	13-2
Register from System Prompt	13-2
Register from MATLAB Command Prompt	13-3
MATLAB COM Automation Server Interface	13-4
COM Server Types	13-4
Shared and Dedicated Servers	13-4
Programmatic Identifiers	13-4
In-Process and Out-of-Process Servers	13-5
Creating the MATLAB Server	13-7
Getting Started	13-7
Get or Set the Status of a MATLAB Automation Server ...	13-8
Connecting to an Existing MATLAB Server	13-9
Using Visual Basic .NET Code	13-9
Using MATLAB Application as DCOM Server	13-10
Using VT_DATE Data Type	13-11
Data Types For Visual Basic .NET Clients	13-12
Using the Visible Property	13-13
Specifying Shared or Dedicated Server	13-14
Starting a Shared Server	13-14
Starting a Dedicated Server	13-14
Manually Create Automation Server	13-15
Launch MATLAB as Automation Server in Desktop Mode	13-16
Call MATLAB Function from Visual Basic .NET Client ...	13-17
Pass Complex Data to MATLAB from C# Client	13-18
Call MATLAB Function from C# Client	13-20

View MATLAB Functions from Visual Basic .NET Object Browser	13-22
Waiting for MATLAB Application to Complete	13-23

Using Web Services with MATLAB

14

Set Up WSDL Tools	14-2
Display a World Map	14-3
Using WSDL Web Service with MATLAB	14-8
What Are Web Services in MATLAB?	14-8
What are WSDL Documents?	14-8
What You Need to Use WSDL with MATLAB	14-9
Access Services That Use WSDL Documents	14-10
Error Handling	14-12
Considerations Using Web Services	14-12
Error Handling with try/catch Statements	14-12
Use a Local Copy of the WSDL Document	14-12
Java Errors Accessing Service	14-13
Anonymous Types Not Supported	14-13
XML-MATLAB Data Type Conversion	14-14
Limitations to WSDL Document Support	14-16

Serial Port I/O

15

Capabilities and Supported Interfaces and Platforms	15-2
What Is the MATLAB Serial Port Interface?	15-2
Supported Serial Port Interface Standards	15-3
Supported Platforms	15-3

Using the Examples with Your Device	15-3
Overview of the Serial Port	15-4
Introduction	15-4
What Is Serial Communication?	15-4
The Serial Port Interface Standard	15-4
Connecting Two Devices with a Serial Cable	15-5
Serial Port Signals and Pin Assignments	15-6
Serial Data Format	15-10
Finding Serial Port Information for Your Platform	15-13
Using Virtual USB Serial Ports	15-15
Selected Bibliography	15-15
Getting Started with Serial I/O	15-16
Example: Getting Started	15-16
The Serial Port Session	15-16
Configuring and Returning Properties	15-17
Creating a Serial Port Object	15-22
Overview of a Serial Port Object	15-22
Configuring Properties During Object Creation	15-23
The Serial Port Object Display	15-24
Creating an Array of Serial Port Objects	15-24
Connecting to the Device	15-26
Configuring Communication Settings	15-27
Writing and Reading Data	15-28
Before You Begin	15-28
Example — Introduction to Writing and Reading Data ...	15-28
Controlling Access to the MATLAB Command Line	15-29
Writing Data	15-30
Reading Data	15-35
Example — Writing and Reading Text Data	15-41
Example — Parsing Input Data Using textscan	15-42
Example — Reading Binary Data	15-43
Events and Callbacks	15-46
Introduction	15-46
Example — Introduction to Events and Callbacks	15-46
Event Types and Callback Properties	15-47
Responding To Event Information	15-49

Creating and Executing Callback Functions	15-51
Enabling Callback Functions After They Error	15-52
Example — Using Events and Callbacks	15-52
Using Control Pins	15-54
Properties of Serial Port Control Pins	15-54
Signaling the Presence of Connected Devices	15-54
Controlling the Flow of Data: Handshaking	15-57
Debugging: Recording Information to Disk	15-60
Introduction	15-60
Recording Properties	15-60
Example: Introduction to Recording Information	15-61
Creating Multiple Record Files	15-61
Specifying a Filename	15-61
The Record File Format	15-62
Example: Recording Information to Disk	15-63
Saving and Loading	15-66
Using save and load	15-66
Using Serial Port Objects on Different Platforms	15-66
Disconnecting and Cleaning Up	15-68
Disconnecting a Serial Port Object	15-68
Cleaning Up the MATLAB Environment	15-68
Property Reference	15-70
The Property Reference Page Format	15-70
Serial Port Object Properties	15-70
Properties — Alphabetical List	15-74

Hardware Support

16

Support Package Installation	16-2
What Is a Support Package?	16-2
Install Support Packages	16-2
Install Downloaded Support Package on Multiple Computers	16-3

Troubleshoot Timed Out Connections	16-4
Support Package Installer Help	16-5
About Support Package Installer	16-5
Select an Action	16-6
Select Support Package to Install or Select Support Package to	
Download	16-7
Log In to MathWorks Account	16-10
The MathWorks, Inc. Software License Agreement	16-12
Third-Party Software Licenses	16-13
Confirm Installation, Confirm Download, Confirm	
Uninstall	16-14
Install or Update Complete, Download Complete, Uninstall	
Complete	16-15
Set Up Support Package	16-16
Support Package Setup Complete	16-18
Special Instructions	16-18
MATLAB Supported Hardware	16-19

Python Interface Topics

- “Install Supported Python Implementation” on page 1-3
- “Call Python from MATLAB” on page 1-4
- “Call User-Defined Custom Module” on page 1-10
- “Use Python Numeric Types in MATLAB” on page 1-12
- “Call Python Methods with Numeric Arguments” on page 1-13
- “Default Numeric Types” on page 1-14
- “Use Python array Types in MATLAB” on page 1-15
- “Pass MATLAB String to Python Method” on page 1-16
- “Use Python str Type in MATLAB” on page 1-17
- “Pass MATLAB Backslash Control Character” on page 1-18
- “Create Python list Variable” on page 1-19
- “Use Python list Type in MATLAB” on page 1-20
- “Use Python list of Numeric Types in MATLAB” on page 1-22
- “Pass Cell Array as Python Sequence Type” on page 1-23
- “Read Element of Nested list Type” on page 1-25
- “Use Python tuple Type in MATLAB” on page 1-26
- “Create Python tuple Variable” on page 1-27
- “Create Singleton Python tuple Variable” on page 1-28
- “Create Python dict Variable” on page 1-29
- “Pass dict Argument to Python Method” on page 1-30
- “Use Python dict Type in MATLAB” on page 1-31
- “Convert Python dict Type to MATLAB Structure” on page 1-33
- “Pass Keyword Arguments” on page 1-34
- “Index into Python String” on page 1-35
- “Index into Python list” on page 1-36

- “Index into Python tuple” on page 1-38
- “Index into Python dict” on page 1-39
- “Use Python List as Values in for Loop” on page 1-40
- “Display Stepped Range of Elements” on page 1-41
- “Accessing Elements in Python Container Types” on page 1-42
- “Viewing Python Numeric Values” on page 1-45
- “Call Methods on Python Variables” on page 1-47
- “System and Configuration Requirements” on page 1-49
- “Creating a Python Object” on page 1-51
- “Passing Data to Python” on page 1-54
- “Handling Data Returned from Python” on page 1-57
- “How MATLAB Represents Python Operators” on page 1-59
- “Execute Callable Python Object” on page 1-61
- “Python import and MATLAB import Commands” on page 1-62
- “List, Tuple, and Dictionary Types” on page 1-64
- “Limitations to Python Support” on page 1-65
- “Limitations to Indexing into Python Objects” on page 1-66
- “Undefined variable "py" or function "py.command"” on page 1-67
- “Help for Python Functions” on page 1-70
- “Handle Python Exceptions” on page 1-72
- “Troubleshooting Error Messages” on page 1-73
- “Using Python Data in MATLAB” on page 1-75
- “Call Python eval Function” on page 1-76
- “Precedence Order of Methods and Functions” on page 1-78

Install Supported Python Implementation

In this section...
“Install Python Version 2.7” on page 1-3
“Install Python Version 3.3 or 3.4” on page 1-3

Install Python Version 2.7

- Access <https://www.python.org/downloads> and scroll down to the Looking for a specific release section.
- Find the 2.7 version you want and click Download.
- Click the format you want, and follow the online instructions.

Note: For 64-bit MATLAB[®] on Microsoft[®] Windows[®] systems, select the 64-bit Python[®] version, called Windows x86-64 MSI installer.

Install Python Version 3.3 or 3.4

- Access <https://www.python.org/downloads> and scroll down to the Looking for a specific release section.
- Find the 3.3/3.4 version you want and click Download.
- Click the format you want, and follow the online instructions.

Note: For 64-bit MATLAB on Windows systems, select the 64-bit Python version, called Windows x86-64 MSI installer.

Call Python from MATLAB

These examples show how to use Python® language functions and modules within MATLAB®. The first example calls a text-formatting module from the Python standard library. The second example shows how to use a third-party module, Beautiful Soup. If you want to run that example, follow the guidelines in the step for installing the module.

MATLAB supports the reference implementation of Python, often called CPython, versions 2.7, 3.3, and 3.4. If you are on a Mac or Linux platform, you already have Python installed. If you are on Windows, you need to install a distribution, such as those found at <https://www.python.org/download>, if you have not already done so. For more information, see “Install Supported Python Implementation”.

Call a Python Function to Wrap Text in a Paragraph

MATLAB has equivalencies for much of the Python standard library, but not everything. For example, `textwrap` is a module for formatting blocks of text with carriage returns and other conveniences. MATLAB also provides a `textwrap` function, but it only wraps text to fit inside a UI control.

Create a paragraph of text to play with.

```
T = 'MATLAB(R) is a high-level language and interactive environment for numerical computing and data analysis.'
```

Convert a Python String to a MATLAB String

Call the `textwrap.wrap` function by typing the characters `py.` in front of the function name. Do not type `import textwrap`.

```
wrapped = py.textwrap.wrap(T);  
whos wrapped
```

Name	Size	Bytes	Class	Attributes
wrapped	1x7	112	py.list	

`wrapped` is a Python list, which is a list of Python strings. MATLAB shows this type as `py.list`.

Convert `py.list` to a cell array of Python strings.

```
wrapped = cell(wrapped);  
whos wrapped
```

Name	Size	Bytes	Class	Attributes
wrapped	1x7	1568	cell	

Although `wrapped` is a MATLAB cell array, each cell element is a Python string.

```
wrapped{1}
```

```
ans =
```

```
Python str with no properties.
```

```
MATLAB(R) is a high-level language and interactive environment for
```

Convert the Python strings to MATLAB strings using the `char` function.

```
wrapped = cellfun(@char, wrapped, 'UniformOutput', false);
wrapped{1}
```

```
ans =
```

```
MATLAB(R) is a high-level language and interactive environment for
```

Now each cell element is a MATLAB string.

Customize the Paragraph

Customize the output of the paragraph using keyword arguments.

The previous code uses the `wrap` convenience function, but the module provides many more options using the `py.textwrap.TextWrapper` functionality. To use the options, call `py.textwrap.TextWrapper` with keyword arguments described at <https://docs.python.org/2/library/textwrap.html#textwrap.TextWrapper>.

Create keyword arguments using the MATLAB `pyargs` function with a comma-separated list of name/value pairs. `width` formats the text to be 30 characters wide. The `initial_indent` and `subsequent_indent` keywords begin each line with the comment character, `%`, used by MATLAB.

```
tw = py.textwrap.TextWrapper(pyargs(...
```

```
    'initial_indent', '% ', ...
    'subsequent_indent', '% ', ...
    'width', int32(30));
wrapped = wrap(tw,T);
```

Convert to a MATLAB argument and display the results.

```
wrapped = cellfun(@char, cell(wrapped), 'UniformOutput', false);
fprintf('%s\n', wrapped{:})
```

```
% MATLAB(R) is a high-level
% language and interactive
% environment for numerical
% computation, visualization,
% and programming. Using
% MATLAB, you can analyze
% data, develop algorithms,
% and create models and
% applications. The language,
% tools, and built-in math
% functions enable you to
% explore multiple approaches
% and reach a solution faster
% than with spreadsheets or
% traditional programming
% languages, such as C/C++ or
% Java(TM).
```

Use Beautiful Soup, a Third-Party Python Module

This example shows how to use a third-party module, Beautiful Soup, a tool for parsing HTML. If you want to run the example, you need to install this module using `apt-get`, `pip`, `easy_install`, or other tool you use to install Python modules.

First, find a Web page that includes a table of data. This example uses a table of the population of the world from the following English-language Wikipedia site. This example assumes the first table contains the population data, and assumes the country name is in the second column and the third column contains the population.

```
html = webread('http://en.wikipedia.org/wiki/List_of_countries_by_population');
soup = py.bs4.BeautifulSoup(html);
```

Next, extract all of the table data from the HTML, creating a cell array. If you want a deeper understanding of what is happening, refer to the documentation for Beautiful Soup.

```
tables = soup.find_all('table');
t = cell(tables);
```

The first table is the one of interest; extract its rows.

```
c = cell(t{1}.find_all('tr'));
c = cell(c)';
```

Now loop over the cell array, extracting the country name and population from each row, found in the second and third columns respectively.

```
countries = cell(size(c));
populations = nan(size(c));

for i = 1:numel(c)
    row = c{i};
    row = cell(row.find_all('td'));
    if ~isempty(row)
        countries{i} = char(row{2}.get_text());
        populations(i) = str2double(char(row{3}.get_text()));
    end
end
```

Finally, create a MATLAB table from the data, and eliminate any lingering `nan` values; these NaNs represented invalid rows when importing the HTML.

```
data = table(countries, populations, ...
    'VariableNames', {'Country', 'Population'});
data = data(~isnan(data.Population), :);
```

Trim the tail end of the table and make a pie chart


```
restofWorldPopulation = sum(data.Population(11:end));
data = data(1:10, :);
data = [data; table({' Rest of World'}, restofWorldPopulation, ...
    'VariableNames', {'Country', 'Population'})]
pie(data.Population)
legend(data.Country, 'Location', 'EastOutside');
title('Distribution of World Population')
```

```
data =
```

Country	Population
---------	------------

'China[8]'	1.3682e+09
'India'	1.2634e+09
'United States'	3.192e+08
'Indonesia'	2.5216e+08
'Brazil'	2.0353e+08
'Pakistan'	1.8831e+08
'Nigeria'	1.7852e+08
'Bangladesh'	1.5742e+08
'Russia[9]'	1.4623e+08
'Japan'	1.2708e+08
'Rest of World'	2.9697e+09

Distribution of World Population



Learn More

It is sufficient to remember that Python is yet another potential source of libraries for the MATLAB user. If you want to learn about moving data between MATLAB and Python, including Python data types such as tuples and dictionaries, see “Call Python Libraries”.

Call User-Defined Custom Module

This example shows how to call methods from the following Python module. This module contains functions used by examples in this documentation.

Change your current folder to a writable folder.

Open a new file in MATLAB Editor.

Copy these commands and save the file as `mymod.py`.

```
# mymod.py
"""Python module demonstrates passing MATLAB types to Python functions"""
def search(words):
    """Return list of words containing 'son'"""
    newlist = [w for w in words if 'son' in w]
    return newlist

def theend(words):
    """Append 'The End' to list of words"""
    words.append('The End')
    return words
```

Add the current folder to the Python search path.

```
if count(py.sys.path, '') == 0
    insert(py.sys.path,int32(0), '');
end
```

Read the function signature for the `search` function. The function takes one input argument, `words`.

```
def search(words):
```

Read the function help. According to the Python website documentation, help is in “a string literal that occurs as the first statement in a module, function, class, or method definition.” The help for `search` is:

```
"""Return list of words containing 'son'"""
```

The function returns a list.

Create the input argument, a list of names.


```
N = py.list({'Jones', 'Johnson', 'James'})
```

```
N =
```

```
Python list with no properties.
```

```
['Jones', 'Johnson', 'James']
```

Call the `search` function. Type `py.` in front of the module name and function name.

```
names = py.mymod.search(N)
```

```
names =
```

```
Python list with no properties.
```

```
['Johnson']
```

The function returns a `py.list` value.

The original input, `N` is unchanged.

```
N
```

```
N =
```

```
Python list with no properties.
```

```
['Jones', 'Johnson', 'James']
```

External Web Sites

- [PEP 257 -- Docstring Conventions](#)

Use Python Numeric Types in MATLAB

This example shows how to use Python numbers in MATLAB. The trigonometry functions in the `math` module return Python `float` types. MATLAB automatically converts this type to `double`.

```
pynum = py.math.radians(90)
class(pynum)
```

```
pynum =
    1.5708
```

```
ans =
double
```

More About

- “Passing Data to Python” on page 1-54

Call Python Methods with Numeric Arguments

This example shows how to call the Python `math.fsum` function, which sums the floating-point values in an `iterable` input argument.

Open the MATLAB `patients.mat` sample data file and read the numeric array, `Height`.

```
load patients.mat
class(Height)
```

```
ans =
```

```
double
```

MATLAB automatically converts the numeric values to Python numeric values. However, `Height` is a 100-by-1 array, and MATLAB must pass a 1-by-N array to a Python `iterable` argument.

```
size(Height)
```

```
ans =
```

```
    100     1
```

Transform `Height` to a 1-by-N matrix before calling `fsum`.

```
py.math.fsum(Height')
```

```
ans =
```

```
    6707
```

More About

- “Passing Data to Python” on page 1-54

Default Numeric Types

By default, a number in MATLAB is a `double` type. By default, a number (without a fractional part) in Python is an integer type. This difference can cause confusion when passing numbers to Python functions.

For example, when you pass the following MATLAB numbers to the Python `datetime` function, Python reads them as `float` types.

```
d = py.datetime.date(2014,12,31)
```

```
Python Error: integer argument expected, got float
```

Explicitly convert each number to an integer type:

```
d = py.datetime.date(int32(2014),int32(12),int32(31))
```

```
d =
```

```
Python date with properties:
```

```
    day: 31  
  month: 12  
   year: 2014
```

```
2014-12-31
```

Use Python array Types in MATLAB

This example shows how to sum the elements of a Python `array.array` of type `double`.

Suppose that you have a Python function that returns the following array, `P`.

```
P =
```

```
Python array with properties:
```

```
  itemsize: 8
```

```
  typecode: [1x1 py.str]
```

```
  array('d', [1.0, 2.0, 3.0, 4.0, 5.0])
```

Convert `P` to a MATLAB array of type `double`.

```
A = double(P);
```

Sum the elements of `A`.

```
sum(A)
```

```
ans =
```

```
    15
```

Pass MATLAB String to Python Method

This example shows how to display the contents of a folder using the Python `os.listdir` method. The `listdir` method returns a list containing the names of the entries in the folder given by the path input argument.

Create a MATLAB string representing a valid folder.

```
folder = fullfile(matlabroot, 'help', 'examples');
```

Pass the string to the `os.listdir` function. MATLAB automatically converts `folder` to the Python `str` type.

```
F = py.os.listdir(folder)
```

```
F =
```

```
Python list with no properties.
```

```
['graphics', 'graphics2', 'matlab']
```

MATLAB displays a list of folders, based on your product.

More About

- “Passing Data to Python” on page 1-54

Use Python str Type in MATLAB

This example shows how to use the Python path separator character (;).

```
p = py.os.path.pathsep
p =
    Python str with no properties.
    ;
```

In MATLAB, a Python character is a `py.str` variable.

MATLAB uses the same path separator character, ;.

```
c = pathsep
c =
    ;
```

Compare the MATLAB variable type to the Python type.

```
isequal(class(p),class(c))
ans =
    0
```

A `py.str` type is not equivalent to a MATLAB `char` type.

Convert `p` to a MATLAB type and append the character to a file name.

```
f = ['myfile' char(p)]
f =
    myfile;
```

More About

- “Explicit Type Conversions” on page 1-57

Pass MATLAB Backslash Control Character

This example shows how to pass the backslash control character (\) to a Python `str` type.

Call the MATLAB `sprintf` function to insert the `\n` new line control character.

```
py.str(sprintf('The rain\nin Spain.'))
```

```
ans =
```

```
Python str with no properties.
```

```
The rain  
in Spain.
```

Python replaces `\n` with a new line.

Without the `sprintf` function, both MATLAB and Python interpret `\` as a literal backslash.

```
py.str(('The rain\nin Spain.'))
```

```
ans =
```

```
Python str with no properties.
```

```
The rain\nin Spain.
```

Pass this string to a Python string function, `split`.

```
split(py.str(('The rain\nin Spain.')))
```

```
ans =
```

```
Python list with no properties.
```

```
['The', 'rain\\nin', 'Spain.']
```

Python treats the MATLAB string as a *raw string* and adds a `\` character to preserve the original backslash.

Create Python list Variable

This example shows how to create a `list` variable to pass to a Python function.

```
students = py.list({'Robert', 'Mary', 'Joseph'})
```

```
students =
```

```
    Python list with no properties.
```

```
    ['Robert', 'Mary', 'Joseph']
```

Display number of students in the list.

```
n = py.len(students)
```

```
n =
```

```
    3
```

More About

- “List, Tuple, and Dictionary Types” on page 1-64

Use Python list Type in MATLAB

This example shows how to display folders on your system using the MATLAB `disp` function on the Python `sys.path` variable. `sys.path` is a list type.

Create a Python list, `P`, of folders on the Python search path.

```
P = py.sys.path;  
class(P)
```

```
ans =
```

```
py.list
```

Convert list `P` to a MATLAB type. The first step is to convert the list to a cell array of folder names, `cP`.

```
cP = cell(P);  
class(cP)
```

```
ans =
```

```
cell
```

Each folder name is a Python string.

```
class(cP{1})
```

```
ans =
```

```
py.str
```

Convert the Python strings in `cP` to MATLAB strings using the `char` function. Put the values into a new cell array, `cellP`. Display the folder names.

```
cellP = cell(1, numel(cP));  
for n=1:numel(cP)  
    strP = char(cP{n});  
    cellP(n) = {strP};  
    disp(strP)  
end
```

```
C:\Python27\lib\site-packages\protobuf-2.5.0-py2.7.egg  
C:\windows\system32\python27.zip  
C:\Python27\DLLs
```

```
C:\Python27\lib  
C:\Python27\lib\plat-win  
C:\Python27\lib\lib-tk  
C:\Python27  
C:\Python27\lib\site-packages
```

MATLAB displays information specific to your Python installation.

Alternatively, create `cellP` using the `cellfun` function to combine the conversion functions.

```
cellP = cellfun(@char,cell(P), 'UniformOutput', false);
```

Display the folder names.

```
for n=1:py.len(P)  
    disp(cellP{n})  
end
```

See Also

`cell` | `cellfun`

More About

- “Handling Data Returned from Python” on page 1-57

Use Python list of Numeric Types in MATLAB

This example shows how to convert a Python `list` of numeric values into a MATLAB array of double.

A Python list contains elements of any type and can contain elements of mixed types. The MATLAB `double` function used in this example assumes all elements of the Python list are numeric.

Suppose that you have a Python function that returns the following `list` of integers, `P`.

```
P =
```

```
Python list with no properties.
```

```
[1, 2, 3, 4]
```

Display the numeric type of the values.

```
class(P{1})
```

```
ans =
```

```
int64
```

Convert `P` to a MATLAB cell array.

```
cP = cell(P);
```

Convert the cell array to a MATLAB array of double.

```
A = cellfun(@double,cP)
```

```
A =
```

```
1 2 3 4
```

See Also

[cell](#) | [cellfun](#)

Related Examples

- “Use Python array Types in MATLAB” on page 1-15

Pass Cell Array as Python Sequence Type

This example shows how to pass a MATLAB cell array to a Python function.

The following Python module contains the function `theend`, which appends a string to the end of a list. Create a text file, copy this Python module, and save the file as `mymod.py` in a writable folder, for example, your `prefdir` folder.

```
# mymod.py
"""Python module demonstrates passing MATLAB types to Python functions"""
def search(words):
    """Return list of words containing 'son'"""
    newlist = [w for w in words if 'son' in w]
    return newlist

def theend(words):
    """Append 'The End' to list of words"""
    words.append('The End')
    return words
```

Add the folder containing `mymod.py` to the Python search path using the `append` method of the `list` type.

```
P = py.sys.path;
append(P,prefdir);
```

Open the MATLAB sample data file, creating the cell array, `LastName`.

```
load patients.mat
```

Convert the cell array to a 1-by-N `py.list` array.

```
L = py.list(LastName');
class(L)
```

```
ans =
```

```
py.list
```

Call `mymod.theend` on the list.

```
py.mymod.theend(L);
```

The Python function does not return variable L as an output argument. Instead, the function updates the value by reference.

View the last item in the list.

```
L{end}
```

```
ans =
```

```
Python str with no properties.  
The End
```

You can pass variable L to other Python functions.

Related Examples

- “Use Python list Type in MATLAB” on page 1-20

Read Element of Nested list Type

This example shows how to access an element of a Python `list` containing `list` elements.

```
matrix = py.list({{1, 2, 3, 4},{'hello','world'},{9, 10}});
```

Display element 'world', at index (2,2).

```
disp(char(matrix{2}{2}))
```

```
world
```

More About

- “Multilevel Indexing to Access Parts of Cells”

Use Python tuple Type in MATLAB

This example shows how to use a Python tuple, returned by the `os.path.split` function, in MATLAB.

```
pn = py.os.path.split('C:\Program Files\MATLAB\R2014a\help\examples')
```

```
pn =
```

```
Python tuple with no properties.
```

```
( 'C:\\Program Files\\MATLAB\\R2014a\\help', 'examples' )
```

Convert the parts of the folder to MATLAB strings and display the results.

```
head = char(pn{1})  
tail = char(pn{end})
```

```
head =
```

```
C:\Program Files\MATLAB\R2014a\help
```

```
tail =
```

```
examples
```


Create Python tuple Variable

This example shows how to create a `tuple` variable to pass to a Python function.

```
student = py.tuple({'Robert', 19, 'Biology'})
```

```
student =
```

```
    Python tuple with no properties.
```

```
    ('Robert', 19.0, 'Biology')
```

More About

- “List, Tuple, and Dictionary Types” on page 1-64

Create Singleton Python tuple Variable

This example shows how to create a tuple variable with a single element.

```
subject = py.tuple({'Biology'})
```

```
subject =
```

```
    Python tuple with no properties.
```

```
    ('Biology',)
```

A tuple with one element has a trailing comma.

Create Python dict Variable

This example shows how to create a `dict` variable to pass to a Python function.

```
studentID = py.dict(pyargs('Robert',357,'Mary',229,'Jack',391))
```

```
studentID =
```

```
    Python dict with no properties.
```

```
    {'Robert': 357.0, 'Jack': 391.0, 'Mary': 229.0}
```

More About

- “List, Tuple, and Dictionary Types” on page 1-64

Pass dict Argument to Python Method

This example shows how to change a value in a `dict` variable using the Python update method.

Create a menu of items and prices.

```
menu = py.dict(pyargs('soup',3.57,'bread',2.29,'bacon',3.91,'salad',5.00));
```

Update the price for bread using the Python `dict` type update method.

```
update(menu,py.dict(pyargs('bread',2.50)))  
menu
```

```
menu =
```

```
Python dict with no properties.
```

```
{'soup': 3.57, 'bacon': 3.91, 'bread': 2.5, 'salad': 5.0}
```

Use Python dict Type in MATLAB

This example shows how to convert numerical values of a Python `dict` variable into a MATLAB array.

Suppose that you have a Python function, `myfunc`, that returns menu items and prices in a dictionary, `dict`, type.

```
order = myfunc;
```

```
order =
```

```
Python dict with no properties.
```

```
{'soup': 3.57, 'bacon': 3.91, 'salad': 5.0, 'bread': 2.29}
```

A dictionary has pairs of keys and values. Use the Python `keys` function to display the menu items.

```
keys(order)
```

```
ans =
```

```
Python list with no properties.
```

```
['soup', 'bacon', 'salad', 'bread']
```

Use the Python `values` function to display the prices.

```
values(order)
```

```
ans =
```

```
Python list with no properties.
```

```
[3.57, 3.91, 5.0, 2.29]
```

Use the cell function to convert the Python `list` to a MATLAB variable.

```
p = cell(values(order))
```

```
p =
```

```
[3.5700] [3.9100] [5] [2.2900]
```

Convert the prices to a MATLAB array.

```
prices = cellfun(@double,p)
```

```
prices =
```

```
        3.57        3.91        5.00        2.29
```

Calculate the total.

```
total = sum(prices)
```

```
total =
```

```
    14.77
```

Convert Python dict Type to MATLAB Structure

This example shows how to plot numeric data from a Python dictionary.

Suppose a Python function returns a variable, `patient`, with the following values.

```
patient
```

```
patient =
```

```
Python dict with no properties.
```

```
{'test1': array('d', [79.0, 75.0, 73.0]),  
 'test3': array('d', [220.0, 210.0, 205.0]),  
 'test2': array('d', [180.0, 178.0, 177.5]),  
 'name': 'John Doe'}
```

Convert `patient` to a MATLAB structure.

```
P = struct(patient)
```

```
P =
```

```
test1: [1x1 py.array.array]  
test3: [1x1 py.array.array]  
test2: [1x1 py.array.array]  
name: [1x8 py.str]
```

The values of the fields remain as Python types.

Plot the test results after converting the numeric data to type double.

```
bar([double(P.test1);double(P.test2);double(P.test3)])
```

MATLAB displays a bar graph.

Pass Keyword Arguments

The Python built-in `print` function has keyword arguments, `sep`, `end`, and `file`.

```
print(*objects, sep=' ', end='\n', file=sys.stdout)
```

The following examples use the default value for `file`.

Create some string variables.

```
x1 = py.str('c:');  
x2 = py.os.curdir;  
x3 = py.os.getenv('foo');  
py.print(x1,x2,x3)
```

```
c: . None
```

To display the values on separate lines, use newline, `\n`, as a separator.

```
py.print(x1,x2,x3,pyargs('sep',sprintf('\n')))
```

```
c:  
.  
None
```

Use the following statement to change `sep` to an empty string and change the `end` value to display `THE END`.

```
py.print(x1,x2,x3,pyargs('end', sprintf(' THE END\n'),'sep',py.str))
```

```
c: .None THE END
```

See Also

`pyargs`

External Web Sites

- python.org print method

Index into Python String

This example shows how to display the first character of a Python `str` variable. The example compares indexing into a MATLAB string with indexing into the Python variable.

Create a MATLAB string and display the first character.

```
str = 'myfile';  
str(1)
```

```
ans =
```

```
m
```

Convert the string to a Python `str` type and display the first character.

```
pstr = py.str(str);  
pstr(1)
```

```
ans =
```

```
Python str with no properties.
```

```
m
```

Index into Python list

This example shows how to display the last element in a Python `list` variable. The example compares indexing into a MATLAB cell array with indexing into a Python list.

Create a MATLAB cell array and display the last element.

```
C = {1,2,3,4};  
n = C(end)  
  
n =
```

```
[4]
```

MATLAB returns a cell array.

Display the contents of the last element.

```
n = C{end}  
  
n =
```

```
4
```

Convert the cell array to a Python list.

```
li = py.list(C)  
  
li =
```

```
Python list with no properties.
```

```
[1.0, 2.0, 3.0, 4.0]
```

Display the last element.

```
n = li(end)  
  
n =
```

```
Python list with no properties.
```

```
[4.0]
```

MATLAB returns a list.

Display the contents of the last element.

```
n = li{end}
```

```
n =
```

```
4
```

Index into Python tuple

This example shows how to display elements in a tuple.

Create a tuple and display the first two elements.

```
t = py.tuple({'a', 'bc', 1, 2, 'def'});  
t(1:2)
```

```
ans =
```

```
Python tuple with no properties.
```

```
('a', 'bc')
```

MATLAB returns a tuple.

Index into Python dict

This example shows how to display an element in a dictionary.

Create a dictionary variable.

```
customers = py.dict
customers =
    Python dict with no properties.
    {}
```

Populate the dict with customer names and account numbers.

```
customers{'Smith'} = int32(2112);
customers{'Anderson'} = int32(3010);
customers{'Audrey'} = int32(4444);
customers{'Megan'} = int32(5000);

customers =
    Python dict with no properties.
    {'Audrey': 4444, 'Anderson': 3010, 'Smith': 2112, 'Megan': 5000}
```

The output depends on your Python version.

Read the account number for customer Anderson.

```
acct = customers{'Anderson'}
acct =
    3010
```

The result is a double.

```
class(acct)
ans =
double
```

Use Python List as Values in for Loop

This example shows how to display elements of a Python list.

```
li = py.list({1,2,3,4});  
for n = li  
    disp(n{1})  
end
```

1

2

3

4

Variable `n` is a `py.list` with one element.

More About

- “Accessing Elements in Python Container Types” on page 1-42

Display Stepped Range of Elements

This example shows how to use an incremental step in indexing.

If you use slicing to access elements of a Python object, be aware that the format in Python is `start:stop:step`. In MATLAB, the syntax is of the form `start:step:stop`.

```
li = py.list({'a', 'bc', 1, 2, 'def'});  
li(1:2:end)
```

```
ans =
```

```
Python list with no properties.
```

```
['a', 1.0, 'def']
```

Accessing Elements in Python Container Types

In this section...

“Sequence Types” on page 1-42

“Mapping Types” on page 1-43

“Size and Dimensions” on page 1-43

“Array Support” on page 1-44

“Use Zero-Based Indexing for Python Functions” on page 1-44

Typically, to work with a Python variable in MATLAB, you convert the Python object to a MATLAB array, and then index into the array as needed. In some cases, you want to preserve the Python object.

A Python *container* is typically a *sequence* type (list or tuple) or a *mapping* type (dict). In Python, use square brackets [] or the operator `.getitem` function to access an element in the container.

Sequence Types

Python sequence types behave like MATLAB cell arrays.

Use smooth-parenthesis () indexing to get a subsequence.

```
li = py.list({1,2,3,4});  
res = li(2:3)
```

```
res =
```

```
    Python list with no properties.
```

```
    [2.0, 3.0]
```

Use curly braces { } to get the contents of the element.

```
res = li{1}
```

```
res =
```

```
    1
```


Mapping Types

For mapping types, use curly braces with the Python *key* argument.

```
patient = py.dict(pyargs('name', 'John Doe', 'billing', 127));  
patient{'billing'}
```

```
ans =
```

```
127
```

Size and Dimensions

MATLAB displays information for your system.

```
p = py.sys.path;  
class(p)
```

```
ans =
```

```
py.list
```

Index into p.

```
p(1)  
p{1}
```

```
ans =
```

```
Python list with no properties.
```

```
['c:\\work']
```

```
ans =
```

```
Python str with no properties.
```

```
c:\work
```

Inspect dimensions.

```
len = length(p)  
sz = size(p)
```

```
len =  
    11  
  
sz =  
    1    11
```

Array Support

MATLAB converts a sequence type into a 1-by-N array.

Use Zero-Based Indexing for Python Functions

Python uses zero-based indexing; MATLAB uses one-based indexing. When you call a Python function, such as `py.sys.path`, the index value of the first element of a Python container, `x`, is `int32(0)`. The index value for the last element is `int32(py.len(x) - 1)`.

Related Examples

- “Index into Python String” on page 1-35
- “Index into Python list” on page 1-36
- “Index into Python tuple” on page 1-38
- “Index into Python dict” on page 1-39

More About

- “Explicit Type Conversions” on page 1-57
- “Limitations to Indexing into Python Objects” on page 1-66
- “Pass MATLAB Backslash Control Character” on page 1-18

Viewing Python Numeric Values

In this section...

“Why Do I See Properties When I Display a Number?” on page 1-45

“What Is the L Character Attached to a Number?” on page 1-45

Why Do I See Properties When I Display a Number?

MATLAB displays all Python types as objects, including a list of properties of the object.

```
py.int(5)
ans =
    Python int with properties:
      denominator: 1
         imag: 0
      numerator: 5
         real: 5
5
```

MATLAB displays the expected output value (5) on the last line.

What Is the L Character Attached to a Number?

Python appends an L character to the representation (display) of a long data type. For example, using Python version 2.7, type:

```
py.repr(py.long(5))
ans =
    Python str with no properties.
5L
```

MATLAB displays Python `str` and appends L for any Python function that uses the `repr` function to display its output.

You treat a `long` data type like any numeric type. For example, add two numbers:

```
py.long(5) + py.long(2)
```

```
ans =
```

```
Python long with properties:
```

```
denominator: [1x1 py.long]  
  imag: [1x1 py.long]  
numerator: [1x1 py.long]  
  real: [1x1 py.long]
```

```
7
```

The answer is the number 7.

Call Methods on Python Variables

This example shows how to update a Python `list` of folder names using the `append` method.

Create a `list` of folders, `P`, using the Python `sys.path` variable.

```
P = py.sys.path;
```

Display the Python functions for a `list` type.

```
methods(P)
```

```
Methods for class py.list:
```

```
append  count  display  ge      insert  lt      plus     reverse
cell    details eq       gt      le      mtimes  pop      sort
char    disp   extend  index  list    ne      remove
```

```
Methods of py.list inherited from handle.
```

Read the documentation for `append`.

```
py.help('list.append')
```

```
Help on method_descriptor in list:
```

```
list.append = append(...)
    L.append(object) -- append object to end
```

Add the current folder to the end of the path.

```
append(P, pwd)
```

Display number of folders on the path. The list has `py.len` elements.

```
py.len(P)
```

```
ans =
```

```
Python int with properties:
```

```
    real: [1x1 py.int]
denominator: [1x1 py.int]
    imag: [1x1 py.int]
```

```
numerator: [1x1 py.int]
```

```
11
```

11 is the number of folders on this path. Your value might be different. The type of this number is `py.int`.

Related Examples

- “Use Python list Type in MATLAB” on page 1-20

System and Configuration Requirements

In this section...

“Python Version Support” on page 1-49

“Set Python Version on Windows Platform” on page 1-49

“Set Python Version on Mac and Linux Platforms” on page 1-50

“64-bit/32-bit Versions of Python on Windows Platforms” on page 1-50

“Requirements for Building Python Executable” on page 1-50

Python Version Support

To call Python modules in MATLAB you must have a supported version of the reference implementation (CPython) installed on your system. MATLAB supports the following versions:

- Version 2.7
- Version 3.3
- Version 3.4

To determine if your system has a supported version, use the `pyversion` function. The value set by `pyversion` is persistent across MATLAB sessions.

You cannot switch between versions of Python in a single MATLAB session. MATLAB automatically selects and loads a Python version when you type a Python command, such as:

```
py.funcname
```

If you want to change versions, restart MATLAB and then run `pyversion` with the new version information.

Set Python Version on Windows Platform

On Windows platforms, use either:

```
pyversion version
```

or

```
pyversion executable
```

Note: If you downloaded a Python interpreter, but did not register it in the Windows registry, use:

```
pyversion executable
```

Set Python Version on Mac and Linux Platforms

To set the version, type:

```
pyversion executable
```

where *executable* is the full path to the Python executable file.

64-bit/32-bit Versions of Python on Windows Platforms

The architecture of Python must match the architecture of MATLAB. If you run a 64-bit version of MATLAB, download a 64-bit version of Python. If you run a 32-bit version of MATLAB, download a 32-bit version of Python.

Note: On the Python download website, downloads for Microsoft Windows platforms are 32-bit versions by default. To download the 64-bit version, choose options with the name "Windows x86-64 MSI installer".

Requirements for Building Python Executable

On Linux[®] and Mac systems, if you build the Python executable, configure the build with the `--enable-shared` option.

See Also

```
pyversion
```

External Web Sites

- <https://www.python.org/downloads>

Creating a Python Object

The syntax to create a Python object `pyObj` is:

```
pyObj = py.modulename.ClassName(varargin)
```

where `varargin` is the list of constructor arguments specified by the `__init__` method in `ClassName`.

In MATLAB, Python objects are *reference types* (handle objects) and do not adhere to the MATLAB copy-on-assignment and pass-by-value rules. When you copy a handle object, only the handle is copied and both the old and new handles refer to the same data. When you copy a MATLAB variable (a value object), the variable data is also copied. The new variable is independent of changes to the original variable.

The following example creates an object of the `TextWrapper` class in the Python standard library `textwrap` module.

Read the constructor signature, `__init__`.

```
py.help('textwrap.TextWrapper.__init__')
```

```
Help on method __init__ in textwrap.TextWrapper:
```

```
textwrap.TextWrapper.__init__ = __init__(self, width=70, initial_indent='', subsequent_
```

Create a default `TextWrapper` object. You do not need to pass any input arguments because each argument has a default value, identified by the equal sign (=) character.

```
tw = py.textwrap.TextWrapper;
```

```
tw =
```

Python `TextWrapper` with properties:

```

        width: 70
    subsequent_indent: [1x1 py.str]
wordsep_simple_re_uni: [1x1 py._sre.SRE_Pattern]
    fix_sentence_endings: 0
        break_on_hyphens: 1
        break_long_words: 1
    wordsep_re_uni: [1x1 py._sre.SRE_Pattern]
    initial_indent: [1x1 py.str]
        expand_tabs: 1

```

```
replace_whitespace: 1
drop_whitespace: 1
```

```
<textwrap.TextWrapper instance at 0x000000006D58F808>
```

To change a logical value, for example, the `break_long_words` property, type:

```
tw.break_long_words = 0;
```

To change a numeric value, for example, the `width` property, first determine the numeric type.

```
class(tw.width)
```

```
ans =
```

```
int64
```

By default, when you pass a MATLAB number to a Python function, Python reads it as a float. If the function expects an integer, Python throws an error. Explicitly convert the MATLAB number to an integer. For example, type:

```
tw.width = int64(3);
```

Read the help for the `wrap` method.

```
py.help('textwrap.TextWrapper.wrap')
```

```
Help on method wrap in textwrap.TextWrapper:
```

```
textwrap.TextWrapper.wrap = wrap(self, text) unbound textwrap.TextWrapper method
wrap(text : string) -> [string]
```

```
Reformat the single paragraph in 'text' so it fits in lines of
no more than 'self.width' columns, and return a list of wrapped
lines. Tabs in 'text' are expanded with string.expandtabs(),
and all other whitespace characters (including newline) are
converted to space.
```

Create a list of wrapped lines, `w`, from input string, `T`.

```
T = 'MATLAB® is a high-level language and interactive environment for numerical comput
w = wrap(tw,T);
whos w
```

Name	Size	Bytes	Class	Attributes
------	------	-------	-------	------------

```
w          1x1          112 py.list
```

Convert the `py.list` to a cell array and display the results.

```
wrapped = cellfun(@char, cell(w), 'UniformOutput', false);  
fprintf('%s\n', wrapped{:})
```

```
MATLAB®  
is  
a  
high-  
level  
language  
and  
interactive  
environment  
for  
numerical  
computation,  
visualization,  
and  
programming.
```

Although `width` is 3, setting the `break_long_words` property to `false` overrides the `width` value in the display.

Related Examples

- “Call Python from MATLAB” on page 1-4
- “Pass Keyword Arguments” on page 1-34

More About

- “MATLAB Objects”

Passing Data to Python

In this section...

“MATLAB Type to Python Type Mapping” on page 1-54

“MATLAB Vector to Python Mapping” on page 1-55

“Unsupported MATLAB Types” on page 1-55

MATLAB Type to Python Type Mapping

When you pass MATLAB data as arguments to Python, MATLAB converts the data into types that best represent the data to the Python language.

MATLAB Input Argument Type — Scalar Values Only	Resulting Python Type
double single	float
Complex single Complex double	complex
int8 uint8 int16 uint16 int32	int
uint32 int64 uint64	int long (version 2.7 only)
NaN	float(nan)
Inf	float(inf)
logical	bool
Structure	dict
Python object — <i>py.type</i>	<i>type</i>

MATLAB Vector to Python Mapping

MATLAB Input Argument Type — 1-by-N Vector	Resulting Python Type
double	<code>array.array('d')</code>
single	<code>array.array('f')</code>
int8	<code>array.array('b')</code>
uint8	<code>array.array('B')</code>
int16	<code>array.array('h')</code>
uint16	<code>array.array('H')</code>
int32	<code>array.array('i')</code>
uint32	<code>array.array('I')</code>
int64 (Not supported for Python 2.7 on Windows)	<code>array.array('q')</code>
uint64 (Not supported for Python 2.7 on Windows)	<code>array.array('Q')</code>
char array containing values greater than <code>intmax('uint8')</code> (version 2.7 only)	unicode
char array	str
cell vector	tuple

Unsupported MATLAB Types

The following MATLAB types are not supported in Python.

Unsupported MATLAB Types
Multidimensional arrays (numeric, char, or cell)
Structure arrays
Complex, scalar integers or arrays
Sparse arrays
Logical vectors

Unsupported MATLAB Types
categorical, table, containers.Map, datetime types
MATLAB objects
Function handle, @
meta.class (py.class)

Related Examples

- “Pass dict Argument to Python Method” on page 1-30

More About

- “Handling Data Returned from Python” on page 1-57

Handling Data Returned from Python

In this section...

“Automatic Python Type to MATLAB Type Mapping” on page 1-57

“Explicit Type Conversions” on page 1-57

Automatic Python Type to MATLAB Type Mapping

The following table shows how MATLAB converts data returned from Python into MATLAB types.

Python Return Type, as Displayed in Python	Resulting MATLAB Type — Scalar
bool	logical
int (version 2.7 only). For Python versions 3.x int, you must convert explicitly.	int64
float	double
complex	Complex double
All other Python types — <i>type</i>	Python object — <i>py.type</i>

If you pass a MATLAB function handle, @, to Python, it comes back as a function handle.

Explicit Type Conversions

MATLAB provides the following functions to convert Python data types to MATLAB types manually.

Python Return Type or Protocol, as Displayed in MATLAB	MATLAB Conversion Function
py.str (version 2.7)	char uint8
py.str (version 3.x)	char
py.unicode	char
Object with <code>__str__</code> method	char
py.bytes	uint8

Python Return Type or Protocol, as Displayed in MATLAB	MATLAB Conversion Function
<code>py.int</code>	double or int64
<code>py.long</code>	double or int64
<code>py.array.array^a</code>	numeric double single int8 uint8 int16 uint16 int32 uint32 int64 uint64
Sequence protocol; for example, <code>py.list</code> and <code>py.tuple</code>	cell
Mapping protocol; for example, <code>py.dict</code>	struct

a. You can convert `py.array.array` of any format to the MATLAB type you want.

More About

- “Passing Data to Python” on page 1-54

How MATLAB Represents Python Operators

MATLAB supports the following overloaded operators.

Python Operator Symbol	Python Methods	MATLAB Methods
+ (binary)	<code>__add__</code> , <code>__radd__</code>	plus, +
- (binary)	<code>__sub__</code> , <code>__rsub__</code>	minus, -
* (binary)	<code>__mul__</code> , <code>__rmul__</code>	mtimes, *
/	<code>__truediv__</code> , <code>__rtruediv__</code>	mrdivide, /
==	<code>__eq__</code>	eq, ==
>	<code>__gt__</code>	gt, >
<	<code>__lt__</code>	lt, <
!=	<code>__ne__</code>	ne, ~=
>=	<code>__ge__</code>	ge, >=
<=	<code>__le__</code>	le, <=
- (unary)	<code>__neg__</code>	uminus, -a
+ (unary)	<code>__pos__</code>	uplus, +a

The following Python operators are not supported.

Python Operator Symbol	Python Method
%	<code>__mod__</code> , <code>__rmod__</code>
**	<code>__pow__</code> , <code>__rpow__</code>
<<	<code>__lshift__</code> , <code>__rlshift__</code>
>>	<code>__rshift__</code> , <code>__rrshift__</code>
&	<code>__and__</code> , <code>__rand__</code>
^	<code>__xor__</code> , <code>__rxor__</code>
	<code>__or__</code> , <code>__ror__</code>
// (binary)	<code>__floordiv__</code> , <code>__rfloordiv__</code>
+= (unary)	<code>__iadd__</code>

Python Operator Symbol	Python Method
-= (unary)	<code>__isub__</code>
*= (unary)	<code>__imul__</code>
/= (unary)	<code>__itruediv__</code>
//= (unary)	<code>__ifloordiv__</code>
%= (unary)	<code>__imod__</code>
**= (unary)	<code>__ipow__</code>
<<= (unary)	<code>__ilshift__</code>
>>= (unary)	<code>__irshift__</code>
&= (unary)	<code>__iand__</code>
^= (unary)	<code>__ixor__</code>
!= (unary)	<code>__ior__</code>
~ (unary)	<code>__invert__</code>

Execute Callable Python Object

To execute a callable Python object, use the `feval` function. For example, if instance *obj* of a Python class is callable, replace the Python syntax `obj(x1, ..., xn)` with one of the following MATLAB statements:

```
feval(obj,x1, ..., xn)
```

```
obj(x1, ..., xn)
```

See Also

`feval`

Python import and MATLAB import Commands

In this section...

“Do Not Type “import <i>pythonmodule</i> ”” on page 1-62
--

“Use MATLAB import to Shorten Class or Function Names” on page 1-62

Do Not Type “import *pythonmodule*”

MATLAB automatically loads Python when you type:

```
py.command
```

Do not type “import *pythonmodule*” in MATLAB.

The `import` statement does not have the same functionality in MATLAB as in Python. Python uses the `import` statement to load and make code accessible. MATLAB uses the `import` function to refer to a class or function without using the package name.

Use MATLAB import to Shorten Class or Function Names

The Python `from...import` statement lets you reference a module without using the fully qualified name. Replace the following Python statement:

```
from x import y
```

with the MATLAB command

```
import x.y
```

where `y` is a class name or function name you want to use.

For example, the Python `textwrap` module formats blocks of text.

```
S = py.textwrap.wrap('This is a string');
```

Since `wrap` is not a MATLAB function, you can shorten the calling syntax using the `import` function. After calling this command, you do not need to type the package (`py`) and module (`textwrap`) names.

```
import py.textwrap.wrap
```

```
S = wrap('This is a string');
```

Note: Do not call:

```
import py.*
```

If you do, MATLAB calls the Python function instead of the MATLAB function of the same name.

If you call this command, you must call the MATLAB command:

```
clear import
```

See Also

import

List, Tuple, and Dictionary Types

The following table shows the commands for creating `list`, `tuple`, and `dict` types. The commands on the left are run from the Python interpreter. The commands on the right are MATLAB commands.

Python list – []	MATLAB <code>py.list</code>
<code>['Robert', 'Mary', 'Joseph']</code>	<code>py.list({'Robert', 'Mary', 'Joseph'})</code>
<code>[[1,2],[3,4]]</code>	<code>py.list({py.list([1,2]),py.list([3,4])})</code>
Python tuple – ()	MATLAB <code>py.tuple</code>
<code>('Robert', 19, 'Biology')</code>	<code>py.tuple({'Robert',19,'Biology'})</code>
Python dict – {}	MATLAB <code>py.dict</code>
<code>{'Robert': 357, 'Joe': 391, 'Mary': 229}</code>	<code>py.dict(pyargs(... 'Robert',357,'Mary',229,'Joe',391))</code>

See Also

`pyargs`

Related Examples

- “Use Python list Type in MATLAB” on page 1-20
- “Use Python tuple Type in MATLAB” on page 1-26
- “Use Python dict Type in MATLAB” on page 1-31

Limitations to Python Support

Features Not Supported in MATLAB
Editing and reloading a Python module in the same MATLAB session. To use an updated module, restart MATLAB.
Closing the Python interpreter while running MATLAB.
Saving (serializing) Python objects into a MAT-file.
Interactive Python help (calling <code>py.help</code> without input arguments).
<code>py.input</code> and <code>py.raw_input</code> (version 2.7).
Accessing static properties of a Python class.
MATLAB <code>isa</code> function does not recognize virtual inheritance.
MATLAB class inheritance from a Python class.
Overloaded attribute access.
Nested Python classes.
Modules that start MATLAB in a separate process, for example, the <code>multiprocessing</code> module.
Modules that read <code>sys.argv</code> , the command-line arguments passed to a Python script, for example, <code>Tkinter</code> .
Dynamically generated Python classes, for example, <code>collections.namedtuple</code> .
Dynamically attaching new object attributes. Instead, use <code>py setattr</code> .
Class names or other identifiers starting with an underscore (<code>_</code>) character. Instead, use the Python <code>py.getattr</code> and <code>py.setattr</code> functions.

More About

- “Python import and MATLAB import Commands” on page 1-62

Limitations to Indexing into Python Objects

You can access data in Python container objects, like lists and dictionaries, with index values, similar to referencing an element in a MATLAB matrix. There are, however, ways to index into matrices which are not supported for these Python types.

Indexing Features Not Supported in MATLAB
Use of square brackets, [].
Indexing into a container type that does not inherit from <code>collections.Sequence</code> or <code>collections.Mapping</code> .
Logical indexing.
Accessing data in a container with an arbitrary array of indices. An index must be of the form <code>start:step:stop</code> .
Comma-separated lists.
<code>numel</code> function does not return number of array elements. Returns 1.

More About

- “Matrix Indexing”

Undefined variable "py" or function "py.command"

MATLAB automatically loads Python when you type `py.command` in the Command Window. If MATLAB displays this message, a failure has occurred.

```
Undefined variable "py" or function "py.command"
```

Use this page to help troubleshoot the failure.

In this section...

“Python Not Installed” on page 1-67

“64-bit/32-bit Versions of Python on Windows Platforms” on page 1-67

“MATLAB Cannot Find Python” on page 1-68

“Error in User-Defined Python Module” on page 1-68

“Python Module Not on Python Search Path” on page 1-68

“Module Name Conflicts” on page 1-69

“Python Tries to Execute command in Wrong Module” on page 1-69

Python Not Installed

Python is not installed on your computer. Download and install Python from <https://www.python.org/downloads>.

On Microsoft Windows, Python downloads the 32-bit version of Python by default. If you run a 64-bit version of MATLAB, download a 64-bit version of Python, identified by the name "Windows x86-64 MSI installer". For more information, see “64-bit/32-bit Versions of Python on Windows Platforms” on page 1-50.

On Linux and Mac systems, if you build Python from source files, configure the build with the `--enable-shared` option.

64-bit/32-bit Versions of Python on Windows Platforms

You installed a 32-bit version of Python for a 64-bit version of MATLAB or a 64-bit version of Python for a 32-bit version of MATLAB.

MATLAB Cannot Find Python

Python is in a nonstandard location. To provide the path to the Python executable, use the `pyversion` function. For example:

```
pyversion C:\Users\uname\WinPython-64bit-3.3.2.1\python-3.3.2.amd64\python.exe
```

On Windows systems, Python is not found in the Windows registry. If you downloaded a Python interpreter, but did not register it in the Windows registry, specify the Python location using the command:

```
pyversion executable
```

Error in User-Defined Python Module

There is an error in the user-defined Python module. To test if your module, *mymod*, contains errors, type:

```
py.importlib.import_module('mymod')
```

If Python detects an error in the module, MATLAB displays a Python error message.

Alternatively, execute the equivalent command at the Python command prompt to get the Python error message.

After you fix the error, to access the updated module, restart MATLAB, and add it to the search path.

Python Module Not on Python Search Path

If *command* is a valid Python command, make sure the Python module is on the Python search path. To test if module *mymod* is on the path, type:

```
py.importlib.import_module('mymod')
```

If Python cannot find the module, MATLAB displays a Python error message.

To add *mymod*, in folder *modpath*, to the path, type:

```
P = py.sys.path;  
if count(P, 'modpath') == 0  
    insert(P, int32(0), 'modpath');
```

end

The Python search path is associated with the Python interpreter loaded in the current session of MATLAB. You can modify the search path in MATLAB, but the modifications are not present if you run other instances of the interpreter outside of MATLAB.

Module Name Conflicts

If you call a Python module that has the same name as a module in the standard library or any 3rd-party modules installed on your system, MATLAB might load the wrong module.

Python Tries to Execute *command* in Wrong Module

If *command* is in a user-defined module, make sure that the module name does not conflict with modules in the Python standard library, or any 3rd-party modules on your system.

See Also

pyversion

More About

- “System and Configuration Requirements” on page 1-49

External Web Sites

- <https://www.python.org/downloads>

Help for Python Functions

For a complete description of Python functionality, consult outside resources, in particular, `python.org`. There are different versions of the Python documentation, so be sure to refer to the version corresponding to the version on your system. Many examples in the MATLAB documentation refer to functions in the Python standard library.

To use functions in a third-party or user-defined Python module, refer to your vendor's product documentation for information about how to install the module and for details about its functionality.

The `py.help` command displays the Python help found at `www.python.org/doc`. Help for packages and classes can be extensive and might not be useful when displayed in the MATLAB command window.

- Package

```
py.help('textwrap')
```

- Class

```
py.help('textwrap.TextWrapper')
```

- Method of a class

```
py.help('textwrap.TextWrapper.wrap')
```

- Function

```
py.help('textwrap.fill')
```

Do not use the MATLAB `help` function to get information because MATLAB does not provide documentation for Python functions. You can identify a Python function by the `py.` prefix. Some examples are:

- `py.list` — Data type
- `py.len` — Built-in function
- `py.os.listdir` — Module function
- `py.mymod.search` — User-defined function

If you do type `help py.pyfunc`, you might find references to `pyfunc` in the MATLAB documentation. Click the `search the documentation` link in the help message to search for this information.

If MATLAB displays an error message of the following format, refer to your Python documentation for more information.

Python Error: *message*

Note: You cannot use the interactive Python help, calling `py.help` without input arguments, in MATLAB.

More About

- “Handle Python Exceptions” on page 1-72

External Web Sites

- www.python.org

Handle Python Exceptions

MATLAB catches exceptions thrown by Python and converts them into a `matlab.exception.PyException` object, which is derived from the `MException` class. For example:

```
try
    py.list('x','y',1)
catch e
    e.message
    if(isa(e, ''))
        e.ExceptionObject
    end
end

ans =
```

Python Error: list() takes at most 1 argument (3 given)

If MATLAB displays an error message of the following format, refer to your Python documentation for more information.

Python Error: *message*

See Also

`matlab.exception.PyException`

Troubleshooting Error Messages

Troubleshooting errors when using a MATLAB external interface is a challenge. Is the error in the Python application or in your MATLAB code? Common errors include errors reported by Python and errors from attempting to convert Python data to MATLAB and conversely.

In this section...

“Python Error: message” on page 1-73

“Python Module Errors” on page 1-73

“Errors Converting Python Data” on page 1-74

Python Error: *message*

MATLAB displays an error message in the following format:

```
Python Error: message
```

This error comes from Python and for information you must refer to your version of Python documentation at www.python.org/doc or the product documentation from third-party vendors. For example:

```
p = py.os.path.split(pwd);  
py.operator.setitem(p,int32(1),py.str('temp'));
```

```
Python Error: 'tuple' object does not support item assignment
```

Search for the term “tuple” on the Python documentation site for your version of Python. Tuple is a built-in function described here: <https://docs.python.org/2/library/functions.html#tuple>.

Python Module Errors

MATLAB reports some Python errors as a MATLAB error loading a module. For more information, see “Undefined variable “py” or function “py.command”” on page 1-67.

If you write your own Python modules or modify the source code from an existing module, test your MATLAB commands by writing the equivalent Python command in your Python interpreter. This workflow is beyond the scope of MATLAB documentation and product support.

Note: You cannot edit and reload a Python module in the same MATLAB session. To use an updated module, restart MATLAB.

Errors Converting Python Data

When the data is compatible, MATLAB automatically converts Python data to MATLAB data. For the list of data types you must explicitly convert, see “Explicit Type Conversions” on page 1-57.

For example, although MATLAB supports multidimensional arrays, you can only pass vectors of data to Python.

```
x = py.len([2 3 4; 4 5 6])
```

```
Error using py.len  
Conversion of MATLAB 'double' to Python is only supported for 1-N vectors.
```

More About

- “Data Types”
- “Limitations to Python Support” on page 1-65

External Web Sites

- www.python.org/doc

Using Python Data in MATLAB

MATLAB automatically converts compatible Python data to MATLAB data.

For Python types that do not have compatible MATLAB types, such as `list` and `dict`, use the MATLAB functions shown in the Explicit Type Conversion table. This table also describes how to convert strings and certain numeric types explicitly.

More About

- “Automatic Python Type to MATLAB Type Mapping” on page 1-57
- “Explicit Type Conversions” on page 1-57

Call Python eval Function

This example shows how to evaluate the expression, `x+y`, in Python. To evaluate an expression, pass a Python dict value for the `globals` namespace parameter.

Read the help for `eval`.

```
py.help('eval')
```

```
Help on built-in function eval in module __builtin__:
```

```
eval(...)  
eval(source[, globals[, locals]]) -> value
```

```
Evaluate the source in the context of globals and locals.  
The source may be a string representing a Python expression  
or a code object as returned by compile().  
The globals must be a dictionary and locals can be any mapping,  
defaulting to the current globals and locals.  
If only globals is given, locals defaults to it.
```

Create a Python dict variable for the `x` and `y` values.

```
workspace = py.dict(pyargs('x',1,'y',6))
```

```
workspace =
```

```
Python dict with no properties.
```

```
{'y': 6.0, 'x': 1.0}
```

Evaluate the expression.

```
res = py.eval('x+y',workspace)
```

```
res =
```

```
7
```

Add two numbers without assigning variables. Pass an empty dict value for the `globals` parameter.

```
res = py.eval('1+6',py.dict)
```

```
res =
```

7

Precedence Order of Methods and Functions

If a Python class defines a method with the same name as a MATLAB converter method for Python types, MATLAB calls the Python method. This means you cannot call the MATLAB converter method on an object of that class.

For example, if a Python class defines a `char` method, the following statement calls the Python method.

```
char(obj)
```

To use the MATLAB `char` function, type:

```
char(py.str(obj))
```

Read and Write MATLAB MAT-Files in C/C++ and Fortran

- “Writing Custom Applications to Access MAT-Files” on page 2-2
- “MAT-File Library and Include Files” on page 2-5
- “What You Need to Build Custom Applications” on page 2-7
- “Copy External Data into MAT-File Format with Standalone Programs” on page 2-8
- “Create MAT-File in C or C++” on page 2-13
- “Read MAT-File in C/C++” on page 2-14
- “Create MAT-File in Fortran” on page 2-15
- “Read MAT-File in Fortran” on page 2-16
- “Work with mxArray” on page 2-17
- “Table of MAT-File Source Code Files” on page 2-19
- “Building on Mac and Linux Operating Systems” on page 2-21
- “Building on Windows Operating Systems” on page 2-23
- “Sharing MAT-File Applications” on page 2-24

Writing Custom Applications to Access MAT-Files

In this section...
“Why Write Custom Applications?” on page 2-2
“MAT-File Interface Library” on page 2-3
“Exchanging Data Files Between Platforms” on page 2-4

Why Write Custom Applications?

To bring data into a MATLAB application, see “Methods for Importing Data”. To save data to a MAT-file, see “Save, Load, and Delete Workspace Variables”. Use these procedures when you program your entire application in MATLAB, or if you share data with other MATLAB users. There are situations, however, when you must write a custom program to interact with data. For example:

- Your data has a custom format.
- You create applications for users who do not run MATLAB, and you want to provide them with MATLAB data.
- You want to read data from an external application, but you do not have access to the source code.

Before writing a custom application, determine if MATLAB meets your data exchange needs by reviewing the following topics:

- The `save` and `load` functions.
- “Supported File Formats for Import and Export”.
- The `importdata` function and “Import Images, Audio, and Video Interactively”.
- “Methods for Importing Data”.

If these features are not sufficient, you can create custom C/C++ or Fortran programs to read and write data files in the format required by your application. There are two types of custom programs:

- Standalone program — Run from a system prompt or execute in MATLAB (see Run External Commands, Scripts, and Programs). Requires MATLAB libraries to build the application.
- MEX-file — Built and executed from the MATLAB command prompt. For information about creating and building MEX-files, see “MEX-File Creation API”.

MAT-File Interface Library

The MAT-File Library contains routines for reading and writing MAT-files. Call these routines from your own C/C++ and Fortran programs. Use these routines, rather than attempt to write your own code, to perform these operations, since using the library insulates your applications from future changes to the MAT-file structure.

MATLAB provides the `MATFile` type for representing a MAT-file.

MAT-File Routines

MAT-Function	Purpose
<code>matOpen</code>	Open a MAT-file.
<code>matClose</code>	Close a MAT-file.
<code>matGetDir</code>	Get a list of MATLAB arrays from a MAT-file.
<code>matGetVariable</code>	Read a MATLAB array from a MAT-file.
<code>matPutVariable</code>	Write a MATLAB array to a MAT-file.
<code>matGetNextVariable</code>	Read the next MATLAB array from a MAT-file.
<code>matDeleteVariable</code>	Remove a MATLAB array from a MAT-file.
<code>matPutVariableAsGlobal</code>	Put a MATLAB array into a MAT-file such that the <code>load</code> command places it into the global workspace.
<code>matGetVariableInfo</code>	Load a MATLAB array header from a MAT-file (no data).
<code>matGetNextVariableInfo</code>	Load the next MATLAB array header from a MAT-file (no data).

MAT-File C-Only Routines

<code>matGetFp</code>	Get an ANSI [®] C file pointer to a MAT-file.
-----------------------	--

The MAT-File Interface Library does not support MATLAB objects created by user-defined classes.

Do not create different MATLAB sessions on different threads using MAT-File Library functions. MATLAB libraries are not multithread safe so you can use these functions only on a single thread at a time.

Exchanging Data Files Between Platforms

You can work with MATLAB software on different computer systems and send MATLAB applications to users on other systems. MATLAB applications consist of MATLAB code containing functions and scripts, and MAT-files containing binary data.

Both types of files can be transported directly between machines: MATLAB source files because they are platform independent, and MAT-files because they contain a machine signature in the file header. MATLAB checks the signature when it loads a file and, if a signature indicates that a file is foreign, performs the necessary conversion.

Using MATLAB across different machine architectures requires a facility for exchanging both binary and ASCII data between the machines. Examples of this type of facility include FTP, NFS, and Kermit. When using these programs, be careful to transmit MAT-files in *binary file mode* and MATLAB source files in *ASCII file mode*. Failure to set these modes correctly corrupts the data.

MAT-File Library and Include Files

MATLAB provides the include and library files needed to write programs to read and write MAT-files. The following table lists the path names to these files. The term *matlabroot* refers to the root folder of your MATLAB installation. The term *arch* is a unique string identifying the platform.

MAT-Function Folders

Platform	Contents	Folder
Microsoft Windows	Include files	<i>matlabroot</i> \extern\include
	Libraries	<i>matlabroot</i> \bin\win32 or <i>matlabroot</i> \bin\win64
	Examples	<i>matlabroot</i> \extern\examples\eng_mat
Mac Linux	Include files	<i>matlabroot</i> /extern/include
	Libraries	<i>matlabroot</i> /bin/ <i>arch</i>
	Examples	<i>matlabroot</i> /extern/examples/eng_mat

MAT-Function Include Files

The *matlabroot*\extern\include folder holds header files containing function declarations with prototypes for the routines that you can access in the API Library. These files are the same for Windows, Mac, and Linux systems. The folder contains:

- The *matrix.h* header file that contains a definition of the *mxArray* structure and function prototypes for matrix access routines.
- The *mat.h* header file that contains function prototypes for *mat* routines.

MAT-Function Libraries

The name of the libraries folder, which contains the shared (dynamically linkable) libraries, is platform-dependent.

Shared Libraries on Windows Systems

The *bin* folder contains the run-time version of the shared libraries:

- The *libmat.dll* library of MAT-file routines (C/C++ and Fortran)

- The `libmx.dll` library of array access and creation routines

Shared Libraries on Mac and Linux Systems

The `bin/arch` folder, where *arch* is your machine's architecture, contains the shared libraries. For example, on Apple Macintosh 64-bit systems, the folder is `bin/maci64`:

- The `libmat.dylib` library of MAT-file routines (C/C++ and Fortran)
- The `libmx.dylib` library of array access and creation routines

Example Files

The `examples/eng_mat` folder contains C/C++ and Fortran source code for examples demonstrating how to use the MAT-file routines.

What You Need to Build Custom Applications

To create a custom application, you need the tools and knowledge to modify and build source code. In particular, you need a compiler supported by MATLAB.

To exchange custom data with MATLAB data, use a *MAT-file*, a MATLAB format binary file. You do not need the MAT-file format specifications because the MAT-File Interface Library provides the API to the data. You need to know the details of your data to map it into MATLAB data. Get this information from your product documentation, then use the `mxArray` type in the Matrix Library to declare the data in your program.

In your custom program, use functions in the MATLAB C/C++ and Fortran API:

- MAT-File Interface Library
- Matrix Library

To build the application, use the `mex` build script with the `-client engine` option.

See Also

`mex` | `mxArray`

More About

- “MAT-File Library and Include Files” on page 2-5
- “Building Engine Applications with IDE” on page 7-20

External Web Sites

- Supported and Compatible Compilers

Copy External Data into MAT-File Format with Standalone Programs

In this section...

- “Overview of `matimport.c` Example” on page 2-8
- “Declare Variables for External Data” on page 2-9
- “Create `mxArray` Variables” on page 2-9
- “Create MATLAB Variable Names” on page 2-10
- “Read External Data into `mxArray` Data” on page 2-10
- “Create and Open MAT-File” on page 2-11
- “Write `mxArray` Data to File” on page 2-11
- “Clean Up” on page 2-11
- “Build the Application” on page 2-11
- “Create the MAT-File” on page 2-11
- “Import Data into MATLAB” on page 2-12

Overview of `matimport.c` Example

This topic shows how to create a standalone program, `matimport`, to copy data from an external source into a MAT-file. The format of the data is custom, that is, it is not one of the file formats supported by MATLAB.

The `matimport.c` example:

- Creates variables to read the external data.
- Copies the data into `mxArray` variables.
- Assigns a variable name to each `mxArray`. This is the variable name to use in the MATLAB workspace.
- Writes the `mxArray` variables and associated variable names to the MAT-file.

To use the data in MATLAB:

- Build the standalone program `matimport`.
- Run `matimport` to create the MAT-file `matimport.mat`.

- Open MATLAB.
- Use one of the techniques described in “Save, Load, and Delete Workspace Variables”.

The following topics describe these steps in detail. To see the code, open the file in the MATLAB Editor. The C statements in these topics are code snippets shown to illustrate a task. The statements in the topics are not necessarily sequential in the source file.

Declare Variables for External Data

There are two external data values, a string and an array of type double. The following table shows the relationship between the variables in this example.

External Data	Variable to Read External Data	mxArray Variable	MATLAB Variable Name
Array of type double	extData	pVarNum	inputArray
String	extString	pVarChar	titleString

The following statements declare the type and size for variables `extString` and `extData`:

```
#define BUFSIZE 256
char extString[BUFSIZE];
double extData[9];
```

Use these variables to read values from a file or a subroutine available from your product. This example uses initialization to create the external data:

```
const char *extString = "Data from External Device";
double extData[9] = { 1.0, 4.0, 7.0, 2.0, 5.0, 8.0, 3.0, 6.0, 9.0 };
```

Create mxArray Variables

The MAT-File Library uses pointers of type `mxArray` to reference MATLAB data. The following statements declare `pVarNum` and `pVarChar` as pointers to an array of any size or type:

```
/*Pointer to the mxArray to read variable extData */
mxArray *pVarNum;
/*Pointer to the mxArray to read variable extString */
```

```
mxAarray *pVarChar;
```

To create a variable of the proper size and type, select one of the `mxCreat*` functions from the MX Matrix Library.

The size of `extData` is 9, which the example copies into a 3-by-3 matrix. Use the `mxCreatedoubleMatrix` function to create a two-dimensional, double-precision, floating-point `mxAarray` initialized to 0.

```
pVarNum = mxCreatedoubleMatrix(3,3,mxREAL);
```

Use the `mxCreatestring` function to create an `mxAarray` variable for `extString`:

```
pVarChar = mxCreatestring(extString);
```

Create MATLAB Variable Names

`matimport.c` assigns variable names `inputArray` and `titleString` to the `mxAarray` data. Use these names in the MATLAB workspace. For more information, see “View the Contents of a MAT-File”.

```
const char *myDouble = "inputArray";  
const char *myString = "titleString";
```

Read External Data into `mxAarray` Data

Copy data from the external source into each `mxAarray`.

The C `memcpy` function copies blocks of memory. This function requires pointers to the variables `extData` and `pVarNum`. The pointer to `extData` is `(void *)extData`. To get a pointer to `pVarNum`, use one of the `mxCreat*` functions from the MX Matrix Library. Since the data contains only real values of type `double`, this example uses the `mxCreatPr` function:

```
memcpy((void *)mxCreatPr(pVarNum), (void *)extData, sizeof(extData));
```

The following statement initializes the `pVarChar` variable with the contents of `extString`:

```
pVarChar = mxCreatestring(extString);
```

Variables `pVarNum` and `pVarChar` now contain the external data.

Create and Open MAT-File

The `matOpen` function creates a handle to a file of type `MATFile`. The following statements create a file pointer `pmat`, name the file `matimport.mat`, and open it for writing:

```
MATFile *pmat;  
const char *myFile = "matimport.mat";  
pmat = matOpen(myFile, "w");
```

Write mxArray Data to File

The `matPutVariable` function writes the `mxArray` and variable name into the file:

```
status = matPutVariable(pmat, myDouble, pVarNum);  
status = matPutVariable(pmat, myString, pVarChar);
```

Clean Up

To close the file:

```
matClose(pmat);
```

To free memory:

```
mxDestroyArray(pVarNum);  
mxDestroyArray(pVarChar);
```

Build the Application

To build the application, use the `mex` function with the `-client` engine option.

```
copyfile(fullfile(matlabroot, 'extern', 'examples', 'eng_mat', 'matimport.c'), '.', 'f')  
mex -v -client engine matimport.c
```

Create the MAT-File

Run `matimport` to create the file `matimport.mat`. Either invoke the program from the system command prompt, or at the MATLAB command prompt, type:

```
!matimport
```

Import Data into MATLAB

Any user with a compatible version of MATLAB can read the `matimport.mat` file. Start MATLAB and use the `load` command to import the data into the workspace:

```
load matimport.mat
```

To see the variables, type `whos`; MATLAB displays:

Name	Size	Bytes	Class
<code>inputArray</code>	3x3	72	double
<code>titleString</code>	1x43	86	char

Related Examples

- “Table of MAT-File Source Code Files” on page 2-19

Create MAT-File in C or C++

In this section...

“Create MAT-File in C” on page 2-13

“Create MAT-File in C++” on page 2-13

Create MAT-File in C

The `matcreat.c` example illustrates how to use the library routines to create a MAT-file that you can load into the MATLAB workspace. The program also demonstrates how to check the return values of MAT-function calls for read or write failures. To see the code, open the file in MATLAB Editor.

After building the program, run the application. This program creates `mattest.mat`, a MAT-file that you can load into MATLAB. To run the application, depending on your platform, either double-click its icon or enter `matcreat` at the system prompt:

```
matcreat
Creating file mattest.mat...
```

To verify the MAT-file, at the command prompt, type:

```
whos -file mattest.mat
  Name              Size          Bytes  Class
  GlobalDouble      3x3             72  double array (global)
  LocalDouble       3x3             72  double array
  LocalString       1x43            86  char array
```

Grand total is 61 elements using 230 bytes

Create MAT-File in C++

The C++ version of `matcreat.c` is `matcreat.cpp`. Open the file in MATLAB Editor.

Related Examples

- “Table of MAT-File Source Code Files” on page 2-19

Read MAT-File in C/C++

The `matdgn.c` example illustrates how to use the library routines to read and diagnose a MAT-file. To see the code, open the file in MATLAB Editor.

After building the program, run the application. This program reads the `mattest.mat` MAT-file created by the “Create MAT-File in C or C++” on page 2-13 example. To run the application, depending on your platform, either double-click its icon or enter `matdgn` at the system prompt.

```
matdgn mattest.mat
Reading file mattest.mat...
```

```
Directory of mattest.mat:
GlobalDouble
LocalString
LocalDouble
```

Examining the header for each variable:

```
According to its header, array GlobalDouble has 2 dimensions
    and was a global variable when saved
According to its header, array LocalString has 2 dimensions
    and was a local variable when saved
According to its header, array LocalDouble has 2 dimensions
    and was a local variable when saved
```

Reading in the actual array contents:

```
According to its contents, array GlobalDouble has 2 dimensions
    and was a global variable when saved
According to its contents, array LocalString has 2 dimensions
    and was a local variable when saved
According to its contents, array LocalDouble has 2 dimensions
    and was a local variable when saved
Done
```

Related Examples

- “Table of MAT-File Source Code Files” on page 2-19

Create MAT-File in Fortran

The `matdemo1.F` example creates the MAT-file, `matdemo.mat`. To see the code, you can open the file in MATLAB Editor.

After building the program, run the application. This program creates a MAT-file, `matdemo.mat`, that you can load into MATLAB. To run the application, depending on your platform, either double-click its icon or type `matdemo1` at the system prompt:

```
matdemo1
```

```
Creating MAT-file matdemo.mat ...
Done creating MAT-file
```

To verify the MAT-file, at the command prompt, type:

```
whos -file matdemo.mat
```

Name	Size	Bytes	Class	Attributes
Numeric	3x3	72	double	
NumericGlobal	3x3	72	double	global
String	1x33	66	char	

Note: For an example of a Microsoft Windows standalone program (not MAT-file specific), see `engwindemo.c` in the `matlabroot\extern\examples\eng_mat` folder.

Related Examples

- “Table of MAT-File Source Code Files” on page 2-19

Read MAT-File in Fortran

The `matdemo2.F` example illustrates how to use the library routines to read the MAT-file created by `matdemo1.F` and describe its contents. To see the code, open the file in MATLAB Editor.

After building the program, view the results:

```
matdemo2
Directory of Mat-file:
String
Numeric
Getting full array contents:
  1
Retrieved String
  With size  1-by- 33
  3
Retrieved Numeric
  With size  3-by- 3
```

Related Examples

- “Table of MAT-File Source Code Files” on page 2-19

Work with mxArray

In this section...

“Read Structures from a MAT-File” on page 2-17

“Read Cell Arrays from a MAT-File” on page 2-18

The MAT-File Interface Library lets you access MATLAB arrays (type `mxArray`) in a MAT-file. To work directly with an `mxArray` in a C/C++ application, use functions in the Matrix Library.

You can find examples for working with the `mxArray` type in the `matlabroot/extern/examples/mex` and `matlabroot/extern/examples/mx` folders. The following topics show C code examples, based on these MEX examples, for working with cells and structures. The examples show how to read cell and structure arrays and display information based on the type of the `mxArray` within each array element.

If you create an application from one of the MEX examples, here are some tips for adapting the code to a standalone application.

- The MAT-file example, `matdgns.c`, shows how to open and read a MAT-file. For more information about the example, see “Read MAT-File in C/C++” on page 2-14.
- The MEX example, `explore.c`, has functions to read any MATLAB type using the `mxClassID` function. For more information about the example, see “Using Data Types”.
- Some MEX examples use functions, such as `mexPrintf`, from the “MEX Library” `libmex`. You do not need to use these functions to work with an `mxArray`, but if your program calls any of them, you must link to the MEX Library. To do this, add `libmex.lib` to the link statement.

Read Structures from a MAT-File

The `matreadstructarray.c` example is based on the `analyze_structure` function in `explore.c`. For simplicity this example only processes real elements of type `double`; refer to the `explore.c` example for error checking and processing other types.

To see the code, open the file in the MATLAB Editor.

After building the program, run the application on the MAT-file, `testpatient.mat`.

First, create a structure, `patient`, and save it:

```
patient(1).name = 'John Doe';
patient(1).billing = 127.00;
patient(1).test = [79 75 73; 180 178 177.5; 172 170 169];
patient(2).name = 'Ann Lane';
patient(2).billing = 28.50;
patient(2).test = [68 70 68; 118 118 119; 172 170 169];

save testpatient.mat
```

To calculate the total of the `billing` field, type:

```
!matreadstruct testpatient.mat patient billing
```

```
Total for billing: 155.50
```

Read Cell Arrays from a MAT-File

The `matreadcellarray.c` example is based on the `analyze_cell` function in `explore.c`.

To see the code, open the file in the MATLAB Editor.

After building the program, run the application on the MAT-file, `testcells.mat`.

First, create 3 cell variables and save:

```
cellvar = {'hello'; [2 3 4 6 8 9]; [2; 4; 5]};
structvar = {'cell with a structure'; patient; [2; 4; 5]};
multicellvar = {'cell with a cell'; cellvar; patient};

save testcells.mat cellvar structvar multicellvar
```

To display the `mxArray` type for the contents of cell `cellvar`, type:

```
!matreadcell testcells.mat cellvar
```

```
0: string
1: numeric class
2: numeric class
```

Related Examples

- “Table of MAT-File Source Code Files” on page 2-19

Table of MAT-File Source Code Files

The `matlabroot/extern/examples/eng_mat` folder contains C/C++ and Fortran source code for examples demonstrating how to use the MAT-file routines. These examples create standalone programs. The source code is the same for both Windows, Mac, and Linux systems.

To build a code example, first copy the file to a writable folder, such as `c:\work` on your Windows path:

```
copyfile(fullfile(matlabroot,'extern','examples','eng_mat',...
'filename'), fullfile('c:','work'))
```

where *filename* is the name of the source code file.

For build information, see:

- “MAT-File Library and Include Files” on page 2-5
- “Building on Mac and Linux Operating Systems” on page 2-21
- “Building on Windows Operating Systems” on page 2-23

Example	Description
<code>matcreat.c</code>	C program that demonstrates how to use the library routines to create a MAT-file that you can load into MATLAB.
<code>matcreat.cpp</code>	C++ version of the <code>matcreat.c</code> program.
<code>matdgn.c</code>	C program that demonstrates how to use the library routines to read and diagnose a MAT-file.
<code>matdemo1.F</code>	Fortran program that demonstrates how to call the MATLAB MAT-file functions from a Fortran program.
<code>matdemo2.F</code>	Fortran program that demonstrates how to use the library routines to read the MAT-file created by <code>matdemo1.F</code> and describe its contents.
<code>matimport.c</code>	C program based on <code>matcreat.c</code> used in the example for writing standalone applications.
<code>matreadstructarray.c</code>	C program based on <code>explore.c</code> to read contents of a structure array.
<code>matreadcellarray.c</code>	C program based on <code>explore.c</code> to read contents of a cell array.

Example	Description
<code>matcreat.c</code>	C program that demonstrates how to use the library routines to create a MAT-file that you can load into MATLAB.
<code>matcreat.cpp</code>	C++ version of the <code>matcreat.c</code> program.
<code>matdgns.c</code>	C program that demonstrates how to use the library routines to read and diagnose a MAT-file.
<code>matdemo1.F</code>	Fortran program that demonstrates how to call the MATLAB MAT-file functions from a Fortran program.
<code>matdemo2.F</code>	Fortran program that demonstrates how to use the library routines to read the MAT-file created by <code>matdemo1.F</code> and describe its contents.
<code>matimport.c</code>	C program based on <code>matcreat.c</code> used in the example for writing standalone applications.
<code>matreadstructarray.c</code>	C program based on <code>explore.c</code> to read contents of a structure array.
<code>matreadcellarray.c</code>	C program based on <code>explore.c</code> to read contents of a cell array.

For examples using the Matrix Library, see:

- “Table of MEX-File Source Code Files” on page 5-24.
- The `explore.c` example described in “Using Data Types” on page 4-12.

Building on Mac and Linux Operating Systems

In this section...

“Setting Run-Time Library Path” on page 2-21

“Building the Application” on page 2-22

Setting Run-Time Library Path

At run time, you must tell the Mac and Linux operating system where the API shared libraries reside by setting an environment variable. The Mac or Linux command you use and the values you provide depend on your shell and system architecture. The following table lists the name of the environment variable (*envvar*) and the values (*pathspec*) to assign to it. The term *matlabroot* refers to the root folder of your MATLAB installation.

Operating System	<i>envvar</i>	<i>pathspec</i>
64-bit Apple Mac	DYLD_LIBRARY_PATH	<i>matlabroot</i> /bin/maci64: <i>matlabroot</i> /sys/os/maci64
64-bit Linux	LD_LIBRARY_PATH	<i>matlabroot</i> /bin/glnxa64: <i>matlabroot</i> /sys/os/glnxa64

Using the C Shell

Set the library path using the command:

```
setenv envvar pathspec
```

Replace the terms *envvar* and *pathspec* with the appropriate values from the table. For example, on a Macintosh system use:

```
setenv DYLD_LIBRARY_PATH  
matlabroot/bin/maci64:matlabroot/sys/os/maci64
```

You can place these commands in a startup script, such as `~/ .cshrc`.

Using the Bourne Shell

Set the library path using the command:

```
envvar = pathspec:envvar
```

```
export envvar
```

Replace the terms *envvar* and *pathspec* with the appropriate values from the table. For example, on a Macintosh system use:

```
DYLD_LIBRARY_PATH=matlabroot/bin/maci64:matlabroot/sys/os/maci64:$DYLD_LIBRARY_PATH  
export DYLD_LIBRARY_PATH
```

You can place these commands in a startup script such as `~/ .profile`.

Building the Application

To compile and link the `matcreat.c` example, use the `mex` script with the `-client` engine option.

```
copyfile(fullfile(matlabroot, 'extern', 'examples', 'eng_mat', 'matcreat.c'), '.', 'f')
```

Use the following command to build it:

```
mex -v -client engine matcreat.c
```

If you need to modify the build instructions for your particular compiler, use the `-v -n` options to view the current compiler and linker settings. Then, modify the settings using the `mex varname=varvalue` option.

See Also

`mex`

Building on Windows Operating Systems

To compile and link MAT-file programs, use the `mex` script with the `-client engine` option.

```
copyfile(fullfile(matlabroot, 'extern', 'examples', 'eng_mat', 'matcreat.c'), '.', 'f')
```

Use the following command to build it:

```
mex -v -client engine matcreat.c
```

If you need to modify the build instructions for your particular compiler, use the `-v -n` options to view the current compiler and linker settings. Then, modify the settings using the `mex varname=varvalue` option.

See Also

`mex`

Sharing MAT-File Applications

MATLAB requires shared library files for building any MAT-file application. You must also distribute the run-time versions of these files along with any MAT-file application that you deploy to another system. Install the appropriate libraries in the *matlabroot/bin/arch* folder.

Library File Names by Operating System

Windows	Linux	Mac
libmat.dll	libmat.so	libmat.dylib
libmx.dll	libmx.so	libmx.dylib

In addition to these libraries, you must have all third-party library files that `libmat` requires. MATLAB uses these additional libraries to support Unicode[®] character encoding and data compression in MAT-files. These library files must reside in the same folder as `libmx`. Determine the libraries using the platform-specific methods described in the following table.

Library Dependency Commands

Windows	Linux	Mac
See the following instructions for Dependency Walker	<code>ldd -d libmat.so</code>	<code>otool -L libmat.dylib</code>

On Windows systems, to find library dependencies, use the third-party product Dependency Walker. Dependency Walker is a free utility that scans any 32-bit or 64-bit Windows module and builds a hierarchical tree diagram of all dependent modules. For each module found, it lists all the functions exported by that module, and which of those functions are called by other modules. Download the Dependency Walker utility from the website <http://www.dependencywalker.com/>. See <http://www.mathworks.com/matlabcentral/answers/92362-how-do-i-determine-which-libraries-my-mex-file-or-stand-alone-application-requires> for information on using the Dependency Walker.

Drag and drop the file *matlabroot/bin/win32/libmat.dll* or *matlabroot/bin/win64/libmat.dll* into Depends window.

Calling C Shared Library Functions from MATLAB

- “Calling Functions in Shared Libraries” on page 3-2
- “Limitations to Shared Library Support” on page 3-8
- “Module Not Found Error” on page 3-13
- “No Matching Signature Error” on page 3-14
- “MATLAB Crashes Calling Function in Shared Library” on page 3-15
- “Passing Arguments to Shared Library Functions” on page 3-16
- “Shared Library shrlibsample.c” on page 3-20
- “Pass String Arguments” on page 3-21
- “Pass Structures” on page 3-23
- “Pass Enumerated Types” on page 3-26
- “Pass Pointers” on page 3-28
- “Pass Arrays” on page 3-29
- “Iterate Through an Array” on page 3-32
- “Working with Pointer Arguments” on page 3-34
- “Working with Structure Arguments” on page 3-45
- “Work with libstruct Objects” on page 3-47
- “MATLAB Prototype Files” on page 3-49

Calling Functions in Shared Libraries

In this section...

“What Is a Shared Library?” on page 3-2

“Loading and Unloading the Library” on page 3-3

“Viewing Library Functions” on page 3-4

“Invoking Library Functions” on page 3-6

What Is a Shared Library?

A shared library is a collection of functions designed to be dynamically loaded by an application at run time. This MATLAB interface supports libraries containing functions programmed in any language, provided the functions have a C interface. MATLAB supports dynamic linking on all supported platforms.

Platform	Shared Library	File Extension
Microsoft Windows	dynamic link library file	.dll
UNIX [®] and Linux	shared object file	.so
Apple Macintosh	dynamic shared library	.dylib

A shared library needs a *header file*, which provides *signatures* for the functions in the library. A function signature, or prototype, establishes the name of the function and the number and types of its parameters. You need to know the full path of the shared library and its header file.

You need an installed MATLAB-supported C compiler. For an up-to-date list of supported compilers, see the Supported and Compatible Compilers website.

MATLAB accesses C routines built into external, shared libraries through a command-line interface. This interface lets you load an external library into MATLAB memory and access functions in the library. Although types differ between the two language environments, in most cases you can pass types to the C functions without converting. MATLAB does this for you.

Details about using a shared library are in the topics:

- “Loading and Unloading the Library” on page 3-3
- “Viewing Library Functions” on page 3-4
- “Invoking Library Functions” on page 3-6

If the library function passes arguments, you need to determine the data passed to and from the function. For information about data, see:

- “Passing Arguments to Shared Library Functions” on page 3-16
- “Manually Converting Data Passed to Functions” on page 3-19
- “Working with Pointer Arguments” on page 3-34
- “Working with Structure Arguments” on page 3-45

When you are finished working with the shared library, it is important to unload the library to free memory.

For more information, see “Limitations to Shared Library Support” on page 3-8

Loading and Unloading the Library

To give MATLAB access to functions in a shared library, you must first load the library into memory. After you load the library, you can request information about library functions and call them directly from the MATLAB command line. When you no longer need the library, unload it from memory to conserve memory usage.

To load a shared library into MATLAB, use the `loadlibrary` function. The most common syntax is:

```
loadlibrary('shrlib', 'hfile')
```

where *shrlib* is the shared library file name, and *hfile* is the name of the header file containing the function prototypes.

Note: The header file provides signatures for the functions in the library and is a required argument for `loadlibrary`.

For example, load the `libmx` library that defines the MATLAB Matrix Library routines. The following command creates the full path for the library header file, `matrix.h`:

```
hfile = fullfile(matlabroot, 'extern', 'include', 'matrix.h');
```

To load the library, type:

```
loadlibrary('libmx', hfile)
```

Use the `unloadlibrary` function to unload the library and free up memory.

Note: If you call `loadlibrary` on a library that is already loaded, MATLAB displays a message, but does not reload the library. To determine if a library is loaded, use the `libisloaded` function.

Viewing Library Functions

- “Viewing Functions in the Command Window” on page 3-4
- “Viewing Functions in a UI” on page 3-5

Viewing Functions in the Command Window

Use the `libfunctions` command to display information about a library's functions in the MATLAB Command Window. For example, to see what functions are available in the `libmx` library, type:

```
if not(libisloaded('libmx'))
    hfile = [matlabroot '\extern\include\matrix.h'];
    loadlibrary('libmx', hfile)
end
libfunctions libmx
```

MATLAB displays (in part):

Functions in library libmx:

<code>mxAddField</code>	<code>mxGetScalar</code>
<code>mxArrayToString</code>	<code>mxGetString_730</code>
<code>mxCalcSingleSubscript_730</code>	<code>mxGetUserBits</code>
<code>mxCalloc</code>	<code>mxIsCell</code>
<code>mxCreateCellArray_730</code>	<code>mxIsChar</code>
<code>mxCreateCellMatrix_730</code>	<code>mxIsClass</code>
<code>:</code>	<code>:</code>
<code>:</code>	<code>:</code>

To view function signatures, use the `-full` switch. This shows the MATLAB syntax for calling functions written in C. The types used in the argument lists and return values are MATLAB types, not C types. For more information on types, see “C and MATLAB Equivalent Types” on page 3-16. For example, at the command line enter:

```
list = libfunctions('libmx', '-full')
```

MATLAB displays (in part):

```
list =
' [int32, MATLAB array, cstring] mxAddField(MATLAB array, cstring) '
' [cstring, MATLAB array] mxArrayToString(MATLAB array) '
' [uint64, MATLAB array, uint64Ptr] mxCalcSingleSubscript_730(
MATLAB array, uint64, uint64Ptr) '
' lib.pointer mxCalloc(uint64, uint64) '
' [MATLAB array, uint64Ptr] mxCreateCellArray_730(uint64, uint64Ptr) '
' MATLAB array mxCreateCellMatrix_730(uint64, uint64) '
.
.
.
```

Viewing Functions in a UI


Use the `libfunctionsview` function to get information about functions in a library. MATLAB creates a new window to display the following information:

Heading	Description
Return Type	Types the method returns
Name	Function name
Arguments	Valid types for input arguments

To see the functions in the `libmx` library, type:

```
if not(libisloaded('libmx'))
    hfile = [matlabroot '\extern\include\matrix.h'];
    loadlibrary('libmx', hfile)
end
libfunctionsview libmx
```

MATLAB displays the following window:



Return Type	Name	Arguments
[int32, MATLAB array, cstring]	mxAddField	(MATLAB array, cstring)
[cstring, MATLAB array]	mxArrayToString	(MATLAB array)
[int32, MATLAB array, int32Ptr]	mxCalcSingleSubscript	(MATLAB array, int32, int32Ptr)
lib.pointer	mxCalloc	(uint32, uint32)
MATLAB array	mxClearScalarDoubleFlag	(MATLAB array)
[MATLAB array, int32Ptr]	mxCreateCellArray	(int32, int32Ptr)
MATLAB array	mxCreateCellMatrix	(int32, int32)
[MATLAB array, int32Ptr]	mxCreateCharArray	(int32, int32Ptr)
[MATLAB array, stringPtrPtr]	mxCreateCharMatrixFromStrings	(int32, stringPtrPtr)
MATLAB array	mxCreateDoubleMatrix	(int32, int32, mxComplexity)
MATLAB array	mxCreateDoubleScalar	(double)
[MATLAB array, int32Ptr]	mxCreateLogicalArray	(int32, int32Ptr)
MATLAB array	mxCreateLogicalMatrix	(uint32, uint32)
MATLAB array	mxCreateLogicalScalar	(bool)

The types used in the argument lists and return values are MATLAB types, not C types. For more information on types, see “C and MATLAB Equivalent Types” on page 3-16.

Invoking Library Functions

After loading a shared library into the MATLAB workspace, use the `calllib` function to call functions in the library. The syntax for `calllib` is:

```
calllib('libname', 'funcname', arg1, ..., argN)
```

You need to specify the library name, function name, and, if required, any arguments that get passed to the function.

The following example calls functions from the `libmx` library. To load the library, type:

```
if not(libisloaded('libmx'))
    hfile = [matlabroot '\extern\include\matrix.h'];
    loadlibrary('libmx', hfile)
end
```

To create an array `y`, type:

```
y = rand(4,7,2);
```

To get information about `y`, type:

```
calllib('libmx','mxGetNumberOfElements',y)
```

```
ans =  
    56
```

MATLAB displays the number of elements in the array.

Type:

```
calllib('libmx','mxGetClassID',y)
```

```
ans =  
    mxDOUBLE_CLASS
```

MATLAB displays the class of the array.

For information on how to define the argument types, see “Passing Arguments to Shared Library Functions” on page 3-16.

Limitations to Shared Library Support

In this section...

“MATLAB Supports C Library Routines” on page 3-8

“Workarounds for Loading C++ Libraries” on page 3-8

“Using Bit Fields” on page 3-9

“Using Enum Declarations” on page 3-10

“Unions Not Supported” on page 3-10

“Compiler Dependencies” on page 3-11

“Limitations Using Structures” on page 3-11

“Limitations Using Pointers” on page 3-11

“Functions with Variable Number of Input Arguments Not Supported” on page 3-11

MATLAB Supports C Library Routines

The MATLAB shared library interface supports C library routines only. Most professionally written libraries designed to be used by multiple languages and platforms work fine. Many homegrown libraries or libraries that have only been tested from C++ have interfaces that are not usable and require modification or an interface layer. In this case, we recommend using MEX-files.

Workarounds for Loading C++ Libraries

The shared library interface does not support C++ classes or overloaded functions elements. However, you can apply one of the following methods to load a C++ library using `loadlibrary`.

Declare Functions as extern “C”

For example, the following function prototype from the file `shrlibsample.h` shows the syntax to use for each function:

```
#ifdef __cplusplus
extern "C" {
#endif
void addMixedTypes(
    short x,
```

```
    int    y,  
    double z  
);  
  
/* other prototypes may be here */  
  
#ifdef __cplusplus  
}  
#endif
```

The following C++ code is not legal C code for the header file:

```
extern "C" void addMixedTypes(short x,int y,double z);
```

Add Module Definition File in Visual Studio

While building the DLL from C++ code in Microsoft Visual Studio[®], add a Module Definition File (.DEF) in the project. At a minimum, the DEF file must contain the following module-definition statements:

- The first statement in the file must be the LIBRARY statement.
- The EXPORTS statement lists the names and, optionally, the ordinal values of the functions exported by the DLL.

For example, if a DLL exports functions `multDoubleArray` and `addMixedTypes`, `module.def` contains:

```
LIBRARY  
EXPORTS  
multDoubleArray  
addMixedTypes
```

Using Bit Fields

You can modify a bit field declaration by using type `int` or an equivalent. For example, if your library has the following declared in its header file:

```
int myfunction();  
  
struct mystructure  
{  
    /* note the sum of fields bits */  
    unsigned field1 :4;
```

```
    unsigned field2 :4;
};
```

you can replace it with:

```
int myfunction();

struct mystructure
{
    /* field 8 bits wide to be manipulated in MATLAB */
    /* A char is 8 bits on all supported platforms */
    char allfields;
};
```

It is then possible to access the data in the two fields using bit masking in MATLAB.

Using Enum Declarations

`char` definitions for `enum` are not supported. In C, a `char` constant, for example `'A'`, is automatically converted to its numeric equivalent (65). MATLAB does not convert constants. To use this type of `enum`, modify the header file by replacing `'A'` with the number 65 (`int8('A') == 65`). For example, replace:

```
enum Enum1 {ValA='A',ValB='B'};
```

with:

```
enum Enum1 {ValA=65,ValB=66};
```

Unions Not Supported

Unions are not supported. It might be possible to modify the source code taking out the `union` declaration and replacing it with the largest alternative, then writing MATLAB code to interpret the results as needed. For example, replace the following union:

```
struct mystruct
{
    union
    {
        struct {char byte1,byte2;};
        short word;
    };
};
```

with:

```
struct mystruct
{
    short word;
};
```

where on a little-endian based machine, `byte1` is `mod(f,256)`, `byte2` is `f/256`, and `word=byte2*256+byte1`.

Compiler Dependencies

Header files must be compatible with the supported compilers on a platform. For an up-to-date list of supported compilers, see the [Supported and Compatible Compilers](#) website. You cannot load external libraries with explicit dependencies on other compilers.

Limitations Using Structures

MATLAB returns pointers to structures. Return by value is not supported.

Nested structures or structures containing a pointer to a structure are not supported. However, MATLAB can access an array of structures created in an external library.

Limitations Using Pointers

Function Pointers

The shared library interface does not support library functions that work with function pointers.

Multilevel Pointers

Limited support for multilevel pointers and structures containing pointers. Using inputs and outputs and structure members declared with more than two levels of indirection is unsupported. For example, `double ***outp` translated to `doublePtrPtrPtr` is not supported.

Functions with Variable Number of Input Arguments Not Supported

The shared library interface does not support library functions with variable number of arguments, represented by an ellipsis (`...`).

You can create multiple alias functions in a prototype file, one for each set of arguments used to call the function. For more information, see “MATLAB Prototype Files” on page 3-49.

Module Not Found Error

This error occurs when the shared library has dependencies which MATLAB can not find.

On Windows systems, to find library dependencies, use the third-party product Dependency Walker. Dependency Walker is a free utility that scans any 32-bit or 64-bit Windows module and builds a hierarchical tree diagram of all dependent modules. For each module found, it lists all the functions exported by that module, and which of those functions are called by other modules. Download the Dependency Walker utility from the website <http://www.dependencywalker.com/>. See <http://www.mathworks.com/matlabcentral/answers/92362-how-do-i-determine-which-libraries-my-mex-file-or-stand-alone-application-requires> for information on using the Dependency Walker.

No Matching Signature Error

This error occurs when you call a function without the correct input arguments, or if there is an error in the function signature in the header file.

For example, the function signature for the `addStructByRef` function in `shrlibsample` is:

```
[double, c_structPtr] addStructByRef(c_structPtr)
```

Load the library.

```
addpath(fullfile(matlabroot, 'extern', 'examples', 'shrlib'))  
loadlibrary('shrlibsample')
```

Create a structure, and call `addStructByRef`.

```
struct.p1 = 4;  
struct.p2 = 7.3;  
struct.p3 = -290;
```

If you call the function without the input argument, MATLAB displays the error message.

```
[res,st] = calllib('shrlibsample','addStructByRef')
```

```
Error using calllib  
No method with matching signature.
```

The correct call is:

```
[res,st] = calllib('shrlibsample','addStructByRef',struct)
```

MATLAB Crashes Calling Function in Shared Library

Some shared libraries, compiled as Microsoft Windows 32-bit libraries, use a calling convention that is incompatible with the default MATLAB calling convention. The default calling convention for MATLAB and for Microsoft C and C++ compilers is `cdecl`. For more information, see the MSDN® Calling Conventions article.

If your library uses a different calling convention, you must create a `loadlibrary` prototype file and modify it with the correct settings, as described in <http://www.mathworks.com/matlabcentral/answers/96578-why-does-matlab-crash-when-i-make-a-function-call-on-a-dll-in-matlab-7-6-r2008a>.

See Also

`loadlibrary`

Related Examples

- Why does MATLAB crash when I make a function call on a DLL in MATLAB 7.6 (R2008a)?

More About

- “MATLAB Prototype Files” on page 3-49

External Web Sites

- Calling Conventions

Passing Arguments to Shared Library Functions

In this section...

“C and MATLAB Equivalent Types” on page 3-16

“Passing Arguments” on page 3-18

“Passing a NULL Pointer” on page 3-18

“Manually Converting Data Passed to Functions” on page 3-19

C and MATLAB Equivalent Types

The shared library interface supports all standard scalar C types. The following table shows these C types with their equivalent MATLAB types. MATLAB uses the type from the right column for arguments having the C type shown in the left column.

Note: All scalar values returned by MATLAB are of type double.

MATLAB Primitive Types

C Type	Equivalent MATLAB Type
char, byte	int8
unsigned char, byte	uint8
short	int16
unsigned short	uint16
int	int32
long (Windows)	int32, long
long (Linux)	int64, long
unsigned int	uint32
unsigned long (Windows)	uint32, long
unsigned long (Linux)	uint64, long

C Type	Equivalent MATLAB Type
float	single
double	double
char *	char array (1xn)
*char[]	cell array of strings

The following table shows how MATLAB maps C pointers (column 1) to the equivalent MATLAB function signature (column 2). In most cases, you can pass a variable from the Equivalent MATLAB Type column to functions with the corresponding Argument Data Type. See “Pointer Arguments in C Functions” on page 3-34 for information about when you might choose to use a `lib.pointer` object instead.

MATLAB Extended Types

C Pointer Type	Argument Data Type	Equivalent MATLAB Type
double *	doublePtr	double
float *	singlePtr	single
intsize * (integer pointer types)	(u)int(size)Ptr For example, int64 * becomes int64Ptr.	(u)int(size)
byte[]	int8Ptr	int8
char[] (null-terminated string passed by value)	cstring	char array (1xn)
char ** (array of pointers to strings)	stringPtrPtr	cell array of strings
enum	enumPtr	
type **	typePtrPtr For example, double ** becomes doublePtrPtr.	lib.pointer object
void *	voidPtr	
void **	voidPtrPtr	lib.pointer object
struct (C-style structure)	structure	MATLAB struct
mxArray *	MATLAB array	MATLAB array
mxArray **	MATLAB arrayPtr	lib.pointer object

Passing Arguments

Here are some important things to note about the input and output arguments shown in the Functions in library `shrlibsample` listing:

- Many arguments (like `int32` and `double`) are similar to their C counterparts. In these cases, you need only to pass in the MATLAB types shown for these arguments.
- Some C arguments (for example, `**double`, or predefined structures), are different from standard MATLAB types. In these cases, you can either pass a standard MATLAB type and let MATLAB convert it for you, or you convert the data yourself using the MATLAB functions `libstruct` and `libpointer`. For more information, see “Manually Converting Data Passed to Functions” on page 3-19.
- C functions often return data in input arguments passed by reference. MATLAB creates additional output arguments to return these values. Note that in the listing in the previous section, all input arguments ending in `Ptr` or `PtrPtr` are also listed as outputs.

Guidelines for Passing Arguments

- Nonscalar arguments must be declared as passed by reference in the library functions.
- If the library function uses single subscript indexing to reference a two-dimensional matrix, keep in mind that C programs process matrices row by row while MATLAB processes matrices by column. To get C behavior from the function, transpose the input matrix before calling the function, and then transpose the function output.
- Use an empty array, `[]`, to pass a NULL parameter to a library function that supports optional input arguments. This is valid only when the argument is declared as a `Ptr` or `PtrPtr` as shown by `libfunctions` or `libfunctionsview`.

Passing a NULL Pointer

You can create a NULL pointer to pass to library functions in the following ways:

- Pass an empty array `[]` as the argument.
- Use the `libpointer` function:

```
p = libpointer; % no arguments
```

```
p = libpointer('string') % string argument
```

```
p = libpointer('cstring') % pointer to a string argument
```

- Use the `libstruct` function:

```
p = libstruct('structtype'); % structure type
```

Creating an Empty `libstruct` Object

To create an empty `libstruct` object, call `libstruct` with only the `structtype` argument. For example:

```
sci = libstruct('c_struct')
get(sci)
```

```
p1: 0
p2: 0
p3: 0
```

MATLAB displays the initialized values.

Manually Converting Data Passed to Functions

Under most conditions, MATLAB software automatically converts data passed to and from external library functions to the type expected by the external function. However, you may choose to convert your argument data manually. Circumstances under which you might find this advantageous are:

- When you pass the same piece of data to a series of library functions, you can convert it once manually before the call to the first function rather than having MATLAB convert it automatically on every call. This reduces the number of unnecessary copy and conversion operations.
- When you pass large structures, you can save memory by creating MATLAB structures that match the shape of the C structures used in the external function instead of using generic MATLAB structures. The `libstruct` function creates a MATLAB structure modeled from a C structure taken from the library. See “Working with Structure Arguments” on page 3-45 for more information.
- When an argument to an external function uses more than one level of referencing (e.g., `double **`), you must pass a pointer created using the `libpointer` function rather than relying on MATLAB to convert the type automatically.

Shared Library `shrlibsample.c`

MATLAB software includes a sample external library called `shrlibsample.c`. The library is in the folder `matlabroot\extern\examples\shrlib`. To see the code, open the file in MATLAB Editor. The corresponding header file is `shrlibsample.h`. To see the code, open this file.

To use the `shrlibsample` library, you first need to either add this folder to your MATLAB path with the command:

```
addpath(fullfile(matlabroot, 'extern', 'examples', 'shrlib'))
```

or make the folder your current working folder with the command:

```
cd(fullfile(matlabroot, 'extern', 'examples', 'shrlib'))
```

The following code loads the library and displays the MATLAB syntax for calling functions in the library:

```
loadlibrary('shrlibsample')  
libfunctions shrlibsample -full
```

Functions in `shrlibsample` Library

Functions in library `shrlibsample`:

```
[double, doublePtr] addDoubleRef(double, doublePtr, double)  
double addMixedTypes(int16, int32, double)  
[double, c_structPtr] addStructByRef(c_structPtr)  
double addStructFields(c_struct)  
c_structPtrPtr allocateStruct(c_structPtrPtr)  
voidPtr deallocateStruct(voidPtr)  
lib.pointer exportedDoubleValue  
lib.pointer getListOfStrings  
doublePtr multDoubleArray(doublePtr, int32)  
[lib.pointer, doublePtr] multDoubleRef(doublePtr)  
int16Ptr multiplyShort(int16Ptr, int32)  
doublePtr print2darray(doublePtr, int32)  
printExportedDoubleValue  
cstring readEnum(Enum1)  
[cstring, cstring] stringToUpper(cstring)
```


Pass String Arguments

For arguments that require `char *`, you can pass a MATLAB string (a character array). For example, see the `stringToUpper` function in the `shrllibsample` library.

`stringToUpper` C Function

```
EXPORTED_FUNCTION char* stringToUpper(char *input)
{
    char *p = input;

    if (p != NULL)
        while (*p!=0)
            *p++ = toupper(*p);
    return input;
}
```

`libfunctions` shows that you can use a MATLAB `cstring` for this input. Type:

```
libfunctions shrllibsample -full
```

`stringToUpper` Function Signature

Return Type	Name	Arguments
[<code>cstring</code> , <code>cstring</code>]	<code>stringToUpper</code>	(<code>cstring</code>)

Create a MATLAB character array, `str`, and pass it as the input argument:

```
str = 'This was a Mixed Case string';
calllib('shrllibsample', 'stringToUpper', str)
```

```
ans =
    THIS WAS A MIXED CASE STRING
```

Although the input argument that MATLAB passes to `stringToUpper` resembles a pointer to type `char`, it is not a true pointer data type because it does not contain the address of the MATLAB character array, `str`. When the function executes, it returns the correct result, but does not modify the value in `str`. If you examine `str`, you find it is unchanged. Type:

```
str
```

```
str =  
    This was a Mixed Case string
```

Pass Structures

In this section...

“Add Values of Fields in Structure” on page 3-23

“Preconvert MATLAB Structure Before Adding Values” on page 3-24

“Display Structure Field Names” on page 3-25

Add Values of Fields in Structure

This example shows how to pass a MATLAB structure to the function, `addStructFields`. `addStructFields`, in the `shrlibsampl.c` example library, sums the values of the fields in a structure.

Read the function signature.

`addStructFields` Function Signature

Return Type	Name	Arguments
double	<code>addStructFields</code>	(struct <code>c_struct</code> <code>st</code>)

The input argument is a structure of type `c_struct`.

Look at the definition in the `shrlibsampl.h` header file for information about how to create the structure.

`c_struct` Structure Definition

```
struct c_struct {
    double p1;
    short p2;
    long p3;
};
```

Create and initialize structure `sm`:

```
sm.p1 = 476;
sm.p2 = -299;
sm.p3 = 1000;
```

Each field is of type double.

Load the library.

```
if not(libisloaded('shrllibsample'))
    addpath(fullfile(matlabroot,'extern','examples','shrllib'))
    loadlibrary('shrllibsample')
end
```

Call the function.

```
calllib('shrllibsample','addStructFields',sm)

ans =
     1177
```

MATLAB automatically converts the fields of structure `sm` to the library definition for `c_struct`.

Preconvert MATLAB Structure Before Adding Values

This example shows how to preconvert structure `sm` to `c_struct` before calling `addStructFields`.

Create and initialize structure `sm`:

```
sm.p1 = 476;
sm.p2 = -299;
sm.p3 = 1000;
```

Convert the fields, which are of type double, to match the `c_struct` structure type.

```
if (libisloaded('shrllibsample'))
    sc = libstruct('c_struct',sm);
end
```

The fields of `libstruct` object `sc` are double, short, and long.

Call the function.

```
calllib('shrllibsample','addStructFields',sc)

ans =
```

1177

Display Structure Field Names

This example shows how to display the field names of an externally-defined structure.

Create a libstruct object from `c_struct`, in the `shrlibsample.c` example library.

```
if (libisloaded('shrlibsample'))  
    s = libstruct('c_struct');  
end
```

To get the names of the fields, type:

```
get(s)  
  
    p1: 0  
    p2: 0  
    p3: 0
```

MATLAB displays the field names `p1`, `p2`, and `p3` and their values.

See Also

“Shared Library `shrlibsample.c`” on page 3-20

More About

- “Strategies for Passing Structures” on page 3-45

Pass Enumerated Types

In this section...

“Call Function with Enumeration String” on page 3-26

“Call Function with Integer Equivalent of Enumeration” on page 3-26

In MATLAB, you can express an enumerated type as either the enumeration string or its equivalent numeric value.

The `readEnum` function from the `shrllibsample` library displays a string that matches the input argument.

`readEnum` Function Signature

Return Type	Name	Arguments
<code>cstring</code>	<code>readEnum</code>	(Enum1)

Look at the definition in the `shrllibsample.h` header file for information about the values for the Enum1 input.

Enum1 enum Definition

```
typedef enum Enum1 {en1 = 1, en2, en4 = 4} TEnum1;
```

Call Function with Enumeration String

This example shows how to call `readEnum` with a string.

```
calllib('shrllibsample', 'readEnum', 'en4')
```

```
ans =  
    You chose en4
```

Call Function with Integer Equivalent of Enumeration

This example shows how to call `readEnum` with the numeric argument.

The Enum1 definition declares enumeration `en4` equal to 4.

```
calllib('shrllibsample', 'readEnum', 4)
```

```
ans =  
  You chose en4
```

Pass Pointers

Pass Primitive MATLAB Type

MATLAB automatically converts an argument passed by value into an argument passed by reference when the external function prototype defines the argument as a pointer. For example, a MATLAB `double` argument passed to a function that expects `double *` is converted to a `double` pointer by MATLAB.

`addDoubleRef` is a C function that takes an argument of type `double *`.

`addDoubleRef` C Function

```
EXPORTED_FUNCTION double addDoubleRef(double x, double *y, double z)
{
    return (x + *y + z);
}
```

Call the function with three arguments of type `double`, and MATLAB handles the conversion:

```
calllib('shrlibsample', 'addDoubleRef', 1.78, 5.42, 13.3)
ans =
    20.5000
```


Pass Arrays

In this section...

“Two Dimensional MATLAB Arrays” on page 3-29

“More than Two Dimensional MATLAB Arrays” on page 3-30

Two Dimensional MATLAB Arrays

All MATLAB data is stored columnwise, and MATLAB uses one-based indexing for subscripts. MATLAB uses these conventions because it was originally written in Fortran. To demonstrate how this may affect your MATLAB data when using C functions, create the following matrix:

```
m = 1:12;
m = reshape(m,4,3)
dims = size(m)
```

```
m =
     1     5     9
     2     6    10
     3     7    11
     4     8    12
```

```
dims =
     4     3
```

Matrix `m` is a 4-by-3 array.

You might need to transpose MATLAB arrays before passing them to a C function since C assumes a row by column format. The `print2darray` function in the `shrlibsample` library shows this.

`print2darray` C Function

```
EXPORTED_FUNCTION void print2darray(double my2d[][3],int len)
{
    int indxi,indxj;
    for(indxi=0;indxi<len;++indxi)
    {
        for(indxj=0;indxj<3;++indxj)
        {
```

```
        mexPrintf("%10g",my2d[indxi][indxj]);
    }
    mexPrintf("\n");
}
}
```

The first argument is a two dimensional array. The `len` argument is the number of rows. The function displays each element of the matrix. Using matrix `m`:

```
calllib('shrllibsample','print2darray',m,4)
```

```
    1         2         3
    4         5         6
    7         8         9
   10        11        12
```

You must transpose `m` to get the desired result:

```
calllib('shrllibsample','print2darray',m',4)
```

```
    1         5         9
    2         6        10
    3         7        11
    4         8        12
```

More than Two Dimensional MATLAB Arrays

When passing an array having more than two dimensions, the shape of the array might be altered by MATLAB. To ensure that the array retains its shape, store the size of the array before making the call, and then use this same size to reshape the output array to the correct dimensions. For example:

```
vs = size(vin)           % Store the original dimensions
vs =
    2     5     2

vout = calllib('shrllibsample','multDoubleArray',vin,20)

size(vout)              % Dimensions have been altered
ans =
    2    10

vout = reshape(vout,vs); % Restore the array to 2-by-5-by-2
```

```
size(vout)
ans =
     2     5     2
```

Iterate Through an Array

In this section...

“Create Cell Array from lib.pointer Object” on page 3-32

“Perform Pointer Arithmetic on Structure Array” on page 3-33

Create Cell Array from lib.pointer Object

This example shows how to create a MATLAB cell array of strings, `mlStringArray`, from the output of the `getListOfStrings` function.

The `getListOfStrings` function creates an array of strings and returns a pointer to the array.

```
if not(libisloaded('shrlibsample'))
    addpath(fullfile(matlabroot, 'extern', 'examples', 'shrlib'))
    loadlibrary('shrlibsample')
end
```

Call the function.

```
ptr = calllib('shrlibsample', 'getListOfStrings')
class(ptr)
```

```
ans =
```

```
lib.pointer
```

Create indexing variables to iterate through the arrays. Use `ptrindex` for the strings returned by the function and `index` for the MATLAB array:

```
ptrindex = ptr;
index = 1;
```

Create the cell array of strings, `mlStringArray`:

```
while ischar(ptrindex.value{1}) %stop at end of list (NULL)
    mlStringArray{index} = ptrindex.value{1};
    ptrindex = ptrindex + 1; %increment pointer
    index = index + 1; %increment array index
end
```

To view the contents of the cell array, type:

```
m1StringArray
m1StringArray =
    'String 1'    'String Two'    ''    'Last string'
```

Perform Pointer Arithmetic on Structure Array

This example shows how to use pointer arithmetic to access elements of a structure.

The example creates a MATLAB structure, based on the `c_struct` definition in the `shrlibsample.h` header file.

Load the definition.

```
if not(libisloaded('shrlibsample'))
    addpath(fullfile(matlabroot,'extern','examples','shrlib'))
    loadlibrary('shrlibsample')
end
```

Create the MATLAB structure.

```
s = struct('p1',{1,2,3},'p2',{1.1,2.2,3.3},'p3',{0});
```

Create a pointer to the structure.

```
sptr = libpointer('c_struct',s);
```

Read the values of the first element.

```
v1 = sptr.Value;
```

To read the values of the next element, increment the pointer.

```
sptr = sptr + 1;
v2 = sptr.Value;
```

Working with Pointer Arguments

In this section...

“Pointer Arguments in C Functions” on page 3-34

“Creating a Pointer to a Primitive Type” on page 3-34

“Creating a Pointer to a Structure” on page 3-37

“Passing a Pointer to the First Element of an Array” on page 3-39

“Putting a String into a Void Pointer” on page 3-40

“Passing an Array of Strings” on page 3-40

“Memory Allocation for an External Library” on page 3-42

“Multilevel Pointers” on page 3-43

Pointer Arguments in C Functions

Many functions in external libraries pass arguments by reference. When you pass by reference, you pass a *pointer* to the value. In the function signature, these are the arguments with names ending in `Ptr` and `PtrPtr`. Although MATLAB does not support passing by reference, you can create a MATLAB argument, called a *lib.pointer object*, that is compatible with a C pointer. This object is an instance of the MATLAB `lib.pointer` class.

In many cases, you can simply pass a MATLAB variable (passing an argument by value), even when the signature for that function declares the argument to be a pointer. There are times, however, when it is useful to pass a `lib.pointer`.

- You want to modify the data in the input arguments.
- You are passing large amounts of data, and you want to control when MATLAB makes copies of the data.
- The library stores and uses the pointer for a period of time so you want the MATLAB function to control the lifetime of the `lib.pointer` object.

Creating a Pointer to a Primitive Type

The following example illustrates how to construct and pass a pointer, and how to interpret the output. It uses the `multDoubleRef` function in the `shrlibsample` library,

which multiplies the input by 5. The input is a pointer to a `double`, and it returns a pointer to a `double`.

multiDoubleRef C Function

```
EXPORTED_FUNCTION double *multiDoubleRef(double *x)
{
    *x *= 5;
    return x;
}
```

Construct a `lib.pointer` object, `xp`, to point to the input data, `x`.

```
x = 15;
xp = libpointer('doublePtr',x);
```

Verify the contents of `xp`:

```
get(xp)

    Value: 15
  DataType: 'doublePtr'
```

Now call the function and check the results:

```
calllib('shrllibsample', 'multiDoubleRef', xp)
xp.Value

ans =
    75
```

The object `xp` is a *handle object*. All copies of this handle refer to the same underlying object and any operations you perform on a handle object affect all copies of that object. However, object `xp` is not a C language pointer. Although it points to `x`, it does not contain the address of `x`. The function modifies the `Value` property of `xp` but does not modify the value in the underlying object `x`. The original value of `x` is unchanged. Type:

```
x

x =
    15
```

Reading Function Return Values

In the previous example, the result of the function called from MATLAB could be obtained by examining the modified input pointer. But this function also returns data in its output arguments that may be useful.

To see the MATLAB signature for `multDoubleRef`, type:

```
libfunctions shrlibsample -full
```

multDoubleRef Function Signature

Return Type	Name	Arguments
[lib.pointer, doublePtr]	multDoubleRef	(doublePtr)

The function returns two outputs—a `lib.pointer` object and the `Value` property of the input argument:

Run the example again:

```
x = 15;  
xp = libpointer('doublePtr',x);
```

Check the output values:

```
[xout,xval] = calllib('shrlibsample','multDoubleRef',xp)  
  
xout =  
    lib.pointer  
xval =  
     75
```

Like the input argument `xp`, `xout` is also a `lib.pointer` object. You can examine this output, but first you need to initialize its type and size because the function does not define these properties. Use the `setdatatype` method in the `lib.pointer` class to set the data type to `doublePtr` and the size to 1-by-1. Once initialized, you can examine outputs by typing:

```
setdatatype(xout,'doublePtr',1,1)  
get(xout)  
  
ans =  
    Value: 75  
    DataType: 'doublePtr'
```

The second output of `multDoubleRef`, `xval`, is a copy of the `Value` property of input `xp`.

Creating a Pointer by Offsetting from an Existing `lib.pointer` Object

You can use the `plus` operator (+) to create a new pointer that is offset from an existing pointer by a scalar numeric value. For example, suppose you create a `lib.pointer` to the vector `x`:

```
x = 1:10;
xp = libpointer('doublePtr',x);
xp.Value

ans =
     1     2     3     4     5     6     7     8     9    10
```

Use the `plus` operator to create a new `lib.pointer` that is offset from `xp`:

```
xp2 = xp+4;
xp2.Value

ans =
     5     6     7     8     9    10
```

Note: The new pointer (`xp2` in this example) is valid only as long as the original pointer, `xp`, exists.

Creating a Pointer to a Structure

If a function has an input argument that is a pointer to a structure, you can either pass the structure itself, or pass a pointer to the structure. Creating a pointer to a structure is similar to creating a pointer to a primitive type.

The `addStructByRef` function in the `shrlibsample` library takes a pointer to a structure of type `c_struct`. The output argument is the sum of all fields in the structure. The function also modifies the fields of the input structure.

`addStructByRef` C Function

```
EXPORTED_FUNCTION double addStructByRef(struct c_struct *st) {
    double t = st->p1 + st->p2 + st->p3;
    st->p1 = 5.5;
    st->p2 = 1234;
    st->p3 = 12345678;
```

```
    return t;  
}
```

Passing the Structure Itself

Although the input to the `addStructByRef` function is a pointer to a structure, you can pass the structure itself and let MATLAB make the conversion to a pointer.

In the following example, create the structure `sm` and call `addStructByRef`:

```
sm.p1 = 476;  
sm.p2 = -299;  
sm.p3 = 1000;  
x = calllib('shrllibsample', 'addStructByRef', sm)  
  
x =  
    1177
```

However, MATLAB does not modify the contents of `sm`, since it is not a pointer. Type:

```
sm  
  
sm =  
    p1: 476  
    p2: -299  
    p3: 1000
```

Passing a Structure Pointer

The following example passes a pointer to the structure. First, create the `lib.pointer` object:

```
sp = libpointer('c_struct', sm);  
sp.Value  
  
ans =  
    p1: 476  
    p2: -299  
    p3: 1000
```

The `lib.pointer`, `sp`, has the same values as the structure `sm`.

Pass the `lib.pointer` to the function:

```
if not(libisloaded('shrllibsample'))
```

```

    addpath(fullfile(matlabroot,'extern','examples','shrlib'))
    loadlibrary('shrlibsample')
end
calllib('shrlibsample','addStructByRef',sp)

ans =
    1177

```

In this case, the function modifies the structure fields. Type:

```
sp.Value
```

```

ans =
    p1: 5.5000
    p2: 1234
    p3: 12345678

```

MATLAB displays the updated values.

Passing a Pointer to the First Element of an Array

In cases where a function defines an input argument that is a pointer to the first element of a data array, MATLAB automatically passes an argument that is a pointer of the correct type to the first element of data in the MATLAB vector or matrix.

The following **pseudo-code** shows how to do this. Suppose you have a function `mySum` in a library `myLib`. The signature of the C function is:

Return Type	Name	Arguments
int	mySum	(int size, short* data)

The C variable `data` is an array of type `short`. The equivalent MATLAB type is `int16`. You can pass any of the following MATLAB variables to this function:

```

Data = 1:100;
shortData = int16(Data); % equivalent to C short type
lp = libpointer('int16Ptr',Data); % libpointer object

```

The following **pseudo-code** statements are equivalent:

```
summed_data = calllib('myLib','mySum',100,Data)
```

```
summed_data = calllib('myLib', 'mySum', 100, shortData)
summed_data = calllib('myLib', 'mySum', 100, lp)
```

The length of the data vector must be equal to the specified size. For example:

```
% sum last 50 elements
summed_data = calllib('myLib', 'mySum', 50, Data(51:100))
```

Putting a String into a Void Pointer

C represents characters as eight-bit integers. To use a MATLAB string as an input argument, you must convert the string to the proper type and create a `voidPtr`. To do this, use the `libpointer` function as follows:

```
str = 'string variable';
vp = libpointer('voidPtr', [int8(str) 0]);
```

The syntax `[int8(str) 0]` creates the null-terminated string required by the C function. To read the string, and verify the pointer type, enter:

```
char(vp.Value)
vp.DataType

ans =
string variable
ans =
voidPtr
```

You can call a function that takes a `voidPtr` to a string as an input argument using the following syntax because MATLAB automatically converts an argument passed by value into an argument passed by reference when the external function prototype defines the argument as a pointer:

```
func_name([int8(str) 0])
```

Note that while MATLAB converts the argument from a value to a pointer, it must be of the correct type.

Passing an Array of Strings

The `getListOfStrings` function from the `shrlibsample` library returns a `char **`, which you can think of as a pointer to an array of strings.

getListOfStrings Function Signature

Return Type	Name
lib.pointer	getListOfStrings

getListOfStrings C Function

```
EXPORTED_FUNCTION const char ** getListOfStrings(void)
{
    static const char *strings[5];
    strings[0]="String 1";
    strings[1]="String Two";
    strings[2]=""; /* empty string */
    strings[3]="Last string";
    strings[4]=NULL;
    return strings;
}
```

To read this array, type:

```
if not(libisloaded('shrlibsample'))
    addpath(fullfile(matlabroot,'extern','examples','shrlib'))
    loadlibrary('shrlibsample')
end
ptr = calllib('shrlibsample','getListOfStrings')
```

MATLAB creates a `lib.pointer` object `ptr` of type `stringPtrPtr`. This object points to the first string. To display the string, use the `Value` property:

```
ptr.Value
```

To view the other strings, you need to increment the pointer. For example, type:

```
for index = 0:3
    tempPtr = ptr + index;
    tempPtr.Value
end

ans =
    'String 1'
ans =
    'String Two'
ans =
```

```
    {''}  
ans =  
    'Last string'
```

For another example, see “Iterate Through an Array” on page 3-32.

Memory Allocation for an External Library

In general, MATLAB passes a valid memory address each time you pass a variable to a library function. You should use a `lib.pointer` object in cases where the library stores the pointer and accesses the buffer over a period of time. In these cases, you need to ensure that MATLAB has control over the lifetime of the buffer and to prevent copies of the data from being made. The following **pseudo-code** is an example of asynchronous data acquisition that shows how to use a `lib.pointer` in this situation.

Suppose an external library `myLib` has the following functions:

```
AcquireData(int points,short *buffer)  
IsAquisitionDone(void)
```

where `buffer` is declared as follows:

```
short buffer[99]
```

First, create a `lib.pointer` to an array of 99 points:

```
BufferSize = 99;  
pBuffer = libpointer('int16Ptr',zeros(BufferSize,1));
```

Then, begin acquiring data and wait in a loop until it is done:

```
calllib('myLib','AcquireData',BufferSize,pbuffer)  
while (~calllib('myLib','IsAcquisitionDone'))  
    pause(0.1)  
end
```

The following statement reads the data in the buffer:

```
result = pBuffer.Value;
```

When the library is done with the buffer, clear the MATLAB variable:

```
clear pBuffer
```

Multilevel Pointers

Multilevel pointers are arguments that have more than one level of referencing. A multilevel pointer type in MATLAB uses the suffix `PtrPtr`. For example, use `doublePtrPtr` for the C argument `double **`.

When calling a function that takes a multilevel pointer argument, use a `lib.pointer` object and let MATLAB convert it to the multilevel pointer. For example, the `allocateStruct` function in the `shrllibsample` library takes a `c_structPtrPtr` argument.

allocateStruct Function Signature

Return Type	Name	Arguments
<code>c_structPtrPtr</code>	<code>allocateStruct</code>	<code>(c_structPtrPtr)</code>

allocateStruct C Function

```
EXPORTED_FUNCTION void allocateStruct(struct c_struct **val)
{
    *val=(struct c_struct*) malloc(sizeof(struct c_struct));
    (*val)->p1 = 12.4;
    (*val)->p2 = 222;
    (*val)->p3 = 333333;
}
```

Create a `lib.pointer` object of type `c_structPtr` and pass it to the function:

```
if not(libisloaded('shrllibsample'))
    addpath(fullfile(matlabroot,'extern','examples','shrllib'))
    loadlibrary('shrllibsample')
end
sp = libpointer('c_structPtr');
calllib('shrllibsample','allocateStruct',sp)
get(sp)

ans =
    Value: [1x1 struct]
    DataType: 'c_structPtr'
```

Type:

`sp.Value`

```
ans =  
  p1: 12.4000  
  p2: 222  
  p3: 333333
```

When you use `allocateStruct`, you must free memory using the command:

```
calllib('shrllibsample', 'deallocateStruct', sp)
```

Returning an Array of Strings

Suppose you have a library, `myLib`, with a function, `acquireString`, that reads an array of strings. The function signature is:

Return Type	Name	Arguments
char**	acquireString	(void)

```
char** acquireString(void)
```

The following **pseudo-code** shows how to manipulate the return value, an array of pointers to strings.

```
ptr = calllib(myLib, 'acquireString')
```

MATLAB creates a `lib.pointer` object `ptr` of type `stringPtrPtr`. This object points to the first string. To view other strings, you need to increment the pointer. For example, to display the first 3 strings, type:

```
for index = 0:2  
    tempPtr = ptr + index;  
    tempPtr.Value  
end  
  
ans =  
    'str1'  
ans =  
    'str2'  
ans =  
    'str3'
```


Working with Structure Arguments

In this section...

“Structure Argument Requirements” on page 3-45

“Finding Structure Field Names” on page 3-45

“Strategies for Passing Structures” on page 3-45

Structure Argument Requirements

When you pass a MATLAB structure to an external library function:

- Every MATLAB field name must match a field name in the library structure definition. Field names are case sensitive.
- MATLAB structures cannot contain fields that are not in the library structure definition.
- If a MATLAB structure contains fewer fields than defined in the library structure, MATLAB sets undefined fields to zero.

You do not need to match the data types of numeric fields. The `calllib` function converts to the correct numeric type.

Finding Structure Field Names

To determine the name and data type of structure fields, you can:

- Consult the library documentation.
- Look at the structure definition in the library header file.
- Use the `libstruct` function. For an example, see “Display Structure Field Names” on page 3-25.

Strategies for Passing Structures

MATLAB automatically converts a structure to the library definition for that structure type. For most cases, such as working with small structures, this works fine. For an example, see “Add Values of Fields in Structure” on page 3-23.

However, when working with repeated calls that pass one or more large structures, it might be to your advantage to convert the structure manually before making any calls to external functions. In this way, you save processing time by converting the structure data only once at the start rather than at each function call. You can also save memory if the fields of the converted structure take up less space than the original MATLAB structure.

To manually convert, call the `libstruct` function to create a *libstruct object*. Although it is an object, it behaves like a MATLAB structure. The fields of the object are derived from an externally-specified structure type. For an example, see “Preconvert MATLAB Structure Before Adding Values” on page 3-24.

Work with libstruct Objects

This example shows how to display information about a `libstruct` object.

Create libstruct Object

Create `libstruct` object `sc`.

```
sm.p1 = 476;
sm.p2 = -299;
sm.p3 = 1000;
sc = libstruct('c_struct',sm);
```

Class of libstruct Object

A `libstruct` object is an instance of a MATLAB class called `lib.c_struct`.

`whos`

Name	Size	Bytes	Class
<code>sc</code>	1x1		<code>lib.c_struct</code>
<code>sm</code>	1x1	396	struct array

Size of libstruct Object

Use the `lib.c_struct` class method `structsize` to obtain the size of a `libstruct` object.

```
sc.structsize
```

```
ans =
    16
```

Accessing Fields of libstruct Object

The fields are properties of the `lib.c_struct` class. You can read and modify a field using the MATLAB `set` and `get` functions:

```
sc = libstruct('c_struct');
set(sc,'p1',100,'p2',150,'p3',200);
get(sc)

p1: 100
p2: 150
```

p3: 200

You can also read and modify the fields by treating them like MATLAB structure fields:

```
sc.p1 = 23;  
sc.p1
```

```
ans =  
    23
```

MATLAB Prototype Files

In this section...

“When to Use a Prototype File” on page 3-49

“How to Create a Prototype File” on page 3-49

“How to Specify a Thunk file” on page 3-50

“Deploy Applications That Use `loadlibrary`” on page 3-50

“Use `loadlibrary` in a Parallel Computing Environment” on page 3-50

“Change Function Signature” on page 3-50

“Rename Library Function” on page 3-50

“Load Subset of Functions in Library” on page 3-50

“Call Function with Variable Number of Arguments” on page 3-51

When to Use a Prototype File

MATLAB provides a way to modify header file information by creating a *prototype file*, a file of MATLAB commands.

Like a header file, the prototype file contains the function signatures for the library. Here are some reasons for using a prototype file.

- To deploy applications that use `loadlibrary` (using MATLAB Compiler™).
- To use `loadlibrary` in a parallel computing environment (using Parallel Computing Toolbox™).
- To make changes to signatures of the library functions.
- To rename some of the library functions.
- To use only a small percentage of the functions in the library you are loading.
- To use functions with a variable number of arguments.

You can make changes to the prototypes by editing the prototype file and reloading the library.

How to Create a Prototype File

To create a prototype file, use the `mfilename` option of the `loadlibrary` function.

How to Specify a Thunk file

For information about default thunk file names, see `loadlibrary`. To change the name, use the `thunkfilename` option.

Deploy Applications That Use `loadlibrary`

To deploy a MATLAB application that uses `loadlibrary`, using MATLAB Compiler:

- Create a prototype file.
- For 64-bit applications, specify a thunk file.
- Include all the relevant files when creating the project with `mcc`.

Use `loadlibrary` in a Parallel Computing Environment

To use `loadlibrary` in a parallel computing environment (using Parallel Computing Toolbox):

- Create a prototype file.
- For 64-bit applications, specify a thunk file.
- Make sure all relevant files are accessible to all workers.

Change Function Signature

Edit the prototype file, changing the `fcns.LHS` or `fcns.RHS` field for that function. This changes the types of arguments on the left hand side or right hand side, respectively.

Rename Library Function

Edit the prototype file, defining the `fcns.alias` field for that function.

Load Subset of Functions in Library

Edit the prototype file, commenting out the unused functions. This reduces the amount of memory required for the library.

Call Function with Variable Number of Arguments

Create an alias function in a prototype file for each set of arguments you use to call the function.

Intro to MEX-Files

- “Introducing MEX-Files” on page 4-3
- “Using MEX-Files” on page 4-4
- “MEX-File Placement” on page 4-5
- “Use Help Files with MEX-Files” on page 4-6
- “MATLAB Data” on page 4-7
- “Testing for Most-Derived Class” on page 4-15
- “Build MEX-File” on page 4-17
- “Linking Multiple Files” on page 4-18
- “What You Need to Build MEX-Files” on page 4-19
- “Changing Default Compiler” on page 4-20
- “Using MEX Script Options to Custom Build” on page 4-23
- “Compiling MEX-Files with the Microsoft Visual C++ IDE” on page 4-24
- “Call LAPACK and BLAS Functions” on page 4-26
- “Running MEX-Files with .DLL File Extensions on Windows 32-bit Platforms” on page 4-35
- “Upgrade MEX-Files to Use 64-Bit API” on page 4-36
- “Upgrade MEX-Files to Use Graphics Objects” on page 4-47
- “Platform Compatibility” on page 4-52
- “Invalid MEX-File Error” on page 4-53
- “Run MEX-File You Receive from Someone Else” on page 4-54
- “MEX-File Dependent Libraries” on page 4-55
- “Document Build Information in the MEX-File” on page 4-56
- “Version Compatibility” on page 4-58
- “Getting Help When MEX Fails” on page 4-59
- “Understanding MEX-File Problems” on page 4-61

- “Compiler- and Platform-Specific Issues” on page 4-66
- “Memory Management Issues” on page 4-67
- “Compiler Errors in Fortran MEX-Files” on page 4-72

Introducing MEX-Files

You can call your own C, C++, or Fortran subroutines from the MATLAB command line as if they were built-in functions. These programs, called binary *MEX-files*, are dynamically linked subroutines that the MATLAB interpreter loads and executes. The MEX-file contains only one function or subroutine, and its name is the MEX-file name. To call a MEX-file, use the name of the file, without the file extension.

For information about using a MEX-file that someone else created, see “Call MEX-File Functions”.

The term `mex` stands for “MATLAB executable” and has different meanings, as shown in the following table.

MEX Term	Definition
source MEX-file	C, C++, or Fortran source code file.
binary MEX-file	Dynamically linked subroutine executed in the MATLAB environment.
MEX function library	MATLAB C/C++ and Fortran API Reference library to perform operations in the MATLAB environment.
<code>mex</code> build script	MATLAB function to create a binary file from a source file.

Related Examples

- “Create C Source MEX-File” on page 5-18

More About

- “Creating C++ MEX-Files” on page 5-13
- “What You Need to Build MEX-Files” on page 4-19

Using MEX-Files

Binary MEX-files are subroutines produced from C/C++ or Fortran source code. They behave just like MATLAB scripts and built-in functions. While scripts have a platform-independent extension `.m`, MATLAB identifies MEX-files by platform-specific extensions. The following table lists the platform-specific extensions for MEX-files.

MEX-File Platform-Dependent Extension

Platform	Binary MEX-File Extension
Linux (64-bit)	<code>mexa64</code>
Apple Mac (64-bit)	<code>mexmaci64</code>
Microsoft Windows (32-bit)	<code>mexw32</code>
Windows (64-bit)	<code>mexw64</code>

You cannot use a binary MEX-file on a platform if you compiled it on a different platform. Recompile the source code on the platform for which you want to use the MEX-file. For information about using MEX S-functions, see your Simulink[®] documentation.

MEX-File Placement

Put your MEX-files in a folder on the MATLAB path. Alternatively, run MATLAB from the folder containing the MEX-file. MATLAB runs functions in the current working folder before functions on the path.

To see the current folders on your path, use the `path` function. You can add new folders to the path either by using the `addpath` function, or by selecting **File > SetPath** to edit the path.

If you use a Windows operating system and your binary MEX-files are on a network drive, be aware that file servers do not always report folder and file changes correctly. If you change a MEX-file on a network drive and find that MATLAB does not use the latest changes, you can force MATLAB to look for the correct version of the file by changing folders away from and then back to the folder containing the file.

See Also

`addpath` | `path`

Use Help Files with MEX-Files

You can document the behavior of your MEX-files by writing a MATLAB script containing comment lines. The `help` command automatically finds and displays the appropriate text when help is requested and the interpreter finds and executes the corresponding MEX-file when the function is invoked.

For example, copy the following text from the `arrayProduct.c` MEX source file into a file, `arrayproduct.m`.

```
% arrayproduct.m Help file for arrayProduct MEX-file.  
% arrayProduct.c - example in MATLAB External Interfaces  
%  
% Multiplies an input scalar (multiplier)  
% times a 1xN matrix (inMatrix)  
% and outputs a 1xN matrix (outMatrix)  
%  
% The calling syntax is:  
%  
%   outMatrix = arrayProduct(multiplier, inMatrix)  
%  
  
% This is a MEX-file for MATLAB.  
% Copyright 2007-2014 The MathWorks, Inc.  
%
```

When you type:

```
help arrayproduct
```

MATLAB displays the comments.

See Also

`help`

Related Examples

- “Document Build Information in the MEX-File” on page 4-56
- “Add Help for Your Program”

MATLAB Data

In this section...

“The MATLAB Array” on page 4-7

“Lifecycle of mxArray” on page 4-7

“Data Storage” on page 4-8

“MATLAB Types” on page 4-10

“Sparse Matrices” on page 4-11

“Using Data Types” on page 4-12

The MATLAB Array

The MATLAB language works with a single object type: the MATLAB array. All MATLAB variables (including scalars, vectors, matrices, strings, cell arrays, structures, and objects) are stored as MATLAB arrays. In C/C++, the MATLAB array is declared to be of type `mxArray`. The `mxArray` structure contains the following information about the array:

- Its type
- Its dimensions
- The data associated with this array
- If numeric, whether the variable is real or complex
- If sparse, its indices and nonzero maximum elements
- If a structure or object, the number of fields and field names

To access the `mxArray` structure, use the API functions in the Matrix Library. These functions allow you to create, read, and query information about the MATLAB data in your MEX-files. Matrix Library functions use the `mwSize` type to avoid portability issues and allow MEX source files to be compiled correctly on all systems.

Lifecycle of mxArray

Like MATLAB functions, a MEX-file gateway routine passes MATLAB variables by reference. However, these arguments are C pointers. A *pointer* to a variable is the *address* (location in memory) of the variable. MATLAB functions handle data storage for you automatically. When passing data to a MEX-file, you use pointers, which follow

specific rules for accessing and manipulating variables. For information about working with pointers, refer to a programming reference, such as *The C Programming Language* by Kernighan, B. W., and D. M. Ritchie.

Note: Since variables use memory, you need to understand how your MEX-file creates an `mxArray` and your responsibility for releasing (freeing) the memory. This is important to prevent memory leaks. The lifecycle of an `mxArray`—and the rules for managing memory—depends on whether it is an input argument, output argument, or local variable. The function you call to deallocate an `mxArray` depends on the function you used to create it, which is listed in the create function’s MX Matrix Library documentation.

Input Argument `prhs`

An `mxArray` passed to a MEX-file through the `prhs` input parameter exists outside the scope of the MEX-file. Do not free memory for any `mxArray` in the `prhs` parameter. Additionally, `prhs` variables are read-only; do not modify them in your MEX-file.

Output Argument `plhs`

If you create an `mxArray` (allocate memory and create data) for an output argument, the memory and data exist beyond the scope of the MEX-file. Do not free memory on an `mxArray` returned in the `plhs` output parameter.

Local Variable

You allocate memory whenever you use an `mxCreate*` function to create an `mxArray` or when you call the `mxMalloc` and associated functions. After observing the rules for handling input and output arguments, the MEX-file should destroy temporary arrays and free dynamically allocated memory. To deallocate memory, use either `mxDestroyArray` or `mxFree`. Refer to the MX Matrix Library function documentation for information about which function to use.

Data Storage

MATLAB stores data in a column-major (columnwise) numbering scheme, which is how Fortran stores matrices. MATLAB uses this convention because it was originally written in Fortran. MATLAB internally stores data elements from the first column first, then data elements from the second column second, and so on, through the last column.

For example, given the matrix:


```
a = ['house'; 'floor'; 'porch']
```

```
a =
    house
    floor
    porch
```

its dimensions are:


```
size(a)
```

```
ans =
     3     5
```

and its data is stored as:

h	f	p	o	l	o	u	o	r	s	o	c	e	r	h
---	---	---	---	---	---	---	---	---	---	---	---	---	---	---

If a matrix is N-dimensional, MATLAB represents the data in N-major order. For example, consider a three-dimensional array having dimensions 4-by-2-by-3. Although you can visualize the data as:



MATLAB internally represents the data for this three-dimensional array in the following order:

A	B	C	D	E	F	G	H	I	J	K	L	M	N	O	P	Q	R	S	T	U	V	W	X
---	---	---	---	---	---	---	---	---	---	---	---	---	---	---	---	---	---	---	---	---	---	---	---

0	1	2	3	4	5	6	7	8	9	10	11	12	13	14	15	16	17	18	19	20	21	22	23
---	---	---	---	---	---	---	---	---	---	----	----	----	----	----	----	----	----	----	----	----	----	----	----

The `mxCalcSingleSubscript` function creates the offset from the first element of an array to the desired element, using N-dimensional subscripting.

MATLAB Types

Complex Double-Precision Matrices

The most common data type in MATLAB is the complex double-precision, nonsparse matrix. These matrices are of type `double` and have dimensions `m`-by-`n`, where `m` is the number of rows and `n` is the number of columns. The data is stored as two vectors of double-precision numbers—one contains the real data and one contains the imaginary data. The pointers to this data are referred to as `pr` (pointer to real data) and `pi` (pointer to imaginary data), respectively. A noncomplex matrix is one whose `pi` is `NULL`.

Numeric Matrices

MATLAB also supports other types of numeric matrices. These are single-precision floating-point and 8-, 16-, and 32-bit integers, both signed and unsigned. The data is stored in two vectors in the same manner as double-precision matrices.

Logical Matrices

The logical data type represents a logical `true` or `false` state using the numbers `1` and `0`, respectively. Certain MATLAB functions and operators return logical `1` or logical `0` to indicate whether a certain condition was found to be true or not. For example, the statement `(5 * 10) > 40` returns a logical `1` value.

MATLAB Strings

MATLAB strings are of type `char` and are stored the same way as unsigned 16-bit integers except there is no imaginary data component. Unlike C, MATLAB strings are not null terminated.

Cell Arrays

Cell arrays are a collection of MATLAB arrays where each `mxArray` is referred to as a cell. This allows MATLAB arrays of different types to be stored together. Cell arrays are stored in a similar manner to numeric matrices, except the data portion contains a single vector of pointers to `mxArrays`. Members of this vector are called cells. Each cell can be of any supported data type, even another cell array.

Structures

A 1-by-1 structure is stored in the same manner as a 1-by- n cell array where n is the number of fields in the structure. Members of the data vector are called fields. Each field is associated with a name stored in the `mxArray`.

Objects

Objects are stored and accessed the same way as structures. In MATLAB, objects are named structures with registered methods. Outside MATLAB, an object is a structure that contains storage for an additional class name that identifies the name of the object.

Multidimensional Arrays

MATLAB arrays of any type can be multidimensional. A vector of integers is stored where each element is the size of the corresponding dimension. The storage of the data is the same as matrices.

Empty Arrays

MATLAB arrays of any type can be empty. An empty `mxArray` is one with at least one dimension equal to zero. For example, a double-precision `mxArray` of type `double`, where m and n equal 0 and `pr` is `NULL`, is an empty array.

Sparse Matrices

Sparse matrices have a different storage convention from that of full matrices in MATLAB. The parameters `pr` and `pi` are still arrays of double-precision numbers, but these arrays contain only nonzero data elements. There are three additional parameters: `nzmax`, `ir`, and `jc`.

- `nzmax` is an integer that contains the length of `ir`, `pr`, and, if it exists, `pi`. It is the maximum number of nonzero elements in the sparse matrix.
- `ir` points to an integer array of length `nzmax` containing the row indices of the corresponding elements in `pr` and `pi`.
- `jc` points to an integer array of length $n+1$, where n is the number of columns in the sparse matrix. The `jc` array contains column index information. If the j th column of the sparse matrix has any nonzero elements, `jc[j]` is the index in `ir` and `pr` (and `pi` if it exists) of the first nonzero element in the j th column, and `jc[j+1] - 1` is the index of the last nonzero element in that column. For the j th column of the sparse

matrix, `jc[j]` is the total number of nonzero elements in all preceding columns. The last element of the `jc` array, `jc[n]`, is equal to `nnz`, the number of nonzero elements in the entire sparse matrix. If `nnz` is less than `nzmax`, more nonzero entries can be inserted into the array without allocating more storage.

Using Data Types

You can write source MEX-files, MAT-file applications, and engine applications in C/C++ that accept any class or data type supported by MATLAB (see “Data Types”). In Fortran, only the creation of double-precision *n*-by-*m* arrays and strings are supported. You use binary C/C++ and Fortran MEX-files like MATLAB functions.

Caution MATLAB does not check the validity of MATLAB data structures created in C/C++ or Fortran using one of the Matrix Library create functions (for example, `mxCreateStructArray`). Using invalid syntax to create a MATLAB data structure can result in unexpected behavior in your C/C++ or Fortran program.

Declaring Data Structures

To handle MATLAB arrays, use type `mxArray`. The following statement declares an `mxArray` named `myData`:

```
mxArray *myData;
```

To define the values of `myData`, use one of the `mxCreate*` functions. Some useful array creation routines are `mxCreateNumericArray`, `mxCreateCellArray`, and `mxCreateCharArray`. For example, the following statement allocates an *m*-by-1 floating-point `mxArray` initialized to 0:

```
myData = mxCreateDoubleMatrix(m, 1, mxREAL);
```

C/C++ programmers should note that data in a MATLAB array is in column-major order. (For an illustration, see “Data Storage” on page 4-8.) Use the MATLAB `mxGet*` array access routines to read data from an `mxArray`.

Manipulating Data

The `mxGet*` array access routines get references to the data in an `mxArray`. Use these routines to modify data in your MEX-file. Each function provides access to specific information in the `mxArray`. Some useful functions are `mxGetData`, `mxGetPr`, `mxGetM`,

and `mxGetString`. Many of these functions have corresponding `mxSet*` routines to allow you to modify values in the array.

The following statements read the input string `prhs[0]` into a C-style string `buf`:

```
char *buf;
int buflen;
int status;
buflen = mxGetN(prhs[0])*sizeof(mxChar)+1;
buf = mxMalloc(buflen);
status = mxGetString(prhs[0], buf, buflen);
```

The explore Example

There is an example source MEX-file included with MATLAB, called `explore.c`, that identifies the data type of an input variable. The source code for this example is in `matlabroot/extern/examples/mex`, where `matlabroot` represents the top-level folder where MATLAB is installed on your system.

Note: In platform-independent discussions that refer to folder paths, this documentation uses the UNIX convention. For example, a general reference to the `mex` folder is `matlabroot/extern/examples/mex`.

To build the example MEX-file, first copy the file to a writable folder on your path.

```
copyfile(fullfile(matlabroot, 'extern', 'examples', 'mex', 'explore.c'), '.', 'f')
```

Use the `mex` function to build the MEX-file.

```
mex -largeArrayDims explore.c
```

Type:

```
x = 2;
explore(x)
```

```
-----
Name: prhs[0]
Dimensions: 1x1
Class Name: double
-----
```

```
(1,1) = 2
```

`explore` accepts any data type. Try using `explore` with these examples:

```
explore([1 2 3 4 5])
explore 1 2 3 4 5
explore({1 2 3 4 5})
explore(int8([1 2 3 4 5]))
explore {1 2 3 4 5}
explore(sparse(eye(5)))
explore(struct('name', 'Joe Jones', 'ext', 7332))
explore(1, 2, 3, 4, 5)
```

Testing for Most-Derived Class

If you define functions that require inputs that are:

- MATLAB built-in types
- Not subclasses of MATLAB built-in types

use the following technique to exclude subclasses of built-in types from the input arguments.

- Define a cell array that contains the names of built-in types accepted by your function.
- Call `class` and `strcmp` to test for specific types in a MATLAB control statement.

The following code tests an input argument, `inputArg`:

```
if strcmp(class(inputArg),'single')
    % Call function
else
    inputArg = single(inputArg);
end
```

Testing for a Category of Types

Suppose that you create a MEX-function, `myMexFcn`, that requires two numeric inputs that must be of type `double` or `single`:

```
outArray = myMexFcn(a,b)
```

Define a cell array `floatTypes` that contains the strings `double` and `single`:

```
floatTypes = {'double','single'};

% Test for proper types
if any(strcmp(class(a),floatTypes)) && ...
    any(strcmp(class(b),floatTypes))
    outArray = myMexFcn(a,b);
else
    % Try to convert inputs to avoid error
    ...
end
```

Another Test for Built-In Types

You can use `isobject` to separate built-in types from subclasses of built-in types. The `isobject` function returns `false` for instances of built-in types. For example:

```
% Create a int16 array  
a = int16([2,5,7,11]);  
isobject(a)
```

```
ans =  
    0
```

Determine if an array is one of the built-in integer types:

```
if isa(a, 'integer') && ~isobject(a)  
    % a is a built-in integer type  
    ...  
end
```


Build MEX-File

This example shows how to build the example MEX-file, `timestwo`. Use this example to verify the build configuration for your system.

To build a code example, first copy the file to a writable folder on your path.

```
copyfile(fullfile(matlabroot, 'extern', 'examples', 'refbook', 'timestwo.c'), '.', 'f')
```

Use the `mex` function to build the MEX-file.

```
mex timestwo.c
```

```
Building with 'Microsoft Visual C++ 2010 (C)'.  
MEX completed successfully.
```

This command creates the file `timestwo.ext`, where `ext` is the value returned by the `mexext` function.

The `timestwo` function takes a scalar input and doubles it. Call `timestwo` as if it were a MATLAB function.

```
timestwo(4)
```

```
ans =  
     8
```

See Also

`mex` | `mexext`

More About

- “What You Need to Build MEX-Files” on page 4-19
- “Upgrade MEX-Files to Use 64-Bit API” on page 4-36

Linking Multiple Files

You can combine multiple source files, object files, and file libraries to build a binary MEX-file. To do this, list the additional files, with their file extensions, separated by spaces. The name of the MEX-file is the name of the first file in the list.

The following command combines multiple files of different types into a binary MEX-file called `circle.ext`, where `ext` is the extension corresponding to the current platform:

```
mex circle.c square.obj rectangle.c shapes.lib
```

For a Fortran files, type:

```
mex circle.F square.o rectangle.F shapes.o
```

You can use a software development tool like `MAKE` to manage MEX-file projects involving multiple source files. Create a `MAKEFILE` that contains a rule for producing object files from each of your source files, and then invoke the `mex` build script to combine your object files into a binary MEX-file. This method ensures that your source files are recompiled only when necessary.

What You Need to Build MEX-Files

To create a MEX-file:

- Install a MATLAB-supported compiler.
- Assemble your functions and the MATLAB API functions into one or more C/C++ or Fortran source files.
- Write a gateway function in one of your source files.
- Use the MATLAB `mex` function, called a build script, to build a binary MEX-file.
- Use your binary MEX-file like any MATLAB function.

If you have multiple compilers installed on your system, see “Changing Default Compiler” on page 4-20.

See Also

`mex`

Related Examples

- “Build MEX-File” on page 4-17

More About

- “C/C++ Matrix Library API”
- “Fortran Matrix Library API”
- “Troubleshoot MEX-Files”

External Web Sites

- Supported and Compatible Compilers

Changing Default Compiler

In this section...
“Windows Systems” on page 4-20
“Mac and Linux Systems” on page 4-21
“Do Not Use mex -f optionsfile Syntax” on page 4-21

Windows Systems

If you have multiple MATLAB-supported compilers for a language installed on your Windows system, MATLAB selects one as the default compiler. You can change the default using the `mex -setup language` command. If you have multiple compilers, MATLAB displays a message with links to set up a different compiler.

If you call `mex -setup` without the *language* argument, MATLAB displays links to the other supported languages. Select a link to change the default for building MEX-files in that language. MATLAB maintains separate default compiler options for C language and C++ language files.

If you call `mex -setup` from an operating system prompt, MATLAB displays the same information. However, the messages do not contain links. Instead, MATLAB displays the appropriate `mex` command syntax for changing the default compiler. Copy the command and paste it into the operating system prompt.

The compiler you choose remains the default until you call `mex -setup` to select a different default.

C Compilers

To change the default C compiler, at the MATLAB command prompt, type:

```
mex -setup
```

`mex -setup` defaults to information about the C compiler. Alternatively, type:

```
mex -setup c
```

C++ Compilers

To change the default C++ compiler, type:

```
mex -setup cpp
```

Mac and Linux Systems

MATLAB supports only one compiler for each language on Linux and Mac platforms. If you have multiple compilers installed, the default compiler might not be the MATLAB-supported compiler. You can either change the system default compiler for all applications, or select the MATLAB-supported compiler each time you run the `mex` command.

Change System Default Compiler

To determine the default gcc compiler for your system, in MATLAB, type:

```
!which gcc
```

If this is not a MATLAB-supported compiler, you can change the default. This becomes the default compiler for all applications on your system. To change the system default compiler:

Select MATLAB-Supported Compiler When Running `mex`

To change the compiler in the `mex` command, set the `varname` variable. `varname` for the gcc compiler is `GCC`, in uppercase letters. For example, if the currently supported gcc compiler is version 4.7, and it is installed in the `/usr/bin/gcc-4.7` folder on your system, to build `yprime.c`, type:

```
copyfile(fullfile(matlabroot, 'extern', 'examples', 'refbook', 'timestwo.c'), '.', 'f')  
mex -v GCC='/usr/bin/gcc-4.7' timestwo.c
```

Do Not Use `mex -f optionsfile` Syntax

The `mex` command `-f` option to specify a build configuration file will be removed in a future release. Instead, use the work flows described in this topic for specifying a compiler.

See Also

`mex`

Related Examples

- “Choose a C++ Compiler” on page 5-28

External Web Sites

- Supported and Compatible Compilers

Using MEX Script Options to Custom Build

The `mex` build script is sufficient for building MEX-files. Following are reasons that you might need more detailed information:

- You want to use an Integrated Development Environment (IDE), rather than the provided script, to build MEX-files.
- You want to exercise more control over the build process than the script uses.

Use the `mex -v -n` options to display the build commands to configure an IDE. You can also use the `mex` script options to modify the build steps.

Include Files

Header files for the MATLAB API (MEX-files, engine, and MAT-files). These files are in the `matlabroot\extern\include` folder.

- `matrix.h`—C/C++ header file containing a definition of the `mxArray` structure and function prototypes for matrix access routines.
- `mex.h`—Header file for building C/C++ MEX-files. Contains function prototypes for `mex` routines.
- `engine.h`—C/C++ header file for MATLAB engine programs. Contains function prototypes for engine routines.
- `mat.h`—C/C++ header file for programs accessing MAT-files. Contains function prototypes for `mat` routines.
- `fintrf.h`—Header file for building Fortran MEX-files. Contains function prototypes for `mex` routines.

See Also

`mex`

Compiling MEX-Files with the Microsoft Visual C++ IDE

Note: This topic provides information on how to compile source MEX-files in the Microsoft Visual C++[®] IDE. It assumes that you know how to use the IDE. If you need more information, refer to the corresponding Microsoft documentation.

To build MEX-files with the Microsoft Visual C++ integrated development environment:

- 1 Create a project and insert your MEX source files.
- 2 Create a `.def` file to export the MEX entry point. On the **Project** menu, click **Add New Item** and select **Module-Definition File (.def)**. For example:

```
LIBRARY MYFILE
EXPORTS mexFunction      <-- for a C MEX-file
    or
EXPORTS _MEXFUNCTION     <-- for a Fortran MEX-file
```

- 3 On the **Project** menu, click **Properties** for the project to open the property pages.
- 4 Under **C/C++ General** properties, add the MATLAB include folder, `matlab\extern\include`, as an additional include folder.
- 5 Under **C/C++ Preprocessor** properties, add `MATLAB_MEX_FILE` as a preprocessor definition.
- 6 Under **Linker General** properties, change the output file extension. If you are building for a 32-bit platform, use `.mexw32`. If you are building for a 64-bit platform, use `.mexw64`.
- 7 Locate the `.lib` files for the compiler you are using under `matlabroot\extern\lib\win32\microsoft` or `matlabroot\extern\lib\win64\microsoft`. Under **Linker Input** properties, add `libmx.lib`, `libmex.lib`, and `libmat.lib` as additional dependencies.
- 8 Under **Linker Input properties**, add the module definition (`.def`) file you created.
- 9 Under **Linker Debugging properties**, if you intend to debug the MEX-file using the IDE, specify that the build generates debugging information. For more information about debugging, see “Debugging on Microsoft Windows Platforms” on page 5-51.

If you are using a compiler other than the Microsoft Visual C++ compiler, the process for building MEX-files is similar. In step 4, locate the `.lib` files for the compiler you are

using in a folder of *matlabroot*\extern\lib\win32 or *matlabroot*\extern\lib\win64.

Call LAPACK and BLAS Functions

In this section...

“What You Need to Know” on page 4-26

“Creating a MEX-File Using LAPACK and BLAS Functions” on page 4-26

“Preserving Input Values from Modification” on page 4-28

“Passing Arguments to Fortran Functions from C/C++ Programs” on page 4-29

“Passing Arguments to Fortran Functions from Fortran Programs” on page 4-30

“Handling Complex Numbers in LAPACK and BLAS Functions” on page 4-31

“Modifying the Function Name on UNIX Systems” on page 4-34

What You Need to Know

You can call a LAPACK or BLAS function using a MEX-file. To create a MEX-file, you need C/C++ or Fortran programming experience and the software resources (compilers and linkers) to build an executable file. It also is helpful to understand how to use Fortran subroutines. MATLAB provides the `mwlapack` and `mwblas` libraries in `matlabroot/extern/lib`. To work with complex numbers, use the conversion routines in the `fort.c` and `fort.h` files in `matlabroot/extern/examples/refbook`. To help you get started, there are source code examples in `matlabroot/extern/examples/refbook`.

Creating a MEX-File Using LAPACK and BLAS Functions

To call LAPACK or BLAS functions:

- 1 Create a source MEX-file containing the `mexFunction` gateway routine.
- 2 Select a supported compiler for your platform.
- 3 Build a binary MEX-file using the `mex` command with one or more of the following options:
 - Link your source file to one or both of the libraries, `mwlapack` and `mwblas`.
 - Use the `-largeArrayDims` option; the `mwlapack` and `mwblas` libraries only support 64-bit integers for matrix dimensions.

- If your function uses complex numbers, build your source file with `fort.c` and include the `fort.h` header file.

The following topics show how to use the `mex` command using the example `matrixMultiply.c`. To work with this file, copy it to a local folder. For example:

```
copyfile(fullfile(matlabroot, 'extern', 'examples', 'refbook', 'matrixMultiply.c'), '.')
```

The example files are read-only files. To modify an example, ensure the file is writable by typing:

```
fileattrib('matrixMultiply.c', '+w')
```

Building on Windows Platforms

There are compiler-specific versions of the libraries on the Windows platform. To link to a specific library, look at the `matlabroot/extern/lib/` folder and choose the path for your architecture and compiler.

For example, to link to the libraries for a Microsoft C/C++ compiler, create the following build command variables, `lapacklib` and `blaslib`, which identify the full path and file name of each library.

```
lapacklib = fullfile(matlabroot, 'extern', 'lib', computer('arch'), 'microsoft', ...
    'libmwlapack.lib');
blaslib = fullfile(matlabroot, 'extern', 'lib', computer('arch'), 'microsoft', ...
    'libmwblas.lib');
```

When you use a variable to identify the library, use the function syntax of the `mex` command. (For more information, see “Command vs. Function Syntax”.) To build `matrixMultiply.c`, which uses functions from the BLAS library, type:

```
mex('-v', '-largeArrayDims', 'matrixMultiply.c', blaslib)
```

To build a MEX-file with functions that use complex numbers, see “Handling Complex Numbers in LAPACK and BLAS Functions” on page 4-31.

Building on UNIX Platforms

To build the MEX-file `matrixMultiply.c`, which uses functions from the BLAS library, type:

```
mex -v -largeArrayDims matrixMultiply.c -lmwblas
```

To build a MEX-file with functions that use complex numbers, see “Handling Complex Numbers in LAPACK and BLAS Functions” on page 4-31.

Testing the `matrixMultiply` MEX-File

To run the `matrixMultiply` MEX-file, type:

```
A = [1 3 5; 2 4 7];  
B = [-5 8 11; 3 9 21; 4 0 8];  
X = matrixMultiply(A,B)
```

```
X =  
    24    35   114  
    30    52   162
```

Preserving Input Values from Modification

Many LAPACK and BLAS functions modify the values of arguments passed to them. It is good practice to make a copy of arguments you can modify before passing them to these functions. For information about how MATLAB handles arguments to the `mexFunction`, see “Managing Input and Output Parameters” on page 5-4.

Example — `matrixDivide.c`

The following example calls the LAPACK function `dgesv` that modifies its input arguments. The code in this example makes copies of `prhs[0]` and `prhs[1]`, and passes the copies to `dgesv` to preserve the contents of the input arguments.

To see the example, open the file in the MATLAB Editor. To create the MEX-file, copy the source file to a writable folder.

```
copyfile(fullfile(matlabroot, 'extern', 'examples', 'refbook', 'matrixDivide.c'), '.')
```

To build the file on Windows, type:

```
lapacklib = fullfile(matlabroot, 'extern', 'lib', computer('arch'), 'microsoft', ...  
    'libmwlpack.lib');  
mex('-v', '-largeArrayDims', 'matrixDivide.c', lapacklib)
```

To build the file on UNIX type:

```
mex -v -largeArrayDims matrixDivide.c -lmwlapack
```

To test, type:

```
A = [1 2; 3 4];
B = [5; 6];
X = matrixDivide(A,B)

X =
    -4.0000
     4.5000
```

Passing Arguments to Fortran Functions from C/C++ Programs

The LAPACK and BLAS functions are written in Fortran. C/C++ and Fortran use different conventions for passing arguments to and from functions. Fortran functions expect the arguments to be passed by reference, while arguments to C/C++ functions are passed by value. When you pass by value, you pass a copy of the value. When you pass by reference, you pass a pointer to the value. A reference is also the address of the value.

When you call a Fortran subroutine, like a function from LAPACK or BLAS, from a C/C++ program, be sure to pass the arguments by reference. To do this, precede the argument with an ampersand (&), unless that argument is already a reference. For example, when you create a matrix using the `mXGetPr` function, you create a reference to the matrix and do not need the ampersand before the argument.

In the following code snippet, variables `m`, `n`, `p`, `one`, and `zero` need the `&` character to make them a reference. Variables `A`, `B`, `C`, and `chn` are pointers, which are references.

```
/* pointers to input & output matrices*/
double *A, *B, *C;
/* matrix dimensions */
mwSignedIndex m,n,p;
/* other inputs to dgemm */
char *chn = "N";
double one = 1.0, zero = 0.0;

/* call BLAS function */
dgemm(chn, chn, &m, &n, &p, &one, A, &m, B, &p, &zero, C, &m);
```

Example — `matrixMultiply.c`

The `matrixMultiply.c` example calls `dgemm`, passing all arguments by reference. To see the source code, open the file in the MATLAB Editor. To build and run this example, see “Creating a MEX-File Using LAPACK and BLAS Functions” on page 4-26.

Passing Arguments to Fortran Functions from Fortran Programs

You can call LAPACK and BLAS functions from Fortran MEX-files. The following example takes two matrices and multiplies them by calling the BLAS routine `dgemm`. To run the example, copy the code into the editor and name the file `callldgemm.F`.

```
#include "fintrf.h"

subroutine mexFunction(nlhs, plhs, nrhs, prhs)
mwPointer plhs(*), prhs(*)
integer nlhs, nrhs
mwPointer mxcreatedoublematrix
mwPointer mxgetpr
mwPointer A, B, C
mwSize mxgetm, mxgetn
mwSignedIndex m, n, p
mwSize numel
double precision one, zero, ar, br
character ch1, ch2

ch1 = 'N'
ch2 = 'N'
one = 1.0
zero = 0.0

A = mxgetpr(prhs(1))
B = mxgetpr(prhs(2))
m = mxgetm(prhs(1))
p = mxgetn(prhs(1))
n = mxgetn(prhs(2))

plhs(1) = mxcreatedoublematrix(m, n, 0.0)
C = mxgetpr(plhs(1))
numel = 1
call mxcopyprtoreal8(A, ar, numel)
call mxcopyprtoreal8(B, br, numel)

call dgemm(ch1, ch2, m, n, p, one, %val(A), m,
+          %val(B), p, zero, %val(C), m)

return
end
```

Link to the BLAS library, which contains the `dgemm` function.

```
blaslib = fullfile(matlabroot, 'extern', 'lib', computer('arch'), 'microsoft', ...
    'libmwbblas.lib');
```

To build the file, type:

```
mex('-v', '-largeArrayDims', 'callldgemm.F', blaslib)
```

Handling Complex Numbers in LAPACK and BLAS Functions

MATLAB stores complex numbers differently than Fortran. MATLAB stores the real and imaginary parts of a complex number in separate, equal length vectors, `pr` and `pi`. Fortran stores the same complex number in one location with the real and imaginary parts interleaved.

As a result, complex variables exchanged between MATLAB and a Fortran function are incompatible. Use the conversion routines, `mat2fort` and `fort2mat`, that change the storage format of complex numbers to address this incompatibility.

- `mat2fort` — Convert MATLAB complex matrix to Fortran complex storage.
- `fort2mat` — Convert Fortran complex storage to MATLAB real and imaginary parts.

The `fort.c` and `fort.h` files provide routines for conversion between MATLAB and Fortran complex data structures. These files define the `mat2fort` and `fort2mat` routines.

To use these routines:

- 1 Include the `fort.h` header file in your source file, using the statement `#include "fort.h"`.
- 2 Link the `fort.c` file with your program. Specify the full path, `matlabroot/extern/examples/refbook` for `fort.c` in the build command.
- 3 To indicate the header file, use the `-Ipathname` switch. Specify the full path, `matlabroot/extern/examples/refbook` for `fort.h` in the build command.
- 4 When you specify the full path, replace the term `matlabroot` with the actual folder name.

Handling Complex Number Input Values

It is unnecessary to copy arguments for functions that use complex number input values. The `mat2fort` conversion routine creates a copy of the arguments for you. For information, see “Preserving Input Values from Modification” on page 4-28.

Handling Complex Number Output Arguments

For complex variables returned by a Fortran function, do the following:

- 1 When allocating storage for the variable, allocate a real variable with twice as much space as you would for a variable of the same size. Do this because the returned variable uses the Fortran format, which takes twice the space. See the allocation of `zout` in the example.
- 2 To make the variable compatible with MATLAB, use the `fort2mat` function.

Example — Passing Complex Variables

This example shows how to call a function, passing complex `prhs[0]` as input and receiving complex `plhs[0]` as output. Temporary variables `zin` and `zout` contain the input and output values in Fortran format. To see the example, open the file in the MATLAB Editor. To create the MEX-file, copy the source file to a writable folder.

```
copyfile(fullfile(matlabroot, 'extern', 'examples', 'refbook', 'matrixDivideComplex.c'), '.');
```

To build the file on a Windows platform, type:

```
lapacklib = fullfile(matlabroot, 'extern', 'lib', computer('arch'), 'microsoft', ...  
    'libmwlpack.lib');  
fortfile = fullfile(matlabroot, 'extern', 'examples', 'refbook', 'fort.c');  
fortheaderdir = fullfile(matlabroot, 'extern', 'examples', 'refbook');  
mex('-v', '-largeArrayDims', ['-I' fortheaderdir], ...  
    'matrixDivideComplex.c', fortfile, lapacklib)
```

To build on a UNIX platform, type:

```
fortfile = fullfile(matlabroot, 'extern', 'examples', 'refbook', 'fort.c');  
fortheaderdir = fullfile(matlabroot, 'extern', 'examples', 'refbook');  
mex('-v', '-largeArrayDims', ['-I' fortheaderdir], ...  
    'matrixDivideComplex.c', fortfile, '-lmwlapack')
```

To test:

```
Areal = [1 2; 3 4];  
Aimag = [1 1; 0 0];  
Breal = [5; 6];  
Bimag = [0; 0];  
Acomplex = complex(Areal,Aimag);  
Bcomplex = complex(Breal,Bimag);  
X = matrixDivideComplex(Acomplex,Bcomplex)
```



```
X =
  -4.4000 + 0.8000i
   4.8000 - 0.6000i
```

Example — Handling Fortran Complex Return Type

Some level 1 BLAS functions (for example, `zdotu` and `zdotc`) return a **double complex** type, which the C language does not support. The following C MEX-file, `dotProductComplex.c`, shows how to handle the Fortran complex return type for function `zdotu`. To see the example, open the file in the MATLAB Editor.

The calling syntax for a C program calling a Fortran function that returns a value in an output argument is platform-dependent. On the Windows platform, the return value needs to be passed in as the first input argument. MATLAB provides a macro, `FORTRAN_COMPLEX_FUNCTIONS_RETURN_VOID`, to handle these differences.

The `dotProductComplex` example computes the dot product X of each element of two complex vectors A and B . The calling syntax is:

```
X = dotProductComplex(A,B)
```

where A and B are complex vectors of the same size and X is a complex scalar.

For example, to build the MEX-file on a Windows platform, type:

```
blaslib = fullfile(matlabroot, 'extern', 'lib', computer('arch'), 'microsoft', ...
    'libmwblas.lib');
fortfile = fullfile(matlabroot, 'extern', 'examples', 'refbook', 'fort.c');
fortheadir = fullfile(matlabroot, 'extern', 'examples', 'refbook');
mex('-v', '-largeArrayDims', ['-I' fortheadir], ...
    'dotProductComplex.c', fortfile, blaslib)
```

To test, type;

```
a1 = [1+2i; 2+3i];
b1 = [-1+2i; -1+3i];
X = dotProductComplex(a1,b1)
```

```
X =
  -16.0000 + 3.0000i
```

Example — Symmetric Indefinite Factorization Using LAPACK

The example `utdu_slv.c` calls LAPACK functions `zhesvx` and `dsysvx`. To see the example, open the file in the MATLAB Editor. To create the MEX-file, copy the source file to a writable folder.

```
copyfile(fullfile(matlabroot, 'extern', 'examples', 'refbook', 'utdu_slv.c'), '.')
```

To build the file on Windows, type:

```
lapacklib = fullfile(matlabroot, 'extern', 'lib', computer('arch'), 'microsoft', ...  
    'libmwlpack.lib');  
forheaderdir = fullfile(matlabroot, 'extern', 'examples', 'refbook');  
mex('-v', '-largeArrayDims', ['-I' forheaderdir], 'utdu_slv.c', fortfile, lapacklib)
```

To build on a UNIX platform, type:

```
mex -v -largeArrayDims utdu_slv.c -lmwlapack
```

Modifying the Function Name on UNIX Systems

Add an underscore character following the function name when calling LAPACK or BLAS functions on a UNIX system. For example, to call `dgemm`, use:

```
dgemm_(arg1, arg2, ..., argn);
```

Or add these lines to your source code:

```
#if !defined(_WIN32)  
#define dgemm dgemm_  
#endif
```

Running MEX-Files with .DLL File Extensions on Windows 32-bit Platforms

A MEX-file is a shared library dynamically loaded at runtime. Shared libraries are sometimes called `.dll` files, for dynamically linked library. MEX-files have a platform-dependent extension, which the `mex` function automatically assigns.

On 32-bit Windows platforms, the MEX-file extension is `.mexw32`. MATLAB also supports `.dll` as a secondary MEX-file extension. However, future versions of MATLAB will not support this extension.

To convert a MEX-file to the `.mexw32` file extension, rebuild the source file.

More About

- “Call MEX-File Functions”
- “Build MEX-File” on page 4-17

Upgrade MEX-Files to Use 64-Bit API

In this section...

“MATLAB Support for 64-Bit Indexing” on page 4-36

“MEX Uses 32-Bit API by Default” on page 4-36

“What If I Do Not Upgrade?” on page 4-38

“How to Upgrade MEX-Files to Use the 64-Bit API” on page 4-38

MATLAB Support for 64-Bit Indexing

MATLAB Version 7.3 (R2006b) added support for 64-bit indexing. With 64-bit indexing, you can create variables with up to $2^{48}-1$ elements on 64-bit platforms. Before Version 7.3, the C/C++ and Fortran API Reference library functions used `int` in C/C++ and `INTEGER*4` in Fortran to represent array dimensions. These types limit the size of an array to 32-bit integers. Simply building and running MEX-files on a 64-bit platform does not guarantee you access to the additional address space. You must update your MEX source code to take advantage of this functionality.

The following changes to the MX Matrix Library support 64-bit indexing:

- New types, `mwSize` and `mwIndex`, enabling large-sized data.
- Updated MX Matrix Library functions use `mwSize` and `mwIndex` types for inputs and outputs. These functions are called the *64-bit API* or the large-array-handling API.
- New `-largeArrayDims` flag for `mex` build command enabling use of the 64-bit API.

To help transition your MEX-files to the 64-bit API, MATLAB maintains an interface, or *compatibility layer*. To build MEX-files with this interface, use the `-compatibleArrayDims` flag.

Note: Only variables representing array size or index value require the `mwSize` or `mwIndex` types. The C-language `int` data type is valid for variables representing, for example, the number of fields or arrays.

MEX Uses 32-Bit API by Default

The `mex` command uses the `-compatibleArrayDims` flag (32-bit API) by default. In a future version of MATLAB, the `mex` command will change to use the large-array-

handling API. Then, the `-largeArrayDims` option will be the default. This topic describes how to upgrade your MEX-files now in preparation for that transition.

Can I Run Existing Binary MEX-Files?

You can run existing binary MEX-files without upgrading the files for use with the 64-bit API. However, unrelated incompatibilities that prevent execution of an existing MEX-file can occur. If your MEX-file does not execute properly, review the MEX Compatibility Considerations topics in the Release Notes for this release. To find MEX topics, check the External Interfaces section of the Compatibility Summary for MATLAB release notes table for each relevant version.

Must I Update Source MEX-Files on 64-Bit Platforms?

If you build MEX-files on 64-bit platforms or write platform-independent applications, you must upgrade your MEX-files when the default changes. To *upgrade*, review your source code, make appropriate changes, and rebuild using the `mex` command.

Previous versions of the External Interfaces Release Notes provide instructions for updating your MEX-files. What action you take now depends on whether your MEX-files currently use the 64-bit API. The following table helps you identify your next actions.

State of Your Source Code	Next Action
I do not plan to update my code.	You have chosen to opt out and you must build using the <code>-compatibleArrayDims</code> flag.
I want to update my code. Where do I start?	See “How to Upgrade MEX-Files to Use the 64-Bit API” on page 4-38.
I use MEX-files, but do not have access to the source code.	Ask the owner of the source code to follow the steps in “How to Upgrade MEX-Files to Use the 64-Bit API” on page 4-38.
I use third-party libraries.	Ask the vendor if the libraries support 64-bit indexing. If not, you cannot use these libraries to create 64-bit MEX-files. Build your MEX-file using the <code>-compatibleArrayDims</code> flag. If the libraries support 64-bit indexing, review your source code, following the steps

State of Your Source Code	Next Action
	in “How to Upgrade MEX-Files to Use the 64-Bit API” on page 4-38, and then test.
I updated my code in a previous release.	Review your source code, following the steps in “How to Upgrade MEX-Files to Use the 64-Bit API” on page 4-38, and then test.

Must I Update Source MEX-Files on 32-Bit Platforms?

There are no changes to building 32-bit MEX-files. However, in a future version of MATLAB, the compatibility layer, with the `-compatibleArrayDims` flag, might be unsupported and you then would need to upgrade your MEX-files.

If you build MEX-files exclusively on 32-bit platforms, but want to write platform-independent code, you still can upgrade your code. If possible, build on a 64-bit system to validate your changes.

What If I Do Not Upgrade?

On 32-bit platforms, you do not need to make any changes to build MEX-files.

On 64-bit platforms, you can build MEX-files by using the `-compatibleArrayDims` flag.

On 64-bit platforms, if you do not update your source files and you build without the `-compatibleArrayDims` flag, the results are unpredictable. One or more of the following could occur:

- Increased compiler warnings and/or errors from your native compiler
- Run-time errors
- Wrong answers

How to Upgrade MEX-Files to Use the 64-Bit API

To review and update MEX-file source code, use the following checklist.

- 1 Prepare your code before editing — see “Back Up Files and Create Tests” on page 4-39.

2 Iteratively change and test code.

Before building your MEX-files with the 64-bit API, refactor your existing code by checking for the following conditions:

- a** “Update Variables” on page 4-40.
- b** “Replace Unsupported Functions” on page 4-42.
- c** If necessary, “Update Fortran Source Code” on page 4-44.

After each change, build and test your code:

- Build with the 32-bit API. For example, to build `myMexFile.c`, type:

```
mex -compatibleArrayDims myMexFile.c
```
- Test after each refactoring — see “Test, Debug, and Resolve Differences After Each Refactoring Iteration” on page 4-42.

3 Compile using the 64-bit API. To build `myMexFile.c`, type:

```
mex -largeArrayDims myMexFile.c
```

- 4** Resolve failures and warnings — see “Resolve `-largeArrayDims` Build Failures and Warnings” on page 4-43.
- 5** Compare Results — see “Execute 64-Bit MEX-File and Compare Results with 32-Bit Version” on page 4-43.
- 6** Check memory — see “Experiment with Large Arrays” on page 4-43.

The following procedures use C/C++ terminology and example code. Fortran MEX-files share the same issues, with more tasks described in “Update Fortran Source Code” on page 4-44.

Back Up Files and Create Tests

Before adapting your code to handle large arrays, verify the MEX-file works with the traditional 32-bit array dimensions. At a minimum, build a list of expected inputs and outputs, or create a full test suite. To compare the results with the upgraded source code, use these tests. The results should be identical.

Back up all source, binary, and test files.

Update Variables

To handle large arrays, convert variables containing array indices or sizes to use the `mwSize` and `mwIndex` types instead of the 32-bit `int` type. Review your code to see if it contains the following types of variables:

- Variables used directly by the MX Matrix Library functions — see “Update Arguments Used to Call Functions in the 64-Bit API” on page 4-40.
- Intermediate variables — see “Update Variables Used for Array Indices and Sizes” on page 4-41.
- Variables used as both size/index values and as 32-bit integers — see “Analyze Other Variables” on page 4-41.

Update Arguments Used to Call Functions in the 64-Bit API

Identify the 64-bit API functions in your code that use the `mwSize` / `mwIndex` types. For the list of functions, see “Using the 64-Bit API” on page 5-60. Search for the variables that you use to call the functions. Check the function signature, shown under the **Syntax** heading on the function reference documentation. The signature identifies the variables that take `mwSize` / `mwIndex` values as input or output values. Change your variables to use the correct type.

For example, suppose that your code uses the `mxCreateDoubleMatrix` function, as shown in the following statements:

```
int nrows,ncolumns;  
...  
y_out = mxCreateDoubleMatrix(nrows, ncolumns, mxREAL);
```

To see the function signature, type:

```
doc mxCreateDoubleMatrix
```

The signature is:

```
mxArray *mxCreateDoubleMatrix(mwSize m, mwSize n,  
                               mxComplexity ComplexFlag)
```

The type for input arguments `m` and `n` is `mwSize`. Change your code as shown in the table.

Replace:	With:
<code>int nrows,ncolumns;</code>	<code>mwSize nrows,ncolumns;</code>

Update Variables Used for Array Indices and Sizes

If your code uses intermediate variables to calculate size and index values, use `mwSize` / `mwIndex` for these variables. For example, the following code declares the inputs to `mxCreateDoubleMatrix` as type `mwSize`:

```
mwSize nrows,ncolumns; /* inputs to mxCreateDoubleMatrix */
int numDataPoints;
nrows = 3;
numDataPoints = nrows * 2;
ncolumns = numDataPoints + 1;
...
y_out = mxCreateDoubleMatrix(nrows, ncolumns, mxREAL);
```

This example uses the intermediate variable, *numDataPoints* (of type `int`), to calculate the value of *ncolumns*. If you copy a 64-bit value from *nrows* into the 32-bit variable, *numDataPoints*, the resulting value truncates. Your MEX-file could crash or produce incorrect results. Use type `mwSize` for *numDataPoints*, as shown in the following table.

Replace:	With:
<code>int numDataPoints;</code>	<code>mwSize numDataPoints;</code>

Analyze Other Variables

You do not need to change every integer variable in your code. For example, field numbers in structures and status codes are of type `int`. However, you need to identify variables used for multiple purposes and, if necessary, replace them with multiple variables.

The following example creates a matrix, *myNumeric*, and a structure, *myStruct*, based on the number of sensors. The code uses one variable, *numSensors*, for both the size of the array and the number of fields in the structure.

```
mxAarray *myNumeric, *myStruct;
int numSensors;
mwSize m, n;
char **fieldnames;
...
myNumeric = mxCreateDoubleMatrix(numSensors, n, mxREAL);
myStruct = mxCreateStructMatrix(m, n, numSensors, fieldnames);
```

The function signatures for `mxCreateDoubleMatrix` and `mxCreateStructMatrix` are:

```
mxAarray *mxCreateDoubleMatrix(mwSize m, mwSize n,
```

```

    mxComplexity ComplexFlag)
mxArray *mxCreateStructMatrix(mwSize m, mwSize n,
    int nfields, const char **fieldnames);

```

For the `mxCreateDoubleMatrix` function, your code uses `numSensors` for the variable `m`. The type for `m` is `mwSize`. For the `mxCreateStructMatrix` function, your code uses `numSensors` for the variable `nfields`. The type for `nfields` is `int`. Replace `numSensors` with two new variables to handle both functions, as shown in the following table.

Replace:	With:
<pre>int numSensors;</pre>	<pre>/* create 2 variables */ /* of different types */ mwSize numSensorSize; int numSensorFields;</pre>
<pre>myNumeric = mxCreateDoubleMatrix(numSensors, n, mxREAL);</pre>	<pre>/* use mwSize variable */ /* numSensorSize */ myNumeric = mxCreateDoubleMatrix(numSensorSize, n, mxREAL);</pre>
<pre>myStruct = mxCreateStructMatrix(m, n, numSensors, fieldnames);</pre>	<pre>/* use int variable */ /* numSensorFields */ myStruct = mxCreateStructMatrix(m, n, numSensorFields, fieldnames);</pre>

Replace Unsupported Functions

While updating older MEX-files, you could find calls to unsupported functions, such as `mxCreateFull`, `mxGetName`, or `mxIsString`. MATLAB removed support for these functions in Version 7.1 (R14SP3). You cannot use unsupported functions with 64-bit array dimensions. For the list of unsupported functions and the recommended replacements, see “Obsolete Functions No Longer Documented”.

Update your code to use an equivalent function, if available. For example, use `mxCreateDoubleMatrix` instead of `mxCreateFull`.

Test, Debug, and Resolve Differences After Each Refactoring Iteration

To build `myMexFile.c` with the 32-bit API, type:

```
mex -compatibleArrayDims myMexFile.c
```

Use the tests you created at the beginning of this process to compare the results of your updated MEX-file with your original binary file. Both MEX-files should return identical results. If not, debug and resolve any differences. Differences are easier to resolve now than when you build using the 64-bit API.

Resolve -largeArrayDims Build Failures and Warnings

After reviewing and updating your code, compile your MEX-file using the large array handling API. To build `myMexFile.c` with the 64-bit API, type:

```
mex -largeArrayDims myMexFile.c
```

Since the `mwSize / mwIndex` types are MATLAB types, your compiler sometimes refers to them as `size_t`, `unsigned_int64`, or by other similar names.

Most build problems are related to type mismatches between 32- and 64-bit types. Refer to <http://www.mathworks.com/matlabcentral/answers/99144-how-do-i-update-mex-files-to-use-the-large-array-handling-api-largearraydims>, Step 5 to identify common build problems for specific compilers, and possible solutions.

Execute 64-Bit MEX-File and Compare Results with 32-Bit Version

Compare the results of running your MEX-file compiled with the 64-bit API with the results from your original binary. If there are any differences or failures, use a debugger to investigate the cause. For information on the capabilities of your debugger, refer to your compiler documentation.

Refer to <http://www.mathworks.com/matlabcentral/answers/99144-how-do-i-update-mex-files-to-use-the-large-array-handling-api-largearraydims>, Step 6 to identify issues you might encounter when running your MEX-files, and possible solutions.

After you resolve any issues and upgrade your MEX-file, it replicates the functionality of your original code while using the large array handling API.

Experiment with Large Arrays

If you have access to a machine with large amounts of memory, you can experiment with large arrays. An array of double-precision floating-point numbers (the default in MATLAB) with 2^{32} elements takes approximately 32 GB of memory.

For an example that demonstrates the use of large arrays, see the `arraySize.c` MEX-file in “Handling Large mxArrays” on page 5-60.

Update Fortran Source Code

All of the previous information applies to Fortran, as well as C/C++. Fortran uses similar API signatures, identical `mwSize` / `mwIndex` types, and similar compilers and debuggers. To make your Fortran source code 64-bit compatible, perform these additional tasks:

- “Use Fortran API Header File” on page 4-44
- “Declare Fortran Pointers” on page 4-44
- “Require Fortran Type Declarations” on page 4-44
- “Use Variables in Function Calls” on page 4-45
- “Manage Reduced Fortran Compiler Warnings” on page 4-46

Use Fortran API Header File

To make your Fortran MEX-file compatible with the 64-bit API, use the `fintrf.h` header file in your Fortran source files. Name your source files with an uppercase `.F` file extension. For more information about these requirements, see “Components of Fortran MEX-File” on page 6-2.

Declare Fortran Pointers

Pointers are 32- or 64-bit addresses, based on machine type. This requirement is not directly tied to array dimensions, but you could encounter problems when moving 32-bit code to 64-bit machines as part of this conversion.

For more information, see “Preprocessor Macros” on page 6-5 and `mwPointer`.

The C/C++ compiler automatically handles pointer size. In Fortran, MATLAB uses the `mwPointer` type to handle this difference. For example, `mxCreateDoubleMatrix` returns an `mwPointer`:

```
mwPointer mxCreateDoubleMatrix(m, n, ComplexFlag)
mwSize m, n
integer*4 ComplexFlag
```

Require Fortran Type Declarations

Fortran uses implicit type definitions. This means undeclared variables starting with letters `I` through `N` are implicitly declared type `INTEGER`. Variable names starting with

other letters are implicitly declared type `REAL*4`. Using the implicit `INTEGER` type could work for 32-bit indices, but is not safe for large array dimension MEX-files. To force you to declare all variables, add the `IMPLICIT NONE` statement to your Fortran subroutines. For example:

```
subroutine mexFunction(nlhs, plhs, nrhs, prhs)
implicit none
```

This statement helps identify 32-bit integers in your code that do not have explicit type declarations. Then, you can declare them as `INTEGER*4` or `mwSize / mwIndex`, as appropriate. For more information on `IMPLICIT NONE`, refer to your Fortran compiler documentation.

Use Variables in Function Calls

If you use a number as an argument to a function, your Fortran compiler could assign the argument an incorrect type. On a 64-bit platform, an incorrect type can produce **Out of Memory** errors, segmentation violations, or incorrect results. For example, definitions for the argument types for the `mxCreateDoubleMatrix` function are:

```
mwPointer mxCreateDoubleMatrix(m, n, ComplexFlag)
mwSize m, n
integer*4 ComplexFlag
```

Suppose that you have a C/C++ MEX-file with the following statement:

```
myArray = mxCreateDoubleMatrix(2, 3, mxREAL);
```

Most C/C++ compilers interpret the number `2` as a 64-bit value. Some Fortran compilers cannot detect this requirement, and supply a 32-bit value. For example, an equivalent Fortran statement is:

```
myArray = mxCreateDoubleMatrix(2, 3, 0)
```

The compiler interprets the value of the `ComplexFlag` argument `0` correctly as type `INTEGER*4`. However, the compiler could interpret the argument `2` as a 32-bit value, even though the argument `m` is declared type `mwSize`.

A compiler-independent solution to this problem is to declare and use an `mwSize / mwIndex` variable instead of a literal value. For example, the following statements unambiguously call the `mxCreateDoubleMatrix` function in Fortran:

```
mwSize nrows, ncols
INTEGER*4 flag
```

```
nrows = 2
ncols = 3
flag = 0
myArray = mxCreateDoubleMatrix(nrows, ncols, flag)
```

Manage Reduced Fortran Compiler Warnings

Some Fortran compilers cannot detect as many type mismatches as similar C/C++ compilers. This inability can complicate the step “Resolve -largeArrayDims Build Failures and Warnings” on page 4-43 by leaving more issues to find with your debugger in the step “Execute 64-Bit MEX-File and Compare Results with 32-Bit Version” on page 4-43.

Upgrade MEX-Files to Use Graphics Objects

MATLAB Version 8.4 (R2014b) changes the data type of handles to graphics objects from `double` to `object`.

Before Version 8.4, MEX-files used the C/C++ and Fortran API Reference library functions `mexGet` and `mexSet`, which declare the input handle argument as type `double`. If your MEX function uses `mexGet` or `mexSet`, MATLAB displays the following “Deprecated MEX function” error.

```
Error using mex
```

```
Deprecated MEX function mexGet|mexSet was called. Either update the source code to use mxGetProperty|mxSetProperty, OR rerun MEX with the -DMEX_DOUBLE_HANDLE added to the command line to enter compatibility mode.
```

To upgrade your MEX-file, consider one or more of the following actions.

In this section...

“Replace `mexGet` and `mexSet` Functions” on page 4-47

“`mex` Automatically Converts Handle Type” on page 4-50

“I Want to Rebuild MEX Source Code Files” on page 4-50

“I Do Not Have MEX Source Code File” on page 4-50

Replace `mexGet` and `mexSet` Functions

To upgrade a MEX-file to use a graphics object, replace calls to `mexGet` with `mxGetProperty` and calls to `mexSet` with `mxSetProperty`. The following program listings show an example of a before and after source MEX file.

The following code uses `mexCallMATLAB` to create a plot, which returns the graphics handle in variable `plhs[0]`. To change the line color, the example uses `mxGetScalar` to convert the handle to a `double`, then passes it to `mexGet` and `mexSet`.

```
#include "mex.h"
#define RED 0
#define GREEN 1
#define BLUE 2

void fill_array(double *x)
```

```
{
    int i = 0;
    for(i = 0 ; i < 4 ; i++)
    {
        x[i] = i+1;
    }
}

void mexFunction(int nlhs, mxArray *plhs[], int nrhs, const mxArray *prhs[])
{
    mxArray *color;
    int ret;
    double handle;
    mxArray *copycolor;
    double *acolor;

    mxArray *data = mxCreateDoubleMatrix(1,4,mxREAL);
    fill_array(mxGetPr(data));

    ret = mexCallMATLAB(1,&plhs[0],1,&data,"plot");
    if(!ret)
    {
        handle = mxGetScalar(plhs[0]);
        color = mexGet(handle,"Color");
        copycolor = mxDuplicateArray(color);
        acolor = mxGetPr(copycolor);
        acolor[RED] = (1 + acolor[RED]) /2;
        acolor[GREEN] = acolor[GREEN]/2;
        acolor[BLUE] = acolor[BLUE]/2;

        mexSet(handle,"Color",copycolor);
        mxSetProperty(plhs[0],0,"Color",copycolor);
    }
}
```

When you build this MEX-file, MATLAB displays the “Deprecated MEX function” error.

To change the source file, make the following edits. This code uses the variable `plhs[0]` in `mxGetProperty` to get the `Color` property directly. There is no need to create an intermediate `handle` variable.

```
#include "mex.h"
#define RED 0
#define GREEN 1
```



```

#define BLUE 2

void fill_array(double *x)
{
    int i = 0;
    for(i = 0 ; i < 4 ; i++)
    {
        x[i] = i+1;
    }
}

void mexFunction(int nlhs, mxArray *plhs[], int nrhs, const mxArray *prhs[])
{
    mxArray *color;
    int ret;

    mxArray *copycolor;
    double *acolor;

    mxArray *data = mxCreateDoubleMatrix(1,4,mxREAL);
    fill_array(mxGetPr(data));

    ret = mexCallMATLAB(1,&plhs[0],1,&data,"plot");
    if(!ret)
    {
        color = mxGetProperty(plhs[0],0,"Color");
        copycolor = mxDuplicateArray(color);
        acolor = mxGetPr(copycolor);
        acolor[RED] = (1 + acolor[RED]) /2;
        acolor[GREEN] = acolor[GREEN]/2;
        acolor[BLUE] = acolor[BLUE]/2;

        mxSetProperty(plhs[0],0,"Color",copycolor);
    }
}

```

To build this MEX-file, type:

```
mex mymex.c
```

```
Building with 'Microsoft Visual C++ 2010 (C)'.
MEX completed successfully.
```

Alternatively, you can build the original source file by following the steps in “I Want to Rebuild MEX Source Code Files” on page 4-50.

mex Automatically Converts Handle Type

If your MEX function uses the `mexCallMATLAB` or `mexGetVariable` functions to get a graphics handle and to pass the handle to the `mexGet` and `mexSet` APIs, then MATLAB automatically detects that behavior and your MEX function will continue to execute correctly. You know your MEX function uses this pattern if the function executes without error.

If you rebuild this MEX-file in MATLAB R2014b or later, MATLAB displays the “Deprecated MEX function” error. To rebuild the file, follow the instructions in either “Replace `mexGet` and `mexSet` Functions” on page 4-47 or “I Want to Rebuild MEX Source Code Files” on page 4-50.

I Want to Rebuild MEX Source Code Files

If you rebuild your MEX source files in MATLAB R2014b or later, MATLAB displays the “Deprecated MEX function” error.

You might be able to use the `mex` function compatibility flag, `-DMEX_DOUBLE_HANDLE`, to build the MEX-file to work with graphics objects. If the MEX-function calls a function that returns a graphics handle using the `mexCallMATLAB` or `mexGetVariable` functions, MATLAB automatically detects and converts the handle type. To build the source file, `mymex.c`, type:

```
mex -DMEX_DOUBLE_HANDLE mymex.c
```

If you pass a graphics handle to a MEX function, convert the handle to `double` before calling the function. For more information, see “I Do Not Have MEX Source Code File” on page 4-50.

I Do Not Have MEX Source Code File

If you get a runtime error and you do not have the source code, you might be able to use the following workaround. This applies only to MEX functions that take a graphics handle as an input argument.

Before you pass a graphics handle to the MEX function, first convert the handle to a `double`. For example, if you call MEX function, `mymex`:

```
Y = 1:10;  
h = plot(Y);
```

```
mymex(h)
```

add a statement to convert the handle `h` to double:

```
Y = 1:10;  
h = plot(Y);  
h = double(h);  
mymex(h)
```

See Also

[mxGetProperty](#) | [mxSetProperty](#)

More About

- “Graphics Object Handles”

Platform Compatibility

In this section...

“Verify the MEX-File Is Built For Your Platform” on page 4-52

“Verify Your Architecture on Windows Platforms” on page 4-52

Verify the MEX-File Is Built For Your Platform

If you obtain a binary MEX-file from another source, be sure that the file was compiled for the same platform on which you want to run it. The file extension reflects the platform, as shown in the following table. To determine the extension for your platform, use the `mexext` function.

MEX-File Platform-Dependent Extension

Platform	Binary MEX-File Extension
Linux (64-bit)	mexa64
Apple Mac (64-bit)	mexmaci64
Microsoft Windows (32-bit)	mexw32
Windows (64-bit)	mexw64

Verify Your Architecture on Windows Platforms

Verify the MEX-file is for the same architecture, 32- vs. 64-bit.

On non-Windows platforms, MATLAB is supported for 64-bit architectures only.

Invalid MEX-File Error

MATLAB fails to load binary MEX-files if it cannot find all `.dll` files referenced by the MEX-file. When this happens, MATLAB displays the following error message:

```
Invalid MEX-file <mexfilename>:  
The specified module could not be found.
```

where `mexfilename` is the module with the dependency error. This module cannot find its dependent libraries. To resolve this error, you must find the names of the dependent libraries, and determine if they are present on your system and available on the system path.

On Windows systems, to find library dependencies, use the third-party product Dependency Walker. Dependency Walker is a free utility that scans any 32-bit or 64-bit Windows module and builds a hierarchical tree diagram of all dependent modules. For each module found, it lists all the functions exported by that module, and which of those functions are called by other modules. Download the Dependency Walker utility from the website <http://www.dependencywalker.com/>. See <http://www.mathworks.com/matlabcentral/answers/92362-how-do-i-determine-which-libraries-my-mex-file-or-stand-alone-application-requires> for information on using the Dependency Walker.

For `.dll` files that the MEX-file linked against when it was built, the `.dll` files must be on the system path or in the same folder as the MEX-file.

MEX-files might require additional libraries that are not linked to the MEX-file. Failure to find one of these explicitly loaded libraries might not prevent a MEX-file from loading, but will prevent it from working correctly. The search path used to find these explicitly loaded libraries is controlled by the code that loads the libraries and might not include the folder that contains the MEX-file. Consult the library documentation on proper installation locations.

Possible reasons for failure include:

- MATLAB version incompatibility
- Missing compiler runtime libraries. If your system does not have the same compiler that built the MEX-file, see the Microsoft MSDN website for information about Visual C++ Redistributable Packages.
- Missing or incorrectly installed specialized runtime libraries. Contact your MEX-file or library vendor.

Run MEX-File You Receive from Someone Else

To call a MEX-file, put the file on your MATLAB path. Then type the name of the file, without the file extension.

If you have MEX-file source code, see “Build MEX-File” on page 4-17 for information about creating the executable function.

If you get runtime errors when you call a MEX-file that you did not create, consider the following:

- “Platform Compatibility”
- “Version Compatibility” on page 4-58
- On Windows platforms, install the C++ compiler runtime libraries used to create the MEX-file. This step is needed if you do not have the same compiler installed on your machine that was used to compile the MEX-file.
- If the MEX-file uses specialized runtime libraries, those libraries must be installed on your system.

If you write a MEX-file, build it, and then execute it in the same MATLAB session, all of the dependent libraries are available, as expected. However, if you receive a MEX-file from another MATLAB user, you might not have all of the dependent libraries.

A MEX-file is a *dynamically linked* subroutine that the MATLAB interpreter loads and executes when you call the function. Dynamic linking means that when you call the function, the program looks for dependent libraries. MEX-files use MATLAB runtime libraries and language-specific libraries. A MEX-file might also use specialized runtime libraries. The code for these libraries is not included in the MEX-file; the libraries must be present on your computer when you run the MEX-file.

For troubleshooting library dependencies, see “Invalid MEX-File Error” on page 4-53.

For information about how MATLAB finds a MEX-file, see “Files and Folders that MATLAB Accesses”.

MEX-File Dependent Libraries

When you build a MEX-file, MATLAB *dynamically links* your code with the following libraries:

- MATLAB runtime libraries, `libmex.dll` and `libmx.dll`. To avoid compatibility issues, run the MEX-file with the same version of MATLAB that was used to create the MEX-file. For more information, see “Version Compatibility” on page 4-58.
- Language-specific libraries, provided by the compiler. C-language MEX-files built on Windows systems require Visual C++ runtime libraries.
- Other runtime libraries, which you specify in the build command.

Dynamic linking means that when you call the function, the program looks for these dependent libraries. The code for these libraries is not included in the MEX-file. When you share a MEX-file with another MATLAB user, these libraries must be present on the user’s computer.

Document Build Information in the MEX-File

This example shows how to document the `xtimesy` MEX-file built on a Windows platform using a Microsoft Visual C++ compiler.

When you share a MEX-file, your users need the following information about the configuration used to build the MEX-file:

- MATLAB version.
- Build platform.
- Compiler.

Copy the source file to a folder on your MATLAB path.

```
copyfile(fullfile(matlabroot, 'extern', 'examples', 'refbook', 'xtimesy.c'), '.')
```

Create a help file, `xtimesy.m`, and copy the header information from the source file.

```
% xtimesy.m Help file for XTIMESY MEX-file
%
% XTIMESY Multiplies a scalar and a matrix
%   C = XTIMESY(b,A) multiplies scalar b with matrix A,
%   and returns the result in C
%
%   MEX-File function.
```

Identify your MATLAB version.

```
v = ver('matlab');
v.Release
```

```
ans =
(R2012a)
```

Identify your platform.

```
archstr = computer('arch')
```

```
archstr =
win64
```

Identify the MEX-file extension.

```
ext = mexext
```



```
ext =  
mexw64
```

Identify your C compiler.

```
cc = mex.getCompilerConfigurations('C', 'Selected');  
cc.Name
```

```
ans =  
Microsoft Visual C++ 2008 (C)
```

Add this information to the help file.

```
% xtimesy.m Help file for XTIMESY MEX-file  
%  
% XTIMESY Multiplies a scalar and a matrix  
% C = XTIMESY(b,A) multiplies scalar b with matrix A,  
% and returns the result in C  
%  
% Created with:  
% MATLAB R2012a  
% Platform: win64  
% Microsoft Visual C++ 2008  
  
% MEX-File function.
```

Provide your users with the following.

- `xtimesy.mexw64`
- `xtimesy.m`
- Instructions for downloading and installing the runtime library from the Microsoft Visual C++ 2008 Redistributable Package.
- If you build a MEX-file with a third-party library, instructions for acquiring and installing the necessary files.

Version Compatibility

For best results, your version of MATLAB must be the same version that was used to create the MEX-file.

MEX-files use MATLAB runtime libraries. MEX-files are usually backward compatible, which means you can run a MEX-file that was created on an earlier version of MATLAB on later versions of MATLAB. If the MEX-file generates errors, recompile the MEX-file from the source code.

Sometimes a MEX-file created on a newer version of MATLAB runs on an older version of MATLAB (forward compatibility), but this is not supported.

Getting Help When MEX Fails

In this section...

“Errors Finding Supported Compiler” on page 4-59

“Errors Building MEX Function” on page 4-59

“Preview mex Build Commands” on page 4-60

To help diagnose compiler setup and build errors, call `mex` with the verbose option, `-v`. For an example of the information `mex` provides, type the following commands from a writable folder:

```
copyfile(fullfile(matlabroot, 'extern', 'examples', 'refbook', 'timestwo.c'), '.', 'f')
mex -v timestwo.c
```

Errors Finding Supported Compiler

In verbose mode, `mex` displays the steps used to find a supported compiler and to determine if it is properly installed. Each step begins with the following text:

```
... Looking for
```

If the compiler is not configured properly, these messages show you the expected values for specific files, paths, and variables in the configuration.

If the compiler is found, `mex` displays a message similar to:

```
Building with 'Microsoft Visual C++ 2010 (C)'
```

Errors Building MEX Function

After locating the installed compiler, indicated by the “Building with” message, verbose mode displays the compile and link commands `mex` passes to the build tools. For example, the compile command on Windows platforms might be similar to the following:

```
cl /c /GR /W3 /EHs /nologo /MD /DMX_COMPAT_32 /D_CRT_SECURE_NO_DEPRECATED /D_SCL_SECURE_NO_WARNINGS timestwo.c
```

`mex` displays error messages from the compiler build tools. For information about errors and warnings, see your compiler or language reference documentation.

If you have experience with program development and want to modify a command parameter, use the `mex varname=varvalue` option.

Preview mex Build Commands

To display the build command details without executing the commands, type:


```
mex -n timestwo.c
```

See Also

`mex`

Understanding MEX-File Problems

Use the following figure to help isolate common problems that occur when creating binary MEX-files.



Troubleshooting MEX-File Creation Problems

In this section...

“Problem 1 — Compiling a Source MEX-File Fails” on page 4-63

“Problem 2 — Compiling Your Own Program Fails” on page 4-63

“Problem 3 — Binary MEX-File Load Errors” on page 4-64

“Problem 4 — Segmentation Fault” on page 4-65

“Problem 5 — Program Generates Incorrect Results” on page 4-65

Problems 1 through 5 refer to the corresponding numbered sections of the previous flowchart. For additional suggestions on resolving MEX-file build problems, see the MathWorks Technical Support website <http://www.mathworks.com/support>.

Problem 1 — Compiling a Source MEX-File Fails

Syntax Errors Compiling C/C++ MEX-Files on UNIX

The most common configuration problem in creating C/C++ source MEX-files on UNIX systems involves using a non-ANSI C compiler, or failing to pass to the compiler a flag that tells it to compile ANSI C code.

A reliable way of knowing if you have this type of configuration problem is if the header files supplied by MATLAB generate a string of syntax errors when you try to compile your code. See “What You Need to Build MEX-Files” on page 4-19 or, if necessary, obtain an ANSI C compiler.

File Not Found on Windows

The `mex` function cannot find files located in folder names that contain non-ASCII characters.

Problem 2 — Compiling Your Own Program Fails

Mixing ANSI and non-ANSI C code can generate a string of syntax errors. MATLAB provides header and source files that are ANSI C compliant. Therefore, your C code must also be ANSI compliant.

Other common problems that can occur in any C/C++ program are neglecting to include all necessary header files, or neglecting to link against all required libraries.

Make sure that you are using a MATLAB-supported compiler. For an up-to-date list of supported compilers, see the Supported and Compatible Compilers website. Additional information can be found in “Compiler- and Platform-Specific Issues” on page 4-66.

Symbol mexFunction Unresolved or Not Defined

Attempting to compile a MEX-function that does not include a gateway function generates errors about the `mexFunction` symbol. For example, using a C/C++ compiler, MATLAB displays information like:

```
LINK : error LNK2001: unresolved external symbol mexFunction
```

Using a Fortran compiler, MATLAB displays information like:

```
unresolved external symbol _MEXFUNCTION
```

If you want to call functions from a C/C++ or Fortran library from MATLAB, you must write a gateway function, as described in “Components of MEX-File” on page 5-3.

Problem 3 — Binary MEX-File Load Errors

If you receive an error of the form:

```
Unable to load mex file:  
Invalid MEX-file
```

MATLAB does not recognize your MEX-file.

MATLAB loads MEX-files by looking for the gateway routine, `mexFunction`. If you misspell the function name, MATLAB cannot load your MEX-file and generates an error message. On Windows systems, check that you are exporting `mexFunction` correctly.

On some platforms, if you fail to link against required libraries, you might get an error when MATLAB loads your MEX-file rather than when you compile your MEX-file. In such cases, a system error message referring to *unresolved symbols* or *unresolved references* appears. Be sure to link against the library that defines the function in question.

On Windows systems, MATLAB fails to load MEX-files if it cannot find all `.dll` files referenced by the MEX-file; the `.dll` files must be on the path or in the same folder as the MEX-file. This is also true for third party `.dll` files. To diagnose this problem, see “Invalid MEX-File Error” on page 4-53 for information.

Problem 4 — Segmentation Fault

If a binary MEX-file causes a segmentation violation or assertion, it means the MEX-file attempted to access protected, read-only, or unallocated memory.

These types of programming errors are sometimes difficult to track down. Segmentation violations do not always occur at the same point as the logical errors that cause them. If a program writes data to an unintended section of memory, an error might not occur until the program reads and interprets the corrupted data. Consequently, a segmentation violation can occur after the MEX-file finishes executing.

One cause of memory corruption is to pass a null pointer to a function. To check for this condition, add code in your MEX-file to check for invalid arguments to MEX Library and MX Matrix Library API functions.

To troubleshoot problems of this nature, run MATLAB within a debugging environment. For more information, see “Debugging on Microsoft Windows Platforms” or “Debug Fortran Source MEX-Files”.

Problem 5 — Program Generates Incorrect Results

If your program generates the wrong answers, there are several causes. First, there could be an error in the computational logic. Second, the program could be reading from an uninitialized section of memory. For example, reading the eleventh element of a 10-element vector yields unpredictable results.

Another cause of generating a wrong answer could be overwriting valid data due to memory mishandling. For example, writing to the fifteenth element of a 10-element vector might overwrite data in the adjacent variable in memory. This case can be handled in a similar manner as segmentation violations, as described in Problem 4.

In all of these cases, you can use `mexPrintf` to examine data values at intermediate stages or run MATLAB within a debugger to exploit all the tools the debugger provides.

Compiler- and Platform-Specific Issues

In this section...
“Linux gcc Compiler Version Error” on page 4-66
“Linux gcc -fPIC Errors” on page 4-66

Linux gcc Compiler Version Error

For information concerning a gcc compiler version error on Linux systems, see <http://www.mathworks.com/matlabcentral/answers/97943-why-do-i-receive-an-error-about-gcc-version-when-executing-a-mex-file-or-an-executable-generated-by>.

Linux gcc -fPIC Errors

If you link a static library with a MEX-file, which is a shared library, you might get an error message containing the text `recompile with -fPIC`. Try compiling the static library with the `-fPIC` flag in order to create position independent code. For information about using the gcc compiler, see www.gnu.org. For an up-to-date list of supported compilers, see the Supported and Compatible Compilers website.

Memory Management Issues

In this section...

“Overview” on page 4-67

“Improperly Destroying an mxArray” on page 4-68

“Incorrectly Constructing a Cell or Structure mxArray” on page 4-68

“Creating a Temporary mxArray with Improper Data” on page 4-69

“Creating Potential Memory Leaks” on page 4-70

“Improperly Destroying a Structure” on page 4-70

“Destroying Memory in a C++ Class Destructor” on page 4-71

Overview

When a MEX-file returns control to MATLAB, it returns the results of its computations in the output arguments—the `mxArrays` contained in the left-side arguments `plhs[]`. MATLAB destroys any `mxArray` created by the MEX-file that is not in this argument list. In addition, MATLAB frees any memory that was allocated in the MEX-file using the `mxMalloc`, `mxRealloc`, or `mxMalloc` functions.

In general, MathWorks® recommends that MEX-file functions destroy their own temporary arrays and free their own dynamically allocated memory. It is more efficient to perform this cleanup in the source MEX-file than to rely on the automatic mechanism. This approach is consistent with other MATLAB API applications (MAT-file applications, engine applications, and MATLAB Compiler generated applications, which do not have any automatic cleanup mechanism.)

However, do not destroy an `mxArray` in a source MEX-file when it is:

- passed to the MEX-file in the right-hand side list `prhs[]`
- returned in the left side list `plhs[]`
- returned by `mexGetVariablePtr`
- used to create a structure

This section describes situations specific to memory management. We recommend that you review code in your source MEX-files to avoid using these functions in the

following situations. For more information, see “Memory Management” on page 5-64 in *Creating C/C++ Language MEX-Files*. For guidance on memory issues, see “Strategies for Efficient Use of Memory”.

Potential memory management problems include:

Improperly Destroying an mxArray

Do not use `mxFree` to destroy an `mxArray`.

Example

In the following example, `mxFree` does not destroy the array object. This operation frees the structure header associated with the array, but MATLAB still operates as if the array object needs to be destroyed. Thus MATLAB tries to destroy the array object, and in the process, attempts to free its structure header again:

```
mxArray *temp = mxCreateDoubleMatrix(1,1,mxREAL);  
    ...  
mxFree(temp); /* INCORRECT */
```

Solution

Call `mxDestroyArray` instead:

```
mxDestroyArray(temp); /* CORRECT */
```

Incorrectly Constructing a Cell or Structure mxArray

Do not call `mxSetCell` or `mxSetField` variants with `prhs[]` as the member array.

Example

In the following example, when the MEX-file returns, MATLAB destroys the entire cell array. Since this includes the members of the cell, this implicitly destroys the MEX-file's input arguments. This can cause several strange results, generally having to do with the corruption of the caller's workspace, if the right-hand side argument used is a temporary array (for example, a literal or the result of an expression):

```
myfunction('hello')
```

```

/* myfunction is the name of your MEX-file and your code
/* contains the following: */

    mxArray *temp = mxCreateCellMatrix(1,1);
    ...
    mxSetCell(temp, 0, prhs[0]); /* INCORRECT */

```

Solution

Make a copy of the right-hand side argument with `mxDuplicateArray` and use that copy as the argument to `mxSetCell` (or `mxSetField` variants). For example:

```

mxSetCell(temp, 0, mxDuplicateArray(prhs[0])); /* CORRECT */

```

Creating a Temporary mxArray with Improper Data

Do not call `mxDestroyArray` on an `mxArray` whose data was not allocated by an API routine.

Example

If you call `mxSetPr`, `mxSetPi`, `mxSetData`, or `mxSetImagData`, specifying memory that was not allocated by `mxMalloc`, `mxMalloc`, or `mxRealloc` as the intended data block (second argument), then when the MEX-file returns, MATLAB attempts to free the pointers to real data and imaginary data (if any). Thus MATLAB attempts to free memory, in this example, from the program stack:

```

mxArray *temp = mxCreateDoubleMatrix(0,0,mxREAL);
double data[5] = {1,2,3,4,5};
...
mxSetM(temp,1); mxSetN(temp,5); mxSetPr(temp, data);
/* INCORRECT */

```

Solution

Rather than use `mxSetPr` to set the data pointer, instead, create the `mxArray` with the right size and use `memcpy` to copy the stack data into the buffer returned by `mxGetPr`:

```

mxArray *temp = mxCreateDoubleMatrix(1,5,mxREAL);
double data[5] = {1,2,3,4,5};
...
memcpy(mxGetPr(temp), data, 5*sizeof(double)); /* CORRECT */

```

Creating Potential Memory Leaks

Prior to Version 5.2, if you created an `mxArray` using one of the API creation routines and then you overwrote the pointer to the data using `mxSetPr`, MATLAB still freed the original memory. This is no longer the case.

For example:

```
pr = mxCalloc(5*5, sizeof(double));  
... <load data into pr>  
plhs[0] = mxCreateDoubleMatrix(5,5,mxREAL);  
mxSetPr(plhs[0], pr); /* INCORRECT */
```

will now leak $5*5*8$ bytes of memory, where 8 bytes is the size of a double.

You can avoid that memory leak by changing the code to:

```
plhs[0] = mxCreateDoubleMatrix(5,5,mxREAL);  
pr = mxGetPr(plhs[0]);  
... <load data into pr>
```

or alternatively:

```
pr = mxCalloc(5*5, sizeof(double));  
... <load data into pr>  
plhs[0] = mxCreateDoubleMatrix(5,5,mxREAL);  
mxFree(mxGetPr(plhs[0]));  
mxSetPr(plhs[0], pr);
```

The first solution is more efficient.

Similar memory leaks can also occur when using `mxSetPi`, `mxSetData`, `mxSetImagData`, `mxSetIr`, or `mxSetJc`. You can avoid memory leaks by changing the code as described in this section.

Improperly Destroying a Structure

For a structure, you must call `mxDestroyArray` only on the structure, not on the field data arrays. A field in the structure points to the data in the array used by `mxSetField` or `mxSetFieldByNumber`. When `mxDestroyArray` destroys the structure, it attempts to traverse down through itself and free all other data, including the memory in the data arrays. If you call `mxDestroyArray` on each data array, the same memory is freed twice and this can corrupt memory.

Example

The following example creates three arrays: one structure array `aStruct` and two data arrays, `myDataOne` and `myDataTwo`. Field name `one` contains a pointer to the data in `myDataOne`, and field name `two` contains a pointer to the data in `myDataTwo`.

```
mxArray *myDataOne;
mxArray *myDataTwo;
mxArray *aStruct;
const char *fields[] = { "one", "two" };

myDataOne = mxCreateDoubleScalar(1.0);
myDataTwo = mxCreateDoubleScalar(2.0);

aStruct = mxCreateStructMatrix(1,1,2,fields);
mxSetField( aStruct, 0, "one", myDataOne );
mxSetField( aStruct, 1, "two", myDataTwo );
mxDestroyArray(myDataOne);
mxDestroyArray(myDataTwo);
mxDestroyArray(aStruct); /* tries to free myDataOne and myDataTwo */
```

Solution

The command `mxDestroyArray(aStruct)` destroys the data in all three arrays:

```
...
aStruct = mxCreateStructMatrix(1,1,2,fields);
mxSetField( aStruct, 0, "one", myDataOne );
mxSetField( aStruct, 1, "two", myDataTwo );
mxDestroyArray(aStruct);
```

Destroying Memory in a C++ Class Destructor

Do not use the `mxFree` or `mxDestroyArray` functions in a C++ destructor of a class used in a MEX-function. If the MEX-function throws an error, MATLAB cleans up MEX-file variables, as described in “Automatic Cleanup of Temporary Arrays” on page 5-64.

If an error occurs that causes the object to go out of scope, MATLAB calls the C++ destructor. Freeing memory directly in the destructor means both MATLAB and the destructor free the same memory, which can corrupt memory.

Compiler Errors in Fortran MEX-Files

When you compile a Fortran MEX-file using a free source form format, MATLAB displays an error message of the following form:

```
Illegal character in statement label field
```

mex supports the fixed source form. The difference between free and fixed source forms is explained in the Fortran Language Reference Manual Source Forms topic. The URL for this topic is:

```
http://h21007.www2.hp.com/portal/download/files/unprot/Fortran/docs/lrm/lrm0015.htm#source\_formatmenu?&Record=383697&STASH=7
```

The URL for the Fortran Language Reference Manual is:

```
http://h21007.www2.hp.com/portal/download/files/unprot/Fortran/docs/lrm/df1rm.htm
```


C/C++ MEX-Files

- “Components of MEX-File” on page 5-3
- “MATLAB API Libraries” on page 5-6
- “User Messages” on page 5-8
- “Error Handling” on page 5-9
- “Data Flow in MEX-Files” on page 5-10
- “Creating C++ MEX-Files” on page 5-13
- “C++ Class in MEX-Files” on page 5-15
- “Handle Files with C++” on page 5-16
- “Create C Source MEX-File” on page 5-18
- “Table of MEX-File Source Code Files” on page 5-24
- “Choose a C++ Compiler” on page 5-28
- “Set Up C/C++ Examples” on page 5-29
- “Pass Scalar Values” on page 5-30
- “Pass Strings” on page 5-33
- “Handling Strings in C/C++” on page 5-35
- “Pass Multiple Inputs or Outputs” on page 5-38
- “Pass Structures and Cell Arrays” on page 5-40
- “Create 2-D Cell Array” on page 5-41
- “Fill mxArray” on page 5-42
- “Prompt User for Input” on page 5-44
- “Handle Complex Data” on page 5-45
- “Handle 8-, 16-, and 32-Bit Data” on page 5-46
- “Manipulate Multidimensional Numerical Arrays” on page 5-47
- “Handle Sparse Arrays” on page 5-49
- “Call MATLAB Functions from C/C++ MEX-Files” on page 5-50

- “Debugging on Microsoft Windows Platforms” on page 5-51
- “Debugging on Linux Platforms” on page 5-53
- “Debugging on Mac Platforms” on page 5-55
- “Handling Large mxArray’s” on page 5-60
- “Memory Management” on page 5-64
- “Handling Large File I/O” on page 5-67

Components of MEX-File

In this section...

“mexFunction Gateway Routine” on page 5-3

“Naming the MEX-File” on page 5-3

“Required Parameters” on page 5-3

“Managing Input and Output Parameters” on page 5-4

“Validating Inputs” on page 5-4

“Computational Routine” on page 5-5

mexFunction Gateway Routine

The *gateway routine* is the entry point to the MEX-file. It is through this routine that MATLAB accesses the rest of the routines in your MEX-files. The name of the gateway routine is `mexFunction`. It takes the place of the `main` function in your source code.

Naming the MEX-File

The name of the source file containing `mexFunction` is the name of your MEX-file, and, hence, the name of the function you call in MATLAB.

The file extension of the binary MEX-file is platform-dependent. You find the file extension using the `mexext` function, which returns the value for the current machine.

Required Parameters

The signature for `mexfunction` is:

```
void mexFunction(
    int nlhs, mxArray *plhs[],
    int nrhs, const mxArray *prhs[])
```

Place this function after your computational routine and any other functions in your source file.

The following table describes the parameters for `mexFunction`.

Parameter	Description
<code>prhs</code>	Array of right-side input arguments.
<code>plhs</code>	Array of left-side output arguments.
<code>nrhs</code>	Number of right-side arguments, or the size of the <code>prhs</code> array.
<code>nlhs</code>	Number of left-side arguments, or the size of the <code>plhs</code> array.

Declare `prhs` and `plhs` as type `mxArray *`, which means they point to MATLAB arrays. They are vectors that contain pointers to the arguments of the MEX-file. The keyword `const`, which modifies `prhs`, means that your MEX-file does not modify the input arguments.

You can think of the name `prhs` as representing the “parameters, right-hand side,” that is, the input parameters. Likewise, `plhs` represents the “parameters, left-hand side,” or output parameters.

Managing Input and Output Parameters

Input parameters (found in the `prhs` array) are read-only; do not modify them in your MEX-file. Changing data in an input parameter can produce undesired side effects.

You also must take care when using an input parameter to create output data or any data used locally in your MEX-file. To copy an input array into a locally-defined variable, `myData`, call the `mxDuplicateArray` function to make a copy of the input array. For example:

```
mxArray *myData = mxCreateStructMatrix(1,1,nfields,fnames);  
mxSetField(myData,0,"myFieldName",mxDuplicateArray(prhs[0]));
```

For more information, see the troubleshooting topic “Incorrectly Constructing a Cell or Structure `mxArray`” on page 4-68.

Validating Inputs

For a list of functions to validate inputs to your functions, see the Matrix Library category, “Validate Data”.

The `mxIsClass` function is a general-purpose way to test an `mxArray`. For example, suppose your second input argument (identified by `prhs[1]`) must be a full matrix of real numbers. To check this condition, use the following statements.

```
if(mxIsSparse(prhs[1]) ||  
    mxIsComplex(prhs[1]) ||  
    mxIsClass(prhs[1], "char")) {  
    mexErrMsgTxt("input2 must be full matrix of real values.");  
}
```

This example is not an exhaustive check. You can also test for structures, cell arrays, function handles, and MATLAB objects.

Computational Routine

The *computational routine* contains the code for performing the computations you want implemented in the binary MEX-file. Although not required, consider writing the gateway routine, `mexFunction`, to call a computational routine. Use the `mexFunction` code as a wrapper to validate input parameters and to convert them into the types required by the computational routine.

If you write separate gateway and computational routines, you can combine them into one source file or into separate files. If you use separate files, the file containing `mexFunction` must be the first source file listed in the `mex` command.

See Also

`mexext` | `mexFunction` | `mxDuplicateArray` | `mxIsClass`

More About

- “MATLAB API Libraries” on page 5-6

MATLAB API Libraries

In this section...
“Matrix Library” on page 5-6
“MEX Library” on page 5-6
“Preprocessor Macros” on page 5-6

The Matrix Library and the MEX Library describe functions you can use in your gateway and computational routines that interact with MATLAB programs and the data in the MATLAB workspace. These libraries are part of the MATLAB C/C++ and Fortran API Reference library.

To use these functions, include the `mex` header, which declares the entry point and interface routines. Put this statement in your source file:

```
#include "mex.h"
```

Matrix Library

Use Matrix Library functions to pass *mxArray*, the type MATLAB uses to store arrays, to and from MEX-files. For examples using these functions, see *matlabroot/extern/examples/mx*.

MEX Library

Use MEX Library functions to perform operations in the MATLAB environment. For a list of the C functions, see “C/C++ Source Files”. For examples using these functions, see *matlabroot/extern/examples/mex*.

Unlike MATLAB functions, MEX-file functions do not have their own variable workspace. MEX-file functions operate in the caller's workspace. Use `mexEvalString` to evaluate the string in the caller's workspace. Use the `mexGetVariable` and `mexPutVariable` functions to get and put variables into the caller's workspace.

Preprocessor Macros

The Matrix and MEX libraries use the MATLAB *preprocessor macros* `mwSize` and `mwIndex` for cross-platform flexibility. `mwSize` represents size values, such as array

dimensions and number of elements. `mwIndex` represents index values, such as indices into arrays.

See Also

“MEX Library” | C/C++ Matrix Library | `mexEvalString` | `mexGetVariable` | `mexPutVariable` | `mwIndex` | `mwSize` | `mxArray`

More About

- “MATLAB Data” on page 4-7

User Messages

To print a string in the MATLAB Command Window, use the `mexPrintf` function as you would a C/C++ `printf` function. To print error and warning information in the Command Window, use the `mexErrMsgIdAndTxt` and `mexWarnMsgIdAndTxt` functions.

For example, the following code snippet prints the input string, `prhs[0]`.

```
char *buf;
int buflen;

if (mxGetString(prhs[0], buf, buflen) == 0) {
    mexPrintf("The input string is: %s\n", buf);
}
```

See Also

`mexErrMsgIdAndTxt` | `mexPrintf` | `mexWarnMsgIdAndTxt`

Error Handling

The `mexErrMsgIdAndTxt` function prints error information and terminates your binary MEX-file. The `mexWarnMsgIdAndTxt` function prints information, but does not terminate the MEX-file.

```
char *buf;
int buflen;

if (mxIsChar(prhs[0])) {
    if (mxGetString(prhs[0], buf, buflen) == 0) {
        mexPrintf("The input string is: %s\n", buf);
    }
    else {
        mexErrMsgIdAndTxt("MyProg:ConvertString",
            "Could not convert string data.");
        // exit MEX-file
    }
}
else {
    mexWarnMsgIdAndTxt("MyProg:InputString",
        "Input should be a string to print properly.");
}

// continue with processing
```

See Also

`mexErrMsgIdAndTxt` | `mexWarnMsgIdAndTxt`

Data Flow in MEX-Files

In this section...

“Showing Data Input and Output” on page 5-10

“Gateway Routine Data Flow Diagram” on page 5-11

Showing Data Input and Output


Suppose your MEX-file `myFunction` has two input arguments and one output argument. The MATLAB syntax is `[X] = myFunction(Y, Z)`. To call `myFunction` from MATLAB, type:

```
X = myFunction(Y, Z);
```

The MATLAB interpreter calls `mexFunction`, the gateway routine to `myFunction`, with the following arguments:

```
nlhs = 1
```

```
nrhs = 2
```



Your input is `prhs`, a two-element array (`nrhs = 2`). The first element is a pointer to an mxArray named `Y` and the second element is a pointer to an mxArray named `Z`.

Your output is `plhs`, a one-element array (`nlhs = 1`) where the single element is a null pointer. The parameter `plhs` points at nothing because the output `X` is not created until the subroutine executes.

The gateway routine creates the output array and sets a pointer to it in `plhs[0]`. If the routine does not assign a value to `plhs[0]` but you assign an output value to the function when you call it, MATLAB generates an error.

Note: It is possible to return an output value even if `nlhs = 0`, which corresponds to returning the result in the `ans` variable.


Gateway Routine Data Flow Diagram

The following MEX Cycle diagram shows how inputs enter a MEX-file, what functions the gateway routine performs, and how outputs return to MATLAB.

In this example, the syntax of the MEX-file `func` is `[C, D] = func(A,B)`. In the figure, a call to `func` tells MATLAB to pass variables `A` and `B` to your MEX-file. `C` and `D` are left unassigned.

The gateway routine, `func.c`, uses the `mxCreate*` functions to create the MATLAB arrays for your output arguments. It sets `plhs[0]` and `plhs[1]` to the pointers to the newly created MATLAB arrays. It uses the `mxGet*` functions to extract your data from your input arguments `prhs[0]` and `prhs[1]`. Finally, it calls your computational routine, passing the input and output data pointers as function parameters.

MATLAB assigns `plhs[0]` to `C` and `plhs[1]` to `D`.



C/C++ MEX Cycle

Creating C++ MEX-Files

In this section...

“Creating Your C++ Source File” on page 5-13

“Compiling and Linking” on page 5-13

“Memory Considerations For Class Destructors” on page 5-13

“Use mexPrintf to Print to the MATLAB Command Window” on page 5-14

MEX-files support all C++ language standards. This topic discusses specific C++ language issues to consider when creating and using MEX-files.

Use the C syntax statements in the MATLAB API libraries in your C++ applications. You can also copy MATLAB C code examples into C++ applications. For example, see the `mexcpp.cpp` file that contains both C and C++ statements.

Creating Your C++ Source File

The C++ source code for the examples provided by MATLAB use the `.cpp` file extension. The extension `.cpp` is unambiguous and recognized by C++ compilers. Other possible extensions include `.C`, `.cc`, and `.cxx`.

Compiling and Linking

To build a C++ MEX-file, type:

```
mex filename.cpp
```

where *filename* is the name of the source file.

You can run a C++ MEX-file only on systems with the same version of MATLAB that the file was compiled on.

Memory Considerations For Class Destructors

Do not use the `mxFree` or `mxDestroyArray` functions in a C++ destructor of a class used in a MEX-function. If the MEX-function throws an error, MATLAB cleans up MEX-file variables, as described in “Automatic Cleanup of Temporary Arrays” on page 5-64.

If an error occurs that causes the object to go out of scope, MATLAB calls the C++ destructor. Freeing memory directly in the destructor means both MATLAB and the destructor free the same memory, which can corrupt memory.

Use `mexPrintf` to Print to the MATLAB Command Window

Using `cout` or the C-language `printf` function does not work as expected in C++ MEX-files. Use the `mexPrintf` function instead.

See Also

`mexPrintf`

Related Examples

- “C++ Class in MEX-Files” on page 5-15
- “Handle Files with C++” on page 5-16
- `mexcpp.cpp`

More About

- “Build MEX-File” on page 4-17

C++ Class in MEX-Files

This example, `mexcpp.cpp`, shows how to use C++ code with your C language MEX-file. It uses member functions, constructors, destructors, and the `iostream` include file.

To build this example, at the command prompt type:

```
mex mexcpp.cpp
```

The calling syntax is `mexcpp(num1, num2)`.

The routine defines a class, `myData`, with member functions `display` and `set_data`, and variables `v1` and `v2`. It constructs an object `d` of class `myData` and displays the initialized values of `v1` and `v2`. It then sets `v1` and `v2` to your input, `num1` and `num2`, and displays the new values. Finally, the `delete` operator cleans up the object.

Related Examples

- `mexcpp.cpp`

Handle Files with C++

In this section...

“C++ Example” on page 5-16

“C Example” on page 5-16

The `mexatexit.cpp` example shows C++ file handling features. Compare it with the C code example `mexatexit.c`, which uses the `mexAtExit` function.

C++ Example

The C++ example uses a `fileresource` class to handle the file open and close functions. The MEX-file calls the destructor for this class (which closes the data file). This example also prints a message on the screen when performing operations on the data file. However, in this case, the only C file operation performed is the write operation, `fprintf`.

To build the `mexatexit.cpp` MEX-file, type:

```
mex mexatexit.cpp
```

Type:

```
z = 'for the C++ MEX-file';  
mexatexit(x)  
mexatexit(z)  
clear mexatexit
```

```
Writing data to file.
```

```
Writing data to file.
```

Display the contents of `matlab.data`.

```
type matlab.data
```

```
my input string  
for the C++ MEX-file
```

C Example

The C code example registers the `mexAtExit` function to perform cleanup tasks (close the data file) when the MEX-file clears. This example prints a message on the screen (using `mexPrintf`) when performing file operations `fopen`, `fprintf`, and `fclose`.

To build the MEX-file, type:

```
mex mexatexit.c
```

Run the example.

```
x = 'my input string';  
mexatexit(x)
```

```
Opening file matlab.data.  
Writing data to file.
```

Clear the MEX-file.

```
clear mexatexit
```

```
Closing file matlab.data.
```

Display the contents of `matlab.data`.

```
type matlab.data
```

```
my input string
```

See Also

`mexAtExit`

Related Examples

- `mexatexit.cpp`
- `mexatexit.c`

Create C Source MEX-File

This example shows how to write a MEX-file to call a C function, `arrayProduct`, in MATLAB using a MATLAB matrix. You can use these same C statements in a C++ application.

`arrayProduct` multiplies an n -dimensional array, `y`, by a scalar value, `x`, and returns the results in array, `z`.

```
void arrayProduct(double x, double *y, double *z, int n)
{
    int i;

    for (i=0; i<n; i++) {
        z[i] = x * y[i];
    }
}
```

Create Source File

Open MATLAB Editor, create a new file, and document the MEX-file with the following information.

```
/*
 * arrayProduct.c - example in MATLAB External Interfaces
 *
 * Multiplies an input scalar (multiplier)
 * times a 1xN matrix (inMatrix)
 * and outputs a 1xN matrix (outMatrix)
 *
 * The calling syntax is:
 *
 * outMatrix = arrayProduct(multiplier, inMatrix)
 *
 * This is a MEX-file for MATLAB.
 */
```

Add the C/C++ header file, `mex.h`, containing the MATLAB API function declarations.

```
#include "mex.h"
```

Save the file on your MATLAB path, for example, in `c:\work`, and name it `arrayProduct.c`. The name of your MEX-file is `arrayProduct`.

Create Gateway Routine

Every C program has a `main()` function. MATLAB uses the gateway routine, `mexfunction`, as the entry point to the function. Add the following `mexFunction` code.

```
/* The gateway function */
void mexFunction(int nlhs, mxArray *plhs[],
                 int nrhs, const mxArray *prhs[])
{
/* variable declarations here */

/* code here */
}
```

This table describes the input parameters for `mexfunction`.

Parameter	Description
<code>nlhs</code>	Number of output (left-side) arguments, or the size of the <code>plhs</code> array.
<code>plhs</code>	Array of output arguments.
<code>nrhs</code>	Number of input (right-side) arguments, or the size of the <code>prhs</code> array.
<code>prhs</code>	Array of input arguments.

Verify MEX-File Input and Output Parameters

Verify the number of MEX-file input and output arguments using the `nrhs` and `nlhs` arguments.

To check for two input arguments, `multiplier` and `inMatrix`, use this code.

```
if(nrhs!=2) {
    mexErrMsgIdAndTxt("MyToolbox:arrayProduct:nrhs",
                     "Two inputs required.");
}
```

Use this code to check for one output argument, the product `outMatrix`.

```
if(nlhs!=1) {
    mexErrMsgIdAndTxt("MyToolbox:arrayProduct:nlhs",
                     "One output required.");
}
```

```
}
```

Verify the argument types using the `plhs` and `prhs` arguments. This code validates that `multiplier`, represented by `prhs[0]`, is a scalar.

```
/* make sure the first input argument is scalar */  
if( !mxIsDouble(prhs[0]) ||  
    mxIsComplex(prhs[0]) ||  
    mxGetNumberOfElements(prhs[0])!=1 ) {  
    mexErrMsgIdAndTxt("MyToolbox:arrayProduct:notScalar",  
                    "Input multiplier must be a scalar.");  
}
```

This code validates that `inMatrix`, represented by `prhs[1]`, is type `double`.

```
if( !mxIsDouble(prhs[1]) ||  
    mxIsComplex(prhs[1])) {  
    mexErrMsgIdAndTxt("MyToolbox:arrayProduct:notDouble",  
                    "Input matrix must be type double.");  
}
```

Validate that `inMatrix` is a row vector.

```
/* check that number of rows in second input argument is 1 */  
if(mxGetM(prhs[1])!=1) {  
    mexErrMsgIdAndTxt("MyToolbox:arrayProduct:notRowVector",  
                    "Input must be a row vector.");  
}
```

Create Computational Routine

Add the `arrayProduct` code. This function is your *computational routine*, the source code that performs the functionality you want to use in MATLAB.

```
void arrayProduct(double x, double *y, double *z, int n)  
{  
    int i;  
  
    for (i=0; i<n; i++) {  
        z[i] = x * y[i];  
    }  
}
```

A computational routine is optional. Alternatively, you can place the code within the `mexfunction` function block.

Write Code for Cross-Platform Flexibility

MATLAB provides a preprocessor macro, `mwSize`, that represent size values for integers, based on the platform. The computational routine declares the size of the array as `int`. Replace the `int` declaration for variables `n` and `i` with `mwSize`.

```
void arrayProduct(double x, double *y, double *z, mwSize n)
{
    mwSize i;

    for (i=0; i<n; i++) {
        z[i] = x * y[i];
    }
}
```

Declare Variables for Computational Routine

Put the following variable declarations in `mexFunction`.

- Declare variables for the input arguments.

```
double multiplier;      /* input scalar */
double *inMatrix;      /* 1xN input matrix */
```

- Declare `ncols` for the size of the input matrix.

```
mwSize ncols;          /* size of matrix */
```

- Declare the output argument, `outMatrix`.

```
double *outMatrix;     /* output matrix */
```

Later you assign the `mexFunction` arguments to these variables.

Read Input Data

To read the scalar input, use the `mxGetScalar` function.

```
/* get the value of the scalar input */
multiplier = mxGetScalar(prhs[0]);
```

Use the `mxGetPr` function to point to the input matrix data.

```
/* create a pointer to the real data in the input matrix */
inMatrix = mxGetPr(prhs[1]);
```

Use the `mxGetN` function to get the size of the matrix.

```
/* get dimensions of the input matrix */
ncols = mxGetN(prhs[1]);
```

Prepare Output Data

To create the output argument, `plhs[0]`, use the `mxCreateDoubleMatrix` function.

```
/* create the output matrix */
plhs[0] = mxCreateDoubleMatrix(1,ncols,mxREAL);
```

Use the `mxGetPr` function to assign the `outMatrix` argument to `plhs[0]`

```
/* get a pointer to the real data in the output matrix */
outMatrix = mxGetPr(plhs[0]);
```

Perform Calculation

Pass the arguments to `arrayProduct`.

```
/* call the computational routine */
arrayProduct(multiplier,inMatrix,outMatrix,ncols);
```

View Complete Source File

Compare your source file with `arrayProduct.c`, located in `matlabroot/extern/examples/mex`. Open the file in the editor.

Build Binary MEX-File

At the MATLAB command prompt, build the binary MEX-file.

```
mex arrayProduct.c
```

Test the MEX-File

```
s = 5;
A = [1.5, 2, 9];
B = arrayProduct(s,A)

B =
    7.5000    10.0000    45.0000
```

Validate MEX-File Input Arguments

It is good practice to validate the type of a MATLAB variable before calling a MEX-file. To test the input variable, `inputArg`, and convert it to `double`, if necessary, use this code.

```
A = [1.5, 2, 9];
inputArg = int16(A);
if ~strcmp(class(inputArg), 'double')
    inputArg = double(inputArg);
end
B = arrayProduct(s, inputArg)
```

See Also

[mexfunction](#) | [mwSize](#) | [mxCreateDoubleMatrix](#) | [mxGetN](#) | [mxGetPr](#) | [mxGetScalar](#)

Related Examples

- [arrayProduct.c](#)

More About

- “Creating C++ MEX-Files” on page 5-13

Table of MEX-File Source Code Files

Source code for the MEX examples shown in the following table is in subfolders of *matlabroot/extern/examples*. Make sure that you have a MATLAB-supported compiler installed.

To build a code example, first copy the file to a writable folder on your path:

```
copyfile(fullfile(matlabroot, 'extern', 'examples', 'foldername', ...
    'filename'), '.', 'f')
```

where *filename* is the name of the example, for example `arrayProduct.c`, and *foldername* is the subfolder name, for example `mex`.

You can create and compile MEX-files in MATLAB or at your operating system prompt. At either prompt, type:

```
mex -v filename
```

For examples listing multiple Fortran sources files, both files are required to build the MEX-file.

```
mex -v file1.F file2.F
```

You can modify the source code for the examples. For convenience, the example instructions open the files in MATLAB Editor, but you can use any code development editor.

Example Name	Example Subfolder	Description
<code>arrayFillGetPr.c</code>	<code>refbook</code>	Fill <code>mxArray</code> using <code>mxGetPr</code>
<code>arrayFillSetData.c</code>	<code>refbook</code>	Fill <code>mxArray</code> with non-double values
<code>arrayFillSetPr.c</code>	<code>refbook</code>	Fill <code>mxArray</code> using <code>mxSetPr</code> to dynamically allocate memory
<code>arrayProduct.c</code>	<code>mex</code>	Multiply a scalar times 1xN matrix
<code>arraySize.c</code>	<code>mex</code>	Illustrate memory requirements of large <code>mxArray</code>

Example Name	Example Subfolder	Description
convec.c convec.F	refbook	Pass complex data
dblmat.F compute.F	refbook	Use of Fortran %VAL
dotProductComplex.c	refbook	Handle Fortran complex return type for function called from a C MEX-file
doubleelement.c	refbook	Use unsigned 16-bit integers
explore.c	mex	Identify data type of input variable
findnz.c	refbook	Use N-dimensional arrays
fulltosparse.c fulltosparse.F, loadsparse.F	refbook	Populate a sparse matrix
matrixDivide.c	refbook	Call a LAPACK function
matrixDivideComplex.c	refbook	Call a LAPACK function with complex numbers
matrixMultiply.c	refbook	Call a BLAS function
matsq.F	refbook	Pass matrices in Fortran
matsqint8.F	refbook	Pass non-double matrices in Fortran
mexatexit.c mexatexit.cpp	mex	Register an exit function to close a data file
mexcallmatlab.c	mex	Call built-in MATLAB disp function
mexcallmatlabwithtrap.c	mex	How to capture error information
mexcpp.cpp	mex	Illustrate some C++ language features in a MEX-file
mexevalstring.c	mex	Use mexEvalString to assign variables in MATLAB

Example Name	Example Subfolder	Description
mexfunction.c	mex	How to use <code>mexfunction</code>
mexgetproperty.c	mex	Use <code>mxGetProperty</code> and <code>mxSetProperty</code> to change the <code>Color</code> property of a graphics object
mexgetarray.c	mex	Use <code>mexGetVariable</code> and <code>mexPutVariable</code> to track counters in the MEX-file and in the MATLAB global workspace
mexlock.c mexlockf.F	mex	How to lock and unlock a MEX-file
mxcalcsinglesubscript.c	mx	Demonstrate MATLAB 1-based matrix indexing versus C 0-based indexing
mxcreatecellmatrix.c mxcreatecellmatrixf.F	mx	Create 2-D cell array
mxcreatecharmatrixfromstr.c	mx	Create 2-D string array
mxcreatestructarray.c	mx	Create MATLAB structure from C structure
mxgeteps.c mxgetepssf.F	mx	Read MATLAB <code>eps</code> value
mxgetinf.c	mx	Read <code>inf</code> value
mxgetnzmax.c	mx	Display number of nonzero elements in a sparse matrix and maximum number of nonzero elements it can store
mxisclass.c	mx	Check if array is member of specified class
mxisfinite.c	mx	Check for NaN and infinite values
mxislogical.c	mx	Check if workspace variable is logical or global

Example Name	Example Subfolder	Description
mxmalloc.c	mx	Allocate memory to copy a MATLAB string to a C string
mxsetdimensions.c mxsetdimensionsf.F	mx	Reshape an array
mxsetnzmax.c	mx	Reallocate memory for sparse matrix and reset values of <code>pr</code> , <code>pi</code> , <code>ir</code> and <code>nzmax</code>
passstr.F	refbook	Pass C character matrix from Fortran to MATLAB
phonebook.c	refbook	Manipulate structures and cell arrays
revord.c revord.F	refbook	Copy MATLAB string data to and from C-style string
sincall.c sincall.F, fill.F	refbook	Create <code>mxArray</code> and pass to MATLAB <code>sin</code> and <code>plot</code> functions
timestwo.c timestwo.F	refbook	Demonstrate common workflow of MEX-file
utdu_slv.c	refbook	Use LAPACK for symmetric indefinite factorization
xtimesy.c xtimesy.F	refbook	Pass multiple parameters
yprime.c yprimef.F, yprimefg.F	mex	Solve simple three body orbit problem

Choose a C++ Compiler

This example shows how to determine and change the default compiler for building C++ MEX-files when you have multiple versions of Microsoft Visual Studio on your system. The messages in this example assume you have Microsoft Visual C++ 2012 and Microsoft Visual C++ 2010. Use these steps for any C++ compilers on your system.

MATLAB chooses a default compiler for C source files and a default compiler for C++ source files. To see the default C++ compiler, type:

```
mex -setup c++
```

```
MEX configured to use 'Microsoft Visual C++ 2012' for C++ language compilation.
```

MATLAB also displays links to other C++ compilers installed on your system.

To change the default to MSVC 2010, click the link:

```
Microsoft Visual C++ 2010
```

```
MEX configured to use 'Microsoft Visual C++ 2010' for C++ language compilation.
```

Microsoft Visual C++ 2010 remains the default until you call `mex -setup c++` to select a different default.

When you call the `mex` command with a source file, MATLAB displays the name of the compiler used to build the MEX-file. You can also find this information using the `mex -setup lang` command. By default, when you type `mex -setup`, MATLAB shows you information for the C compiler only. If you want information for C++ compilers, type:

```
mex -setup c++
```

More About

- “Changing Default Compiler” on page 4-20

Set Up C/C++ Examples

The Matrix Library provides a full set of routines that handle the types supported by MATLAB. For each data type, there is a specific set of functions that you can use for data manipulation. The first example discusses the simple case of doubling a scalar. After that, the examples discuss how to pass in, manipulate, and pass back various data types, and how to handle multiple inputs and outputs. Finally, the sections discuss passing and manipulating various MATLAB types.

Source code for the examples in this section is in the *matlabroot/extern/examples/refbook* folder. To build an example, first copy the file to a writable folder on your path:

```
copyfile(fullfile(matlabroot,'extern','examples','refbook',...  
    'filename.c'),'.','f')
```

where *filename* is the name of the example.

At the MATLAB command prompt, type:

```
mex filename.c
```

The following topics look at source code for the examples. Unless otherwise specified, the term "MEX-file" refers to a source file.

For a list of MEX example files available with MATLAB, see "Table of MEX-File Source Code Files".

Pass Scalar Values

In this section...

“Pass Scalar as Matrix” on page 5-30

“Pass Scalar by Value” on page 5-31

Pass Scalar as Matrix

This example shows how to write a MEX-file that passes scalar values.

Suppose that you have the following C code, `timestwo`, that takes a scalar input, a 1-by-1 matrix, and doubles it.

```
void timestwo(double y[], double x[])
{
    y[0] = 2.0*x[0];
    return;
}
```

C Code Analysis

To see the function written as a MEX-file, open the file, `timestwo.c`, in the MATLAB Editor.

In C/C++, the compiler checks function arguments for number and type. However, in MATLAB, you can pass any number or type of arguments to a function; the function is responsible for argument checking. MEX-files also allow variable inputs. Your MEX-file must safely handle any number of input or output arguments of any supported type.

This code checks for the proper number of arguments.

```
if(nrhs!=1) {
    mexErrMsgIdAndTxt( "MATLAB:timestwo:invalidNumInputs",
        "One input required.");
} else if(nlhs>1) {
    mexErrMsgIdAndTxt( "MATLAB:timestwo:maxlhs",
        "Too many output arguments.");
}
```

This code checks if the input is a scalar double value.

```

mrows = mxGetM(prhs[0]);
ncols = mxGetN(prhs[0]);
if( !mxIsDouble(prhs[0]) || mxIsComplex(prhs[0]) ||
    !(mrows==1 && ncols==1) ) {
    mexErrMsgIdAndTxt( "MATLAB:timestwo:inputNotRealScalarDouble",
        "Input must be a noncomplex scalar double.");
}

```

Build and Test Example

Build the MEX-file.

```
mex -v timestwo.c
```

Call the function.

```

x = 2;
y = timestwo(x)

y =
     4

```

Pass Scalar by Value

This example shows how to write a MEX-file that passes a scalar by value.

The `mxGetScalar` function returns the value of a scalar instead of a pointer to a copy of the scalar variable, `x`.

The following C code implements the `timestwo_alt` function.

```

void timestwo_alt(double *y, double x)
{
    *y = 2.0*x;
}

```

Compare the `timestwo_alt` function signature with the `timestwo` function signature.

```

void timestwo_alt(double *y, double x)
void timestwo(double y[], double x[])

```

The input value `x` is a scalar of type `double`. In the `timestwo` function, the input value is a matrix of type `double`.

To see the function written as a MEX-file, open the file, `timestwoalt.c`, in the MATLAB Editor.

Compare the call to `timestwo_alt` to the call to `timestwo`.

```
/* Get the scalar value of the input x */
/* note: mxGetScalar returns a value, not a pointer */
x = mxGetScalar(prhs[0]);

/* Assign a pointer to the output */
y = mxGetPr(plhs[0]);

/* Call the timestwo_alt subroutine */
timestwo_alt(y,x);

/* Assign pointers to each input and output. */
x = mxGetPr(prhs[0]);
y = mxGetPr(plhs[0]);

/* Call the timestwo subroutine. */
timestwo(y,x);
```

The value `x`, created by `mxGetScalar`, is a scalar not a pointer.

Pass Strings

This example shows how to pass strings to a MEX-file. The example `revord.c` accepts a string and returns the characters in reverse order.

C Code Analysis

To see the code, open the file, `revord.c`, in the MATLAB Editor.

The gateway function, `mexFunction`, creates a C string from the input variable, `prhs[0]`. By isolating variables of type `mxArray` from the computational subroutine, `revord`, you can avoid making significant changes to your original C and C++ code.

Convert the input argument, `prhs[0]`, to a C-style string, `input_buf`.

```
input_buf = mxArrayToString(prhs[0]);
```

Allocate memory for the output argument, `output_buf`, a C-style string.

```
output_buf=mxMalloc(buflen, sizeof(char));
```

The size of the output argument is equivalent to the size of the input argument.

Call the computational subroutine, `revord`.

```
revord(input_buf, buflen, output_buf);
```

Convert the output, `output_buf`, to an `mxArray` and assign to `plhs[0]`.

```
plhs[0] = mxCreateString(output_buf);
```

Do not release memory for this variable because it is an output argument.

The `mxArrayToString` function, used to create the temporary `input_buf` variable, allocates memory; use the `mxFree` function to release the memory.

```
mxFree(input_buf);
```

Build and Test Example

Run the following commands from the MATLAB command line.

Build the example.

```
mex -v revord.c
```

Call the function.

```
x = 'hello world';  
y = revord(x)
```

```
y =  
dlrow olleh
```

Related Examples

- `revord.c`

Handling Strings in C/C++

In this section...

“How MATLAB Represents Strings in MEX-Files” on page 5-35

“Character Encoding and Multibyte Encoding Schemes” on page 5-35

“Converting MATLAB String to C-Style String” on page 5-36

“Converting C-Style String to MATLAB String” on page 5-36

“Returning Modified Input String” on page 5-36

“Memory Management” on page 5-36

How MATLAB Represents Strings in MEX-Files

In C/C++ MEX-files, a MATLAB string is an `mxArray` of type `mxChar`, using a locale-neutral data representation (Unicode encoding). MATLAB represents C-style strings as type `char`, and uses the character encoding scheme specified by the user locale setting.

The following C/C++ Matrix Library functions provides string handling functions to help you work with both `mxArrays` and C-style strings.

- `mxCreateString` — Creates a string `mxArray` initialized to the input string.
- `mxArrayToString` — Copies a string `mxArray` into a C-style string. Supports multibyte encoded characters.
- `mxGetString` — Copies a string `mxArray` into a C-style string. Best used with single-byte encoded characters. Supports multibyte encoded characters when you calculate string buffer size.
- `mxGetChars` — Returns a pointer to the first `mxChar` element in the `mxArray`.

Consider the following topics when choosing a string handling function.

Character Encoding and Multibyte Encoding Schemes

MATLAB supports the character encoding scheme specified by the user locale setting. When an MX Library function converts `mxChar` data to a C `char` type, MATLAB also converts the character to the user default encoding.

If you use a multibyte encoding scheme, use the `mxArrayToString` function.

The `mxGetChars` function provides a pointer to the `mxChar` array; it does not change the character encoding.

You can also use the `mxGetString` function with multibyte encoding schemes. `mxGetString` converts the `mxChar` data to your user default encoding, and copies the converted characters to the destination buffer. However, you must calculate the size of the destination buffer. For single-byte encoding, the size of the buffer is the number of characters, plus 1 for the null terminator. For multibyte encoding, the size of a character is one or more bytes. Some options for calculating the buffer size are to overestimate the amount (calculating the number of characters times the maximum number of bytes used by the encoding scheme), analyze the string to determine the precise size used by each character, or utilize 3rd-party string buffer libraries. After this calculation, add 1 for the null terminator.

Converting MATLAB String to C-Style String

When you pass a character array to a MEX-function, it is an `mxArray` of type `mxChar`. If you call a C function to manipulate the string, first convert the data to a C type `char` using the `mxArrayToString` or `mxGetString` functions.

Converting C-Style String to MATLAB String

If your MEX-file creates a C string and returns the data to MATLAB, use the `mxCreateString` function to copy the C string into an `mxChar` array.

Returning Modified Input String

Suppose your MEX-file takes a string input argument, modifies it, and returns the result. Since MEX-file input parameters (the `prhs` array) are read-only, you must define a separate output parameter to handle the modified string.

Memory Management

MathWorks recommends that MEX-file functions destroy their own temporary arrays and free their own dynamically allocated memory. The function you use to release memory depends on how you use the string buffer and what function you use to create the buffer.

If you call this function:	Release memory using this function:
Any string function listed here	Do not destroy an <code>mxAarray</code> in a source MEX-file when it is: <ul style="list-style-type: none"> • Passed to the MEX-file in the right-hand side list <code>prhs []</code>. • Returned in the left side list <code>plhs []</code>. • Returned by the <code>mexGetVariablePtr</code> function. • Used to create a structure.
<code>mxAarrayToString</code>	<code>mxFree</code>
<code>mxAarrayGetString</code>	When using <code>mxAarrayCalloc</code> / <code>mxAarrayMalloc</code> / <code>mxAarrayRealloc</code> to create input argument <code>buf</code> , call <code>mxFree(buf)</code> .
<code>mxAarrayCreateString</code>	<code>mxAarrayDestroyArray</code>
<code>mxAarrayGetChars</code>	None. Function creates a pointer to an <code>mxAarray</code> but does not allocate additional memory.

More About

- “C/C++ Matrix Library API”
- “How the MATLAB Process Uses Locale Settings”

Pass Multiple Inputs or Outputs

This example shows how to call a MEX-file with multiple inputs. The function, `xtimesy`, multiplies an input scalar by a scalar or matrix and outputs a matrix.

The `plhs[]` and `prhs[]` parameters are vectors that contain pointers to each left-side (output) variable and each right-side (input) variable, respectively. `plhs[0]` contains a pointer to the first left-side argument, `plhs[1]` contains a pointer to the second left-side argument, and so on. Likewise, `prhs[0]` contains a pointer to the first right-side argument, `prhs[1]` points to the second, and so on.

C Code Analysis

To see the code, open the file, `xtimesy.c`, in the MATLAB Editor.

Get the scalar input value, `x`.

```
x = mxGetScalar(prhs[0]);
```

Get the second input, `y`, which can be either a scalar or a matrix.

```
y = mxGetPr(prhs[1]);
```

Create the output argument, `plhs[0]`, which is the same size as argument `y`.

```
/* get the dimensions of the matrix input y */
mrows = mxGetM(prhs[1]);
ncols = mxGetN(prhs[1]);

/* set the output pointer to the output matrix */
plhs[0] = mxCreateDoubleMatrix( (mwSize)mrows, (mwSize)ncols, mxREAL);
```

Build and Test Example

Run the following commands from the MATLAB command line.

Build the example.

```
mex -v xtimesy.c
```

Call the function with scalar values.

```
x = 7;
y = 7;
```

```
z = xtimesy(x,y)
```

```
z =  
    49
```

Call the function with a matrix.

```
x = 9;  
y = ones(3);  
z = xtimesy(x,y)
```

```
z =  
     9     9     9  
     9     9     9  
     9     9     9
```

Related Examples

- `xtimesy.c`

Pass Structures and Cell Arrays

Passing structures and cell arrays into MEX-files is like passing any other data type, except the data itself is of type `mxArray`. In practice, `mxGetField` (for structures) and `mxGetCell` (for cell arrays) return pointers of type `mxArray`. You treat the pointers like any other pointers of type `mxArray`. To pass the data contained in the `mxArray` to a C/C++ routine, use an API function such as `mxGetData` to access it.

This example takes an `m`-by-`n` structure matrix as input and returns a new 1-by-1 structure that contains these fields:

- String input generates an `m`-by-`n` cell array
- Numeric input (noncomplex, scalar values) generates an `m`-by-`n` vector of numbers with the same class ID as the input, for example, `int`, `double`, and so on.

To build this example, at the command prompt type:

```
mex phonebook.c
```

To see how this program works, enter this structure:

```
friends(1).name = 'Jordan Robert';  
friends(1).phone = 3386;  
friends(2).name = 'Mary Smith';  
friends(2).phone = 3912;  
friends(3).name = 'Stacy Flora';  
friends(3).phone = 3238;  
friends(4).name = 'Harry Alpert';  
friends(4).phone = 3077;
```

Call the MEX-file:

```
phonebook(friends)  
  
ans =  
    name: {1x4 cell }  
    phone: [3386 3912 3238 3077]
```

Related Examples

- `phonebook.c`

Create 2-D Cell Array

This example shows how to create a cell array in a MEX-file, using the `mxcreatecellmatrix.c` function, which places input arguments in a cell array.

C Code Analysis

To see the code, open the file in MATLAB Editor.

Create a cell array for the number of input arguments.

```
cell_array_ptr = mxCreateCellMatrix((mwSize)nrhs,1);
```

Copy the input arguments into the cell array.

```
for( i=0; i<(mwIndex)nrhs; i++){  
    mxSetCell(cell_array_ptr,i,mxDuplicateArray(prhs[i]));
```

Build and Test Example

Run the following commands from the MATLAB command line.

Build the example.

```
mex -v mxcreatecellmatrix.c
```

Create input arguments.

```
str1 = 'hello';  
str2 = 'world';  
num = 2012;
```

Create a 3-x-1 cell array and call `disp` to display the contents.

```
mxcreatecellmatrix(str1,str2,num)
```

The contents of the created cell is:

```
'hello'  
'world'  
[2012]
```

Related Examples

- `mxcreatecellmatrix.c`

Fill mxArray

In this section...

“Options” on page 5-42

“Copying Data Directly into an mxArray” on page 5-42

“Pointing to Data” on page 5-42

Options

You can move data from a C/C++ program into an mxArray using the Matrix Library. The functions you use depend on the type of data in your application. Use the `mxSetPr` and `mxGetPr` functions for data of type `double`. For numeric data other than `double`, use the `mxSetData` function. For nonnumeric data, see the examples for the `mxCreateString` function.

The following examples use a variable, `data`, to represent data from a computational routine. Each example creates an mxArray using the `mxCreateNumericMatrix` function, fills it with `data`, and returns it as the output argument `plhs[0]`.

These examples use real data only. If you have complex data, use the `mxGetPi` and `mxSetPi` functions as needed.

Copying Data Directly into an mxArray

The `arrayFillGetPr.c` example uses the `mxGetPr` function to copy the values from `data` to `plhs[0]`.

Pointing to Data

The `arrayFillSetPr.c` example uses the `mxSetPr` function to point `plhs[0]` to `data`.

The example `arrayFillSetData.c` shows how to fill an mxArray for numeric types other than `double`.

See Also

`mxCreateString` | `mxGetPr` | `mxSetData` | `mxSetPr`

Related Examples

- `arrayFillGetPr.c`
- `arrayFillSetPr.c`
- `arrayFillSetData.c`

Prompt User for Input

Because MATLAB does not use `stdin` and `stdout`, do not use C/C++ functions like `scanf` and `printf` to prompt for user input. The following example shows how to use `mexCallMATLAB` with the `input` function to get a number from the user.

```
#include "mex.h"
#include "string.h"
void mexFunction( int nlhs, mxArray *plhs[],
                  int nrhs, const mxArray *prhs[] )
{
    mxArray  *new_number, *str;
    double out;

    str = mxCreateString("Enter extension: ");
    mexCallMATLAB(1,&new_number,1,&str,"input");
    out = mxGetScalar(new_number);
    mexPrintf("You entered: %.0f ", out);
    mxDestroyArray(new_number);
    mxDestroyArray(str);
    return;
}
```

For information about getting user input from a MATLAB function or script, see the `input` function.

Handle Complex Data

MATLAB separates complex data into real and imaginary parts. The MATLAB API provides two functions, `mxGetPr` and `mxGetPi`, that return pointers (of type `double *`) to the real and imaginary parts of your data.

This example, `convec.c`, takes two complex row vectors and convolves them.

To build this example, at the command prompt type:

```
mex convec.c
```

Enter these numbers at the MATLAB prompt.

```
x = [3.000 - 1.000i, 4.000 + 2.000i, 7.000 - 3.000i];
y = [8.000 - 6.000i, 12.000 + 16.000i, 40.000 - 42.000i];
```

Call the MEX-file.

```
z = convec(x,y)
```

```
z =
    1.0e+02 *
```

```
Columns 1 through 4
```

```
0.1800 - 0.2600i 0.9600 + 0.2800i 1.3200 - 1.4400i 3.7600 - 0.1200i
```

```
Column 5
```

```
1.5400 - 4.1400i
```

Compare the results with the built-in MATLAB function `conv`.

See Also

`mxGetPi` | `mxGetPr`

Related Examples

- `convec.c`

Handle 8-, 16-, and 32-Bit Data

The MATLAB API provides a set of functions that support signed and unsigned 8-, 16-, and 32-bit data. For example, the `mxCreateNumericArray` function constructs an unpopulated N-dimensional numeric array with a specified data size. For more information, see `mxClassID`.

Once you have created an unpopulated MATLAB array of a specified data type, you can access the data using `mxGetData` and `mxGetImagData`. These two functions return pointers to the real and imaginary data. You can perform arithmetic on data of 8-, 16-, or 32-bit precision in MEX-files and return the result to MATLAB, which recognizes the correct data class.

The example, `doubleelement.c`, constructs a 2-by-2 matrix with unsigned 16-bit integers, doubles each element, and returns both matrices to MATLAB.

To build this example, at the command prompt type:

```
mex doubleelement.c
```

Call the example.

```
doubleelement
```

```
ans =  
     2     6  
     4     8
```

The output of this function is a 2-by-2 matrix populated with unsigned 16-bit integers.

See Also

`mxClassID` | `mxCreateNumericArray` | `mxGetData` | `mxGetImagData`

Related Examples

- `doubleelement.c`

Manipulate Multidimensional Numerical Arrays

You can manipulate multidimensional numerical arrays by using `mxGetData` and `mxGetImagData`. These functions return pointers to the real and imaginary parts of the data stored in the original multidimensional array. The example, `findnz.c`, takes an N-dimensional array of doubles and returns the indices for the nonzero elements in the array.

Build the example.

```
mex findnz.c
```

Create a sample matrix.

```
matrix = [ 3 0 9 0; 0 8 2 4; 0 9 2 4; 3 0 9 3; 9 9 2 0]
```

```
matrix =  
  3   0   9   0  
  0   8   2   4  
  0   9   2   4  
  3   0   9   3  
  9   9   2   0
```

`findnz` determines the position of all nonzero elements in the matrix.

```
nz = findnz(matrix)
```

```
nz =  
  1   1  
  4   1  
  5   1  
  2   2  
  3   2  
  5   2  
  1   3  
  2   3  
  3   3  
  4   3  
  5   3  
  2   4  
  3   4  
  4   4
```

See Also

`mxGetData` | `mxGetImagData`

Related Examples

- `findnz.c`

Handle Sparse Arrays

The MATLAB API provides a set of functions that allow you to create and manipulate sparse arrays from within your MEX-files. These API routines access and manipulate `ir` and `jc`, two of the parameters associated with sparse arrays. For more information on how MATLAB stores sparse arrays, see “The MATLAB Array” on page 4-7.

The example, `fulltosparse.c`, shows how to populate a sparse matrix.

Build the example.

```
mex fulltosparse.c
```

Create a full, 5-by-5 identity matrix.

```
full = eye(5)

full =
     1     0     0     0     0
     0     1     0     0     0
     0     0     1     0     0
     0     0     0     1     0
     0     0     0     0     1
```

Call `fulltosparse` to produce the corresponding sparse matrix.

```
spar = fulltosparse(full)

spar =
    (1,1)      1
    (2,2)      1
    (3,3)      1
    (4,4)      1
    (5,5)      1
```

Related Examples

- `fulltosparse.c`

Call MATLAB Functions from C/C++ MEX-Files

It is possible to call MATLAB functions, operators, user-defined functions, and other binary MEX-files from within your C/C++ source code by using the API function `mexCallMATLAB`.

The example, `sincall.c`, creates an `mxArray`, passes various pointers to a local function to acquire data, and calls `mexCallMATLAB` to calculate the `sine` function and plot the results.

To build this example, at the command prompt type:

```
mex sincall.c
```

Run the example.

```
sincall
```

MATLAB displays a sin curve equivalent to executing the following MATLAB commands:

```
MAX = 1000;  
  
mm = MAX/2;  
for i = 1:mm-1  
    X(i) = i*(4*3.14159/MAX);  
end  
  
Y = sin(X);  
plot(X,Y)
```

See Also

`mexCallMATLAB`

Related Examples

- `sincall.c`

Debugging on Microsoft Windows Platforms

This example shows how to debug `yprime.c`, found in your `matlabroot/extern/examples/mex/` folder, with Microsoft Visual Studio 2010.

- 1 Make sure Visual Studio is your selected C compiler:

```
cc = mex.getCompilerConfigurations('C','Selected');
cc.Name
```

```
ans =
```

```
Microsoft Visual C++ 2010 (C)
```

- 2 Compile the source MEX-file with the `-g` option, which builds the file with debugging symbols included. For example:

```
copyfile(fullfile(matlabroot,'extern','examples','mex','yprime.c'),'.','f')
mex -g yprime.c
```

- 3 Start Visual Studio. Do not exit your MATLAB session.
- 4 From the Visual Studio **Tools** menu, select **Attach to Process...**
- 5 In the Attach to Process dialog box, select the MATLAB process and click **Attach**.

Visual Studio loads data then displays an empty code pane.

- 6 Open the source file `yprime.c` by selecting **File > Open > File**. Locate `yprime.c` in the folder, `c:\work`.
- 7 Set a breakpoint by right-clicking the desired line of code and following **Breakpoint > Insert Breakpoint** on the context menu. It is often convenient to set a breakpoint at `mexFunction` to stop at the beginning of the gateway routine.

If you have not yet run the executable file, ignore any “!” icon that appears with the breakpoint next to the line of code.

Once you hit one of your breakpoints, you can make full use of any commands the debugger provides to examine variables, display memory, or inspect registers.

- 8 Open MATLAB and type:

```
yprime(1,1:4)
```

`yprime.c` is opened in the Visual Studio debugger at the first breakpoint.

- 9 If you select **Debug > Continue**, MATLAB displays:

```
ans =  
    2.0000    8.9685    4.0000   -1.0947
```

For more information on how to debug in the Visual Studio environment, see your Microsoft documentation.

Notes on Debugging

Binary MEX-files built with the `-g` option do not execute on other computers because they rely on files that are not distributed with MATLAB. For more information on isolating problems with MEX-files, see “Troubleshoot MEX-Files”.

Debugging on Linux Platforms

The GNU[®] Debugger `gdb`, available on Linux systems, provides complete source code debugging, including the ability to set breakpoints, examine variables, and step through the source code line-by-line.

In this procedure, the MATLAB command prompt `>>` is shown in front of MATLAB commands, and `linux>` represents a Linux prompt; your system might show a different prompt. The debugger prompt is `<gdb>`.

To debug with `gdb`:

- 1 Compile the source MEX-file with the `-g` option, which builds the file with debugging symbols included. For this example, at the Linux prompt, type:

```
linux> mex -g yprime.c
```

- 2 At the Linux prompt, start the `gdb` debugger using the `matlab -D` option.

```
linux> matlab -Dgdb
```

- 3 Tell `gdb` to stop for debugging.

```
<gdb> handle SIGSEGV SIGBUS nostop noprint
```

- 4 Start MATLAB without the Java[®] Virtual Machine (JVM[™]) by using the `-nojvm` startup flag.

```
<gdb> run -nojvm
```

- 5 In MATLAB, enable debugging with the `dbmex` function and run your binary MEX-file.

```
>> dbmex on  
>> yprime(1,1:4)
```

- 6 You are ready to start debugging.

It is often convenient to set a breakpoint at `mexFunction` so you stop at the beginning of the gateway routine.

```
<gdb> break mexFunction  
<gdb> r
```

- 7 Once you hit one of your breakpoints, you can make full use of any commands the debugger provides to examine variables, display memory, or inspect registers.

To proceed from a breakpoint, type:

```
<gdb> continue
```

- 8** After stopping at the last breakpoint, type:

```
<gdb> continue
```

`yprime` finishes and MATLAB displays:

```
ans =
```

```
2.0000    8.9685    4.0000   -1.0947
```

- 9** From the MATLAB prompt you can return control to the debugger by typing:

```
>> dbmex stop
```

Or, if you are finished running MATLAB, type:

```
>> quit
```

- 10** When you are finished with the debugger, type:

```
<gdb> quit
```

You return to the Linux prompt.

Refer to the documentation provided with your debugger for more information on its use.

Debugging on Mac Platforms

In this section...

“Using Xcode” on page 5-55

“Using LLDB” on page 5-57

Using Xcode

This example shows how to debug the MEX-file, `yprime.c`, using Xcode.

Copy the source MEX file

The `yprime.c` source code is in the `matlabroot` folder. In MATLAB, copy the file to a local, writable folder, for example `/usr/work/my_data`. Create the folder if it does not already exist.

```
copyfile(fullfile(matlabroot, 'extern', 'examples', 'mex', 'yprime.c'), ...  
fullfile('/', 'usr', 'work', 'my_data'))
```

Set your current folder in MATLAB to `/usr/work/my_data`.

Compile the source MEX file

Compile the source MEX-file with the `-g` option, which adds debugging symbols.

```
mex -g yprime.c
```

MATLAB creates the binary MEX-file, `yprime.mexmaci64`.

Create an empty Xcode project for debugging

In Xcode,

- Select **File > New > Project**.
- In the Choose a template for your project dialog box, in the **OS X** section, select **Other**.
- Select **Empty**.
- Set **Product Name** to `debug_yprime`.

Add yprime files to the project

To add breakpoints to your source code file, add the `yprime.c` file to the project. You can either drag the file directly into the project or right-click in the project and click **Add files to "debug_yprime"** to add files.

Make sure the **Destination** option, **Copy items into destination group's folder (if needed)**, is unchecked. Unchecking this option enables breakpoints to be added to the file that MATLAB runs.

Click **Finish** to add the file.

Create a scheme

- Select **Product > Scheme > New Scheme...**
- Set **Name** to `debug`.
- Set **Target** to `None`.
- Press **OK**. The scheme editing dialog box opens.
- Set the **Run > Info > Executable** option to the MATLAB executable to use to debug the MEX-file, for example, `MATLAB_R2014a.app`.

Add a symbolic breakpoint

Open the **Debug** menu:

- In Xcode 4.6.x:
Select **Product > Debug > Create Symbolic Breakpoint**.
- In Xcode 5.0 and later:
Select **Debug > Breakpoints > Create Symbolic Breakpoint**.

Set **Symbol** to `UIApplicationMain`.

Click **Add action** to add the following debugger command:

```
process handle -p true -n false -s false SIGSEGV SIGBUS
```

Check **Automatically continue after evaluating**.

Set breakpoints

To add a breakpoint to `yprime.c`, click the gutter next to the line where you want execution to pause. For more information, refer to the Xcode documentation.

Start MATLAB

Click **Run** at the top left of the project window (or type **Command-R**) to start the MATLAB executable. The executable pauses twice; press **Continue**.

Run the binary MEX-file in MATLAB

In MATLAB, change the current folder to the folder with the `yprime` files.

Run the binary MEX-file.

```
yprime(1,1:4)
```

The debugger opens `yprime.c` at the first breakpoint.

Press **Continue**. MATLAB displays:

```
ans =  
    2.0000    8.9685    4.0000   -1.0947
```

Using LLDB

LLDB is the debugger available with Xcode on Mac OS X systems. Refer to the documentation provided with your debugger for more information on its use.

In this procedure, `>>` indicates the MATLAB command prompt, and `%` represents a Mac Terminal prompt. The debugger prompt is `(lldb)`.

- “Debug MEX Without JVM” on page 5-57
- “Debug MEX with JVM” on page 5-59

Debug MEX Without JVM

This example debugs the `yprime` MEX-file without the Java Virtual Machine (JVM). Running MATLAB in this mode minimizes memory usage and improves initial startup speed, but restricts functionality. For example, you cannot use the desktop.

- 1 Compile the source MEX-file with the `-g` option, which builds the file with debugging symbols included. At the Terminal prompt, type:

```
% mex -g yprime.c
```

- 2 Start the `lldb` debugger using the `matlab` function `-D` option:

```
% matlab -Dlldb
```

- 3** Start MATLAB using the `-nojvm` startup flag:

```
(lldb) run -nojvm
```

- 4** In MATLAB, enable debugging with the `dbmex` function and run your MEX-file:

```
>> dbmex on  
>> yprime(1,1:4)
```

The debugger traps a user-defined signal and the prompt returns to `lldb`.

- 5** You are ready to start debugging.

It is often convenient to set a breakpoint at `mexFunction` so you stop at the beginning of the gateway routine.

```
(lldb) b mexFunction
```

- 6** Once you hit a breakpoint, you can use any debugger commands to examine variables, display memory, or inspect registers. To proceed from a breakpoint, type:

```
(lldb) c
```

- 7** After stopping at the last breakpoint, type:

```
(lldb) c
```

`yprime` finishes and MATLAB displays:

```
ans =
```

```
    2.0000    8.9685    4.0000   -1.0947
```

- 8** From the MATLAB prompt, return control to the debugger by typing:

```
>> dbmex stop
```

Or, if you are finished running MATLAB, type:

```
>> quit
```

- 9** When you are finished with the debugger, type:

```
(lldb) q
```

You return to the Terminal prompt.

Debug MEX with JVM

To debug a MEX-file with the JVM, you must first handle `SIGSEGV` and `SIGBUS` process signals. To do this, start MATLAB, stop at the first instruction, and then handle the signals.

- - At the Terminal prompt, compile the MEX-file and start the lldb debugger.

```
% mex -g yprime.c  
% matlab -Dlldb
```
 - Start MATLAB.

```
(lldb) process launch -s
```
 - Tell the process to continue when these process signals occur.

```
(lldb) process handle -p true -n false -s false SIGSEGV SIGBUS
```
 - You can set break points and execute other debugger commands.

Handling Large mxArray

In this section...

“Using the 64-Bit API” on page 5-60

“Building the Binary MEX-File” on page 5-62

“Example” on page 5-62

“Caution Using Negative Values” on page 5-62

“Building Cross-Platform Applications” on page 5-63

Binary MEX-files built on 64-bit platforms can handle 64-bit mxArray. These large data arrays can have up to $2^{48}-1$ elements. The maximum number of elements a sparse mxArray can have is $2^{48}-2$.

Using the following instructions creates platform-independent binary MEX-files as well.

Your system configuration can affect the performance of MATLAB. The 64-bit processor requirement enables you to create the mxArray and access data in it. However, the system memory, in particular the size of RAM and virtual memory, determine the speed at which MATLAB processes the mxArray. The more memory available, the faster the processing.

The amount of RAM also limits the amount of data you can process at one time in MATLAB. For guidance on memory issues, see “Strategies for Efficient Use of Memory” in the Programming Fundamentals documentation. Memory management within source MEX-files can have special considerations, as described in “Memory Management” on page 5-64.

Using the 64-Bit API

The signatures of the API functions shown in the following table use the `mwSize` or `mwIndex` types to work with a 64-bit mxArray. The variables you use in your source code to call these functions must be the correct type.

mxArray Functions Using `mwSize`/`mwIndex`

<code>mxCalcSingleSubscript</code>	<code>mxCreateSparseLogicalMatrix</code> ²
<code>mxMalloc</code>	<code>mxCreateStructArray</code>
<code>mxCopyCharacterToPtr</code> ¹	<code>mxCreateStructMatrix</code>

<code>mxCopyComplex16ToPtr¹</code>	<code>mxGetCell</code>
<code>mxCopyComplex8ToPtr¹</code>	<code>mxGetDimensions</code>
<code>mxCopyInteger1ToPtr¹</code>	<code>mxGetElementSize</code>
<code>mxCopyInteger2ToPtr¹</code>	<code>mxGetField</code>
<code>mxCopyInteger4ToPtr¹</code>	<code>mxGetFieldByNumber</code>
<code>mxCopyPtrToCharacter¹</code>	<code>mxGetIr</code>
<code>mxCopyPtrToComplex16¹</code>	<code>mxGetJc</code>
<code>mxCopyPtrToComplex8¹</code>	<code>mxGetM</code>
<code>mxCopyPtrToInteger1¹</code>	<code>mxGetN</code>
<code>mxCopyPtrToInteger2¹</code>	<code>mxGetNumberOfDimensions</code>
<code>mxCopyPtrToInteger4¹</code>	<code>mxGetNumberOfElements</code>
<code>mxCopyPtrToPtrArray¹</code>	<code>mxGetNzmax</code>
<code>mxCopyPtrToReal14¹</code>	<code>mxGetProperty</code>
<code>mxCopyPtrToReal18¹</code>	<code>mxGetString</code>
<code>mxCopyReal14ToPtr¹</code>	<code>mxMalloc</code>
<code>mxCopyReal18ToPtr¹</code>	<code>mxRealloc</code>
<code>mxCreateCellArray</code>	<code>mxSetCell</code>
<code>mxCreateCellMatrix</code>	<code>mxSetDimensions</code>
<code>mxCreateCharArray</code>	<code>mxSetField</code>
<code>mxCreateCharMatrixFromStrings</code>	<code>mxSetFieldByNumber</code>
<code>mxCreateDoubleMatrix</code>	<code>mxSetIr</code>
<code>mxCreateLogicalArray²</code>	<code>mxSetJc</code>
<code>mxCreateLogicalMatrix²</code>	<code>mxSetM</code>
<code>mxCreateNumericArray</code>	<code>mxSetN</code>
<code>mxCreateNumericMatrix</code>	<code>mxSetNzmax</code>
<code>mxCreateSparse</code>	<code>mxSetProperty</code>

¹Fortran function only.

²C function only.

Functions in this API use the `mwIndex` and `mwSize` types.

Building the Binary MEX-File

Use the `mex` build script option `-largeArrayDims` with the 64-bit API.

Example

The example, `arraySize.c` in `matlabroot/extern/examples/mex`, shows memory requirements of large `mxAArrays`. To see the example, open the file in MATLAB Editor.

This function requires one positive scalar numeric input, which it uses to create a square matrix. It checks the size of the input to make sure that your system can theoretically create a matrix of this size. If the input is valid, it displays the size of the `mxAArray` in kilobytes.

Build this MEX-file.

```
mex -largeArrayDims arraySize.c
```

Run the MEX-file.

```
arraySize(2^10)
```

```
Dimensions: 1024 x 1024  
Size of array in kilobytes: 1024
```

If your system does not have enough memory to create the array, MATLAB displays an `Out of memory error`.

You can experiment with this function to test the performance and limits of handling large arrays on your system.

Caution Using Negative Values

When using the 64-bit API, `mwSize` and `mwIndex` are equivalent to `size_t` in C/C++. This type is unsigned, unlike `int`, which is the type used in the 32-bit API. Be careful not to pass any negative values to functions that take `mwSize` or `mwIndex` arguments.

Do not cast negative `int` values to `mwSize` or `mwIndex`; the returned value cannot be predicted. Instead, change your code to avoid using negative values.

Building Cross-Platform Applications

If you develop cross-platform applications (programs that can run on both 32- and 64-bit architectures), you must pay attention to the upper limit of values you use for `mwSize` and `mwIndex`. The 32-bit application reads these values and assigns them to variables declared as `int` in C/C++. Be careful to avoid assigning a large `mwSize` or `mwIndex` value to an `int` or other variable that might be too small.

Memory Management

In this section...

“Automatic Cleanup of Temporary Arrays” on page 5-64

“Example” on page 5-65

“Persistent Arrays” on page 5-65

Automatic Cleanup of Temporary Arrays

When a MEX-file returns control to MATLAB, it returns the results of its computations in the output arguments—the `mxArrays` contained in the left-side arguments `plhs[]`. MATLAB destroys any `mxArray` created by the MEX-file that is not in this argument list. In addition, MATLAB frees any memory that was allocated in the MEX-file using the `mxMalloc`, `mxRealloc`, or `mxMalloc` functions.

MathWorks recommends that MEX-file functions destroy their own temporary arrays and free their own dynamically allocated memory. It is more efficient to perform this cleanup in the source MEX-file than to rely on the automatic mechanism. However, there are several circumstances in which the MEX-file does not reach its normal return statement.

The normal return is not reached if:

- MATLAB calls `mexErrMsgTxt`.
- MATLAB calls `mexCallMATLAB` and the function being called creates an error. (A source MEX-file can trap such errors by using the `mexCallMATLABWithTrap` function, but not all MEX-files necessarily need to trap errors.)
- The user interrupts the binary MEX-file's execution using **Ctrl+C**.
- The binary MEX-file runs out of memory. The MATLAB out-of-memory handler terminates the MEX-file.

For the first two cases, a MEX-file programmer can ensure safe cleanup of temporary arrays and memory before returning, but not in the last two cases. The automatic cleanup mechanism is necessary to prevent memory leaks in those cases.

You must use the MATLAB-provided functions, such as `mxMalloc` and `mxFree`, to manage memory. Do not use the standard C library counterparts; doing so can produce unexpected results, including program termination.

Example

This example shows how to allocate memory for variables in a MEX-file. For example, if the first input to your function (`prhs[0]`) is a string, in order to manipulate the string, create a buffer `buf` of size `buflen`. The following statements declare these variables:

```
char *buf;  
int buflen;
```

The size of the buffer depends the number of dimensions of your input array and the size of the data in the array. This statement calculates the size of `buflen`:

```
buflen = mxGetN(prhs[0])*sizeof(mxChar)+1;
```

Next, allocate memory for `buf`:

```
buf = mxMalloc(buflen);
```

At the end of the program, if you do not return `buf` as a `plhs` output parameter, then free its memory as follows:

```
mxFree(buf);
```

Before exiting the MEX-file, destroy any temporary arrays and free any dynamically allocated memory, except if such an `mxArray` is returned in the output argument list, returned by `mexGetVariablePtr`, or used to create a structure. Also, never delete input arguments.

Use `mxFree` to free memory allocated by the `mxMalloc`, `mxMalloc`, or `mxRealloc` functions. Use `mxDestroyArray` to free memory allocated by the `mxCreate*` functions.

Persistent Arrays

You can exempt an array, or a piece of memory, from the MATLAB automatic cleanup by calling `mexMakeArrayPersistent` or `mexMakeMemoryPersistent`. However, if a MEX-file creates such persistent objects, there is a danger that a memory leak could occur if the MEX-file is cleared before the persistent object is properly destroyed. To prevent memory leaks, use the `mexAtExit` function to register a function to free the memory for objects created using these functions.

For example, here is a simple source MEX-file that creates a persistent array and properly disposes of it.

```
#include "mex.h"

static int initialized = 0;
static mxArray *persistent_array_ptr = NULL;

void cleanup(void) {
    mexPrintf("MEX-file is terminating, destroying array\n");
    mxDestroyArray(persistent_array_ptr);
}

void mexFunction(int nlhs,
                 mxArray *plhs[],
                 int nrhs,
                 const mxArray *prhs[])
{
    if (!initialized) {
        mexPrintf("MEX-file initializing, creating array\n");

        /* Create persistent array and register its cleanup. */
        persistent_array_ptr = mxCreateDoubleMatrix(1, 1, mxREAL);
        mexMakeArrayPersistent(persistent_array_ptr);
        mexAtExit(cleanup);
        initialized = 1;

        /* Set the data of the array to some interesting value. */
        *mxGetPr(persistent_array_ptr) = 1.0;
    } else {
        mexPrintf("MEX-file executing; value of first array element is %g\n",
                 *mxGetPr(persistent_array_ptr));
    }
}
```

See Also

[mexAtExit](#) | [mexMakeArrayPersistent](#) | [mxMalloc](#) | [mxFree](#)

More About

- “Memory Allocation”
- “Memory Management Issues” on page 4-67

Handling Large File I/O

In this section...

- “Prerequisites to Using 64-Bit I/O” on page 5-67
- “Specifying Constant Literal Values” on page 5-69
- “Opening a File” on page 5-69
- “Printing Formatted Messages” on page 5-70
- “Replacing fseek and ftell with 64-Bit Functions” on page 5-70
- “Determining the Size of an Open File” on page 5-71
- “Determining the Size of a Closed File” on page 5-72

Prerequisites to Using 64-Bit I/O

MATLAB supports the use of 64-bit file I/O operations in your MEX-file programs. You can read and write data to files that are up to and greater than 2 GB (2^{31-1} bytes) in size. Some operating systems or compilers do not support files larger than 2 GB. The following topics describe how to use 64-bit file I/O in your MEX-file programs.

- “Header File” on page 5-67
- “Type Declarations” on page 5-67
- “Functions” on page 5-68

Header File

Header file `io64.h` defines many of the types and functions required for 64-bit file I/O. The statement to include this file must be the *first* `#include` statement in your source file and must also precede any system header include statements:

```
#include "io64.h"
#include "mex.h"
```

Type Declarations

To declare variables used in 64-bit file I/O, use the following types.

MEX Type	Description	POSIX
<code>fpos_t</code>	Declares a 64-bit <code>int</code> type for <code>setFilePos()</code> and	<code>fpos_t</code>

MEX Type	Description	POSIX
	<code>getFilePos()</code> . Defined in <code>io64.h</code> .	
<code>int64_T</code> , <code>uint64_T</code>	Declares 64-bit signed and unsigned integer types. Defined in <code>tmwtypes.h</code> .	<code>long</code> , <code>long</code>
<code>structStat</code>	Declares a structure to hold the size of a file. Defined in <code>io64.h</code> .	<code>struct stat</code>
FMT64	Used in <code>mexPrintf</code> to specify length within a format specifier such as <code>%d</code> . See example in the section “Printing Formatted Messages” on page 5-70. FMT64 is defined in <code>tmwtypes.h</code> .	<code>%lld</code>
LL, LLU	Suffixes for literal <code>int</code> constant 64-bit values (C Standard ISO [®] /IEC 9899:1999(E) Section 6.4.4.1). Used only on UNIX systems.	LL, LLU

Functions

Use the following functions for 64-bit file I/O. All are defined in the header file `io64.h`.

Function	Description	POSIX
<code>fileno()</code>	Gets a file descriptor from a file pointer	<code>fileno()</code>
<code>fopen()</code>	Opens the file and obtains the file pointer	<code>fopen()</code>
<code>getFileFstat()</code>	Gets the file size of a given file pointer	<code>fstat()</code>
<code>getFilePos()</code>	Gets the file position for the next I/O	<code>fgetpos()</code>
<code>getFileStat()</code>	Gets the file size of a given file name	<code>stat()</code>
<code>setFilePos()</code>	Sets the file position for the next I/O	<code>fsetpos()</code>

Specifying Constant Literal Values

To assign signed and unsigned 64-bit integer literal values, use type definitions `int64_T` and `uint64_T`.

On UNIX systems, to assign a literal value to an integer variable where the value to be assigned is greater than $2^{31} - 1$ signed, you must suffix the value with `LL`. If the value is greater than $2^{32} - 1$ unsigned, then use `LLU` as the suffix. These suffixes apply only to UNIX systems and are considered invalid on the Microsoft Windows systems.

Note: The `LL` and `LLU` suffixes are not required for hardcoded (literal) values less than `G` ($2^{31} - 1$), even if they are assigned to a 64-bit `int` type.

The following example declares a 64-bit integer variable initialized with a large literal `int` value, and two 64-bit integer variables:

```
void mexFunction(int nlhs, mxArray *plhs[], int nrhs,
                 const mxArray *prhs[])
{
    #if defined(_MSC_VER) || defined(__BORLANDC__)    /* Windows */
        int64_T large_offset_example = 9000222000;
    #else                                           /* UNIX */
        int64_T large_offset_example = 9000222000LL;
    #endif

    int64_T offset = 0;
    int64_T position = 0;
```

Opening a File

To open a file for reading or writing, use the C/C++ `fopen` function as you normally would. As long as you have included `io64.h` at the start of your program, `fopen` works correctly for large files. No changes at all are required for `fread`, `fwrite`, `fprintf`, `fscanf`, and `fclose`.

The following statements open an existing file for reading and updating in binary mode.

```
fp = fopen(filename, "r+b");
if (NULL == fp)
```

```
{
/* File does not exist. Create new file for writing
 * in binary mode.
 */
fp = fopen(filename, "wb");
if (NULL == fp)
    {
    sprintf(str, "Failed to open/create test file '%s'",
            filename);
    mexErrMsgTxt(str);
    return;
    }
else
    {
    mexPrintf("New test file '%s' created\n",filename);
    }
}
else mexPrintf("Existing test file '%s' opened\n",filename);
```

Printing Formatted Messages

You cannot print 64-bit integers using the `%d` conversion specifier. Instead, use `FMT64` to specify the appropriate format for your platform. `FMT64` is defined in the header file `tmwtypes.h`. The following example shows how to print a message showing the size of a large file:

```
int64_T large_offset_example = 9000222000LL;

mexPrintf("Example large file size: %" FMT64 "d bytes.\n",
          large_offset_example);
```

Replacing `fseek` and `ftell` with 64-Bit Functions

The ANSI C `fseek` and `ftell` functions are not 64-bit file I/O capable on most platforms. The functions `setFilePos` and `getFilePos`, however, are defined as the corresponding POSIX[®] `fsetpos` and `fgetpos`, (or `fsetpos64` and `fgetpos64`), as required by your platform/OS. These functions are 64-bit file I/O capable on all platforms.

The following example shows how to use `setFilePos` instead of `fseek`, and `getFilePos` instead of `ftell`. It uses `getFileFstat` to find the size of the file, and then uses `setFilePos` to seek to the end of the file to prepare for adding data at the end of the file.

Note: Although the `offset` parameter to `setFilePos` and `getFilePos` is really a pointer to a signed 64-bit integer, `int64_T`, it must be cast to an `fpos_T*`. The `fpos_T` type is defined in `io64.h` as the appropriate `fpos64_t` or `fpos_t`, as required by your platform/OS.

```
getFileFstat(fileno(fp), &statbuf);
fileSize = statbuf.st_size;
offset = fileSize;

setFilePos(fp, (fpos_T*) &offset);
getFilePos(fp, (fpos_T*) &position );
```

Unlike `fseek`, `setFilePos` supports only absolute seeking relative to the beginning of the file. If you want to do a relative seek, first call `getFileFstat` to obtain the file size, and then convert the relative offset to an absolute offset that you can pass to `setFilePos`.

Determining the Size of an Open File

To get the size of an open file:

- Refresh the record of the file size stored in memory using `getFilePos` and `setFilePos`.
- Retrieve the size of the file using `getFileFstat`.

Refreshing the File Size Record

Before attempting to retrieve the size of an open file, first refresh the record of the file size residing in memory. If you skip this step on a file that is opened for writing, the file size returned might be incorrect or 0.

To refresh the file size record, seek to any offset in the file using `setFilePos`. If you do not want to change the position of the file pointer, you can seek to the current position in the file. This example obtains the current offset from the start of the file. It then seeks to the current position to update the file size without moving the file pointer.

```
getFilePos( fp, (fpos_T*) &position);
setFilePos( fp, (fpos_T*) &position);
```

Getting the File Size

The `getFileFstat` function takes a file descriptor input argument. Use `fileno` function to get the file pointer of the open file. `getFileFstat` returns the size of that file in bytes in the `st_size` field of a `structStat` structure.

```
structStat statbuf;
int64_T fileSize = 0;

if (0 == getFileFstat(fileno(fp), &statbuf))
{
    fileSize = statbuf.st_size;
    mexPrintf("File size is %" FMT64 "d bytes\n", fileSize);
}
```

Determining the Size of a Closed File

The `getFileStat` function takes the file name of a closed file as an input argument. `getFileStat` returns the size of the file in bytes in the `st_size` field of a `structStat` structure.

```
structStat statbuf;
int64_T fileSize = 0;

if (0 == getFileStat(filename, &statbuf))
{
    fileSize = statbuf.st_size;
    mexPrintf("File size is %" FMT64 "d bytes\n", fileSize);
}
```


Fortran MEX-Files

- “Components of Fortran MEX-File” on page 6-2
- “MATLAB Fortran API Libraries” on page 6-5
- “Data Flow in Fortran MEX-Files” on page 6-8
- “User Messages” on page 6-11
- “Error Handling” on page 6-12
- “Build Fortran MEX-File” on page 6-13
- “Create Fortran Source MEX-File” on page 6-14
- “Set Up Fortran Examples” on page 6-19
- “Pass Scalar Values” on page 6-20
- “Pass Strings” on page 6-21
- “Pass Arrays of Strings” on page 6-22
- “Pass Matrices” on page 6-23
- “Pass Integers” on page 6-24
- “Pass Multiple Inputs or Outputs” on page 6-25
- “Handle Complex Data” on page 6-26
- “Dynamically Allocate Memory” on page 6-27
- “Handle Sparse Matrices” on page 6-28
- “Call MATLAB Functions from Fortran MEX-Files” on page 6-29
- “Debug Fortran Source MEX-Files” on page 6-31
- “Handling Large mxArray” on page 6-34
- “Memory Management” on page 6-37
- “MATLAB Supports Fortran 77” on page 6-38

Components of Fortran MEX-File

In this section...

“mexFunction Gateway Routine” on page 6-2

“Naming the MEX-File” on page 6-2

“Difference Between .f and .F Files” on page 6-2

“Required Parameters” on page 6-3

“Managing Input and Output Parameters” on page 6-3

“Validating Inputs” on page 6-4

“Computational Routine” on page 6-4

mexFunction Gateway Routine

The *gateway routine* is the entry point to the MEX-file. It is through this routine that MATLAB accesses the rest of the routines in your MEX-files. The name of the gateway routine is `mexFunction`. It takes the place of the main program in your source code.

Naming the MEX-File

The name of the source file containing `mexFunction` is the name of your MEX-file, and, hence, the name of the function you call in MATLAB. Name your Fortran source file with an uppercase `.F` file extension.

The file extension of the binary MEX-file is platform-dependent. You find the file extension using the `mexext` function, which returns the value for the current machine.

Difference Between .f and .F Files

To ensure your Fortran MEX-file is platform independent, use an uppercase `.F` file extension.

Fortran compilers assume source files using a lowercase `.f` file extension have been preprocessed. On most platforms, `mex` makes sure that the file is preprocessed regardless of the file extension. However, on Apple Macintosh platforms, `mex` cannot force preprocessing.

Required Parameters

The Fortran signature for `mexfunction` is:

```
subroutine mexFunction(nlhs, plhs, nrhs, prhs)
integer nlhs, nrhs
mwpointer plhs(*), prhs(*)
```

Place this subroutine after your computational routine and any other subroutines in your source file.

The following table describes the parameters for `mexFunction`.

Parameter	Description
<code>prhs</code>	Array of right-side input arguments.
<code>plhs</code>	Array of left-side output arguments.
<code>nrhs</code>	Number of right-side arguments, or the size of the <code>prhs</code> array.
<code>nlhs</code>	Number of left-side arguments, or the size of the <code>plhs</code> array.

Declare `prhs` and `plhs` as type `mwPointer`, which means they point to MATLAB arrays. They are vectors that contain pointers to the arguments of the MEX-file.

You can think of the name `prhs` as representing the “parameters, right-hand side,” that is, the input parameters. Likewise, `plhs` represents the “parameters, left side,” or output parameters.

Managing Input and Output Parameters

Input parameters (found in the `prhs` array) are read-only; do not modify them in your MEX-file. Changing data in an input parameter can produce undesired side effects.

You also must take care when using an input parameter to create output data or any data used locally in your MEX-file. If you want to copy an input array into an output array, for example `plhs(1)`, call the `mxDuplicateArray` function to make a copy of the input array. For example:

```
plhs(1) = mxDuplicateArray(prhs(1))
```

For more information, see the troubleshooting topic “Incorrectly Constructing a Cell or Structure `mxArray`” on page 4-68.

Validating Inputs

For a list of functions to validate inputs to your subroutines, see the Matrix Library category, “Validate Data”. The `mxIsClass` function is a general-purpose way to test an `mxArray`.

Computational Routine

The *computational routine* contains the code for performing the computations you want implemented in the binary MEX-file. Although not required, consider writing the gateway routine, `mexFunction`, to call a computational routine. To validate input parameters and to convert them into the types required by the computational routine, use the `mexFunction` code as a wrapper.

If you write separate gateway and computational routines, you can combine them into one source file or into separate files. If you use separate files, the file containing `mexFunction` must be the first source file listed in the `mex` command.

See Also

`mexext` | `mexFunction` | `mwPointer` | `mxDuplicateArray` | `mxIsClass`

MATLAB Fortran API Libraries

In this section...

“Matrix Library” on page 6-5

“MEX Library” on page 6-5

“Preprocessor Macros” on page 6-5

“Using the Fortran %val Construct” on page 6-6

The Matrix Library and the MEX Library describe functions you can use in your gateway and computational routines that interact with MATLAB programs and the data in the MATLAB workspace. These libraries are part of the MATLAB C/C++ and Fortran API Reference library.

To use these functions, include the `fintrf` header, which declares the entry point and interface routines. Put this statement in your source file:

```
#include "fintrf.h"
```

Matrix Library

Use Fortran Matrix Library functions to pass *mxArray*, the type MATLAB uses to store arrays, to and from MEX-files. For examples using these functions, see *matlabroot/extern/examples/mx*.

MEX Library

Use MEX Library functions to perform operations in the MATLAB environment. For a list of the Fortran functions, see “Fortran Source Files”. For examples using these functions, see *matlabroot/extern/examples/mex*.

Unlike MATLAB functions, MEX-file functions do not have their own variable workspace. MEX-file functions operate in the caller workspace. To evaluate a string, use `mexEvalString`. To get and put variables into the caller workspace, use the `mexGetVariable` and `mexPutVariable` functions.

Preprocessor Macros

The Matrix and MEX libraries use the MATLAB *preprocessor macros* `mwSize` and `mwIndex` for cross-platform flexibility. `mwSize` represents size values, such as array

dimensions and number of elements. `mwIndex` represents index values, such as indices into arrays.

MATLAB has an extra preprocessor macro for Fortran files, `mwPointer`. MATLAB uses a unique data type, the `mxArray`. Because you cannot create a data type in Fortran, MATLAB passes a special identifier, created by the `mwPointer` preprocessor macro, to a Fortran program. This is how you get information about an `mxArray` in a native Fortran data type. For example, you can find out the size of the `mxArray`, determine whether it is a string, and look at the contents of the array. Use `mwPointer` to build platform-independent code.

The Fortran preprocessor converts `mwPointer` to `integer*4` when building binary MEX-files on 32-bit platforms and to `integer*8` when building on 64-bit platforms.

Note: Declaring a pointer to be the incorrect size might cause your program to crash.

Using the Fortran `%val` Construct

The Fortran `%val(arg)` construct specifies that an argument, *arg*, is to be passed by value, instead of by reference. Most, but not all, Fortran compilers support the `%val` construct.

If your compiler does not support the `%val` construct, copy the array values into a temporary true Fortran array using the `mxCopy*` routines (for example, `mxCopyPtrToReal8`).

`%val` Construct Example

If your compiler supports the `%val` construct, you can use routines that point directly to the data (that is, the pointer returned by `mxGetPr` or `mxGetPi`). You can use `%val` to pass the contents of this pointer to a subroutine, where it is declared as a Fortran double-precision matrix.

For example, consider a gateway routine that calls its computational routine, `yprime`, by:

```
call yprime(%val(y), %val(t), %val(y))
```

If your Fortran compiler does not support the `%val` construct, you would replace the call to the computational subroutine with:

```
C Copy array pointers to local arrays.  
    call mxCopyPtrToReal8(t, tr, 1)  
    call mxCopyPtrToReal8(y, yr, 4)  
C  
C Call the computational subroutine.  
    call yprime(ypr, tr, yr)  
C  
C Copy local array to output array pointer.  
    call mxCopyReal8ToPtr(ypr, yp, 4)
```

You must also add the following declaration line to the top of the gateway routine:

```
real*8 ypr(4), tr, yr(4)
```

If you use `mxCopyPtrToReal8` or any of the other `mxCopy*` routines, the size of the arrays declared in the Fortran gateway routine must be greater than or equal to the size of the inputs to the MEX-file coming in from MATLAB. Otherwise, `mxCopyPtrToReal8` does not work correctly.

See Also

“Fortran Matrix Library API” | “MEX Library” | `mwIndex` | `mwPointer` | `mwSize` | `mxArray`

Data Flow in Fortran MEX-Files

In this section...

“Showing Data Input and Output” on page 6-8

“Gateway Routine Data Flow Diagram” on page 6-9

Showing Data Input and Output


Suppose your MEX-file `myFunction` has two input arguments and one output argument. The MATLAB syntax is `[X] = myFunction(Y, Z)`. To call `myFunction` from MATLAB, type:

```
X = myFunction(Y, Z);
```

The MATLAB interpreter calls `mexFunction`, the gateway routine to `myFunction`, with the following arguments:

```
nlhs = 1
```

```
nrhs = 2
```



Your input is `prhs`, a two-element array (`nrhs = 2`). The first element is a pointer to an `mxAarray` named `Y` and the second element is a pointer to an `mxAarray` named `Z`.

Your output is `plhs`, a one-element array (`nlhs = 1`) where the single element is a `null` pointer. The parameter `plhs` points at nothing because the output `X` is not created until the subroutine executes.

The gateway routine creates the output array and sets a pointer to it in `plhs[0]`. If the routine does not assign a value to `plhs[0]` but you assign an output value to the function when you call it, MATLAB generates an error.

Note: It is possible to return an output value even if `nlhs = 0`, which corresponds to returning the result in the `ans` variable.


Gateway Routine Data Flow Diagram

The following MEX Cycle diagram shows how inputs enter a MEX-file, what functions the gateway routine performs, and how outputs return to MATLAB.

In this example, the syntax of the MEX-file `func` is `[C, D] = func(A,B)`. In the figure, a call to `func` tells MATLAB to pass variables `A` and `B` to your MEX-file. `C` and `D` are left unassigned.

The gateway routine uses the `mxCreate*` functions to create the MATLAB arrays for your output arguments. It sets `plhs[0]` and `plhs[1]` to the pointers to the newly created MATLAB arrays. It uses the `mxGet*` functions to extract your data from your input arguments `prhs[0]` and `prhs[1]`. Finally, it calls your computational routine, passing the input and output data pointers as function parameters.

MATLAB assigns `plhs[0]` to `C` and `plhs[1]` to `D`.



Fortran MEX Cycle

User Messages

To print a string in the MATLAB Command Window, use the `mexPrintf` function. To print error and warning information in the Command Window, use the `mexErrMsgIdAndTxt` and `mexWarnMsgIdAndTxt` functions.

For example, the following code snippet displays an error message.

```
parameter(maxbuf = 100)
character*100 input_buf

if (status = mxGetString(prhs(1), input_buf, maxbuf) .ne. 0) then
    call mexErrMsgIdAndTxt ('MATLAB:myfunc:readError',
+                          'Error reading string.')
endif
```

See Also

`mexErrMsgIdAndTxt` | `mexPrintf` | `mexWarnMsgIdAndTxt`

Error Handling

The `mexErrMsgIdAndTxt` function prints error information and terminates your binary MEX-file. For an example, see the following code in `matlabroot/extern/examples/mx/mxcreatecellmatrixf.F`.

```
C      Check for proper number of input and output arguments
      if (nrhs .lt. 1) then
          call mexErrMsgIdAndTxt( 'MATLAB:mxcreatecellmatrixf:minrhs',
+          'One input argument required.')
      end if
```

The `mexWarnMsgIdAndTxt` function prints information, but does not terminate the MEX-file. For an example, see the following code in `matlabroot/extern/examples/mx/mxgetepsf.F`.

```
C      Check for equality within eps
      do 20 j=1,elements
          if ((abs(first(j) - second(j))).gt.(abs(second(j)*eps))) then
              call mexWarnMsgIdAndTxt(
+              'MATLAB:mxgetepsf:NotEqual',
+              'Inputs are not the same within eps.')
              go to 21
          end if
      20 continue
```

See Also

`mexErrMsgIdAndTxt` | `mexWarnMsgIdAndTxt`

Related Examples

- `mxcreatecellmatrixf.F`
- `mxgetepsf.F`

Build Fortran MEX-File

This example shows how to build the example MEX-file, `timestwo`. Use this example to verify the build configuration for your system.

To build a code example, first copy the file to a writable folder, such as `c:\work`, on your path:

```
copyfile(fullfile(matlabroot, 'extern', 'examples', 'refbook', 'timestwo.F'), '.', 'f')
```

Use the `mex` function to build the MEX-file.

```
mex timestwo.F
```

This command creates the file `timestwo.ext`, where `ext` is the value returned by the `mexext` function.

The `timestwo` function takes a scalar input and doubles it. Call `timestwo` as if it were a MATLAB function.

```
timestwo(4)
ans =
     8
```

See Also

`mex` | `mexext`

More About

- “Handling Large mxArrays” on page 5-60
- “Upgrade MEX-Files to Use 64-Bit API” on page 4-36

Create Fortran Source MEX-File

This example shows how to write a MEX-file to call a Fortran subroutine, `timestwo`, in MATLAB using a MATLAB matrix.

`timestwo` multiplies an n -dimensional array, `x_input`, by 2, and returns the results in array, `y_output`.

```
subroutine timestwo(y_output, x_input)
  real*8 x_input, y_output

  y_output = 2.0 * x_input
  return
end
```

Create Source File

Open MATLAB Editor, create a file, and document the MEX-file with the following information.

```
C=====
C   timestwo.f
C   Computational function that takes a scalar and doubles it.
C   This is a MEX-file for MATLAB.
C=====
```

Add the Fortran header file, `fintrf.h`, containing the MATLAB API function declarations.

```
#include "fintrf.h"
```

Save the file on your MATLAB path, for example, in `c:\work`, and name it `timestwo.F`. The name of your MEX-file is `timestwo`.

Create Gateway Routine

MATLAB uses the gateway routine, `mexfunction`, as the entry point to a Fortran subroutine. Add the following `mexFunction` code.

```
C   Gateway routine
C   subroutine mexFunction(nlhs, plhs, nrhs, prhs)

C   Declarations
```

```
C    Statements
```

```
    return
    end
```

Add the following statement to your `mexfunction` subroutine to force you to declare all variables.

```
implicit none
```

Explicit type declaration is necessary for 64-bit arrays.

Declare `mexfunction` Arguments

To declare `mxArray` variables, use the MATLAB type, `mwPointer`. Add this code after the `Declarations` statement.

```
C    mexFunction arguments:
    mwPointer plhs(*), prhs(*)
    integer nlhs, nrhs
```

Declare Functions and Local Variables

- Declare the symbolic names and types of MATLAB API functions used in this MEX-file.

```
C    Function declarations:
    mwPointer mxGetPr
    mwPointer mxCreateDoubleMatrix
    integer mxIsNumeric
    mwPointer mxGetM, mxGetN
```

To determine the type of a function, refer to the MATLAB API function reference documentation. For example, see the documentation for `mxGetPr`.

- Declare local variables for the `mexfunction` arguments.

```
C    Pointers to input/output mxArray:
    mwPointer x_ptr, y_ptr
```

- Declare matrix variables.

```
C    Array information:
    mwPointer mrows, ncols
    mwSize size
```

Verify MEX-File Input and Output Arguments

Verify the number of MEX-file input and output arguments using the `nrhs` and `nlhs` arguments. Add these statements to the `mexfunction` code block.

```
C    Check for proper number of arguments.
      if(nrhs .ne. 1) then
        call mexErrMsgIdAndTxt ('MATLAB:timestwo:nInput',
+                               'One input required.')
      elseif(nlhs .gt. 1) then
        call mexErrMsgIdAndTxt ('MATLAB:timestwo:nOutput',
+                               'Too many output arguments.')
      endif
```

Verify the input argument type using the `prhs` argument.

```
C    Check that the input is a number.
      if(mxIsNumeric(prhs(1)) .eq. 0) then
        call mexErrMsgIdAndTxt ('MATLAB:timestwo:NonNumeric',
+                               'Input must be a number.')
      endif
```

Create Computational Routine

Add the `timestwo` code. This subroutine is your computational routine, the source code that performs the functionality you want to use in MATLAB.

```
C    Computational routine

      subroutine timestwo(y_output, x_input)
      real*8 x_input, y_output

      y_output = 2.0 * x_input
      return
      end
```

A computational routine is optional. Alternatively, you can place the code within the `mexfunction` function block.

Declare Variables for Computational Routine

Put the following variable declarations in `mexFunction`.

```
C    Arguments for computational routine:
```



```
real*8 x_input, y_output
```

Read Input Array

To point to the input matrix data, use the `mxGetPr` function.

```
x_ptr = mxGetPr(prhs(1))
```

To create a Fortran array, `x_input`, use the `mxCopyPtrToReal8` function.

```
C    Get the size of the input array.
    mrows = mxGetM(prhs(1))
    ncols = mxGetN(prhs(1))
    size = mrows*ncols

C    Create Fortran array from the input argument.
    call mxCopyPtrToReal8(x_ptr,x_input,size)
```

Prepare Output Data

To create the output argument, `plhs(1)`, use the `mxCreateDoubleMatrix` function.

```
C    Create matrix for the return argument.
    plhs(1) = mxCreateDoubleMatrix(mrows,ncols,0)
```

Use the `mxGetPr` function to assign the `y_ptr` argument to `plhs(1)`.

```
y_ptr = mxGetPr(plhs(1))
```

Perform Calculation

Pass the arguments to `timestwo`.

```
C    Call the computational subroutine.
    call timestwo(y_output, x_input)
```

Copy Results to Output Argument

```
C    Load the data into y_ptr, which is the output to MATLAB.
    call mxCopyReal8ToPtr(y_output,y_ptr,size)
```

View Complete Source File

Compare your source file with `timestwo.F`, located in the `matlabroot/extern/examples/refbook` folder. Open the file in the editor.

Build Binary MEX-File

At the MATLAB command prompt, build the binary MEX-file.

```
mex timestwo.F
```

Test the MEX-File

```
x = 99;  
y = timestwo(x)  
  
y =  
    198
```

See Also

[mexfunction](#) | [mwPointer](#) | [mwSize](#) | [mxCreateDoubleMatrix](#) | [mxGetM](#) | [mxGetN](#)
| [mxGetPr](#) | [mxIsNumeric](#)

Related Examples

- [timestwo.F](#)

Set Up Fortran Examples

The “Fortran Matrix Library API” provides a set of Fortran routines that handle the types supported by MATLAB. For each data type, there is a specific set of functions that you can use for data manipulation.

Source code for Fortran examples is located in the *matlabroot/extern/examples/refbook* folder of your MATLAB installation. To build an example, first copy the file to a writable folder, such as `c:\work`, on your path:

```
copyfile(fullfile(matlabroot,'extern','examples','refbook','filename.F'),'.','f')
```

where *filename* is the name of the example.

Make sure that you have a Fortran compiler installed. Then, at the MATLAB command prompt, type:

```
mex filename.F
```

where *filename* is the name of the example.

This section looks at source code for the examples. Unless otherwise specified, the term “MEX-file” refers to a source file.

For a list of MEX example files available with MATLAB, see “Table of MEX-File Source Code Files”.

Pass Scalar Values

Here is a Fortran computational routine that takes a scalar and doubles it.

```
      subroutine timestwo(y, x)
      real*8 x, y
C
      y = 2.0 * x
      return
      end
```

To see the same function written in the MEX-file format (`timestwo.F`), open the file in MATLAB Editor.

To build this example, at the command prompt type:

```
mex timestwo.F
```

This command creates the binary MEX-file called `timestwo` with an extension corresponding to the machine type on which you are running. You can now call `timestwo` like a MATLAB function:

```
x = 2;
y = timestwo(x)

y =
     4
```

Pass Strings

Passing strings from MATLAB to a Fortran MEX-file is straightforward. The program `revord.F` accepts a string and returns the characters in reverse order. To see the example `revord.F`, open the file in MATLAB Editor.

After checking for the correct number of inputs, the gateway routine `mexFunction` verifies that the input was a row vector string. It then finds the size of the string and places the string into a Fortran character array. For character strings, it is not necessary to copy the data into a Fortran character array using `mxCopyPtrToCharacter`. (`mxCopyPtrToCharacter` is a convenience function for working with MAT-files.)

To build this example, at the command prompt type:

```
mex revord.F
```

Type:

```
x = 'hello world';  
y = revord(x)
```

```
y =
```

```
dlrow olleh
```

Pass Arrays of Strings

Passing arrays of strings adds a complication to the example “Pass Strings” on page 6-21. Because MATLAB stores elements of a matrix by column instead of by row, the size of the string array must be correctly defined in the Fortran MEX-file. The key point is that the row and column sizes as defined in MATLAB must be reversed in the Fortran MEX-file. So, when returning to MATLAB, the output matrix must be transposed.

This example places a string array/character matrix into MATLAB as output arguments rather than placing it directly into the workspace.

To build this example, at the command prompt type:

```
mex passstr.F
```

Type:

```
passstr
```

to create the 5-by-15 `mystring` matrix. You need to do some further manipulation. The original string matrix is 5-by-15. Because of the way MATLAB reads and orients elements in matrices, the size of the matrix must be defined as `M=15` and `N=5` in the MEX-file. After the matrix is put into MATLAB, the matrix must be transposed. The program `passstr.F` illustrates how to pass a character matrix. To see the code `passstr.F`, open the file in MATLAB Editor.

Type:

```
passstr
```

```
ans =
```

```
MATLAB  
The Scientific  
Computing  
Environment  
by TMM, Inc.
```

Pass Matrices

In MATLAB, you can pass matrices into and out of MEX-files written in Fortran. You can manipulate the MATLAB arrays by using `mxGetPr` and `mxGetPi` to assign pointers to the real and imaginary parts of the data stored in the MATLAB arrays. You can create new MATLAB arrays from within your MEX-file by using `mxCreateDoubleMatrix`.

The example `matsq.F` takes a real 2-by-3 matrix and squares each element. To see the source code, open the file in MATLAB Editor.

After performing error checking to ensure that the correct number of inputs and outputs was assigned to the gateway subroutine and to verify the input was in fact a numeric matrix, `matsq.F` creates a matrix. The matrix is copied to a Fortran matrix using `mxCopyPtrToReal8`. Now the computational subroutine can be called, and the return argument is placed into `y_ptr`, the pointer to the output, using `mxCopyReal8ToPtr`.

To build this example, at the command prompt type:

```
mex matsq.F
```

For a 2-by-3 real matrix, type:

```
x = [1 2 3; 4 5 6];  
y = matsq(x)
```

```
y =  
    1     4     9  
   16    25    36
```

See Also

`mxCreateDoubleMatrix` | `mxGetPi` | `mxGetPr`

Pass Integers

The example `matsqint8.F` accepts a matrix of MATLAB type `int8` and squares each element. To see the source code, open the file in MATLAB Editor. Data of type `int8`, a signed 8-bit integer, is equivalent to Fortran type `integer*1`, a signed 1-byte integer. To copy values between MATLAB and Fortran arrays, use the `mxCopyPtrToInteger1` and `mxCopyInteger1ToPtr` functions.

To build this example, at the command prompt type:

```
mex matsqint8.F
```

Type:

```
B = int8([1 2; 3 4; -5 -6]);  
y = matsqint8(B)
```

```
y =  
    1     4  
    9    16  
   25    36
```

For information about using other integer data types, consult your Fortran compiler manual.

See Also

`mxCopyInteger1ToPtr` | `mxCopyPtrToInteger1`

Pass Multiple Inputs or Outputs

The `plhs` and `prhs` parameters (see “Components of Fortran MEX-File” on page 6-2) are vectors containing pointers to the left side (output) variables and right-hand side (input) variables. `plhs(1)` contains a pointer to the first left side argument, `plhs(2)` contains a pointer to the second left side argument, and so on. Likewise, `prhs(1)` contains a pointer to the first right-hand side argument, `prhs(2)` points to the second, and so on.

The example `xtimesy.F` multiplies an input scalar times an input scalar or matrix. To see the source code, open the file in MATLAB Editor.

As this example shows, creating MEX-file gateways that handle multiple inputs and outputs is straightforward. Keep track of which indices of the vectors `prhs` and `plhs` correspond to which input and output arguments of your function. In this example, the input variable `x` corresponds to `prhs(1)` and the input variable `y` to `prhs(2)`.

To build this example, at the command prompt type:

```
mex xtimesy.F
```

For an input scalar `x` and a real 3-by-3 matrix, type:

```
x = 3;  
y = ones(3);  
z = xtimesy(x, y)
```

```
z =  
    3     3     3  
    3     3     3  
    3     3     3
```

Handle Complex Data

MATLAB stores complex double-precision data as two vectors of numbers—one vector contains the real data and the other contains the imaginary data. The functions `mxCopyPtrToComplex16` and `mxCopyComplex16ToPtr` copy MATLAB data to a native `complex*16` Fortran array.

The example `convec.F` takes two complex vectors (of length 3) and convolves them. To see the source code, open the file in MATLAB Editor.

To build this example, at the command prompt type:

```
mex convec.F
```

Enter the following at the command prompt:

```
x = [3 - 1i, 4 + 2i, 7 - 3i];  
y = [8 - 6i, 12 + 16i, 40 - 42i];
```

Type:

```
z = convec(x, y)
```

```
z =
```

```
1.0e+02 *
```

```
Columns 1 through 4
```

```
0.1800 - 0.2600i    0.9600 + 0.2800i    1.3200 - 1.4400i  
3.7600 - 0.1200i
```

```
Column 5
```

```
1.5400 - 4.1400i
```

which agrees with the results the built-in MATLAB function `conv.m` produces.

Dynamically Allocate Memory

To allocate memory dynamically in a Fortran MEX-file, use `%val`. (See “Using the Fortran `%val` Construct” on page 6-6.) The example `dblmat.F` takes an input matrix of real data and doubles each of its elements. To see the source code, open the file in MATLAB Editor. `compute.F` is the subroutine `dblmat` calls to double the input matrix. (Open the file in MATLAB Editor.)

To build this example, at the command prompt type:

```
mex dblmat.F compute.F
```

For the 2-by-3 matrix, type:

```
x = [1 2 3; 4 5 6];  
y = dblmat(x)
```

```
y =  
    2     4     6  
    8    10    12
```

Note: The `dblmat.F` example, as well as `fulltosparse.F` and `sincall.F`, are split into two parts, the gateway and the computational subroutine, because of restrictions in some compilers.

Handle Sparse Matrices

MATLAB provides a set of functions that allow you to create and manipulate sparse matrices. There are special parameters associated with sparse matrices, namely `ir`, `jc`, and `nzmax`. For information on how to use these parameters and how MATLAB stores sparse matrices in general, see “Sparse Matrices” on page 4-11.

Note: Sparse array indexing is zero-based, not one-based.

The `fulltosparse.F` example illustrates how to populate a sparse matrix. To see the source code, open the file in MATLAB Editor. `loadsparse.F` is the subroutine `fulltosparse` calls to fill the `mxArray` with the sparse data. (Open the file in MATLAB Editor.)

To build this example, at the command prompt type:

```
mex fulltosparse.F loadsparse.F
```

At the command prompt, type:

```
full = eye(5)

full =
     1     0     0     0     0
     0     1     0     0     0
     0     0     1     0     0
     0     0     0     1     0
     0     0     0     0     1
```

MATLAB creates a full, 5-by-5 identity matrix. Using `fulltosparse` on the full matrix produces the corresponding sparse matrix:

```
spar = fulltosparse(full)

spar =
    (1,1)     1
    (2,2)     1
    (3,3)     1
    (4,4)     1
    (5,5)     1
```

Call MATLAB Functions from Fortran MEX-Files

You can call MATLAB functions, operators, user-defined functions, and other binary MEX-files from within your Fortran source code by using the API function `mexCallMATLAB`. The `sincall.F` example creates an `mxArray`, passes various pointers to a local function to acquire data, and calls `mexCallMATLAB` to calculate the sine function and plot the results. To see the source code, open the file in MATLAB Editor. `fill.F` is the subroutine `sincall` calls to fill the `mxArray` with data. (Open the file in MATLAB Editor.)

It is possible to use `mexCallMATLAB` (or any other API routine) from within your computational Fortran subroutine. You can only call most MATLAB functions with double-precision data. Some functions that perform computations, such as `eig`, do not work correctly with data that is not double precision.


To build this example, at the command prompt type:

```
mex sincall.F fill.F
```

Running this example:

```
sincall
```

displays the results:



Note: You can generate an object of type `mxUNKNOWN_CLASS` using `mexCallMATLAB`. See the following example.

This function returns two variables but only assigns one of them a value:

```
function [a,b]=foo[c]
a=2*c;
```

If you then call `foo` using `mexCallMATLAB`, the unassigned output variable is now of type `mxUNKNOWN_CLASS`.

Debug Fortran Source MEX-Files

In this section...

“Notes on Debugging” on page 6-31

“Debugging on Microsoft Windows Platforms” on page 6-31

“Debugging on Linux Platforms” on page 6-31

Notes on Debugging

The examples show how to debug `timestwo.F`, found in your `matlabroot/extern/examples/refbook` folder.

Binary MEX-files built with the `-g` option do not execute on other computers because they rely on files that are not distributed with MATLAB software. For more information on isolating problems with MEX-files, see “Troubleshoot MEX-Files”.

Debugging on Microsoft Windows Platforms

For MEX-files compiled with any version of the Intel® Visual Fortran compiler, you can use the debugging tools found in your version of Microsoft Visual Studio. Refer to the “Creating C/C++ Language MEX-Files” topic “Debugging on Microsoft Windows Platforms” on page 5-51 for instructions on using this debugger.

Debugging on Linux Platforms

The MATLAB supported Fortran compiler `g95` has a `-g` option for building binary MEX-files with debug information. Such files can be used with `gdb`, the GNU Debugger. This section describes using `gdb`.

GNU Debugger `gdb`

In this example, the MATLAB command prompt `>>` is shown in front of MATLAB commands, and `linux>` represents a Linux prompt; your system might show a different prompt. The debugger prompt is `<gdb>`.

1 To compile the source MEX-file, type:

```
linux> mex -g timestwo.F
```

- 2 At the Linux prompt, start the gdb debugger using the `matlab -D` option:

```
linux> matlab -Dgdb
```

- 3 Start MATLAB without the Java Virtual Machine (JVM) by using the `-nojvm` startup flag:

```
<gdb> run -nojvm
```

- 4 In MATLAB, enable debugging with the `dbmex` function and run your binary MEX-file:

```
>> dbmex on  
>> y = timestwo(4)
```

- 5 You are ready to start debugging.

It is often convenient to set a breakpoint at `mexFunction` so you stop at the beginning of the gateway routine.

Note: The compiler might alter the function name. For example, it might append an underscore. To determine how this symbol appears in a given MEX-file, use the Linux command `nm`. For example:

```
linux> nm timestwo.mexa64 | grep -i mexfunction
```

The operating system responds with something like:

```
0000091c T mexfunction_
```

Use `mexFunction` in the breakpoint statement. Be sure to use the correct case.

```
<gdb> break mexfunction_  
<gdb> continue
```

- 6 Once you hit one of your breakpoints, you can make full use of any commands the debugger provides to examine variables, display memory, or inspect registers.

To proceed from a breakpoint, type `continue`:

```
<gdb> continue
```


- 7** After stopping at the last breakpoint, type:

```
<gdb> continue
```

`timestwo` finishes and MATLAB displays:

```
y =
```

```
      8
```

- 8** From the MATLAB prompt you can return control to the debugger by typing:

```
>> dbmex stop
```

Or, if you are finished running MATLAB, type:

```
>> quit
```

- 9** When you are finished with the debugger, type:

```
<gdb> quit
```

You return to the Linux prompt.

Refer to the documentation provided with your debugger for more information on its use.

Handling Large mxArray

In this section...

“Using the 64-Bit API” on page 6-34

“Building the Binary MEX-File” on page 6-36

“Caution Using Negative Values” on page 6-36

“Building Cross-Platform Applications” on page 6-36

Binary MEX-files built on 64-bit platforms can handle 64-bit mxArray. These large data arrays can have up to $2^{48}-1$ elements. The maximum number of elements a sparse mxArray can have is $2^{48}-2$.

Using the following instructions creates platform-independent binary MEX-files as well.

Your system configuration can affect the performance of MATLAB. The 64-bit processor requirement enables you to create the mxArray and access data in it. However, the system memory, in particular the size of RAM and virtual memory, determine the speed at which MATLAB processes the mxArray. The more memory available, the faster the processing.

The amount of RAM also limits the amount of data you can process at one time in MATLAB. For guidance on memory issues, see “Strategies for Efficient Use of Memory”. Memory management within source MEX-files can have special considerations, as described in “Memory Management” on page 5-64.

Using the 64-Bit API

The signatures of the API functions shown in the following table use the `mwSize` or `mwIndex` types to work with a 64-bit mxArray. The variables you use in your source code to call these functions must be the correct type.

mxArray Functions Using `mwSize`/`mwIndex`

<code>mxCalcSingleSubscript</code>	<code>mxCreateSparseLogicalMatrix</code> ²
<code>mxMalloc</code>	<code>mxCreateStructArray</code>
<code>mxCopyCharacterToPtr</code> ¹	<code>mxCreateStructMatrix</code>

<code>mxCopyComplex16ToPtr¹</code>	<code>mxGetCell</code>
<code>mxCopyComplex8ToPtr¹</code>	<code>mxGetDimensions</code>
<code>mxCopyInteger1ToPtr¹</code>	<code>mxGetElementSize</code>
<code>mxCopyInteger2ToPtr¹</code>	<code>mxGetField</code>
<code>mxCopyInteger4ToPtr¹</code>	<code>mxGetFieldByNumber</code>
<code>mxCopyPtrToCharacter¹</code>	<code>mxGetIr</code>
<code>mxCopyPtrToComplex16¹</code>	<code>mxGetJc</code>
<code>mxCopyPtrToComplex8¹</code>	<code>mxGetM</code>
<code>mxCopyPtrToInteger1¹</code>	<code>mxGetN</code>
<code>mxCopyPtrToInteger2¹</code>	<code>mxGetNumberOfDimensions</code>
<code>mxCopyPtrToInteger4¹</code>	<code>mxGetNumberOfElements</code>
<code>mxCopyPtrToPtrArray¹</code>	<code>mxGetNzmax</code>
<code>mxCopyPtrToReal14¹</code>	<code>mxGetProperty</code>
<code>mxCopyPtrToReal18¹</code>	<code>mxGetString</code>
<code>mxCopyReal14ToPtr¹</code>	<code>mxMalloc</code>
<code>mxCopyReal18ToPtr¹</code>	<code>mxRealloc</code>
<code>mxCreateCellArray</code>	<code>mxSetCell</code>
<code>mxCreateCellMatrix</code>	<code>mxSetDimensions</code>
<code>mxCreateCharArray</code>	<code>mxSetField</code>
<code>mxCreateCharMatrixFromStrings</code>	<code>mxSetFieldByNumber</code>
<code>mxCreateDoubleMatrix</code>	<code>mxSetIr</code>
<code>mxCreateLogicalArray²</code>	<code>mxSetJc</code>
<code>mxCreateLogicalMatrix²</code>	<code>mxSetM</code>
<code>mxCreateNumericArray</code>	<code>mxSetN</code>
<code>mxCreateNumericMatrix</code>	<code>mxSetNzmax</code>
<code>mxCreateSparse</code>	<code>mxSetProperty</code>

¹Fortran function only.

²C function only.

Functions in this API use the `mwIndex`, `mwSize`, and `mwPointer` preprocessor macros.

Building the Binary MEX-File

Use the `mex` build script option `-largeArrayDims` with the 64-bit API.

Caution Using Negative Values

When using the 64-bit API, `mwSize` and `mwIndex` are equivalent to `INTEGER*8` in Fortran. This type is unsigned, unlike `INTEGER*4`, which is the type used in the 32-bit API. Be careful not to pass any negative values to functions that take `mwSize` or `mwIndex` arguments. Do not cast negative `INTEGER*4` values to `mwSize` or `mwIndex`; the returned value cannot be predicted. Instead, change your code to avoid using negative values.

Building Cross-Platform Applications

If you develop cross-platform applications (programs that can run on both 32- and 64-bit architectures), pay attention to the upper limit of values you use for `mwSize` and `mwIndex`. The 32-bit application reads these values and assigns them to variables declared as `INTEGER*4` in Fortran. Be careful to avoid assigning a large `mwSize` or `mwIndex` value to an `INTEGER*4` or other variable that might be too small.

Memory Management

When a MEX-file returns control to MATLAB, it returns the results of its computations in the output arguments—the `mxArrays` contained in the left-side arguments `plhs[]`. MATLAB destroys any `mxArray` created by the MEX-file that is not in this argument list. In addition, MATLAB frees any memory that was allocated in the MEX-file using the `mxMalloc`, `mxRealloc`, or `mxMalloc` functions.

Any misconstructed arrays left over at the end of a binary MEX-file execution have the potential to cause memory errors.

MathWorks recommends that MEX-file functions destroy their own temporary arrays and free their own dynamically allocated memory. It is more efficient to perform this cleanup in the source MEX-file than to rely on the automatic mechanism. For more information on memory management techniques, see the sections “Memory Management” on page 5-64 in *Creating C/C++ Language MEX-Files* and “Memory Management Issues” on page 4-67.

MATLAB Supports Fortran 77

MATLAB supports MEX-files written in Fortran 77. When troubleshooting MEX-files written in other versions of Fortran, refer to the Fortran Language Reference Manual, <http://h21007.www2.hp.com/portal/download/files/unprot/Fortran/docs/lrm/dflrm.htm>. This manual describes features for different versions of Fortran.

For example, the length of the following statement is less than 72 characters.

```
mwPointer mxGetN, mxSetM, mxSetN, mxCreateStructMatrix, mxGetM
```

However, when MATLAB expands the preprocessor macro, `mwPointer`, the length of the statement exceeds the limit supported by Fortran 77.

Calling MATLAB Engine from C/C++ and Fortran Programs

- “Introducing MATLAB Engine” on page 7-2
- “Callbacks in Applications” on page 7-4
- “Call MATLAB Functions from C/C++ Applications” on page 7-5
- “Call MATLAB Functions from Fortran Applications” on page 7-7
- “Attach to Existing MATLAB Sessions” on page 7-9
- “Build Windows Engine Application” on page 7-11
- “Run Windows Engine Application” on page 7-12
- “Setting Run-Time Library Path on Windows Systems” on page 7-13
- “Registering MATLAB as a COM Server” on page 7-15
- “Build Linux Engine Application” on page 7-16
- “Run Linux Engine Application” on page 7-17
- “Setting Run-Time Library Path on Mac and Linux Systems” on page 7-18
- “Building Engine Applications with IDE” on page 7-20
- “Can't Start MATLAB Engine” on page 7-23
- “Debugging MATLAB Functions Used in Engine Applications” on page 7-24
- “Multithreaded Applications” on page 7-25
- “Getting Started” on page 7-26

Introducing MATLAB Engine

The MATLAB engine library contains routines that allow you to call MATLAB from your own programs, using MATLAB as a computation engine. Using the MATLAB engine requires an installed version of MATLAB; you cannot run the MATLAB engine on a machine that only has the MATLAB Compiler Runtime (MCR).

Engine programs are standalone C/C++ or Fortran programs. These programs communicate with a separate MATLAB process via pipes, on UNIX systems, and through a Microsoft Component Object Model (COM) interface, on Microsoft Windows systems. MATLAB provides a library of functions that allows you to start and end the MATLAB process, send data to and from MATLAB, and send commands to be processed in MATLAB.

Some of the things you can do with the MATLAB engine are:

- Call a math routine, for example, to invert an array or to compute an FFT from your own program. When employed in this manner, MATLAB is a powerful and programmable mathematical subroutine library.
- Build an entire system for a specific task. For example, the front end (user interface) is programmed in C/C++ and the back end (analysis) is programmed in MATLAB.

The MATLAB engine operates by running in the background as a separate process from your own program. Some advantages are:

- On UNIX systems, the engine can run on your machine, or on any other UNIX machine on your network, including machines of a different architecture. This configuration allows you to implement a user interface on your workstation and perform the computations on a faster machine located elsewhere on your network. For more information, see the `engOpen` reference page.
- Instead of requiring your program to link to the entire MATLAB program (a substantial amount of code), it links to a smaller engine library.

The MATLAB engine cannot read MAT-files in a format based on HDF5. These MAT-files save data using the `-v7.3` option of the `save` function or are opened using the `w7.3` mode argument to the C or Fortran `matOpen` function.

Note: To run MATLAB engine on the UNIX platform, you must have the C shell `csH` installed at `/bin/csh`.

Communicating with MATLAB Software

On UNIX systems, the engine library communicates with the engine using pipes, and, if needed, `rsh` for remote execution. On Microsoft Windows systems, the engine library communicates with the engine using a Component Object Model (COM) interface. For more information, see “MATLAB COM Integration” on page 11-2.

Callbacks in Applications

If you have a user interface that executes many callbacks through the MATLAB engine, force these callbacks to be evaluated in the context of the base workspace. Use `evalin` to specify the base workspace for evaluating the callback expression. For example:

```
engEvalString(ep, "evalin('base', expression)")
```

Specifying the base workspace ensures MATLAB processes the callback correctly and returns results for that call.

This advice does not apply to computational applications that do not execute callbacks.

See Also

`engEvalString` | `evalin`

Call MATLAB Functions from C/C++ Applications


The program `engdemo.c`, in the `matlabroot/extern/examples/eng_mat` folder, illustrates how to call the engine functions from a standalone C program. For the Microsoft Windows version of this program, see `engwindemo.c`.

To see `engdemo.c`, open this file in MATLAB Editor.

To see the Windows version `engwindemo.c`, open this file.

There is a C++ version of `engdemo` in the `matlabroot\extern\examples\eng_mat` folder. To see `engdemo.cpp`, open this file.

The first part of this program starts MATLAB and sends it data. MATLAB analyzes the data and plots the results.



The program continues with:

Press Return to continue

Pressing **Return** continues the program:

Done for Part I.

Enter a MATLAB command to evaluate. This command should create a variable X. This program will then determine what kind of variable you created.

For example: `X = 1:5`

Entering `X = 17.5` continues the program execution.

```
X = 17.5
```

```
X =
```

```
    17.5000
```

```
Retrieving X...  
X is class double  
Done!
```

Finally, the program frees memory, closes the MATLAB engine, and exits.

Related Examples

- “Build Windows Engine Application” on page 7-11
- “Build Linux Engine Application” on page 7-16


More About

- “Building Engine Applications with IDE” on page 7-20

Call MATLAB Functions from Fortran Applications

The program `fengdemo.F`, in the `matlabroot/extern/examples/eng_mat` folder, illustrates how to call the engine functions from a standalone Fortran program. To see the code, open this file.

Executing this program starts MATLAB, sends it data, and plots the results.



The program continues with:

```
Type 0 <return> to Exit
Type 1 <return> to continue
```

Entering 1 at the prompt continues the program execution:

```
1
MATLAB computed the following distances:
  time(s)  distance(m)
  1.00    -4.90
  2.00   -19.6
  3.00   -44.1
  4.00   -78.4
  5.00  -123.
  6.00  -176.
  7.00  -240.
  8.00  -314.
  9.00  -397.
```

10.0 -490.

Finally, the program frees memory, closes the MATLAB engine, and exits.

Attach to Existing MATLAB Sessions

This example shows how to attach an engine program to a MATLAB session that is already running.

On a Windows platform, start MATLAB with `-automation` in the command line. When you call `engOpen`, it connects to this existing session. You should only call `engOpen` once, because any `engOpen` calls now connect to this one MATLAB session.

The `-automation` option also causes the command window to be minimized. You must open it manually.

On the Mac and Linux platforms, you cannot make an engine program connect to an existing MATLAB session.

Shut down any MATLAB sessions.

From the **Start** button on the Windows menu bar, click **Run**.

In MATLAB, capture the value returned by the command:

```
path = fullfile(matlabroot, 'bin', computer('arch'))
```

In the **Run** dialog box **Open** field, type the following command, replacing `path` with the value from the previous step:

```
path\matlab.exe -automation
```

Click **OK**. This starts MATLAB.

In MATLAB, copy the `engwindemo.c` example to a writable folder.

```
copyfile(fullfile(matlabroot, 'extern', 'examples', 'eng_mat', 'engwindemo.c'), '.', 'f')
```

Build the example.

```
mex -client engine engwindemo.c
```

Run the `engwindemo` program by typing at the MATLAB prompt:

```
!engwindemo
```

This does not start another MATLAB session, but rather uses the MATLAB session that is already open.

More About

- “Launch MATLAB as Automation Server in Desktop Mode” on page 13-16
- “MATLAB COM Integration” on page 11-2

Build Windows Engine Application

This example shows how to verify the build process on Windows platforms using the C example, `engwindemo.c`.

Start MATLAB as a user with administrator privileges. Based on your User Account Control (UAC) settings, you might need to right-click the MATLAB icon and select **Run as administrator**. If that option is not available, contact your system administrator.

Register MATLAB as a COM server.

```
!matlab -regserver
```

MATLAB displays a second, minimized command window. Close that window.

Verify your current folder is writable and copy the example.

```
copyfile(fullfile(matlabroot, 'extern', 'examples', 'eng_mat', 'engwindemo.c'), '.', 'f')
```

Build the application.

```
mex -v -client engine engwindemo.c
```

Related Examples

- “Call MATLAB Functions from C/C++ Applications” on page 7-5
- “Run Windows Engine Application” on page 7-12

More About

- “Registering MATLAB as a COM Server” on page 7-15

Run Windows Engine Application

This example shows how to run the C example, `engwindemo.c`, from the Windows system prompt. You need to know the value of `matlabroot` (the folder where MATLAB is installed) and the value returned by the MATLAB `computer('arch')` command (`arch`).

Set the run-time library path by modifying the system PATH variable.

```
set PATH=matlabroot\bin\arch;%PATH%
```

Make sure that you include the `;` path terminator character.

Run the example. The `engwindemo` application must be on your system path.

```
engwindemo
```

MATLAB Starts and displays the results.

Click **Ok** in the MATLAB whos window to close the application.

See Also

`computer` | `matlabroot`

Related Examples

- “Build Windows Engine Application” on page 7-11
- “Call MATLAB Functions from C/C++ Applications” on page 7-5

More About

- “Setting Run-Time Library Path on Windows Systems” on page 7-13

Setting Run-Time Library Path on Windows Systems

In this section...

“Change Path Each Time You Run the Application” on page 7-13

“Permanently Change Path” on page 7-13

“Troubleshooting” on page 7-14

At run time, tell the operating system where the API shared libraries reside by setting the `Path` environment variable. Set the value to the path string returned by the following MATLAB command:

```
res = fullfile(matlabroot, 'bin', computer('arch'))
```

Change Path Each Time You Run the Application

To set the run-time library path from the Windows command prompt, type the following command, where `res` is the string returned from the `fullfile` command. Set the path every time you open the Windows Command Processor.

```
set PATH=res;%PATH%
```

You must set the path each time that you open the Windows prompt.

Permanently Change Path

To set the run-time library path permanently to `res`, modify the `Path` variable using the Control Panel. For the setting to take effect, close the command prompt window, then open a new command prompt window.

To remove the run-time library path, follow the same instructions, deleting the path name from the variable.

Windows 7

- Select **Computer** from the Start menu.
- Choose **System properties** from the context menu.
- Click **Advanced system settings > Advanced** tab.
- Click **Environment Variables**.

- Under **System variables**, select **Path** and click **Edit**.
- Modify **Path** by inserting `res;` at the beginning of the **Variable value:** text field.
- Click **Ok** to close the dialog boxes, then close the **Control Panel** dialog box.

Troubleshooting

If you have multiple versions of MATLAB installed on your system, the version you use to build your engine applications must be the first listed in your system **Path** environment variable. Otherwise, MATLAB displays `Can't start MATLAB engine`.

Registering MATLAB as a COM Server

To run the engine application on a Windows operating system, you must register MATLAB as a COM server. Do this for every session, to ensure that the current version of MATLAB is the registered version. If you run older versions, the registered version could change. If there is a mismatch of version numbers, MATLAB displays Can ' t start MATLAB engine.

To register MATLAB manually as a server, start MATLAB as a user with administrator privilege. Then type:

```
!matlab -regserver
```

Close the MATLAB window that appears.

Build Linux Engine Application

This example shows how to verify the build process on a Linux platform using the C example, `engdemo.c`.

Open MATLAB.

Verify your current folder is writable and copy the example.

```
copyfile(fullfile(matlabroot, 'extern', 'examples', 'eng_mat', 'engdemo.c'), '.', 'f')
```

Build the application.

```
mex -v -client engine engdemo.c
```

Related Examples

- “Call MATLAB Functions from C/C++ Applications” on page 7-5
- “Run Linux Engine Application” on page 7-17

Run Linux Engine Application

This example shows how to run the C example, `engdemo.c`, from the Linux system prompt. You need to know the value of `matlabroot`, the folder where MATLAB is installed.

Set the run-time library path.

```
setenv LD_LIBRARY_PATH matlabroot/bin/glnxa64:matlabroot/sys/os/glnxa64
```

This command replaces the value, if any, in `LD_LIBRARY_PATH`.

Set the path.

```
setenv PATH matlabroot/bin:$PATH
```

Make sure that you include the `:` path terminator character.

Run the example. The `engdemo` application must be on your system path.

```
./engdemo
```

MATLAB starts and displays a figure.

Press Return to close the figure.

Create variable `X`, for example:

```
X = 'hello'
```

MATLAB displays the results and closes.

Related Examples

- “Build Linux Engine Application” on page 7-16
- “Call MATLAB Functions from C/C++ Applications” on page 7-5

More About

- “Setting Run-Time Library Path on Mac and Linux Systems” on page 7-18

Setting Run-Time Library Path on Mac and Linux Systems

At run time, tell the operating system where the API shared libraries reside by setting an environment variable. Set the path every time you run MATLAB. Alternatively, place the commands in a MATLAB startup script.

The shell command you use and the value you provide to set the run-time library path depend on your shell and system architecture. The following table lists the name of the environment variable, *envvar*, and the values, *pathspec*, to assign to it.

Operating System	<i>envvar</i>	<i>pathspec</i>
64-bit Apple Mac	DYLD_LIBRARY_PATH	<i>matlabroot/bin/maci64:</i> <i>matlabroot/sys/os/maci64</i>
64-bit Linux	LD_LIBRARY_PATH	<i>matlabroot/bin/glnxa64:</i> <i>matlabroot/sys/os/glnxa64</i>

These commands replace the existing value in *envvar*.

If you have multiple versions of MATLAB installed on your system, the version you use to build your engine applications must be the first listed in your system **Path** environment variable. Otherwise, MATLAB displays Can't start MATLAB engine.

C Shell

Set the library path using the command, replacing the terms *envvar* and *pathspec* with the appropriate values from the table.

```
setenv envvar pathspec
```

For example, on a Mac system:

```
setenv DYLD_LIBRARY_PATH matlabroot/bin/maci64:matlabroot/sys/os/maci64
```

You can place these commands in a startup script, such as `~/ .cshrc`.

Bourne Shell

Set the library path using the command, replacing the terms *envvar* and *pathspec* with the appropriate values from the table.


```
envvar = pathspec:envvar export envvar
```

For example, on a Mac system:

```
DYLD_LIBRARY_PATH=matlabroot/bin/maci64:matlabroot/sys/os/maci64:$DYLD_LIBRARY_PATH  
export DYLD_LIBRARY_PATH
```

You can place these commands in a startup script such as `~/ .profile`.

Building Engine Applications with IDE

In this section...
“Configuring the IDE” on page 7-20
“Engine Include Files” on page 7-20
“Engine Libraries” on page 7-20
“Library Files Required by libeng” on page 7-21

Configuring the IDE

If your integrated development environment (IDE) has a MATLAB-supported compiler, you can use the IDE to build engine applications. For an up-to-date list of supported compilers, see the Supported and Compatible Compilers website.

Engine applications require the Engine Library `libeng`, the Matrix Library `libmx`, and supporting include files. When you build using the `mex` command, MATLAB is configured to locate these files. When you build in your IDE, you must configure the IDE to locate them. Where these settings are depends on your IDE. Refer to your product documentation.

Engine Include Files

Header files contain function declarations with prototypes for the routines you access in the API libraries. These files are in the `matlabroot\extern\include` folder and are the same for Windows, Mac, and Linux systems. Engine applications use:

- `engine.h` — function prototypes for engine routines
- `matrix.h` — definition of the `mxArray` structure and function prototypes for matrix access routines

In your IDE, set the pre-processor include path to the value returned by the following MATLAB command:

```
fullfile(matlabroot, 'extern', 'include')
```

Engine Libraries

You need the `libeng` and `libmx` shared libraries. The name of the file is platform-specific, as shown in the following table.

Library File Names by Operating System

Windows ^a	Linux	Mac
libeng.lib	libeng.so	libeng.dylib
libmx.lib	libmx.so	libmx.dylib

- a. These files are located in the folder
`fullfile(matlabroot, 'extern', 'lib', computer('arch'), 'microsoft')`.

Add these library names to your IDE configuration. Set the library path to the value returned by the following MATLAB command:

```
fullfile(matlabroot, 'bin', computer('arch'))
```

Refer to your IDE product documentation for instructions.

Library Files Required by libeng

The `libeng` library requires additional third-party library files. MATLAB uses these libraries to support Unicode character encoding and data compression in MAT-files.

These library files must reside in the same folder as the `libmx` library. You can determine what these libraries are using the platform-specific commands shown in the following table. Once you identify these files, update your IDE.

Library Dependency Commands

Windows	Linux	Mac
See the following instructions for Dependency Walker	<code>ldd -d libeng.so</code>	<code>otool -L libeng.dylib</code>

On Windows systems, to find library dependencies, use the third-party product Dependency Walker. Dependency Walker is a free utility that scans any 32-bit or 64-bit Windows module and builds a hierarchical tree diagram of all dependent modules. For each module found, it lists all the functions exported by that module, and which of those functions are called by other modules. Download the Dependency Walker utility from the website <http://www.dependencywalker.com/>. See <http://www.mathworks.com/matlabcentral/answers/92362-how-do-i-determine-which-libraries-my-mex-file-or-stand-alone-application-requires> for information on using the Dependency Walker.

Drag and drop the `libeng.dll` file into the Depends window. Identify the dependent libraries and add them to your IDE configuration.

Related Examples

- “Build Windows Engine Application” on page 7-11
- “Build Linux Engine Application” on page 7-16

External Web Sites

- How can I compile a MATLAB Engine application using Microsoft Visual Studio 9.0 or 10.0?
- How can I build an Engine application using the Xcode IDE on Mac?

Can't Start MATLAB Engine

If you have multiple versions of MATLAB installed on your system, the version you use to build your engine applications must be the first listed in your system `Path` environment variable. Otherwise, MATLAB displays `Can't start MATLAB engine`.

On Windows operating systems, you also must register MATLAB as a COM server. If you have multiple versions of MATLAB, the version you are using must be the registered version.

Related Examples

- “Registering MATLAB as a COM Server” on page 7-15

Debugging MATLAB Functions Used in Engine Applications

When creating MATLAB functions for use in engine applications, it is good practice to debug the functions in MATLAB before calling them via the engine interface.

Although you cannot use the MATLAB Editor/Debugger from an engine application, you can use the MATLAB workspace to examine variables passed to MATLAB. For example, you have the following MATLAB function:

```
function y = myfcn(x)
y = x+2;
end
```

Your engine application calls `myfcn` with your variable `mycmxarray`, as shown in the following code:

```
engPutVariable(ep, "aVar", mycmxarray);
engEvalString(ep, "result = myfcn(aVar)");
mycmxarrayResult = engGetVariable(ep, "result");
```

If you do not get the expected result, you can examine two possibilities: if the input, `mycmxarray`, is incorrect, or if the MATLAB function is incorrect.

To examine the input to `myfcn`, first modify the function to save the MATLAB workspace to the file `debugmyfcn.mat`.

```
function y = myfcn(x)
save debugmyfcn.mat
y = x+2;
end
```

Execute your engine application, then start MATLAB and load `debugmyfcn.mat`.

```
load debugmyfcn.mat
whos x
```

Variable `x` contains the value from `mycmxarray`. If `x` is not what you expect, debug your engine code. If `x` is correct, debug the MATLAB function. To debug `myfcn`, open the function in the MATLAB Editor/Debugger, and then call the function from the MATLAB command line:

```
myfcn(x)
```

Multithreaded Applications

MATLAB libraries are not thread-safe. If you create multithreaded applications, make sure that only one thread accesses the engine application.

Getting Started

To build an engine application, you need:

- The ability to write C/C++ or Fortran source code. You can create these files with the MATLAB Editor.
- A compiler supported by MATLAB. For an up-to-date list of supported compilers, see the Supported and Compatible Compilers website.
- “C/C++ Matrix Library API” or “Fortran Matrix Library API” functions.
- C and Fortran Engine Library functions.
- The `mex` build script with the `-client engine` option.
- To use your own build tools, see “Building Engine Applications with IDE”.

To run the application:

- “Setting Run-Time Library Path on Windows Systems” on page 7-13
- “Registering MATLAB as a COM Server”
- “Setting Run-Time Library Path on Mac and Linux Systems” on page 7-18

MATLAB Engine for Python Topics

- “Get Started with MATLAB Engine for Python” on page 8-2
- “Install MATLAB Engine for Python” on page 8-5
- “Start and Stop MATLAB Engine for Python” on page 8-7
- “Call MATLAB Functions from Python” on page 8-9
- “Call MATLAB Functions Asynchronously from Python” on page 8-11
- “Call User Script and Function from Python” on page 8-12
- “Redirect Standard Output and Error to Python” on page 8-14
- “Use MATLAB Handle Objects in Python” on page 8-15
- “Use MATLAB Engine Workspace in Python” on page 8-17
- “Pass Data to MATLAB from Python” on page 8-18
- “Handle Data Returned from MATLAB to Python” on page 8-20
- “MATLAB Arrays as Python Variables” on page 8-23
- “Use MATLAB Arrays in Python” on page 8-28
- “Sort and Plot MATLAB Data from Python” on page 8-30
- “Get Help for MATLAB Functions from Python” on page 8-34
- “Default Numeric Types in MATLAB and Python” on page 8-36
- “System Requirements for MATLAB Engine for Python” on page 8-38
- “Limitations to MATLAB Engine for Python” on page 8-40
- “Troubleshoot MATLAB Errors in Python” on page 8-41

Get Started with MATLAB Engine for Python

The MATLAB Engine for Python provides a Python package named `matlab` that enables you to call MATLAB functions from Python. You install the package once, and then you can call the engine in your current or future Python sessions. For help on installing or starting the engine, refer to:

- “Install MATLAB Engine for Python”
- “Start and Stop MATLAB Engine for Python”

The `matlab` package contains the following:

- The MATLAB Engine for Python
- A set of MATLAB array classes in Python (see “MATLAB Arrays as Python Variables”)

The engine provides functions to call MATLAB, and the array classes provide functions to create MATLAB arrays as Python objects. You can create an engine and call MATLAB functions with `matlab.engine`. You can create MATLAB arrays in Python by calling constructors of an array type (for example, `matlab.double` to create an array of doubles). MATLAB arrays can be input arguments to MATLAB functions called with the engine.

The table shows the structure of the `matlab` package.

Package	Function or Class	Description
<code>matlab.engine</code>	<code>start_matlab()</code>	Python function to create a <code>MatlabEngine</code> object, and attach it to a new MATLAB process
<code>matlab.engine</code>	<code>MatlabEngine</code>	Python class to provide methods for calling MATLAB functions
<code>matlab.engine</code>	<code>FutureResult</code>	Python class to hold results from a MATLAB

Package	Function or Class	Description
		function called asynchronously
matlab	double	Python class to hold array of MATLAB type <code>double</code>
matlab	single	Python class to hold array of MATLAB type <code>single</code>
matlab	int8	Python class to hold array of MATLAB type <code>int8</code>
matlab	int16	Python class to hold array of MATLAB type <code>int16</code>
matlab	int32	Python class to hold array of MATLAB type <code>int32</code>
matlab	int64	Python class to hold array of MATLAB type <code>int64</code>
matlab	uint8	Python class to hold array of MATLAB type <code>uint8</code>
matlab	uint16	Python class to hold array of MATLAB type <code>uint16</code>
matlab	uint32	Python class to hold array of MATLAB type <code>uint32</code>
matlab	uint64	Python class to hold array of MATLAB type <code>uint64</code>

Package	Function or Class	Description
matlab	logical	Python class to hold array of MATLAB type <code>logical</code>
matlab	object	Python class to hold a handle to a MATLAB object

Install MATLAB Engine for Python

To start the MATLAB engine within a Python session, you first must install the engine as a Python package. The engine supports Python versions 2.7, 3.3, and 3.4.

- 1 Ensure that Python is installed on your system and that you can run Python at the operating system prompt.
 - To install Python 2.7, 3.3, or 3.4, see “Install Supported Python Implementation”.
- 2 Add the Python folder to your PATH environment variable, if it is not already there.
- 3 Find the MATLAB folder. Start MATLAB and type `matlabroot` in the command window. Copy the path returned by `matlabroot`.
- 4 Go back to the operating system prompt. Execute the following commands where *matlabroot* is the path you copied in step 3.

```
cd "matlabroot\extern\engines\python"
python setup.py install
```

MATLAB provides a standard Python `setup.py` file for building and installing the engine using the `distutils` module. To install the engine in an alternate location, refer to the Python `distutils` documentation at [Installing Python Modules](#).

Install MATLAB Engine for Python Without Administrator Privileges

To install the MATLAB Engine for Python when you do not have administrator privileges, follow steps 1–3 of “Install MATLAB Engine for Python”. Then use folders *builddir* and *installdir* to build and install the engine. You must have write permission to the *builddir* and *installdir* folders. Execute the following commands at the operating system prompt where *matlabroot* is the path to the MATLAB folder.

```
cd "matlabroot\extern\engines\python"
python setup.py build --build-base="builddir" install --prefix="installdir"
```

You must include *installdir* in the search path for Python packages. Add *installdir* to the PYTHONPATH environment variable.

If you install the engine for your use only, you can use the `--user` option to install the package in your home folder.

```
cd "matlabroot\extern\engines\python"
```

```
python setup.py build --build-base="builddir" install --user
```

When you install with `--user`, you do not need to add a new folder to PYTHONPATH.

More About

- “System Requirements for MATLAB Engine for Python” on page 8-38

Start and Stop MATLAB Engine for Python

In this section...

“Start MATLAB Engine for Python” on page 8-7

“Run Multiple Engines” on page 8-7

“Stop MATLAB Engine” on page 8-7

“Start Engine with Startup Options” on page 8-8

Start MATLAB Engine for Python

- Start Python at the operating system prompt.
- Import the `matlab.engine` package into your Python session.
- Start a new MATLAB process by calling `start_matlab`. The `start_matlab` function returns a Python object, `eng`, which allows you to pass data and call functions executed by MATLAB.

```
import matlab.engine
eng = matlab.engine.start_matlab()
```

Run Multiple Engines

Start each engine separately. Each engine starts and communicates with its own MATLAB process.

```
eng1 = matlab.engine.start_matlab()
eng2 = matlab.engine.start_matlab()
```

Stop MATLAB Engine

Call either the `exit` or the `quit` function.

```
eng.quit()
```

If you exit Python with an engine still running, Python automatically stops the engine and its MATLAB process

Start Engine with Startup Options

Start the engine and pass the options as an input argument string to `matlab.engine.start_matlab`. For example, start MATLAB with the desktop.

```
eng = matlab.engine.start_matlab("-desktop")
```

You can define multiple startup options with a single string. For example, start the desktop and set the numeric display format to short.

```
eng = matlab.engine.start_matlab("-desktop -r 'format short'")
```

You also can start the desktop after you start the engine.

```
import matlab.engine
eng = matlab.engine.start_matlab()
eng.desktop(nargout=0)
```


Call MATLAB Functions from Python

In this section...

“Return Output Argument from MATLAB Function” on page 8-9

“Return Multiple Output Arguments from MATLAB Function” on page 8-9

“Return No Output Arguments from MATLAB Function” on page 8-9

“Stop Execution of Function” on page 8-10

Return Output Argument from MATLAB Function

You can call any MATLAB function directly and return the results to Python. For example, to determine if a number is prime, use the engine to call the `isprime` function.

```
import matlab.engine
eng = matlab.engine.start_matlab()
tf = eng.isprime(37)
print(tf)
```

```
True
```

Return Multiple Output Arguments from MATLAB Function

When you call a function with the engine, by default the engine returns a single output argument. If you know that the function can return multiple arguments, use the `nargout` argument to specify the number of output arguments.

To determine the greatest common denominator of two numbers, use the `gcd` function. Set `nargout` to return the three output arguments from `gcd`.

```
import matlab.engine
eng = matlab.engine.start_matlab()
t = eng.gcd(100.0,80.0,nargout=3)
print(t)
```

```
(20.0, 1.0, -1.0)
```

Return No Output Arguments from MATLAB Function

Some MATLAB functions return no output arguments. If the function returns no arguments, set `nargout` to 0.

Open the MATLAB Help browser from Python.

```
import matlab.engine
eng = matlab.engine.start_matlab()
eng.doc(nargout=0)
```

The MATLAB `doc` function opens the browser, but does not return output arguments. If you do not specify `nargout=0`, the engine raises an error.

Stop Execution of Function

To stop execution of a MATLAB function press **Ctrl+C**. Control returns to Python.

See Also

`matlab.engine.MatlabEngine` | `matlab.engine.FutureResult`

Related Examples

- “Call MATLAB Functions Asynchronously from Python” on page 8-11
- “Call User Script and Function from Python” on page 8-12
- “Use MATLAB Arrays in Python” on page 8-28
- “Sort and Plot MATLAB Data from Python” on page 8-30

Call MATLAB Functions Asynchronously from Python

This example shows how to call the MATLAB `sqrt` function asynchronously from Python and retrieve the square root later.

The engine calls MATLAB functions synchronously by default. Control returns to Python only when the MATLAB function finishes. But the engine also can call functions asynchronously. Control immediately returns to Python while MATLAB is still executing the function. The engine stores the result in a Python variable that can be inspected after the function finishes.

Use the `async` argument to call a MATLAB function asynchronously.

```
import matlab.engine
eng = matlab.engine.start_matlab()
future = eng.sqrt(4.0, async=True)
ret = future.result()
print(ret)
```

```
2.0
```

Use the `done` method to check if an asynchronous call finished.

```
tf = future.done()
print(tf)
```

```
True
```

To stop execution of the function before it finishes, call `future.cancel()`.

See Also

`matlab.engine.MatlabEngine` | `matlab.engine.FutureResult`

Related Examples

- “Call MATLAB Functions from Python” on page 8-9
- “Call User Script and Function from Python” on page 8-12

Call User Script and Function from Python

This example shows how to call a MATLAB script to compute the area of a triangle from Python.

In your current folder, create a MATLAB script in a file named `triarea.m`.

```
b = 5;  
h = 3;  
a = 0.5*(b.* h)
```

After you save the file, start Python and call the script.

```
import matlab.engine  
eng = matlab.engine.start_matlab()  
eng.triarea(nargout=0)
```

```
a =
```

```
7.5000
```

Specify `nargout=0`. Although the script prints output, it returns no output arguments to Python.

Convert the script to a function and call the function from the engine. Open the MATLAB editor to edit the file.

```
eng.edit('triarea',nargout=0)
```

Delete the three statements. Then add a function declaration and save the file.

```
function a = triarea(b,h)  
a = 0.5*(b.* h);
```

Call the new `triarea` function from the engine.

```
ret = eng.triarea(1.0,5.0)  
print(ret)
```

```
2.5
```

The `triarea` function returns only one output argument, so there is no need to specify `nargout`.

See Also

`matlab.engine.MatlabEngine` | `matlab.engine.FutureResult`

Related Examples

- “Call MATLAB Functions from Python” on page 8-9

Redirect Standard Output and Error to Python

This example shows how to redirect standard output and standard error from a MATLAB function to Python `StringIO` objects.

In Python 2.7, use the `StringIO` module to create `StringIO` objects. Specify `stdout` and `stderr` to capture a warning message from `dec2hex`.

```
import matlab.engine
eng = matlab.engine.start_matlab()
import StringIO
out = StringIO.StringIO()
err = StringIO.StringIO()
ret = eng.dec2hex(2**60, stdout=out, stderr=err)
print(out.getvalue())
```

Warning: At least one of the input numbers is larger than the largest integer-valued f

In Python 3.3 or 3.4, use the `io` module to create `StringIO` objects.

```
import matlab.engine
eng = matlab.engine.start_matlab()
import io
out = io.StringIO()
err = io.StringIO()
ret = eng.dec2base(2**60, 16, stdout=out, stderr=err)
```

`dec2base` raises an exception when an input argument is greater than 2^{52} . Display the error message captured in `err`.

```
print(err.getvalue())
```

```
Error using dec2base (line 22)
First argument must be an array of integers, 0 <= D <= 2^52.
```

See Also

`matlab.engine.MatlabEngine` | `matlab.engine.FutureResult`

Related Examples

- “Call MATLAB Functions from Python” on page 8-9

Use MATLAB Handle Objects in Python

This example shows how to create an object from a MATLAB handle class and call its methods in Python.

In your current folder, create a MATLAB handle class in a file named `Triangle.m`.

```
classdef Triangle < handle
    properties (SetAccess = private)
        Base = 0;
        Height = 0;
    end

    methods
        function TR = Triangle(b,h)
            TR.Base = b;
            TR.Height = h;
        end

        function a = area(TR)
            a = 0.5 .* TR.Base .* TR.Height;
        end

        function setBase(TR,b)
            TR.Base = b;
        end

        function setHeight(TR,h)
            TR.Height = h;
        end
    end
end
```

Start Python. Create a `Triangle` handle object and call its `area` method with the engine. Pass the handle object as the first positional argument.

```
import matlab.engine
eng = matlab.engine.start_matlab()
tr = eng.Triangle(5.0,3.0)
a = eng.area(tr)
print(a)
```

7.5

Copy `tr` to the MATLAB workspace. You can use `eval` to access the properties of a handle object from the workspace.

```
eng.workspace["wtr"] = tr
b = eng.eval("wtr.Base")
print(b)
```

5.0

Change the height with the `setHeight` method. If your MATLAB handle class defines `get` and `set` methods for properties, you can access properties without using the MATLAB workspace.

```
eng.setHeight(tr,8.0,nargout=0)
a = eng.area(tr)
print(a)
```

20.0

See Also

`matlab.engine.MatlabEngine` | `matlab.engine.FutureResult`

Related Examples

- “Call MATLAB Functions from Python” on page 8-9

Use MATLAB Engine Workspace in Python

This example shows how to add variables to the MATLAB engine workspace in Python.

When you start the engine, it provides an interface to a collection of all MATLAB variables. This collection, named `workspace`, is implemented as a Python dictionary that is attached to the engine. The name of each MATLAB variable becomes a key in the `workspace` dictionary. The keys in `workspace` must be valid MATLAB identifiers (e.g., you cannot use numbers as keys). You can add variables to the engine workspace in Python, and then you can use the variables in MATLAB functions.

Add a variable to the engine workspace.

```
import matlab.engine
eng = matlab.engine.start_matlab()
x = 4.0
eng.workspace['y'] = x
a = eng.eval('sqrt(y)')
print(a)
```

```
2.0
```

In this example, `x` exists only as a Python variable. Its value is assigned to a new entry in the engine workspace, called `y`, creating a new MATLAB variable. You can then call the MATLAB `eval` function to execute the `sqrt(y)` statement in MATLAB and return the output value, 2.0, to Python.

See Also

`matlab.engine.MatlabEngine` | `matlab.engine.FutureResult`

Related Examples

- “Call MATLAB Functions from Python” on page 8-9
- “Sort and Plot MATLAB Data from Python” on page 8-30

Pass Data to MATLAB from Python

In this section...

“Python Type to MATLAB Scalar Type Mapping” on page 8-18

“Python Container to MATLAB Array Type Mapping” on page 8-18

“Unsupported Python Types” on page 8-19

Python Type to MATLAB Scalar Type Mapping

When you pass Python data as input arguments to MATLAB functions, the MATLAB Engine for Python converts the data into equivalent MATLAB data types.

Python Input Argument Type — Scalar Values Only	Resulting MATLAB Data Type
float	double
complex	Complex double
int	int64
long (Python 2.7 only)	int64
float(nan)	NaN
float(inf)	Inf
bool	logical
str	char
unicode (Python 2.7 only)	char
dict	Structure if all keys are strings not supported otherwise

Python Container to MATLAB Array Type Mapping

Python Input Argument Type — Container	Resulting MATLAB Data Type
matlab numeric array object (see “MATLAB Arrays as Python Variables”)	Numeric array

Python Input Argument Type — Container	Resulting MATLAB Data Type
<code>bytearray</code>	<code>uint8</code> array
<code>bytes</code> (Python 3.3 and 3.4) <code>bytes</code> (Python 2.7)	<code>uint8</code> array <code>char</code> array
<code>list</code>	Cell array
<code>set</code>	Cell array
<code>tuple</code>	Cell array

Unsupported Python Types

The following Python types are not supported by the MATLAB Engine for Python:

- `array.array` (use MATLAB numeric array objects instead; see “MATLAB Arrays as Python Variables”)
- `None`
- `module.type` object

Handle Data Returned from MATLAB to Python

In this section...

“MATLAB Scalar Type to Python Type Mapping” on page 8-20

“MATLAB Array Type to Python Type Mapping” on page 8-21

“Unsupported MATLAB Types” on page 8-21

MATLAB Scalar Type to Python Type Mapping

When MATLAB functions return output arguments, the MATLAB Engine for Python converts the data into equivalent Python data types.

MATLAB Output Argument Type — Scalar Values Only	Resulting Python Data Type
double	float
single	float
Complex (any numeric type)	complex
int8	int
uint8	int
int16	int
uint16	int
int32	int
uint32	int (Python 3.3 and 3.4) long (Python 2.7)
int64	int (Python 3.3 and 3.4) long (Python 2.7)
uint64	int (Python 3.3 and 3.4) long (Python 2.7)
NaN	float(nan)
Inf	float(inf)
logical	bool
char returned to Python 3.3 or 3.4	str

MATLAB Output Argument Type — Scalar Values Only	Resulting Python Data Type
char returned to Python 2.7	str (when MATLAB char value is less than or equal to <code>intmax('uint8')</code>) unicode (when MATLAB char value is greater than <code>intmax('uint8')</code>)
Structure	dict
MATLAB handle object (such as the <code>containers.Map</code> type)	<code>matlab.object</code>

MATLAB Array Type to Python Type Mapping

MATLAB Output Argument Type — Array	Resulting Python Data Type
Numeric array	<code>matlab</code> numeric array object (see “MATLAB Arrays as Python Variables”)
char array (1-by-N, N-by-1) returned to Python 3.3 or 3.4	str
char array (1-by-N, N-by-1) returned to Python 2.7	str (when MATLAB char array has values less than or equal to <code>intmax('uint8')</code>) unicode (when MATLAB char array has any value greater than <code>intmax('uint8')</code>)
Row or column cell array	list

Unsupported MATLAB Types

The following MATLAB data types are not supported by the MATLAB Engine for Python:

- Categorical array
- char array (M-by-N)
- Cell array (M-by-N)
- Function handle
- Sparse array

- Structure array
- Table
- MATLAB value objects (for a discussion of handle and value classes see “Comparing Handle and Value Classes”)
- Non-MATLAB objects (such as Java objects)

MATLAB Arrays as Python Variables

In this section...

“Create MATLAB Arrays in Python” on page 8-23

“MATLAB Array Attributes and Methods in Python” on page 8-25

“Multidimensional MATLAB Arrays in Python” on page 8-25

“Index Into MATLAB Arrays in Python” on page 8-25

“Slice MATLAB Arrays in Python” on page 8-26

“Reshape MATLAB Arrays in Python” on page 8-27

The `matlab` Python package provides array classes to represent arrays of MATLAB numeric types as Python variables so that MATLAB arrays can be passed between Python and MATLAB.

Create MATLAB Arrays in Python

You can create MATLAB numeric arrays in a Python session by calling constructors from the `matlab` Python package (for example, `matlab.double`, `matlab.int32`). The name of the constructor indicates the MATLAB numeric type. You can pass MATLAB arrays as input arguments to functions called with the MATLAB Engine for Python. When a MATLAB function returns a numeric array as an output argument, the engine returns the array to Python.

You can initialize the array with an optional `initializer` input argument that contains numbers. `initializer` must be a Python sequence type such as a list, tuple, or other array type. The optional `size` input argument sets the array size from a sequence. You can create multidimensional arrays by specifying `initializer` to contain multiple sequences of numbers, or by specifying `size` to be multidimensional. You can create a MATLAB array of complex numbers by setting the optional `is_complex` input argument to `True`. The `matlab` package provides the MATLAB array constructors listed in the table.

matlab Class	Constructor Call in Python
<code>matlab.double</code>	<code>matlab.double(initializer=None, size=None, is_complex=False)</code>

matlab Class	Constructor Call in Python
<code>matlab.single</code>	<code>matlab.single(initializer=None, size=None, is_complex=False)</code>
<code>matlab.int8</code>	<code>matlab.int8(initializer=None, size=None, is_complex=False)</code>
<code>matlab.int16</code>	<code>matlab.int16(initializer=None, size=None, is_complex=False)</code>
<code>matlab.int32</code>	<code>matlab.int32(initializer=None, size=None, is_complex=False)</code>
<code>matlab.int64^a</code>	<code>matlab.int64(initializer=None, size=None, is_complex=False)</code>
<code>matlab.uint8</code>	<code>matlab.uint8(initializer=None, size=None, is_complex=False)</code>
<code>matlab.uint16</code>	<code>matlab.uint16(initializer=None, size=None, is_complex=False)</code>
<code>matlab.uint32</code>	<code>matlab.uint32(initializer=None, size=None, is_complex=False)</code>
<code>matlab.uint64^b</code>	<code>matlab.uint64(initializer=None, size=None, is_complex=False)</code>
<code>matlab.logical</code>	<code>matlab.logical(initializer=None, size=None)^c</code>
<code>matlab.object</code>	No constructor. When a function returns a handle to a MATLAB object, the engine returns a <code>matlab.object</code> to Python.

- a. In Python 2.7 on Windows, `matlab.int64` is converted to `int32` in MATLAB. Also, MATLAB cannot return an `int64` array to Python.
- b. In Python 2.7 on Windows, `matlab.uint64` is converted to `uint32` in MATLAB. Also, MATLAB cannot return a `uint64` array to Python.
- c. Logicals cannot be made into an array of complex numbers.

When you create an array with N elements, the size is 1-by-N because it is a MATLAB array.

```
import matlab.engine
A = matlab.int8([1,2,3,4,5])
print(A.size)
```



```
(1, 5)
```

The initializer is a Python list containing five numbers. The MATLAB array size is 1-by-5, indicated by the tuple (1,5).

MATLAB Array Attributes and Methods in Python

All MATLAB arrays created with `matlab` package constructors have the attributes and methods listed in this table.

Attribute or Method	Purpose
<code>size</code>	Size of array returned as a tuple
<code>reshape(size)</code>	Reshape array as specified by sequence <code>size</code>

Multidimensional MATLAB Arrays in Python

In Python, you can create multidimensional MATLAB arrays of any numeric type. Use two Python lists of numbers to create a 2-by-5 MATLAB array of doubles.

```
import matlab.engine
A = matlab.double([[1,2,3,4,5], [6,7,8,9,10]])
print(A)

[[1.0,2.0,3.0,4.0,5.0],[6.0,7.0,8.0,9.0,10.0]]
```

The `size` attribute of `A` shows that it is a 2-by-5 array.

```
print(A.size)

(2, 5)
```

Index Into MATLAB Arrays in Python

You can index into MATLAB arrays just as you can index into Python lists and tuples.

```
import matlab.engine
A = matlab.int8([1,2,3,4,5])
print(A[0])

[1,2,3,4,5]
```

The size of the MATLAB array is (1,5); therefore, A[0] is [1,2,3,4,5]. Index into the array to get 3.

```
print(A[0][2])
```

```
3
```

Python indexing is zero-based. When you access elements of MATLAB arrays in a Python session, use zero-based indexing.

Index into a multidimensional MATLAB array.

```
A = matlab.double([[1,2,3,4,5], [6,7,8,9,10]])
print(A[1][2])
```

```
8.0
```

Slice MATLAB Arrays in Python

You can slice MATLAB arrays the same way you slice Python lists and tuples.

```
import matlab.engine
A = matlab.int8([1,2,3,4,5])
print(A[0][1:4])
```

```
[2,3,4]
```

You can assign data to a slice. This code shows assignment from a Python list to a slice of an array.

```
A = matlab.double([[1,2,3,4],[5,6,7,8]]);
A[0] = [10,20,30,40]
print(A)
```

```
[[10.0,20.0,30.0,40.0],[5.0,6.0,7.0,8.0]]
```

You can assign data from another MATLAB array, or from any Python iterable that contains numbers.

You can specify slices for assignment as shown here.

```
A = matlab.int8([1,2,3,4,5,6,7,8]);
A[0][2:4] = [30,40]
A[0][6:8] = [70,80]
```

```
print(A)
[[1,2,30,40,5,6,70,80]]
```

Note: Slicing MATLAB arrays behaves differently from slicing a Python list. Slicing a MATLAB array returns a view instead of a shallow copy.

Given a MATLAB array and a Python list with the same values, assigning a slice results in different results as shown below.

```
A = matlab.int32([[1,2],[3,4],[5,6]])
L = [[1,2],[3,4],[5,6]]
A[0] = A[0][::-1]
L[0] = L[0][::-1]
print(A)

[[2,2],[3,4],[5,6]]

print(L)

[[2, 1], [3, 4], [5, 6]]
```

Reshape MATLAB Arrays in Python

You can reshape a MATLAB array in Python with the `reshape` method. Input argument `size` must be a sequence that preserves the number of elements. Use `reshape` to change a 1-by-9 MATLAB array to 3-by-3.

```
import matlab.engine
A = matlab.int8([1,2,3,4,5,6,7,8,9])
A.reshape((3,3))
print(A)

[[1,4,7],[2,5,8],[3,6,9]]
```

Use MATLAB Arrays in Python

This example shows how to create a MATLAB array in Python and pass it as the input argument to the MATLAB `sqrt` function.

The `matlab` package provides constructors to create MATLAB arrays in Python. The MATLAB Engine for Python can pass such arrays as input arguments to MATLAB functions, and can return such arrays as output arguments to Python. You can create arrays of any MATLAB numeric or logical type from Python sequence types.

Create a MATLAB array from a Python list. Call the `sqrt` function on the array.

```
import matlab.engine
eng = matlab.engine.start_matlab()
a = matlab.double([1,4,9,16,25])
b = eng.sqrt(a)
print(b)
```

```
[[1.0,2.0,3.0,4.0,5.0]]
```

The engine returns `b`, which is a 1-by-5 `matlab.double` array.

Create a multidimensional array. The `magic` function returns a 2-D `matlab.double` array to Python. Use a `for` loop to print each row on a separate line. (Press **Enter** again when you see the `...` prompt to close the loop and print.)

```
a = eng.magic(6)
for x in a: print(x)
...

[35.0,1.0,6.0,26.0,19.0,24.0]
[3.0,32.0,7.0,21.0,23.0,25.0]
[31.0,9.0,2.0,22.0,27.0,20.0]
[8.0,28.0,33.0,17.0,10.0,15.0]
[30.0,5.0,34.0,12.0,14.0,16.0]
[4.0,36.0,29.0,13.0,18.0,11.0]
```

Call the `tril` function to get the lower triangular portion of `a`. Print each row on a separate line.

```
b = eng.tril(a)
for x in b: print(x)
...
```

```
[35.0,0.0,0.0,0.0,0.0,0.0]
[3.0,32.0,0.0,0.0,0.0,0.0]
[31.0,9.0,2.0,0.0,0.0,0.0]
[8.0,28.0,33.0,17.0,0.0,0.0]
[30.0,5.0,34.0,12.0,14.0,0.0]
[4.0,36.0,29.0,13.0,18.0,11.0]
```

Related Examples

- “Call MATLAB Functions from Python” on page 8-9

More About

- “MATLAB Arrays as Python Variables” on page 8-23

Sort and Plot MATLAB Data from Python

This example shows how to sort data about patients into lists of smokers and nonsmokers in Python and plot blood pressure readings for the patients with MATLAB.

Start the engine, and read data about a set of patients into a MATLAB table. MATLAB provides a sample comma-delimited file, `patients.dat`, which contains information on 100 different patients.

```
import matlab.engine
eng = matlab.engine.start_matlab()
eng.eval("T = readtable('patients.dat');",nargout=0)
```

The MATLAB `readtable` function reads the data into a table. The engine does not support the MATLAB table data type. However, with the MATLAB `table2struct` function you can convert the table to a scalar structure, which is a data type the engine does support.

```
eng.eval("S = table2struct(T,'ToScalar',true);",nargout=0)
eng.eval("disp(S)",nargout=0)
```

```
        LastName: {100x1 cell}
           Gender: {100x1 cell}
             Age: [100x1 double]
        Location: {100x1 cell}
           Height: [100x1 double]
           Weight: [100x1 double]
            Smoker: [100x1 double]
        Systolic: [100x1 double]
        Diastolic: [100x1 double]
SelfAssessedHealthStatus: {100x1 cell}
```

You can pass `S` from the MATLAB workspace into your Python session. The engine converts `S` to a Python dictionary, `D`.

```
D = eng.workspace["S"]
```

`S` has fields that contain arrays. The engine converts cell arrays to Python lists, and numeric arrays to MATLAB arrays. Therefore, `D["LastName"]` is of data type `list`, and `D["Age"]` is of data type `matlab.double`.

Sort blood pressure readings into lists of smokers and nonsmokers. In `patients.dat`, the column `Smoker` indicated a smoker with logical 1 (true), and a nonsmoker with a logical 0 (false). Convert `D["Smoker"]` to a `matlab.logical` array for sorting.

```
smoker = matlab.logical(D["Smoker"])
```

Convert the `Diastolic` blood pressure readings and `Smoker` indicators into 1-by-100 MATLAB arrays for sorting.

```
pressure = D["Diastolic"]
pressure.reshape((1,100))
pressure = pressure[0]
smoker.reshape((1,100))
smoker = smoker[0]
```

Sort the `pressure` array into lists of blood pressure readings for smokers and nonsmokers. Python list comprehensions provide a compact method for iterating over sequences. With the Python `zip` function, you can iterate over multiple sequences in a single `for` loop.

```
sp = [p for (p,s) in zip(pressure,smoker) if s is True]
nsp = [p for (p,s) in zip(pressure,smoker) if s is False]
```

Display the length of `sp`, the blood pressure readings for smokers in a list.

```
print(len(sp))
```

```
34
```

Display the length of `nsp`, the list of readings for nonsmokers.

```
print(len(nsp))
```

```
66
```

Calculate the mean blood pressure readings for smokers and nonsmokers. Convert `sp` and `nsp` to MATLAB arrays before passing them to the MATLAB `mean` function.

```
sp = matlab.double(sp)
nsp = matlab.double(nsp)
print(eng.mean(sp))
```

```
89.9117647059
```

Display the mean blood pressure for the nonsmokers.

```
print(eng.mean(nsp))
```

```
79.3787878788
```

Plot blood pressure readings for the smokers and nonsmokers. Call the MATLAB `linspace` function to define two x -axes for plotting. You can plot the 34 smokers and 66 nonsmokers on the same scatter plot.

```
sdx = eng.linspace(1.0,34.0,34)
nsdx = eng.linspace(1.0,34.0,66)
```

Show the axes boundaries with the `box` function.

```
eng.figure(nargout=0)
eng.hold("on",nargout=0)
eng.box("on",nargout=0)
```

You must call the `figure`, `hold`, and `box` functions with `nargout=0`, because these functions do not return output arguments.

Plot the blood pressure readings for the smokers and nonsmokers, and label the plot. For many MATLAB functions, the engine can return a handle to a MATLAB graphics object. You can store a handle to a MATLAB object in a Python variable, but you cannot manipulate the object's properties in Python. You can pass MATLAB objects as input arguments to other MATLAB functions.


```
eng.scatter(sdx,sp,10,'blue')
<matlab.object object at 0x22d1510>
```

In the rest of this example, assign the output argument of MATLAB functions to `h` as a placeholder.

```
h = eng.scatter(nsdx,nsp,10,'red')
h = eng.xlabel("Patient (Anonymized)")
h = eng.ylabel("Diastolic Blood Pressure (mm Hg)")
h = eng.title("Blood Pressure Readings for All Patients")
h = eng.legend("Smokers","Nonsmokers")
```

Draw lines to show the average blood pressure readings for smokers and nonsmokers.

```
x = matlab.double([0,35])
y = matlab.double([89.9,89.9])
h = eng.line(x,y,"Color","blue")
h = eng.text(21.0,88.5,"89.9 (Smoker avg.)","Color","blue")
y = matlab.double([79.4,79.4])
h = eng.line(x,y,"Color","red")
h = eng.text(5.0,81.0,"79.4 (Nonsmoker avg.)","Color","red")
```

Get Help for MATLAB Functions from Python

In this section...

“How to Find MATLAB Help” on page 8-34

“Open MATLAB Help Browser from Python” on page 8-34

“Display MATLAB Help at Python Prompt” on page 8-35

How to Find MATLAB Help

From Python, you can access supporting documentation for all MATLAB functions. This documentation includes examples and describes input arguments, output arguments, and calling syntax for each function.

The MATLAB Engine for Python enables you to use the MATLAB `doc` and `help` functions. Use `doc` to open the MATLAB Help browser. Use `help` to get a brief description of a MATLAB function at the Python prompt.

Open MATLAB Help Browser from Python

From Python, you can use the Help browser to open MATLAB function reference pages and search the documentation.

For example, display the reference page for the MATLAB `plot` function. (Since `doc` returns no output arguments, you must set `nargout=0`.)

```
import matlab.engine
eng = matlab.engine.start_matlab()
eng.doc("plot",nargout=0)
```

The reference page includes a description of the function, examples, and links to related documentation.

Note: Click an example title, or on the arrow next to a title, if you do not see the examples on a MATLAB reference page. Examples can be expanded or collapsed within a page, and are collapsed by default.

If you call `eng.doc` with no positional arguments, it opens the Help browser. (You still must set the keyword argument `nargout=0`).

```
eng.doc(nargout=0)
```

To search the MATLAB documentation, type an expression in the search box at the top of any page in the Help browser. The browser returns a list of search results, highlighting words that match the expression.

Alternatively, you can search the documentation with the `docsearch` function. For example, search for pages that mention `plot`.

```
eng.docsearch("plot",nargout=0)
```

Display MATLAB Help at Python Prompt

Call the MATLAB `help` function to display help text for a function at the Python prompt. For example, display the help text for `erf`.

```
import matlab.engine
eng = matlab.engine.start_matlab()
eng.help("erf",nargout=0)
```

```
ERF Error function.
```

```
Y = ERF(X) is the error function for each element of X. X must be
real. The error function is defined as:
```

```
erf(x) = 2/sqrt(pi) * integral from 0 to x of exp(-t^2) dt.
```

```
See also ERFC, ERFCX, ERFINV, ERFCINV.
```

```
Other functions named erf:
```

```
codistributed/erf
gpuArray/erf
sym/erf
```

```
Reference page in Help browser
doc erf
```

The output displays the help text, but does not include any links to help for other MATLAB functions that might be mentioned.

Default Numeric Types in MATLAB and Python

MATLAB stores all numeric values as double-precision floating point numbers by default. This differs from Python, which stores some numbers as integers by default. Because of this difference, you might pass integers as input arguments to MATLAB functions that expect double-precision numbers.

Consider these variable assignments in MATLAB:

```
x = 4;  
y = 4.0;
```

Both `x` and `y` are of data type `double`. Now consider the same assignments in Python:

```
x = 4  
y = 4.0
```

`x` and `y` are of different numeric data types.

```
print(type(x))
```

```
<type 'int'>
```

```
print(type(y))
```

```
<type 'float'>
```

Most MATLAB functions take numeric input arguments of data type `double`. The best practice is to ensure that numbers you pass as input arguments to MATLAB functions are of Python data type `float`, not Python data type `int`. You can ensure that Python variables are floating point numbers if you:

- Make literals floating point numbers. For example, type `4.0` instead of `4`.
- Convert to data type `float`. For example, `x = float(4)` casts the number to data type `float`.
- Create a MATLAB array from a number or sequence. For example, `x = matlab.double([1,2,3,4,5])` creates an array of MATLAB data type `double` from a list of Python integers.

When you pass an integer to a MATLAB function that takes an input argument of data type `double`, the engine raises an error. See “MatlabExecutionError: Undefined Function” on page 8-41 for an example.

When you call a MATLAB function that does take integers as numeric input arguments, you can pass input arguments of Python data type `int` to the function.

System Requirements for MATLAB Engine for Python

In this section...
“Python Version Support” on page 8-38
“64-bit or 32-bit Versions of Python and MATLAB” on page 8-38
“Requirements for Building Python from Source” on page 8-39

Python Version Support

To use the MATLAB Engine for Python, you must have a supported version of the reference Python implementation (also known as CPython) installed on your system. The engine supports the following versions:

- version 2.7
- version 3.3
- version 3.4

To download and install Python, see “Install Supported Python Implementation”.

Note: For 64-bit MATLAB on Microsoft Windows systems, select the 64-bit Python version, called Windows x86-64 MSI installer.

To call Python from your operating system prompt, you must either add the full path to Python to your PATH environment variable, or include the full path when you call the Python interpreter.

To determine if you are calling a supported version, type `python -V` at your operating system prompt to display the Python version number.

For help on the Python language, see www.python.org/doc in the python.org documentation. For help on third-party or user-defined modules, refer to the product documentation.

64-bit or 32-bit Versions of Python and MATLAB

The architecture of MATLAB must match the architecture of Python. This means if you run a 64-bit version of Python, you can call only a 64-bit version of MATLAB with the

engine. Likewise, if you are running a 32-bit version of Python, you can call only a 32-bit version of MATLAB.

On the Python download site, downloads for Microsoft Windows platforms are 32-bit versions by default. To download the 64-bit version, choose options with the name *Windows x86-64 MSI installer*.

To test whether your version of Python is 32-bit or 64-bit, type the following code at the Python prompt:

```
import sys
print(sys.maxsize > 2**32)
```

This code returns `True` if the Python interpreter is 64-bit, and `False` if it is 32-bit. (See Cross Platform for more details.)

To test whether your version of MATLAB is 32-bit or 64-bit, from the MATLAB Command Window select **Help > About MATLAB** or use the `computer` function at the command prompt.

Requirements for Building Python from Source

If you build Python from source on a Linux or Mac system, configure the build with the `--enable-shared` option. The MATLAB Engine for Python must link to the Python shared library. The library builds only if you set the `--enable-shared` option.

To enable wide-unicode support for Python 2.7 on Linux, configure the build with the `--enable-unicode=ucs4` option. This configure option is not needed when you build any version of Python on Mac systems, or Python 3.3 or 3.4 on Linux.

Limitations to MATLAB Engine for Python

- The engine cannot connect to an instance of MATLAB that is already running. When you create an engine by calling `matlab.engine.start_matlab()`, you always start a new instance of MATLAB.
- The engine cannot start MATLAB on a remote machine.
- Python keyword arguments cannot be input arguments to MATLAB functions called with the engine. The engine passes only positional arguments to MATLAB functions.
- A recursive data structure cannot be passed as an input argument to a MATLAB function, or put into an engine workspace. (A recursive data structure is a Python data structure that includes itself as a value.)
- The MATLAB Engine for Python is not thread-safe.

Troubleshoot MATLAB Errors in Python

In this section...

“MATLAB Errors in Python” on page 8-41

“MatlabExecutionError: Undefined Function” on page 8-41

“SyntaxError: Expression Not Valid Target” on page 8-42

“SyntaxError: Invalid Syntax” on page 8-42

MATLAB Errors in Python

When a MATLAB function raises an error, the MATLAB Engine for Python stops the function and catches the exception raised by MATLAB. The engine copies the error message to a new Python exception. The engine raises the Python exception.

If the Python interpreter catches the exception, the interpreter displays the error message that came from MATLAB. You also can handle exceptions raised by the engine in your Python code. See the `matlab.engine.MatlabEngine` and `matlab.engine.FutureResult` reference pages for the types of exceptions that the engine can raise.

MatlabExecutionError: Undefined Function

Call the MATLAB `sqrt` function on an integer from Python. (This code sample omits the Python traceback and shows the error message only.)

```
import matlab.engine
eng = matlab.engine.start_matlab()
print(eng.sqrt(4))
```

```
matlab.engine.MatlabExecutionError: Undefined function 'sqrt' for input arguments of type
```

MATLAB defines a `sqrt` function, but expects the input argument to be of data type `double`, not an integer. However, the input argument is 4, and before it is passed to MATLAB, Python interprets 4 as an integer. The engine converts the Python integer to an `int64` MATLAB data type.

MATLAB and Python define different default types for numbers. If you type `x = 4` at the MATLAB command line, `x` is a MATLAB `double`. If you type `x = 4` at the Python command line, `x` is a Python `int`.

To avoid this error, specify input arguments that are of Python data type `float`. The engine converts this type to MATLAB `double`.

```
print(eng.sqrt(4.0))  
2.0
```

SyntaxError: Expression Not Valid Target

You can call the MATLAB `eval` function from Python to create MATLAB variables. (This code sample omits the Python traceback and shows the error message only.)

```
import matlab.engine  
eng = matlab.engine.start_matlab()  
eng.eval("x = 4;")
```

```
SyntaxError: Error: The expression to the left of the equals sign is not a valid target
```

When the engine calls `eval`, it passes a statement to MATLAB for execution. When you do not specify the input argument `nargout` input argument, the engine expects one output argument. However, this MATLAB statement returns no output arguments.

To avoid this error, specify `nargout` as 0 whenever the MATLAB function you call returns no output arguments.

```
eng.eval("x = 4;",nargout=0)
```

SyntaxError: Invalid Syntax

Call the MATLAB `print` function from Python 2.7 to print a plot you create with the MATLAB `surf` function.

```
import matlab.engine  
eng = matlab.engine.start_matlab()  
eng.eval("surf(peaks)",nargout=0)  
eng.print("-djpeg", "surf",nargout=0)  
  
File "<stdin>", line 1  
    eng.print("-djpeg", "surf",nargout=0)  
        ^
```

```
SyntaxError: invalid syntax
```

MATLAB and Python functions can have the same name. When this happens, the engine calls the MATLAB function.

However, the engine cannot directly call a MATLAB function that has a name that also is a reserved word in the Python language. For example, in Python 2.7, `print` is a reserved word. (In Python 3.3 and 3.4, the above code runs because `print` is a built-in function, not a reserved word.)

To avoid this error, call the MATLAB function with `eval`.

```
eng.eval("print('-djpeg','surf');",nargout=0)
```

If the MATLAB function is a function that you created, you can rename it so that its name is no longer a Python reserved word. The Python documentation lists reserved words:

- Python 2.7 reserved words (https://docs.python.org/2/reference/lexical_analysis.html#keywords)
- Python 3.3 and 3.4 reserved words (https://docs.python.org/3/reference/lexical_analysis.html#keywords)

Using Java Libraries from MATLAB

- “Using Java Libraries” on page 9-2
- “Bringing Java Classes into MATLAB Workspace” on page 9-4
- “Creating and Using Java Objects” on page 9-12
- “Invoking Methods on Java Objects” on page 9-20
- “Working with Java Arrays” on page 9-28
- “Passing Data to Java Methods” on page 9-45
- “Handling Data Returned from Java Methods” on page 9-55
- “Read URL” on page 9-61
- “Find Internet Protocol Address” on page 9-63
- “Create and Use Phone Book” on page 9-65
- “Java Heap Memory Preferences” on page 9-77

Using Java Libraries

In this section...
“Java Software Is Integral to MATLAB” on page 9-2
“When to Use Java Libraries in MATLAB” on page 9-2
“To Learn More About Java Programming Language” on page 9-3
“Platform Support for JVM Software” on page 9-3

Java Software Is Integral to MATLAB

Every installation of MATLAB includes Java Virtual Machine (JVM) software. You can use the Java interpreter via MATLAB commands, and you can create and run programs that create and access Java objects.

From MATLAB, you can:

- Access Java API (application programming interface) class packages that support essential activities such as I/O and networking. For example, the `URL` class provides convenient access to resources on the Internet.
- Access third-party Java classes
- Easily construct Java objects in MATLAB workspace
- Call Java object methods, using either Java or MATLAB syntax
- Pass data between MATLAB variables and Java objects

When to Use Java Libraries in MATLAB

The MATLAB Java interface is intended for MATLAB users who want to take advantage of the special capabilities of the Java programming language.

- You need to access, from MATLAB, the capabilities of available Java classes.
- You are familiar with object-oriented programming in Java or in another language, such as C++.
- You are familiar with the MATLAB Class System, or with “MEX-File Creation API”.

To Learn More About Java Programming Language

For a complete description of the Java language and for guidance in object-oriented software design and programming, consult outside resources.

Platform Support for JVM Software

To find out which version of JVM software MATLAB uses on your platform, type the following at the MATLAB prompt:

```
version -java
```

Bringing Java Classes into MATLAB Workspace

In this section...

“Introduction” on page 9-4

“Sources of Java Classes” on page 9-4

“Defining New Java Classes” on page 9-5

“Java Class Path” on page 9-5

“Making Java Classes Available in MATLAB Workspace” on page 9-6

“Loading Java Class Definitions” on page 9-8

“Simplifying Java Class Names” on page 9-9

“Locating Native Method Libraries” on page 9-10

“Java Classes Contained in a JAR File” on page 9-10

Introduction

You can draw from an extensive collection of existing Java classes or create your own class definitions to use with MATLAB. This section explains how to go about finding the class definitions that you need or how to create classes of your own design. Once you have the classes you need, defined in either individual `.class` files, packages, or Java Archive (JAR) files, you can make them available in the MATLAB workspace. This section also describes how to specify the native method libraries used by Java code.

Sources of Java Classes

Following are Java class sources that you can use in the MATLAB workspace:

- Java built-in classes — general-purpose class packages, such as `java.util`, included in the Java language. See your Java language documentation for descriptions of these packages.
- Third-party classes — packages of special-purpose Java classes.
- User-defined classes — Java classes or subclasses of existing classes that you define using a Java language development environment.

Defining New Java Classes

To define new Java classes and subclasses of existing classes, use a Java Development Kit external to MATLAB. For information on supported versions of JDK™ software, see the Supported and Compatible Compilers website.

After you create class definitions in `.java` files, use your Java compiler to produce `.class` files from them. The next step is to make the class definitions in those `.class` files available for you to use in MATLAB.

Java Class Path

MATLAB loads Java class definitions from files that are on the *Java class path*. The class path is a series of file and folder specifications that MATLAB uses to locate third-party and user-defined class definitions. When loading a Java class, MATLAB searches files and folders in the order they occur on the class path. The search ends when MATLAB finds a file that contains the class definition.

MATLAB segments the Java class path into a static path and a dynamic path. MATLAB provides the dynamic path as a convenience for when you develop your own Java classes. After you develop and debug a Java class, add the class to the static path.

To view the two path segments, use the `javaclasspath` function.

Static Path

Use the static path if you want the class functionality to run the same way it does in Java. Also, the static path offers better class loading performance than the dynamic path.

To add files to the static path, create a `javaclasspath.txt` file:

- 1 Create an ASCII text file and name the file `javaclasspath.txt`.
- 2 Enter the name of a Java class folder or jar file, one per line. For example:

```
c:\work\javaclasses
```
- 3 To simplify folder specifications in cross-platform environments, use these macros: `$matlabroot`, `$arch`, and `$jre_home`.
- 4 Save the file in your preferences folder. To view the location of the preferences folder, type:

```
prefdir
```

Alternatively, save the `javaclasspath.txt` file in your MATLAB startup folder. Classes specified in this file override classes specified in the `javaclasspath.txt` file in the preferences folder.

5 Restart MATLAB.

MATLAB reads the static class path only at startup. If you edit `javaclasspath.txt` or change your `.class` files while MATLAB is running, restart MATLAB to put those changes into effect.

If you do not want MATLAB to use the entries in the `javaclasspath.txt` file, start MATLAB with the `-nouserjavapath` option.

Note: Do not put Java classes on the static path if they have dependencies on classes on the dynamic path.

Dynamic Path

You can change class definitions on the dynamic path without restarting MATLAB. Therefore, it is useful to put a user-defined Java class definition on the dynamic path while you develop and debug the class.

MATLAB always searches the static path before the dynamic path.

To add a class to the dynamic path, use the `javaclasspath` and `javaaddpath` functions. To remove an entry, use the `javarmppath` function. These functions clear all existing variables and global variables in the workspace.

The dynamic path offers greater flexibility in changing the path. However, Java classes on the dynamic path might load more slowly than classes on the static path. Also, classes on the dynamic path might not behave identical to classes on the static path. If your class does not behave as expected, use the static path.

After developing a Java class, put the class on the static path.

Making Java Classes Available in MATLAB Workspace

To make third-party and user-defined Java classes available to MATLAB, place them on either the static or dynamic Java class path.

- To put classes on the static path, edit the `javaclasspath.txt` file.
- To put classes on the dynamic path, use the `javaclasspath`, `javaaddpath`, and `javarmppath` functions.

Making Individual (Unpackaged) Classes Available

You can use individual classes (classes that are not part of a package) in MATLAB. To make them available, specify the full path to the folder you want to use for the `.class` files.

For example, to make available your compiled Java classes in the file `d:\work\javaclasses\test.class`, add the following entry to the static or dynamic class path:

```
d:\work\javaclasses
```

To put this folder on the static class path, edit the `javaclasspath.txt` file, described in “Static Path” on page 9-5.

To put this folder on the dynamic class path, use the following command:

```
javaaddpath d:\work\javaclasses
```

Making Entire Packages Available

You can access classes in a package. To make a package available to MATLAB, specify the full path to the *parent folder of the highest level folder* of the package path. This folder is the first component in the package name.

For example, if your Java class package `com.mw.tbx.ini` has its classes in folder `d:\work\com\mw\tbx\ini`, add the following folder to your static or dynamic class path:

```
d:\work
```

Making Classes in a JAR File Available

You can use the `jar` (Java Archive) tool to create a JAR file, containing multiple Java classes and packages in a compressed ZIP format. For information on `jar` and JAR files, consult your Java development documentation.

To make the contents of a JAR file available for use in MATLAB, specify the full path, *including full file name*, for the JAR file. You also can put the JAR file on the MATLAB path.

Note: The path requirement for JAR files is different from the requirement for `.class` files and packages, for which you do not specify any file name.

For example, to make available the JAR file `e:\java\classes\utilpkg.jar`, add the following file specification to your static or dynamic class path:

```
e:\java\classes\utilpkg.jar
```

Loading a Class Using Java `Class.forName` Method

Use the `javaObjectEDT` function instead of the Java `Class.forName` method. For example, replace the following statement:

```
java.lang.Class.forName('xyz.myapp.MyClass')
```

with:

```
javaObjectEDT('xyz.myapp.MyClass')
```

Loading Java Class Definitions

Normally, MATLAB loads a Java class automatically when your code first uses it, for example, when you call its constructor. However, be aware of the following exception. When you use the `which` function on methods defined by Java classes, the function only acts on the classes currently *loaded* into the MATLAB workspace. In contrast, `which` always operates on MATLAB classes, whether they are loaded.

Determining Which Classes Are Loaded

At any time during a MATLAB session, you can obtain a listing of all the Java classes that are currently loaded. To do so, use the `inmem` function as follows:

```
[M,X,J] = inmem
```

This function returns the list of Java classes in the output argument `J`. (It also returns the names of all currently loaded MATLAB functions in `M`, and the names of all currently loaded MEX-files in `X`.)

Here is a sample of output from the `inmem` function:

```
[m,x,j] = inmem;
```

```
j
```

MATLAB displays:

```
j =
'java.util.Date'
'com.mathworks.ide.desktop.MLDesktop'
```

Simplifying Java Class Names

Your MATLAB commands can refer to any Java class by its fully qualified name, which includes its package name. For example, the following are fully qualified names:

- `java.lang.String`
- `java.util.Enumeration`

A fully qualified name can be long, making commands and functions, such as constructors, cumbersome to edit and to read. To refer to classes by the class name alone (without a package name), first import the fully qualified name into MATLAB.

MATLAB adds all classes that you import to a list called the *import list*. You can see what classes are on that list by typing `import`, without any arguments. Your code can refer to any class on the list by class name alone.

When called from a function, `import` adds the specified classes to the import list in effect for that function. When invoked at the command prompt, `import` uses the base import list for your MATLAB platform.

For example, suppose that a function contains the following statements:

```
import java.lang.String
import java.util.* java.awt.*
import java.util.Enumeration
```

Any code that follows these `import` statements can refer to the `String`, `Frame`, and `Enumeration` classes without using the package names. For example:

```
str = String('hello');    % Create java.lang.String object
frm = Frame;              % Create java.awt.Frame object
methods Enumeration      % List java.util.Enumeration methods
```

To remove the list of imported Java classes, type:

```
clear import
```

Locating Native Method Libraries

Java classes can dynamically load native methods using the Java method `java.lang.System.loadLibrary("LibFile")`. In order for the JVM software to locate the specified library file, the folder containing it must be on the Java Library Path. This path is established when the MATLAB runs the JVM software at startup.

You can augment the search path for native method libraries by creating an ASCII text file named `javalibrarypath.txt` in your preferences folder. Follow these guidelines when editing this file:

- Specify each new folder on a line by itself.
- Specify only the folder names, not the names of the DLL files. The `loadLibrary` call reads the file names.
- To simplify the specification of directories in cross-platform environments, use any of these macros: `$matlabroot`, `$arch`, and `$jre_home`.

You also can create a `javalibrarypath.txt` file in your MATLAB startup folder. Libraries specified in this file override libraries specified in the `javalibrarypath.txt` file in the preferences folder.

To disable using the `javalibrarypath.txt` file, execute MATLAB with the `-nouserjavapath` option.

Java Classes Contained in a JAR File

You can access Java classes that are contained in a JAR file once you have added the JAR file to either the static or dynamic class path. See “Java Class Path” on page 9-5 for more information on how MATLAB uses the Java class path.

For example, suppose that you have a file, `myArchive.jar`, in a folder called `work` in your MATLAB root folder. You can construct the path to this file using the `matlabroot` command:

```
[matlabroot '/work/myArchive.jar']
```

Add the JAR file to your dynamic class path using the `javaaddpath` function (`fullfile` adds the platform-correct folder separators):

```
javaaddpath(fullfile(matlabroot, 'work', 'myArchive.jar'))
```

You can now call the public methods in the JAR file. For information about these methods, refer to the JAR file documentation.

Creating and Using Java Objects

In this section...

“Overview” on page 9-12

“Constructing Java Objects” on page 9-12

“Concatenating Java Objects” on page 9-14

“Saving and Loading Java Objects to MAT-Files” on page 9-15

“Finding the Public Data Fields of an Object” on page 9-16

“Accessing Private and Public Data” on page 9-17

“Determining the Class of an Object” on page 9-18

Overview

You create a Java object in the MATLAB workspace by calling one of the constructors of that class. You then use commands and programming statements to perform operations on these objects. You also can save your Java objects to a MAT-file and, in subsequent sessions, reload them into MATLAB.

Constructing Java Objects

You construct Java objects in the MATLAB workspace by calling the Java class constructor, which has the same name as the class. For example, the following constructor creates a `myDate` object:

```
myDate = java.util.Date  
  
myDate =  
Thu Aug 23 12:58:54 EDT 2007
```

MATLAB displays information for your system.

Using the `javaObjectEDT` Function

Under certain circumstances, use the `javaObjectEDT` function to construct a Java object. The following syntax invokes the Java constructor for class, `class_name`, with the argument list that matches `x1, . . . , xn`, and returns a new object, `J`.


```
J = javaObjectEDT('class_name',x1,...,xn);
```

For example, to construct and return a Java object of class `java.lang.String`, type:

```
jstr = javaObjectEDT('java.lang.String','hello');
```

With the `javaObjectEDT` function you can:

- Use classes that have names that exceed the maximum length of a MATLAB identifier. (Call the `namelengthmax` function to obtain the maximum identifier length.)
- Specify the class for an object at run time, for example, as input from an application user

The default MATLAB constructor syntax requires that no segment of the input class name can be longer than `namelengthmax` characters. (A *class name segment* is any portion of the class name before, between, or after a dot. For example, there are three segments in class, `java.lang.String`.) MATLAB truncates any class name segment that exceeds `namelengthmax` characters. In the rare case where you use a class name of this length, use `javaObjectEDT` to instantiate the class.

The `javaObjectEDT` function also allows you to specify the Java class for the object being constructed at run time. In this situation, you call `javaObjectEDT` with a string variable in place of the class name argument.

```
class = 'java.lang.String';  
text = 'hello';  
jstr = javaObjectEDT(class, text);
```

In the usual case, when the class to instantiate is known at development time, it is more convenient to use the MATLAB constructor syntax. For example, to create a `java.lang.String` object, type:

```
jstr = java.lang.String('hello');
```

Use the `javaObjectEDT` function instead of the Java `Class.forName` method. For example, replace the following statement:

```
java.lang.Class.forName('xyz.myapp.MyClass')
```

with:

```
javaObjectEDT('xyz.myapp.MyClass')
```

Note: Typically, you do not need to use `javaObjectEDT`. The default MATLAB syntax for instantiating a Java class is simpler and is preferable for most applications. Use `javaObjectEDT` primarily for the previously described cases.

Java Objects Are References in MATLAB Applications

In MATLAB, Java objects are *references* and do not adhere to MATLAB copy-on-assignment and pass-by-value rules. For example:

```
myDate = java.util.Date;
setHours(myDate,10)
newDate = myDate;
```

In this example, the variable `newDate` is a reference to `myDate`, not a copy of the object. Any change to the object referenced by `newDate` also changes the object at `myDate`. Either MATLAB code or Java code might change the object.

The following example shows that `myDate` and `newDate` are references to the same object. When you change the hour via one reference (`newDate`), the change is reflected through the other reference (`myDate`), as well.

```
setHours(newDate,8)
getHours(myDate)

ans =
     8
```

Concatenating Java Objects

You can concatenate Java objects in the same way that you concatenate native MATLAB types. You use either the `cat` function or the `[]` operators to tell MATLAB to assemble the enclosed objects into a single object.

Concatenating Objects of the Same Class

If concatenate objects of the same Java class, the concatenation is an array of objects from the same class.

In the following example, the `cat` function concatenates two objects of the class `java.awt.Integer`. The class of the result is also `java.awt.Integer`.

```
value1 = java.lang.Integer(88);
value2 = java.lang.Integer(45);
```

```

cat(1, value1, value2)

ans =
java.lang.Integer[]:
    [88]
    [45]

```

Concatenating Objects of Unlike Classes

If you concatenate objects of unlike classes, MATLAB finds one class from which all of the input objects inherit. The concatenation is an instance of this class. MATLAB selects the lowest common parent in the Java class hierarchy as the output class.

For example, concatenating objects of `java.lang.Byte`, `java.lang.Integer`, and `java.lang.Double` creates an object of the common parent to the three input classes, `java.lang.Number`.

```

byte = java.lang.Byte(127);
integer = java.lang.Integer(52);
double = java.lang.Double(7.8);
[byte integer double]

ans =
java.lang.Number[]:
    [ 127]
    [ 52]
    [7.8000]

```

If there is no common, lower-level parent, then the resultant class is `java.lang.Object`, which is the root of the entire Java class hierarchy.

```

byte = java.lang.Byte(127);
point = java.awt.Point(24,127);
[byte point]

ans =
java.lang.Object[]:
    [ 127]
    [1x1 java.awt.Point]

```

Saving and Loading Java Objects to MAT-Files

Use the `save` function to save a Java object to a MAT-file. To load it back into MATLAB from that MAT-file, use the `load` function. When you save or load a Java object, the object and its class must meet all of the following criteria.

- The class implements the `Serializable` interface (part of the Java API), either directly or by inheriting it from a parent class. Any embedded or otherwise referenced objects must also implement `Serializable`.
- The definition of the class is not changed between saving and loading the object. Any change to the data fields or methods of a class prevents the loading (deserialization) of an object that was constructed with the old class definition.
- Either the class does not have any transient data fields, or the values in transient data fields of the object to be saved are not significant. Values in transient data fields are never saved with the object.

If you define your own Java classes, or subclasses of existing classes, follow this criteria to enable saving and loading objects of the class in MATLAB. For details on defining classes to support serialization, consult your Java development documentation.

Finding the Public Data Fields of an Object

To list the public fields that belong to a Java object, use the `fieldnames` function, which takes either of these forms.

```
names = fieldnames(obj)
names = fieldnames(obj, '-full')
```

Calling `fieldnames` without `-full` returns the names of all the data fields (including inherited) on the object. With the `-full` qualifier, `fieldnames` returns the full description of the data fields defined for the object, including type, attributes, and inheritance information.

For example, create an `Integer` object with the command:

```
value = java.lang.Integer(0);
```

To see a full description of the data fields of `value`, type:

```
fieldnames(value, '-full')

ans =
    'static final int MIN_VALUE'
    'static final int MAX_VALUE'
    'static final java.lang.Class TYPE'
    'static final int SIZE'
```

Accessing Private and Public Data

Java API classes provide accessor methods you can use to read from and, where allowed, to modify *private* data fields. These methods are sometimes referred to as *get* and *set* methods, respectively.

Some Java classes have *public* data fields, which your code can read or modify directly. To access these fields, use the syntax `object.field`.

Examples

The `java.awt.Frame` class provides an example of access to both private and public data fields. This class has the read accessor method `getSize`, which returns a `java.awt.Dimension` object. The `Dimension` object has data fields `height` and `width`, which are public and therefore directly accessible. For example, to access this data, type:

```
frame = java.awt.Frame;  
frameDim = getSize(frame);  
height = frameDim.height;  
frameDim.width = 42;
```

The sample code for “Find Internet Protocol Address” on page 9-63 uses calls to data field accessors on a `java.net.InetAddress` object.

```
hostname = address.getHostNam;e;  
ipaddress = address.getHostAddress;
```

Accessing Data from a Static Field

In a Java language program, a *static data field* is a field that applies to an entire class of objects. Static fields are most commonly accessed in relation to the class name itself. For example, the following code accesses the `TYPE` field of the `Integer` class using the package and class names, `java.lang.Integer`.

```
thisType = java.lang.Integer.TYPE;
```

In MATLAB, you can use that same syntax. Or you can refer to the `TYPE` field as an instance of the class. The following example creates an instance of `java.lang.Integer` called `value`, and then accesses the `TYPE` field using the name `value` rather than the package and class names.

```
value = java.lang.Integer(0);  
thatType = value.TYPE
```

```
thatType =  
int
```

Assigning to a Static Field

Assign values to static fields using the static `set` method of the class. Alternatively, assign values using an instance of the class. For more information, see “Accessing Data from a Static Field” on page 9-17. You can assign `value` to the field `staticFieldName` in the following example by referring to this field as an instance of the class.

```
objectName = java.className;  
objectName.staticFieldName = value;
```

Note: MATLAB does not allow assignment to static fields using the class name itself.

Determining the Class of an Object

To find the class of a Java object, use the query form of the `class` function. After execution of the following example, `myClass` contains the name of the package and class that the object `value` instantiates.

```
value = java.lang.Integer(0);  
myClass = class(value)
```

```
myClass =  
java.lang.Integer
```

Because this form of `class` also works on MATLAB objects, it does not, in itself, tell you whether it is a Java class. To determine the type of class, use the `isjava` function, which returns 1 if `obj` is a Java object, and 0 if it is not. For example, type:

```
isjava(value)
```

```
ans =  
    1
```

To find out if an object is an instance of a specified class, use the `isa` function. The class can be a MATLAB built-in or user-defined class, as well as a Java class. For example, type:

```
isa(value, 'java.lang.Integer')
```

```
ans =  
  1
```

Invoking Methods on Java Objects

In this section...

- “Calling Syntax” on page 9-20
- “Obtaining Method Information” on page 9-22
- “Java Methods That Affect MATLAB Commands” on page 9-25
- “How MATLAB Handles Undefined Methods” on page 9-26
- “Handling Java Exceptions” on page 9-27
- “Method Execution in MATLAB” on page 9-27

Calling Syntax

To call methods on Java objects, you can use either Java calling syntax or MATLAB calling syntax. Under certain circumstances, use the MATLAB `javaMethod` function.

- “Java Calling Syntax” on page 9-20
- “MATLAB Calling Syntax” on page 9-20
- “Using the `javaMethod` Function” on page 9-21
- “Calling Syntax for Static Methods of Java Classes” on page 9-21

Java Calling Syntax

To call methods on Java objects, use the Java syntax:

```
object.method(arg1, . . . , argn)
```

For example, to call the `getHours` and `setHours` methods of a `java.util.Date` object:

```
myDate = java.util.Date;  
setHours(myDate,3)  
getHours(myDate)
```

```
ans =  
    3
```

MATLAB Calling Syntax

To call methods on Java objects, use the MATLAB syntax:


```
method(object, arg1, ..., argn)
```

For example, to call the `getHours` and `setHours` methods using MATLAB syntax:

```
m1Date = java.util.Date;  
setHours(m1Date, 3)  
getHours(m1Date)
```

```
ans =  
    3
```

Using the `javaMethod` Function

Use the MATLAB `javaMethod` function to:

- Use Java methods with names that exceed the maximum length of a MATLAB identifier. (Call the `namelengthmax` function to obtain the maximum identifier length.)
- Specify a Java method to invoke at run time.

For example, your code calls `javaMethod` with a string variable in place of the `method` argument. When you use `javaMethod` to invoke a static method, you also can use a string variable in place of the class name argument.

Note: The MATLAB syntax is the preferred syntax for invoking a Java method. Use `javaMethod` for these special cases only.

Calling Syntax for Static Methods of Java Classes

To invoke a static method on a Java class, use the Java syntax:

```
class.method(arg1, ..., argn)
```

For example, call the static method, `isNaN`:

```
java.lang.Double.isNaN(2.2)
```

```
ans =  
    0
```

Obtaining Method Information

MATLAB provides the `methods` and `methodsview` functions to obtain information about the Java methods you are using. You also can request a listing of every Java class that you loaded into MATLAB that implements a specified method.

- “Using methods to Display Method Names and Arguments” on page 9-22
- “Using methodsview to Display Argument Types and Exceptions” on page 9-23
- “Using which to Determine What Classes Define a Method” on page 9-24

Using methods to Display Method Names and Arguments

The `methods` function returns information on methods of MATLAB and Java classes.

To return the names of all the methods (including inherited methods) of the class, use `methods` without the `'-full'` qualifier. Names of overloaded methods are listed only once.

With the `'-full'` qualifier, `methods` returns a listing of the method names (including inherited methods) along with attributes, argument lists, and inheritance information on each. Each overloaded method is listed separately.

For example, display a full description of all methods of the `java.awt.Dimension` object.

```
methods java.awt.Dimension -full
```

```
Methods for class java.awt.Dimension:
Dimension()
Dimension(java.awt.Dimension)
Dimension(int,int)
java.lang.Class getClass() % Inherited from java.lang.Object
int hashCode() % Inherited from java.lang.Object
boolean equals(java.lang.Object)
java.lang.String toString()
void notify() % Inherited from java.lang.Object
void notifyAll() % Inherited from java.lang.Object
void wait(long) throws java.lang.InterruptedException
    % Inherited from java.lang.Object
void wait(long,int) throws java.lang.InterruptedException
    % Inherited from java.lang.Object
void wait() throws java.lang.InterruptedException
    % Inherited from java.lang.Object
```

```
java.awt.Dimension getSize()
void setSize(java.awt.Dimension)
void setSize(int,int)
```


Using `methodsview` to Display Argument Types and Exceptions

To see methods implemented by a particular Java (or MATLAB) class, use the `methodsview` function. Specify the class name (along with its package name, for Java classes) in the command line. If you have imported the package that defines this class, then the class name alone suffices.

The following command lists information on all methods in the `java.awt.MenuItem` class. Type:

```
methodsview java.awt.MenuItem
```

A new window appears, listing one row of information for each method in the class.



Qualifiers	Return Type	Name	Arguments
		MenuItem	()
		MenuItem	(java.lang.String)
		MenuItem	(java.lang.String,java.awt.MenuShortcut)
synchronized	void	addActionListener	(java.awt.event.ActionListener)
	void	addNotify	()
	void	deleteShortcut	()
synchronized	void	disable	()
	void	dispatchEvent	(java.awt.AWTEvent)
synchronized	void	enable	()
	void	enable	(boolean)
	boolean	equals	(java.lang.Object)
	java.lang.String	getActionCommand	()
	java.lang.Class	getClass	()
	java.awt.Font	getFont	()
	java.lang.String	getLabel	()
	java.lang.String	getName	()
	java.awt.MenuContainer	getParent	()
	java.awt.peer.MenuComponentPeer	getPeer	()
	java.awt.MenuShortcut	getShortcut	()
	int	hashCode	()
	boolean	isEnabled	()
	void	notify	()
	void	notifyAll	()

Each row in the window displays up to six fields of information describing the method. The following table lists the fields displayed in the `methodsview` window along with a description and examples of each field type.

Fields Displayed in `methodsview` Window

Field Name	Description	Examples
Qualifiers	Method type qualifiers	abstract, synchronized
Return Type	Type returned by the method	void, java.lang.String
Name	Method name	addActionListener, dispatchEvent
Arguments	Types of arguments passed to method	boolean, java.lang.Object
Other	Other relevant information	throws java.io.IOException
Inherited From	Parent of the specified class	java.awt.MenuComponent

Using `which` to Determine What Classes Define a Method

Use the `which` function to display the fully qualified name (package and class name) of a method implemented by a *loaded* Java class. To find all classes that define the specified method, use the `which` function with the `-all` qualifier.

For example, suppose you want to find the package and class name for the `concat` method. Type:

```
which concat
```

If the `java.lang.String` class is loaded, MATLAB displays:

```
concat is a Java method % java.lang.String method
```

If the `String` class has not been loaded, MATLAB displays:

```
concat not found.
```

Suppose that you loaded the Java `String` and `java.awt.Frame` classes. Both of these classes have an `equals` method. Type:

```
which -all equals
```

The MATLAB display includes entries like the following:

```

equals is a Java method      % java.lang.String method
equals is a Java method      % java.awt.Frame.equals
equals is a Java method      % com.mathworks.jmi.MatlabPath method

```

The `which` function operates differently on Java classes than it does on MATLAB classes. `which` always displays MATLAB classes, whether they are loaded. `which` only displays Java classes that are loaded. You can find out which Java classes are currently loaded by using the command `[m,x,j]=inmem`, described in “Determining Which Classes Are Loaded” on page 9-8.

For a description of how Java classes are loaded, see “Making Java Classes Available in MATLAB Workspace” on page 9-6.

Java Methods That Affect MATLAB Commands

MATLAB commands that operate on Java objects and arrays use the methods that are implemented within, or inherited by, these objects' classes. There are some MATLAB commands that you can alter in behavior by changing the Java methods that they use.

Changing the Effect of `disp` and `display`

You are calling the `disp` function when you:

- Display the value of a variable or an expression in MATLAB.
- Terminate a command line without a semicolon.
- Display a Java object in MATLAB.

When calling `disp` on a Java object, MATLAB formats the output using the object `toString` method. If the class does not implement this method, then MATLAB uses an inherited `toString` method. If no intermediate ancestor classes define this method, MATLAB uses the `toString` method defined by the `java.lang.Object` class.

To change the way MATLAB displays an object, implement your own `toString` method in your class definition.

Changing the Effect of `isequal`

The MATLAB `isequal` function compares two or more arrays for equality in type, size, and contents. Also, you can use this function to test Java objects for equality.

When you compare two Java objects using `isequal`, MATLAB performs the comparison using the Java method, `equals`. MATLAB first determines the class of the objects specified in the command, and then uses the `equals` method implemented by that class. If `equals` is not implemented in this class, then MATLAB uses an inherited `equals` method. If no intermediate ancestor classes define this method, MATLAB uses the `equals` method defined by the `java.lang.Object` class.

To change the way MATLAB compares members of a class, implement your own `equals` method in your class definition.

Changing the Effect of `double` and `char`

You can change the output of the MATLAB `double` and `char` functions by defining your own Java methods, `toDouble` and `toChar`. For more information, see “Converting to the MATLAB double Type” on page 9-57 and “Converting to the MATLAB char Type” on page 9-58.

How MATLAB Handles Undefined Methods

If your MATLAB command invokes a nonexistent method on a Java object, MATLAB looks for a function with the same name. If MATLAB finds a function of that name, it attempts to invoke it. If MATLAB does not find a function with that name, it displays a message stating that it cannot find a method by that name for the class.

For example, MATLAB has a function named `size`, and the Java API `java.awt.Frame` class also has a `size` method. If you call `size` on a `Frame` object, the `size` method defined by `java.awt.Frame` is executed. However, if you call `size` on an object of `java.lang.String`, MATLAB does not find a `size` method for this class. It executes the MATLAB `size` function instead.

```
string = java.lang.String('hello');  
size(string)
```

```
ans =  
    1    1
```

Note: When you define a Java class for use in MATLAB, avoid giving any of its methods the same name as a MATLAB function.

Handling Java Exceptions

Use the `matlab.exception.JavaException` class to handle Java exceptions.

Method Execution in MATLAB

When calling a `main` method from MATLAB, the method returns when it executes its last statement, even if the method creates a thread that is still executing. In other environments, the `main` method does not return until the thread completes execution.

You, therefore, be cautious when calling `main` methods from MATLAB, particularly `main` methods that start a user interface. `main` methods are written assuming they are the entry point to application code. When called from MATLAB this is not the case, and the fact that other Java UI code might be already running can lead to problems.

Working with Java Arrays

In this section...

“Introduction” on page 9-28

“How MATLAB Represents the Java Array” on page 9-28

“Creating an Array of Objects in MATLAB” on page 9-32

“Accessing Elements of a Java Array” on page 9-35

“Assigning to a Java Array” on page 9-38

“Concatenating Java Arrays” on page 9-41

“Creating a New Array Reference” on page 9-42

“Creating a Copy of a Java Array” on page 9-43

Introduction

You can pass singular Java objects to and from methods or you can pass them in an array, providing the method expects them in that form. This array must either be a Java array (returned from another method call or created within the MATLAB) or, under certain circumstances, a MATLAB cell array. This section describes how to create and manipulate Java arrays in MATLAB. Later sections describe how to use MATLAB cell arrays in calls to Java methods.

Note: The term *dimension* refers to the number of subscripts required to address the elements of an array. Dimension is not a measure of length, width, and height. For example, a 5-by-1 array is one-dimensional, as its individual elements can be indexed using one subscript.

How MATLAB Represents the Java Array

The term *Java array* refers to any array of Java objects returned from a call to a Java class constructor or method. You can also construct a Java array within MATLAB using the `javaArray` function. The structure of a Java array is different from the structure of a MATLAB matrix or array. MATLAB *hides* these differences whenever possible, allowing you to operate on the arrays using the usual MATLAB command syntax. Just the same, keep in mind the following differences as you work with Java arrays.

- “Representing More Than One Dimension” on page 9-29
- “Array Indexing” on page 9-30
- “The Shape of the Java Array” on page 9-31
- “Interpreting the Size of a Java Array” on page 9-31
- “Interpreting the Number of Dimensions of a Java Arrays” on page 9-32


Representing More Than One Dimension

An array in the Java language is strictly a one-dimensional structure because it is measured only in length. If you want to work with a two-dimensional array, you can create an equivalent structure using an array of arrays. To add further dimensions, you add more levels to the array, making it an array of arrays of arrays, and so on. You can use such multilevel arrays when working in MATLAB, as it is a matrix and array-based programming language.


MATLAB makes it easy for you to work with multilevel Java arrays by treating them like the matrices and multidimensional arrays that are a part of the language itself. You access elements of an array of arrays using the same MATLAB syntax that you use if you are handling a matrix. If you add more levels to the array, MATLAB can access and operate on the structure as if it is a multidimensional MATLAB array.

The left side of the following figure shows Java arrays of one, two, and three dimensions. To the right of each representation is the same array represented in MATLAB. Single-dimension arrays are represented as column vectors.


Array Access from Java



Simple Array




Array of Arrays




Array of Arrays of Arrays


Array Access from MATLAB



One-dimensional Array



Two-Dimensional Array



Three-Dimensional Array

Array Indexing

Java array indexing is different than MATLAB array indexing. Java array indices are zero-based, MATLAB array indices are one-based. In Java programming, you access the elements of array y of length N using $y[0]$ through $y[N-1]$. When working with this array in MATLAB, you access these same elements using the MATLAB indexing style of $y(1)$ through $y(N)$. Thus, if you have a Java array of 10 elements, the seventh element is obtained using $y(7)$, and not $y[6]$ as you use when writing a Java language program.

The Shape of the Java Array

A Java array can be different from a MATLAB array in its overall *shape*. A two-dimensional MATLAB array maintains a rectangular shape, as each row is of equal length and each column of equal height. The Java counterpart, an array of arrays, does not necessarily hold to this rectangular form. Each individual lower level array might have a different length.

The following picture shows an array of three underlying arrays of different lengths. The terms *jagged* or *ragged* are commonly used to describe this arrangement of array elements as the array ends do not match up evenly. When a Java method returns an array with this type of structure, it is stored in a cell array by MATLAB.




Interpreting the Size of a Java Array

Calling the MATLAB `size` function on a Java array returns the length of the Java array. The number of columns is always 1.

Determining the size of a Java array of arrays is not so simple. The potentially ragged shape of an array returned from a Java method makes it impossible to size the array in the same way as for a rectangular matrix. In a ragged Java array, there is no single value that represents the size of the lower-level arrays.

When the `size` function is applied to a Java array of arrays, the resulting value describes the top level of the specified array. For the Java array:



`size(A)` returns the dimensions of the highest array level of A. The highest level of the array has a size of 3-by-1.

```
size(A)
ans =
     3     1
```

To find the size of a lower-level array, say the five-element array in row 3, refer to the row explicitly.

```
size(A(3))
ans =
     5     1
```

You can specify a dimension in the `size` command using the following syntax. However, this is useful only for sizing the first dimension, `dim=1`, the only non-unary dimension.

```
m = size(X,dim)
size(A, 1)
ans =
     3
```

Interpreting the Number of Dimensions of a Java Arrays

The MATLAB `ndims` function always returns a value of 2 for the number of dimensions in a Java array. This is the number of dimensions in the top-level array.

Creating an Array of Objects in MATLAB

To call a Java method that has one or more arguments defined as an array of Java objects, you must, under most circumstances, pass your objects in a Java array. You can construct an array of objects in a call to a Java method or constructor. Or you can create the array within MATLAB.

The MATLAB `javaArray` function lets you create a Java array structure that can be handled in MATLAB as a single multidimensional array. You specify the number and size of the array dimensions along with the class of objects you intend to store in it. Using the one-dimensional Java array as its primary building block, MATLAB then builds an array structure that satisfies the dimensions requested in the `javaArray` command.

- “Using the `javaArray` Function” on page 9-33
- “Using MATLAB Syntax” on page 9-33

Using the javaArray Function

To create a Java object array, use the MATLAB `javaArray` function, which has the following syntax:

```
A = javaArray('element_class', m, n, p, ...)
```

The first argument is the `'element_class'` string, which names the class of the elements in the array. Specify the fully qualified name (package and class name). The remaining arguments (`m`, `n`, `p`, ...) are the number of elements in each dimension of the array.

An array that you create with `javaArray` is equivalent to the array that you create with the Java code.

```
A = new element_class[m][n][p]...;
```

The following command builds a Java array of four lower-level arrays, each capable of holding five objects of the `java.lang.Double` class.

```
dblArray = javaArray('java.lang.Double',4,5);
```

The `javaArray` function does not deposit any values into the array elements that it creates. You must do this separately. The following MATLAB code stores objects of the `java.lang.Double` type in the Java array `dblArray` that was created.

```
for m = 1:4
    for n = 1:5
        dblArray(m,n) = java.lang.Double((m*10) + n);
    end
end
```

```
dblArray
```

```
dblArray =
java.lang.Double[][]:
    [11]    [12]    [13]    [14]    [15]
    [21]    [22]    [23]    [24]    [25]
    [31]    [32]    [33]    [34]    [35]
    [41]    [42]    [43]    [44]    [45]
```

Using MATLAB Syntax

You also can create an array of Java objects using syntax that is more typical to MATLAB. For example, the following syntax creates a 4-by-5 MATLAB array of type `double` and assigns zero to each element of the array.

```
matlabArr(4,5) = 0;
```

You use similar syntax to create a Java array in MATLAB, except that you specify the Java class name. The value being assigned, 0 in this example, is stored in the final element of the array, `javaArr(4,5)`. All other elements of the array receive the empty matrix.

```
javaArr(4,5) = java.lang.Double(0)
```

```
javaArr =  
java.lang.Double[][]:  
    []    []    []    []    []  
    []    []    []    []    []  
    []    []    []    []    []  
    []    []    []    []    [0]
```

Note: You cannot change the number of dimensions of an existing Java array as you can with a MATLAB array. The same restriction exists when working with Java arrays in the Java language. See the following example.

This example first creates a scalar MATLAB array, and then changes it to a 2D array.

```
matlabArr = 0;  
matlabArr(4,5) = 0
```

```
matlabArr =  
  
    0    0    0    0    0  
    0    0    0    0    0  
    0    0    0    0    0  
    0    0    0    0    0
```

When you try this technique with a Java array, you get an error message.

```
javaArr = java.lang.Double(0);  
javaArr(4,5) = java.lang.Double(0);
```

```
Index exceeds Java array dimensions.
```

Similarly, you cannot create an array of Java arrays from a Java array.

Accessing Elements of a Java Array

- “MATLAB Array Indexing” on page 9-35
- “Single Subscript Indexing” on page 9-35
- “Colon Operator Indexing” on page 9-36
- “Using END in a Subscript” on page 9-37
- “Elements of `java.lang.Object` Arrays Are Converted to MATLAB Types” on page 9-38

MATLAB Array Indexing

You can access elements of a Java object array by using the MATLAB array indexing syntax, `A(row,col)`. For example, to access the element of array `dblArray` at row 3, column 4, use:

```
row3_col4 = dblArray(3,4)

row3_col4 =
34.0
```

To access this element in a Java language program, use `dblArray[2][3]`.

You also can use MATLAB array indexing syntax to access an element in the data field of an object. Suppose that `myMenuObj` is an instance of a window menu class. This user-supplied class has a data field, `menuItemArray`, which is a Java array of `java.awt.MenuItem`. To get element 3 of this array, use the following command.

```
currentItem = myMenuObj.menuItemArray(3)
```

Single Subscript Indexing

Elements of a MATLAB matrix are most commonly referenced using both row and column subscripts. For example, you use `x(3,4)` to reference the array element at the intersection of row 3 and column 4. Sometimes it is more advantageous to use just a single subscript. MATLAB provides this capability (see the section on “Linear Indexing” in MATLAB Mathematics).

Indexing into a MATLAB matrix using a single subscript references one element of the matrix. Using the MATLAB matrix shown here, `matlabArr(3)` returns a single element of the matrix.

```
matlabArr = [11 12 13 14 15; 21 22 23 24 25; ...
```

```
31 32 33 34 35; 41 42 43 44 45]

matlabArr =
    11    12    13    14    15
    21    22    23    24    25
    31    32    33    34    35
    41    42    43    44    45

matlabArr(3)

ans =
    31
```

Indexing this way into a Java array of arrays references an entire subarray of the overall structure. Using the `dblArray` Java array, that looks the same as `matlabArr`, `dblArray(3)` returns the 5-by-1 array that makes up the entire third row.

```
row3 = dblArray(3)

row3 =
java.lang.Double[]:
 [31]
 [32]
 [33]
 [34]
 [35]
```

This feature allows you to specify an entire array from a larger array structure, and then manipulate it as an object.

Colon Operator Indexing

Use of the MATLAB colon operator (`:`) is supported in subscripting Java array references. This operator works just the same as when referencing the contents of a MATLAB array. Using the Java array of `java.lang.Double` objects shown here, the statement `dblArray(2,2:4)` refers to a portion of the lower-level array, `dblArray(2)`. A new array, `row2Array`, is created from the elements in columns 2 through 4.

```
dblArray

dblArray =
java.lang.Double[][]:
 [11] [12] [13] [14] [15]
 [21] [22] [23] [24] [25]
 [31] [32] [33] [34] [35]
 [41] [42] [43] [44] [45]
```



```
row2Array = dblArray(2,2:4)
```

```
row2Array =  
java.lang.Double[:]  
    [22]  
    [23]  
    [24]
```

You also can use the colon operator in single-subscript indexing, as covered in “Single Subscript Indexing” on page 9-35. By making your subscript a colon rather than a number, you can convert an array of arrays into one linear array. The following example converts the 4-by-5 array `dblArray` into a 20-by-1 linear array.

```
linearArray = dblArray(:)
```

```
linearArray =  
java.lang.Double[:]  
    [11]  
    [12]  
    [13]  
    [14]  
    [15]  
    [21]  
    [22]  
    .  
    .  
    .
```

This method also works on an N-dimensional Java array structure. Using the colon operator as a single subscripted index into the array produces a linear array composed of all of the elements of the original array.

Note: Java and MATLAB arrays are stored differently in memory. This is reflected in the order they are given in a linear array. Java array elements are stored in an order that matches the *rows* of the matrix (`linearArray` elements 11, 12, 13, . . .). MATLAB array elements are stored in an order that matches the *columns* (elements 11, 21, 31, . . .).

Using END in a Subscript

You can use the `end` keyword in the first subscript of an access statement. The first subscript references the top-level array in a multilevel Java array structure.

Note: Using `end` on lower-level arrays is not valid due to the potentially ragged nature of these arrays (see “The Shape of the Java Array” on page 9-31). In this case, there is no consistent end value to be derived.

The following example displays data from the third to the last row of Java array `dblArray`.

```
last2rows = dblArray(3:end, :)  
  
last2rows =  
java.lang.Double[][]:  
    [31]    [32]    [33]    [34]    [35]  
    [41]    [42]    [43]    [44]    [45]
```

Elements of `java.lang.Object` Arrays Are Converted to MATLAB Types

When you access an element of a `java.lang.Object` array, MATLAB converts the element to a MATLAB type, according to the table in “Conversion of Java Object Return Types” on page 9-56. MATLAB does not convert elements of any other type of Java array.

For example, if a `java.lang.Object` array contains a `java.lang.Double` element, MATLAB converts the element to MATLAB `double`. But MATLAB does not convert a `java.lang.Double` element in a `java.lang.Double` array; MATLAB returns it as `java.lang.Double`.

Assigning to a Java Array

- “Using Single Subscript Indexing for Array Assignment” on page 9-39
- “Assigning to a Linear Array” on page 9-39
- “Assigning the Empty Matrix” on page 9-40
- “Subscripted Deletion” on page 9-40

You assign values to objects in a Java array in essentially the same way as you do in a MATLAB array. Although Java and MATLAB arrays are structured differently, you use the same command syntax to specify which elements you want to assign to. See “Introduction” on page 9-28 for more information on Java and MATLAB array differences.

The following example assigns the value 300 in the `dblArray` element at row 3, column 2. In a Java language program, this is `dblArray[2][1]`.

```
dblArray(3,2) = java.lang.Double(300)
```

```
dblArray =
java.lang.Double[][]:
  [11]  [ 12]  [13]  [14]  [15]
  [21]  [ 22]  [23]  [24]  [25]
  [31]  [300]  [33]  [34]  [35]
  [41]  [ 42]  [43]  [44]  [45]
```

Use the same syntax to assign to an element to the data field of an object. Continuing with the `myMenuObj` example shown in “Accessing Elements of a Java Array” on page 9-35, assign to the third menu item in `menuItemArray` as follows.

```
myMenuObj.menuItemArray(3) = java.lang.String('Save As...');
```

Using Single Subscript Indexing for Array Assignment

You can use a single-array subscript to index into a Java array structure that has more than one dimension. Refer to “Single Subscript Indexing” on page 9-35 for a description of this feature as used with Java arrays.

You can use single-subscript indexing to assign values to an array as well. The following example assigns a one-dimensional Java array, `onedimArray`, to a row of a two-dimensional Java array, `dblArray`. Start out by creating the one-dimensional array.

```
onedimArray = javaArray('java.lang.Double', 5);
for k = 1:5
    onedimArray(k) = java.lang.Double(100 * k);
end
```

Since `dblArray(3)` refers to the 5-by-1 array displayed in the third row of `dblArray`, you can assign the entire, similarly dimensioned, 5-by-1 `onedimArray` to it.

```
dblArray(3) = onedimArray
```

```
dblArray =
java.lang.Double[][]:
  [ 11]  [ 12]  [ 13]  [ 14]  [ 15]
  [ 21]  [ 22]  [ 23]  [ 24]  [ 25]
 [100]  [200]  [300]  [400]  [500]
  [ 41]  [ 42]  [ 43]  [ 44]  [ 45]
```

Assigning to a Linear Array

You can assign a value to *every* element of a multidimensional Java array by treating the array structure as if it were a single linear array. This entails replacing the single,

numerical subscript with the MATLAB colon operator. If you start with the `dblArray` array, you can initialize the contents of every object in the two-dimensional array with the following statement.

```
dblArray(:) = java.lang.Double(0)
```

```
dblArray =  
java.lang.Double[][]:  
    [0]    [0]    [0]    [0]    [0]  
    [0]    [0]    [0]    [0]    [0]  
    [0]    [0]    [0]    [0]    [0]  
    [0]    [0]    [0]    [0]    [0]
```

You can use the MATLAB colon operator as you would when working with MATLAB arrays. The following statements assign given values to each of the four rows in the Java array, `dblArray`. Remember that each row actually represents a separate Java array in itself.

```
dblArray(1,:) = java.lang.Double(125);  
dblArray(2,:) = java.lang.Double(250);  
dblArray(3,:) = java.lang.Double(375);  
dblArray(4,:) = java.lang.Double(500)
```

```
dblArray =  
java.lang.Double[][]:  
    [125]    [125]    [125]    [125]    [125]  
    [250]    [250]    [250]    [250]    [250]  
    [375]    [375]    [375]    [375]    [375]  
    [500]    [500]    [500]    [500]    [500]
```

Assigning the Empty Matrix

When working with MATLAB arrays, you can assign the empty matrix, (that is, the 0-by-0 array denoted by `[]`) to an element of the array. For Java arrays, you also can assign `[]` to array elements. This stores the `null` value, rather than a 0-by-0 array, in the Java array element.

Subscripted Deletion

When you assign the empty matrix value to an entire row or column of a MATLAB array, you find that MATLAB actually removes the affected row or column from the array. In the example below, the empty matrix is assigned to all elements of the fourth column in the MATLAB matrix, `matlabArr`. Thus, the fourth column is eliminated from the matrix. This changes its dimensions from 4-by-5 to 4-by-4.

```
matlabArr = [11 12 13 14 15; 21 22 23 24 25; ...
            31 32 33 34 35; 41 42 43 44 45]
```

```
matlabArr =
    11    12    13    14    15
    21    22    23    24    25
    31    32    33    34    35
    41    42    43    44    45
```

```
matlabArr(:,4) = []
```

```
matlabArr =
    11    12    13    15
    21    22    23    25
    31    32    33    35
    41    42    43    45
```

You can assign the empty matrix to a Java array, but the effect is different. The next example shows that, when the same operation is performed on a Java array, the structure is not collapsed; it maintains its 4-by-5 dimensions.

```
dblArray(:,4) = []
```

```
dblArray =
java.lang.Double[][]:
    [125]    [125]    [125]    []    [125]
    [250]    [250]    [250]    []    [250]
    [375]    [375]    [375]    []    [375]
    [500]    [500]    [500]    []    [500]
```

The `dblArray` data structure is actually an array of five-element arrays of `java.lang.Double` objects. The empty array assignment placed the `null` value in the fourth element of each of the lower-level arrays.

Concatenating Java Arrays

You can concatenate arrays of Java objects in the same way as arrays of other types. Java objects, however, can only be concatenated along the first or second axis. To understand how scalar Java objects are concatenated in MATLAB, see “Concatenating Java Objects” on page 9-14.

Use either the `cat` function or the square bracket (`[]`) operators. This example horizontally concatenates two Java arrays: `d1` and `d2`.

```
% Construct a 2-by-3 array of java.lang.Double.
d1 = javaArray('java.lang.Double',2,3);
for m = 1:2
    for n = 1:3
        d1(m,n) = java.lang.Double(n*2 + m-1);
    end
end
```

d1

```
d1 =
java.lang.Double[][]:
    [2]    [4]    [6]
    [3]    [5]    [7]
```

```
% Construct a 2-by-2 array of java.lang.Double.
d2 = javaArray('java.lang.Double',2,2);
for m = 1:2
    for n = 1:2
        d2(m,n) = java.lang.Double((n+3)*2 + m-1);
    end
end
```

d2

```
d2 =
java.lang.Double[][]:
    [8]    [10]
    [9]    [11]
```

```
% Concatenate the two along the second dimension.
d3 = cat(2,d1,d2)
```

```
d3 =
java.lang.Double[][]:
    [2]    [4]    [6]    [ 8]    [10]
    [3]    [5]    [7]    [ 9]    [11]
```

Creating a New Array Reference

Because Java arrays in MATLAB are *references*, assigning an array variable to another variable results in a second reference to the array.

Consider the following example where two separate array variables reference a common array. The original array, `origArray`, is created and initialized. The statement

`newArrayRef = origArray` creates a copy of this array variable. Changes made to the array referred to by `newArrayRef` also show up in the original array.

```
origArray = javaArray('java.lang.Double', 3, 4);
for m = 1:3
    for n = 1:4
        origArray(m,n) = java.lang.Double((m * 10) + n);
    end
end
```

`origArray`

```
origArray =
java.lang.Double[][]:
    [11]    [12]    [13]    [14]
    [21]    [22]    [23]    [24]
    [31]    [32]    [33]    [34]
```

```
% Make a copy of the array reference
newArrayRef = origArray;
newArrayRef(3,:) = java.lang.Double(0);
```

`origArray`

```
origArray =
java.lang.Double[][]:
    [11]    [12]    [13]    [14]
    [21]    [22]    [23]    [24]
    [ 0]    [ 0]    [ 0]    [ 0]
```

Creating a Copy of a Java Array

You can create an entirely new array from an existing Java array by indexing into the array to describe a block of elements, or subarray, and assigning this subarray to a variable. The assignment copies the values in the original array to the corresponding cells of the new array.

As with the example in section “Creating a New Array Reference” on page 9-42, an original array is created and initialized. But, this time, a copy is made of the array contents rather than copying the array reference. Changes made using the reference to the new array do not affect the original.

```
origArray = javaArray('java.lang.Double', 3, 4);
for m = 1:3
```

```
    for n = 1:4
        origArray(m,n) = java.lang.Double((m * 10) + n);
    end
end
```

origArray

```
origArray =
java.lang.Double[][]:
    [11]    [12]    [13]    [14]
    [21]    [22]    [23]    [24]
    [31]    [32]    [33]    [34]
```

```
% ----- Make a copy of the array contents -----
newArray = origArray(:,:);
newArray(3,:) = java.lang.Double(0);
```

origArray

```
origArray =
java.lang.Double[][]:
    [11]    [12]    [13]    [14]
    [21]    [22]    [23]    [24]
    [31]    [32]    [33]    [34]
```


Passing Data to Java Methods

In this section...

“Introduction” on page 9-45
 “Conversion of MATLAB Argument Data” on page 9-45
 “Passing Built-In Types” on page 9-47
 “Converting Numbers to Integer Arguments” on page 9-48
 “Passing String Arguments” on page 9-49
 “Passing Java Objects” on page 9-49
 “Other Data Conversion Topics” on page 9-52
 “Passing Data to Overloaded Methods” on page 9-53

Introduction

When you call a Java method, MATLAB types you pass in the call are converted to types native to the Java language. MATLAB performs this conversion on each argument that is passed, except for those arguments that are already Java objects. This section describes the conversion that is performed on specific MATLAB types and, at the end, also looks at how argument types affect calls made to overloaded methods.

If the method returns data, MATLAB converts the data to the appropriate MATLAB format. This process is covered in “Handling Data Returned from Java Methods” on page 9-55.

Conversion of MATLAB Argument Data

MATLAB converts MATLAB data, passed as arguments to Java methods, into types that best represent the data to the Java language. The following table shows all of the MATLAB base types for passed arguments and the Java types defined for the parameters. Each row shows a MATLAB type followed by the possible Java argument matches, from left to right in order of closeness of the match. The MATLAB types (except cell arrays) can all be scalar (1-by-1) arrays or matrices. All of the Java types can be scalar values or arrays.

Conversion of MATLAB Types to Java Types

MATLAB Argument	Java Parameter Type (Scalar or Array)						
	Closest Type <-----> Least Close Type						
logical	boolean	byte	short	int	long	float	double
double	double	float	long	int	short	byte	boolean
single	float	double					
char (1-by-1 scalar)	String	char					
char (1-by-n or n-by-1, n>1)	String	char[]					
char(m-by-n, m,n>1)	String[]						
uint8 int8	byte	short	int	long	float	double	
uint16 int16	short	int	long	float	double		
uint32 int32	int	long	float	double			
uint64 int64	long	float	double				
cell array of strings	String[]						
Java object	Object						
cell array of object	Object[]						
MATLAB object	Unsupported						

For more information about type conversion of arguments passed to Java code, see:

- “Passing Built-In Types” on page 9-47
- “Passing String Arguments” on page 9-49
- “Passing Java Objects” on page 9-49

Passing Built-In Types

The Java language has eight types that are intrinsic to the language and are not represented as Java objects. These are often referred to as *built in*, or *elemental*, types and they include `boolean`, `byte`, `short`, `long`, `int`, `double`, `float`, and `char`. MATLAB converts its own types to these Java built-in types according to the table, Conversion of MATLAB Types to Java Types. Built-in types are in the first 10 rows of the table.

When a Java method you are calling expects one of these types, you can pass it the type of MATLAB argument shown in the leftmost column of the table. If the method takes an array of one of these types, you can pass a MATLAB array of the type. MATLAB converts the type of the argument to the type assigned in the method declaration.

The following MATLAB code creates a top-level window frame and sets its dimensions. The call to `setBounds` passes four MATLAB scalars of the `double` type to the inherited Java Frame method, `setBounds`, that takes four arguments of the `int` type. MATLAB converts each 64-bit double type to a 32-bit integer before calling the method.

The `setBounds` method declaration:

```
public void setBounds(int x, int y, int width, int height)
```

The MATLAB code that calls the method:

```
frame = java.awt.Frame;
setBounds(frame,200,200,800,400)
setVisible(frame,1)
```

Passing Built-In Types in an Array

To call a Java method with an argument defined as an *array* of a built-in type, you can create and pass a MATLAB matrix with a compatible base type. The following code defines a polygon by sending four *x* and *y* coordinates to the Polygon constructor. Two 1-by-4 MATLAB arrays of `double` are passed to `java.awt.Polygon`, which expects integer arrays in the first two arguments. Shown here is the Java method declaration followed by MATLAB code that calls the method, and then verifies the set coordinates.

```
public Polygon(int xpoints[], int ypoints[], int npoints)

poly = java.awt.Polygon([14 42 98 124], [55 12 -2 62], 4);
[poly.xpoints poly.ypoints]      % Verify the coordinates
```

```
ans =  
14    55  
42    12  
98    -2  
124   62
```

MATLAB Arrays Are Passed by Value

Since MATLAB arrays are passed by value, any changes that a Java method makes to them are not visible to your MATLAB code. To access changes that a Java method makes to an array, then, rather than passing a MATLAB array, create and pass a Java array, which is a reference. For a description of using Java arrays in MATLAB, see “Working with Java Arrays” on page 9-28.

Note: Generally, it is preferable to have methods return data that has been modified using the return argument mechanism as opposed to passing a reference to that data in an argument list.

Converting Numbers to Integer Arguments

When passing an integer type to a Java method that takes a Java integer parameter, the MATLAB conversion is the same as the Java conversion between integer types. In particular, if the integer is out-of-range (does not fit into the number of bits of the parameter type), MATLAB discards all lowest n bits, where n is the number of bits in the parameter type. This is unlike conversion between MATLAB integer types, where out-of-range integers are converted to the maximum or minimum value represented by the destination type.

If the argument is floating point, MATLAB does not convert to an integer in the same manner as Java. A floating point number is first converted to a 64-bit signed integer with the fractional part truncated and then processed as if it were an `int64` argument.

When a floating point number is too large to be represented in a 64-bit integer (outside the range from -2^{63} – 2^{63}), MATLAB converts the value as follows:

- Convert `int`, `short`, and `byte` parameter values to 0.
- Convert `long` parameter values to `java.lang.Long.MIN_VALUE`.
- Convert `Inf` and `-Inf` values to `-1`.
- Convert `NaN` values to 0.

Passing String Arguments

To call a Java method that has an argument defined as an object of class `java.lang.String`, you can pass either a `String` object that was returned from an earlier Java call or a MATLAB 1-by-n character array. If you pass the character array, MATLAB converts the array to a Java object of `java.lang.String` for you.

For a programming example, see “Read URL” on page 9-61. This example shows a MATLAB character array that holds a URL being passed to the Java `URL` class constructor. The following constructor expects a Java `String` argument.

```
public URL(String spec) throws MalformedURLException
```

In the MATLAB call to this constructor, a character array specifying the URL is passed. MATLAB converts this array to a Java `String` object before calling the constructor.

```
url = java.net.URL('http://archive.ncsa.uiuc.edu/demoweb/')
```

Passing Strings in an Array

When the method you are calling expects an argument of an array of type `String`, you can create such an array by packaging the strings together in a MATLAB cell array. The strings can be of varying lengths since you are storing them in different cells of the array. As part of the method call, MATLAB converts the cell array to a Java array of `String` objects.

In the following example, the `echoPrompts` method of a user-written class accepts a string array argument that MATLAB converted from its original format as a cell array of strings. The parameter list in the Java method appears as follows:

```
public String[] echoPrompts(String s[])
```

You create the input argument by storing both strings in a MATLAB cell array. MATLAB converts this structure to a Java array of `String`.

```
myaccount.echoPrompts({'Username: ', 'Password: '})
ans =
'Username: '
'Password: '
```

Passing Java Objects

When calling a method that has a parameter belonging to a Java class (other than `java.lang.Object`), you must pass a Java object that is an instance of that class.

MATLAB does not automatically convert MATLAB types to Java Object types. Unlike Java, MATLAB does not do autoboxing for numbers, such as converting `double` to `Double`.

In the example below, the `add` method belonging to the `java.awt.Menu` class requires, as an argument, an object of the `java.awt.MenuItem` class. The method declaration is:

```
public MenuItem add(MenuItem mi)
```

The example operates on the frame created in the previous example in “Passing Built-In Types” on page 9-47. The second, third, and fourth lines of code shown here add items to a menu to be attached to the existing window frame. In each of these calls to `menu1.add`, an object that is an instance of the `java.awt.MenuItem` Java class is passed.

```
menu1 = java.awt.Menu('File Options');
menu1.add(java.awt.MenuItem('New'));
menu1.add(java.awt.MenuItem('Open'));
menu1.add(java.awt.MenuItem('Save'));
```

```
menuBar=java.awt.MenuBar;
menuBar.add(menu1);
frame.setMenuBar(menuBar);
```

Handling Objects of Class `java.lang.Object`

A special case exists when the method being called takes an argument of the `java.lang.Object` class. Since this class is the root of the Java class hierarchy, you can pass objects of any class in the argument. When passing a MATLAB argument, the argument is automatically converted to the closest Java Object type, which might include Java-style autoboxing, as shown in the following table.

MATLAB Argument	Java Object
logical	Boolean
double	Double
single	Float
char (1-by-1 scalar)	Character
char (1-by-n or n-by-1, n>1)	String
uint8 int8	Byte

MATLAB Argument	Java Object
uint16 int16	Short
uint32 int32	Integer
uint64 int64	Long
cell array of strings	String[]
Java object	Object
cell array of object	Object[]
MATLAB object	Unsupported

Passing Objects in an Array

The only types of object arrays that you can pass to Java methods are Java arrays and MATLAB cell arrays. MATLAB automatically converts the cell array elements to `java.lang.Object` class objects. In order for a cell array to be passed from MATLAB, the corresponding argument in the Java method signature must specify `java.lang.Object` or an array of `java.lang.Object`.

If the objects are already in a Java array, either an array returned from a Java constructor or constructed in MATLAB by the `javaArray` function, then you simply pass it as the argument to the method being called. MATLAB does not convert the argument, because the argument is already a Java array.

The following example shows the `mapPoints` method of a user-written class accepting an array of `java.awt.Point` objects. The declaration for this method is:

```
public Object mapPoints(java.awt.Point p[])
```

The following MATLAB code creates a 4-by-1 array containing four Java `Point` objects. When the array is passed to the `mapPoints` method, no conversion is necessary because the `javaArray` function created a Java array of `java.awt.Point` objects.

```
pointObj = javaArray('java.awt.Point',4);
pointObj(1) = java.awt.Point(25,143);
pointObj(2) = java.awt.Point(31,147);
pointObj(3) = java.awt.Point(49,151);
pointObj(4) = java.awt.Point(52,176);
```

```
testData.mapPoints(pointObj);
```

Handling a Cell Array of Java Objects

You create a cell array of Java objects by using the MATLAB syntax `{a1,a2,...}`. You index into a cell array of Java objects in the usual way, with the syntax `a{m,n,...}`.

The following example creates a cell array of two `Frame` objects, `frame1` and `frame2`, and assigns it to variable `frameArray`.

```
frame1 = java.awt.Frame('Frame A');  
frame2 = java.awt.Frame('Frame B');
```

```
frameArray = {frame1, frame2}
```

```
frameArray =  
[1x1 java.awt.Frame]    [1x1 java.awt.Frame]
```

The next statement assigns element `{1,2}` of the cell array `frameArray` to variable `f`.

```
f = frameArray {1,2}
```

```
f =  
java.awt.Frame[frame2,0,0,0x0,invalid,hidden,layout =  
java.awt.BorderLayout,resizable,title=Frame B]
```

Other Data Conversion Topics

There are several remaining items of interest regarding the way MATLAB converts its data to a compatible Java type. This includes how MATLAB matches array dimensions, and how it handles empty matrices and empty strings.

How Array Dimensions Affect Conversion

The term *dimension* refers to the number of subscripts required to address the elements of an array. For example, a 5-by-1 array has one dimension, because you can index individual elements using only one array subscript.

In converting MATLAB to Java arrays, MATLAB handles dimension in a special manner. For a MATLAB array, dimension can be considered as the number of nonsingleton dimensions in the array. For example, a 10-by-1 array has dimension 1, and a 1-by-1 array has dimension 0. In Java code, dimension is determined solely by the

number of nested arrays. For example, `double[][]` has dimension 2, and `double` has dimension 0.

If the number of dimensions of the Java array exactly matches the MATLAB array's number of dimensions n , the conversion results in a Java array with n dimensions. If the Java array has fewer than n dimensions, the conversion drops singleton dimensions, starting with the first one, until the number of remaining dimensions matches the number of dimensions in the Java array.

Empty Matrices and Nulls

An empty matrix is converted to a Java `null`. The empty string (' ') in MATLAB translates into an empty (not `null`) `String` object in Java code. Empty (0-length) Java arrays remain unchanged.

Passing Data to Overloaded Methods

When you invoke an overloaded method on a Java object, MATLAB determines which method to invoke by comparing the arguments your call passes to the arguments defined for the methods. In this discussion, the term *method* includes constructors. When it determines the method to call, MATLAB converts the calling arguments to Java method types according to Java conversion rules, except for conversions involving objects or cell arrays. See “Passing Objects in an Array” on page 9-51.

How MATLAB Determines the Method to Call

When your MATLAB function calls a Java method, MATLAB:

- 1 Checks to make sure that the object (or class, for a static method) has a method by that name.
- 2 Determines whether the invocation passes the same number of arguments of at least one method with that name.
- 3 Makes sure that each passed argument can be converted to the Java type defined for the method.

If all of the preceding conditions are satisfied, MATLAB calls the method.

In a call to an overloaded method, if there is more than one candidate, MATLAB selects the one with arguments that best fit the calling arguments. First, MATLAB rejects all methods that have any argument types that are incompatible with the passed arguments

(for example, if the method has a `double` argument and the passed argument is a `char` type).

Among the remaining methods, MATLAB selects the one with the highest fitness value, which is the sum of the fitness values of all its arguments. The fitness value for each argument is the fitness of the base type minus the difference between the MATLAB array dimension and the Java array dimension. (Array dimensionality is explained in “How Array Dimensions Affect Conversion” on page 9-52.) If two methods have the same fitness, the first one defined in the Java class is chosen.

Example — Calling an Overloaded Method

Suppose that a function constructs a `java.io.OutputStreamWriter` object, `osw`, and then invokes a method on the object.

```
osw.write('Test data', 0, 9);
```

MATLAB finds that the class `java.io.OutputStreamWriter` defines three `write` methods.

```
public void write(int c);  
public void write(char[] cbuf, int off, int len);  
public void write(String str, int off, int len);
```

MATLAB rejects the first `write` method, because it takes only one argument. Then, MATLAB assesses the fitness of the remaining two `write` methods. These differ only in their first argument, as explained below.

In the first of these two `write` methods, the first argument is defined with base type, `char`. The table, Conversion of MATLAB Types to Java Types, shows that for the type of the calling argument (MATLAB `char`), Java type, `char`, has a value of 6. There is no difference between the dimension of the calling argument and the Java argument. So the fitness value for the first argument is 6.

In the other `write` method, the first argument has Java type `String`, which has a fitness value of 7. The dimension of the Java argument is 0, so the difference between it and the calling argument dimension is 1. Therefore, the fitness value for the first argument is 6.

Because the fitness value of those two `write` methods is equal, MATLAB calls the one listed first in the class definition, with `char[]` first argument.

Handling Data Returned from Java Methods

In this section...

“Introduction” on page 9-55

“Conversion of Java Return Types” on page 9-55

“Conversion of Java Object Return Types” on page 9-56

“Built-In Types” on page 9-56

“Converting Objects to MATLAB Types” on page 9-57

Introduction

In many cases, data returned from a Java method is incompatible with the types operated on in the MATLAB platform. When this is the case, MATLAB converts the returned value to a type native to the MATLAB language. This section describes the conversion performed on the various types that can be returned from a call to a Java method.

Conversion of Java Return Types

The following table lists Java return types and the resulting MATLAB types. For some Java base return types, MATLAB treats scalar and array returns differently. For information about `java.lang.Object` type, see “Conversion of Java Object Return Types” on page 9-56.

Conversion of Java Types to MATLAB Types

Java Return Type	If Scalar Return, Resulting MATLAB Type	If Array Return, Resulting MATLAB Type
<code>boolean</code>	<code>logical</code>	<code>logical</code>
<code>byte</code>	<code>double</code>	<code>int8</code>
<code>short</code>	<code>double</code>	<code>int16</code>
<code>int</code>	<code>double</code>	<code>int32</code>
<code>long</code>	<code>double</code>	<code>int64</code>
<code>float</code>	<code>double</code>	<code>single</code>
<code>double</code>	<code>double</code>	<code>double</code>

Java Return Type	If Scalar Return, Resulting MATLAB Type	If Array Return, Resulting MATLAB Type
char	char	char

Note: MATLAB converts rectangular Java arrays to arrays of the resulting type. When Java returns a nonrectangular (jagged) array, MATLAB converts it to a cell array. For more information, see “How MATLAB Represents the Java Array” on page 9-28.

Conversion of Java Object Return Types

When a method call returns data of type `java.lang.Object`, MATLAB converts its value, depending on its actual type, according to the following table. Other object types, including `Object` arrays, are not converted; they remain Java objects. However, if you index into a returned `Object` array, the value will be converted according to the table. For more information, see “Elements of `java.lang.Object` Arrays Are Converted to MATLAB Types” on page 9-38.

Conversion of `java.lang.Object` Type to MATLAB Types

Actual Java Type	Return Scalar MATLAB Type
<code>java.lang.Boolean</code>	logical
<code>java.lang.Byte</code>	double
<code>java.lang.Short</code>	double
<code>java.lang.Integer</code>	double
<code>java.lang.Long</code>	double
<code>java.lang.Float</code>	double
<code>java.lang.Double</code>	double
<code>java.lang.Character</code>	char
<code>java.lang.String</code>	char

Built-In Types

Java *built-in* types are described in “Passing Built-In Types” on page 9-47. This type includes `boolean`, `byte`, `short`, `long`, `int`, `double`, `float`, and `char`. When the value

returned from a method call is one of these types, MATLAB converts it according to the table Conversion of Java Types to MATLAB Types.

A single numeric or `boolean` value converts to a 1-by-1 matrix of `double`, which is convenient for use in MATLAB. An array of a numeric or `boolean` return values converts each member of the array to the closest base type to minimize the required storage space. Array member conversions are listed in the right-hand column of the table.

A return value of Java type `char` converts to a 1-by-1 matrix of `char`. An array of Java `char` converts to a MATLAB array of that type.

Converting Objects to MATLAB Types

Except for objects of class `Object`, MATLAB does not convert Java objects returned from method calls to a native MATLAB type. If you want to convert Java object data to a form more readily usable in MATLAB, there are a few MATLAB functions that enable you to do this. These are described in the following sections.

- “Converting to the MATLAB double Type” on page 9-57
- “Converting to the MATLAB char Type” on page 9-58
- “Converting to a MATLAB Structure” on page 9-58
- “Converting to a MATLAB Cell Array” on page 9-59

Converting to the MATLAB double Type

Using the `double` function in MATLAB, you can convert any Java object or array of objects to the MATLAB `double` type. The action taken by the `double` function depends on the class of the object you specify:

- If the object is an instance of a numeric class (`java.lang.Number` or one of the classes that inherit from that class), MATLAB uses a preset conversion algorithm to convert the object to a MATLAB `double`.
- If the object is not an instance of a numeric class, MATLAB checks the class definition to see if it implements a method called `toDouble`. MATLAB uses `toDouble` to perform its conversion of Java objects to the MATLAB `double` type. If such a method is implemented for this class, MATLAB executes it to perform the conversion.
- If you are using a class of your own design, you can write your own `toDouble` method to perform conversions on objects of that class to a MATLAB `double`. This enables you to specify your own means of type conversion for objects belonging to your own classes.

Note: If the class of the specified object is not `java.lang.Number`, does not inherit from that `java.lang.Number`, and does not implement a `toDouble` method, then an attempt to convert the object using the `double` function results in a MATLAB error message.

The syntax for the `double` command is as follows, where `object` is a Java object or Java array of objects:

```
double(object);
```

Converting to the MATLAB char Type

With the MATLAB `char` function, you can convert `java.lang.String` objects and arrays to MATLAB character arrays.

The syntax for the `char` command is as follows, where `object` is a Java object or Java array of objects:

```
char(object);
```

If the object specified in the `char` command is not an instance of the `java.lang.String` class, MATLAB checks its class to see if it implements a method named `toChar`. If so, MATLAB executes the `toChar` method of the class to perform the conversion. If you write your own class definitions, you can use this feature by writing a `toChar` method that performs the conversion according to your own needs.

Note: If the class of the specified object is not `java.lang.String` and it does not implement a `toChar` method, an attempt to convert the object using the `char` function results in a MATLAB error message.

Converting to a MATLAB Structure

Java objects are similar to the MATLAB `struct` type in that many of an object's characteristics are accessible via field names defined within the object. You might want to convert a Java object into a MATLAB `struct` to facilitate the handling of its data in MATLAB. Use the MATLAB `struct` function to do this.

The syntax for the `struct` command is as follows, where `object` is a Java object or a Java array of objects:

```
struct(object);
```

The following example converts a `java.awt.Polygon` object into a MATLAB `struct`. You can access the fields of the object directly using MATLAB `struct` operations. The last line indexes into the array, `pstruct.xpoints`, to deposit a new value into the third array element.

```
polygon = java.awt.Polygon([14 42 98 124], [55 12 -2 62], 4);
pstruct = struct(polygon)
```

```
pstruct =
  npoints: 4
  xpoints: [4x1 int32]
  ypoints: [4x1 int32]
```

```
pstruct.xpoints
```

```
ans =
    14
    42
    98
   124
```

```
pstruct.xpoints(3) = 101;
```

Converting to a MATLAB Cell Array

Use the `cell` function to convert a Java array or Java object into a MATLAB cell array. Elements of the resulting cell array are of the MATLAB type (if any) closest to the Java array elements or Java object.

The syntax for the `cell` command is as follows, where `object` is a Java object or a Java array of objects.

```
cell(object);
```

The following example uses the `cell` command to create a MATLAB cell array in which each cell holds an array of a different type.

```
import java.lang.* java.awt.*;

% Create a Java array of double
dblArray = javaArray('java.lang.Double', 1, 10);
for m = 1:10
    dblArray(1, m) = Double(m * 7);
end
```

```
% Create a Java array of points
ptArray = javaArray('java.awt.Point', 3);
ptArray(1) = Point(7.1, 22);
ptArray(2) = Point(5.2, 35);
ptArray(3) = Point(3.1, 49);

% Create a Java array of strings
strArray = javaArray('java.lang.String', 2, 2);
strArray(1,1) = String('one');    strArray(1,2) = String('two');
strArray(2,1) = String('three');  strArray(2,2) = String('four');

% Convert each to cell arrays
cellArray = {cell(dblArray), cell(ptArray), cell(strArray)}
cellArray =
    {1x10 cell}    {3x1 cell}    {2x2 cell}

cellArray{1,1}    % Array of type double
ans =

    [7]    [14]    [21]    [28]    [35]    [42]    [49]    [56]    [63]    [70]

cellArray{1,2}    % Array of type Java.awt.Point
ans =
    [1x1 java.awt.Point]
    [1x1 java.awt.Point]
    [1x1 java.awt.Point]

cellArray{1,3}    % Array of type char array
ans =
    'one'    'two'
    'three'    'four'
```


Read URL

In this section...

“Overview” on page 9-61

“Description of URLdemo” on page 9-61

“Running the Example” on page 9-62

Overview

This program, `URLdemo`, opens a connection to a website specified by a URL (Uniform Resource Locator) to read text from a file at that site.

`URLdemo` constructs an object of the Java API class, `java.net.URL`, which enables convenient handling of URLs. Then, it calls a method on the URL object, to open a connection.

To read and display the lines of text at the site, `URLdemo` uses classes from the Java I/O package `java.io`. It creates an `InputStreamReader` object, and then uses that object to construct a `BufferedReader` object. Finally, it calls a method on the `BufferedReader` object to read the specified number of lines from the site.

Description of URLdemo

The major tasks performed by `URLdemo` are:

- 1 Construct a URL object.

The example first calls a constructor on `java.net.URL` and assigns the resulting object to variable `url`. The URL constructor takes a single argument, the name of the URL to be accessed, as a string. The constructor checks whether the input URL has a valid form.

```
url = java.net.URL('http://www.mathworks.com')
```

- 2 Open a connection to the URL.

The second statement of the example calls the method, `openStream`, on the URL object `url`, to establish a connection with the website named by the object. The method returns an `InputStream` object to variable, `is`, for reading bytes from the site.

```
is = openStream(url);
```

- 3 Set up a buffered stream reader.

The next two lines create a buffered stream reader for characters. The `java.io.InputStreamReader` constructor is called with the input stream `is`, to return to variable `isr` an object that can read characters. Then, the `java.io.BufferedReader` constructor is called with `isr`, to return a `BufferedReader` object to variable `br`. A buffered reader provides for efficient reading of characters, arrays, and lines.

```
isr = java.io.InputStreamReader(is);  
br = java.io.BufferedReader(isr);
```

- 4 Read and display lines of text.

The following statements read the lines of HTML text from the site, looking for text beginning with a paragraph tag, `<p>`. Within the MATLAB `while` loop, the `BufferedReader` method `readLine` reads each line of text (terminated by a return and/or line feed character) from the site.

```
p1 = java.lang.String('<p>');  
p2 = java.lang.String('</p>');  
s = readLine(br);  
while ~(s.startsWith(p1))  
    s = readLine(br);  
end
```

- 5 Display the text.

```
disp(s.substring(p1.length,s.length-p2.length))
```

Running the Example

When you run this example, you see output similar to the following.

Explore products for MATLAB, the language of technical computing, and Simulink, for sin

Find Internet Protocol Address

In this section...

“Overview” on page 9-63

“Description of `resolveip`” on page 9-63

“Running the Example” on page 9-64

Overview

The `resolveip` function returns either the name or address of an IP (internet protocol) host. If you pass `resolveip` a host name, it returns the IP address. If you pass `resolveip` an IP address, it returns the host name. The function uses the `java.net.InetAddress` class, which enables you to find an IP address for a host name, or the host name for a given IP address, without making DNS calls.

`resolveip` calls a static method on the `InetAddress` class to obtain an `InetAddress` object. Then, it calls accessor methods on the `InetAddress` object to get the host name and IP address for the input argument. It displays either the host name or the IP address, depending on the program input argument.

Description of `resolveip`

The major tasks performed by `resolveip` are:

- 1 Create an `InetAddress` object.

Instead of constructors, the `java.net.InetAddress` class has static methods that return an instance of the class. The `try` statement calls one of those methods, `getByName`, passing the `input` argument that the user has passed to `resolveip`. The `input` argument can be either a host name or an IP address. If `getByName` fails, the `catch` statement displays an error message.

```
function resolveip(input)
try
  address = java.net.InetAddress.getByName(input);
catch
  error(sprintf('Unknown host %s.', input))
end
```

- 2 Retrieve the host name and IP address.

The example uses calls to the `getHostName` and `getHostAddress` accessor functions on the `java.net.InetAddress` object, to obtain the host name and IP address, respectively. These two functions return objects of class `java.lang.String`; use the `char` function to convert them to character arrays.

```
hostname = char(address.getHostName);  
ipaddress = char(address.getHostAddress);
```

- 3 Display the host name or IP address.

The example uses the MATLAB `strcmp` function to compare the `input` argument to the resolved IP address. If it matches, MATLAB displays the host name for the internet address. If the input does not match, MATLAB displays the IP address.

```
if strcmp(input,ipaddress)  
    disp(sprintf('Host name of %s is %s', input, hostname))  
else  
    disp(sprintf('IP address of %s is %s', input, ipaddress))  
end
```

Running the Example

Here is an example of calling the `resolveip` function with a host name.

```
resolveip ('www.mathworks.com')  
IP address of www.mathworks.com is 144.212.100.10
```

Here is a call to the function with an IP address.

```
resolveip ('144.212.100.10')  
Host name of 144.212.100.10 is www.mathworks.com
```

Create and Use Phone Book

In this section...

“Overview” on page 9-65
“Description of Function phonebook” on page 9-66
“Description of Function pb_lookup” on page 9-70
“Description of Function pb_add” on page 9-70
“Description of Function pb_remove” on page 9-71
“Description of Function pb_change” on page 9-72
“Description of Function pb_listall” on page 9-73
“Description of Function pb_display” on page 9-74
“Description of Function pb_keyfilter” on page 9-74
“Running the phonebook Program” on page 9-75

Overview

The main function, `phonebook`, can be called either with no arguments, or with one argument, which is the key of an entry that exists in the phone book. The function first determines the folder to use for the phone book file.

If no phone book file exists, it creates one by constructing a `java.io.FileOutputStream` object, and then closing the output stream. Next, it creates a data dictionary by constructing an object of `java.util.Properties`, which is a subclass of `java.util.Hashtable`, for storing key/value pairs in a hash table. For the `phonebook` program, the key is a name, and the value is one or more telephone numbers.

The `phonebook` function creates and opens an input stream for reading by constructing a `java.io.FileInputStream` object. It calls `load` on that object to load the hash table contents, if it exists. If the user passed the key to an entry to look up, it looks up the entry by calling `pb_lookup`, which finds and displays it. Then, the `phonebook` function returns.

If `phonebook` was called without the name argument, it then displays a textual menu of the available phone book actions:

- Look up an entry
- Add an entry

- Remove an entry
- Change the phone number(s) in an entry
- List all entries

The menu also has a selection to exit the program. The function uses MATLAB functions to display the menu and to input the user selection.

The `phonebook` function iterates accepting user selections and performing the requested phone book action until the user selects the menu entry to exit. The `phonebook` function then opens an output stream for the file by constructing a `java.io.FileOutputStream` object. It calls `save` on the object to write the current data dictionary to the phone book file. It finally closes the output stream and returns.

Description of Function `phonebook`

The major tasks performed by `phonebook` are:

- 1 Determine the data folder and full file name.

The first statement assigns the phone book file name, 'myphonebook', to the variable `pbname`. If the `phonebook` program is running on a Windows system, it calls the `java.lang.System` static method `getProperty` to find the location of the data dictionary. This is set to the user's current working folder. Otherwise, it uses MATLAB function `getenv` to determine the location, using the system variable `HOME`, which you can define beforehand to anything you like. It then assigns to `pbname` the full path, consisting of the data folder and file name 'myphonebook'.

```
function phonebook(varargin)
pbname = 'myphonebook'; % name of data dictionary
if ispc
    datadir = char(java.lang.System.getProperty('user.dir'));
else
    datadir = getenv('HOME');
end
pbname = fullfile(datadir, pbname);
```

- 2 If needed, create a file output stream.

If the `phonebook` file does not exist, `phonebook` asks the user whether to create a new one. If the user answers `y`, `phonebook` creates a phone book by constructing a `FileOutputStream` object. In the `try` clause of a `try/catch` block, the argument `pbname` passed to the `FileOutputStream` constructor is the full name of the file

that the constructor creates and opens. The next statement closes the file by calling `close` on the `FileOutputStream` object `FOS`. If the output stream constructor fails, the `catch` statement prints a message and terminates the program.

```

if ~exist(pbname)
    disp(sprintf('Data file %s does not exist.', pbname))
    r = input('Create a new phone book (y/n)?','s');
    if r == 'y',
        try
            FOS = java.io.FileOutputStream(pbname);
            FOS.close
        catch
            error(sprintf('Failed to create %s', pbname))
        end
    else
        return
    end
end
end

```

3 Create a hash table.

The example constructs a `java.util.Properties` object to serve as the hash table for the data dictionary.

```
pb_hhtable = java.util.Properties;
```

4 Create a file input stream.

In a `try` block, the example invokes a `FileInputStream` constructor with the name of the phone book file, assigning the object to `FIS`. If the call fails, the `catch` statement displays an `error` message and terminates the program.

```

try
    FIS = java.io.FileInputStream(pbname);
catch
    error(sprintf('Failed to open %s for reading.', pbname))
end

```

5 Load the phone book keys and close the file input stream.

The example calls `load` on the `FileInputStream` object `FIS`, to load the phone book keys and their values (if any) into the hash table. It then closes the file input stream.

```

pb_hhtable.load(FIS)
FIS.close

```

6 Display the Action menu and get the user's selection.

Within a `while` loop, several `disp` statements display a menu of actions that the user can perform on the phone book. Then, an `input` statement requests the user's typed selection.

```
while 1
    disp ' '
    disp ' Phonebook Menu:'
    disp ' '
    disp ' 1. Look up a phone number'
    disp ' 2. Add an entry to the phone book'
    disp ' 3. Remove an entry from the phone book'
    disp ' 4. Change the contents of an entry in the phone book'
    disp ' 5. Display entire contents of the phone book'
    disp ' 6. Exit this program'
    disp ' '
    s = input('Please type the number for a menu selection: ','s');
```

7 Invoke the function to perform a phone book action

Still within the `while` loop, a `switch` statement provides a case to handle each user selection `s`. Each of the first five cases invokes the function to perform a phone book action.

```
switch s
```

Case 1 prompts for a name that is a key to an entry. It calls `isempty` to determine whether the user has entered a name. If a name has not been entered, it calls `disp` to display an error message. If a name has been input, it passes it to `pb_lookup`. The `pb_lookup` routine looks up the entry and, if it finds it, displays the entry contents.

```
case '1',
    name = input('Enter name to look up: ','s');
    if isempty(name)
        disp 'No name entered'
    else
        pb_lookup(pb_htable, name)
    end
```

Case 2 calls `pb_add`, which prompts the user for a new entry and then adds it to the phone book.


```
case '2',
    pb_add(pb_hhtable)
```

Case 3 uses `input` to prompt for the name of an entry to remove. If a name has not been entered, it calls `disp` to display an error message. If a name has been entered, it passes it to `pb_remove`.

```
case '3',
    name = input('Enter name of entry to remove: ', 's');
    if isempty(name)
        disp 'No name entered'
    else
        pb_remove(pb_hhtable, name)
    end
```

Case 4 uses `input` to prompt for the name of an entry to change. If a name has not been entered, it calls `disp` to display an error message. If a name has been entered, it passes it to `pb_change`.

```
case '4',
    name = input('Enter name of entry to change: ', 's');
    if isempty(name)
        disp 'No name entered'
    else
        pb_change(pb_hhtable, name)
    end
```

Case 5 calls `pb_listall` to display all entries.

```
case '5',
    pb_listall(pb_hhtable)
```

- 8 Exit by creating an output stream and saving the phone book.

If the user has selected case 6 to exit the program, a `try` statement calls the constructor for a `FileOutputStream` object, passing it the name of the phone book. If the constructor fails, the `catch` statement displays an error message.

If the object is created, the next statement saves the phone book data by calling `save` on the `Properties` object `pb_hhtable`, passing the `FileOutputStream` object `FOS` and a descriptive header string. It then calls `close` on the `FileOutputStream` object, and returns.

```
case '6',
    try
        FOS = java.io.FileOutputStream(pbname);
    catch
        error(sprintf('Failed to open %s for writing.',pbname))
    end
    pb_hhtable.save(FOS, 'Data file for phonebook program')
    FOS.close
    return
otherwise
    disp 'That selection is not on the menu.'
end

end % switch
```

Description of Function `pb_lookup`

Arguments passed to `pb_lookup` are the Properties object `pb_hhtable` and the name key for the requested entry. The `pb_lookup` function first calls `get` on `pb_hhtable` with the name key, on which support function `pb_keyfilter` is called to change spaces to underscores. The `get` method returns the entry (or null, if the entry is not found) to variable `entry`. `get` takes an argument of type `java.lang.Object` and also returns an argument of that type. In this invocation, the key passed to `get` and the entry returned from it are actually character arrays.

`pb_lookup` then calls `isempty` to determine whether `entry` is null. If it is, it uses `disp` to display a message stating that the name was not found. If `entry` is not null, it calls `pb_display` to display the entry.

```
function pb_lookup(pb_hhtable,name)
entry = pb_hhtable.get(pb_keyfilter(name));
if isempty(entry),
    disp(sprintf('The name %s is not in the phone book',name))
else
    pb_display(entry)
end
```

Description of Function `pb_add`

- 1 Input the entry to add.

The `pb_add` function takes one argument, the `Properties` object `pb_htable`. `pb_add` uses `disp` to prompt for an entry. Using the up arrow (^) character as a line delimiter, `input` inputs a name to the variable `entry`. Then, within a `while` loop, it uses `input` to get another line of the entry into variable `line`. If the line is empty, indicating that the user has finished the entry, the code breaks out of the `while` loop. If the line is not empty, the `else` statement appends `line` to `entry` and then appends the line delimiter. At the end, the `strcmp` checks the possibility that no input was entered and, if that is the case, returns.

```
function pb_add(pb_htable)
disp 'Type the name for the new entry, followed by Enter.'
disp 'Then, type the phone number(s), one per line.'
disp 'To complete the entry, type an extra Enter.'
name = input(':: ', 's');
entry = [name '^'];
while 1
    line = input(':: ', 's');
    if isempty(line)
        break
    else
        entry = [entry line '^'];
    end
end

if strcmp(entry, '^')
    disp 'No name entered'
    return
end
```

- 2 Add the entry to the phone book.

After the input has completed, `pb_add` calls `put` on `pb_htable` with the hash key `name` (on which `pb_keyfilter` is called to change spaces to underscores) and `entry`. It then displays a message that the entry has been added.

```
pb_htable.put(pb_keyfilter(name), entry)
disp ' '
disp(sprintf('%s has been added to the phone book.', name))
```

Description of Function `pb_remove`

- 1 Look for the key in the phone book.

Arguments passed to `pb_remove` are the `Properties` object `pb_hhtable` and the name `key` for the entry to remove. The `pb_remove` function calls `containsKey` on `pb_hhtable` with the `name` key, on which support function `pb_keyfilter` is called to change spaces to underscores. If `name` is not in the phone book, `disp` displays a message and the function returns.

```
function pb_remove(pb_hhtable,name)
if ~pb_hhtable.containsKey(pb_keyfilter(name))
    disp(sprintf('The name %s is not in the phone book',name))
    return
end
```

- 2 Ask for confirmation and if given, remove the key.

If the key is in the hash table, `pb_remove` asks for user confirmation. If the user confirms the removal by entering `y`, `pb_remove` calls `remove` on `pb_hhtable` with the (filtered) `name` key, and displays a message that the entry has been removed. If the user enters `n`, the removal is not performed and `disp` displays a message that the removal has not been performed.

```
r = input(sprintf('Remove entry %s (y/n)? ',name), 's');
if r == 'y'
    pb_hhtable.remove(pb_keyfilter(name))
    disp(sprintf('%s has been removed from the phone book',name))
else
    disp(sprintf('%s has not been removed',name))
end
```

Description of Function `pb_change`

- 1 Find the entry to change, and confirm.

Arguments passed to `pb_change` are the `Properties` object `pb_hhtable` and the name `key` for the requested entry. The `pb_change` function calls `get` on `pb_hhtable` with the `name` key, on which `pb_keyfilter` is called to change spaces to underscores. The `get` method returns the entry (or `null`, if the entry is not found) to variable `entry`. `pb_change` calls `isempty` to determine whether the entry is empty. If the entry is empty, `pb_change` displays a message that the name is added to the phone book, and allows the user to enter the phone number for the entry.

If the entry is found, in the `else` clause, `pb_change` calls `pb_display` to display the entry. It then uses `input` to ask the user to confirm the replacement. If the user enters anything other than `y`, the function returns.

```

function pb_change(pb_hhtable,name)
entry = pb_hhtable.get(pb_keyfilter(name));
if isempty(entry)
    disp(sprintf('The name %s is not in the phone book', name))
    return
else
    pb_display(entry)
    r = input('Replace phone numbers in this entry (y/n)? ','s');
    if r ~= 'y'
        return
    end
end
end

```

- 2 Input new phone numbers and change the phone book entry.

`pb_change` uses `disp` to display a prompt for new phone numbers. Then, `pb_change` inputs data into variable `entry`, with the same statements described in “Description of Function `pb_lookup`” on page 9-70.

Then, to replace the existing entry with the new one, `pb_change` calls `put` on `pb_hhtable` with the (filtered) key `name` and the new entry. It then displays a message that the entry has been changed.

```

disp('Type in the new phone number(s), one per line.')
disp('To complete the entry, type an extra Enter.')
disp(sprintf(':: %s', name))
entry = [name '^'];
while 1
    line = input(':: ','s');
    if isempty(line)
        break
    else
        entry = [entry line '^'];
    end
end
pb_hhtable.put(pb_keyfilter(name),entry)
disp(' ')
disp(sprintf('The entry for %s has been changed', name))

```

Description of Function `pb_listall`

The `pb_listall` function takes one argument, the `Properties` object `pb_hhtable`. The function calls `propertyNames` on the `pb_hhtable` object to return to `enum` a

`java.util.Enumeration` object, which supports convenient enumeration of all the keys. In a `while` loop, `pb_listall` calls `hasMoreElements` on `enum`, and if it returns true, `pb_listall` calls `nextElement` on `enum` to return the next key. It then calls `pb_display` to display the key and entry, which it retrieves by calling `get` on `pb_hhtable` with the key.

```
function pb_listall(pb_hhtable)
enum = pb_hhtable.propertyNames;
while enum.hasMoreElements
    key = enum.nextElement;
    pb_display(pb_hhtable.get(key))
end
```

Description of Function `pb_display`

The `pb_display` function takes an argument `entry`, which is a phone book entry. After displaying a horizontal line, `pb_display` calls MATLAB function `strtok` to extract the first line of the entry, up to the line delimiter (^), into `t` and the remainder into `r`. Then, within a `while` loop that terminates when `t` is empty, it displays the current line in `t`. Then it calls `strtok` to extract the next line from `r`, into `t`. When all lines have been displayed, `pb_display` indicates the end of the entry by displaying another horizontal line.

```
function pb_display(entry)
disp ' '
disp '-----'
[t,r] = strtok(entry, '^');
while ~isempty(t)
    disp(sprintf(' %s',t))
    [t,r] = strtok(r, '^');
end
disp '-----'
```

Description of Function `pb_keyfilter`

The `pb_keyfilter` function takes an argument `key`, which is a name used as a key in the hash table, and either filters it for storage or unfilters it for display. The filter, which replaces each space in the key with an underscore (`_`), makes the key usable with the methods of `java.util.Properties`.

```
function out = pb_keyfilter(key)
if ~isempty(strfind(key, ' '))
```

```

    out = strep(key, ' ', '_');
else
    out = strep(key, '_', ' ');
end

```

Running the phonebook Program

In this sample run, a user invokes `phonebook` with no arguments. The user selects menu action 5, which displays the two entries currently in the phone book (all entries are fictitious). Then, the user selects 2, to add an entry. After adding the entry, the user again selects 5, which displays the new entry along with the other two entries.

Phonebook Menu:

1. Look up a phone number
2. Add an entry to the phone book
3. Remove an entry from the phone book
4. Change the contents of an entry in the phone book
5. Display entire contents of the phone book
6. Exit this program

Please type the number for a menu selection: 5

```

-----
Sylvia Woodland
(508) 111-3456
-----

```

```

-----
Russell Reddy
(617) 999-8765
-----

```

Phonebook Menu:

1. Look up a phone number
2. Add an entry to the phone book
3. Remove an entry from the phone book
4. Change the contents of an entry in the phone book
5. Display entire contents of the phone book
6. Exit this program

Please type the number for a menu selection: 2

Type the name for the new entry, followed by Enter.
Then, type the phone number(s), one per line.
To complete the entry, type an extra Enter.
:: BriteLites Books
:: (781) 777-6868
::

BriteLites Books has been added to the phone book.

Phonebook Menu:

1. Look up a phone number
2. Add an entry to the phone book
3. Remove an entry from the phone book
4. Change the contents of an entry in the phone book
5. Display entire contents of the phone book
6. Exit this program

Please type the number for a menu selection: 5


```
-----  
BriteLites Books  
(781) 777-6868  
-----  
  
-----  
Sylvia Woodland  
(508) 111-3456  
-----  
  
-----  
Russell Reddy  
(617) 999-8765  
-----
```


Java Heap Memory Preferences

You can adjust the amount of memory that MATLAB software allocates for Java objects.

Note: The default heap size is sufficient for most cases.

To adjust the Java heap size:

- 1 On the **Home** tab, in the **Environment** section, click  **Preferences**. Select **MATLAB > General > Java Heap Memory**.
- 2 Select a Java heap size value using the slider or spin box.

Note: Increasing the Java heap size decreases the amount of memory available for storing data in arrays.

- 3 Click **OK**.
- 4 Restart MATLAB.

If the amount of memory you specified is not available upon restart, MATLAB resets the value to the default, and displays an error dialog box. To readjust the value, repeat the previous steps.

If increasing the heap size does not eliminate memory errors, check your Java code for memory leaks. Eliminate references to objects that are no longer useful. For more information, see the Java SE Troubleshooting guide at <http://www.oracle.com/technetwork/java/javase/index-138283.html>.

Using .NET Libraries from MATLAB

- “Access a Simple .NET Class” on page 10-4
- “Load a Global .NET Assembly” on page 10-9
- “Work with Microsoft Excel Spreadsheets Using .NET” on page 10-10
- “Work with Microsoft Word Documents Using .NET” on page 10-12
- “Assembly is Library of .NET Classes” on page 10-13
- “Limitations to .NET Support” on page 10-14
- “System Requirements for Using MATLAB Interface to .NET” on page 10-16
- “Using .NET from MATLAB” on page 10-17
- “Using a .NET Object” on page 10-19
- “Build a .NET Application for MATLAB Examples” on page 10-21
- “Troubleshooting Security Policy Settings From Network Drives” on page 10-22
- “.NET Terminology” on page 10-23
- “Simplify .NET Class Names” on page 10-24
- “Use import in MATLAB Functions” on page 10-25
- “Nested Classes” on page 10-26
- “Handle .NET Exceptions” on page 10-27
- “Pass Numeric Arguments” on page 10-28
- “Pass System.String Arguments” on page 10-29
- “Pass System.Enum Arguments” on page 10-31
- “Pass System.Nullable Arguments” on page 10-33
- “Pass Cell Arrays of .NET Data” on page 10-37
- “Pass Jagged Arrays” on page 10-40
- “Convert Nested System.Object Arrays” on page 10-43
- “Passing Data to .NET Objects” on page 10-44
- “Handling Data Returned from .NET Objects” on page 10-51

- “Using Arrays with .NET Applications” on page 10-56
- “Set Static .NET Properties” on page 10-60
- “Using .NET Properties” on page 10-62
- “MATLAB Does Not Display Protected Properties” on page 10-64
- “Work with .NET Methods Having Multiple Signatures” on page 10-65
- “SampleMethods Class” on page 10-67
- “Call .NET Methods With out Keyword” on page 10-69
- “Call .NET Methods With ref Keyword” on page 10-70
- “Call .NET Methods With params Keyword” on page 10-71
- “Call .NET Methods with Optional Arguments” on page 10-72
- “Calling .NET Methods” on page 10-75
- “Calling .NET Generic Methods” on page 10-77
- “Calling .NET Methods with Optional Arguments” on page 10-78
- “Calling .NET Extension Methods” on page 10-79
- “Call .NET Properties That Take an Argument” on page 10-80
- “How MATLAB Represents .NET Operators” on page 10-82
- “Limitations to Support of .NET Methods” on page 10-83
- “Use .NET Events in MATLAB” on page 10-84
- “Call .NET Delegates in MATLAB” on page 10-86
- “Create Delegates from .NET Object Methods” on page 10-88
- “Create Delegate Instances Bound to .NET Methods” on page 10-89
- “Call Delegates With out and ref Type Arguments” on page 10-91
- “Combine and Remove .NET Delegates” on page 10-92
- “.NET Delegates” on page 10-94
- “Calling .NET Methods Asynchronously” on page 10-95
- “Limitations to Support of .NET Events” on page 10-99
- “Limitations to Support of .NET Delegates” on page 10-100
- “Use Bit Flags with .NET Enumerations” on page 10-101
- “Read Special System Folder Path” on page 10-105
- “.NET Enumerations in MATLAB” on page 10-106

- “Default Methods for an Enumeration” on page 10-107
- “NetDocEnum Example Assembly” on page 10-109
- “Work with Members of a .NET Enumeration” on page 10-110
- “Refer to a .NET Enumeration Member” on page 10-112
- “Display .NET Enumeration Members as Character Strings” on page 10-114
- “Convert .NET Enumeration Values to Type Double” on page 10-115
- “Iterate Through a .NET Enumeration” on page 10-116
- “Use .NET Enumerations to Test for Conditions” on page 10-118
- “Underlying Enumeration Values” on page 10-120
- “Limitations to Support of .NET Enumerations” on page 10-121
- “Create .NET Collections” on page 10-122
- “Convert .NET Collections to MATLAB Arrays” on page 10-124
- “Create .NET Arrays of Generic Type” on page 10-125
- “Display .NET Generic Methods Using Reflection” on page 10-126
- “.NET Generic Classes” on page 10-129
- “Accessing Items in .NET Collections” on page 10-130
- “Call .NET Generic Methods” on page 10-131

Access a Simple .NET Class

In this section...

“System.DateTime Example” on page 10-4

“Create .NET Object From Constructor” on page 10-5

“View Information About .NET Object” on page 10-5

“Introduction to .NET Data Types” on page 10-7

System.DateTime Example

This example shows how to access functionality already loaded on your system. The topics following the example introduce some key steps and ideas to help you get started using .NET in MATLAB.

The Microsoft .NET Framework class library contains classes, such as `System.DateTime`, you can use in MATLAB. The following code creates an object and uses `DateTime` properties and methods to display information about the current date and time.

```
% Create object for current date and time
netDate = System.DateTime.Now;

% Display properties
netDate.DayOfWeek
netDate.Hour

% Call methods
ToShortTimeString(netDate)
AddDays(netDate,7);

% Call static method
System.DateTime.DaysInMonth(netDate.Year,netDate.Month)
```

The following topics provide more information about creating and viewing information about objects and an introduction to .NET data types.

For information about the .NET Framework class library, refer to the third party documentation described in “To Learn More About the .NET Framework”.

Create .NET Object From Constructor

The example in the previous section uses the `Now` property to create a `DateTime` object. The following example shows how to create an object using one of the `DateTime` constructors.

```
myDate = System.DateTime(2000,1,31);
```

To call this constructor, or any method, you need to know its argument list, or *function signature*. Your vendor product documentation shows the function signatures. You can also display the signatures using the MATLAB `methodsview` function. Type `methodsview('System.DateTime')` and search the list for `DateTime` entries, such as shown in the following table.

Return Type	Name	Arguments
System.DateTime obj	DateTime	(int32 scalar year, etc.

From the .NET Class Framework documentation, the following signature initializes a new instance of the `DateTime` structure to the specified year, month, and day, which is the information required for the `myDate` variable.

Return Type	Name	Arguments
System.DateTime obj	DateTime	(int32 scalar year, int32 scalar month, int32 scalar day)

For more information, see “Reading Method Signatures” on page 10-76.

View Information About .NET Object

Although the vendor documentation contains information about `DateTime` objects, you can use MATLAB commands, like `properties` and `methods`, to display information about .NET objects. For example:

```
% Display an object
netDate = System.DateTime.Now
% Display its properties
properties System.DateTime
% Display its methods
methods System.DateTime
```

MATLAB displays the following information. (The property values reflect your specific date and time.)

Display of DateTime Object

```
netDate =  
System.DateTime  
Package: System  
  
Properties:  
    Date: [1x1 System.DateTime]  
    Day: 11  
    DayOfWeek: [1x1 System.DayOfWeek]  
    DayOfYear: 11  
    Hour: 12  
    Kind: [1x1 System.DateTimeKind]  
    Millisecond: 413  
    Minute: 31  
    Month: 1  
    Now: [1x1 System.DateTime]  
    UtcNow: [1x1 System.DateTime]  
    Second: 38  
    Ticks: 634303458984133595  
    TimeOfDay: [1x1 System.TimeSpan]  
    Today: [1x1 System.DateTime]  
    Year: 2011  
    MinValue: [1x1 System.DateTime]  
    MaxValue: [1x1 System.DateTime]  
Methods, Superclasses
```

Display of DateTime Properties

Properties for class System.DateTime:

```
Date  
Day  
DayOfWeek  
DayOfYear  
Hour  
Kind  
Millisecond  
Minute  
Month  
Now  
UtcNow
```



```

Second
Ticks
TimeOfDay
Today
Year
MinValue
MaxValue

```

Display of DateTime Methods

Methods for class System.DateTime:

Add	GetType	ToUniversalTime
AddDays	GetTypeCode	addlistener
AddHours	IsDaylightSavingTime	delete
AddMilliseconds	Subtract	eq
AddMinutes	ToBinary	findobj
AddMonths	ToFileTime	findprop
AddSeconds	ToFileTimeUtc	ge
AddTicks	ToLocalTime	gt
AddYears	ToLongDateString	invalid
CompareTo	ToLongTimeString	le
DateTime	ToOADate	lt
Equals	ToShortDateString	ne
GetDateTimeFormats	ToShortTimeString	notify
GetHashCode	ToString	

Static methods:

Compare	Parse	op_GreaterThan
DaysInMonth	ParseExact	op_GreaterThanOrEqual
FromBinary	SpecifyKind	op_Inequality
FromFileTime	TryParse	op_LessThan
FromFileTimeUtc	TryParseExact	op_LessThanOrEqual
FromOADate	op_Addition	op_Subtraction
IsLeapYear	op_Equality	

For more information, see:

- “Using .NET Properties”
- “Calling .NET Methods” on page 10-75

Introduction to .NET Data Types

To use .NET objects in MATLAB, you need to understand how MATLAB treats .NET data types. For example, the following `DateTime` properties and methods create variables of various .NET types:

```
netDate = System.DateTime.Now;
```

```
thisDay = netDate.DayOfWeek;  
thisHour = netDate.Hour;  
thisDate = ToLongDateString(netDate);  
thisTime = ToShortTimeString(netDate);  
monthSz = System.DateTime.DaysInMonth(netDate.Year,netDate.Month);  
whos
```

Name	Size	Bytes	Class
netDate	1x1	112	System.DateTime
monthSz	1x1	4	int32
thisDate	1x1	112	System.String
thisDay	1x1	104	System.DayOfWeek
thisHour	1x1	4	int32
thisTime	1x1	112	System.String

MATLAB displays the type as a class name.

To use these variables in MATLAB, consider the following:

- Numeric values (`int32`) — MATLAB preserves .NET numeric types by mapping them into equivalent MATLAB types. In the following example, `h` is type `int32`.

```
h = thisHour + 1;
```

For more information, see “.NET Type to MATLAB Type Mapping” on page 10-51 and “Numeric Types”.

- Strings (`System.String`) — Use the `char` function to convert a `System.String` object to a MATLAB string:

```
disp(['The time is ' char(thisTime)])
```

- Objects (`System.DateTime`) — Refer to the .NET Framework class library documentation for information about using a `DateTime` object.
- Enumerations (`System.DayOfWeek`) — According to the `DateTime` documentation, `DayOfWeek` is an enumeration. To display the enumeration members, type:

```
enumeration(thisDay)
```

For more information, see “Enumerations”.

For a complete list of supported types and mappings, see “Handling Data Returned from .NET Objects” on page 10-51.

Load a Global .NET Assembly

This example shows you how to make .NET classes visible to MATLAB by loading a global assembly using the `NET.addAssembly` function.

The speech synthesizer class (available in .NET Framework Version 3.0 and above) provides ready-to-use text-to-speech features. For example, type:

```
NET.addAssembly('System.Speech');  
speak = System.Speech.Synthesis.SpeechSynthesizer;  
speak.Volume = 100;  
Speak(speak, 'You can use .NET Libraries in MATLAB')
```

The speech synthesizer class, like any .NET class, is part of an *assembly*. To work with the class, call `NET.addAssembly` to load the assembly into MATLAB. Your vendor documentation contains the assembly name. For example, search the Microsoft .NET Framework website for the `System.SpeechSynthesizer` class. The assembly name is `System.Speech`.

```
NET.addAssembly('System.Speech');
```

The `System.Speech` assembly is a *global* assembly. If your assembly is a *private* assembly, use the full path for the input to `NET.addAssembly`.

The “System.DateTime Example” on page 10-4 does not call `NET.addAssembly` because MATLAB dynamically loads its assembly (`mscorlib`) at startup.

Note: You cannot unload an assembly in MATLAB.

For more information, see:

- “Assembly is Library of .NET Classes” on page 10-13

Work with Microsoft Excel Spreadsheets Using .NET

This example creates a spreadsheet, copies some MATLAB data to it, and closes it. The example uses classes from the `Microsoft.Office.Interop.Excel.ApplicationClass` class. For information about the class and using the interface with different versions of Excel®, refer to documentation on the MSDN website <http://msdn.microsoft.com/>.

To create a workbook, type:

```
NET.addAssembly('microsoft.office.interop.excel');
app = Microsoft.Office.Interop.Excel.ApplicationClass;
books = app.Workbooks;
newWB = Add(books);
app.Visible = true;
```

Create a new sheet:

```
sheets = newWB.Worksheets;
newSheet = Item(sheets,1);
```

`newSheet` is a `System.__ComObject` because `sheets.Item` can return different types, such as a `Chart` or a `Worksheet`. To make the sheet a `Worksheet`, use the command:

```
newWS = Microsoft.Office.Interop.Excel.Worksheet(newSheet);
```

Create MATLAB data and write columns 1 and 2 to a range of cells.

```
excelArray = rand(10);
newRange = Range(newWS, 'A1');
newRange.Value2 = 'Data from Location A';
newRange = Range(newWS, 'A3:B12');
newRange.Value2 = excelArray;
```

Add three text strings to column C.

```
% Create a 3x1 System.Object
strArray = NET.createArray('System.Object',3,1);
strArray(1,1) = 'Add';
strArray(2,1) = 'text';
strArray(3,1) = 'to column C';
newRange = Range(newWS, 'C3:C5');
newRange.Value2 = strArray;
```

Modify cell format and name the worksheet:

```
newFont = newRange.Font;  
newFont.Bold = 1;  
newWS.Name = 'Test Data';
```

If this is a new spreadsheet, use the `SaveAs` method:

```
SaveAs(newWB, 'mySpreadsheet.xlsx');
```

Close and quit:

```
Close(newWB)  
Quit(app)
```

Work with Microsoft Word Documents Using .NET

This example uses classes from the `Microsoft.Office.Interop.Word.ApplicationClass` class. For information about the class and using the interface with different versions of Microsoft Word, refer to documentation on the MSDN website <http://msdn.microsoft.com/>.

The following code creates a new Word document:

```
NET.addAssembly('microsoft.office.interop.word');  
wordApp = Microsoft.Office.Interop.Word.ApplicationClass;  
wordDoc = wordApp.Documents;  
newDoc = Add(wordDoc);
```

If you want to type directly into the document, type the MATLAB command:

```
wordApp.Visible = true;
```

Put the cursor into the document window and enter text.

To name the document `myDocument.docx` and save it in the My Documents folder, type:

```
SaveAs(newDoc, 'myDocument.docx');
```

When you are finished, to close the document and application, type:

```
Save(newDoc);  
Close(newDoc);  
Quit(wordApp);
```

Assembly is Library of .NET Classes

Assemblies are the building blocks of .NET Framework applications; they form the fundamental unit of deployment, version control, reuse, activation scoping, and security permissions. An *assembly* is a collection of types and resources built to work together and form a logical unit of functionality.

To work with a .NET application, you need to make its assemblies visible to MATLAB. How you do this depends on how the assembly is deployed, either privately or globally.

- *global* assembly—Shared among applications and installed in a common directory, called the *Global Assembly Cache* (GAC).
- *private* assembly—Used by a single application.

To load a global assembly into MATLAB, use the short name of the assembly, which is the file name without the extension. To load a private assembly, you need the *full path* (folder and file name with extension) of the assembly. This information is in the vendor documentation for the assembly. Refer to the vendor documentation for information about using your product.

The following assemblies from the .NET Framework class library are available at startup. MATLAB dynamically loads them the first time you type “NET.” or “System.”.

- `mscorlib.dll`
- `system.dll`

To use any other .NET assembly, load the assembly using the `NET.addAssembly` command. After loading the assembly, you can work with the classes defined by the assembly.

Note: You cannot unload an assembly in MATLAB. If you modify and rebuild your own assembly, you must restart MATLAB to access the changes.

See Also

`NET.addAssembly`

Limitations to .NET Support

MATLAB supports the .NET features C# supports, except for the limits noted in the following table.

Features Not Supported in MATLAB
Cannot use <code>ClassName.propertyname</code> syntax to set static properties. Use <code>NET.setStaticProperty</code> instead.
Unloading an assembly
Passing a structure array, sparse array, or complex number to a .NET property or method
Subclassing .NET classes from MATLAB
Accessing nonpublic class members
Displaying generic methods using <code>methods</code> or <code>methodsview</code> functions. For a workaround, see “Display .NET Generic Methods Using Reflection” on page 10-126.
Creating an instance of a nested class. For a workaround, see “Nested Classes” on page 10-26.
Saving (serializing) .NET objects into a MAT-file
Creating .NET arrays with a specific lower bound
Concatenating multiple .NET objects into an array
Implementing interface methods
Hosting .NET controls in figure windows
Casting operations
Calling constructors with <code>ref</code> or <code>out</code> type arguments
Using <code>System.Console.WriteLine</code> to write text to the command window
Pointer type arguments, function pointers, <code>Dllimport</code> keyword
.NET remoting
Using the MATLAB <code>:</code> (colon) operator in a <code>foreach</code> iteration
Adding event listeners to .NET events defined in static classes
Handling .NET events with signatures that do not conform to the standard signature
Creating empty .NET objects

Features Not Supported in MATLAB

Creating .NET objects that do not belong to a namespace

System Requirements for Using MATLAB Interface to .NET

The MATLAB interface to .NET is available on the Windows platform only.

You must have the Microsoft .NET Framework installed on your system.

The MATLAB interface requires the .NET Framework Version 4.0 and above. The interface continues to support assemblies built on Framework 2.0 and above. To determine if your system has the supported framework, use the `NET.IsNETSupported` function.

To use a .NET application, refer to your vendor's product documentation for information about how to install the program and for details about its functionality.

MATLAB Configuration File

MATLAB provides a configuration file, `MATLAB.exe.config`, in your `matlabroot/bin/arch` folder. With this file, MATLAB loads the latest core assemblies available on your system. You can modify and use the configuration file at your own risk. For additional information on elements that can be used in the configuration file, please visit the Configuration File Schema for the .NET Framework Web page at <http://msdn.microsoft.com/en-us/library/1fk1t1t0.aspx>.

Using .NET from MATLAB

In this section...

“Benefits of the MATLAB .NET Interface” on page 10-17

“Why Use the MATLAB .NET Interface?” on page 10-17

“NET Assembly Integration Using MATLAB Compiler SDK” on page 10-18

“To Learn More About the .NET Framework” on page 10-18

Benefits of the MATLAB .NET Interface

The MATLAB .NET interface enables you to:

- Create instances of .NET classes.
- Interact with .NET applications via their class members.

Why Use the MATLAB .NET Interface?

Use the MATLAB .NET interface to take advantage of the capabilities of the Microsoft .NET Framework. For example:

- You have a professionally developed .NET assembly and want to use it to do certain operations, such as access hardware.
- You want to leverage the capabilities of programming in .NET (for example, you have existing C# programs).
- You want to access existing Microsoft-supplied classes for .NET.

The speech synthesizer class, available in .NET Framework Version 3.0 and above, is an example of a ready-to-use feature. Create the following `Speak` function in MATLAB:

```
function Speak(text)
NET.addAssembly('System.Speech');
speak = System.Speech.Synthesis.SpeechSynthesizer;
speak.Volume = 100;
Speak(speak, text)
end
```

For an example rendering text to speech, type:

```
Speak('You can use .NET Libraries in MATLAB')
```

NET Assembly Integration Using MATLAB Compiler SDK

The MATLAB .NET interface is for MATLAB users who want to use .NET assemblies in MATLAB.

NET Assembly Integration in the MATLAB Compiler SDK™ product packages MATLAB functions so that .NET programmers can access them. It brings MATLAB into .NET applications. For information about NET Assembly Integration, see the MATLAB Compiler SDK product documentation.

To Learn More About the .NET Framework

For a complete description of the .NET Framework, you need to consult outside resources.

One source of information is the Microsoft Developer Network. Search the .NET Framework Development Center at <http://msdn.microsoft.com/en-us/netframework/aa496123> for the term “.NET Framework Class Library”. The .NET Framework Class Library is a programming reference manual. Many examples in this documentation refer to classes in this library. There are different versions of the .NET Framework documentation, so be sure to refer to the version that is on your system. See “System Requirements for Using MATLAB Interface to .NET” on page 10-16 for information about version support in MATLAB.

More About

- “Limitations to .NET Support” on page 10-14

Using a .NET Object

In this section...

“Creating a .NET Object” on page 10-19

“What Classes Are in a .NET Assembly?” on page 10-19

“Using the delete Function on a .NET Object” on page 10-20

Creating a .NET Object

You often need to create objects when working with .NET classes. An *object* is an instance of a particular class. Methods are functions that operate exclusively on objects of a class. Data types package together objects and methods so that the methods operate on objects of their own type. For more information about objects, see “MATLAB Objects”.

You construct .NET objects in the MATLAB workspace by calling the class constructor, which has the same name as the class. The syntax to create a .NET object `classObj` is:

```
classObj = namespace.ClassName(varargin)
```

where `varargin` is the list of constructor arguments to create an instance of the class specified by `ClassName` in the given `namespace`. For an example, see “Create .NET Object From Constructor” on page 10-5.

To call method `methodName`:

```
returnedValue = methodName(classObj, args, ...)
```

For more information, see:

- “Properties”
- “Methods”
- “Events and Delegates”

What Classes Are in a .NET Assembly?

The product documentation for your assembly contains information about its classes. However, you can use the `NET.addAssembly` command to read basic information about an assembly.

For example, to view the class names of the `mscorlib` library, type:

```
asm = NET.addAssembly('mscorlib');  
asm.Classes
```

This assembly has hundreds of entries. You can open a window to the online document for the `System` namespace reference page on the Microsoft Developer Network. For information about using this documentation, see “To Learn More About the .NET Framework” on page 10-18.

Using the `delete` Function on a .NET Object

Objects created from .NET classes appear in MATLAB as reference types, or handle objects. Calling the `delete` function on a .NET handle releases all references to that .NET object from MATLAB, but does not invoke any .NET finalizers. The .NET Framework manages garbage collection.

For more information about managing handle objects, see “Destroying Objects”.

Build a .NET Application for MATLAB Examples

You can use C# code examples in MATLAB, such as the `NetDocCell` assembly provided in “Converting .NET Arrays to Cell Arrays”. Build an application using a C# development tool, like Microsoft Visual Studio and then load it into MATLAB using the `NET.addAssembly` function. The following are basic steps to do this; consult your development tool documentation for specific instructions.

- 1** From your development tool, open a new project and create a C# class library.
- 2** Copy the classes and other constructs from the C# files into your project.
- 3** Build the project as a DLL.
- 4** The name of this assembly is the namespace. Note the full path to the DLL file. Since it is a private assembly, you must use the full path to load it in MATLAB.
- 5** After you load the assembly, if you modify and rebuild it, you must restart MATLAB to access the new assembly. You cannot unload an assembly in MATLAB.

Troubleshooting Security Policy Settings From Network Drives

If you run a .NET command on a MATLAB session started from a network drive, you could see a warning message. To resolve this problem, run the `enableNETfromNetworkDrive.m` file, from the `matlabroot\toolbox\matlab\winfun\NET` folder.

This file adds the following entry to the security policy on your machine to trust the `dotnetcli` assembly, which is the MATLAB interface to .NET module:

- Creates a group named `MathWorks_Zone` with `LocalIntranet` permission.
- Creates a `dotnetcli` subgroup within `MathWorks_Zone`.
- Provides `Full-Trust` to the `dotnetcli.dll` strong name for access to the local intranet.

You must have administrative privileges to make changes to your configuration.

.NET Terminology

A *namespace* is a way to group identifiers. A namespace can contain other namespaces. In MATLAB, a namespace is a package. In MATLAB, a .NET type is a class.

The syntax `namespace.ClassName` is known as a *fully qualified name*.

.NET Framework System Namespace

`System` is the root namespace for fundamental types in the .NET Framework. This namespace also contains classes (for example, `System.String` and `System.Array`) and second-level namespaces (for example, `System.Collections.Generic`). The `microsoft` and `system` assemblies, which MATLAB loads at startup, contain many, but not all `System` namespaces. For example, to use classes in the `System.Xml` namespace, load the `system.xml` assembly using the `NET.addAssembly` command. Refer to the Microsoft .NET Framework Class Library Reference to learn what assembly to use for a specific namespace.

Reference Type Versus Value Type

Objects created from .NET classes (for example, the `System.Reflection.Assembly` class) appear in MATLAB as *reference types*, or handle objects. Objects created from .NET structures (for example, the `System.DateTime` structure) appear as *value types*. You use the same MATLAB syntax to create and access members of classes and structures.

However, handle objects are different from value objects. When you copy a handle object, only the handle is copied and both the old and new handles refer to the same data. When you copy a value object, the object's data is also copied and the new object is independent of changes to the original object. For more information about these differences, see “Copying Objects”.

Do not confuse an object created from a .NET structure with a MATLAB structure array (see “Structures”). You cannot pass a structure array to a .NET method.

Simplify .NET Class Names

In a MATLAB command, you can refer to any class by its fully qualified name, which includes its package name. A fully qualified name might be long, making commands and functions, such as constructors, cumbersome to edit and to read. You can refer to classes by the class name alone (without a package name) if you first import the fully qualified name into MATLAB. The `import` function adds all classes that you import to a list called the import list. You can see what classes are on that list by typing `import`, without any arguments.

For example, to eliminate the need to type `System.` before every command in the “Access a Simple .NET Class” on page 10-4 example, type:

```
import System.*  
import System.DateTime.*
```

To create the object, type:

```
netDate = DateTime.Today;
```

To use a static method, type:

```
DaysInMonth(netDate.Year, netDate.Month)
```

Use import in MATLAB Functions

If you use the `import` command in a MATLAB function, add the corresponding .NET assembly before calling the function. For example, the following function `getPrinterInfo` calls methods in the `System.Drawing` namespace.

```
function ptr = getPrinterInfo
import System.Drawing.Printing.*;
ptr = PrinterSettings;
end
```

To call the function, type:

```
NET.addAssembly('System.Drawing');
printer = getPrinterInfo;
```

You cannot add the command `NET.addAssembly('System.Drawing')` to the `getPrinterInfo` function. MATLAB processes the `getPrinterInfo.m` code before executing the `NET.addAssembly` command. In that case, `PrinterSettings` is not fully qualified and MATLAB does not recognize the name.

Likewise, the scope of the `import` command is limited to the `getPrinterInfo` function. At the command line, type:

```
ptr = PrinterSettings;
```

```
Undefined function or variable 'PrinterSettings'.
```

See Also

`import`

Nested Classes

In MATLAB, you cannot directly instantiate a nested class but here is how to do it through reflection. The following C# code defines `InnerClass` nested in `OuterClass`:

```
namespace MyClassLibrary
{
    public class OuterClass
    {
        public class InnerClass
        {
            public String strmethod(String x)
            {
                return "from InnerClass " + x;
            }
        }
    }
}
```

If the `MyClassLibrary` assembly is in your `c:\work` folder, load the file:

```
a = NET.addAssembly('C:\Work\MyClassLibrary.dll');
a.Classes
```

```
ans =
    'MyClassLibrary.OuterClass'
    'MyClassLibrary.OuterClass+InnerClass'
```

To call `strmethod`, type:

```
t = a.AssemblyHandle.GetType('MyClassLibrary.OuterClass+InnerClass');
sa = System.Activator.CreateInstance(t);
strmethod(sa, 'hello')

ans =
from InnerClass hello
```

Handle .NET Exceptions

MATLAB catches exceptions thrown by .NET and converts them into a `NET.NetException` object, which is derived from the `MException` class. The default display of `NetException` contains the `Message`, `Source` and `HelpLink` fields of the `System.Exception` class that caused the exception. For example:

```
try
    NET.addAssembly('C:\Work\invalidfile.dll')
catch e
    e.message
    if(isa(e,'NET.NetException'))
        e.ExceptionObject
    end
end
```

Pass Numeric Arguments

In this section...

“Call .NET Methods with Numeric Arguments” on page 10-28

“Use .NET Numeric Types in MATLAB” on page 10-28

Call .NET Methods with Numeric Arguments

When you call a .NET method in MATLAB, MATLAB automatically converts numeric arguments into equivalent .NET types, as shown in the table in “Pass Primitive .NET Types” on page 10-44.

Use .NET Numeric Types in MATLAB

MATLAB automatically converts numeric data returned from a .NET method into equivalent MATLAB types, as shown in the table in “.NET Type to MATLAB Type Mapping” on page 10-51.

Note that MATLAB preserves .NET arrays as the relevant `System.Array` types, for example, `System.Double[]`.

MATLAB has rules for handling integers. If you are familiar with using integer types in MATLAB, and just need a reference to the rules, see the links at the end of this topic.

The default data type in MATLAB is `double`. If the data in your applications uses the default, then you need to pay attention to the numeric outputs of your .NET applications.

For more information, see:

- “Numeric Types”
- “Valid Combinations of Unlike Classes”
- “Combining Unlike Integer Types”
- “Integers”

Pass System.String Arguments

In this section...

“Call .NET Methods with System.String Arguments” on page 10-29

“Use System.String in MATLAB” on page 10-29

Call .NET Methods with System.String Arguments

If an input argument to a .NET method is `System.String`, you can pass a MATLAB string. MATLAB automatically converts a `char` array (string) argument into `System.String`. For example, the following code uses the `System.DateTime.Parse` method to convert a date represented by a string into a `DateTime` object:

```
strDate = '01 Jul 2010 3:33:02 GMT';
convertedDate = System.DateTime.Parse(strDate);
ToShortTimeString(convertedDate)
ToLongDateString(convertedDate)
```

To view the function signature for the `System.DateTime.Parse` method, type:

```
methodsview('System.DateTime')
```

Search the list for `Parse`.

Qualifiers	Return Type	Name	Arguments
Static	System.DateTime RetVal	Parse	(System.String s)

For more information, see:

- “Pass MATLAB Strings” on page 10-46
- Search the MSDN website at <http://msdn.microsoft.com/en-us/default.aspx> for the term `System.DateTime`.

Use System.String in MATLAB

This example shows how to use a `System.String` object in a MATLAB function.

Create an object representing the current time.

```
netDate = System.DateTime.Now;  
thisTime = ToShortTimeString(netDate);  
class(thisTime)
```

```
ans =  
System.String
```

The current time, `thisTime`, is a `System.String` object.

To display `thisTime` in MATLAB, use the `char` function to convert the `System.String` object to a MATLAB string.

```
disp(['The time is ' char(thisTime)])
```

More About

- “How MATLAB Handles `System.String`” on page 10-52

Pass System.Enum Arguments

In this section...

“Call .NET Methods with System.Enum Arguments” on page 10-31

“Use System.Enum in MATLAB” on page 10-32

Call .NET Methods with System.Enum Arguments

An example of an enumeration is `System.DayOfWeek`. To see how to call a .NET method with this input type, use the `GetAbbreviatedDayName` method in the `System.Globalization.DateTimeFormatInfo` class. The following code displays the abbreviation for “Thursday”.

```
% Create a DayOfWeek object
thisDay = System.DayOfWeek.Thursday;
dtformat = System.Globalization.DateTimeFormatInfo;
% Display the abbreviated name of the specified day based on the
% culture associated with the current DateTimeFormatInfo object.
dtformat.GetAbbreviatedDayName(thisDay)
```

To view the function signature for the `GetAbbreviatedDayName` method, type:

```
methodsview('System.Globalization.DateTimeFormatInfo')
```

Search the list for `GetAbbreviatedDayName`.

Return Type	Name	Arguments
System.String RetVal	GetAbbreviatedDayName	(System.Globalization.DateTimeFormatInfo this, System.DayOfWeek dayofweek)

For more information, see:

- “.NET Enumerations in MATLAB” on page 10-106
- Search the MSDN website at <http://msdn.microsoft.com/en-us/default.aspx> for the term `DateTimeFormatInfo`.

Use System.Enum in MATLAB

In MATLAB, an enumeration is a class having a finite set of named instances. You can work with .NET enumerations using features of the MATLAB enumeration class and some features unique to the .NET Framework. Some ways to use the `System.DayOfWeek` enumeration in MATLAB:

- Display an enumeration member. For example:

```
myDay = System.DateTime.Today;
disp(myDay.DayOfWeek)
```

- Use an enumeration in comparison statements. For example:

```
myDay = System.DateTime.Today;
switch(myDay.DayOfWeek)
    case {System.DayOfWeek.Saturday, System.DayOfWeek.Sunday}
        disp('Weekend')
    otherwise
        disp('Work day')
end
```

- Perform calculations. For example, the underlying type of `DayOfWeek` is `System.Int32` which you can use to perform integer arithmetic. To display the date of the first day of the current week, type:

```
myDay = System.DateTime.Today;
dow = myDay.DayOfWeek;
startDateOfWeek = AddDays(myDay, -double(dow));
ToShortDateString(startDateOfWeek)
```

- Perform bit-wise operations. For examples, see “Creating .NET Enumeration Bit Flags” on page 10-101.

For more information, see:

- “Iterate Through a .NET Enumeration” on page 10-116
- “Use .NET Enumerations to Test for Conditions” on page 10-118
- “Use Bit Flags with .NET Enumerations” on page 10-101

Pass System.Nullable Arguments

This example shows how to handle .NET methods with `System.Nullable` type arguments, whose underlying value type is `double`.

The example shows how to call a method with a `System.Nullable` input argument. It uses the MATLAB `plot` function to show to handle a `System.Nullable` output argument.

Build Custom Assembly NetDocNullable

To execute the MATLAB code in this example, build the `NetDocNullable` assembly. The assembly is created with the C# code, `NetDocNullable.cs`, in the `matlabroot/extern/examples/NET/NetSample` folder. To see the code, open the file in MATLAB Editor and build the `NetDocNullable` assembly.

`NetDocNullable` defines method `SetField` which has `System.Nullable` arguments.

SetField Function Signature

Return Type	Name	Arguments
<code>System.Nullable<System*Double></code> <code>RetVal</code>	<code>SetField</code>	<code>(NetDocNullable. MyClass this, System.Nullable <System*Double> db)</code>

Load NetDocNullable Assembly

The example assumes you put the assembly in your `c:\work` folder. You can modify the example to change the path, `dllPath`, of the assembly.

```
dllPath = fullfile('c:', 'work', 'NetDocNullable.dll');
asm = NET.addAssembly(dllPath);
cls = NetDocNullable.MyClass;
```

Use the `cls` variable to call `SetField`, which creates a `System.Nullable<System*Double>` value from your input.

Pass System.Nullable Input Arguments

MATLAB automatically converts `double` and `null` values to `System.Nullable<System*Double>` objects.

Pass a **double** value.

```
field1 = SetField(cls,10)

field1 =
  System.Nullable<System*Double>
  Package: System

  Properties:
    HasValue: 1
    Value: 10
  Methods, Superclasses
```

The **HasValue** property is true (1) and the **Value** property is 10.

Pass null value, [].

```
field2 = SetField(cls,[])

field2 =
  System.Nullable<System*Double>
  Package: System

  Properties:
    HasValue: 0
  Methods, Superclasses
```

The **HasValue** property is false (0), and it has no **Value** property.

Handle System.Nullable Output Arguments in MATLAB

Before you use a **System.Nullable** object in MATLAB, first decide how to handle **null** values. If you ignore **null** values, you might get unexpected results when you use the value in a MATLAB function.

The **System.Nullable** class provides two techniques for handling **null** values. To provide special handling for **null** values, use the **HasValue** property. To treat a **null** value in the same way as a **double**, use the **GetValueOrDefault** method.

Create a MATLAB function, **plotValue.m**, which detects **null** values and treats them differently from numeric values. The input is a **System.Nullable<System*Double>** type. If the input is **null**, the function displays a message. If the input value is **double**, it creates a line graph from 0 to the value.

```
function plotValue(x)
```

```

% x is System.Nullable<System*Double> type
if (x.HasValue && isfloat(x.Value))
    plot([0 x.Value])
else
    disp('No Data')
end

```

The `plotValue` function uses the `HasValue` property of the input argument to detect null values and calls the MATLAB `plot` function using the `Value` property.

Call `plotValue` with variable `field1` to display a line graph.

```
plotValue(field1)
```

Call `plotValue` with the variable `field2`, a null value.

```
plotValue(field2)
```

```
No Data
```

If you do not need special processing for null values, use the `GetValueOrDefault` method. To display the `GetValueOrDefault` function signature, type:

```
methodsview(field1)
```

Look for the following function signature:

GetValueOrDefault Function Signature

Return Type	Name	Arguments
double scalar RetVal	GetValueOrDefault	(System.Nullable <System*Double> this)

This method converts the input variable to `double` so you can directly call the MATLAB `plot` function:

```
myData = GetValueOrDefault(field1);
plot([0 myData+2])
```

The `GetValueOrDefault` method converts a null value to the default numeric value, 0.

```
defaultData = GetValueOrDefault(field2)
```

```
defaultData =
```

0

Call `plot`:

```
plot([0 defaultData])
```

You can change the default value using the `GetValueOrDefault` method. Open the `methodsvi` window and look for the following function signature:

GetValueOrDefault Function Signature to Change Default

Return Type	Name	Arguments
double scalar RetVal	GetValueOrDefault	(System.Nullable <System*Double> this, double scalar defaultValue)

Set the `defaultValue` input argument to a new value, `-1`, and plot the results for `null` value `field2`.

```
defaultData = GetValueOrDefault(field2, -1);
plot([0 defaultData])
```

Related Examples

- “Build a .NET Application for MATLAB Examples” on page 10-21

More About

- “Pass System.Nullable Type” on page 10-46
- “How MATLAB Handles System.Nullable” on page 10-54

External Web Sites

- <http://msdn.microsoft.com/en-us/default.aspx>

Pass Cell Arrays of .NET Data

In this section...

“Example of Cell Arrays of .NET Data” on page 10-37

“Create a Cell Array for Each System.Object” on page 10-38

“Create MATLAB Variables from the .NET Data” on page 10-38

“Call MATLAB Functions with MATLAB Variables” on page 10-38

Example of Cell Arrays of .NET Data

In the “Converting Nested System.Object Arrays” on page 10-57 example, the cell array `mldata` contains data from the `MyGraph.getNewData` method. By reading the class documentation in the source file, you can create the following MATLAB graph:

```
dllPath = fullfile('c:', 'work', 'NetDocCell.dll');
asm = NET.addAssembly(dllPath);
graph = NetDocCell.MyGraph;

% Create cell array containing all data
mldata = cell(graph.getNewData);

% Plot the data and label the graph
figure('Name', char(mldata{1}))
plot(double(mldata{2}(2)))
xlabel(char(mldata{2}(1)))
```

However, keeping track of data of different types and dimensions and the conversions necessary to map .NET data into MATLAB types is complicated using the cell array structure. Here are some tips for working with the contents of nested `System.Object` arrays in MATLAB. After reading data from a .NET method:

- Create cell arrays for all `System.Object` arrays.
- Convert the .NET types to MATLAB types, according to the information in “Handling Data Returned from .NET Objects” on page 10-51.
- Create MATLAB variables for each type within the cell arrays.
- Call MATLAB functions with the MATLAB variables.

Create a Cell Array for Each System.Object

This example shows how to copy `System.Object` data into a cell array.

The following statement creates the cell array `mldata`:

```
mldata = cell(graph.getNewData)

mldata =
    [1x1 System.String]    [1x1 System.Object[]]
```

This cell array contains elements of these types.

To access the contents of the `System.Object` array, create another cell array `mldata`:

```
mldata = cell(mldata{2})

mldata =
    [1x1 System.String]    [1x1 System.Double[]]
```

This cell array contains elements of these types.

Create MATLAB Variables from the .NET Data

Assign cell data to MATLAB variables and convert:

```
% Create descriptive variables
% Convert System.String to char
mytitle = char(mldata{1});
myxlabel = char(mldata{1});
% Convert System.Double to double
y = double(mldata{2});
```

Call MATLAB Functions with MATLAB Variables

Create a MATLAB graph with this data:

```
% Remove the previous figure
close
% Plot the data and label the graph
figure('Name',mytitle,'NumberTitle','off')
plot(y)
```



```
xlabel(myxlabel)
```

Pass Jagged Arrays

In this section...

“Create System.Double .NET Jagged Array” on page 10-40

“Call .NET Method with System.String Jagged Array Arguments” on page 10-40

“Call .NET Method with Multidimensional Jagged Array Arguments” on page 10-41

Create System.Double .NET Jagged Array

This example shows how to create a .NET jagged array of `System.Double` using the `NET.createArray` function.

Create a 3 element array.

```
jArr = NET.createArray('System.Double[]',3)
```

```
jArr =
```

```
Double[][] with properties:
```

```

    Length: 3
    LongLength: 3
    Rank: 1
    SyncRoot: [1x1 System.Double[][]]
    IsReadOnly: 0
    IsFixedSize: 1
    IsSynchronized: 0

```

You can pass `jArr` to any .NET method with an input or output argument of type `System.Double[][]`.

Call .NET Method with System.String Jagged Array Arguments

This example shows how to create an array of MATLAB strings to pass to a method, `MethodStringArr`, with a `System.String[][]` input argument.

The following is the MATLAB function signature for `MethodStringArr`.

Return Type	Name	Arguments
System.String[][] RetVal	MethodStringArr	(NetPackage.StringClass this,

Return Type	Name	Arguments
		System.String[][] arr)

The MATLAB strings you want to pass to the method are:

```
str1 = {'this', 'is'};
str2 = 'jagged';
```

Create a variable, `netArr`, of `System.String` arrays, which contains two arrays. Using the `NET.createArray`, the `typeName` for this array is `System.String[]`, and the dimension is 2.

```
netArr = NET.createArray('System.String[]',2);
```

The arrays contain empty strings.

Create `System.String` arrays to correspond to the MATLAB strings, `str1` and `str2`.

```
netArr(1) = NET.createArray('System.String',2);
netArr(2) = NET.createArray('System.String',1);
```

Assign `str1` and `str2` to `netArr`.

```
netArr(1) = str1;
netArr(2,1) = str2;
```

Because `str2` is a scalar and `netArr(2)` expects an array, you must assign `str2` to the specific element `netArr(2,1)`.

Now you can pass `netArr` to the `MethodStringArr` method.

```
class(netArr)
ans =
System.String[][]
```

Call .NET Method with Multidimensional Jagged Array Arguments

This example shows how to create a MATLAB array to pass to a method, `MethodMultiDArr`, with a multidimensional jagged array input argument of `System.Double` type.

The following is the MATLAB function signature for `MethodMultiDArr`. The input is a multidimensional jagged array that contains single dimensional elements.

Return Type	Name	Arguments
System.Double[][][,] RetVal	MethodMultiDArr	(NetPackage.NumericClass this, System.Double[][][,] arr)

Create a 2-by-3 array with typeName of System.Double[].

```
arr = NET.createArray('System.Double[]',2,3);
```

The elements are empty arrays.

The MATLAB arrays you want to pass to the method are:

```
A1 = [1 2 3];
A2 = [5 6 7 8];
```

MATLAB automatically converts a numeric array to the equivalent .NET type.

```
arr(1,1) = A1;
arr(1,2) = A2;
```

Array arr is a System.Double[][][,] jagged array.

```
arr
```

```
arr =
```

```
Double[][][, ] with properties:
```

```
    Length: 6
   LongLength: 6
      Rank: 2
   SyncRoot: [1x1 System.Double[][][,]]
   IsReadOnly: 0
  IsFixedSize: 1
 IsSynchronized: 0
```

Now you can pass arr to the MethodMultiDArr method.

Convert Nested System.Object Arrays

This example shows how to use the `cell` function to convert data in nested `System.Object` arrays.

The conversion is not recursive for a `System.Object` array contained within a `System.Object` array. Use the `cell` function to convert each `System.Object` array.

The C# example `NetDocCell.cs`, in the `matlabroot/extern/examples/NET/NetSample` folder, is used in the following example. To see the code, open the file in MATLAB Editor and build the `NetDocCell` assembly.

Set up the path to your assembly, then load the assembly.

```
dllPath = fullfile('c:', 'work', 'NetDocCell.dll');
NET.addAssembly(dllPath);
```

Create a cell array, `mldata`.

```
j = NetDocCell.MyGraph;
mldata = cell(graph.getNewData)

mldata =
    [1x1 System.String]    [1x1 System.Object[]]
```

To access the contents of the `System.Object` array, create another cell array `mldataPlotData`.

```
mldataPlotData = cell(mldata{2})

mldataPlotData =
    [1x1 System.String]    [1x1 System.Double[]]
```

Related Examples

- “Build a .NET Application for MATLAB Examples” on page 10-21
- “Pass Cell Arrays of .NET Data” on page 10-37

More About

- “Build a .NET Application for MATLAB Examples” on page 10-21

Passing Data to .NET Objects

When you make a call in MATLAB to a .NET method or function, MATLAB automatically converts arguments into .NET types. MATLAB performs this conversion on each passed argument, except for arguments that are already .NET objects.

The following topics provide information about passing specific data to .NET.

In this section...
“Pass Primitive .NET Types” on page 10-44
“Pass Cell Arrays” on page 10-45
“Pass Nonprimitive .NET Objects” on page 10-46
“Pass MATLAB Strings” on page 10-46
“Pass System.Nullable Type” on page 10-46
“Pass NULL Values” on page 10-47
“Unsupported MATLAB Types” on page 10-47
“Choosing Method Signatures” on page 10-47
“Example — Choosing a Method Signature” on page 10-48
“Pass Arrays” on page 10-49
“Pass MATLAB Arrays as Jagged Arrays” on page 10-50

Pass Primitive .NET Types

The following table shows the MATLAB base types for passed arguments and the corresponding .NET types defined for input arguments. Each row shows a MATLAB type followed by the possible .NET argument matches, from left to right in order of closeness of the match.

MATLAB Primitive Type Conversion Table

MATLAB Type	Closest Type <----- Other Matching .NET Types -----> Least Close Type Preface Each .NET Type with System.											
logical	Boolean	Byte	SByte	Int16	UInt16	Int32	UInt32	Int64	UInt64	Single	Double	Object
double	Double	Single	Decim	Int64	UInt64	Int32	UInt32	Int16	UInt16	SByte	Byte	Object
single	Single	Double	Decim	Object								

MATLAB Type	Closest Type <----- Other Matching .NET Types -----> Least Close Type										
	Preface Each .NET Type with System.										
int8	SByte	Int16	Int32	Int64	Single	Double	Object				
uint8	Byte	UInt16	UInt32	UInt64	Single	Double	Object				
int16	Int16	Int32	Int64	Single	Double	Object					
uint16	UInt16	UInt32	UInt64	Single	Double	Object					
int32	Int32	Int64	Single	Double	Object						
uint32	UInt32	UInt64	Single	Double	Object						
int64	Int64	Double	Object								
uint64	UInt64	Double	Object								
char	Char	String	Object								

The following primitive .NET argument types do not have direct MATLAB equivalent types. MATLAB passes these types as is:

- `System.IntPtr`
- `System.UIntPtr`
- `System.Decimal`
- enumerated types

Pass Cell Arrays

You can pass a cell array to a .NET property or method expecting an array of `System.Object` or `System.String` arguments, as shown in the following table.

MATLAB Cell Array Conversion Table

MATLAB Type	Closest Type <--- Other Matching .NET Types ---> Least Close Type	
Cell array of strings	<code>System.String[]</code>	<code>System.Object[]</code>
Cell array (not all strings)	<code>System.Object[]</code>	<code>System.Object</code>

Elements of a cell can be any of the following supported types:

- Any non-sparse, non-complex built-in numeric type shown in the MATLAB Primitive Type Conversion Table
- `char`
- `logical`
- cell array
- .NET object

Pass Nonprimitive .NET Objects

When calling a method that has an argument of a particular .NET class, you must pass an object that is an instance of that class or its derived classes. You can create such an object using the class constructor, or use an object returned by a member of the class. When a class member returns a .NET object, MATLAB leaves it as a .NET object so you can continue to use it to interact with other class members.

Pass MATLAB Strings

MATLAB automatically converts a string or `char` array to a .NET `System.String` object. To pass an array of strings, create a cell array.

Pass System.Nullable Type

You can pass any of the following to a .NET method with `System.Nullable<ValueType>` input arguments:

- Variable of the underlying `<ValueType>`
- `null` value, `[]`
- `System.Nullable<ValueType>` object

When you pass a MATLAB variable of type `ValueType`, MATLAB reads the signature and automatically converts your variable to a `System.Nullable<ValueType>` object. For a complete list of possible `ValueType` values accepted for `System.Nullable<ValueType>`, refer to the MATLAB Primitive Type Conversion Table.

For examples, see “Pass System.Nullable Arguments”.

Pass NULL Values

MATLAB uses empty double ([]) values for reference type arguments.

Unsupported MATLAB Types

You cannot pass the following MATLAB types to .NET methods:

- Structure arrays
- Sparse arrays
- Complex numbers

Choosing Method Signatures

MATLAB chooses the correct .NET method signature (including constructor, static and nonstatic methods) based on the following criteria.

When your MATLAB function calls a .NET method, MATLAB:

- 1 Checks to make sure that the object (or class, for a static method) has a method by that name.
- 2 Determines whether the invocation passes the same number of arguments of at least one method with that name.
- 3 Makes sure that each passed argument can be converted to the type defined for the method.

If all the preceding conditions are satisfied, MATLAB calls the method.

In a call to an overloaded method, if there is more than one candidate, MATLAB selects the one with arguments that best fit the calling arguments, based on the MATLAB Primitive Type Conversion Table. First, MATLAB rejects all methods that have any argument types that are incompatible with the passed arguments. Among the remaining methods, MATLAB selects the one with the highest fitness value, which is the sum of the fitness values of all its arguments. The fitness value for each argument is how close the MATLAB type is to the .NET type. If two methods have the same fitness, MATLAB chooses the first one defined in the class.

For class types, MATLAB chooses the method signature based on the distance of the incoming class type to the expected .NET class type. The closer the incoming type is to the expected type, the better the match.

The rules for overloaded methods with optional arguments are described in “Determining Which Overloaded Method Is Invoked”.

Example — Choosing a Method Signature

Open a `methodsviw` window for the `System.String` class and look at the entries for the `Concat` method:

```
import System.*
methodsviw('System.String')
```

The `Concat` method takes one or more arguments. If the arguments are of type `System.String`, the method concatenates the values. For example, create two strings:

```
str1 = String('hello');
str2 = String('world');
```

When you type:

```
String.Concat(str1,str2)
```

MATLAB verifies the method `Concat` exists and looks for a signature with two input arguments. The following table shows the two signatures.

Qualifiers	Return Type	Name	Arguments
Static	System.String RetVal	Concat	(System.Object arg0, System.Object arg1)
Static	System.String RetVal	Concat	(System.String str0, System.String str1)

Since `str1` and `str2` are of class `System.String`, MATLAB chooses the second signature and displays:

```
ans =
helloworld
```

If the arguments are of type `System.Object`, the method displays the string representations of the values. For example, create two `System.DateTime` objects:

```
dt = DateTime.Today;
myDate = System.DateTime(dt.Year,3,1,11,32,5);
```

When you type:

```
String.Concat(dt,myDate)
```

MATLAB chooses the following signature, since `System.DateTime` objects are derived from the `System.Object` class.

Qualifiers	Return Type	Name	Arguments
Static	System.String RetVal	Concat	(System.Object arg0, System.Object arg1)

This `Concat` method first applies the `ToString` method to the objects, then concatenates the strings. MATLAB displays information like:

```
ans =  
12/23/2008 12:00:00 AM3/1/2008 11:32:05 AM
```

Pass Arrays

For information about passing MATLAB arrays to .NET methods, see “Using Arrays with .NET Applications” on page 10-56 and “Pass MATLAB Arrays as Jagged Arrays” on page 10-50.

How Array Dimensions Affect Conversion

The dimension of a .NET array is the number of subscripts required to access an element of the array. To get the number of dimensions, use the `Rank` property of the .NET `System.Array` type. The dimensionality of a MATLAB array is the number of non-singleton dimensions in the array.

MATLAB matches the array dimensionality with the .NET method signature, as long as the dimensionality of the MATLAB array is lower than or equal to the expected dimensionality. For example, you can pass a scalar input to a method that expects a 2-D array.

For a MATLAB array with number of dimensions, `N`, if the .NET array has fewer than `N` dimensions, the MATLAB conversion drops singleton dimensions, starting with the first one, until the number of remaining dimensions matches the number of dimensions in the .NET array.

Converting a MATLAB Array to System.Object

You can pass a MATLAB array to a method that expects a `System.Object`.

Pass MATLAB Arrays as Jagged Arrays

A MATLAB array is a rectangular array. The .NET Framework supports a *jagged array*, which is an array of arrays. This means the elements of a jagged array can be of different dimensions and sizes.

Although .NET languages support jagged arrays, the term **jagged** is not a language keyword. C# function signatures use multiple pairs of square brackets (`[][]`) to represent a jagged array. In addition, a jagged array can be nested (`[][][]`), multidimensional (`[,]`), or nested with multidimensional elements (for example, `[, ,] [,][]`).

MATLAB automatically converts MATLAB arrays of numeric types to the corresponding jagged array type. If the input argument is a non-numeric type or multidimensional, use the `NET.createArray` function to create an array to pass as a jagged array. For examples using `NET.createArray`, see “Pass Jagged Arrays”.

Handling Data Returned from .NET Objects

In this section...

- “.NET Type to MATLAB Type Mapping” on page 10-51
- “How MATLAB Handles System.String” on page 10-52
- “How MATLAB Handles System.__ComObject” on page 10-53
- “How MATLAB Handles System.Nullable” on page 10-54
- “How MATLAB Handles dynamic Type” on page 10-55
- “How MATLAB Handles Jagged Arrays” on page 10-55

.NET Type to MATLAB Type Mapping

The following table shows how MATLAB converts data from a .NET object into MATLAB types. These are the values displayed in a method signature.

C# .NET Type	MATLAB Type
System.Int16	int16 scalar
System.UInt16	uint16 scalar
System.Int32	int32 scalar
System.UInt32	uint32 scalar
System.Int64	int64 scalar
System.UInt64	uint64 scalar
System.Single	single scalar
System.Double	double scalar
System.Boolean	logical scalar
System.Byte	uint8 scalar
System.Enum	enum
System.Char	char
System.Decimal	System.Decimal
System.Object	System.Object

C# .NET Type	MATLAB Type
System.IntPtr	System.IntPtr
System.UIntPtr	System.UIntPtr
System.String	System.String
System.Nullable<ValueType>	System.Nullable<ValueType>
System.Array	See “Using Arrays with .NET Applications” on page 10-56
System.__ComObject	See “How MATLAB Handles System.__ComObject” on page 10-53
<i>class name</i>	<i>class name</i>
<i>struct name</i>	<i>struct name</i>

How MATLAB Handles System.String

Use the `char` function to convert a `System.String` object to a MATLAB string. For example, type:

```
str = System.String('create a System.String');
strml = char(str);
whos
```

```

Name          Size          Bytes  Class

str           1x1             60  System.String
strml        1x22            44   char
```

MATLAB displays the string value of `System.String` objects, instead of the standard object display. For example, type:

```
a = System.String('test')
b = String.Concat(a, ' hello', ' world')

a =
test
b =
test hello world
```

The `System.String` class illustrates how MATLAB handles fields and properties, as described in “Call .NET Properties That Take an Argument”. To see reference

information about the class, search for the term `System.String` in the .NET Framework Class Library, as described in “To Learn More About the .NET Framework” on page 10-18.

How MATLAB Handles `System.__ComObject`

The `System.__ComObject` type represents a Microsoft COM object. It is a non-visible, public class in the `mscorlib` assembly with no public methods. Under certain circumstances, a .NET object returns an instance of `System.__ComObject`. MATLAB handles the `System.__ComObject` based on the return types defined in the metadata.

MATLAB Converts Object

If the return type of a method or property is strongly typed, and the result of the invocation is `System.__ComObject`, MATLAB automatically converts the returned object to the appropriate type.

For example, suppose your assembly defines a type, `TestType`, and provides a method, `GetTestType`, with the following signature.

Return Type	Name	Arguments
<code>NetDocTest.TestType</code> <code>RetVal</code>	<code>GetTestType</code>	<code>(NetDocTest.MyClass this)</code>

The return type of `GetTestType` is strongly typed and the .NET Framework returns an object of type `System.__ComObject`. MATLAB automatically converts the object to the appropriate type, `NetDocTest.TestType`, shown in the following **pseudo-code**:

```
cls = NetDocTest.MyClass;
var = GetTestType(cls)

var =

    TestType handle with no properties.
```

Casting Object to Appropriate Type

If the return type of a method or property is `System.Object`, and the result of the invocation is `System.__ComObject`, MATLAB returns `System.__ComObject`. To use

the returned object, you must cast it to a valid class or interface type. Use your product documentation to identify the valid types for this object.

To call a member of the new type, cast the object using the MATLAB conversion syntax:

```
objConverted = namespace.className(obj)
```

where `obj` is a `System.__ComObject` type.

For example, an item in a Microsoft Excel sheet collection can be a chart or a worksheet. The following command converts the `System.__ComObject` variable `mySheet` to a `Chart` or a `Worksheet` object `newSheet`:

```
newSheet = Microsoft.Office.Interop.Excel.interfacename(mySheet);
```

where `interfacename` is `Chart` or `Worksheet`. For an example, see “Work with Microsoft Excel Spreadsheets Using .NET”.

Pass a COM Object Between Processes

If you pass a COM object to or from a function, you must lock the object so that MATLAB does not automatically release it when the object goes out of scope. To lock the object, call the `NET.disableAutoRelease` function. You must then unlock the object, using the `NET.enableAutoRelease` function, after you are through using it.

How MATLAB Handles System.Nullable

If .NET returns a `System.Nullable` type, MATLAB returns the corresponding `System.Nullable` type.

A `System.Nullable` type lets you assign null values to types, such as numeric types, that do not support null value. To use a `System.Nullable` object in MATLAB, you first need to decide how to handle null values.

- If you want to process null values differently from `<ValueType>` values, use the `HasValue` property.
- If you want every value to be of the underlying `<ValueType>`, use the `GetValueOrDefault` method. This method assigns a default value of type `<ValueType>` to null values.

Use a variable of the object's underlying type where appropriate in any MATLAB expression. For examples, see “Pass System.Nullable Arguments”.

How MATLAB Handles dynamic Type

MATLAB handles dynamic types as `System.Object`. For example, the following C# method `exampleMethod` has a dynamic input argument `d` and returns a dynamic output value:

```
public dynamic exampleMethod(dynamic d)
```

The following table shows the corresponding MATLAB function signature.

Return Type	Name	Arguments
<code>System.Object</code> <code>RetVal</code>	<code>exampleMethod</code>	<code>(namespace.classname this, System.Object d)</code>

How MATLAB Handles Jagged Arrays

You must convert a .NET jagged array before using it in a MATLAB command. To convert:

- If the shape of the array is rectangular, use the corresponding MATLAB numeric function.
- If the array is not rectangular, use the `cell` function.

If the jagged array is multidimensional, you must individually convert the arrays in each dimension.

Using Arrays with .NET Applications

In this section...

“Passing MATLAB Arrays to .NET” on page 10-56

“Accessing .NET Array Elements in MATLAB” on page 10-56

“Converting .NET Arrays to Cell Arrays” on page 10-57

“Converting .NET Jagged Arrays to MATLAB Arrays” on page 10-59

“Limitations to Support of .NET Arrays” on page 10-59

Passing MATLAB Arrays to .NET

MATLAB automatically converts arrays to .NET types, as described in the MATLAB Primitive Type Conversion Table. To pass an array of strings, create a cell array. For all other types, use the MATLAB `NET.createArray` function.

MATLAB creates a .NET array, copies the elements from the MATLAB array to the .NET array, and passes it to C#.

Accessing .NET Array Elements in MATLAB

You access elements of a .NET array with subscripts, just like with MATLAB arrays.

You cannot refer to the elements of a multidimensional .NET array with a single subscript (linear indexing) like you can in MATLAB, as described in “Matrix Indexing”. You must specify the index for each dimension of the .NET array.

You can only use scalar indexing to access elements of a .NET array. The colon operator, described in “Generating a Numeric Sequence”, is not supported.

Using the Get and Set Instance Functions

Alternatively, you can access elements of a .NET array using the `Set` and `Get` instance functions. When using `Set` or `Get` you must use C# array indexing, which is zero-based.

For example, create two `System.String` arrays, using the `Set` function and direct assignment:

```
d1 = NET.createArray('System.String',3);
```

```
d1.Set(0, 'one');
d1.Set(1, 'two');
d1.Set(2, 'three');

d2 = NET.createArray('System.String',3);
d2(1) = 'one';
d2(2) = 'two';
d2(3) = 'zero';
```

To compare the values of the first elements in each array, type:

```
System.String.Compare(d1(1),d2.Get(0))
```

MATLAB displays 0, meaning the strings are equal.

Converting .NET Arrays to Cell Arrays

You can convert .NET `System.String` and `System.Object` arrays to MATLAB cell arrays using the `cell` function. Elements of the cell array are of the MATLAB type closest to the .NET type, described in “.NET Type to MATLAB Type Mapping” on page 10-51.

For example, create a cell array of names of the folders in your `C:\` folder, using the .NET Framework `System.IO.Directory` class:

```
myList = cell(System.IO.Directory.GetDirectories('C:\'));
```

Converting Nested System.Object Arrays

The conversion is not recursive for a `System.Object` array contained within a `System.Object` array. You must use the `cell` function to convert each `System.Object` array.

To run this example, build the `NetDocCell` assembly using the directions in “Build a .NET Application for MATLAB Examples” on page 10-21. The source code is here:

C# NetDocCell Source File

```
using System;
/*
 * C# Assembly used in MATLAB .NET documentaion.
 * Method getNewData is used to demonstrate
 * how MATLAB handles a System.Object
```

```
* that includes another System.Object.
*/
namespace NetDocCell
{
    public class MyGraph
    {
        public Object[] getNewData()
        /*
         * Create a System.Object array to use in MATLAB examples.
         * Returns containerArr System.Object array containing:
         * fLabel System.String object
         * plotData System.Object array containing:
         *     xLabel System.String object
         *     doubleArr System.Double array
         */
        {
            String fLabel = "Figure Showing New Graph Data";
            Double[] doubleArr = {
18, 32, 3.133, 44, -9.9, -13, 33.03 };
            String xLabel = "X-Axis Label";
            Object[] plotData = { xLabel, doubleArr };
            Object[] containerArr = { fLabel, plotData };
            return containerArr;
        }
    }
}
```

Load the assembly and create a cell array, `mldata`:

```
dllPath = fullfile('c:', 'work', 'NetDocCell.dll');
NET.addAssembly(dllPath);
obj = NetDocCell.MyGraph;
mldata = cell(obj.getNewData)
```

The cell array contains elements of the following type:

```
mldata =
    [1x1 System.String]    [1x1 System.Object[]]
```

To access the contents of the `System.Object` array, create another cell array `mldataPlotData`:

```
mldataPlotData = cell(mldata{2})
```

This cell array contains elements of the following type:

```
m1PlotData =  
    [1x1 System.String]    [1x1 System.Double[]]
```

For another example, see “Pass Cell Arrays of .NET Data” on page 10-37.

Converting .NET Jagged Arrays to MATLAB Arrays

You must convert a .NET jagged array before using it in a MATLAB command.

- If the shape of the array is rectangular, use the corresponding MATLAB numeric function.
- If the array is not rectangular, use the `cell` function.

If the jagged array is multidimensional, you must individually convert the arrays in each dimension.

Limitations to Support of .NET Arrays

MATLAB does not support:

- Arrays which specify a lower bound
- Concatenating .NET objects into an array
- The `end` function as the last index in a .NET array
- Array indices of complex values
- Autoconversion of `char` or `cell` arrays to jagged array arguments.
- Autoconversion of MATLAB arrays to multidimensional jagged array arguments.

Set Static .NET Properties

In this section...

“System.Environment.CurrentDirectory Example” on page 10-60

“Do Not Use ClassName.PropertyName Syntax for Static Properties” on page 10-60

System.Environment.CurrentDirectory Example

This example shows how to set a static property using the `NET.setStaticProperty` function.

The `CurrentDirectory` property in the `System.Environment` class is a static, read/write property. The following code creates a folder, `temp`, in the current folder and changes the `CurrentDirectory` property to the new folder.

Set your current folder to a specific path, for example:

```
cd('C:\Work')
```

Set the `CurrentDirectory` property:

```
saveDir = System.Environment.CurrentDirectory;  
newDir = [char(saveDir) '\temp'];  
mkdir(newDir)  
NET.setStaticProperty('System.Environment.CurrentDirectory',newDir)  
System.Environment.CurrentDirectory
```

```
ans =  
C:\Work\temp
```

To restore the original `CurrentDirectory` value, type:

```
NET.setStaticProperty('System.Environment.CurrentDirectory',saveDir)
```

Do Not Use ClassName.PropertyName Syntax for Static Properties

This example shows how to mistakenly create a `struct` array instead of setting a class property.

If you use the `ClassName.PropertyName` syntax to set a static property, MATLAB creates a `struct` array.

The following code creates a structure named `System`:

```
saveDir = System.Environment.CurrentDirectory;
newDir = [char(saveDir) '\temp'];
System.Environment.CurrentDirectory = newDir;
whos
```

Name	Size	Bytes	Class
System	1x1	376	struct
newDir	1x12	24	char
saveDir	1x1	112	System.String

Try to use a member of the `System` namespace.

```
oldDate = System.DateTime(1992,3,1);
```

Reference to non-existent field 'DateTime'.

To restore your environment, type:

```
clear System
NET.setStaticProperty('System.Environment.CurrentDirectory',saveDir)
```

Using .NET Properties

In this section...

“How MATLAB Represents .NET Properties” on page 10-62

“How MATLAB Maps C# Property and Field Access Modifiers” on page 10-62

How MATLAB Represents .NET Properties

To view property names, use the `properties` function.

To get and set the value of a class property, use the MATLAB dot notation:

```
x = ClassName.PropertyName;  
ClassName.PropertyName = y;
```

The following example gets the value of a property (the current day of the month):

```
dtnow = System.DateTime.Now;  
d = dtnow.Day;
```

The following example sets the value of a property (the `Volume` for a `SpeechSynthesizer` object):

```
NET.addAssembly('System.Speech');  
ss = System.Speech.Synthesis.SpeechSynthesizer;  
ss.Volume = 50;  
Speak(ss, 'You can use .NET Libraries in MATLAB')
```

To set a static property, call the `NET.setStaticProperty` function. For an example, see “Set Static .NET Properties” on page 10-60.

MATLAB represents public .NET fields as properties.

MATLAB represents .NET properties that take an argument as methods. For more information, see “Call .NET Properties That Take an Argument”.

How MATLAB Maps C# Property and Field Access Modifiers

MATLAB maps C# keywords to MATLAB property attributes, as shown in the following table.

C# Property Keyword	MATLAB Attribute
public, static	Access = public
protected, private, internal	Not visible to MATLAB
get, set	Access = public
Get	GetAccess = public, SetAccess = private
Set	SetAccess = public, GetAccess = private

MATLAB maps C# keywords to MATLAB field attributes, as shown in the following table.

C# Field Keyword	MATLAB Mapping
public	Supported
protected, private, internal, protected internal	Not visible to MATLAB

For more information about MATLAB properties, see “Property Attributes”.

MATLAB Does Not Display Protected Properties

The `System.Windows.Media.ContainerVisual` class, available in .NET Framework Version 3.0 and above, has several protected properties. MATLAB only displays public properties and fields. Type:

```
NET.addAssembly('PresentationCore');  
properties('System.Windows.Media.ContainerVisual')
```

Display Public Properties

Properties for class `System.Windows.Media.ContainerVisual`:

```
Children  
Parent  
Clip  
Opacity  
OpacityMask  
CacheMode  
BitmapEffect  
BitmapEffectInput  
Effect  
XSnappingGuidelines  
YSnappingGuidelines  
ContentBounds  
Transform  
Offset  
DescendantBounds  
DependencyObjectType  
IsSealed  
Dispatcher
```

To see how MATLAB handles property and field C# keywords, see “How MATLAB Maps C# Property and Field Access Modifiers” on page 10-62.

Work with .NET Methods Having Multiple Signatures

To create the `NetSample` assembly, see “Build a .NET Application for MATLAB Examples” on page 10-21.

The `SampleMethodSignature` class defines the three constructors shown in the following table.

Return Type	Name	Arguments
<code>netdoc.SampleMethodSignature obj</code>	<code>SampleMethodSignature</code>	
<code>netdoc.SampleMethodSignature obj</code>	<code>SampleMethodSignature</code>	<code>(double scalar d)</code>
<code>netdoc.SampleMethodSignature obj</code>	<code>SampleMethodSignature</code>	<code>(System.String s)</code>

SampleMethodSignature Class

```
using System;
namespace netdoc
{
    public class SampleMethodSignature
    {
        public SampleMethodSignature ()
        {}

        public SampleMethodSignature (double d)
        { myDoubleField = d; }

        public SampleMethodSignature (string s)
        { myStringField = s; }

        public int myMethod(string strIn, ref double dbRef,
out double dbOut)
        {
            dbRef += dbRef;
            dbOut = 65;
            return 42;
        }

        private Double myDoubleField = 5.5;
    }
}
```

```
        private String myStringField = "hello";  
    }  
}
```

Display Function Signature Example

If you have not already loaded the `NetSample` assembly, type:

```
NET.addAssembly('c:\work\NetSample.dll')
```

Create a `SampleMethodSignature` object `obj`:

```
obj = netdoc.SampleMethodSignature;
```

To see the method signatures, type:

```
methods(obj, '-full')
```

Look for the following signatures in the MATLAB output:

```
netdoc.SampleMethodSignature obj SampleMethodSignature  
netdoc.SampleMethodSignature obj SampleMethodSignature(double scalar d)  
netdoc.SampleMethodSignature obj SampleMethodSignature(System.String s)
```

For more information about argument types, see “Handling Data Returned from .NET Objects” on page 10-51.

SampleMethods Class

To create the `NetSample` assembly, see “Build a .NET Application for MATLAB Examples” on page 10-21.

The `SampleMethods` class defines the following methods:

- `refTest`
- `outTest`
- `paramsTest`

SampleMethods Class

```
using System;
namespace netdoc
{
    public class SampleMethods
    {
        //test ref keyword
        public void refTest(ref double db1)
        {
            db1 = db1 * 2;
        }

        //test out keyword
        public void outTest(double db1, out double db2)
        {
            db1 = db1 * 2.35;
            db2 = db1;
        }

        //test params keyword
        public int paramsTest(params int[] num)
        {
            int total = 0;
            foreach (int i in num)
            {
                total = total + i;
            }
            return total;
        }
    }
}
```

Load the `NetSample` assembly:

```
NET.addAssembly('c:\work\NetSample.dll')
```

Call .NET Methods With out Keyword

This example shows how to call methods using an `out` keyword.

Use the `outTest` method in the `SampleMethods` class, which has the following function signature.

Return Type	Name	Arguments
double scalar db2	outTest	(netdoc.SampleMethods this, double scalar db1)

Type:

```
cls = netdoc.SampleMethods;  
db3 = outTest(cls,6)
```

```
db3 =  
    14.1000
```

Related Examples

- “SampleMethods Class” on page 10-67

Call .NET Methods With ref Keyword

This example shows how to call methods using a `ref` keyword.

Use the `refTest` method in the `SampleMethods` class, which has the following function signature.

Return Type	Name	Arguments
double scalar db1	refTest	(netdoc.SampleMethods this, double scalar db1)

Type:

```
cls = netdoc.SampleMethods;  
db4 = refTest(cls,6)
```

```
db4 =  
    12
```

Related Examples

- “SampleMethods Class” on page 10-67

Call .NET Methods With params Keyword

This example shows how to call methods using a `params` keyword.

Use the `paramsTest` method in the `SampleMethods` class, which has the following function signature.

Return Type	Name	Arguments
int32 scalar RetVal	paramsTest	(netdoc.SampleMethods this, System.Int32[] num)

Type:

```
cls = netdoc.SampleMethods;  
mat = [1, 2, 3, 4, 5, 6];  
db5 = paramsTest(cls,mat)
```

```
db5 =  
    21
```

Related Examples

- “SampleMethods Class” on page 10-67

Call .NET Methods with Optional Arguments

In this section...

“Setting Up the Examples” on page 10-72

“Skip Optional Arguments” on page 10-72

“Call Overloaded Methods” on page 10-73

Setting Up the Examples

To use the examples in this topic, build the `NetDocOptional` assembly. This C# example, `NetDocOptional.cs` in the `matlabroot/extern/examples/NET/NetSample` folder, defines the methods used in these examples. To see the code, open the file in MATLAB Editor. To build the `NetDocOptional` assembly, see “Build a .NET Application for MATLAB Examples” on page 10-21. The examples assume you put the assembly in your `c:\work` folder. You can modify the examples to change the path to the assembly.

Skip Optional Arguments

This example shows how to use default values in optional arguments using the `Greeting` method.

Greeting Function Signature

Arguments `str1` and `str2` are optional.

Return Type	Name	Arguments
<code>System.String RetVal</code>	<code>Greeting</code>	<code>(NetDocOptional.MyClass this, int32 scalar x, optional<System.String> str1, optional<System.String> str2)</code>

Load the `NetDocOptional` assembly, if it is not already loaded.

```
dllPath = fullfile('c:', 'work', 'NetDocOptional.dll');
asm = NET.addAssembly(dllPath);
cls = NetDocOptional.MyClass;
```

Display the default values.

```
Greeting(cls,0)
```

```
ans =  
hello world
```

Use the default value for `str1`.

```
def = System.Reflection.Missing.Value;  
Greeting(cls,0,def,'Mr. Jones')
```

```
ans =  
hello Mr. Jones
```

Use the default value for `str2`. You can omit the argument at the end of a parameter list.

```
Greeting(cls,0,'My')
```

```
ans =  
My world
```

Call Overloaded Methods

This example shows how to use optional arguments with an overloaded method, `calc`.

calc Function Signatures

The following table shows the signatures for `calc`, which adds the input arguments. The difference is the type of optional argument, `y`.

Return Type	Name	Arguments
single scalarRetVal	calc	(NetDocOptional.MyClass this, optional<int32 scalar> x, optional<single scalar> y)
double scalarRetVal	calc	(NetDocOptional.MyClass this, optional<int32 scalar> x, optional<double scalar> y)

Load the `NetDocOptional` assembly, if it is not already loaded.

```
dllPath = fullfile('c:', 'work', 'NetDocOptional.dll');
```

```
asm = NET.addAssembly(dllPath);  
cls = NetDocOptional.MyClass;
```

Call `calc` with explicit arguments.

```
calc(cls,3,4)
```

```
ans =  
    7
```

If you try to use the default values by omitting the parameters, MATLAB cannot determine which signature to use.

```
calc(cls)
```

Cannot choose between the following .NET method signatures due to unspecified optional arguments in the call to 'calc':

```
'NetDocOptional.MyClass.calc(NetDocOptional.MyClass this,  
optional<int32 scalar> x, optional<single scalar> y)' and  
'NetDocOptional.MyClass.calc(NetDocOptional.MyClass this,  
optional<int32 scalar> x, optional<double scalar> y)'
```

You can resolve this ambiguity by specifying enough additional optional arguments so that there is only one possible matching .NET method.

To use the default values, you must provide both arguments.

```
def = System.Reflection.Missing.Value;  
calc(cls,def,def)  
calc(cls,3,def)  
calc(cls,def,4)
```

```
ans =  
    44  
ans =  
    14  
ans =  
    37
```

Calling .NET Methods

In this section...

“Calling Object Methods” on page 10-75
 “Getting Method Information” on page 10-75
 “C# Method Access Modifiers” on page 10-75
 “VB.NET Method Access Modifiers” on page 10-76
 “Reading Method Signatures” on page 10-76

Calling Object Methods

This topic describes information specific to .NET methods. For general information about calling methods on objects in MATLAB, see “Calling Object Methods”.

Getting Method Information

Use the following MATLAB functions to view the methods of a class. You can use these functions without creating an instance of the class. These functions do not list generic methods; use your product documentation to get information on generic methods.

- `methods` — View method names
- `methods` with `'-full'` option — View method names with argument list
- `methodsview` — Graphical representation of method list

You might find the `methodsview` window easier to use as a reference guide because you do not need to scroll through the Command Window to find information. For example, open a `methodsview` window for the `System.String` class:

```
methodsview('System.String')
```

C# Method Access Modifiers

MATLAB maps C# keywords to MATLAB method access attributes, as shown in the following table.

C# Method Keyword	MATLAB Attribute
<code>ref</code>	RHS, LHS

C# Method Keyword	MATLAB Attribute
out	LHS
params	Array of particular type
protected, private, internal, protected internal	Not visible to MATLAB

VB.NET Method Access Modifiers

MATLAB maps VB.NET keywords to MATLAB method access attributes, as shown in the following table.

VB.NET Method Keyword	MATLAB Attribute
ByRef	LHS, RHS
ByVal	RHS
Optional	Mandatory

Reading Method Signatures

MATLAB uses the following rules to populate method signatures.

- `obj` is the output from the constructor.
- `this` is the object argument.
- `RetVal` is the return type of a method.
- All other arguments use the .NET metadata.

MATLAB uses the following rules to select a method signature.

- Number of inputs
- Input type
- Number of outputs

Calling .NET Generic Methods

To call a generic method, use the `NET.invokeGenericMethod` function.

Calling .NET Methods with Optional Arguments

MATLAB displays optional arguments in a method signature using the `optional<T>` syntax, where T is the specific type. This feature is available in .NET Framework Version 4.0 and above.

To use a default method argument, pass an instance of `System.Reflection.Missing.Value`.

Skipping Optional Arguments

If the method is not overloaded, you are not required to fill in all optional values at the end of a parameter list. For examples, see “Skip Optional Arguments” on page 10-72.

Determining Which Overloaded Method Is Invoked

If a .NET class has overloaded methods with optional arguments, MATLAB picks the method matching the exact number of input arguments.

If the optional arguments of the methods are different by type, number, or dimension, MATLAB first compares the types of the mandatory arguments. If the types of the mandatory arguments are different, MATLAB chooses the first overloaded method defined in the class. If the types of the mandatory arguments are the same, specify enough optional arguments so that there is only one possible matching .NET method. Otherwise, MATLAB throws an error. For examples, see “Call Overloaded Methods” on page 10-73.

Support for ByRef Attribute in VB.NET

The rules for optional `ByRef` arguments are the same as for other method arguments, as described in “VB.NET Method Access Modifiers” on page 10-76. `ByRef` arguments on the RHS appear as optional and behave like any other optional argument.

Calling .NET Extension Methods

Unlike C# applications, MATLAB handles an extension method as a static method of the class that defines the method. Refer to your product documentation for the namespace and class name you need to call such methods.

For information about extension methods, see the MSDN article at [http://msdn.microsoft.com/en-us/library/bb383977\(v=VS.90\).aspx](http://msdn.microsoft.com/en-us/library/bb383977(v=VS.90).aspx).

Call .NET Properties That Take an Argument

MATLAB represents a property that takes an argument as a method. For example, the `System.String` class has two properties, `Chars` and `Length`. The `Chars` property gets the character at a specified character position in the `System.String` object. For example:

```
str = System.String('my new string');  
methods(str)
```

Display of System.String Methods

Methods for class `System.String`:

<code>Chars</code>	<code>Normalize</code>	<code>TrimStart</code>
<code>Clone</code>	<code>PadLeft</code>	<code>addlistener</code>
<code>CompareTo</code>	<code>PadRight</code>	<code>char</code>
<code>Contains</code>	<code>Remove</code>	<code>delete</code>
<code>CopyTo</code>	<code>Replace</code>	<code>eq</code>
<code>EndsWith</code>	<code>Split</code>	<code>findobj</code>
<code>Equals</code>	<code>StartsWith</code>	<code>findprop</code>
<code>GetEnumerator</code>	<code>String</code>	<code>ge</code>
<code>GetHashCode</code>	<code>Substring</code>	<code>gt</code>
<code>GetType</code>	<code>ToCharArray</code>	<code>isvalid</code>
<code>GetTypeCode</code>	<code>ToLower</code>	<code>le</code>
<code>IndexOf</code>	<code>ToLowerInvariant</code>	<code>lt</code>
<code>IndexOfAny</code>	<code>ToString</code>	<code>ne</code>
<code>Insert</code>	<code>ToUpper</code>	<code>notify</code>
<code>IsNormalized</code>	<code>ToUpperInvariant</code>	
<code>LastIndexOf</code>	<code>Trim</code>	
<code>LastIndexOfAny</code>	<code>TrimEnd</code>	

Static methods:

<code>Compare</code>	<code>Intern</code>	<code>op_Equality</code>
<code>CompareOrdinal</code>	<code>IsInterned</code>	<code>op_Inequality</code>
<code>Concat</code>	<code>IsNullOrEmpty</code>	
<code>Copy</code>	<code>IsNullOrWhiteSpace</code>	
<code>Format</code>	<code>Join</code>	

Notice that MATLAB displays the `Chars` property as a method.

The `Chars` method has the following signature.

Return Type	Name	Arguments
char scalarRetVal	Chars	(System.String this, int32 scalar index)

To see the first character, type:

```
Chars(str,0)
```

```
ans =  
m
```

How MATLAB Represents .NET Operators

MATLAB supports overloaded operators, such as the C# operator symbols + and *, as shown in the following table. MATLAB implements all other overloaded operators, such as % and +=, by their static method names, `op_Modulus` and `op_AdditionAssignment`. For a complete list of operator symbols and the corresponding operator names, see [http://msdn.microsoft.com/en-us/library/2sk3x8a7\(VS.71\).aspx](http://msdn.microsoft.com/en-us/library/2sk3x8a7(VS.71).aspx) on the Microsoft Developer Network website.

C++ operator symbol	.NET operator	MATLAB methods
+ (binary)	<code>op_Addition</code>	<code>plus</code> , +
- (binary)	<code>op_Subtraction</code>	<code>minus</code> , -
* (binary)	<code>op_Multiply</code>	<code>mtimes</code> , *
/	<code>op_Division</code>	<code>mrdivide</code> , /
&&	<code>op_LogicalAnd</code>	<code>and</code> , &
	<code>op_LogicalOr</code>	<code>or</code> ,
==	<code>op_Equality</code>	<code>eq</code> , ==
>	<code>op_GreaterThan</code>	<code>gt</code> , >
<	<code>op_LessThan</code>	<code>lt</code> , <
!=	<code>op_Inequality</code>	<code>ne</code> , ~=
>=	<code>op_GreaterThanOrEqual</code>	<code>ge</code> , >=
<=	<code>op_LessThanOrEqual</code>	<code>le</code> , <=
- (unary)	<code>op_UnaryNegation</code>	<code>uminus</code> , -a
+ (unary)	<code>op_UnaryPlus</code>	<code>uplus</code> , +a

Limitations to Support of .NET Methods

The `methods` and `methodsview` functions do not list generic methods.

Overloading MATLAB Functions

If your application implements a method with the same name as a MATLAB function, the method must have the same signature as the MATLAB function. Otherwise, MATLAB throws an error. For information about how MATLAB handles overloaded functions, see the following topics:

- “Overload Functions for Your Class”
- “Methods That Modify Default Behavior”

Use .NET Events in MATLAB

These examples use the `addlistener` function to handle .NET events with MATLAB callbacks.

In this section...

“Monitor Changes to .TXT File” on page 10-84

“Monitor Changes to Windows Form ComboBox” on page 10-84

Monitor Changes to .TXT File

This example uses the `System.IO.FileSystemWatcher` class in the `System` assembly to monitor changes to a .TXT file in the `C:\work\temp` folder. Create the following event handler, `eventhandlerChanged.m`:

```
function eventhandlerChanged(source,arg)
disp('TXT file changed')
end
```

Create a `FileSystemWatcher` object `fileObj` and watch the `Changed` event for files with a `.txt` extension in the folder `C:\work\temp`.

```
file = System.IO.FileSystemWatcher('c:\work\temp');
file.Filter = '*.txt';
file.EnableRaisingEvents = true;
addlistener(file, 'Changed', @eventhandlerChanged);
```

If you modify and save a `.txt` file in the `C:\work\temp` folder, MATLAB displays:

```
TXT file changed
```

The `FileSystemWatcher` documentation says that a simple file operation can raise multiple events.

To turn off the event handler, type:

```
file.EnableRaisingEvents = false;
```

Monitor Changes to Windows Form ComboBox

This example shows how to listen for changes to values in a `ComboBox` on a Windows Form. This example uses the `SelectedValueChanged` event defined by the `System.Windows.Forms.ComboBox` class.

Create a 64-bit Windows Forms Application, `myForm`, in your `C:\work` folder. Add a `ComboBox` control to `Form1`, and then add one or more items to `ComboBox1`. Build the application.

Create the following MATLAB class, `EnterComboData`, which uses the `attachListener` method to add a listener to the `form` property.

```
classdef EnterComboData < handle
properties
    form
end
methods
    function x = EnterComboData
        NET.addAssembly('C:\work\myForm\myForm\bin\x64\Debug\myForm.exe');
        x.form = myForm.Form1;
        Show(x.form)
        Activate(x.form)
    end
    function r = attachListener(x)
        % create listener
        r = addlistener(
            x.form.Controls.Item(0),
            'SelectedValueChanged',
            @x.anyChange);
    end
    function anyChange(~,~,~)
        % listener action if comboBox changes
        disp('Field updated')
    end
end
end
```

To execute the following MATLAB commands, you must create and load the application named `myForm.exe`. Use the `EnterComboData` class to create a form and call its `attachListener` method:

```
form = EnterComboData;
form.attachListener;
```

To trigger an event, select an item from the drop-down menu on the `ComboBox`. MATLAB displays:

```
Field updated
```

Call .NET Delegates in MATLAB

This example shows you how to use a delegate in MATLAB. It creates a delegate using a MATLAB function (`char`). For another example, see “Create Delegates from .NET Object Methods” on page 10-88.

This example consists of the following tasks:

In this section...

“Declare a Delegate in a C# Assembly” on page 10-86

“Load the Assembly Containing the Delegate into MATLAB” on page 10-86

“Select a MATLAB Function” on page 10-86

“Create an Instance of the Delegate in MATLAB” on page 10-87

“Invoke the Delegate Instance in MATLAB” on page 10-87

Declare a Delegate in a C# Assembly

The C# example `NetDocDelegate.cs`, in the `matlabroot/extern/examples/NET/NetSample` folder, defines delegates used in the following examples. To see the code, open the file in MATLAB Editor. To run the examples, build the `NetDocDelegate` assembly as described in “Build a .NET Application for MATLAB Examples” on page 10-21.

Load the Assembly Containing the Delegate into MATLAB

If the `NetDocDelegate` assembly is in your `c:\work` folder, load the file with the command:

```
dllPath = fullfile('c:', 'work', 'NetDocDelegate.dll');  
NET.addAssembly(dllPath);
```

Select a MATLAB Function

The `delInteger` delegate encapsulates any method that takes an integer input and returns a string. The MATLAB `char` function, which converts a nonnegative integer into a character array (string), has a signature that matches the `delInteger` delegate. For example, the following command displays the `!` character:


```
char(33)
```

Create an Instance of the Delegate in MATLAB

To create an instance of the `delInteger` delegate, pass the function handle of the `char` function:

```
myFunction = NetDocDelegate.delInteger(@char);
```

Invoke the Delegate Instance in MATLAB

Use `myFunction` the same as you would `char`. For example, the following command displays the `!` character:

```
myFunction(33)
```

Create Delegates from .NET Object Methods

The following C# class defines the methods `AddEggs` and `AddFlour`, which have signatures matching the `delInteger` delegate:

C# Recipe Source File

```
using System;
namespace Recipe
{
    public class MyClass
    {
        public string AddEggs(double n)
        {
            return "Add " + n + " eggs";
        }

        public string AddFlour(double n)
        {
            return "Add " + n + " cups flour";
        }
    }
}
```

Build the `Recipe` assembly, and then load it and create a delegate `myFunc` using `AddEggs` as the callback:

```
NET.addAssembly(dllPath);
NET.addAssembly('c:\work\Recipe.dll');
myRec = Recipe.MyClass;
myFunc = NetDocDelegate.delInteger(@myRec.AddEggs);
myFunc(2)

ans =
Add 2 eggs
```

Create Delegate Instances Bound to .NET Methods

For a C# delegate defined as:

```
namespace MyNamespace
{
    public delegate void MyDelegate();
}
```

MATLAB creates the following constructor signature.

Return Type	Name	Arguments
MyNamespace.MyDelegate obj	MyDelegate	(target, string methodName)

The argument `target` is one of the following:

- An instance of the invocation target object when binding to the instance method
- A string with fully qualified .NET class name when binding to a static method

`methodName` is a string specifying the callback method name.

Example — Create a Delegate Instance Associated with a .NET Object Instance Method

For the following C# delegate and class definition:

```
namespace MyNamespace
{
    public delegate void MyDelegate();

    public class MyClass
    {
        public void MyMethod(){}
    }
}
```

To instantiate the delegate in MATLAB, type:

```
target = MyNamespace.MyClass();
delegate = MyNamespace.MyDelegate(target, 'MyMethod');
```

Example — Create a Delegate Instance Associated with a Static .NET Method

For the following C# delegate and class definition:

```
namespace MyNamespace
{
    public delegate void MyDelegate();

    public class MyClass
    {
        public static void MyStaticMethod(){}
    }
}
```

To instantiate the delegate in MATLAB, type:

```
delegate = MyNamespace.MyDelegate('MyNamespace.MyClass', 'MyStaticMethod');
```

Call Delegates With out and ref Type Arguments

The MATLAB rules for mapping `out` and `ref` types for delegates are the same as for methods. See “C# Method Access Modifiers” on page 10-75.

For example, the following C# statement declares a delegate with a `ref` argument:

```
public delegate void delref(ref Double refArg);
```

The signature for an equivalent MATLAB delegate function maps `refArg` as both RHS and LHS arguments:

```
function refArg = myFunc(refArg)
```

The following C# statement declares a delegate with an `out` argument:

```
public delegate void delout(  
    Single argIn,  
    out Single argOut);
```

The signature for an equivalent MATLAB delegate function maps `argOut` as an LHS argument:

```
function argOut = myFunc(argIn)
```

Combine and Remove .NET Delegates

MATLAB provides the instance method `Combine`, that lets you combine a series of delegates into a single delegate. The `Remove` and `RemoveAll` methods delete individual delegates. For more information, refer to the .NET Framework Class Library, as described in “To Learn More About the .NET Framework” on page 10-18.

For example, create the following MATLAB functions to use with the `NetDocDelegate.delInteger` delegate:

```
function out = action1(n)
out = 'Add flour';
disp(out)
end
```

```
function out = action2(n)
out = 'Add eggs';
disp(out)
end
```

Create delegates `step1` and `step2`:

```
step1 = NetDocDelegate.delInteger(@action1);
step2 = NetDocDelegate.delInteger(@action2);
```

To combine into a new delegate, `mixItems`, type:

```
mixItems = step1.Combine(step2);
```

Or, type:

```
mixItems = step1.Combine(@action2);
```

Invoke `mixItems`:

```
result = mixItems(1);
```

In this case, the function `action2` follows `action1`:

```
Add flour
Add eggs
```

The value of `result` is the output from the final delegate (`step2`).

```
result =  
Add eggs
```

You also can use the `System.Delegate` class static methods, `Combine`, `Remove`, and `RemoveAll`.

To remove a `step1` from `mixItems`, type:

```
step3 = mixItems.Remove(step1);
```

.NET Delegates

In the .NET Framework, a *delegate* is a type that defines a method signature. It lets you pass a function as a parameter. The use of delegates enables .NET applications to make calls into MATLAB callback functions or class instance methods. For the rules MATLAB uses to define the signature of a callback function or class method, see “Reading Method Signatures” on page 10-76 in Using a .NET Object. For a complete description of delegates and when to use them, consult an outside resource, such as the Microsoft Developer Network.

There are three steps to using delegates:

- Declaration — Your .NET application contains the declaration. You cannot declare a delegate in the MATLAB language.
- Instantiation — In MATLAB, create an instance of the delegate and associate it with a specific MATLAB function or .NET object method.
- Invocation — Call the function with specified input and output arguments. Use the delegate name in place of the function name.

Calling .NET Methods Asynchronously

In this section...

“How MATLAB Handles Asynchronous Method Calls in .NET” on page 10-95

“Calling a Method Asynchronously Using a Callback When an Asynchronous Call Finishes” on page 10-95

“Calling a Method Asynchronously Without a Callback” on page 10-97

“Using EndInvoke With out and ref Type Arguments” on page 10-98

“Using Polling to Detect When Asynchronous Call Finishes” on page 10-98

How MATLAB Handles Asynchronous Method Calls in .NET

It is possible to call a synchronous method asynchronously in MATLAB. With some modifications, you can use the Microsoft `BeginInvoke` and `EndInvoke` methods. For more information, refer to the MSDN article “Calling Synchronous Methods Asynchronously” at <http://msdn.microsoft.com>.

You can use delegates to call a synchronous method asynchronously by using the `BeginInvoke` and `EndInvoke` methods. If the thread that initiates the asynchronous call does not need to be the thread that processes the results, you can execute a callback method when the call completes. For information about using a callback method, see “Calling a Method Asynchronously Using a Callback When an Asynchronous Call Finishes” on page 10-95.

Note: MATLAB is a single-threaded application. Therefore, handling asynchronous calls in the MATLAB environment might result in deadlocks.

Calling a Method Asynchronously Using a Callback When an Asynchronous Call Finishes

You can execute a callback method when an asynchronous call completes. A callback method executes on a different thread than the thread that processes the results of the asynchronous call.

The following is an overview of the procedure. If you do not use a callback function, follow the procedure in “Calling a Method Asynchronously Without a Callback” on page 10-97.

- Select or create a MATLAB function to execute asynchronously.
- Select or create a C# delegate and associate it with the MATLAB function.
- Create a MATLAB callback function with a System.AsyncCallback Delegate delegate signature. The signature, shown at the MSDN website, is:

```
public delegate void AsyncCallback(IAsyncResult ar)
```

- 1 Using MATLAB code, initiate the asynchronous call using the `BeginInvoke` method, specifying the callback delegate and, if required, object parameters.
- 2 Continue executing commands in MATLAB.
- 3 When the asynchronous function completes, MATLAB calls the callback function, which executes the `EndInvoke` method to retrieve the results.

Callback Example

In this example, create the following MATLAB function to execute asynchronously:

```
function X = DivideFunction(A, B)
if B ~= 0
    X = A / B;
else
    errid = 'MyID:DivideFunction:DivisionByZero';
    error(errid, 'Division by 0 not allowed.')
end
end
```

Create the following MATLAB function, which executes as the callback when the asynchronous method invocation completes. This function displays the `result` value of the `EndInvoke` method.

```
function myCallback(asyncRes)
result = asyncRes.AsyncDelegate.EndInvoke(asyncRes);
disp(result)
end
```

Use the `del2Integer` delegate, defined in the `NetDocDelegate` assembly:

```
public delegate Int32 del2Integer(Int32 arg1, Int32 arg2);
```

Run the example:

```
% Create the delegate
divDel = NetDocDelegate.del2Integer(@DivideFunction);
A = 10;
B = 5;
% Initiate the asynchronous call.
asyncRes = divDel.BeginInvoke(A,B,@myCallback,[]);
```

MATLAB displays the result: 2

Calling a Method Asynchronously Without a Callback

The following is an overview of the procedure. If you want to use a callback function, follow the procedure in “Calling a Method Asynchronously Using a Callback When an Asynchronous Call Finishes” on page 10-95.

- Select or create a MATLAB function to execute asynchronously.
 - Select or create a C# delegate and associate it with the MATLAB function.
- 1 In MATLAB, initiate the asynchronous call using the `BeginInvoke` method.
 - 2 Continue executing commands in MATLAB.
 - 3 Poll for asynchronous call completion using the MATLAB `pause` function.
 - 4 When the asynchronous function completes, call the `EndInvoke` method to retrieve the results.

Example Without Callback

In this example, create the following MATLAB function, `myFunction`:

```
% MATLAB function to execute asynchronously
function res = myFunction(strValue)
res = strValue;
end
```

Use the `delString` delegate, defined in the `NetDocDelegate` assembly:

```
public delegate string delString(string message);
```

In MATLAB, create the delegate, `myDelegate`, define the input values, and start the asynchronous call:

```
myDelegate = NetDocDelegate.delString(@myFunction);  
A = 'Hello';  
asyncRes = myDelegate.BeginInvoke(A,[],[]);
```

The `BeginInvoke` method returns the object, `asyncRes`, which you use to monitor the progress of the asynchronous call. Poll for results, using the MATLAB `pause` function to let MATLAB process the events:

```
while asyncRes.IsCompleted ~= true  
    pause(0.01)  
end
```

Retrieve and display the results of the asynchronous call:

```
result = myDelegate.EndInvoke(asyncRes);  
disp(result)
```

```
Hello
```

Using EndInvoke With out and ref Type Arguments

The MATLAB delegate signature for `EndInvoke` follows special mapping rules if your delegate has `out` or `ref` type arguments. For information about the mapping, see “Call Delegates With out and ref Type Arguments” on page 10-91. For examples, see the `EndInvoke` reference page.

Using Polling to Detect When Asynchronous Call Finishes

For MATLAB to process the event that executes the delegate's callback on the main thread, call the MATLAB `pause` (or a similar) function.

Limitations to Support of .NET Events

MATLAB Support of Standard Signature of an Event Handler Delegate

An event handler in C# is a delegate with the following signature:

```
public delegate void MyEventHandler(object sender, MyEventArgs e)
```

The argument `sender` specifies the object that fired the event. The argument `e` holds data that can be used in the event handler. The class `MyEventArgs` is derived from the .NET Framework class `EventArgs`. MATLAB only handles events with this standard signature.

Limitations to Support of .NET Delegates

MATLAB does not support associating a delegate instance with a generic .NET method.

When calling a method asynchronously, use the technique described in “Calling a Method Asynchronously Without a Callback” on page 10-97. Be aware that:

- MATLAB is a single-threaded application. Therefore, handling asynchronous calls in the MATLAB environment might result in deadlocks.
- For the technique described in the MSDN topic Blocking Application Execution Using an AsyncWaitHandle, MATLAB does not support the use of the `WaitOne()` method overload with no arguments.
- You cannot call `EndInvoke` to wait for the asynchronous call to complete.

Use Bit Flags with .NET Enumerations

In this section...

“How MATLAB Supports Bit-Wise Operations on `System.Enum`” on page 10-101

“Creating .NET Enumeration Bit Flags” on page 10-101

“Removing a Flag from a Variable” on page 10-102

“Replacing a Flag in a Variable” on page 10-102

“Testing for Membership” on page 10-103

How MATLAB Supports Bit-Wise Operations on `System.Enum`

Many .NET languages support bit-wise operations on enumerations defined with the `System.Flags` attribute. The MATLAB language does not have equivalent operations, and, therefore, provides instance methods for performing bit-wise operations on an enumeration object. The bit-wise methods are `bitand`, `bitnot`, `bitor`, and `bitxor`.

An enumeration can define a *bit flag*. A bit flag lets you create instances of an enumeration to store combinations of values defined by the members. For example, files and folders have attributes, such as `Archive`, `Hidden`, and `ReadOnly`. For a given file, perform an operation based on one or more of these attributes. With bit-wise operators, you can create and test for combinations.

To use bit-wise operators, the enumeration must have:

- The `Flags` attribute. In Framework Version 4, these enumerations also have the `HasFlag` method.
- Values that correspond to powers of 2.

Creating .NET Enumeration Bit Flags

Use the MATLAB example, `NetDocEnum.MyDays` enumeration, in the following examples.

Suppose that you have the following scheduled activities:

- Monday — Department meeting at 10:00
- Wednesday and Friday — Team meeting at 2:00
- Thursday — Volley ball night

You can combine members of the `MyDays` enumeration to create MATLAB variables using the `bitor` method, which joins two members. For example, to create a variable `teamMtgs` of team meeting days, type:

```
teamMtgs = bitor(...  
    NetDocEnum.MyDays.Friday,...  
    NetDocEnum.MyDays.Wednesday);
```

Create a variable `allMtgs` of all days with meetings:

```
allMtgs = bitor(teamMtgs,...  
    NetDocEnum.MyDays.Monday);
```

To see which days belong to each variable, type:

```
teamMtgs  
allMtgs  
  
teamMtgs =  
Wednesday, Friday  
  
allMtgs =  
Monday, Wednesday, Friday
```

Removing a Flag from a Variable

Suppose that your manager cancels the Wednesday meeting this week. To remove Wednesday from the `allMtgs` variable, use the `bitxor` method.

```
thisWeekMtgs = bitxor(allMtgs,NetDocEnum.MyDays.Wednesday)  
  
thisWeekMtgs =  
Monday, Friday
```

Using a bit-wise method such as `bitxor` on `allMtgs` does not modify the value of `allMtgs`. This example creates a variable, `thisWeekMtgs`, which contains the result of the operation.

Replacing a Flag in a Variable

Suppose that you change the team meeting permanently from Wednesday to Thursday. To remove Wednesday, use `bitxor`, and use `bitor` to add Thursday. Since this is a permanent change, update the `teamMtgs` and `allMtgs` variables.

```
teamMtgs = bitor(...
```



```

        (bitand(teamMtgs,...
            bitnot(NetDocEnum.MyDays.Wednesday)),...
        NetDocEnum.MyDays.Thursday);
allMtgs = bitor(teamMtgs,...
    NetDocEnum.MyDays.Monday);
teamMtgs
allMtgs

teamMtgs =
Thursday, Friday

allMtgs =
Monday, Thursday, Friday

```

Testing for Membership

Create the following RemindMe function:

```

function RemindMe(day)
% day = NetDocEnum.MyDays enumeration
teamMtgs = bitor(...
    NetDocEnum.MyDays.Friday,...
    NetDocEnum.MyDays.Wednesday);
allMtgs = bitor(teamMtgs,...
    NetDocEnum.MyDays.Monday);

if eq(day,bitand(day,teamMtgs))
    disp('Team meeting today.')
elseif eq(day,bitand(day,allMtgs))
    disp('Meeting today.')
else
    disp('No meetings today!')
end
end

```

Use the RemindMe function:

```

today = NetDocEnum.MyDays.Monday;
RemindMe(today)

Meeting today.

```

See Also

bitand | bitnot | bitor | bitxor

Related Examples

- “NetDocEnum Example Assembly” on page 10-109

Read Special System Folder Path

```
function result = getSpecialFolder(arg)
% Returns the special system folders such as "Desktop", "MyMusic" etc.
% arg can be any one of the enum element mentioned in this link
% http://msdn.microsoft.com/en-us/library/
% system.environment.specialfolder.aspx
% e.g.
%     >> getSpecialFolder('Desktop')
%
%     ans =
%     C:\Users\jsmith\Desktop

% Get the type of SpecialFolder enum, this is a nested enum type.
specialFolderType = System.Type.GetType(...
    'System.Environment+SpecialFolder');
% Get a list of all SpecialFolder enum values
folders = System.Enum.GetValues(specialFolderType);
enumArg = [];

% Find the matching enum value requested by the user
for i = 1:folders.Length
    if (strcmp(char(folders(i)), arg))
        enumArg = folders(i);
        break
    end
end

% Validate
if isempty(enumArg)
    error('Invalid Argument')
end

% Call GetFolderPath method and return the result
result = System.Environment.GetFolderPath(enumArg);
end
```

.NET Enumerations in MATLAB

MATLAB allows you to work with *.NET enumerations* using features of the MATLAB enumeration class and some features unique to the .NET Framework.

Terms you should know:

- Enumeration — In MATLAB, a class having a finite set of named instances.
- Enumeration member — Named instance of an enumeration class.
- Underlying value — Numeric value associated with an enumeration member.

Enumerations contain the following information:

- Members
- Methods
- Underlying Values

In this topic, the term **enumeration** refers to a .NET enumeration.

Note: The MATLAB language supports user-defined enumeration classes. If you are using enumerations defined in MATLAB, refer to the topics under Enumerations.

Default Methods for an Enumeration

By default, MATLAB provides the following methods for a .NET enumeration:

- Relational operators — `eq`, `ne`, `ge`, `gt`, `le`, and `lt`.
- Conversion methods — `char`, `double`, and a method to get the underlying value.
- Bit-wise methods — Only for enumerations with the `System.Flags` attribute.

For example, type:

```
methods('System.DayOfWeek')
```

```
Methods for class System.DayOfWeek:
```

```
CompareTo      eq
DayOfWeek      ge
Equals         gt
GetHashCode    int32
GetType        le
GetTypeCode    lt
ToString       ne
char
double
```

The method to get the underlying value is `int32`.

The `NetDocEnum.MyDays` enumeration, which has the `Flags` attribute, has the bit-wise methods. To list the methods, type:

```
methods('NetDocEnum.MyDays')
```

```
Methods for class NetDocEnum.MyDays:
```

```
CompareTo      char
Equals         double
GetHashCode    eq
GetType        ge
GetTypeCode    gt
MyDays         int32
ToString       le
bitand         lt
bitnot         ne
bitor
```

bitxor

Related Examples

- “Using Relational Operations” on page 10-118
- “Using Switch Statements” on page 10-118
- “Display .NET Enumeration Members as Character Strings” on page 10-114
- “NetDocEnum Example Assembly” on page 10-109

More About

- “Use Bit Flags with .NET Enumerations” on page 10-101

NetDocEnum Example Assembly

The C# example `NetDocEnum.cs`, in the `matlabroot/extern/examples/NET/NetSample` folder, defines enumerations used in examples. To see the code, open the file in MATLAB Editor. To run the examples, build the `NetDocEnum` assembly as described in “Build a .NET Application for MATLAB Examples” on page 10-21.

If the `NetDocEnum` assembly is in your `c:\work` folder, load the file:

```
dllPath = fullfile('c:', 'work', 'NetDocEnum.dll');
asm = NET.addAssembly(dllPath);
asm.Enums

ans =
    'NetDocEnum.MyDays'
    'NetDocEnum.Range'
```

Work with Members of a .NET Enumeration

To display the member names of an enumeration, use the MATLAB enumeration function. For example, to list the member names of the `System.DayOfWeek` enumeration, type:

```
enumeration('System.DayOfWeek')  
  
Enumeration members for class 'System.DayOfWeek':  
    Sunday  
    Monday  
    Tuesday  
    Wednesday  
    Thursday  
    Friday  
    Saturday
```

You cannot use the `enumeration` command to return arrays of .NET enumeration objects. You can read the names and values of the enumeration into arrays, using the `System.Enum` methods `GetNames`, `GetValues`, and `GetType`.

For example, to create arrays `allNames` and `allValues` for the `System.DayOfWeek` enumeration, type:

```
myDay = System.DayOfWeek;  
allNames = System.Enum.GetNames(myDay.GetType);  
allValues = System.Enum.GetValues(myDay.GetType);
```

The class of the names array is `System.String`, while the class of the values array is the enumeration type `System.DayOfWeek`.

```
whos all*  
  
    Name          Size  Bytes  Class  
  
    allNames      1x1   112   System.String[]  
    allValues     1x1   112   System.DayOfWeek[]
```

Although the types are different, the information MATLAB displays is the same. For example, type:

```
allNames(1)  
  
ans =
```


Sunday

Type:

allValues(1)

ans =
Sunday

See Also

enumeration

Related Examples

- “Iterate Through a .NET Enumeration” on page 10-116

More About

- “Information About System.Enum Methods” on page 10-116
- “How MATLAB Handles System.String” on page 10-52

Refer to a .NET Enumeration Member

You use an *enumeration member* in your code as an instance of an enumeration. To refer to an enumeration member, use the C# namespace, enumeration, and member names:

```
Namespace . EnumName . MemberName
```

For example, the `System` namespace in the .NET Framework class library has a `DayOfWeek` enumeration. The members of this enumeration are:

```
Enumeration members for class 'System.DayOfWeek':  
    Sunday  
    Monday  
    Tuesday  
    Wednesday  
    Thursday  
    Friday  
    Saturday
```

To create a variable with the value `Thursday`, type:

```
gameDay = System.DayOfWeek.Thursday;  
whos  
  
    Name      Size Bytes Class  
  
    gameDay   1x1   104   System.DayOfWeek
```

Using the Implicit Constructor

The implicit constructor, *Namespace.EnumName*, creates a member with the default value of the underlying type. For example, the `NetDocEnum.Range` enumeration has the following members:

```
Enumeration members for class 'NetDocEnum.Range':  
    Max  
    Min
```

Type:

```
x = NetDocEnum.Range  
whos x  
  
x =
```

0

Name	Size	Bytes	Class
x	1x1	104	NetDocEnum.Range

Related Examples

- “NetDocEnum Example Assembly” on page 10-109

Display .NET Enumeration Members as Character Strings

To get the descriptive name of an enumeration, use the `char` method. For example, type:

```
gameDay = System.DayOfWeek.Thursday;  
[ 'Next volleyball game is ',char(gameDay) ]
```

```
ans =  
Next volleyball game is Thursday
```

Convert .NET Enumeration Values to Type Double

To convert a value to a MATLAB double, type:

```
gameDay = System.DayOfWeek.Thursday;  
myValue = double(gameDay)
```

```
myValue =  
    4
```

Iterate Through a .NET Enumeration

In this section...

“Information About System.Enum Methods” on page 10-116

“Display Enumeration Member Names” on page 10-117

Information About System.Enum Methods

To create MATLAB arrays from an enumeration, use the static `System.Enum` methods `GetNames` and `GetValues`. The input argument for these methods is an enumeration type. Use the `GetType` method for the type of the current instance. To display the signatures for these methods, type:

```
methodsview('System.Enum')
```

Look at the following signatures:

Qualifiers	Return Type	Name	Arguments
	<code>System.Type</code>	<code>GetType</code>	<code>(System.Enum this)</code>
Static	<code>System.String[]</code>	<code>GetNames</code>	<code>(System.Type enumType)</code>
Static	<code>System.Array</code>	<code>GetValues</code>	<code>(System.Type enumType)</code>

To use `GetType`, create an instance of the enumeration. For example:

```
myEnum = System.DayOfWeek;
```

The `enumType` for `myEnum` is:

```
myEnumType = myEnum.GetType;
```

To create an array of names using the `GetNames` method, type:

```
allNames = System.Enum.GetNames(myEnumType);
```

Alternatively:

```
allNames = System.Enum.GetNames(myEnum.GetType);
```

Display Enumeration Member Names

To display all member names of the `System.DayOfWeek` enumeration, create a `System.String` array of names. Use the `Length` property of this array to find the number of members. For example:

```
myDay = System.DayOfWeek;  
allNames = System.Enum.GetNames(myDay.GetType);  
disp(['Members of ' class(myDay)])  
for idx = 1:allNames.Length  
    disp(allNames(idx))  
end
```

```
Members of System.DayOfWeek  
Sunday  
Monday  
Tuesday  
Wednesday  
Thursday  
Friday  
Saturday
```

Use .NET Enumerations to Test for Conditions

In this section...

“Using Switch Statements” on page 10-118

“Using Relational Operations” on page 10-118

With relational operators, you can use enumeration members in `if` and `switch` statements and other functions that test for equality.

Using Switch Statements

The following `Reminder` function displays a message depending on the day of the week:

```
function Reminder(day)
% day = System.DayOfWeek enumeration value
% Add error checking here
switch(day)
    case System.DayOfWeek.Monday
        disp('Department meeting at 10:00')
    case System.DayOfWeek.Tuesday
        disp('Meeting Free Day!')
    case {System.DayOfWeek.Wednesday System.DayOfWeek.Friday}
        disp('Team meeting at 2:00')
    case System.DayOfWeek.Thursday
        disp('Volley ball night')
end
end
```

For example, type:

```
today = System.DayOfWeek.Wednesday;
Reminder(today)
```

```
ans =
Team meeting at 2:00
```

Using Relational Operations

Create the following function to display a message:

```
function VolleyballMessage(day)
```



```
% day = System.DayOfWeek enumeration value
if gt(day, System.DayOfWeek.Thursday)
    disp('See you next week at volleyball.')
else
    disp('See you Thursday!')
end
end
```

For a day before Thursday:

```
myDay = System.DayOfWeek.Monday;
VolleyballMessage(myDay)
```

See you Thursday!

For a day after Thursday:

```
myDay = System.DayOfWeek.Friday;
VolleyballMessage(myDay)
```

See you next week at volleyball.

Underlying Enumeration Values

MATLAB supports enumerations of any numeric type.

To find the underlying type of an enumeration, use the `System.Enum` static method `GetUnderlyingType`. For example, the following C# statement in the `NetDocEnum` assembly declares the enumeration `Range`:

```
public enum Range : long {Max = 2147483648L,Min = 255L}
```

To display the underlying type:

```
maxValue = NetDocEnum.Range.Max;  
System.Enum.GetUnderlyingType(maxValue.GetType).FullName  
  
ans =  
System.Int64
```

Related Examples

- “NetDocEnum Example Assembly” on page 10-109

Limitations to Support of .NET Enumerations

You cannot create arrays of .NET enumerations, or any .NET objects, in MATLAB.

Create .NET Collections

This example uses two `System.String` arrays, `d1` and `d2`, to create a generic collection list. It shows how to manipulate the list and access its members. To create the arrays, type:

```
d1 = NET.createArray('System.String',3);  
d1(1) = 'Brachiosaurus';  
d1(2) = 'Shunosaurus';  
d1(3) = 'Allosaurus';  
  
d2 = NET.createArray('System.String',4);  
d2(1) = 'Tyrannosaurus';  
d2(2) = 'Spinosaurus';  
d2(3) = 'Velociraptor';  
d2(4) = 'Triceratops';
```

Create a generic collection, `dc`, to contain `d1`. The `System.Collections.Generic.List` class is in the `mscorlib` assembly, which MATLAB loads automatically.

```
dc = NET.createGeneric('System.Collections.Generic.List',...  
    {'System.String'},3)  
  
List<System*String> handle  
  
    Capacity: 3  
    Count: 0
```

The `List` object `dc` has a `Capacity` of three, but currently is empty (`Count = 0`).

Use the `AddRange` method to add the contents of `d1` to the list. For more information, search the Web for `System.Collections.Generic` and select the `List` class.

```
AddRange(dc,d1);
```

List `dc` now has three items:

```
dc.Count
```

To display the contents, use the `Item` method and zero-based indexing:

```
for i = 1:dc.Count  
    disp(dc.Item(i-1))
```

```
end
```

```
Brachiosaurus  
Shunosaurus  
Allosaurus
```

Another way to add values is to use the `InsertRange` method. Insert the `d2` array starting at index 1:

```
InsertRange(dc,1,d2);
```

The size of the array has grown to seven. To display the values, type:

```
for i = 1:dc.Count  
    disp(dc.Item(i-1))  
end
```

```
Brachiosaurus  
Tyrannosaurus  
Spinosaurus  
Velociraptor  
Triceratops  
Shunosaurus  
Allosaurus
```

The first item in the `d2` array ('Tyrannosaurus') is at index 1 in list `dc`:

```
System.String.Compare(d2(1),dc.Item(1))
```

The `System.String.Compare` answer, 0, indicates that the two values are equal.

Convert .NET Collections to MATLAB Arrays

Use the `ToArray` method of the `System.Collections.Generic.List` class to convert a collection to an array. For example, use `GetRange` to get three values from the list, starting with index 2. Then call `ToArray` to create a `System.String` array `dArr`, and display the results:

```
temp = GetRange(dc,2,3);  
dArr = ToArray(temp);  
for i = 1:dArr.Length  
    disp(dArr(i))  
end
```

```
Spinosaurus  
Velociraptor  
Triceratops
```

To create a MATLAB array `D`:

```
D = {char(dArr(1)),char(dArr(2)),char(dArr(3))}  
  
D =  
    'Spinosaurus'    'Velociraptor'    'Triceratops'
```

Now you can use `D` in MATLAB functions. For example, if you type:

```
D'  
  
ans =  
    'Spinosaurus'  
    'Velociraptor'  
    'Triceratops'
```

Sort the array alphabetically:

```
sort(D)  
  
ans =  
    'Spinosaurus'    'Triceratops'    'Velociraptor'
```

Create .NET Arrays of Generic Type

This example creates a .NET array of `List<Int32>` generic type.

```
genType = NET.GenericClass('System.Collections.Generic.List', ...  
    'System.Int32');  
arr = NET.createArray(genType, 5)
```

```
arr =
```

```
List<System*Int32>[] with properties:
```

```
    Length: 5  
    LongLength: 5  
    Rank: 1  
    SyncRoot: [1x1 System.Collections.Generic.List<System*Int32>[]]  
    IsReadOnly: 0  
    IsFixedSize: 1  
    IsSynchronized: 0
```

Display .NET Generic Methods Using Reflection

In this section...

“showGenericMethods Function” on page 10-126

“Display Generic Methods in a Class” on page 10-127

“Display Generic Methods in a Generic Class” on page 10-128

showGenericMethods Function

The `showGenericMethods` function, reads a .NET object or a fully qualified class name and returns a cell array of the names of the generic method in the given class or object. Create the following MATLAB functions:

```
function output = showGenericMethods(input)
% if input is a .NET object, get MethodInfo[]
if IsNetObject(input)
    methods = GetType.GetMethods(input);
    % if input is a string, get the type and get get MethodInfo[]
elseif ischar(input) && ~isempty(input)
    type = getType(input);
    if isempty(type)
        disp(strcat(input, ' not found'))
        return
    end
    methods = GetMethods(type);
else
    return
end
% generate generic method names from MethodInfo[]
output = populateGenericMethods(methods);

end

function output = populateGenericMethods(methods)
% generate generic method names from MethodInfo[]
index = 1;
for i = 1:methods.Length
    method = methods(i);
    if method.IsGenericMethod
        output{index,1} = method.ToString.char;
        index = index + 1;
    end
end
end
```



```

        end
    end
end

function result = IsNetObject(input)
% Must be sub class of System.Object to be a .NET object
result = isa(input, 'System.Object');
end

function outputType = getType(input)
% Input is a string representing the class name
% First try the static GetType method of Type handle.
% This method can find any type from
% System or mscorlib assemblies
outputType = System.Type.GetType(input, false, false);
if isempty(outputType)
    % Framework's method to get the type failed.
    % Manually look for it in
    % each assembly visible to MATLAB
    assemblies = System.AppDomain.CurrentDomain.GetAssemblies;
    for i = 1:assemblies.Length
        asm = assemblies.Get(i-1);
        % Look for a particular type in the assembly
        outputType = GetType(asm, input, false, false);
        if ~isempty(outputType)
            % Found the type - done
            break
        end
    end
end
end
end
end

```

Display Generic Methods in a Class

The `NetDocGeneric` assembly contains a class with generic methods.

```

dllPath = fullfile('c:', 'work', 'NetDocGeneric.dll');
asm = NET.addAssembly(dllPath);
asm.Classes

ans =
    'NetDocGeneric.SampleClass'

```

Display the methods in `SampleClass`:

```
showGenericMethods('NetDocGeneric.SampleClass')  
  
ans =  
    'K GenMethod[K](K)'  
    'K GenMethodWithMixedArgs[K](K, K, Boolean)'  
    'K GenStaticMethod[K](K)'  
    'K GenStaticMethodWithMixedArgs[K](K, K, Boolean)'
```

Display Generic Methods in a Generic Class

The `NetDocGeneric` assembly contains a generic class with generic methods.

```
dllPath = fullfile('c:', 'work', 'NetDocGeneric.dll');  
asm = NET.addAssembly(dllPath);  
asm.GenericTypes
```

```
ans =  
    'NetDocGeneric.SampleGenericClass`1[T]'
```

Display the methods in `SampleGenericClass`:

```
cls = NET.createGeneric('NetDocGeneric.SampleGenericClass', {'System.Double'});  
showGenericMethods(cls)  
  
ans =  
    'System.String ParameterizedGenMethod[K](Double, K)'  
    'T GenMethod[T](T)'  
    'K GenStaticMethod[K](K)'  
    'K GenStaticMethodWithMixedArgs[K](K, K, Boolean)'  
    'System.String ParameterizedStaticGenMethod[K](Double, K)'
```

.NET Generic Classes

Generics are classes and methods that have placeholders (type parameters or *parameterized types*) for one or more types. This lets you design classes that take in a generic type and determine the actual type at run time. A common use for generic classes is to work with collections. For information about generic methods, see “Call .NET Generic Methods” on page 10-131.

The `NET.createGeneric` function creates an instance of the specialized generic class given the following:

- Fully qualified name of the generic class definition
- List of fully qualified parameter type names for generic type specialization
- Variable list of constructor arguments

Use instances of the `NET.GenericClass` helper class in `NET.createGeneric` function’s parameter type list when specialization requires another parameterized class definition. The class instances serve as parameterized data type definitions and are constructed using fully qualified generic type name and a variable length list of fully qualified type names for generic type specialization. This list can also contain instances of `NET.GenericClass` if an extra nested level of parameterization is required.

Accessing Items in .NET Collections

Use the `Item` property of the `System.Collections.Generic.List` class to get or set an element at a specified index. Since `Item` is a property that takes arguments, MATLAB maps it to a pair of methods to get and set the value. For example, the syntax to use `Item` to get a value is:

Return Type	Name	Arguments
<code>System.String</code> <code>RetVal</code>	<code>Item</code>	<code>(System.Collections.Generic.List<System*String> this, int32 scalar index)</code>

The syntax to use `Item` to set a value is:

Return Type	Name	Arguments
<code>none</code>	<code>Item</code>	<code>(System.Collections.Generic.List<System*String> this, int32 scalar index, System.String value)</code>

Call .NET Generic Methods

A *generic method* declares one or more parameterized types. For more information, search for the term **generics** in the .NET Framework Class Library, as described in “To Learn More About the .NET Framework” on page 10-18.

Use the `NET.invokeGenericMethod` function to call a generic method. How you use the `NET.invokeGenericMethod` depends if the method is static or if it is a member of a generic class.

In this section...

“Using the `NetDocGeneric` Example” on page 10-131

“Invoke Generic Class Member Function” on page 10-132

“Invoke Static Generic Functions” on page 10-132

“Invoke Static Generic Functions of a Generic Class” on page 10-132

“Invoke Generic Functions of a Generic Class” on page 10-133

Using the `NetDocGeneric` Example

The C# example `NetDocGeneric.cs`, in the `matlabroot/extern/examples/NET/NetSample` folder, defines simple generic methods to illustrate the `NET.invokeGenericMethod` syntax. To see the code, open the file in MATLAB Editor. Build the `NetDocGeneric` assembly as described in “Build a .NET Application for MATLAB Examples” on page 10-21.

If you created the assembly `NetDocGeneric` and put it in your `C:\work` folder, type the following MATLAB commands to load the assembly:

```
dllPath = fullfile('c:', 'work', 'NetDocGeneric.dll');  
NET.addAssembly(dllPath);
```

Note: The `methods` and `methodsview` functions do not list generic methods. Use the “Display .NET Generic Methods Using Reflection” on page 10-126 example.

Invoke Generic Class Member Function

The `GenMethod` method in `NetDocGeneric.SampleClass` returns the input argument as type `K`. To call `GenMethod`, create an object, `cls`:

```
cls = NetDocGeneric.SampleClass();
```

To convert `5` to an integer parameter type, such as `System.Int32`, call `NET.invokeGenericMethod` with the object:

```
ret = NET.invokeGenericMethod(cls,...  
    'GenMethod',...  
    {'System.Int32'},...  
    5);
```

The `GenMethodWithMixedArgs` method has parameterized typed arguments, `arg1` and `arg2`, and a strongly-typed argument, `tf`, of type `bool`. The `tf` flag controls which argument `GenMethodWithMixedArgs` returns. To return `arg1`, use the syntax:

```
ret = NET.invokeGenericMethod(cls, 'GenMethodWithMixedArgs',...  
    {'System.Double'},5,6,true);
```

To return `arg2`, use the syntax:

```
ret = NET.invokeGenericMethod(cls, 'GenMethodWithMixedArgs',...  
    {'System.Double'},5,6,false);
```

Invoke Static Generic Functions

To invoke static method `GenStaticMethod`, call `NET.invokeGenericMethod` with the fully qualified class name:

```
ret = NET.invokeGenericMethod('NetDocGeneric.SampleClass',...  
    'GenStaticMethod',...  
    {'System.Int32'},...  
    5);
```

Invoke Static Generic Functions of a Generic Class

If a static function is a member of a generic class, create a class definition using the `NET.GenericClass` constructor:

```
genClsDef = NET.GenericClass('NetDocGeneric.SampleGenericClass',...
```

```
'System.Double');
```

To invoke static method `GenStaticMethod` of `SampleGenericClass`, call `NET.invokeGenericMethod` with the class definition:

```
ret = NET.invokeGenericMethod(genClsDef, ...  
    'GenStaticMethod', ...  
    { 'System.Int32' }, ...  
    5);
```

Invoke Generic Functions of a Generic Class

If a generic method uses the same parameterized type as the generic class, you can call the function directly on the class object. If the generic uses a different type than the class, use the `NET.invokeGenericMethod` function.

Using COM Objects from MATLAB

- “MATLAB COM Integration” on page 11-2
- “Getting Started with COM” on page 11-7
- “Use Internet Explorer in MATLAB Figure” on page 11-10
- “Add Grid ActiveX Control in a Figure” on page 11-15
- “Read Excel Spreadsheet Data” on page 11-23
- “Supported Client/Server Configurations” on page 11-30

MATLAB COM Integration

In this section...
“What Is COM?” on page 11-2
“Concepts and Terminology” on page 11-2
“The MATLAB COM Client” on page 11-4
“The MATLAB COM Automation Server” on page 11-4
“Registering Controls and Servers” on page 11-5

What Is COM?

Note: MATLAB supports the Microsoft .NET Framework on the Windows platform. For more information about this alternative, see “Using .NET from MATLAB” on page 10-17.

The Microsoft *Component Object Model (COM)* provides a framework for integrating reusable, binary software components into an application. Because components are implemented with compiled code, the source code can be written in any of the many programming languages that support COM. Upgrades to applications are simplified, as components can simply be swapped without the need to recompile the entire application. In addition, a component's location is transparent to the application, so components can be relocated to a separate process or even a remote system without having to modify the application.

Using COM, developers and end users can select application-specific components produced by different vendors and integrate them into a complete application solution. For example, a single application might require database access, mathematical analysis, and presentation-quality business graphs. Using COM, a developer can choose a database-access component by one vendor, a business graph component by another, and integrate these into a mathematical analysis package produced by yet a third.

MATLAB software supports COM integration on the Microsoft Windows platform only.

Concepts and Terminology

While the ideas behind COM technology are straightforward, the terminology is not. The meaning of COM terms has changed over time and few concise definitions exist. Here are

some terms that you should be familiar with. These are not comprehensive definitions. For a complete description of COM, you'll need to consult outside resources.

- “COM Objects, Clients, and Servers” on page 11-3
- “Interfaces” on page 11-3
- “COM Server Types” on page 13-4
- “Programmatic Identifiers” on page 13-4
- “Shared and Dedicated Servers” on page 13-4
- “In-Process and Out-of-Process Servers” on page 13-5

COM Objects, Clients, and Servers

A COM *object* is a software component that conforms to the Component Object Model. COM enforces encapsulation of the object, preventing direct access of its data and implementation. COM objects expose “Interfaces” on page 11-3, which consist of properties, methods and events.

A COM *client* is a program that makes use of COM objects. COM objects that expose functionality for use are called COM *servers*. COM servers can be in-process or out-of-process. An example of an out-of-process server is Microsoft Excel spreadsheet program. These configurations are described in “In-Process and Out-of-Process Servers” on page 13-5.

A Microsoft *ActiveX*[®] *control* is a type of in-process COM server that requires a control container. ActiveX controls typically have a user interface. An example is the Microsoft Calendar control. A control container is an application capable of hosting ActiveX controls. A MATLAB figure window or a Simulink model are examples of control containers.

MATLAB can be used as either a COM client or COM server.

Interfaces

The functionality of a component is defined by one or more interfaces. To use a COM component, you must learn about its interfaces, and the methods, properties, and events implemented by the component. The component vendor provides this information.

There are two standard COM interfaces:

- **IUnknown** — An interface required by all COM components. All other COM interfaces are derived from IUnknown.
- **IDispatch** — An interface that exposes objects, methods and properties to applications that support Automation.

The MATLAB COM Client

Using MATLAB as a COM client provides two techniques for developing programs in MATLAB:

- You can include COM components in your MATLAB application (for example, a spreadsheet).
- You can access existing applications that expose objects via Automation.

In a typical scenario, MATLAB creates ActiveX controls in figure windows, which are manipulated by MATLAB through the controls' properties, methods, and events. This is useful because there exists a wide variety of graphical user interface components implemented as ActiveX controls. For example, the Microsoft Internet Explorer[®] program exposes objects that you can include in a figure to display an HTML file. There also are treeviews, spreadsheets, and calendars available from a variety of sources.

MATLAB COM clients can access applications that support Automation, such as the Excel spreadsheet program. In this case, MATLAB creates an Automation server in which to run the application and returns a handle to the primary interface for the object created.

Information about creating and using COM controls and server objects in MATLAB can be found in “Creating COM Objects” on page 12-2.

The MATLAB COM Automation Server

Automation provides an infrastructure whereby applications called automation controllers can access and manipulate (i.e. set properties of or call methods on) shared automation objects that are exported by other applications, called Automation servers. Any Windows program that can be configured as an Automation controller can control MATLAB.

For example, using Microsoft Visual Basic[®] programming language, you can run a MATLAB script in a Microsoft PowerPoint[®] presentation. In this case, PowerPoint is the controller and MATLAB is the server.

Information for creating and connecting to a MATLAB Automation server running MATLAB can be found in “MATLAB COM Automation Server Interface” on page 13-4.

Registering Controls and Servers

Before using COM objects, you must register their controls and servers. Most are registered by default. However, if you get a new `.ocx`, `.dll`, or other object file for the control or server, you must register the file manually in the Windows registry.

Use the Windows `regsvr32` command to register your file. From the Windows prompt, use the `cd` function to go to the folder containing the object file. If your object file is an `.ocx` file, type:

```
regsvr32 filename.ocx
```

For example, to register the MATLAB control `mwsamp2.ocx`, type:

```
cd matlabroot\toolbox\matlab\winfun\win32
regsvr32 mwsamp2.ocx
```

If you encounter problems with this procedure, please consult a Windows manual or contact your local system administrator.

Accessing COM Controls Created with .NET

If you create a COM control using Microsoft .NET Framework 4, use the DOS `regasm` command with the `/codebase` option to register your file.

Verifying the Registration

Here are several ways to verify that a control or server is registered. These examples use the MATLAB `mwsamp` control. Refer to your Microsoft product documentation for information about using Microsoft Visual Studio or the Microsoft Registry Editor programs.

- Go to the Visual Studio .NET 2003 Tools menu and execute the ActiveX control test container. Click **Edit**, insert a new control, and select **MwSamp Control**. If you are able to insert the control without any problems, the control is successfully registered. Note that this method only works on controls.
- Open the Registry Editor by typing `regedit` at the DOS prompt. Search for your control or server object by selecting **Find** from the **Edit** menu. It will likely be in the following structure:

HKEY_CLASSES_ROOT/progid

- Open OLEViewer from the Visual Studio .NET 2003 Tools menu. Look in the following structure for your Control object:

```
Object Classes : Grouped by Component Category : Control :  
Your_Control_Object_Name (i.e. Object Classes : Grouped by  
Component Category : Control : Mwsamp Control)
```

Getting Started with COM

In this section...

“Introduction to COM” on page 11-7

“Basic COM Functions” on page 11-7

Introduction to COM

A COM client is a program that manipulates COM objects. These objects can run in the MATLAB application or can be part of another application that exposes its objects as a programmatic interface to the application.

This section provides examples that show how to use MATLAB as a COM client.

Note: You can also access MATLAB as an Automation server from other applications, such as those written in the Microsoft Visual Basic programming language. For information on this technique, see “MATLAB COM Automation Server Interface” on page 13-4.

Basic COM Functions

To start using COM objects, you need to create the object and get information about it. This section covers the following topics:

- “Creating an Instance of a COM Object” on page 11-7
- “Getting Information About a Particular COM Control” on page 11-8
- “Getting an Object's ProgID” on page 11-8
- “Registering a Custom Control” on page 11-9

Creating an Instance of a COM Object

Two MATLAB functions enable you to create COM objects:

- `actxcontrol` — Creates an instance of a control in a MATLAB figure.
- `actxserver` — Creates and manipulates objects from MATLAB that are exposed in an application that supports Automation.

Each function returns a *handle* to the object's main interface, which you use to access the object's methods, properties, and events, and any other interfaces it provides.

Getting Information About a Particular COM Control

In general, you can determine what you can do with an object using the `methods`, `get`, and `events` functions.

Information about Methods

To list the methods supported by the object *handle*, type:

```
methods(handle)
```

Information about Properties

To list the properties of the object *handle*, type:

```
get(handle)
```

To see the value of the property *PropertyName*, type:

```
get(handle, 'PropertyName')
```

Use `set` to change a property value.

Information about Events

To list the events supported by the object *handle*, type:

```
events(handle)
```

For more information on calling syntax, see “Getting Interfaces to COM Object” on page 12-54 and “Invoking Methods on an Object” on page 12-31. For more information on events, see “Use Events” on page 12-38.

Getting an Object's ProgID

To get the programmatic identifier (**ProgID**) of a COM control that is already registered on your computer, use the `actxcontrollist` command. You can also use the **ActiveX Control Selector**, displayed with the command `actxcontrolselect`. This interface lets you see instances of the controls installed on your computer.

For more information on using these commands, see “Creating an ActiveX Control” on page 12-3.

Registering a Custom Control

If your MATLAB program uses a custom control (e.g., one that you have created especially for your application), you must register it with the Microsoft Windows operating system before you can use it. You can do this from your MATLAB program by issuing an operating system command:

```
!regsvr32 /s filename.ocx
```

where *filename* is the name of the file containing the control. Using this command in your program enables you to provide custom-made controls that you make available to other users by registering the control on their computer when they run your MATLAB program. You might also want to supply versions of a Microsoft ActiveX control to ensure that all users have the same version.

For more information about registration, see “Registering Controls and Servers” on page 11-5.

Use Internet Explorer in MATLAB Figure

This example uses the ActiveX control `Shell.Explorer`, which is exposed by the Microsoft Internet Explorer application, to include an HTML viewer in a MATLAB figure. The figure's window button down function is then used to select a graphics object when the user clicks the graph and load the object's property documentation into the HTML viewer.

Techniques Demonstrated

- Using Internet Explorer from an ActiveX client program.
- Defining a window button down function that displays HTML property documentation for whatever object the user clicks.
- Defining a `resize` function for the figure that also resizes the ActiveX object container.


Using the Figure to Access Properties

This example creates a larger than normal figure window that contains an axes object and an HTML viewer on the lower part of the figure window. By default, the viewer displays the URL `http://www.mathworks.com`. When you issue a plotting command, such as:

```
surf(c( peaks(20) )
```

the graph displays in the axes.

Click anywhere in the graph to see the property documentation for the selected object.



Complete Code Listing

You can open the file that implements this example in MATLAB Editor or you can run this example with the following links:

- [Open file in editor](#)
- [Run this example](#)

Creating the Figure

This example defines the figure size based on the default figure size and adds space for the ActiveX control. Here is the code to define the figure:

```
dfpos = get(0,'DefaultFigurePosition');
hfig = figure('Position',dfpos([1 2 3 4]).* [.8 .2 1 1.65],...
    'Menu','none','Name','Create a plot and click on an object',...
    'ResizeFcn',@reSize,...
    'WindowButtonDownFcn',@wbdf,...
    'Renderer','OpenGL');
```

Note that the figure also defines a resize function and a window button down function by assigning function handles to the `ResizeFcn` and `WindowButtonDownFcn` properties. The callback functions `reSize` and `wbdf` are defined as nested functions in the same file.

Calculating the ActiveX Object Container Size

The `actxcontrol` function creates the ActiveX control inside the specified figure and returns the control's handle. You need to supply the following information:

- Control's programmatic identifier (use `actxcontrollist` to find it)
- Location and size of the control container in the figure (pixels) [left bottom width height]
- Handle of the figure that contains the control:

```
conSize = calcSize; % Calculate the container size
hExp = actxcontrol('Shell.Explorer.2',conSize,hfig); % Create the control
Navigate(hExp,'http://www.mathworks.com/'); % Specify content of html viewer
```

The nested function, `calcSize` calculates the size of the object container based on the current size of the figure. `calcSize` is also used by the figure `resize` function, which is described in the next section.

```
function conSize = calcSize
fp = get(hfig,'Position'); % Get current figure size
conSize = [0 0 1 .45].*fp([3 4 3 4]); % Calculate container size
end % calcSize
```

Automatic Resize

In MATLAB, you can change the size of a figure and the axes automatically resize to fit the new size. This example implements similar resizing behavior for the ActiveX object container within the figure using the object's `move` method. This method enables you to change both size and location of the ActiveX object container (i.e., it is equivalent to setting the figure `Position` property).

When you resize the figure window, the MATLAB software automatically calls the function assigned to the figure's `ResizeFcn` property. This example implements the nested function `reSize` for the figure `reSize` function.

ResizeFcn at Figure Creation

The `reSize` function first determines if the ActiveX object exists because the MATLAB software calls the figure `reSize` function when the figure is first created. Since the ActiveX object has not been created at this point, the `reSize` function simply returns.

When the Figure Is Resized

When you change the size of the figure, the `reSize` function executes and does the following:

- Calls the `calcSize` function to calculate a new size for the control container based on the new figure size.
- Calls the control's `move` method to apply the new size to the control.

Figure `reSizeFcn`.

```
function reSize(~,~)
if ~exist('hExp','var')
    return
end
conSize = calcSize;
move(hExp,conSize);
end % reSize
```

Selecting Graphics Objects

This example uses the figure `WindowButtonDownFcn` property to define a callback function that handles mouse click events within the figure. When you click the left

mouse button while the cursor is over the figure, the MATLAB software executes the `WindowButtonDownFcn` callback on the mouse down event.

The callback determines which object was clicked by querying the figure `CurrentObject` property, which contains the handle of the graphics object most recently clicked. Once you have the object's handle, you can determine its type and then load the appropriate HTML page into the `Shell.Explorer` control.

The nested function `wbdf` implements the callback. Once it determines the type of the selected object, it uses the control `Navigate` method to display the documentation for the object type.

Figure `WindowButtonDownFcn`.

```
function wbdf(~,~)
    cobj = get(hfig,'CurrentObject');
    if isempty(cobj)
        disp('Click somewhere else')
        return
    end
    pth = 'http://www.mathworks.com/access/helpdesk/help/techdoc/ref/';
    typ = get(cobj,'Type');
    switch typ
        case ('figure')
            Navigate(hExp,[pth,'figure_props.html']);
        case ('axes')
            Navigate(hExp,[pth,'axes_props.html']);
        case ('line')
            Navigate(hExp,[pth,'line_props.html']);
        case ('image')
            Navigate(hExp,[pth,'image_props.html']);
        case ('patch')
            Navigate(hExp,[pth,'patch_props.html']);
        case ('surface')
            Navigate(hExp,[pth,'surface_props.html']);
        case ('text')
            Navigate(hExp,[pth,'text_props.html']);
        case ('hgroup')
            Navigate(hExp,[pth,'hgroupproperties.html']);
        otherwise
            Navigate(hExp,[pth(1:end-4),'infotool/hgprop/doc_frame.html']);
    end
end % wbdf
```

Add Grid ActiveX Control in a Figure

This example adds a Microsoft ActiveX spreadsheet control to a figure, which also contains an axes object for plotting the data displayed by the control. Clicking a column in the spreadsheet causes the data in that column to be plotted. Clicking down and dragging the mouse across multiple columns plots all columns touched.


Techniques Demonstrated

- Registering a control for use on your system.
- Writing a handler for one of the control's events and using the event to execute MATLAB plotting commands.
- Writing a `resize` function for the figure that manages the control's size as users resize the figure.

Using the Control

This example assumes that your data samples are organized in columns and that the first cell in each column is a title, which is used by the legend. See “Complete Code Listing” on page 11-16 for an example of how to load data into the control.

Once the data is loaded, click the column to plot the data. The following picture shows a graph of the results of `Test2` and `Test3` created by selecting column `B` and dragging and releasing on column `C`.



Complete Code Listing

You can open the file used to implement this example in MATLAB Editor:

- Open file in editor.

Preparing to Use the Control

The ActiveX control used in this example is typical of those downloadable from the Internet. Once you have downloaded the files you need, register the control on your system using the Windows command `regsvr32`. In a command prompt, enter a command of the following form:

```
regsvr32 sgrid.ocx
```


From the MATLAB command line, type:

```
system 'regsvr32 sgrid.ocx'
```

See the section “Registering Controls and Servers” on page 11-5 for more information.

Finding the Control's ProgID

Once you have installed and registered the control, you can obtain its programmatic identifier using the **ActiveX Control Selector** dialog. To display this dialog box, use the `actxcontrolselect` command. Locate the control in the list and the selector displays the control and the ProgID.



Creating a Figure to Contain the Control

This example creates a figure that contains an axes object and the grid control. The first step is to determine the size of the figure and then create the figure and axes. This example uses the default figure and axes size (obtained from the respective `Position` properties) to calculate a new size and location for each object.

```
dfpos = get(0,'DefaultFigurePosition');
dapos = get(0,'DefaultAxesPosition');
hfig = figure('Position',dfpos([1 2 3 4]).*[1 .8 1 1.25],...
    'Name','Select the columns to plot',...
    'Renderer','ZBuffer',...
    'ResizeFcn',{@reSize dfpos(3)});
hax = axes('Position',dapos([1 2 3 4]).*[1 4 1 .65]);
```

The above code moves the figure down from the top of the screen (multiply second element in position vector by `.8`) and increases the height of the figure (multiply fourth element in position vector by `1.25`). Axes are created and sized in a similar way.

Creating an Instance of the Control

Use the `actxcontrol` function to create an instance of the control in a figure window. This function creates a container for the control and enables you to specify the size of this container, which usually defines the size of the control. See “Managing Figure Resize” on page 11-21 for a specific example.

Specifying the Size and Location

The control size and location in the figure is calculated by a nested function `calcSize`. This function is used to calculate both the initial size of the control container and the size resulting from resize of the figure. It gets the figure's current position (i.e., size and location) and scales the four-element vector so that the control container is

- Positioned at the lower-left corner of the figure.
- Equal to the figure in width.
- Has a height that is `.35` times the figure's height.

The value returned is of the correct form to be passed to the `actxcontrol` function and the control's `move` method.

```
function conSize = calcSize
    fp = get(hfig,'Position');
    conSize = fp([3 4 3 4]).*[0 0 1 .35];
end % conSize
```

Creating the Control

Creating the control entails the following steps:

- Calculating the container size
- Instantiating the control in the figure
- Setting the number of rows and columns to match the size of the data array
- Specifying the width of the columns

```
conSize = calcSize;
```

```
hgrid = actxcontrol('SGRID.SgCtrl.1',conSize,hfig);  
hgrid.NRows = size(dat,1);  
hgrid.NColumns = size(dat,2);  
colwth = 4350; hdwth = hgrid.HdrWidth;  
SetColWidth(hgrid,0,sz(2)-1,colwth,1)
```

Using Mouse-Click Event to Plot Data

This example uses the control's `Click` event to implement interactive plotting. When a user clicks the control, the MATLAB software executes a function that plots the data in the column where the mouse click occurred. Users can also select multiple columns by clicking down and dragging the cursor over more than one column.

Registering the Event

You need to register events with MATLAB so that when the event occurs (a mouse click in this case), the MATLAB software responds by executing the event handler function. Register the event with the `registerevent` function:

```
registerevent(hgrid,{'Click',@click_event});
```

Pass the event name (`Click`) and a function handle for the event handler function inside a cell array.

Defining the Event Handler

The event handler function `click_event` uses the control's `GetSelection` method to determine what columns and rows have been selected by the mouse click. This function plots the data in the selected columns as lines, one line per column.

It is possible to click down on a column and drag the mouse to select multiple columns before releasing the mouse. In this case, each column is plotted because the event is not fired until the mouse button is released (which reflects the way the author chose to implement the control). The `legend` function uses the column number stored in the variable `cols` to label the individual plotted lines. You must add one to `cols` because the control counts the columns starting from zero.

Note that you implement event handlers to accept a variable number of arguments (`varargin`).

```
function click_event(varargin)  
[row1,col1,row2,col2] = hgrid.GetSelection(1,1,1,1,1);
```

```

ncols = (col2-col1)+1;
cols = [col1:col2];
for n = 1:ncols
    hgrid.Col = cols(n);
    for ii = 1:sz(1)
        hgrid.Row = ii;
        plot_data(ii,n) = hgrid.Number;
    end
end
hgrid.SetSelection(row1,col1,row2,col2);
plot(plot_data)
legend(labels(cols+1))
end % click_event

```

Managing Figure Resize

The size and location of a MATLAB axes object is defined in units that are normalized to the figure that contains it. Therefore, when you resize the figure, the axes automatically resize proportionally. When a figure contains objects that are not contained in axes, you are responsible for defining a function that manages the resizing process.

The figure `ResizeFcn` property references a function that executes whenever the figure is resized and also when the figure is first created. This example creates a resize function that manages resizing grid control by doing the following:

- Disables control updates while changes are being made to improve performance (use the `hDisplay` property).
- Calculates a new size for the control container based on the new figure size (`calcSize` function).
- Applies the new size to the control container using its `move` method.
- Scales the column widths of the grid proportional to the change in width of the figure (`SetColWidth` method).
- Refreshes the display of the control, showing the new size.

```

function reSize(src,evnt,dfp)
% Return if control does not exist (figure creation)
if ~exist('hgrid','var')
    return
end
% Resize container
hgrid.bDisplay = 0;

```

```
conSize = calcSize;
move(hgrid,conSize);
% Resize columns
scl = conSize(3)/dfp;
ncolwth = scl*colwth;
nhdrwth = hdwth*(scl);
hgrid.HdrWidth = nhdrwth;
SetColWidth(hgrid,0,sz(2)-1,ncolwth,2)
hgrid.Refresh;
end % reSize
```

Closing the Figure

This example uses the figure delete function (`DeleteFcn` property) to delete the ActiveX object before closing the figure. The MATLAB software calls the figure delete function before deleting the figure, which enables the function to perform any clean up needed before closing the figure. The figure delete function calls the control's `delete` method.

```
function figDelete(src,evnt)
    delete(hgrid);
end
```

Read Excel Spreadsheet Data

This example creates a user interface to access the data in a Microsoft Excel file. To enable the communication between the MATLAB software and the spreadsheet program, this example creates an Microsoft ActiveX object in an Automation server running an Excel application. The MATLAB software then accesses the data in the spreadsheet through the interfaces provided by the Excel Automation server.

Techniques Demonstrated

This example shows how to use the following techniques:


- Use of an Automation server to access another application from the MATLAB software.
- Ways to manipulate Excel data into types used in the UI and plotting.
- Implementing a UI that enables plotting of selected columns of the Excel spreadsheet.
- Inserting a MATLAB figure into an Excel file.

Using the UI

To use the UI, select any items in the list box and click the **Create Plot** button. The sample data provided with this example contain three input and three associated response data sets, all of which are plotted versus the first column in the Excel file, which is the time data.

You can view the Excel data file by clicking the **Show Excel Data File** button, and you can save an image of the graph in a different Excel file by clicking **Save Graph** button. Note that the **Save Graph** option creates a temporary PNG file in the current folder, if you have write-access permission.

The following picture shows the UI with an input/response pair selected in the list box and plotted in the axes.



Complete Code Listing

You can open the file used to implement this example in MATLAB Editor or run this example:

- Open file in editor.
- Run this example.

Excel Spreadsheet Format

This example assumes a particular organization of the Excel spreadsheet, as shown in the following picture.

	A	B	C	D	E	F	G
1	Time	InputAil	InputEle	InputRud	RespAil	RespEle	RespRud
2	0	0.00E+00	2.8827	-0.0004868	0	0	0
3	0	0.00E+00	2.8827	-0.0004868	0	0	0
4	0	0.00E+00	2.8827	-0.0004868	0	0	0
5	0.00E+00	0.00E+00	2.8827	-0.0004868	0	0.00E+00	0.00E+00
6	0.00E+00	0.00E+00	2.8827	-0.0004868	0.00E+00	0.00E+00	0.00E+00
7	0.00E+00	0.00E+00	2.8828	-0.0004868	0.00E+00	0.00E+00	0.00E+00
8	0.00E+00	0.00E+00	2.8832	-0.0004868	0.00E+00	0.00E+00	0.00E+00
9	0.00E+00	0.00E+00	2.8853	-0.0004873	0.00E+00	0.00E+00	0.00E+00
10	0.000141	0.00E+00	2.8955	-0.0004995	0.00E+00	0.00E+00	0.00E+00
11	0.000358	0	2.9154	-0.0005692	0.00E+00	0.00035612	0.00E+00
12	0.000358	0	2.9154	-0.0005692	0.00E+00	0.00035612	0.00E+00
13	0.000358	0	2.9154	-0.0005692	0.00E+00	0.00035612	0.00E+00
14	0.000876	0.00E+00	2.9628	-0.0009769	0	0.0021199	0.00E+00
15	0.000876	0.00E+00	2.9628	-0.0009769	0	0.0021199	0.00E+00
16	0.000876	0.00E+00	2.9628	-0.0009769	0	0.0021199	0.00E+00
17	0.000876	0.00E+00	2.9628	-0.0009769	0	0.0021199	0.00E+00
18	0.000876	0.00E+00	2.9628	-0.0009769	0	0.0021199	0.00E+00

The format of the Excel file is as follows:

- The first element in each column is a text string that identifies the data contain in the column. These strings are extracted and used to populate the list box.
- The first column (Time) is used for the x -axis of all plots of the remaining data.
- All rows in each column are read into the MATLAB software.

Excel Automation Server

The first step in accessing the spreadsheet data from the MATLAB software is to run the Excel application in an Automation server process using the `actxserver` function and the program ID, `excel.application`.

```
exl = actxserver('excel.application');
```

The ActiveX object that is returned provides access to a number of interfaces supported by the Excel program. Use the `workbook` interface to open the Excel file containing the data.

```
exlWkbk = exl.Workbooks;
```

```
exlFile = exlWkbk.Open([docroot ' /techdoc/matlab_external/examples/input_resp_data.xls']);
```

Use the workbook's sheet interface to access the data from a range object, which stores a reference to a range of data from the specified sheet. This example accesses all the data in column A, first cell to column G, last cell:

```
exlSheet1 = exlFile.Sheets.Item('Sheet1');  
robj = exlSheet1.Columns.End(4); % Find the end of the column  
numrows = robj.row; % And determine what row it is  
dat_range = ['A1:G' num2str(numrows)]; % Read to the last row  
rngObj = exlSheet1.Range(dat_range);
```

At this point, the entire data set from the Excel file's `sheet1` is accessed via the range object interface. This object returns the data in a MATLAB cell array, which can contain both numeric and character data:

```
exlData = rngObj.Value;
```

Manipulating the Data in the MATLAB Workspace

Now that the data is in a cell array, you can use MATLAB functions to extract and reshape parts of the data into the forms needed to use in the UI and pass to the plot function.

The following code performs two operations:

- Extracts numeric data from the cell array (indexing with curly braces), concatenates the individual doubles returned by the indexing operation (square brackets), and reshapes it into an array that arranges the data in columns.
- Extracts the string in the first cell in each column of an Excel sheet and stores them in a cell array, which is used to generate the items in the list box.

```
for ii = 1:size(exlData,2)  
    matData(:,ii) = reshape([exlData{2:end,ii}],size(exlData(2:end,ii)));  
    listBox{ii} = [exlData{1,ii}];  
end
```

The Plotter UI

This example uses a UI that enables you to select from a list of input and response data from a list box. All data is plotted as a function of time (which is, therefore, not a choice in the list box) and you can continue to add more data to the graph. Each data plot added to the graph causes the legend to expand.

Additional implementation details include:

- A legend that updates as you add data to a graph
- A clear button that enables you to clear all graphs from the axes
- A save button that saves the graph as a PNG file and adds it to another Excel file
- A toggle button that shows or hides the Excel file being accessed
- The figure delete function (**DeleteFcn** property), which the MATLAB software calls when the figure is closed, is used to terminate the Automation server process.

Selecting and Plotting Data

When you click the **Create Plot** button, its callback function queries the list box to determine what items are selected and plots each data versus time. The legend is updated to display any new data while maintaining the legend for the existing data.

```
function plotButtonCallback(src,evnt)
iSelected = get(listBox,'Value');
grid(a,'on');hold all
for p = 1:length(iSelected)
    switch iSelected(p)
        case 1
            plot(a,tme,matData(:,2))
        case 2
            plot(a,tme,matData(:,3))
        case 3
            plot(a,tme,matData(:,4))
        case 4
            plot(a,tme,matData(:,5))
        case 5
            plot(a,tme,matData(:,6))
        case 6
            plot(a,tme,matData(:,7))
        otherwise
            disp('Select data to plot')
    end
end
end
[b,c,g,lbs] = legend([lbs lBoxList(iSelected+1)]);
end % plotButtonCallback
```

Clearing the Axes

The plotter is designed to continually add graphs as the user selects data from the list box. The **Clear Graph** button clears and resets the axes and clears the variable used to store the labels of the plot data (used by legend).

```
%% Callback for clear button
function clearButtonCallback(src,evt)
    cla(a,'reset')
    lbs = '';
end % clearButtonCallback
```

Display or Hide Excel File

The MATLAB program has access to the properties of the Excel application running in the Automation server. By setting the **Visible** property to 1 or 0, this callback controls the visibility of the Excel file.

```
%% Display or hide Excel file
function dispButtonCallback(src,evt)
    exl.visible = get(src,'Value');
end % dispButtonCallback
```

Close Figure and Terminate Excel Automation Process

Since the Excel Automation server runs in a separate process from the MATLAB software, you must terminate this process explicitly. There is no reason to keep this process running after the UI has been closed, so this example uses the figure's delete function to terminate the Excel process with the **Quit** method. Also, terminate the second Excel process used for saving the graph. See “Inserting MATLAB Graphs Into Excel Spreadsheets” on page 11-28 for information on this second process.

```
%% Terminate Excel processes
function deleteFig(src,evt)
    exlWkbk.Close
    exlWkbk2.Close
    exl.Quit
    exl2.Quit
end % deleteFig
```

Inserting MATLAB Graphs Into Excel Spreadsheets

You can save the graph created with this UI in an Excel file. (This example uses a separate Excel Automation server process for this purpose.) The callback for the **Save Graph** push button creates the image and adds it to an Excel file:

- Both the axes and legend are copied to an invisible figure configured to print the graph as you see it on the screen (figure **PaperPositionMode** property is set to **auto**).

- The `print` command creates the PNG image.
- Use the `Shapes` interface to insert the image in the Excel workbook.

The server and interfaces are instanced during UI initialization phase:

```
exl2 = actxserver('excel.application');
exlWkbk2 = exl2.Workbooks;
wb = invoke(exlWkbk2, 'Add');
graphSheet = invoke(wb.Sheets, 'Add');
Shapes = graphSheet.Shapes;
```

The following code implements the **Save Graph** button callback:

```
function saveButtonCallback(src, evt)
    tempfig = figure('Visible', 'off', 'PaperPositionMode', 'auto');
    tempfigfile = [tempname '.png'];
    ah = findobj(f, 'type', 'axes');
    copyobj(ah, tempfig) % Copy both graph axes and legend axes
    print(tempfig, '-dpng', tempfigfile);
    Shapes.AddPicture(tempfigfile, 0, 1, 50, 18, 300, 235);
    exl2.visible = 1;
end
```

Supported Client/Server Configurations

In this section...

“Introduction” on page 11-30

“MATLAB Client and In-Process Server” on page 11-30

“MATLAB Client and Out-of-Process Server” on page 11-31

“COM Implementations Supported by MATLAB Software” on page 11-32

“Client Application and MATLAB Automation Server” on page 11-32


“Client Application and MATLAB Engine Server” on page 11-33

Introduction

You can configure MATLAB software to either control or be controlled by other COM components. When MATLAB controls another component, MATLAB is the client, and the other component is the server. When another component controls MATLAB, MATLAB is the server.

MATLAB Client and In-Process Server

The following diagram shows how the MATLAB client interacts with an “In-Process Server” on page 13-5.



The server exposes its properties and methods through the IDispatch (Automation) interface or a Custom interface, depending on which interfaces the component implements. For information on accessing interfaces, see “Getting Interfaces to COM Object” on page 12-54 .

Microsoft ActiveX Controls

An ActiveX control is an object with a user interface. When the MATLAB software constructs an ActiveX control, it places the control's UI in a MATLAB figure window.

Click the various options available in the user interface (e.g., making a particular menu selection) to trigger *events* that get communicated from the control in the server to the client MATLAB application. The client decides what to do about each event and responds accordingly.

MATLAB comes with a sample ActiveX control called `mwsamp`. This control draws a circle on the screen and displays some text. You can use this control to try out MATLAB COM features. For more information, see “MATLAB Sample Control” on page 12-68.

DLL Servers

Any COM component that has been implemented as a dynamic link library (DLL) is also instantiated in an in-process server. That is, it is created in the same process as the MATLAB client application. When MATLAB uses a DLL server, it runs in a separate window rather than a MATLAB figure window.


MATLAB responds to events generated by a DLL server in the same way as events from an ActiveX control.

For More Information

To learn more about working with MATLAB as a client, see “Creating COM Objects” on page 12-2.

MATLAB Client and Out-of-Process Server

In this configuration, a MATLAB client application interacts with a component that has been implemented as a “Local Out-of-Process Server” on page 13-5. Examples of out-of-process servers are Microsoft Excel and Microsoft Word programs.



As with in-process servers, this server exposes its properties and methods through the IDispatch (Automation) interface or a Custom interface, depending on which interfaces the component implements. For information on accessing interfaces, see “Getting Interfaces to COM Object” on page 12-54.

Since the client and server run in separate processes, you have the option of creating the server on any system on the same network as the client.

If the component provides a user interface, its window is separate from the client application.

MATLAB responds to events generated by an out-of-process server in the same way as events from an ActiveX control.

For More Information


To learn more about working with MATLAB as a client, see “Creating COM Objects” on page 12-2.

COM Implementations Supported by MATLAB Software

MATLAB only supports COM implementations that are compatible with the Microsoft Active Template Library (ATL) API. In general, your COM object should be able to be contained in an ATL host window in order to work with MATLAB.

Client Application and MATLAB Automation Server

MATLAB operates as the Automation server in this configuration. It can be created and controlled by any Microsoft Windows program that can be an *Automation controller*. Some examples of Automation controllers are Microsoft Excel, Microsoft Access™, Microsoft Project, and many Microsoft Visual Basic and Microsoft Visual C++ programs.



MATLAB Automation server capabilities include the ability to execute commands in the MATLAB workspace, and to get and put matrices directly from and into the workspace. You can start a MATLAB server to run in either a shared or dedicated mode. You also have the option of running it on a local or remote system.

To create the MATLAB server from an external application program, use the appropriate function from that language to instantiate the server. (For example,

use the Visual Basic `CreateObject` function.) For the programmatic identifier, specify `matlab.application`. To run MATLAB as a dedicated server, use the `matlab.application.single` programmatic identifier. See “Shared and Dedicated Servers” on page 13-4 for more information.

The function that creates the MATLAB server also returns a handle to the properties and methods available in the server through the `IDispatch` interface.


Note: Because VBScript client programs require an Automation interface to communicate with servers, this is the only configuration that supports a VBScript client.

For More Information

To learn more about working with Automation servers, see “MATLAB COM Automation Server Interface” on page 13-4.

Client Application and MATLAB Engine Server

MATLAB provides a faster custom interface called `IEngine` for client applications written in C, C++, or Fortran. MATLAB uses `IEngine` to communicate between the client application and the MATLAB engine running as a COM server.



Use the MATLAB Engine API functions to start and end the server process, and to send commands to be processed by MATLAB.

For More Information

To learn more about the MATLAB engine and the functions provided in its C/C++ and Fortran API Reference libraries, see “MATLAB Engine API for C, C++, and Fortran”.

MATLAB COM Client Support

- “Creating COM Objects” on page 12-2
- “Explore COM Objects” on page 12-11
- “Use Object Properties” on page 12-17
- “Use Methods” on page 12-26
- “Use Events” on page 12-38
- “Getting Interfaces to COM Object” on page 12-54
- “Save COM Objects” on page 12-57
- “Handling COM Data in MATLAB Software” on page 12-59
- “Use MATLAB Application as Automation Client” on page 12-68
- “Deploy ActiveX Controls Requiring Run-Time Licenses” on page 12-72
- “Use Microsoft Forms 2.0 Controls” on page 12-74
- “Use COM Collections” on page 12-76
- “Use MATLAB Application as DCOM Client” on page 12-77
- “MATLAB COM Support Limitations” on page 12-78

Creating COM Objects


In this section...
“Creating the Server Process — An Overview” on page 12-2
“Creating an ActiveX Control” on page 12-3
“Creating a COM Server” on page 12-9

Creating the Server Process — An Overview

MATLAB software provides two functions to create a COM object:

- `actxcontrol` — Creates a Microsoft ActiveX control in a MATLAB figure window.
- `actxserver` — Creates an in-process server for a dynamic link library (DLL) component or an out-of-process server for an executable (EXE) component.

The following diagram shows the basic steps in creating the server process. For more information on how the MATLAB software establishes interfaces to the resultant COM object, see “Getting Interfaces to COM Object” on page 12-54.



Creating an ActiveX Control

You can create an instance of an ActiveX control from the MATLAB client using either a user interface (`actxcontrolselect`) or the `actxcontrol` function from the command line. Either of these methods creates an instance of the control in the MATLAB client process and returns a handle to the primary interface to the COM object. Through this interface, you can access the object's public properties or methods. You can also establish more interfaces to the object, including interfaces that use `IDispatch`, and any custom interfaces that might exist.

This section describes how to create an instance of the control and how to position it in the MATLAB figure window.

- “Listing Installed Controls” on page 12-4
- “Finding a Particular Control” on page 12-4
- “Creating Control Objects Using a UI” on page 12-5
- “Creating Control Objects from the Command Line” on page 12-8
- “Repositioning the Control in a Figure Window” on page 12-8
- “Limitations to ActiveX Support” on page 12-8

Listing Installed Controls

The `actxcontrollist` function shows you what COM controls are currently installed on your system. Type:

```
list = actxcontrollist
```

MATLAB displays a cell array listing each control, including its name, programmatic identifier (ProgID), and file name.

This example shows information for several controls (your results might be different):

```
list = actxcontrollist;  
s=sprintf(' Name = %s\n ProgID = %s\n File = %s\n', list{114:115,:})
```

MATLAB displays:

```
s =  
Name = OleInstall Class  
ProgID = Outlook Express Mime Editor  
File = OlePrn.OleInstall.1  
Name = OutlookExpress.MimeEdit.1  
ProgID = C:\WINNT\System32\oleprn.dll  
File = C:\WINNT\System32\inetcomm.dll
```

Finding a Particular Control

If you know the name of a control, you can find it in the list and display its ProgID and the path of the folder containing it. For example, some of the examples in this documentation use the `Mwsamp2` control. You can find it with the following code:

```
list = actxcontrollist;
```

```
for ii = 1:length(list)
    if ~isempty(strfind([list{ii,:}], 'Mwsamp2'))
        s = sprintf(' Name = %s\n ProgID = %s\n File = %s\n', ...
                    list{ii,:})
    end
end
```

MATLAB displays:

```
s =
  Name = Mwsamp2 Control
  ProgID = MWSAMP.MwsampCtrl.2
  File =
  D:\Apps\MATLAB\R2006a\toolbox\matlab\winfun\win32\mwsamp2.ocx
```


The location of this file might be different on your system.

Creating Control Objects Using a UI

Using the `actxcontrolselect` function is the simplest way to create an instance of a control object. This function displays all controls installed on your system. When you select an item from the list and click the **Create** button, MATLAB creates the control and returns a handle to it. Type:

```
h = actxcontrolselect
```

MATLAB displays the **Select an ActiveX Control** dialog box.



The interface has an **ActiveX Control List** selection pane on the left and a **Preview** pane on the right. To see a preview of the control, click one of the control names in the selection pane. (A blank preview pane means that the control does not have a preview.) An error message appears in the preview pane if MATLAB cannot create the instance.

Setting Properties with `actxcontrolselect`

To change property values when creating the control, click the **Properties** button in the **Preview** pane. You can select which figure window to put the control in (**Parent** field), where to position it in the window (**X** and **Y** fields), and what size to make the control (**Width** and **Height**).

You can register events you want the control to respond to in this window. (For an explanation of event registration, see “Responding to Events — an Overview” on page 12-39.) Register an event and the callback routine to handle that event by entering the name of the routine to the right of the event under **Event Handler**.

You can select callback routines by clicking a name in the **Event** column, and then clicking the **Browse** button. To assign a callback routine to more than one event, first press the **Ctrl** key and click individual event names, or drag the mouse over consecutive event names, and then click **Browse** to select the callback routine.

MATLAB only responds to registered events, so if you do not specify a callback, the event is ignored.

For example, in the **ActiveX Control List** pane, select **Calendar Control 10.0** (the version on your system might be different) and click **Properties**. MATLAB displays the Choose ActiveX Control Creation Parameter dialog box. To change the default size for the control, enter a **Width** of 500 and a **Height** of 350. Click **OK** in this window, and click **Create** in the next window to create an instance of the Calendar control.

You can also set control parameters using the `actxcontrol` function. One parameter you can set with `actxcontrol`, but not with `actxcontrolselect`, is the name of an initialization file. When you specify this file name, MATLAB sets the initial state of the control to that of a previously saved control.

Information Returned by `actxcontrolselect`

The `actxcontrolselect` function creates an object that is an instance of the MATLAB COM class. The function returns up to two arguments: a handle for the object, `h`, and a 1-by-3 cell array, `info`, containing information about the control. To get this information, type:

```
[h, info] = actxcontrolselect
```

The cell array `info` shows the name, ProgID, and file name for the control.

If you select the Calendar Control, and then click **Create**, MATLAB displays information like:

```
h =
    COM.mscal.calendar.7
info =
    [1x20 char]    'MSCAL.Calendar.7'    [1x41 char]
```

To expand the `info` cell array, type:

```
info{:}
```

MATLAB displays:

```
ans =  
    Calendar Control 9.0  
ans =  
    MSCAL.Calendar.7  
ans =  
    D:\Applications\MSOffice\Office\MSCAL.OCX
```

Creating Control Objects from the Command Line

If you already know which control you want and you know its ProgID, use the `actxcontrol` function to create an instance of the control.

The ProgID is the only required input to this function. However, as with `actxcontrolselect`, you can supply more inputs that enable you to select which figure window to put the control in, where to position it in the window, and what size to make it. You can also register any events you want the control to respond to, or set the initial state of the control by reading that state from a file. See the `actxcontrol` reference page for a full explanation of its input arguments.

The `actxcontrol` function returns a handle to the primary interface to the object. Use this handle to reference the object in other COM function calls. You can also use the handle to obtain more interfaces to the object. For more information on using interfaces, see “Getting Interfaces to COM Object” on page 12-54.

Repositioning the Control in a Figure Window

After creating a control, you can change its shape and position in the window with the `move` function.

Observe what happens to the object created in the last section when you specify new origin coordinates (70, 120) and new width and height dimensions of 400 and 350:

```
move(h,[70 120 400 350]);
```

Limitations to ActiveX Support

A MATLAB COM ActiveX control container does not in-place activate controls until they are visible.

Creating a COM Server

Instantiating a DLL Component

To create a server for a component implemented as a dynamic link library (DLL), use the `actxserver` function. MATLAB creates an instance of the component in the same process that contains the client application.

The syntax for `actxserver`, when used with a DLL component, is `actxserver(ProgID)`, where `ProgID` is the programmatic identifier for the component.

`actxserver` returns a handle to the primary interface to the object. Use this handle to reference the object in other COM function calls. You can also use the handle to obtain more interfaces to the object. For more information on using interfaces, see “Getting Interfaces to COM Object” on page 12-54.

Unlike Microsoft ActiveX controls, any user interface displayed by the server appears in a separate window.

You cannot use a 32-bit in-process DLL COM object in a 64-bit MATLAB application. For information about this restriction, see <http://www.mathworks.com/matlabcentral/answers/95116-why-am-i-not-able-to-use-32-bit-dll-com-objects-in-64-bit-matlab-7-3-r2006b>.

Instantiating an EXE Component

You can use the `actxserver` function to create a server for a component implemented as an executable (EXE). In this case, MATLAB instantiates the component in an out-of-process server.

The syntax for `actxserver`, when used to create an executable, is `actxserver(ProgID, sysname)`, where `ProgID` is the programmatic identifier for the component, and `sysname` is an optional argument used in configuring a distributed COM (DCOM) system.

`actxserver` returns a handle to the primary interface to the COM object. Use this handle to reference the object in other COM function calls. You can also use the handle to obtain more interfaces to the object. For more information on using interfaces, see “Getting Interfaces to COM Object” on page 12-54.

Any user interface displayed by the server appears in a separate window.

This example creates a COM server application running the Microsoft Excel spreadsheet program. The handle is assigned to `h`.

```
h = actxserver('Excel.Application')
```

MATLAB displays:

```
h =  
    COM.excel.application
```

MATLAB can programmatically connect to an instance of a COM Automation server application that is already running on your computer. To get a reference to such an application, use the `actxGetRunningServer` function.

This example gets a reference to the Excel program, which must already be running on your system. The returned handle is assigned to `h`.

```
h = actxGetRunningServer('Excel.Application')
```

MATLAB displays:

```
h =  
    COM.excel.application
```

Explore COM Objects

In this section...

“About Your Object” on page 12-11

“Exploring Properties” on page 12-11

“Exploring Methods” on page 12-12

“Exploring Events” on page 12-13

“Exploring Interfaces” on page 12-14

“Identifying Objects and Interfaces” on page 12-15

About Your Object

A COM object has properties, methods, events, and interfaces. Your vendor documentation describes these features, but you can also learn about your object using MATLAB commands.

Exploring Properties

A *property* is information that is associated with a COM object. This topic shows you how to look at the properties of your object. For detailed information on reading and setting property values, see “Use Object Properties” on page 12-17.

To see a list of all properties of an object, you can use the COM `get` function or the Property Inspector, a user interface provided by MATLAB to display and modify properties.

In this section, we explore a Microsoft Excel object. To begin, create the object `myApp`:

```
myApp = actxserver('Excel.Application');
```

Listing Properties

The `get` function lists all properties. For example, from the MATLAB command prompt, type:

```
get(myApp)
```

MATLAB displays information like the following:

```
Application: [1x1 Interface.Microsoft_Excel_9.0_
Object_Library._Application]
  Creator: 'xlCreatorCode'
  Parent: [1x1 Interface.Microsoft_Excel_9.0_
Object_Library._Application]
  ActiveCell: []
  ActiveChart: [1x50 char]
  :
OperatingSystem: 'Windows (32-bit) NT 5.01'
OrganizationName: 'The MathWorks'
  :
```

One property is `OrganizationName`; its value in this example is `The MathWorks`.

Using the Property Inspector

The Property Inspector opens a new window showing the object's properties. This topic explains how to open it. For detailed information, see “Using the Property Inspector” on page 12-20.

You can open the Property Inspector using either of these methods:

- Call the `inspect` function from the MATLAB command line.
- Double-click the object in the MATLAB Workspace browser.

For example, type:

```
inspect(myApp)
```

The Inspector window opens. Scroll down until you see the `OrganizationName` property. It should be the same value the `get` function returned; in this case, `The MathWorks`.

Exploring Methods

A *method* is a procedure you call to perform a specific action on the COM object. This topic shows you how to identify methods belonging to your object. For detailed information, see “Use Methods” on page 12-26.

To see a list of all methods supported by the Excel object, type:

```
methodsvew(myApp)
```

MATLAB opens a window showing the method signatures for `COM.Excel_Application` objects. For detailed information about Excel objects, see documentation on the MSDN website. The documentation for Microsoft Office 2010 is at [Excel Object Model Reference](#).

Exploring Events

An *event* is typically a user-initiated action that takes place in a server application, which often requires a reaction from the client. For example, a user clicking the mouse at a particular location in a server interface window might require the client to take some action in response. When an event is *fired*, the server communicates this occurrence to the client. If the client is *listening* for this particular type of event, it responds by executing a routine called an *event handler*.

This topic shows you how to identify events available to your object. For detailed information, see “Use Events” on page 12-38. For information on event handlers, see “Writing Event Handlers” on page 12-49.

Use the `events` function to list all events known to the control or server and use the `eventlisteners` function to list only registered events.

In this section, we use the Microsoft Internet Explorer Web browser. To begin, create the object `myNet`:

```
myNet = actxserver('internetexplorer.application');
```

Listing Server Events

Type:

```
events(myNet)
```

MATLAB displays event information like:

```

:
StatusTextChange = void StatusTextChange(string Text)
ProgressChange = void ProgressChange(int32 Progress,int32 ProgressMax)
CommandStateChange = void CommandStateChange(int32 Command,bool Enable)
:

```

Listing Registered Events

No events are registered now.

```
eventlisteners(myNet)
```

```
ans =  
    {}
```

Exploring Interfaces

An *interface* is a set of related functions used to access a COM object's data. When you create a COM object using the `actxserver` or `actxcontrol` functions, MATLAB returns a handle to an interface. You use the `get` and `interfaces` functions to see other interfaces implemented by your object.

In this section, we explore an Excel object. To begin, create the object `e`:

```
e = actxserver('Excel.Application');
```

Additional Interfaces

Components often provide more interfaces, based on `IDispatch`. To see these interfaces, type:

```
get(e)
```

MATLAB displays information like:

```
Application: [1x1 Interface.Microsoft_Excel_11.0_Object_Library._Application]  
    Creator: 'xlCreatorCode'  
    Parent: [1x1 Interface.Microsoft_Excel_11.0_Object_Library._Application]  
    ActiveCell: []  
    ActiveChart: [1x50 char]  
    :  
    Workbooks: [1x1 Interface.Microsoft_Excel_11.0_Object_Library.Workbooks]  
    :
```

In this example, `Workbooks` is an interface. To explore the `Workbooks` interface, type:

```
w = e.Workbooks;
```

To see its properties, type:

```
get(w)
```

```
Application: [1x1 Interface.Microsoft_Excel_11.0_Object_Library._Application]  
    Creator: 'xlCreatorCode'  
    Parent: [1x1 Interface.Microsoft_Excel_11.0_Object_Library._Application]  
    Count: 0
```

To see its methods, type:

`invoke(w)`

```
Add = handle Add(handle, Variant(Optional))
Close = void Close(handle)
Item = handle Item(handle, Variant)
Open = handle Open(handle, string, Variant(Optional))
OpenText = void OpenText(handle, string, Variant(Optional))
OpenDatabase = handle OpenDatabase(handle, string, Variant(Optional))
CheckOut = void CheckOut(handle, string)
CanCheckOut = bool CanCheckOut(handle, string)
OpenXML = handle OpenXML(handle, string, Variant(Optional))
```

Identifying Objects and Interfaces

You can get more information about a control or server using the following functions.

Function	Description
<code>class</code>	Return the class of an object
<code>isa</code>	Determine if an object is of a given MATLAB class
<code>iscom</code>	Determine if the input is a COM or ActiveX object
<code>isevent</code>	Determine if an item is an event of a COM object
<code>ismethod</code>	Determine if an item is a method of a COM object
<code>isprop</code>	Determine if an item is a property of a COM object
<code>isinterface</code>	Determine if the input is a COM interface

This example creates a COM object in an Automation server running the Excel application, giving it the handle `e`, and a `Workbooks` interface to the object, with handle `w`.

```
e = actxserver('Excel.Application');
w = e.Workbooks;
```

To see if `e` is a handle to a COM object, type:

```
iscom(e)

ans =
     1
```

To test `e` against a known class name, type:

```
isa(e, 'COM.excel_application')
```

```
ans =  
    1
```

To see if `w` is a handle to a COM interface, type:

```
isinterface(w)
```

```
ans =  
    1
```

To find out the class of variable `w`, type:

```
class(w)
```

```
ans =  
    Interface.Microsoft_Excel_11.0_Object_Library.Workbooks
```

To see if `UsableWidth` is a property of `e`, type:

```
isprop(e, 'UsableWidth')
```

```
ans =  
    1
```

To see if `SaveWorkspace` is a method of `e`, type:

```
ismethod(e, 'SaveWorkspace')
```

```
ans =  
    1
```

See Also

[eventlisteners](#) | [events](#) | [get](#) | [inspect](#) | [interfaces](#)

Use Object Properties

In this section...

“About Object Properties” on page 12-17
 “Working with Multiple Objects” on page 12-17
 “Using Enumerated Values for Properties” on page 12-18
 “Using the Property Inspector” on page 12-20
 “Custom Properties” on page 12-21
 “Properties That Take Arguments” on page 12-22

About Object Properties

You can get the value of a property, and, in some cases, change the value. You also can add custom properties. This topic explains how to do these tasks. If you only want to view your object's properties, see “Exploring Properties” on page 12-11 for basic information.

Property names are not case-sensitive. You can abbreviate them as long as the name is unambiguous.

To work with the properties of a COM object, use these MATLAB functions.

Function	Description
<code>addproperty</code>	Add a custom property to a COM object
<code>deleteproperty</code>	Remove a custom property from a COM object
<code>get</code>	List one or more properties and their values
<code>inspect</code>	Display graphical interface to list and modify property values
<code>isprop</code>	Determine if an item is a property of a COM object
<code>propedit</code>	Display the control's built-in property page
<code>set</code>	Set the value of one or more properties

Working with Multiple Objects

You can use the `get` and `set` functions on more than one object at a time by creating a vector of object handles and using these commands on the vector.

Note: To get or set values for multiple objects, use the `get` and `set` functions explicitly. You can only use dot syntax, for example `H.Day`, on scalar objects.

Using Enumerated Values for Properties

Enumeration makes examining and changing properties easier because each possible value for the property is given a string to represent it. For example, one of the values for the `DefaultSaveFormat` property in a Microsoft Excel spreadsheet is `xlUnicodeText`. This is easier to remember than a numeric value like `57`.

This section covers the following topics:

- “Finding All Enumerated Properties” on page 12-18
- “Setting Enumerated Values” on page 12-19
- “Setting Enumerated Values with the Property Inspector” on page 12-20

Finding All Enumerated Properties

The `get` and `set` functions support enumerated values for properties for those applications that provide them. To see which properties use enumerated types, use the `set` function.

For example, create an instance of an Excel spreadsheet:

```
h = actxserver('Excel.Application');
```

Type:

```
set(h)
```

MATLAB displays:

```
ans =  
      Creator: {'xlCreatorCode'}  
  ConstrainNumeric: {}  
 CopyObjectsWithCells: {}  
      Cursor: {4x1 cell}  
  CutCopyMode: {2x1 cell}  
      .  
      .
```

MATLAB displays the properties that accept enumerated types as nonempty cell arrays. In this example, `Cursor` and `CutCopyMode` accept a choice of settings. Properties

for which there is only one possible setting are displayed as a one-row cell array (see `Creator`, above).

Use the `get` function to display the current values of these properties. Type:

```
get(h)
```

MATLAB displays information such as:

```

        Creator: 'xlCreatorCode'
    ConstrainNumeric: 0
    CopyObjectsWithCells: 1
        Cursor: 'xlDefault'
    CutCopyMode: ''
           :
           .

```

Setting Enumerated Values

To list all possible enumerated values for a specific property, use `set` with the property name argument. The output is a cell array of strings, one string for each possible setting of the specified property:

```

set(h, 'Cursor')
ans =
    'xlIBeam'
    'xlDefault'
    'xlNorthwestArrow'
    'xlWait'

```

To set the value of a property, assign the enumerated value to the property name:

```
handle.property = 'enumeratedvalue';
```

You can also use the `set` function with the property name and enumerated value:

```
set(handle, 'property', 'enumeratedvalue');
```

You have a choice of using the enumeration or its equivalent numeric value. You can abbreviate the enumeration string, as in the third line of the following example, as long as you use enough letters in the string to make it unambiguous. Enumeration strings are not case-sensitive.

Make the Excel spreadsheet window visible, and then change the cursor from the MATLAB client. To see how the cursor has changed, click the spreadsheet window.

Either of the following assignments to `h.Cursor` sets the cursor to the `Wait` (hourglass) type:

```
h.Visible = 1;

h.Cursor = 'xlWait'
h.Cursor = 'xlw'           % Abbreviated form of xlWait
```

Read the value of the `Cursor` property you have set:

```
h.Cursor
ans =
    xlWait
```

Setting Enumerated Values with the Property Inspector

You can also set enumerated values using the Property Inspector. To learn how to use this feature, see “Using the Property Inspector on Enumerated Values” on page 12-21.

Using the Property Inspector

The Property Inspector enables you to access the properties of COM objects. To open the Property Inspector, use the `inspect` function from the MATLAB command line or double-click the object in the MATLAB Workspace browser.

For example, create a server object running the Excel program. Then set the object's `DefaultFilePath` property to `C:\ExcelWork`:

```
h = actxserver('Excel.Application');
h.DefaultFilePath = 'C:\ExcelWork';
```

Next call the `inspect` function to display a new window showing the server object's properties:

```
inspect(h)
```

Scroll down until you see the `DefaultFilePath` property that you just changed. It should read `C:\ExcelWork`.

Using the Property Inspector, change `DefaultFilePath` once more, this time to `MyWorkDirectory`. To do this, select the value at the right and type the new value.

Now go back to the MATLAB Command Window and confirm that the `DefaultFilePath` property has changed as expected.

```
h.DefaultFilePath
```

MATLAB displays:

```
ans =
```

```
C:\MyWorkDirectory
```

Note: If you modify properties at the MATLAB command line, refresh the Property Inspector window to see the change reflected there. Refresh the Property Inspector window by reinvoking `inspect` on the object.

Using the Property Inspector on Enumerated Values

A list button next to a property value indicates that the property accepts enumerated values. To see the values, click anywhere in the field on the right. The following figure displays four enumerated values for the `Cursor` property. The current value `xlDefault` is displayed in the field next to the property name.

To change the value, use the list button to display the options for that property, and then click the desired value.

Custom Properties

You can add your own custom properties to an instance of a control using the `addproperty` function. The syntax `h.addproperty('propertyName')` creates a custom property for control `h`.

This example creates the `mwsamp2` control, adds a property called `Position` to it, and assigns the value `[200 120]` to that property:

```
h = actxcontrol('mwsamp.mwsampctr1.2', [200 120 200 200]);  
addproperty(h, 'Position');  
h.Position = [200 120];
```

Use the `get` function to list all properties of control `h`.

```
get(h)
```

You see the new `Position` property has been added.

```
ans =  
    Label: 'Label'  
    Radius: 20  
    Position: [200 120]
```

Type:

```
h.Position
```

MATLAB displays:

```
ans =  
    200    120
```

To remove custom properties from a control, use the `deleteproperty` function. The syntax `h.deleteproperty('propertyName')` deletes `propertyName` from `h`. For example, to delete the `Position` property that you created and show that it no longer exists, type:

```
deleteproperty(h,'Position');  
get(h)
```

MATLAB displays:

```
ans =  
    Label: 'Label'  
    Radius: 20
```

Properties That Take Arguments

Some COM objects have properties that accept input arguments. Internally, MATLAB handles these properties as methods, which means you need to use the `invoke` function (not `get`) to view the property.

To explain how this works, look at a spreadsheet property that takes input arguments. This example is taken from “Using a MATLAB Application as an Automation Client” on page 12-68.

- “An Example” on page 12-23
- “Exploring the Object” on page 12-23
- “Exploring Values” on page 12-23

- “Setting Values” on page 12-24
- “Completing the Example” on page 12-25

An Example

The Excel `Activsheet` interface is an object that takes input arguments. This interface has a property called `Range`. To specify `Range`, pass in range coordinates.

To begin, create the `Worksheet` object `ws`:

```
e = actxserver('Excel.Application');
e.Workbooks.Add;
ws = e.Activesheet;
```

The `ws` object is an interface:

```
ws =
    Interface.Microsoft_Excel_11.0_Object_Library._Worksheet
```

Exploring the Object

You can explore the `ws` object using the `get` and `invoke` functions. (When you type the following commands, MATLAB displays long lists of properties and methods.) When you type `ws.get`, the property `Range` is not in the list. Use the `invoke` function to find `Range`.

```
ws.invoke
```

MATLAB displays (in part):

```
      :
Range = handle Range(handle, Variant, Variant(Optional))
      :
```

Exploring Values

The `get` function also displays the value of a property. For example, one of the properties listed by `get` is `StandardHeight`. To see its value, type:

```
get(ws, 'StandardHeight')
```

MATLAB displays:

```
ans =
```

13.2000

But, if you use this command on `Range`:

```
get(ws, 'Range');
```

MATLAB displays:

```
Invoke Error: Incorrect number of arguments
```

Consulting Microsoft reference documentation, you find `Range` requires arguments `A1:B2`, which specify a rectangular region of the spreadsheet.

If you type:

```
wsRange = get(ws, 'Range', 'A1:B2')
```

MATLAB shows that `wsRange` is an interface:

```
wsRange =  
    Interface.Microsoft_Excel_11.0_Object_Library.Range
```

You find the properties by typing:

```
get(wsRange)
```

From the lengthy list MATLAB displays, look at the `Value` property:

```
      :  
Value: {2x2 cell}  
      :
```

To see the current value, type:

```
wsRange.Value
```

MATLAB displays:

```
ans =  
    [NaN]    [NaN]  
    [NaN]    [NaN]
```

Setting Values

To copy a MATLAB array `A` into the `wsRange` object, type:

```
A = [1 2; 3 4];  
wsRange.Value = A;  
wsRange.Value
```

MATLAB displays:

```
ans =  
    [1]    [2]  
    [3]    [4]
```

Completing the Example

When you are finished with this example, type:

```
e.Workbook.Close;
```

The Excel `Close` method expects a `Yes/No` response about saving the workbook. To terminate and remove the server object, type:

```
Quit(e);  
delete(e);
```

Use Methods

In this section...

“About Methods” on page 12-26

“Getting Method Information” on page 12-26

“Invoking Methods on an Object” on page 12-31

“Exceptions to Using Implicit Syntax” on page 12-32

“Specifying Enumerated Parameters” on page 12-34

“Optional Input Arguments” on page 12-35

“Returning Multiple Output Arguments” on page 12-36

“Argument Callouts in Error Messages” on page 12-36

About Methods

You execute, or *invoke*, COM functions or methods belonging to COM objects. This topic explains how to determine what methods are available for an object and how to invoke them.

Method names are case-sensitive. You cannot abbreviate them.

Use the following MATLAB functions to work with the methods of a COM object.

Function	Description
<code>invoke</code>	Invoke a method or display a list of methods and types
<code>ismethod</code>	Determine if an item is a method of a COM object
<code>methods</code>	List all method names for the control or server
<code>methodsview</code>	Graphic display of information on all methods and types

Getting Method Information

You can see what methods are supported by a COM object using one of the following functions. Each function presents specific information, as described in the table. For complete information, refer to your vendor documentation.

Function	Output
<code>invoke</code>	Cell array of function names and signatures
<code>methodsview</code>	Graphical display of function names and signatures
<code>methods</code> with <code>-full</code> qualifier	Cell array of function names and signatures, sorted alphabetically
<code>methods</code>	Cell array of function names only, sorted alphabetically, with uppercase names listed first

In this topic, you can use the built-in MATLAB control `mwsamp` to try out these functions. To create the control object `sampObj`, type:

```
sampObj = actxcontrol('mwsamp.mwsampctrl1.1', [0 0 500 500]);
```

The control opens a figure window and displays a circle and text label.

Using `invoke`

The `invoke` function returns a cell array containing a list of all methods supported by the object, along with the signatures for these methods. This list is not sorted alphabetically.

For example, type:

```
invoke(sampObj)
```

MATLAB displays:

```
Beep = void Beep(handle)
Redraw = void Redraw(handle)
GetVariantArray = Variant GetVariantArray(handle)
GetIDispatch = handle GetIDispatch(handle)
GetBSTR = string GetBSTR(handle)
GetI4Array = Variant GetI4Array(handle)
GetBSTRArray = Variant GetBSTRArray(handle)
GetI4 = int32 GetI4(handle)
GetR8 = double GetR8(handle)
GetR8Array = Variant GetR8Array(handle)
FireClickEvent = void FireClickEvent(handle)
GetVariantVector = Variant GetVariantVector(handle)
```

```
GetR8Vector = Variant GetR8Vector(handle)
GetI4Vector = Variant GetI4Vector(handle)
SetBSTRArray = Variant SetBSTRArray(handle, Variant)
SetI4 = int32 SetI4(handle, int32)
SetI4Vector = Variant SetI4Vector(handle, Variant)
SetI4Array = Variant SetI4Array(handle, Variant)
SetR8 = double SetR8(handle, double)
SetR8Vector = Variant SetR8Vector(handle, Variant)
SetR8Array = Variant SetR8Array(handle, Variant)
SetBSTR = string SetBSTR(handle, string)
AboutBox = void AboutBox(handle)
```

Using methods with -full

When you include the `-full` qualifier in the `methods` function, MATLAB also specifies the input and output arguments for each method. For an overloaded method, the returned array includes a description of each of its signatures.

Type:

```
methods(sampObj, '-full')
```

MATLAB displays:

```
Methods for class COM.mwsamp_mwsampctrl_1:
```

```
AboutBox(handle)
Beep(handle)
FireClickEvent(handle)
string GetBSTR(handle)
Variant GetBSTRArray(handle)
int32 GetI4(handle)
Variant GetI4Array(handle)
Variant GetI4Vector(handle)
handle GetIDispatch(handle)
double GetR8(handle)
Variant GetR8Array(handle)
Variant GetR8Vector(handle)
Variant GetVariantArray(handle)
Variant GetVariantVector(handle)
Redraw(handle)
string SetBSTR(handle, string)
Variant SetBSTRArray(handle, Variant)
int32 SetI4(handle, int32)
```

```

Variant SetI4Array(handle, Variant)
Variant SetI4Vector(handle, Variant)
double SetR8(handle, double)
Variant SetR8Array(handle, Variant)
Variant SetR8Vector(handle, Variant)
addproperty(handle, string)
MATLAB array constructorargs(handle)
delete(handle, MATLAB array)
deleteproperty(handle, string)
MATLAB array events(handle, MATLAB array)
MATLAB array get(handle)
MATLAB array get(handle, MATLAB array, MATLAB array)
MATLAB array get(handle vector, MATLAB array, MATLAB array)
MATLAB array interfaces(handle)
MATLAB array invoke(handle)
MATLAB array invoke(handle, string, MATLAB array)
load(handle, string)
MATLAB array move(handle, MATLAB array)
MATLAB array move(handle)
propedit(handle)
release(handle, MATLAB array)
save(handle, string)
MATLAB array send(handle)
MATLAB array set(handle vector, MATLAB array, MATLAB array)
MATLAB array set(handle, MATLAB array, MATLAB array)
MATLAB array set(handle)

```

In the `mwsamp` control, `get` is an overloaded function, and MATLAB displays each of its signatures.


Using `methodsview`

The `methodsview` function opens a new window with an easy-to-read display of all methods supported by the object. It displays the same information as the `handle.methods(' -full')` command.

For example, type:

```
methodsview(sampObj)
```

MATLAB opens a window showing (in part):



Return Type	Name	Arguments	Inherited From
	Redraw	(handle)	COM.mwsamp_mwsampctrl_1
string	SetBSTR	(handle, string)	COM.mwsamp_mwsampctrl_1
Variant	SetBSTRArray	(handle, Variant)	COM.mwsamp_mwsampctrl_1
int32	SetI4	(handle, int32)	COM.mwsamp_mwsampctrl_1
Variant	SetI4Array	(handle, Variant)	COM.mwsamp_mwsampctrl_1
Variant	SetI4Vector	(handle, Variant)	COM.mwsamp_mwsampctrl_1
double	SetR8	(handle, double)	COM.mwsamp_mwsampctrl_1
Variant	SetR8Array	(handle, Variant)	COM.mwsamp_mwsampctrl_1
Variant	SetR8Vector	(handle, Variant)	COM.mwsamp_mwsampctrl_1
	addproperty	(handle, string)	COM.mwsamp_mwsampctrl_1
MATLAB array	constructorargs	(handle)	COM.mwsamp_mwsampctrl_1
	delete	(handle, MATLAB array)	COM.mwsamp_mwsampctrl_1
	deleteproperty	(handle, string)	COM.mwsamp_mwsampctrl_1

Using methods

The `methods` function returns the names of all methods for the object, including MATLAB COM functions that you can use on the object. There is no information about how to call the method. This list is sorted alphabetically; however, method names with initial caps are listed before methods with lowercase names.

For example, type:

```
methods(sampObj)
```

MATLAB displays:

```
Methods for class COM.mwsamp_mwsampctrl_1:
```

```
AboutBox          GetVariantVector  deleteproperty
Beep               Redraw            events
FireClickEvent    SetBSTR           get
GetBSTR            SetBSTRArray      interfaces
GetBSTRArray      SetI4             invoke
GetI4              SetI4Array        load
GetI4Array        SetI4Vector       move
GetI4Vector       SetR8             propedit
GetIDispatch      SetR8Array        release
```


GetR8	SetR8Vector	save
GetR8Array	addproperty	send
GetR8Vector	constructorargs	set
GetVariantArray	delete	

Examples of MATLAB COM functions are `addproperty` and `set`. Although the list is sorted alphabetically, uppercase function names are listed first. For example, `Redraw` appears before `get`.

Invoking Methods on an Object

This section covers the following topics:

- “Calling Syntax” on page 12-31
- “Input and Output Arguments” on page 12-32
- “Example Using `mwsamp`” on page 12-32

Calling Syntax

To invoke a method on a COM object, use *dot syntax*, also called dot notation. This is a simpler syntax that doesn't require an explicit function call. For situations where you cannot use this syntax, see “Exceptions to Using Implicit Syntax” on page 12-32.

The format of a dot syntax statement is:

```
outputvalue = object.methodname('arg1', 'arg2', ...);
```

Specify the object name, the dot (`.`), and the name of the function or method. Enclose any input arguments in parentheses after the function name. Specify output arguments to the left of the equal sign.

Dot syntax is a special case of calling by method name. An alternative syntax for calling by method name is:

```
outputvalue = methodname(object, 'arg1', 'arg2', ...);
```

MATLAB also supports the following explicit syntax statements:

```
outputvalue = invoke(object, 'methodname', 'arg1', 'arg2', ...);
outputvalue = object.invoke('methodname', 'arg1', 'arg2', ...);
```

Input and Output Arguments

The `methodsview` output window and the `methods -full` command show what data types to use for input and output arguments. For information about reading a signature statement and using input and output arguments, see “Handling COM Data in MATLAB Software” on page 12-59.

Example Using `mwsamp`

The following example creates three circles in a MATLAB figure window. It shows different commands you can use to change the circles.

To create the COM objects, type:

```
h1 = actxcontrol('mwsamp.mwsampctrl1.2', [0 0 200 200]);  
h2 = actxcontrol('mwsamp.mwsampctrl1.2', [200 200 200 200]);  
h3 = actxcontrol('mwsamp.mwsampctrl1.2', [400 0 200 200]);
```

You can explicitly change the size of and redraw a circle using the commands:

```
set(h1, 'Radius', 100);  
invoke(h1, 'Redraw')
```

You can implicitly change the size using:

```
h2.Radius = 50;  
h3.Radius = 25;
```

To redraw the circles using method name syntax, type:

```
Redraw(h2)  
h3.Redraw
```

Close the figure window.

Exceptions to Using Implicit Syntax

You cannot use dot syntax and must explicitly call the `get`, `set`, and `invoke` functions under the following conditions:

- “Accessing Nonpublic Properties and Methods” on page 12-33
- “Accessing Properties That Take Arguments” on page 12-33
- “Operating on a Vector of Objects” on page 12-33

Accessing Nonpublic Properties and Methods

If the property or method you want to access is not a public property or method of the object class, or if it is not in the type library for the control or server, you must call `get`, `set`, or `invoke` explicitly.

If you use a syntax statement of the following format for a nonpublic property *aProperty*:

```
x = handle.aProperty
```

MATLAB displays a message such as:

```
No appropriate method or public field aProperty for class  
COM.aClass.application.
```

Instead, you must use the `get` function explicitly:

```
x = handle.get('aProperty')
```

To find public properties and methods on COM object *h*, type:

```
publicproperties = h.get  
publicmethods = h.invoke
```

Accessing Properties That Take Arguments

Some COM objects have properties that accept input arguments. MATLAB treats these properties like methods. For an example of this feature, see “Properties That Take Arguments” on page 12-22.

To get or set the value of such a property, you must make an explicit call to the `get` or `set` function, as shown in the following example. In this example, *A1* and *B2* are arguments that specify which `Range` interface to return on the `get` operation:

```
eActivesheetRange = e.Activesheet.get('Range', 'A1', 'B2');
```

Operating on a Vector of Objects

If you operate on a vector of objects you must call `get` or `set` explicitly to access properties. For an example, see “Working with Multiple Objects” on page 12-17. This applies only to the `get` and `set` functions. You cannot invoke a method on multiple COM objects, even if you call the `invoke` function explicitly.

Specifying Enumerated Parameters

Enumeration is a way of assigning a descriptive name to a symbolic value.

For example, the input to a function is the atomic number of an element. It is easier to remember an element name than the atomic number. Using enumeration, you can pass the word 'arsenic' in place of the value 33.

MATLAB supports enumeration for parameters passed to methods under the condition that the type library in use reports the parameter as ENUM, and only as ENUM.

Note: MATLAB does not support enumeration for any parameter that the type library reports as both ENUM and Optional.

In this example, the Location method accepts the enumerated value 'xlLocationAsObject'.

Create a Microsoft Excel Chart object:

```
e = actxserver('Excel.Application');

% Insert a new workbook.
Workbook = e.Workbooks.Add;
e.Visible = 1;
Sheets = e.ActiveWorkBook.Sheets;

% Get a handle to the active sheet.
Activsheet = e.Activesheet;

%Add a Chart
Charts = Workbook.Charts;
Chart = Charts.Add;
```

To see what type of chart you can create, type:

```
inspect(Chart)
```

Scroll through the Property Inspector window to find `ChartType`. Click the drop-down arrow to see all possible `ChartType` values. This is an enumerated list. Close the property inspector.

To programmatically set the `ChartType`, type:

```
% Set chart type to be a line plot.
Chart.ChartType = 'xlXYScatterLines'
C1 = Chart.Location('xlLocationAsObject', 'Sheet1');
```

Close the Excel spreadsheet.

Optional Input Arguments

When calling a method that takes optional input arguments, you can skip any optional argument by specifying an empty array ([]) in its place. The syntax for calling a method with second argument `arg2` not specified is:

```
handle.methodname(arg1, [], arg3);
```

The following example uses the `Add` method to add new sheets to an Excel workbook. The `Add` method has the following optional input arguments:

- **Before** — The sheet before which to add the new sheet
- **After** — The sheet after which to add the new sheet
- **Count** — The total number of sheets to add
- **Type** — The type of sheet to add

The following code creates a workbook with the default number of worksheets, and inserts an additional sheet after Sheet 1. To do this, call `Add` with the second argument, `After`. You omit the first argument, `Before`, by using [] in its place, as shown in the last line of the example:

```
% Open an Excel Server.
e = actxserver('Excel.Application');

% Insert a new workbook.
e.Workbooks.Add;
e.Visible = 1;

% Get the Active Workbook with three sheets.
eSheets = e.ActiveWorkbook.Sheets;

% Add a new sheet after eSheet1.
eSheet1 = eSheets.Item(1);
eNewSheet = eSheets.Add([], eSheet1);
```

Close the Excel spreadsheet.

Returning Multiple Output Arguments

If you know that a server function supports multiple outputs, you can return any or all of those outputs to a MATLAB client.

The following syntax shows a server function `functionname` called by the MATLAB client. `retval` is the function's first output argument, or return value. The other output arguments are `out1`, `out2`,

```
[retval out1 out2 ...] = handle.functionname(in1, in2, ...);
```

MATLAB makes use of the pass-by-reference capabilities in COM to implement this feature. Note that pass-by-reference is a COM feature; MATLAB does not support pass-by-reference.

Argument Callouts in Error Messages

When a MATLAB client sends a command with an invalid argument to a COM server application, the server sends back an error message, similar to the following, identifying the invalid argument.

```
??? Error: Type mismatch, argument 3.
```

If you do not use the dot syntax format, be careful interpreting the argument number in this type of message.

For example, using dot syntax, if you type:

```
handle.PutFullMatrix('a', 'base', 7, [5 8]);
```

MATLAB displays:

```
??? Error: Type mismatch, argument 3.
```

In this case, the argument, 7, is invalid because `PutFullMatrix` expects the third argument to be an array data type, not a scalar. In this example, the error message identifies 7 as argument 3.

However, if you use the syntax:

```
PutFullMatrix(handle, 'a', 'base', 7, [5 8]);
```

MATLAB displays:

??? Error: Type mismatch, argument 3.

In this call to the `PutFullMatrix` function, 7 is argument four. However, the COM server does not receive the first argument. The `handle` argument merely identifies the server. It does not get passed to the server. This means the server sees 'a' as the first argument, and the invalid argument, 7, as the third.

If you use the syntax:

```
invoke(handle, 'PutFullMatrix', 'a', 'base', 7, [5 8]);
```

MATLAB again displays:

??? Error: Type mismatch, argument 3.

As in the previous example, MATLAB uses the `handle` argument to identify the server. The `'PutFullMatrix'` argument is also only used by MATLAB. While the invalid argument is the fifth argument in your MATLAB command, the server still identifies it as argument 3, because the first two arguments are not seen by the server.

Use Events

In this section...
“About Events” on page 12-38
“Functions for Working with Events” on page 12-39
“Examples of Event Handlers” on page 12-39
“Responding to Events — an Overview” on page 12-39
“Responding to Events — Examples” on page 12-41
“Writing Event Handlers” on page 12-49
“Sample Event Handlers” on page 12-51
“Writing Event Handlers as MATLAB Local Functions” on page 12-52

About Events

An *event* is typically a user-initiated action that takes place in a server application, which often requires a reaction from the client. For example, a user clicking the mouse at a particular location in a server interface window might require the client take some action in response. When an event is *fired*, the server communicates this occurrence to the client. If the client is *listening* for this particular type of event, it responds by executing a routine called an *event handler*.

The MATLAB COM client can subscribe to and handle the events fired by a Microsoft ActiveX control or a COM server. Select the events you want the client to listen to by registering each event you want active with the event handler to be used in responding to the event. When a registered event takes place, the control or server notifies the client, which responds by executing the appropriate event handler routine. You can write event handlers as MATLAB functions.

Note: MATLAB does not support asynchronous events.

Note: MATLAB does not support interface events from a Custom server.

Functions for Working with Events

Use the MATLAB functions in the following table to register and unregister events, to list all events, or to list just registered events for a control or server.

Function	Description
<code>actxcontrol</code>	Create a COM control and optionally register those events you want the client to listen to
<code>eventlisteners</code>	Return a list of events attached to listeners
<code>events</code>	List all events, both registered and unregistered, a control or server can generate
<code>isevent</code>	Determine if an item is an event of a COM object
<code>registerevent</code>	Register an event handler with a control or server event
<code>unregisterallevents</code>	Unregister all events for a control or server
<code>unregisterevent</code>	Unregister an event handler with a control or server event

Event names and event handler names are not case sensitive. You cannot abbreviate them.

Examples of Event Handlers

The following examples use event handlers:

- “Add Grid ActiveX Control in a Figure” on page 11-15
- “Read Excel Spreadsheet Data” on page 11-23

Responding to Events — an Overview

This section describes the basic steps to handle events fired by a COM control or server.

- “Identifying All Events” on page 12-40
- “Registering Those Events You Want to Respond To” on page 12-40
- “Identifying Registered Events” on page 12-40
- “Responding to Events As They Occur” on page 12-41
- “Unregistering Events You No Longer Want to Listen To” on page 12-41

Identifying All Events

Use the `events` function to list all events the control or server can respond to. This function returns a structure array, where each field of the structure is the name of an event handler, and the value of that field contains the signature for the handler routine. To invoke `events` on an object with handle `h`, type:

```
S = events(h)
```

Registering Those Events You Want to Respond To

Use the `registerevent` function to register those server events you want the client to respond to. You can register events as follows:

- If you have one function to handle all server events, register this common event handler using the syntax:

```
registerevent(h, 'handler')
```

- If you have a separate event handler function for different events, use the syntax:

```
registerevent(h.{'event1' 'handler1'; 'event2' 'handler2'};)
```

For ActiveX controls, you can register events at the time you create an instance of the control using the `actxcontrol` function.

- To register a common event handler function to respond to all events, use:

```
h = actxcontrol('progid', position, figure, 'handler');
```

- To register a separate function to handle each type of event, use:

```
h = actxcontrol('progid', position, figure, ...  
    {'event1' 'handler1'; 'event2' 'handler2'; ...});
```

The MATLAB client responds only to events you have registered. If you register the same event name to the same callback handler multiple times, MATLAB executes the event only once.

Identifying Registered Events

The `eventlisteners` function lists only currently registered events. This function returns a cell array, with each row representing a registered event and the name of its event handler. For example, to invoke `eventlisteners` on an object with handle `h`, type:

```
C = eventlisteners(h)
```

Responding to Events As They Occur

Whenever a control or server fires an event that the client is listening for, the client responds to the event by invoking one or more event handlers that have been registered for that event. You can implement these routines as MATLAB functions. Read more about event handlers in the section on “Writing Event Handlers” on page 12-49.

Unregistering Events You No Longer Want to Listen To

If you have registered events that you now want the client to ignore, you can unregister them at any time using the functions `unregisterevent` and `unregisterallevents` as follows:

- For a server with handle `h`, to unregister all events registered with a common event handling function `handler`, use:

```
unregisterevent(h, 'handler')
```
- To unregister individual events `eventN`, each registered with its own event handling function `handlerN`, use:

```
unregisterevent(h, {'event1' 'handler1'; 'eventN' 'handlerN'})
```
- To unregister all events from the server regardless of which event handling function they are registered with, use:

```
unregisterallevents(h)
```

Responding to Events — Examples

The following examples show you how to respond to events from different COM objects:

- “Responding to Events from an ActiveX Control” on page 12-41
- “Responding to Events from an Automation Server” on page 12-45
- “Responding to Interface Events from an Automation Server” on page 12-48

Responding to Events from an ActiveX Control

This example describes how to handle events fired by an ActiveX control. It uses a control called `mwsamp2` that ships with MATLAB.

Tasks described in this section are:

- “Creating Event Handler Routines” on page 12-42
- “Creating a Control and Registering Events” on page 12-42
- “Listing Control Events” on page 12-42
- “Responding to Control Events” on page 12-43
- “Unregistering Control Events” on page 12-44
- “Using a Common Event Handling Routine” on page 12-45

Creating Event Handler Routines

You can view the event handler code for the `mwsamp2` control in the section “Sample Event Handlers” on page 12-51. Create the event handler files `myclick.m`, `my2click.m`, and `mymoused.m` and save them on your path, for example, `c:\work`.

Creating a Control and Registering Events

The `actxcontrol` function not only creates the control object, but you can use it to register specific events, as well. The code shown here registers two events (`Click` and `MouseDown`) and two respective handler routines (`myclick` and `mymoused`) with the `mwsamp2` control:

```
f = figure('position', [100 200 200 200]);  
ctrl = actxcontrol('mwsamp.mwsampctrl.2', [0 0 200 200], f, ...  
    {'Click','myclick'; 'MouseDown','mymoused'});
```

If, at some later time, you want to register additional events, use the `registerevent` function. For example:

```
registerevent(ctrl,{'DblClick','my2click'})
```

Unregister the `DblClick` event before continuing with the example:

```
unregisterevent(ctrl,{'DblClick','my2click'})
```

Listing Control Events

At this point, only the `Click` and `MouseDown` events should be registered. To list all events, whether registered or not, type:

```
allEvents = events(ctrl)  
  
allEvents =  
    Click: 'void Click()'
```

```

    DblClick: 'void DblClick()'
    MouseDown: 'void MouseDown(int16 Button, int16 Shift, Variant x, Variant y)'
    Event_Args: 'void Event_Args(int16 typeshort, int32 typelong, double typedou...'
```

This function returns a structure array, where each field of the structure is the name of an event handler and the value of that field contains the signature for the handler routine. For example:

```
allEvents.Event_Args
```

```
ans =
    void Event_Args(int16 typeshort, int32 typelong,
        double typedouble, string typestring, bool typebool)
```

To list only the currently registered events, use the `eventlisteners` function:

```
eventlisteners(ctrl)
```

```
ans =
    'click'          'myclick'
    'mousedown'     'mymoused'
```

This function returns a cell array, with each row representing a registered event and the name of its event handler.

Responding to Control Events

When MATLAB creates the `mwsamp2` control, it also displays a figure window showing a label and circle at the center. If you click different positions in this window, you see a report in the MATLAB Command Window of the X and Y position of the mouse.

Each time you press the mouse button, the `MouseDown` event fires, calling the `mymoused` function. This function prints the position values for that event to the Command Window. For example:

```

The X position is:
ans =
    [122]
The Y position is:
ans =
    [63]
```

The `Click` event displays the message:

```
Single click function
```

Double-clicking the mouse does nothing different, since the `Db1Click` event is not registered.

Unregistering Control Events

When you unregister an event, the client discontinues listening for occurrences of that event. When the event fires, the client does not respond. If you unregister the `MouseDown` event, MATLAB no longer reports the X and Y positions. Type:

```
unregisterevent(ctrl,{'MouseDown' 'mymoused'})
```

When you click in the figure window, MATLAB displays:

```
Single click function
```

Now, register the `Db1Click` event, using the `my2click` event handler:

```
registerevent(ctrl,{'Db1Click', 'my2click'})
```

If you call `eventlisteners` again:

```
eventlisteners(ctrl)
```

MATLAB displays:

```
ans =  
    'click'      'myclick'  
    'dblclick'  'my2click'
```

When you double-click the mouse button, MATLAB displays:

```
Single click function  
Double click function
```

An easy way to unregister all events for a control is to use the `unregisterallevents` function.

```
unregisterallevents(ctrl)  
eventlisteners(ctrl)
```

When there are no events registered, `eventlisteners` returns an empty cell array:

```
ans =  
    {}
```

Clicking the mouse in the control window now does nothing since there are no active events.

Using a Common Event Handling Routine

If you have events that are registered with a common event handling routine, such as `sampev.m` used in the following example, you can use `unregisterevent` to unregister all of these events in one operation. This example first registers all events from the server with a common handling routine `sampev.m`. MATLAB now handles any type of event from this server by executing `sampev`:

```
registerevent(ctrl,'sampev')
```

Verify the registration by listing all event listeners for that server:

```
eventlisteners(ctrl)
```

MATLAB displays:

```
ans =
    'click'          'sampev'
    'dblclick'      'sampev'
    'mousedown'    'sampev'
```

Now unregister all events for the server that use the `sampev` event handling routine:

```
unregisterevent(ctrl,'sampev')
eventlisteners(ctrl)
```

MATLAB displays:

```
ans =
    {}
```

Close the figure window.

Responding to Events from an Automation Server

This example shows how to handle events fired by an Automation server. It creates a server running the Microsoft Internet Explorer program, registers a common event handler for all events, and then has you fire events by browsing to Web sites.

Tasks described in this section are:

- “Creating an Event Handler” on page 12-46
- “Creating a Server” on page 12-46
- “Listing Server Events” on page 12-46

- “Registering Server Events” on page 12-47
- “Responding to Server Events” on page 12-47
- “Unregistering Server Events” on page 12-47
- “Closing the Application” on page 12-48

Creating an Event Handler

Register all events with the same handler routine, `serverevents`. Create the file `serverevents.m`, inserting the following code. Make sure that the file is in your current folder.

```
function serverevents(varargin)

% Display incoming event name
eventname = varargin{end}

% Display incoming event args
eventargs = varargin{end-1}
```

Creating a Server

Next, at the MATLAB command prompt, type the following commands:

```
% Create a server running Internet Explorer.
browser = actxserver('internetexplorer.application');
% Make the server application visible.
set(browser,'Visible', 1);
```

Listing Server Events

Use the `events` function to list all events the server can respond to, and `eventlisteners` to list the registered events:

```
events(browser)
```

MATLAB displays event information like:

```
      :
StatusTextChange = void StatusTextChange(string Text)
ProgressChange = void ProgressChange(int32 Progress,int32 ProgressMax)
CommandStateChange = void CommandStateChange(int32 Command,bool Enable)
      :
```

List the registered events:

```
eventlisteners(browser)
```


If you now use the Web browser, MATLAB only responds to the `TitleChange` event.

Closing the Application

Close a server application when you no longer intend to use it. To unregister all events and close the application, type:

```
unregisterallevents(browser)
Quit(browser);
delete(browser);
```

Responding to Interface Events from an Automation Server

This example, demonstrating how to handle a COM interface event, shows how to set up an event in a Microsoft Excel workbook object and how to handle its `BeforeClose` event.

To create the event handler `OnBeforeCloseWorkbook`, create the file `OnBeforeCloseWorkbook.m`, inserting the following code. Make sure that the file is in your current folder:

```
% Event handler for Excel workbook BeforeClose event
function OnBeforeCloseWorkbook(varargin)
    disp('BeforeClose event occurred');
```

When you run the following commands:

```
% Create Excel automation server instance
xl = actxserver('Excel.Application');
% Make it visible
xl.Visible = 1;

% Get collection of workbooks and add a new workbook
hWbks = xl.Workbooks;
hWorkbook = hWbks.Add;

% Register OnClose event
registerevent(hWorkbook,{'BeforeClose' @OnBeforeCloseWorkbook})

% Close the workbook. This fires the Close event
% and calls the OnClose handler
Close(hWorkbook)
```

MATLAB displays:

BeforeClose event occurred

Writing Event Handlers

This section covers the following topics on writing handler routines to respond to events fired from a COM object:

- “Overview of Event Handling” on page 12-49
- “Arguments Passed to Event Handlers” on page 12-50
- “Event Structure” on page 12-50

Overview of Event Handling

An event is fired when a control or server wants to notify its client that something of interest has occurred. For example, many controls trigger an event when the user clicks somewhere in the interface window of a control. Create and register your own MATLAB functions to respond to events when they occur. These functions are event handlers. You can create one handler function to handle all events or a separate handler for each type of event.

For controls, you can register handler functions either at the time you create an instance of the control (using `actxcontrol`), or at any time afterwards (using `registerevent`).

Both `actxcontrol` and `registerevent` use an event handler argument. The event handler argument can be either the name of a single callback routine or a cell array that associates specific events with their respective event handlers. Strings used in the event handler argument are not case sensitive.

For servers, use `registerevent` to register those events you want the client to listen to. For example, to register the `Click` and `DblClick` events, use:

```
registerevent(h,{'click','myclick'; 'dblclick','my2click'})
```

Use `events` to list all the events a COM object recognizes. For example, to list all events for the `mwsamp2` control, use:

```
f = figure('position',[100 200 200 200]);
h = actxcontrol('mwsamp.mwsampctrl1.2',[0 0 200 200],f);

h.events
    Click = void Click()
```

```
Db1Click = void Db1Click()  
MouseDown = void MouseDown(int16 Button, int16 Shift,  
    Variant x, Variant y)
```

Arguments Passed to Event Handlers

When a registered event is triggered, the MATLAB software passes information from the event to its handler function, as shown in this table.

Arguments Passed by MATLAB Functions

Arg. No.	Contents	Format
1	Object name	MATLAB COM class
2	Event ID	double
3	Start of Event Argument List	As passed by the control
end-2	End of Event Argument List (Argument N)	As passed by the control
end-1	Event Structure	structure
end	Event Name	char array

When writing an event handler function, use the Event Name argument to identify the source of the event. Get the arguments passed by the control from the Event Argument List (arguments 3 through end-2). All event handlers must accept a variable number of arguments:

```
function event (varargin)  
if (strcmp(varargin{end}, 'MouseDown')) % Check the event name  
    x_pos = varargin{5}; % Read 5th Event Argument  
    y_pos = varargin{6}; % Read 6th Event Argument  
end
```

Note: The values passed vary with the particular event and control being used.

Event Structure

The second to last argument passed by MATLAB is the Event Structure, which has the fields shown in the following table.

Fields of the Event Structure

Field Name	Description	Format
Type	Event Name	char array
Source	Control Name	MATLAB COM class
EventID	Event Identifier	double
Event Arg Name 1	Event Arg Value 1	As passed by the control
Event Arg Name 2	Event Arg Value 2	As passed by the control
etc.	Event Arg N	As passed by the control

For example, when the `MouseDown` event of the `mwsamp2` control is triggered, MATLAB passes this Event Structure to the registered event handler:

```
Type: 'MouseDown'
Source: [1x1 COM.mwsamp.mwsampctr1.2]
EventID: -605
Button: 1
Shift: 0
    x: 27
    y: 24
```

Sample Event Handlers

Specify a single callback, `sampev`:

```
f = figure('position',[100 200 200 200]);
h = actxcontrol('mwsamp.mwsampctr1.2',[0 0 200 200],gcf,'sampev')
h =
    COM.mwsamp.mwsampctr1.2
```

Or specify several events using the cell array format:

```
h = actxcontrol('mwsamp.mwsampctr1.2', [0 0 200 200],f,...
    {'Click','myclick'; 'Db1Click','my2click'; ...
    'MouseDown','mymoused'});
```

The event handlers, `myclick.m`, `my2click.m`, and `mymoused.m`, are:

```
function myclick(varargin)
disp('Single click function')
```

```
function my2click(varargin)
disp('Double click function')

function mymoused(varargin)
disp('You have reached the mouse down function')
disp('The X position is: ')
double(varargin{5})
disp('The Y position is: ')
double(varargin{6})
```

Alternatively, you can use the same event handler for all the events you want to monitor using the cell array pairs. Response time is better than using the callback style.

For example:

```
f = figure('position',[100 200 200 200]);
h = actxcontrol('mwsamp.mwsampctrl.2',...
[0 0 200 200],f,{'Click','allevents';...
'DblClick','allevents'; 'MouseDown','allevents'})
```

where `allevents.m` is:

```
function allevents(varargin)
if (strcmp(varargin{end-1}.Type, 'Click'))
    disp ('Single Click Event Fired')
elseif (strcmp(varargin{end-1}.Type, 'Db1Click'))
    disp ('Double Click Event Fired')
elseif (strcmp(varargin{end-1}.Type, 'MouseDown'))
    disp ('Mousedown Event Fired')
end
```

Writing Event Handlers as MATLAB Local Functions

Instead of maintaining a separate function file for every event handler routine you write, you can consolidate routines into a single file using local functions.

This example shows three event handler routines, `myclick`, `my2click`, and `mymoused`, implemented as local functions in the file `mycallbacks.m`. The call to `str2func` converts the input string to a function handle:

```
function a = mycallbacks(str)
a = str2func(str);

function myclick(varargin)
```

```
disp('Single click function')

function my2click(varargin)
disp('Double click function')

function mymoused(varargin)
disp('You have reached the mouse down function')
disp('The X position is: ')
double(varargin{5})
disp('The Y position is: ')
double(varargin{6})
```

To register one of these events, call `mycallbacks`, passing the name of the event handler:

```
h = actxcontrol('mwsamp.mwsampctrl1.2',[0 0 200 200],gcf,'sampev')
registerevent(h,{'Click',mycallbacks('myclick')})
```

Getting Interfaces to COM Object

In this section...

“IUnknown and IDispatch Interfaces” on page 12-54

“Custom Interfaces” on page 12-55

IUnknown and IDispatch Interfaces

When you invoke the `actxserver` or `actxcontrol` functions, the MATLAB software creates the server and returns a handle to the server interface as a means of accessing its properties and methods. The software uses the following process to determine which handle to return:

- 1 First get a handle to the IUnknown interface from the component. All COM components are required to implement this interface.
- 2 Attempt to get the IDispatch interface. If IDispatch is implemented, return a handle to this interface. If IDispatch is not implemented, return the handle to IUnknown.

Additional Interfaces

Components often provide additional interfaces, based on IDispatch, that are implemented as properties. Like any other property, you obtain these interfaces using the MATLAB `get` function.

For example, a Microsoft Excel component contains numerous interfaces. To list these interfaces, along with Excel properties, type:

```
h = actxserver('Excel.Application');  
get(h)
```

MATLAB displays information like:

```
Application: [1x1 Interface.Microsoft_Excel_9.0_
Object_Library_Application]
  Creator: 'xlCreatorCode'
  Parent: [1x1 Interface.Microsoft_Excel_9.0_
Object_Library_Application]
  ActiveCell: []
  ActiveChart: [1x50 char]
```


To see if `Workbooks` is an interface, type:

```
w = h.Workbooks
```

MATLAB displays:

```
w =  
    Interface.Microsoft_Excel_9.0_Object_Library.Workbooks
```

The information displayed depends on the version of the Excel software you have on your system.

For examples using Excel in MATLAB, see:

- “Read Excel Spreadsheet Data”
- “Use MATLAB Application as Automation Client”
- `actxserver`

Custom Interfaces

The MATLAB COM Interface supports custom interfaces for the following client/server configurations:

- “MATLAB Client and In-Process Server” on page 11-30
- “MATLAB Client and Out-of-Process Server” on page 11-31

Limitations to custom interface support are:

- Custom interfaces are not supported on a 64-bit version of MATLAB.
- You cannot invoke functions with optional parameters.

Once you have created a server, you can query the server component to see if any custom interfaces are implemented using the `interfaces` function.

For example, if you have a component with the ProgID `mytestenv.calculator`, you can see its custom interfaces using the commands:

```
h = actxserver('mytestenv.calculator');  
customlist = h.interfaces
```

MATLAB displays the interfaces, which might be:

```
customlist =  
    ICalc1  
    ICalc2  
    ICalc3
```

To get the handle to a particular interface, use the `invoke` function:

```
c1 = invoke(h, 'ICalc1')  
c1 =  
    Interface.Calc_1.0_Type_Library.ICalc_Interface
```

Use this handle `c1` to access the properties and methods of the object through this custom interface `ICalc1`.

For example, to list the properties, use:

```
get(c1)  
    background: 'Blue'  
    height: 10  
    width: 0
```

To list the methods, use:

```
invoke(c1)  
    Add = double Add(handle, double, double)  
    Divide = double Divide(handle, double, double)  
    Multiply = double Multiply(handle, double, double)  
    Subtract = double Subtract(handle, double, double)
```

To add and multiply numbers using the `Add` and `Multiply` methods of the object, use:

```
sum = Add(c1,4,7)  
sum =  
    11  
  
prod = c1.Multiply(4, 7)  
prod =  
    28
```

Save COM Objects

In this section...

“Functions for Saving and Restoring COM Objects” on page 12-57

“Releasing COM Interfaces and Objects” on page 12-58

Functions for Saving and Restoring COM Objects

Use these MATLAB functions to save and restore the state of a COM control object.

Function	Description
load	Load and initialize a COM control object from a file
save	Write and serialize a COM control object to a file

Save, or *serialize*, the current state of a COM control to a file using the `save` function. *Serialization* is the process of saving an object onto a storage medium (such as a file or a memory buffer) or transmitting it across a network connection link in binary form.

The following example creates an `mwsamp2` control and saves its original state to the file `mwsample`:

```
f = figure('position',[100 200 200 200]);
h = actxcontrol('mwsamp.mwsampctr1.2',[0 0 200 200],f);
save(h,'mwsample')
```

Now, alter the figure by changing its label and the radius of the circle:

```
h.Label = 'Circle';
h.Radius = 50;
Redraw(h);
```

Using the `load` function, you can restore the control to its original state:

```
load(h,'mwsample');
```

To verify the results, type:

```
get(h)
```

MATLAB displays:

```
ans =  
    Label: 'Label'  
    Radius: 20
```

Note: MATLAB supports the COM `save` and `load` functions for controls only.

Releasing COM Interfaces and Objects

Use these MATLAB functions to release or delete a COM object or interface.

Function	Description
<code>delete</code>	Delete a COM object or interface
<code>release</code>	Release a COM interface

When you no longer need an interface, use the `release` function to release the interface and reclaim the memory used by it. When you no longer need a control or server, use the `delete` function to delete it. Alternatively, you can use the `delete` function to both release all interfaces for the object and delete the server or control.

Note: In versions of MATLAB earlier than 6.5, failure to explicitly release interface handles or delete the control or server often results in a memory leak. This is true even if the variable representing the interface or COM object has been reassigned. In MATLAB version 6.5 and later, the control or server, along with all interfaces to it, is destroyed on reassignment of the variable or when the variable representing a COM object or interface goes out of scope.

When you delete or close a figure window containing a control, MATLAB automatically releases all interfaces for the control. MATLAB also automatically releases all handles for an Automation server when you exit the program.

Handling COM Data in MATLAB Software

In this section...

“Passing Data to COM Objects” on page 12-59

“Handling Data from COM Objects” on page 12-61

“Unsupported Types” on page 12-62

“Passing MATLAB Data to ActiveX Objects” on page 12-62

“Passing MATLAB SAFEARRAY to COM Object” on page 12-62

“Reading SAFEARRAY from COM Objects in MATLAB Applications” on page 12-64

“Displaying MATLAB Syntax for COM Objects” on page 12-65

Passing Data to COM Objects

When you use a COM object in a MATLAB command, the MATLAB types you pass in the call are converted to types native to the COM object. MATLAB performs this conversion on each argument that is passed. This section describes the conversion.

MATLAB arguments are converted by MATLAB into types that best represent the data to the COM object. The following table shows all the MATLAB base types for passed arguments and the COM types defined for input arguments. Each row shows a MATLAB type followed by the possible COM argument matches. For a description of COM variant types, see the table in “Handling Data from COM Objects” on page 12-61.

MATLAB Argument	Closest COM Type	Allowed Types
handle	VT_DISPATCH VT_UNKNOWN	VT_DISPATCH VT_UNKNOWN
string	VT_BSTR	VT_LPWSTR VT_LPSTR VT_BSTR VT_FILETIME VT_ERROR VT_DECIMAL VT_CLSID VT_DATE
int16	VT_I2	VT_I2

MATLAB Argument	Closest COM Type	Allowed Types
uint16	VT_UI2	VT_UI2
int32	VT_I4	VT_I4 VT_INT
uint32	VT_UI4	VT_UI4 VT_UINT
int64	VT_I8	VT_I8
uint64	VT_UI8	VT_UI8
single	VT_R4	VT_R4
double	VT_R8	VT_R8 VT_CY
logical	VT_BOOL	VT_BOOL
char	VT_I1	VT_I1 VT_UI1

Variant Data

`variant` is any data type except a structure or a sparse array. (For more information, see “Fundamental MATLAB Classes”.)

When used as an input argument, MATLAB treats `variant` and `variant(pointer)` the same way.

MATLAB Argument	Closest COM Type	Allowed Types
<code>variant</code>	VT_VARIANT	VT_VARIANT VT_USERDEFINED VT_ARRAY
<code>variant(pointer)</code>	VT_VARIANT	VT_VARIANT VT_BYREF

SAFEARRAY Data

When a COM method identifies a `SAFEARRAY` or `SAFEARRAY(pointer)`, the MATLAB equivalent is a matrix.

MATLAB Argument	Closest COM Type	Allowed Types
<code>SAFEARRAY</code>	VT_SAFEARRAY	VT_SAFEARRAY

MATLAB Argument	Closest COM Type	Allowed Types
SAFEARRAY(pointer)	VT_SAFEARRAY	VT_SAFEARRAY VT_BYREF

Handling Data from COM Objects

Data returned from a COM object is often incompatible with MATLAB types. When this occurs, MATLAB converts the returned value to a data type native to the MATLAB language. This section describes the conversion performed on the various types that can be returned from COM objects.

The following table shows how MATLAB converts data from a COM object into MATLAB variables.

COM Variant Type	Description	MATLAB Representation
VT_DISPATCH VT_UNKNOWN	IDispatch * IUnknown *	handle
VT_LPWSTR VT_LPSTR VT_BSTR VT_FILETIME VT_ERROR VT_DECIMAL VT_CLSID VT_DATE	wide null terminated string null terminated string OLE Automation string FILETIME SCODE 16-byte fixed point Class ID date	string
VT_INT VT_UINT VT_I2 VT_UI2 VT_I4 VT_UI4 VT_R4 VT_R8 VT_CY	signed machine int unsigned machine int 2 byte signed int unsigned short 4 byte signed int unsigned long 4 byte real 8 byte real currency	double
VT_I8	signed int64	int64
VT_UI8	unsigned int64	uint64
VT_BOOL		logical

COM Variant Type	Description	MATLAB Representation
VT_I1 VT_UI1	signed char unsigned char	char
VT_VARIANT VT_USERDEFINED VT_ARRAY	VARIANT * user-defined type SAFEARRAY*	variant
VT_VARIANT VT_BYREF	VARIANT * void* for local use	variant(pointer)
VT_SAFEARRAY	use VT_ARRAY in VARIANT	SAFEARRAY
VT_SAFEARRAY VT_BYREF		SAFEARRAY(pointer)

Unsupported Types

MATLAB does not support the following COM interface types and displays the warning `ActiveX - unsupported VARIANT type encountered`.

- Structure
- Sparse array
- Multidimensional SAFEARRAYs (greater than two dimensions)
- Write-only properties

Passing MATLAB Data to ActiveX Objects

The tables also show the mapping of MATLAB types to COM types that you must use to pass data from MATLAB to an Microsoft ActiveX object. For all other types, MATLAB displays the warning `ActiveX - invalid argument type or value`.

Passing MATLAB SAFEARRAY to COM Object

The SAFEARRAY data type is a standard way to pass arrays between COM objects. This section explains how MATLAB passes SAFEARRAY data to a COM object.

- “Default Behavior in MATLAB Software” on page 12-63
- “Examples” on page 12-63
- “How to Pass a Single-Dimension SAFEARRAY” on page 12-64

- “Passing SAFEARRAY By Reference” on page 12-64

Default Behavior in MATLAB Software

MATLAB represents an m -by- n matrix as a two-dimensional SAFEARRAY, where the first dimension has m elements and the second dimension has n elements. MATLAB passes the SAFEARRAY by value.

Examples

The following examples use a COM object that expects a SAFEARRAY input parameter.

When MATLAB passes a 1-by-3 array :

```
B = [2 3 4]
B =
     2     3     4
```

the object reads:

```
No. of dimensions: 2
Dim: 1, No. of elements: 1
Dim: 2, No. of elements: 3
Elements:
  2.0
  3.0
  4.0
```

When MATLAB passes a 3-by-1 array:

```
C = [1;2;3]
C =
     1
     2
     3
```

the object reads:

```
No. of dimensions: 2
Dim: 1, No. of elements: 3
Dim: 2, No. of elements: 1
Elements:
  1.0
  2.0
  3.0
```

When MATLAB passes a 2-by-4 array:

```
D = [2 3 4 5;5 6 7 8]
```

```
D =  
    2    3    4    5  
    5    6    7    8
```

the object reads:

```
No. of dimensions: 2  
Dim: 1, No. of elements: 2  
Dim: 2, No. of elements: 4  
Elements:  
    2.0  
    3.0  
    4.0  
    5.0  
    5.0  
    6.0  
    7.0  
    8.0
```

How to Pass a Single-Dimension SAFEARRAY

For information about passing arguments as one-dimensional arrays to a COM object, see <http://www.mathworks.com/matlabcentral/answers/92424-how-can-i-pass-arguments-to-an-activex-server-from-matlab-7-0-r14-as-one-dimensional-arrays>.

Passing SAFEARRAY By Reference

For information about passing arguments by reference to a COM object, see <http://www.mathworks.com/matlabcentral/answers/94888-how-can-i-pass-arguments-by-reference-to-an-activex-server-from-matlab-7-0-r14>.

Reading SAFEARRAY from COM Objects in MATLAB Applications

This section explains how MATLAB reads SAFEARRAY data from a COM object.

MATLAB reads a one dimensional SAFEARRAY with n elements from a COM object as a 1-by-n matrix. For example, using methods from the MATLAB sample control `mwsamp`, type:

```
h=actxcontrol('mwsamp.mwsampctrl.1')
a = GetI4Vector(h)
```

MATLAB displays:

```
a =
      1      2      3
```

MATLAB reads a two-dimensional SAFEARRAY with *n* elements as a 2-by-*n* matrix. For example:

```
a = GetR8Array(h)
```

MATLAB displays:

```
a =
      1      2      3
      4      5      6
```

MATLAB reads a three-dimensional SAFEARRAY with two elements as a 2-by-2-by-2 cell array. For example:

```
a = GetBSTRArray(h)
```

MATLAB displays:

```
a(:,:,1) =
      '1 1 1'      '1 2 1'
      '2 1 1'      '2 2 1'

a(:,:,2) =
      '1 1 2'      '1 2 2'
      '2 1 2'      '2 2 2'
```

Displaying MATLAB Syntax for COM Objects

To determine which MATLAB types to use when passing arguments to COM objects, use the `invoke` or `methodsview` functions. These functions list all the methods found in an object, along with a specification of the types required for each argument.

Consider a server called `MyApp`, which has a single method `TestMeth1` with the following syntax:

```
HRESULT TestMeth1 ([out, retval] double* dret);
```

This method has no input argument, and it returns a variable of type **double**. The following **pseudo-code** displays the MATLAB syntax for calling the method.

```
h = actxserver('MyApp');  
invoke(h)
```

MATLAB displays:

```
ans =  
    TestMeth1 = double TestMeth1 (handle)
```

The signature of **TestMeth1** is:

```
double TestMeth1(handle)
```

MATLAB requires you to use an object handle as an input argument for every method, in addition to any input arguments required by the method itself.

Use one of the following **pseudo-code** commands to create the variable **var**, which is of type **double**.

```
var = h.TestMeth1;
```

or:

```
var = TestMeth1(h);
```

While the following syntax is correct, its use is discouraged:

```
var = invoke(h, 'TestMeth1');
```

Now consider the server called **MyApp1** with the following methods:

```
HRESULT TestMeth1 ([out, retval] double* dret);  
HRESULT TestMeth2 ([in] double* d, [out, retval] double* dret);  
HRESULT TestMeth3 ([out] BSTR* sout,  
                  [in, out] double* dinout,  
                  [in, out] BSTR* sinout,  
                  [in] short sh,  
                  [out] long* ln,  
                  [in, out] float* b1,  
                  [out, retval] double* dret);
```

Using the **invoke** function, MATLAB displays the list of methods:

```
ans =
  TestMeth1 = double TestMeth1 (handle)
  TestMeth2 = double TestMeth2 (handle, double)
  TestMeth3 = [double, string, double, string, int32, single] ...
              TestMeth3(handle, double, string, int16, single)
```

TestMeth2 requires an input argument `d` of type `double`, as well as returning a variable `dret` of type `double`. Some **pseudo-code** examples of calling TestMeth2 are:

```
var = h.TestMeth2(5);
```

or:

```
var = TestMeth2(h, 5);
```

TestMeth3 requires multiple input arguments, as indicated within the parentheses on the right side of the equals sign, and returns multiple output arguments, as indicated within the brackets on the left side of the equals sign.

```
[double, string, double, string, int32, single] %output arguments
TestMeth3(handle, double, string, int16, single) %input arguments
```

The first input argument is the required `handle`, followed by four input arguments.

```
TestMeth3(handle, in1, in2, in3, in4)
```

The first output argument is the return value `retval`, followed by five output arguments.

```
[retval, out1, out2, out3, out4, out5]
```

This is how the arguments map into a MATLAB command:

```
[dret, sout, dinout, sinout, ln, b1] = TestMeth3(handle, ...
                                             dinout, sinout, sh, b1)
```

where `dret` is `double`, `sout` is `string`, `dinout` is `double` and is both an input and an output argument, `sinout` is `string` (input and output argument), `ln` is `int32`, `b1` is `single` (input and output argument), `handle` is the handle to the object, and `sh` is `int16`.

Use MATLAB Application as Automation Client

In this section...

“MATLAB Sample Control” on page 12-68

“Using a MATLAB Application as an Automation Client” on page 12-68

“Connecting to an Existing Excel Application” on page 12-69

“Running a Macro in an Excel Server Application” on page 12-70

“MATLAB COM Client Example” on page 12-71

MATLAB Sample Control

MATLAB software ships with a simple example COM control that draws a circle on the screen, displays some text, and fires events when the user single- or double-clicks the control. Create the control by running the `mwsamp.m` file in the `matlabroot\toolbox\matlab\winfun` folder, or type:

```
h = actxcontrol('mwsamp.mwsampctr1.2',[0 0 300 300]);
```

This control is in the same folder, with the control's *type library*. The type library is a binary file used by COM tools to decipher the control's capabilities. For other examples using the `mwsamp2` control, see “Writing Event Handlers” on page 12-49.

Using a MATLAB Application as an Automation Client

This example uses MATLAB software as an Automation client and the Microsoft Excel spreadsheet program as the server. It provides a good overview of typical functions. In addition, it is a good example of using the Automation interface of another application:

```
% MATLAB Automation client example
%
% Open Excel, add workbook, change active worksheet,
% get/put array, save.

% First, open an Excel Server.
e = actxserver('Excel.Application');

% Insert a new workbook.
```

```
eWorkbook = e.Workbooks.Add;
e.Visible = 1;

% Make the first sheet active.
eSheets = e.ActiveWorkbook.Sheets;

eSheet1 = eSheets.get('Item', 1);
eSheet1.Activate;

% Put a MATLAB array into Excel.
A = [1 2; 3 4];
eActivsheetRange = e.Activesheet.get('Range', 'A1:B2');
eActivsheetRange.Value = A;

% Get back a range.
% It will be a cell array, since the cell range
% can contain different types of data.
eRange = e.Activesheet.get('Range', 'A1:B2');
B = eRange.Value;

% Convert to a double matrix. The cell array must contain only
% scalars.
B = reshape([B{:}], size(B));

% Now, save the workbook.
eWorkbook.SaveAs('myfile.xls');

% Avoid saving the workbook and being prompted to do so
eWorkbook.Saved = 1;
eWorkbook.Close;

% Quit Excel and delete the server.
Quit(e);
delete(e);
```

Note: Make sure that you always close any workbook objects you create. This can prevent potential memory leaks.

Connecting to an Existing Excel Application

You can give MATLAB access to a file that is open by another application by creating a new COM server from the MATLAB client, and then opening the file through this

server. This example shows how to do this for an Excel application that has a file `weekly_log.xls` open:

```
excelapp = actxserver('Excel.Application');  
wkbk = excelapp.Workbooks;  
wdata = wkbk.Open('d:\weatherlog\weekly_log.xls');
```

To see what methods are available, type:

```
wdata.methods  
Methods for class Interface.Microsoft_Excel_10.0_  
Object_Library._Workbook:  
  
AcceptAllChanges      LinkInfo              ReloadAs  
Activate              LinkSources          RemoveUser  
:                     :                     :  
:                     :                     :
```

Access data from the spreadsheet by selecting a particular sheet (called 'Week 12' in the example), selecting the range of values (the rectangular area defined by D1 and F6 here), and then reading from this range:

```
sheets = wdata.Sheets;  
sheet12 = sheets.Item('Week 12');  
range = sheet12.get('Range', 'D1', 'F6');  
range.value  
  
ans =  
    'Temp.'      'Heat Index'      'Wind Chill'  
    [78.4200]    [      32]        [      37]  
    [69.7300]    [      27]        [      30]  
    [77.6500]    [      17]        [      16]  
    [74.2500]    [      -5]        [       0]  
    [68.1900]    [      22]        [      35]
```

```
Close(wkbk);  
Quit(excelapp);
```

Running a Macro in an Excel Server Application

In the following example, MATLAB runs the Microsoft Excel spreadsheet program in a COM server and invokes a macro that has been defined within the active Excel spreadsheet file. The macro, `init_last`, takes no input parameters and is called from the MATLAB client using the statement:


```
handle.ExecuteExcel4Macro('!macroname()');
```

Start the example by opening the spreadsheet file and recording a macro. The macro used here simply sets all items in the last column to zero. Save your changes to the spreadsheet.

Next, in MATLAB, create a COM server running an Excel application, and open the spreadsheet:

```
h = actxserver('Excel.Application');
wkbk = h.Workbooks;
file = wkbk.Open('d:\weatherlog\weekly.xls');
```

Open the sheet that you want to change, and retrieve the current values in the range of interest:

```
sheets = file.Sheets;
sheet12 = sheets.Item('Week 12');
range = sheet12.get('Range', 'D1', 'F5');
range.Value
ans =
    [    78]    [    32]    [    37]
    [    69]    [    27]    [    30]
    [    77]    [    17]    [    16]
    [    74]    [    -5]    [    -1]
    [    68]    [    22]    [    35]
```

Now execute the macro, and verify that the values have changed as expected:

```
h.ExecuteExcel4Macro('!init_last()');
range.Value
ans =
    [    78]    [    32]    [     0]
    [    69]    [    27]    [     0]
    [    77]    [    17]    [     0]
    [    74]    [    -5]    [     0]
    [    68]    [    22]    [     0]
```

MATLAB COM Client Example

MATLAB includes an example, Programming with COM, that illustrates the use of the COM Client with MATLAB.

Deploy ActiveX Controls Requiring Run-Time Licenses

In this section...

“Create a Function to Build the Control” on page 12-72

“Build the Control and the License File” on page 12-72

“Build the Executable” on page 12-73

“Deploy the Files” on page 12-73

When you deploy a Microsoft ActiveX control that requires a run-time license, you must include a license key, which the control reads at run-time. If the key matches the control's own version of the license key, an instance of the control is created. Use the following procedure to deploy a run-time-licensed control with a MATLAB application.

Create a Function to Build the Control

First, create a function to build the control and save it as a `.m` file. The file must contain two elements:

- The pragma `##function actxlicense`. This pragma causes the MATLAB Compiler to embed a function named `actxlicense` into the standalone executable file you build.
- A call to `actxcontrol` to create an instance of the control.

Place this file in a folder outside of the MATLAB code tree.

Here is an example file:

```
function buildcontrol
##function actxlicense
h=actxcontrol('MFCCONTROL2.MFCControl2Ctrl.1',[10 10 200 200]);
```

Build the Control and the License File

Change to the folder where you placed the function you created to build the control. Call the function. When it executes this function, MATLAB determines whether the control requires a run-time license. If it does, MATLAB creates another file, named `actxlicense.m`, in the current working folder. The `actxlicense` function defined in this file provides the license key to MATLAB at run-time.

Build the Executable

Next, call MATLAB Compiler to create the standalone executable from the file you created to build the control. The executable contains both the function that builds the control and the `actxlicense` function.

```
mcc -m buildcontrol
```

Deploy the Files

Finally, distribute `buildcontrol.exe`, `buildcontrol.ctf`, and the control (`.ocx` or `.dll`).

Use Microsoft Forms 2.0 Controls

In this section...
“Affected Controls” on page 12-74
“Replacement Controls” on page 12-74

You might encounter problems when creating or using Microsoft Forms 2.0 controls in MATLAB. Forms 2.0 controls are designed for use with applications enabled by Microsoft Visual Basic for Applications (VBA). An example is Microsoft Office software.

To work around these problems, use the following replacement controls, or consult article 236458 in the Microsoft Knowledge Base for further information:

<http://support.microsoft.com/default.aspx?kbid=236458>

Affected Controls

You might see this behavior with any of the following Forms 2.0 controls:

- `Forms.TextBox.1`
- `Forms.CheckBox.1`
- `Forms.CommandButton.1`
- `Forms.Image.1`
- `Forms.OptionButton.1`
- `Forms.ScrollBar.1`
- `Forms.SpinButton.1`
- `Forms.TabStrip.1`
- `Forms.ToggleButton.1`

Replacement Controls

Microsoft recommends the following replacements:

Old	New
<code>Forms.TextBox.1</code>	<code>RICHTEXT.RichtextCtrl.1</code>

Old	New
Forms.CheckBox.1	vidtc3.Checkbox
Forms.CommandButton.1	MSComCtl2.FlatScrollBar.2
Forms.TabStrip.1	COMCTL.TabStrip.1

Use COM Collections

COM *collections* are a way to support groups of related COM objects that can be iterated over. A collection is itself a special interface with a **Count** property (read only), which contains the number of items in the collection, and an **Item** method, which allows you to retrieve a single item from the collection.

The **Item** method is indexed, which means that it requires an argument that specifies which item in the collection is being requested. The data type of the index can be any data type that is appropriate for the particular collection and is specific to the control or server that supports the collection. Although integer indices are common, the index could just as easily be a string value. Often, the return value from the **Item** method is itself an interface. Like all interfaces, release this interface when you are finished with it.

This example iterates through the members of a collection. Each member of the collection is itself an interface (called **Plot** and represented by a MATLAB COM object called **hPlot**.) In particular, this example iterates through a collection of **Plot** interfaces, invokes the **Redraw** method for each interface, and then releases each interface:

```
hCollection = hControl.Plots;
for i = 1:hCollection.Count
    hPlot = invoke(hCollection,'Item', i);
    Redraw(hPlot);
    release(hPlot);
end;
release(hCollection);
```

Use MATLAB Application as DCOM Client

Distributed Component Object Model (DCOM) is a protocol that allows clients to use remote COM objects over a network. Additionally, MATLAB can be used as a DCOM client with remote Automation servers if the operating system on which MATLAB is running is DCOM enabled.

Note: If you use MATLAB as a remote DCOM server, all MATLAB windows appears on the remote machine.

MATLAB COM Support Limitations

Limitations of MATLAB COM support are:

- MATLAB only supports indexed collections.
- COM controls are not printed with figure windows.
- “Unsupported Types” on page 12-62
- MATLAB does not support asynchronous events.
- A MATLAB COM ActiveX control container does not in-place activate controls until they are visible.

MATLAB COM Automation Server Support

- “Register MATLAB as Automation Server” on page 13-2
- “MATLAB COM Automation Server Interface” on page 13-4
- “Creating the MATLAB Server” on page 13-7
- “Connecting to an Existing MATLAB Server” on page 13-9
- “Using MATLAB Application as DCOM Server” on page 13-10
- “Using VT_DATE Data Type” on page 13-11
- “Data Types For Visual Basic .NET Clients” on page 13-12
- “Using the Visible Property” on page 13-13
- “Specifying Shared or Dedicated Server” on page 13-14
- “Manually Create Automation Server” on page 13-15
- “Launch MATLAB as Automation Server in Desktop Mode” on page 13-16
- “Call MATLAB Function from Visual Basic .NET Client” on page 13-17
- “Pass Complex Data to MATLAB from C# Client” on page 13-18
- “Call MATLAB Function from C# Client” on page 13-20
- “View MATLAB Functions from Visual Basic .NET Object Browser” on page 13-22
- “Waiting for MATLAB Application to Complete” on page 13-23

Register MATLAB as Automation Server

In this section...
“When to Register MATLAB” on page 13-2
“Register from System Prompt” on page 13-2
“Register from MATLAB Command Prompt” on page 13-3

When to Register MATLAB

To use MATLAB as an Automation server, you first must register the application in the Windows registry, which happens when you install a new version of MATLAB. If you have multiple versions of MATLAB installed on your system, only one version is registered. By default, this version is the last version you installed. This version remains registered until you manually change the registry, or install a new version.

To manually register MATLAB, choose one of these options:

- “Register from System Prompt” on page 13-2
- “Register from MATLAB Command Prompt” on page 13-3

You must have administrator privileges to change the Windows registry. Based on your User Account Control (UAC) settings, you might need to right-click the Windows Command Processor or the MATLAB icon and select **Run as administrator**. If that option is not available, contact your system administrator.

If MATLAB is unable to update the registry, it still displays a new minimized command window. Open this window and exit MATLAB.

Register from System Prompt

To register MATLAB as an Automation server from the Windows system prompt, first open a Windows Command Processor using the **Run as administrator** option, if necessary.

Move to the folder containing the executable file for the MATLAB version you want.

```
cd matlabroot\bin\arch
```

If you do not use this folder, the `matlab` command starts the first instance of MATLAB on the system path.

```
matlab -regserver
```

MATLAB displays a minimized command window. Open this window and exit MATLAB.

Register from MATLAB Command Prompt

To register MATLAB as an Automation server from within MATLAB, first start MATLAB, with the **Run as administrator** option, if necessary. Because you open MATLAB to run this command, you know what MATLAB version you will register.

```
!matlab -regserver
```

MATLAB opens a minimized command window. Open this window and exit MATLAB.

See Also

matlab (Windows)

More About

- “Creating the MATLAB Server” on page 13-7

MATLAB COM Automation Server Interface

In this section...
“COM Server Types” on page 13-4
“Shared and Dedicated Servers” on page 13-4
“Programmatic Identifiers” on page 13-4
“In-Process and Out-of-Process Servers” on page 13-5

COM Server Types

There are three types of COM servers:

- Automation — A server that supports the OLE Automation standard. Automation servers are based on the `IDispatch` interface. Clients of all types, including scripting clients, access Automation servers.
- Custom — A server that implements an interface directly derived from `IUnknown`. Custom servers are preferred when faster client access is critical.
- Dual — A server that implements a combination of Automation and Custom interfaces.

Shared and Dedicated Servers

The MATLAB Automation server has two modes:

- Shared — One or more client applications connect to the same MATLAB server. All clients share server.
- Dedicated — Each client application creates its own dedicated MATLAB server.

If you use `matlab.application` as your ProgID, MATLAB creates a shared server. For more information, see “Specifying Shared or Dedicated Server” on page 13-14.

Programmatic Identifiers

To create an instance of a COM object, you use its programmatic identifier, or *ProgID*. The ProgID is a unique string defined by the component vendor to identify the COM object. You obtain a ProgID from your vendor documentation.

The MATLAB ProgIDs for shared servers are:

- `Matlab.Application` — Starts a command window Automation server with the version of MATLAB that was most recently used as an Automation server (might not be the latest installed version of MATLAB).
- `Matlab.Autoserver` — Starts a command window Automation server using the most recent version of MATLAB.
- `Matlab.Desktop.Application` — Starts the full desktop MATLAB as an Automation server using the most recent version of MATLAB.

The ProgIDs for dedicated servers are:

- `Matlab.Application.Single`
- `Matlab.Autoserver.Single`

These version-independent MATLAB ProgIDs specify the currently installed and registered version of MATLAB.

In order to create an instance of a specific installed and registered MATLAB version, you can use a version-dependent ProgID. For example, using the ProgID `Matlab.Application.7.14` creates an instance of MATLAB version 7.14 (R2012a).

In-Process and Out-of-Process Servers

You can configure a server three ways. MATLAB supports all of these configurations.

- “In-Process Server” on page 13-5
- “Local Out-of-Process Server” on page 13-5
- “Remote Out-of-Process Server” on page 13-6

In-Process Server

An in-process server is a component implemented as a dynamic link library (DLL) or ActiveX control that runs in the same process as the client application, sharing address space. Communication between client and server is relatively fast and simple.

Local Out-of-Process Server

A local out-of-process server is a component implemented as an executable (EXE) file that runs in a separate process from the client application. The client and server processes are

on the same computer system. This configuration is slower due to the overhead required when transferring data across process boundaries.

Remote Out-of-Process Server

This is a type of out-of-process server; however, the client and server processes are on different systems and communicate over a network. Network communications, in addition to the overhead required for data transfer, can make this configuration slower than the local out-of-process configuration. This configuration runs only on systems that support the *Distributed Component Object Model (DCOM)*.

Creating the MATLAB Server

In this section...

“Getting Started” on page 13-7

“Get or Set the Status of a MATLAB Automation Server” on page 13-8

Getting Started

To create a server, you need a programmatic identifier (ProgID) to identify the server. The ProgID for MATLAB is `matlab.application`. For a complete list, see “Programmatic Identifiers” on page 13-4.

How you create an Automation server depends on the controller you are using. Consult your controller's documentation for this information. Possible options include:

- Add this statement to a Visual Basic .NET application.

```
MatLab = CreateObject("Matlab.Application")
```

- “Manually Create Automation Server” on page 13-15.
- From a Visual Basic project, “Accessing Methods from the Visual Basic Object Browser” on page 13-7.

Accessing Methods from the Visual Basic Object Browser

You can use the Object Browser of your Visual Basic client application to see what methods are available from a MATLAB Automation server. To do this you need to reference the MATLAB *type library* in your Visual Basic project.

To set up your Visual Basic project:

- 1 Select the **Project** menu.
- 2 Select **Reference** from the subsequent menu.
- 3 Check the box next to the **MATLAB Application Type Library**.
- 4 Click **OK**.

In your Visual Basic code, use the `New` method to create the server:

```
Matlab = New MApp.MApp
```

View MATLAB Automation methods from the Visual Basic Object Browser under the Library called MLAPP.

Get or Set the Status of a MATLAB Automation Server

To make MATLAB an Automation server, use the `enableservice` function. For example, type:

```
enableservice('AutomationServer',true)
```

To determine the current state of a MATLAB Automation server. type:

```
enableservice('AutomationServer')
```

If MATLAB displays:

```
ans =  
    1
```

then MATLAB is currently an Automation server.

See Also

`enableservice`

Related Examples

- “Manually Create Automation Server” on page 13-15

More About

- “Register MATLAB as Automation Server” on page 13-2
- “Programmatic Identifiers” on page 13-4
- “MATLAB Startup Folder”

Connecting to an Existing MATLAB Server

It is not always necessary to create a new instance of a MATLAB server whenever your application needs some task done in MATLAB. Clients can connect to an existing MATLAB Automation server using the `actxGetRunningServer` function or by using a command similar to the Visual Basic .NET `GetObject` command.

Using Visual Basic .NET Code

The Visual Basic .NET command shown here returns a handle `h` to the MATLAB server application:

```
h = GetObject(, "matlab.application")
```

Note: It is important to use the syntax shown above to connect to an existing MATLAB Automation server. Omit the first argument, and make sure the second argument is as shown.

The following Visual Basic .NET example connects to an existing MATLAB server, then executes a plot command in the server. If you do not already have a MATLAB server running, create one following the instructions in “Accessing Methods from the Visual Basic Object Browser” on page 13-7.

```
Dim h As Object
h = GetObject(, "matlab.application")

' Handle h should be valid now.
' Test it by calling Execute.
h.Execute ("plot([0 18], [7 23])")
```

Using MATLAB Application as DCOM Server

Distributed Component Object Model (DCOM) is a protocol that allows COM connections to be established over a network. If you are using a version of the Windows operating system that supports DCOM and a controller that supports DCOM, you can use the controller to start a MATLAB server on a remote machine.

To do this, DCOM must be configured properly, and MATLAB must be installed on each machine that is used as a client or server. (Even though the client machine may not be running MATLAB in such a configuration, the client machine must have a MATLAB installation because certain MATLAB components are required to establish the remote connection.) Consult the DCOM documentation for how to configure DCOM for your environment.

External Web Sites

- <http://www.mathworks.com/matlabcentral/answers/102255-how-can-i-make-a-dcom-server-instance-of-matlab-visible>
- <http://www.mathworks.com/matlabcentral/answers/95647-how-can-i-utilize-matlab-on-a-remote-machine-as-a-distributed-com-dcom-server>

Using VT_DATE Data Type

To pass a VT_DATE type input to a Visual Basic program or an ActiveX control method, use the MATLAB class `COM.date`. For example:

```
d = COM.date(2005,12,21,15,30,05);  
get(d)  
    Value: 7.3267e+005  
    String: '12/21/2005 3:30:05 PM'
```

Use the `now` function to set the `Value` property to a date number:

```
d.Value = now;
```

`COM.date` accepts the same input arguments as `datetime`.

Data Types For Visual Basic .NET Clients

Data types for the arguments and return values of the server functions are expressed as Automation data types, which are language-independent types defined by the Automation protocol.

For example, `BSTR` is a wide-character string type defined as an Automation type, and is the same data format used by the Visual Basic language to store strings. Any COM-compliant controller should support these data types, although the details of how you declare and manipulate these are controller specific.

Using the Visible Property

You have the option of making MATLAB visible or not by setting the `Visible` property. When visible, MATLAB appears on the desktop, enabling the user to interact with it. This might be useful for such purposes as debugging. When not visible, the MATLAB window does not appear, thus perhaps making for a cleaner interface and also preventing any interaction with the application.

By default, the `Visible` property is enabled, or set to 1. You can change the `Visible` property by setting it to 0 (invisible) or 1 (visible).

Specifying Shared or Dedicated Server

You can start the MATLAB Automation server in one of two modes – shared or dedicated. A dedicated server is dedicated to a single client; a shared server is shared by multiple clients. The mode is determined by the programmatic identifier (ProgID) used by the client to start MATLAB.

Starting a Shared Server

The ProgID, `matlab.application`, specifies the default mode, which is shared. You can also use the version-specific ProgID, `matlab.application.N.M`, where N is the major version and M is the minor version of your MATLAB. For example, use N = 7 and M = 4 for MATLAB version 7.4.

Once MATLAB is started as a shared server, all clients that request a connection to MATLAB using the shared server ProgID connect to the already running instance of MATLAB. In other words, there is never more than one instance of a shared server running, since it is shared by all clients that use the shared server ProgID.

Starting a Dedicated Server

To specify a dedicated server, use the ProgID, `matlab.application.single`, (or the version-specific ProgID, `matlab.application.single.N.M`).

Each client that requests a connection to MATLAB using a dedicated ProgID creates a separate instance of MATLAB; it also requests the server not be shared with any other client. Therefore, there can be several instances of a dedicated server running simultaneously, since the dedicated server is not shared by multiple clients.


Manually Create Automation Server

Microsoft Windows operating system automatically creates an Automation server when a controller application first establishes a server connection. Alternatively, you can manually create the server before starting any of the client processes.

To create a MATLAB server manually, use the `-automation` switch in the `matlab` startup command. From the operating system prompt, type:

```
matlab -automation
```

Alternatively, you can add this switch every time you run MATLAB, as follows:

- 1 Right-click the MATLAB shortcut icon  and select **Properties** from the context menu. The Properties dialog box for `matlab.exe` opens to the **Shortcut** tab.
- 2 In the **Target** field, add `-automation` to the end of the target path for `matlab.exe`. Be sure to include a space between the file name and the symbol `-`. For example:

```
"C:\Program Files\MATLAB\R2006a\bin\win32\MATLAB.exe -automation"
```

Note: When the operating system automatically creates a MATLAB server, it too uses the `-automation` switch. In this way, MATLAB servers are differentiated from other MATLAB sessions. This protects controllers from interfering with any interactive MATLAB sessions that might be running.

Launch MATLAB as Automation Server in Desktop Mode

To launch MATLAB as a COM Automation server in full desktop mode, use the programmatic identifier `Matlab.Desktop.Application`. For example, in Microsoft Visual Basic .NET:

```
Dim MatLab As Object  
Dim Result As String  
MatLab = CreateObject("Matlab.Desktop.Application")  
Result = MatLab.Execute("surf(peaks)")
```


Call MATLAB Function from Visual Basic .NET Client

This example calls a user-defined MATLAB function named `solve_bvp` from a Microsoft Visual Basic client application through a COM interface. It also plots a graph in a new MATLAB window and performs a simple computation:

```
Dim MatLab As Object
Dim Result As String
Dim MReal(1, 3) As Double
Dim MImag(1, 3) As Double

MatLab = CreateObject("Matlab.Application")

'Calling MATLAB function from VB
'Assuming solve_bvp exists at specified location
Result = MatLab.Execute("cd d:\matlab\work\bvp")
Result = MatLab.Execute("solve_bvp")

'Executing other MATLAB commands
Result = MatLab.Execute("surf(peaks)")
Result = MatLab.Execute("a = [1 2 3 4; 5 6 7 8]")
Result = MatLab.Execute("b = a + a ")
'Bring matrix b into VB program
MatLab.GetFullMatrix("b", "base", MReal, MImag)
```

Pass Complex Data to MATLAB from C# Client

This example creates data in the client C# program and passes it to MATLAB. The matrix (containing complex data) is then passed back to the C# program.

The reference to the MATLAB Type Library for C# is:

```
MApp.MLApp matlab = new MApp.MLApp();
```

From your C# client program, add a reference to your project to the MATLAB COM object. For example, in Microsoft Visual Studio, open your project. From the **Project** menu, select **Add Reference**. Select the **COM** tab in the Add Reference dialog box. Select the MATLAB application.

Here is the complete example:

```
using System;
namespace ConsoleApplication4
{
class Class1
{
[STAThread]
static void Main(string[] args)
{
MApp.MLApp matlab = new MApp.MLApp();

System.Array pr = new double[4];
pr.SetValue(11,0);
pr.SetValue(12,1);
pr.SetValue(13,2);
pr.SetValue(14,3);

System.Array pi = new double[4];
pi.SetValue(1,0);
pi.SetValue(2,1);
pi.SetValue(3,2);
pi.SetValue(4,3);

matlab.PutFullMatrix("a", "base", pr, pi);

System.Array prresult = new double[4];
System.Array piresult = new double[4];

matlab.GetFullMatrix("a", "base", ref prresult, ref piresult);
```

```
}  
}  
}
```

Call MATLAB Function from C# Client

This example shows how to call a user-defined MATLAB function, `myfunc`, from a C# application.

Create a MATLAB function, `myfunc`, in the folder `c:\temp\example`.

```
function [x,y] = myfunc(a,b,c)
x = a + b;
y = sprintf('Hello %s',c);
```

Create the C# application.

```
using System;
using System.Collections.Generic;
using System.Text;

namespace ConsoleApplication2
{
    class Program
    {
        static void Main(string[] args)
        {
            // Create the MATLAB instance
            MLab.MLab matlab = new MLab.MLab();

            // Change to the directory where the function is located
            matlab.Execute(@"cd c:\temp\example");

            // Define the output
            object result = null;

            // Call the MATLAB function myfunc
            matlab.Feval("myfunc", 2, out result, 3.14, 42.0, "world");

            // Display result
            object[] res = result as object[];

            Console.WriteLine(res[0]);
            Console.WriteLine(res[1]);
            Console.ReadLine();
        }
    }
}
```

In Microsoft Visual Studio, add a reference to your *C#* project to the MATLAB COM object. From the **Project** menu, select **Add Reference**.

Select the **COM** tab in the Add Reference dialog box.

Select the MATLAB application.

View MATLAB Functions from Visual Basic .NET Object Browser

You can find out what methods are available from a MATLAB Automation server using the Object Browser of your Microsoft Visual Basic client application. To do this, follow this procedure in the client application to reference the MATLAB Application Type Library:

- 1 Select the **Project** menu.
- 2 Select **Reference** from the subsequent menu.
- 3 Check the box next to the **MATLAB Application Type Library**.
- 4 Click **OK**.

This enables you to view MATLAB Automation methods from the Visual Basic Object Browser under the Library called MLAPP. You can also see a list of MATLAB Automation methods when you use the term `Matlab` followed by a period. For example:

```
Dim Matlab As MApp.MApp
Private Sub View_Methods()
Matlab = New MApp.MApp
'The next line shows a list of MATLAB Automation methods
Matlab.
End Sub
```

Waiting for MATLAB Application to Complete

When you call a MATLAB function from another program, the program might display a timeout message while waiting for the MATLAB function to complete. Refer to solutions posted in MATLAB Answers™ for tips for handling alerts from other programming languages.

External Web Sites

- Why does Microsoft Excel generate the message "Microsoft Excel is waiting for another application to complete an OLE action." when I use Spreadsheet Link EX?
- Server Busy: Matlab called from Visual Basic (VB, VBA)

Using Web Services with MATLAB

- “Set Up WSDL Tools” on page 14-2
- “Display a World Map” on page 14-3
- “Using WSDL Web Service with MATLAB” on page 14-8
- “Access Services That Use WSDL Documents” on page 14-10
- “Error Handling” on page 14-12
- “XML-MATLAB Data Type Conversion” on page 14-14
- “Limitations to WSDL Document Support” on page 14-16

Set Up WSDL Tools

This example shows how to find information to install the programs required to use a WSDL Web service in MATLAB. You need supported versions of the Oracle® Java JDK and the Apache™ CXF programs. While the programs are available at no charge, they require several hundred megabytes of disk space.

- Download and install the JDK software from the Java SE Downloads Web page. Use Java SE version 7uXX, where XX is the latest update.
- Download and install Apache CXF software from the Apache CXF Web page. Choose the latest release of version 2.7.
- Make note of the installation folders created by these programs. Set the paths to the these variables, `jdk = 'YOUR_JDK_PATH'` and `cxf = 'YOUR_CXF_PATH'`, then call:

```
matlab.wsd1.setWSDLToolPath('JDK',jdk,'CXF',cxf)
```

See Also

`matlab.wsd1.setWSDLToolPath`

External Web Sites

- <http://www.oracle.com/technetwork/java/javase/downloads>
- <http://cxf.apache.org/download>

Display a World Map

This example shows how to access imagery from the United States Geological Survey (USGS) National Map SOAP server. To create the map, you need the following information.

- Get a map tile.
- Get the map name.
- Get the format of the tiles.

This example shows you how to call functions in the USGS Web service, `USGSImageryOnly_MapServer`, to get this information.

You must install the Java JDK and Apache CXF programs and set the tool paths to run this example.

```
p = matlab.wsd1.setWSDLToolPath;
if (isempty(p.JDK) || isempty(p.CXF))
    disp('Install the Java Development Kit (JDK) and Apache CXF programs.')
    disp('See the Set Up WSDL Tools link at the end of this example.')
else
    disp('Paths set to:')
    matlab.wsd1.setWSDLToolPath
end
```

Change your current folder to a writable folder.

Assign the WSDL URL.

```
wsd1File = ...
'http://basemap.nationalmap.gov/arcgis/services/USGSImageryOnly/MapServer?wsdl';
```

Create the class files for the client.

```
matlab.wsd1.createWSDLClient(wsd1File)
```

```
Created USGSImageryOnly_MapServer.
.\USGSImageryOnly_MapServer.m
.\+wsdl
```

In order to use `USGSImageryOnly_MapServer`, you must run `javaaddpath('.\+wsdl\mapserver`

```
ans =
```

```
@USGSImageryOnly_MapServer
```

Add the jar files to the Java path.

```
javaaddpath( './+wsdl\mapserver.jar' )
```

Start the service.

```
wsdl = USGSImageryOnly_MapServer;
```

Explore the service.

```
help USGSImageryOnly_MapServer
```

```
USGSImageryOnly_MapServer  A client to connect to the USGSImageryOnly_MapServer service.  
SERVICE = USGSImageryOnly_MapServer connects to http://basemap.nationalmap.gov/arcgis
```

```
To communicate with the service, call a function on the SERVICE:
```

```
[...] = FUNCTION(SERVICE,arg,...)
```

```
See doc USGSImageryOnly_MapServer for a list of functions.
```

Click the link `doc USGSImageryOnly_MapServer`. MATLAB opens a reference page for `USGSImageryOnly_MapServer` in the Help browser.

Read the documentation for the required inputs to the `GetMapTile` function.

```
help GetMapTile
```

```
--- help for USGSImageryOnly_MapServer/GetMapTile ---
```

```
GetMapTile
```

```
Result = GetMapTile(obj,MapName,Level,Row,Column,Format)
```

```
Inputs:
```

```
obj - USGSImageryOnly_MapServer object
```

```
MapName - string
```

```
Level - numeric scalar (XML int)
```

```
Row - numeric scalar (XML int)
```

```
Column - numeric scalar (XML int)
```

```
Format - string
```

```
Output:
```

```
Result - vector of numbers 0-255 (XML base64Binary)
```

See also `USGSImageryOnly_MapServer`.

You need `MapName`, `Level`, `Row`, `Column`, and `Format` input arguments.

Read the documentation for a function that provides a map name, `GetDefaultMapName`.

help `GetDefaultMapName`

```
--- help for USGSImageryOnly_MapServer/GetDefaultMapName ---
```

```
GetDefaultMapName
Result = GetDefaultMapName(obj)
Inputs:
  obj - USGSImageryOnly_MapServer object
Output:
  Result - string
```

See also `USGSImageryOnly_MapServer`.

This function provides a map name.

Read the documentation for a function that provides a map format information, `GetTileImageInfo`.

help `GetTileImageInfo`

```
--- help for USGSImageryOnly_MapServer/GetTileImageInfo ---
```

```
GetTileImageInfo
Result = GetTileImageInfo(obj,MapName)
Inputs:
  obj - USGSImageryOnly_MapServer object
  MapName - string
Output:
  Result - TileImageInfo object
```

See also `USGSImageryOnly_MapServer`.

This function returns a `TileImageInfo` object.

Read the documentation for the `TileImageInfo` object by clicking the link in the help display to `TileImageInfo`.

```
TileImageInfo(CacheTileFormat,CompressionQuality,Antialiasing) TileImageInfo object fo
```

```
CacheTileFormat - string
    The cache tile format.
CompressionQuality - numeric scalar (XML int)
    The cache tile image compression quality.
Antialiasing - string
See also
USGSImageryOnly_MapServer.
```

MATLAB opens a document in the Help browser. The format information is `CacheTileFormat`.

Create the JPEG data. The following codes requires knowledge of the JPEG image format and the tiling scheme used by the USGS server.

```
% Get the default map name.
defaultMapName = GetDefaultMapName(wsd1);

% Get the map count.
count = GetMapCount(wsd1);

% Get the map name. There is only one map (count value),
% but the index is zero-based.
mapName = GetMapName(wsd1, count-1);

% Get information about the tiles.
tileImageInfo = GetTileImageInfo(wsd1, mapName);

% Get the format of the data.
format = tileImageInfo.CacheTileFormat;

% Since format is specified as 'Mixed' it implies that
% the result of GetMapTile is a JPEG-encoded stream.
% The map tiles are organized with the lowest level as
% the lowest level of detail and the tiles use
% zero-based indexing.
level = 0;
row = 0;
col = 0;
jpeg = GetMapTile(wsd1, mapName, level, row, col, format);
```

Write the JPEG-encoded data to a file. Use `imread` to read and decode the JPEG data and return a M-by-N-by-3 `uint8` matrix.

```
ext = '.jpg';
filename = ['USGSImageryOnly_MapServer' '0_0_0' ext];
```

```
fid = fopen(tilename, 'w');  
fwrite(fid, jpeg);  
fclose(fid);
```

View the map.

```
tileImage = imread(tilename);  
figure  
imshow(tileImage)
```

Related Examples

- “Set Up WSDL Tools” on page 14-2

Using WSDL Web Service with MATLAB

In this section...

“What Are Web Services in MATLAB?” on page 14-8

“What are WSDL Documents?” on page 14-8

“What You Need to Use WSDL with MATLAB” on page 14-9

What Are Web Services in MATLAB?

Web services allow applications running on disparate computers, operating systems, and development environments to communicate with each other. There are two ways to use Web services in MATLAB. When the service you want to use provides:

- RESTful (Representational state transfer), use the `webread` and `websave` functions in “Web Access”.
- Web Services Description Language (WSDL) document, use the MATLAB `matlab.wsd1.createWSDIClient` function, described in the following topics.

What are WSDL Documents?

Using a Web service based on Web Services Description Language (WSDL) document technologies, client workstations access and execute APIs residing on a remote server. The client and server communicate via XML-formatted messages, following the W3C[®] SOAP protocol, and typically via the HTTP protocol.

Using the WSDL interface, MATLAB acts as a Web service client, providing functions you use to access existing services on a server. The functions facilitate communication with the server, relieving you of the need to work with XML, complex SOAP messages, and special Web service tools. Through these functions, you use services in your normal MATLAB environment, such as in the Command Window and in MATLAB programs you write.




Diagram Showing Web Services in MATLAB

An organization that wants to make APIs available to disparate clients creates the APIs and related Web service facilities for the server. Organizations either choose to make the services available only to local clients via the organization's intranet, or offer them to the general public via the Web.

What You Need to Use WSDL with MATLAB

You need to find out from your own organization and the organizations you work with if they provide a Web service of interest to you. There are publicly available services, some for free and some provided for a fee.

Functions for MATLAB WSDL Web services work with services that comply with the Basic Profile 1 to SOAP Binding specification.

You need to know basic information about the service you want to use, provided by the documentation for the service.

You need access to the server from the workstation where you use MATLAB. If there is a proxy server, provide any required settings using Web preferences. To do so, see “Specify Proxy Server Settings for Connecting to the Internet”.

Access Services That Use WSDL Documents

A WSDL document uses a standard format to describe a server's operations, arguments, and transactions. The `matlab.wsdl.createWSDLClient` function creates a MATLAB class that allows you to use the server APIs.

To use the `matlab.wsdl.createWSDLClient` function, you need to know the location of the service's WSDL document. The function works with WSDL documents that comply with the WS-I 1.0 standard and use one of these forms: RPC-literal, Document-literal, or Document-literal-wrapped. `matlab.wsdl.createWSDLClient` does not support RPC-encoded.

You must download supported versions of the Oracle Java JDK and the Apache CXF programs.

To access a service:

- 1 Install and/or locate the Java JDK and Apache CXF programs.
- 2 Set the paths to the JDK and CXF programs using the `matlab.wsdl.setWSDLToolPath` function. Values for the paths are saved across sessions in your user preferences, so you only need to specify them once.
- 3 Change the MATLAB current folder to the location where you want to use the files generated from the WSDL document. You must have write-permission for this folder.
- 4 Run `matlab.wsdl.createWSDLClient`, supplying the WSDL document location, which can be a URL or a path to a file.

The function converts the server's APIs to a MATLAB class, and creates a class folder in the current folder. The class folder contains methods for using the server's APIs. The function always creates a constructor method that has the same name as the class.

You only need to run the `matlab.wsdl.createWSDLClient` function once. You can access the class anytime after that.

- 5 Create an object of the class whenever you want to use the operations of the service.
- 6 View information about the class to see what methods (operations) are available for you to use.
- 7 Use the methods of the object to run applications on and exchange data with the server.

MATLAB automatically converts XML data types to MATLAB types, and vice versa.

See Also

`matlab.wsd1.createWSDLClient` | `matlab.wsd1.setWSDLToolPath`

Related Examples

- “Set Up WSDL Tools” on page 14-2

More About

- “XML-MATLAB Data Type Conversion” on page 14-14
- “Limitations to WSDL Document Support” on page 14-16

Error Handling

In this section...

- “Considerations Using Web Services” on page 14-12
- “Error Handling with try/catch Statements” on page 14-12
- “Use a Local Copy of the WSDL Document” on page 14-12
- “Java Errors Accessing Service” on page 14-13
- “Anonymous Types Not Supported” on page 14-13

Considerations Using Web Services

When creating MATLAB files that rely on a Web service, consider the following:

- A server issues a time-out error. Repeat the MATLAB command.
- Internet performance might make your application performance unpredictable.
- Conventions and established procedures for services and related technologies, like WSDL and SOAP, are still evolving. You might find inconsistencies or unexpected behavior when using a Web service.
- A service might change over time, which can impact its usage and results in MATLAB.
- A server issues other unrecoverable errors.

Error Handling with try/catch Statements

Use the `error` function in `try/catch` statements to catch errors that result from method calls or from the `matlab.wsd1.createWSDLClient` function.

Use a Local Copy of the WSDL Document

You can achieve better performance if you create a local copy and use the local copy instead of the version at the URL.

```
wsd1URL = ...  
['http://basemap.nationalmap.gov/arcgis/services/USGSImageryOnly/MapServer?wsdl'];  
wsdlFile = 'USGSImageryOnly_MapServer';  
if ~exist(wsd1File, 'file')
```

```
    websave(wsdlFile, wsdlURL);  
end
```

Use this strategy when you do not need immediate access to data at the URL.

Java Errors Accessing Service

Once you access a service from MATLAB using the generated client code, you might get Java errors if:

- The WSDL for the service changes and you run `matlab1.wsdl.createWSDLClient` again for the same service in the same MATLAB session.
- You try to access the service using the regenerated code.

These errors are likely to occur if you modify the service between successive calls to `matlab1.wsdl.createWSDLClient`.

If you change a service you already accessed or generate the class files in another location, restart MATLAB.

Anonymous Types Not Supported

Anonymous XML types are unnamed types embedded in other types.

For more information, see the IBM® article, “Web services hints and tips: avoid anonymous types,” at <http://www.ibm.com/developerworks/library/ws-avoid-anonymous-types>.

See Also

error

More About

- “Exception Handling in a MATLAB Application”

External Web Sites

- W3C status codes for HTTP errors

XML-MATLAB Data Type Conversion

MATLAB SOAP functions automatically convert XML data types used in SOAP messages to MATLAB types (classes), and vice-versa. The following table contains the XML type and the corresponding MATLAB type for scalar values used in a WSDL document.

XML Schema Type	MATLAB Type Returned—Scalar
boolean	logical
byte	int8
unsignedByte	uint8
short	int16
unsignedShort	uint16
int	int32
unsignedInt	uint32
long	int64
unsignedLong	uint64
float	double
double	double
string	char array
gYear, gMonth, gDay, gYearMonth, gMonthDay	calendarDuration array
dateTime	dateTime
date	dateTime with Year, Month, Day fields undefined.
time	dateTime with Hours, Minutes, Seconds fields undefined.
duration	duration if no year, month or day calendarDuration otherwise
NOTATION, QName	string containing a legal QName
hexbinary, base64Binary	N-by-1 vector of uint8 representing byte values (0-255) of encoded data

XML Schema Type	MATLAB Type Returned—Scalar
decimal, integer, nonPositiveInteger, nonNegativeInteger, positiveInteger, negativeInteger	double array

The following table contains the XML type and the corresponding MATLAB type for arrays.

XML Schema Type—Array	MATLAB Type Returned—Array
array of string	N-by-1 cell array of string
array of any <i>type</i>	N-by-1 vector of specified <i>type</i>
array of hexbinary, base64Binary	Not supported

Limitations to WSDL Document Support

RPC-encoded WSDL documents are not supported. For these documents, use `createClassFromWsdL`.

The following WSDL documents are not supported:

- Documents that the Apache CXF program cannot compile into complete code.
- Documents that import other WSDL documents that contain WSDL type definitions.
- On Windows, documents that import other WSDL documents might fail if the imported URI contains certain punctuation characters.
- Some documents with messages containing multiple parts.
- Some documents with schemas containing anonymous complex types.
- Some documents defining an input parameter to an operation as a simple type. When you invoke such an operation, for example `GetMyOp`, MATLAB displays one of the following errors.

```
Error using xxx/GetMyOp. Too many input arguments.
```

Or:

```
Error using matlab.internal.callJava  
No GetMyOp method with appropriate signature exists in Java class $Proxy57
```


Serial Port I/O

- “Capabilities and Supported Interfaces and Platforms” on page 15-2
- “Overview of the Serial Port” on page 15-4
- “Getting Started with Serial I/O” on page 15-16
- “Creating a Serial Port Object” on page 15-22
- “Connecting to the Device” on page 15-26
- “Configuring Communication Settings” on page 15-27
- “Writing and Reading Data” on page 15-28
- “Events and Callbacks” on page 15-46
- “Using Control Pins” on page 15-54
- “Debugging: Recording Information to Disk” on page 15-60
- “Saving and Loading” on page 15-66
- “Disconnecting and Cleaning Up” on page 15-68
- “Property Reference” on page 15-70
- “Properties — Alphabetical List” on page 15-74

Capabilities and Supported Interfaces and Platforms

In this section...

“What Is the MATLAB Serial Port Interface?” on page 15-2

“Supported Serial Port Interface Standards” on page 15-3

“Supported Platforms” on page 15-3

“Using the Examples with Your Device” on page 15-3

What Is the MATLAB Serial Port Interface?

The MATLAB serial port interface provides direct access to peripheral devices such as modems, printers, and scientific instruments that you connect to your computer's serial port. This interface is established through a serial port object. The serial port object supports functions and properties that allow you to

- Configure serial port communications
- Use serial port control pins
- Write and read data
- Use events and callbacks
- Record information to disk

Instrument Control Toolbox™ software provides additional serial port functionality. In addition to command-line access, this toolbox has a graphical tool called the Test & Measurement Tool, which allows you to communicate with, configure, and transfer data with your serial device without writing code. The Test & Measurement Tool generates MATLAB code for your serial device that you can later reuse to communicate with your device or to develop UI-based applications. The toolbox includes additional serial I/O utility functions that facilitate object creation and configuration, instrument communication, and so on. With the toolbox you can communicate with GPIB- or VISA-compatible instruments.

If you want to communicate with PC-compatible data acquisition hardware such as multifunction I/O boards, you need Data Acquisition Toolbox™ software.

For more information about these products, visit the MathWorks website at <http://www.mathworks.com/products>.

Supported Serial Port Interface Standards

Over the years, several serial port interface standards have been developed. These standards include RS-232, RS-422, and RS-485 - all of which are supported by the MATLAB serial port object. Of these, the most widely used interface standard for connecting computers to peripheral devices is RS-232.

This guide assumes you are using the RS-232 standard, discussed in “Overview of the Serial Port” on page 15-4. Refer to your computer and device documentation to see which interface standard you can use.

Supported Platforms

The MATLAB serial port interface is supported on:

- Linux 32-bit
- Linux 64-bit
- Mac OS X
- Mac OS X 64-bit
- Microsoft Windows 32-bit
- Microsoft Windows 64-bit

Using the Examples with Your Device

Many of the examples in this section reflect specific peripheral devices connected to a serial port — in particular a Tektronix[®] TDS 210 two-channel oscilloscope connected to the COM1 port, on a Windows platform. Therefore, many of the string commands are specific to this instrument and platform.

If you are using a different platform, or your peripheral device is connected to a different serial port, or if it accepts different commands, modify the examples accordingly.

Overview of the Serial Port

In this section...

“Introduction” on page 15-4

“What Is Serial Communication?” on page 15-4

“The Serial Port Interface Standard” on page 15-4

“Connecting Two Devices with a Serial Cable” on page 15-5

“Serial Port Signals and Pin Assignments” on page 15-6

“Serial Data Format” on page 15-10

“Finding Serial Port Information for Your Platform” on page 15-13

“Using Virtual USB Serial Ports” on page 15-15

“Selected Bibliography” on page 15-15

Introduction

For many serial port applications, you can communicate with your device without detailed knowledge of how the serial port works. If your application is straightforward, or if you are already familiar with the previously mentioned topics, you might want to begin with “The Serial Port Session” on page 15-16 to see how to use your serial port device with MATLAB software.

What Is Serial Communication?

Serial communication is the most common low-level protocol for communicating between two or more devices. Normally, one device is a computer, while the other device can be a modem, a printer, another computer, or a scientific instrument such as an oscilloscope or a function generator.

As the name suggests, the serial port sends and receives bytes of information in a serial fashion — one bit at a time. These bytes are transmitted using either a binary (numerical) format or a text format.

The Serial Port Interface Standard

The serial port interface for connecting two devices is specified by the TIA/EIA-232C standard published by the Telecommunications Industry Association.

The original serial port interface standard was given by RS-232, which stands for Recommended Standard number 232. The term *RS-232* is still in popular use, and is used in this guide when referring to a serial communication port that follows the TIA/EIA-232 standard. RS-232 defines these serial port characteristics:

- The maximum bit transfer rate and cable length
- The names, electrical characteristics, and functions of signals
- The mechanical connections and pin assignments

Primary communication is accomplished using three pins: the Transmit Data pin, the Receive Data pin, and the Ground pin. Other pins are available for data flow control, but are not required.

Other standards such as RS-485 define additional functionality such as higher bit transfer rates, longer cable lengths, and connections to as many as 256 devices.


Connecting Two Devices with a Serial Cable

The RS-232 standard defines the two devices connected with a serial cable as the Data Terminal Equipment (DTE) and Data Circuit-Terminating Equipment (DCE). This terminology reflects the RS-232 origin as a standard for communication between a computer terminal and a modem.


Throughout this guide, your computer is considered a DTE, while peripheral devices such as modems and printers are considered DCEs. Many scientific instruments function as DTEs.

Because RS-232 mainly involves connecting a DTE to a DCE, the pin assignments are defined such that straight-through cabling is used, where pin 1 is connected to pin 1, pin 2 is connected to pin 2, and so on. The following diagram shows a DTE to DCE serial connection using the transmit data (TD) pin and the receive data (RD) pin.

For more information about serial port pins, see “Serial Port Signals and Pin Assignments” on page 15-6.



If you connect two DTEs or two DCEs using a straight serial cable, the TD pins on each device are connected to each other, and the RD pins on each device are connected to each other. Therefore, to connect two like devices, you must use a *null modem* cable. As shown in the following diagram, null modem cables cross the transmit and receive lines in the cable.




Note: You can connect multiple RS-422 or RS-485 devices to a serial port. If you have an RS-232/RS-485 adaptor, you can use the MATLAB serial port object with these devices.

Serial Port Signals and Pin Assignments

Serial ports consist of two signal types: data signals and control signals. To support these signal types, as well as the signal ground, the RS-232 standard defines a 25-pin connection. However, most Windows and UNIX platforms use a 9-pin connection. In fact, only three pins are required for serial port communications: one for receiving data, one for transmitting data, and one for the signal ground.

The following diagram shows the pin assignment scheme for a 9-pin male connector on a DTE.



The pins and signals associated with the 9-pin connector are described in the following table. Refer to the RS-232 standard for a description of the signals and pin assignments used for a 25-pin connector.

Serial Port Pin and Signal Assignments

Pin	Label	Signal Name	Signal Type
1	CD	Carrier Detect	Control
2	RD	Received Data	Data
3	TD	Transmitted Data	Data
4	DTR	Data Terminal Ready	Control
5	GND	Signal Ground	Ground
6	DSR	Data Set Ready	Control
7	RTS	Request to Send	Control
8	CTS	Clear to Send	Control
9	RI	Ring Indicator	Control

The term *data set* is synonymous with *modem* or *device*, while the term *data terminal* is synonymous with *computer*.

Note: The serial port pin and signal assignments are with respect to the DTE. For example, data is transmitted from the TD pin of the DTE to the RD pin of the DCE.


Signal States

Signals can be in either an *active* state or an *inactive* state. An active state corresponds to the binary value 1, while an inactive state corresponds to the binary value 0. An active signal state is often described as *logic 1*, *on*, *true*, or a *mark*. An inactive signal state is often described as *logic 0*, *off*, *false*, or a *space*.

For data signals, the **on** state occurs when the received signal voltage is more negative than -3 volts, while the **off** state occurs for voltages more positive than 3 volts. For control signals, the **on** state occurs when the received signal voltage is more positive than 3 volts, while the **off** state occurs for voltages more negative than -3 volts. The voltage between -3 volts and +3 volts is considered a transition region, and the signal state is undefined.

To bring the signal to the **on** state, the controlling device *unasserts* (or *lowers*) the value for data pins and *asserts* (or *raises*) the value for control pins. Conversely, to bring the signal to the **off** state, the controlling device asserts the value for data pins and unasserts the value for control pins.

The following diagram shows the on and off states for a data signal and for a control signal.



The Data Pins

Most serial port devices support *full-duplex* communication meaning that they can send and receive data at the same time. Therefore, separate pins are used for transmitting and receiving data. For these devices, the TD, RD, and GND pins are used. However, some types of serial port devices support only one-way or *half-duplex* communications. For these devices, only the TD and GND pins are used. This guide assumes that a full-duplex serial port is connected to your device.

The TD pin carries data transmitted by a DTE to a DCE. The RD pin carries data that is received by a DTE from a DCE.

The Control Pins

The control pins of a 9-pin serial port are used to determine the presence of connected devices and control the flow of data. The control pins include

- “The RTS and CTS Pins” on page 15-8
- “The DTR and DSR Pins” on page 15-9
- “The CD and RI Pins” on page 15-9

The RTS and CTS Pins

The RTS and CTS pins are used to signal whether the devices are ready to send or receive data. This type of data flow control—called *hardware handshaking*—is used

to prevent data loss during transmission. When enabled for both the DTE and DCE, hardware handshaking using RTS and CTS follows these steps:

- 1 The DTE asserts the RTS pin to instruct the DCE that it is ready to receive data.
- 2 The DCE asserts the CTS pin indicating that it is clear to send data over the TD pin. If data can no longer be sent, the CTS pin is unasserted.
- 3 The data is transmitted to the DTE over the TD pin. If data can no longer be accepted, the RTS pin is unasserted by the DTE and the data transmission is stopped.

To enable hardware handshaking in MATLAB software, see “Controlling the Flow of Data: Handshaking” on page 15-57.

The DTR and DSR Pins

Many devices use the DSR and DTR pins to signal if they are connected and powered. Signaling the presence of connected devices using DTR and DSR follows these steps:

- 1 The DTE asserts the DTR pin to request that the DCE connect to the communication line.
- 2 The DCE asserts the DSR pin to indicate it is connected.
- 3 DCE unasserts the DSR pin when it is disconnected from the communication line.

The DTR and DSR pins were originally designed to provide an alternative method of hardware handshaking. However, the RTS and CTS pins are usually used in this way, and not the DSR and DTR pins. Refer to your device documentation to determine its specific pin behavior.

The CD and RI Pins


The CD and RI pins are typically used to indicate the presence of certain signals during modem-modem connections.

A modem uses a CD pin to signal that it has made a connection with another modem, or has detected a carrier tone. CD is asserted when the DCE is receiving a signal of a suitable frequency. CD is unasserted if the DCE is not receiving a suitable signal.

The RI pin is used to indicate the presence of an audible ringing signal. RI is asserted when the DCE is receiving a ringing signal. RI is unasserted when the DCE is not receiving a ringing signal (e.g., it is between rings).

Serial Data Format

The serial data format includes one start bit, between five and eight data bits, and one stop bit. A parity bit and an additional stop bit might be included in the format as well. The following diagram illustrates the serial data format.



The following notation expresses the format for serial port data:

number of data bits - parity type - number of stop bits

For example, 8-N-1 is interpreted as eight data bits, no parity bit, and one stop bit, while 7-E-2 is interpreted as seven data bits, even parity, and two stop bits.

The data bits are often referred to as a *character* because these bits usually represent an ASCII character. The remaining bits are called *framing bits* because they frame the data bits.

Bytes Versus Values

A *byte* is the collection of bits that comprise the serial data format. At first, this term might seem inaccurate because a byte is 8 bits and the serial data format can range between 7 bits and 12 bits. However, when serial data is stored on your computer, the framing bits are stripped away, and only the data bits are retained. Moreover, eight data bits are always used regardless of the number of data bits specified for transmission, with the unused bits assigned a value of 0.

When reading or writing data, you might need to specify a *value*, which can consist of one or more bytes. For example, if you read one value from a device using the `int32` format, that value consists of four bytes. For more information about reading and writing values, see “Writing and Reading Data” on page 15-28.

Synchronous and Asynchronous Communication

The RS-232 standard supports two types of communication protocols: synchronous and asynchronous.

Using the synchronous protocol, all transmitted bits are synchronized to a common clock signal. The two devices initially synchronize themselves to each other, and continually send characters to stay synchronized. Even when actual data is not really being sent, a constant flow of bits allows each device to know where the other is at any given time. That is, each bit that is sent is either actual data or an idle character. Synchronous communications allows faster data transfer rates than asynchronous methods, because additional bits to mark the beginning and end of each data byte are not required.

Using the asynchronous protocol, each device uses its own internal clock, resulting in bytes that are transferred at arbitrary times. So, instead of using time as a way to synchronize the bits, the data format is used.

In particular, the data transmission is synchronized using the start bit of the word, while one or more stop bits indicate the end of the word. The requirement to send these additional bits causes asynchronous communications to be slightly slower than synchronous. However, it has the advantage that the processor does not have to deal with the additional idle characters. Most serial ports operate asynchronously.

Note: When used in this guide, the terms *synchronous* and *asynchronous* refer to whether read or write operations block access to the MATLAB command line. For more information, see “Controlling Access to the MATLAB Command Line” on page 15-29.

How Are the Bits Transmitted?

By definition, serial data is transmitted one bit at a time. The order in which the bits are transmitted is:

- 1 The start bit is transmitted with a value of 0.
- 2 The data bits are transmitted. The first data bit corresponds to the least significant bit (LSB), while the last data bit corresponds to the most significant bit (MSB).
- 3 The parity bit (if defined) is transmitted.
- 4 One or two stop bits are transmitted, each with a value of 1.

The *baud rate* is the number of bits transferred per second. The transferred bits include the start bit, the data bits, the parity bit (if defined), and the stop bits.

Start and Stop Bits

As described in “Synchronous and Asynchronous Communication” on page 15-10, most serial ports operate asynchronously. This means that the transmitted byte must be

identified by start and stop bits. The start bit indicates when the data byte is about to begin; the stop bit(s) indicate(s) when the data byte has been transferred. The process of identifying bytes with the serial data format follows these steps:

- 1 When a serial port pin is idle (not transmitting data), it is in an **on** state.
- 2 When data is about to be transmitted, the serial port pin switches to an **off** state due to the start bit.
- 3 The serial port pin switches back to an **on** state due to the stop bit(s). This indicates the end of the byte.

Data Bits

The data bits transferred through a serial port might represent device commands, sensor readings, error messages, and so on. The data can be transferred as either binary data or ASCII data.

Most serial ports use between five and eight data bits. Binary data is typically transmitted as eight bits. Text-based data is transmitted as either seven bits or eight bits. If the data is based on the ASCII character set, a minimum of seven bits is required because there are 2^7 or 128 distinct characters. If an eighth bit is used, it must have a value of 0. If the data is based on the extended ASCII character set, eight bits must be used because there are 2^8 or 256 distinct characters.

The Parity Bit

The parity bit provides simple error (parity) checking for the transmitted data. The following table shows the types of parity checking.

Parity Types

Parity Type	Description
Even	The data bits plus the parity bit result in an even number of 1s.
Mark	The parity bit is always 1.
Odd	The data bits plus the parity bit result in an odd number of 1s.
Space	The parity bit is always 0.

Mark and space parity checking are seldom used because they offer minimal error detection. You might choose to not use parity checking at all.

The parity checking process follows these steps:

- 1 The transmitting device sets the parity bit to 0 or to 1, depending on the data bit values and the type of parity-checking selected.
- 2 The receiving device checks if the parity bit is consistent with the transmitted data. If it is, the data bits are accepted. If it is not, an error is returned.

Note: Parity checking can detect only 1-bit errors. Multiple-bit errors can appear as valid data.

For example, suppose the data bits 01110001 are transmitted to your computer. If even parity is selected, the parity bit is set to 0 by the transmitting device to produce an even number of 1s. If odd parity is selected, the parity bit is set to 1 by the transmitting device to produce an odd number of 1s.

Finding Serial Port Information for Your Platform

This section describes the ways to find serial port information for Windows and UNIX platforms.


Note: Your operating system provides default values for all serial port settings. However, these settings are overridden by your MATLAB code, and will have no effect on your serial port application.

Microsoft Windows Platform

You can access serial port information through the **System Properties** dialog. To access this on a Windows XP platform,

- 1 Right-click My Computer on the desktop, and select **Properties**.
- 2 In the **System Properties** dialog, click the **Hardware** tab.
- 3 Click **Device Manager**.
- 4 In the **Device Manager** dialog, expand the Ports node.
- 5 Double-click the **Communications Port (COM1)** node.
- 6 Select the **Port Settings** tab.

MATLAB displays the following Ports dialog box.



UNIX Platform

To find serial port information for UNIX platforms, you need to know the serial port names. These names might vary between different operating systems.

On a Linux platform, serial port devices are typically named `ttyS0`, `ttyS1`, etc. Use the `setserial` command to display or configure serial port information. For example, to display which ports are available:

```
setserial -bg /dev/ttyS*
/dev/ttyS0 at 0x03f8 (irq = 4) is a 16550A
/dev/ttyS1 at 0x02f8 (irq = 3) is a 16550A
```

To display detailed information about `ttyS0`:

```
setserial -ag /dev/ttyS0
/dev/ttyS0, Line 0, UART: 16550A, Port: 0x03f8, IRQ: 4
      Baud_base: 115200, close_delay: 50, divisor: 0
```

```
closing_wait: 3000, closing_wait2: infinte
Flags: spd_normal skip_test session_lockout
```

Note: If the `setserial -ag` command does not work, make sure you have read and write permission for the port.

For all supported UNIX platforms, use the `stty` command to display or configure serial port information. For example, to display serial port properties for `ttyS0`, enter:

```
stty -a < /dev/ttyS0
```

To configure the baud rate to 4800 bits per second, enter:

```
stty speed 4800 < /dev/ttyS0 > /dev/ttyS0
```

Using Virtual USB Serial Ports

If you have devices that present themselves as serial ports on your operating system, you can use them as virtual USB serial ports in MATLAB. An example of such devices would be a USB Serial Dongle. For Bluetooth® devices, use the Bluetooth support in the Instrument Control Toolbox. See “Bluetooth Interface Overview” for more information.

MATLAB can communicate with these devices as long as the serial drivers provided by the device vendor are able to emulate the native hardware. Certain software, like HyperTerminal, does not require the device driver to fully implement and support the native hardware.

Selected Bibliography

- [1] TIA/EIA-232-F, *Interface Between Data Terminal Equipment and Data Circuit-Terminating Equipment Employing Serial Binary Data Interchange*.
- [2] Jan Axelson, *Serial Port Complete*, Lakeview Research, Madison, WI, 1998.
- [3] *Instrument Communication Handbook*, IOTech, Inc., Cleveland, OH, 1991.
- [4] *TDS 200-Series Two Channel Digital Oscilloscope Programmer Manual*, Tektronix, Inc., Wilsonville, OR.
- [5] *Courier High Speed Modems User's Manual*, U.S. Robotics, Inc., Skokie, IL, 1994.

Getting Started with Serial I/O

In this section...

“Example: Getting Started” on page 15-16

“The Serial Port Session” on page 15-16

“Configuring and Returning Properties” on page 15-17

Example: Getting Started

This example illustrates some basic serial port commands.

Note: This example is shown on a Windows platform.

If you have a device connected to the serial port COM1 and configured for a baud rate of 4800, execute the following example.

```
s = serial('COM1');
set(s, 'BaudRate', 4800);
fopen(s);
fprintf(s, '*IDN?')
out = fscanf(s);
fclose(s)
delete(s)
clear s
```

The `*IDN?` command queries the device for identification information, which is returned to `out`. If your device does not support this command, or if it is connected to a different serial port, modify the previous example accordingly.

Note: `*IDN?` is one of the commands supported by the Standard Commands for Programmable Instruments (SCPI) language, which is used by many modern devices. Refer to your device documentation to see if it supports the SCPI language.

The Serial Port Session

This example describes the steps you use to perform any serial port task from beginning to end.

The serial port *session* comprises all the steps you are likely to take when communicating with a device connected to a serial port. These steps are:

- 1 Create a serial port object — Create a serial port object for a specific serial port using the `serial` creation function.

Configure properties during object creation if necessary. In particular, you might want to configure properties associated with serial port communications such as the baud rate, the number of data bits, and so on.

- 2 Connect to the device — Connect the serial port object to the device using the `fopen` function.

After the object is connected, alter the necessary device settings by configuring property values, read data, and write data.

- 3 Configure properties — To establish the desired serial port object behavior, assign values to properties using the `set` function or dot notation.

In practice, you can configure many of the properties at any time including during, or just after, object creation. Conversely, depending on your device settings and the requirements of your serial port application, you might be able to accept the default property values and skip this step.

- 4 Write and read data — Write data to the device using the `fprintf` or `fwrite` function, and read data from the device using the `fgetl`, `fgets`, `fread`, `fscanf`, or `readasynch` function.

The serial port object behaves according to the previously configured or default property values.

- 5 Disconnect and clean up — When you no longer need the serial port object, disconnect it from the device using the `fclose` function, remove it from memory using the `delete` function, and remove it from the MATLAB workspace using the `clear` command.

The serial port session is reinforced in many of the serial port documentation examples. To see a basic example that uses the steps shown above, see “Example: Getting Started” on page 15-16.

Configuring and Returning Properties

This example describes how you display serial port property names and property values, and how you assign values to properties.

You establish the desired serial port object behavior by configuring property values. You can display or configure property values using the `set` function, the `get` function, or dot notation.

Displaying Property Names and Property Values

After you create the serial port object, use the `set` function to display all the configurable properties to the command line. Additionally, if a property has a finite set of string values, `set` also displays these values.

```
s = serial('COM1');
set(s)
    ByteOrder: [ {littleEndian} | bigEndian ]
    BytesAvailableFcn
    BytesAvailableFcnCount
    BytesAvailableFcnMode: [ {terminator} | byte ]
    ErrorFcn
    InputBufferSize
    Name
    OutputBufferSize
    OutputEmptyFcn
    RecordDetail: [ {compact} | verbose ]
    RecordMode: [ {overwrite} | append | index ]
    RecordName
    Tag
    Timeout
    TimerFcn
    TimerPeriod
    UserData

SERIAL specific properties:
    BaudRate
    BreakInterruptFcn
    DataBits
    DataTerminalReady: [ {on} | off ]
    FlowControl: [ {none} | hardware | software ]
    Parity: [ {none} | odd | even | mark | space ]
    PinStatusFcn
    Port
    ReadAsyncMode: [ {continuous} | manual ]
    RequestToSend: [ {on} | off ]
    StopBits
    Terminator
```

Use the `get` function to display one or more properties and their current values to the command line. To display all properties and their current values:

```
get(s)
  ByteOrder = littleEndian
  BytesAvailable = 0
  BytesAvailableFcn =
  BytesAvailableFcnCount = 48
  BytesAvailableFcnMode = terminator
  BytesToOutput = 0
  ErrorFcn =
  InputBufferSize = 512
  Name = Serial-COM1
  OutputBufferSize = 512
  OutputEmptyFcn =
  RecordDetail = compact
  RecordMode = overwrite
  RecordName = record.txt
  RecordStatus = off
  Status = closed
  Tag =
  Timeout = 10
  TimerFcn =
  TimerPeriod = 1
  TransferStatus = idle
  Type = serial
  UserData = []
  ValuesReceived = 0
  ValuesSent = 0
```

SERIAL specific properties:

```
BaudRate = 9600
BreakInterruptFcn =
DataBits = 8
DataTerminalReady = on
FlowControl = none
Parity = none
PinStatus = [1x1 struct]
PinStatusFcn =
Port = COM1
ReadAsyncMode = continuous
RequestToSend = on
StopBits = 1
Terminator = LF
```

To display the current value for one property, supply the property name to `get`.

```
get(s, 'OutputBufferSize')
ans =
    512
```

To display the current values for multiple properties, include the property names as elements of a cell array.

```
get(s, {'Parity', 'TransferStatus'})
ans =
    'none'    'idle'
```

Use the dot notation to display a single property value.

```
s.Parity
ans =
    none
```

Configuring Property Values

You can configure property values using the `set` function:

```
set(s, 'BaudRate', 4800);
```

or the dot notation:

```
s.BaudRate = 4800;
```

To configure values for multiple properties, supply multiple property name/property value pairs to `set`.

```
set(s, 'DataBits', 7, 'Name', 'Test1-serial')
```

Note that you can configure only one property value at a time using the dot notation.

In practice, you can configure many of the properties at any time while the serial port object exists — including during object creation. However, some properties are not configurable while the object is connected to the device or when recording information to disk. For information about when a property is configurable, see “Property Reference” on page 15-70.

Specifying Property Names

Serial port property names are presented using mixed case. While this makes property names easier to read, use any case you want when specifying property names. For example, to configure the `BaudRate` property:

```
s.BaudRate = 4800;  
s.baudrate = 4800;
```

Default Property Values

Whenever you do not explicitly define a value for a property, the default value is used. All configurable properties have default values.

Note: Your operating system provides default values for all serial port settings such as the baud rate. However, these settings are overridden by your MATLAB code and have no effect on your serial port application.

If a property has a finite set of string values, the default value is enclosed by {}. For example, the default value for the `Parity` property is `none`.

```
set(s,'Parity')  
[ {none} | odd | even | mark | space ]
```

You can find the default value for any property in the property reference pages.

Creating a Serial Port Object

In this section...

“Overview of a Serial Port Object” on page 15-22

“Configuring Properties During Object Creation” on page 15-23

“The Serial Port Object Display” on page 15-24

“Creating an Array of Serial Port Objects” on page 15-24

Overview of a Serial Port Object

The `serial` function requires the name of the serial port connected to your device as an input argument. Additionally, you can configure property values during object creation. To create a serial port object associated with the serial port enter:

```
s = serial('port');
```

This creates a serial port object associated with the serial port specified by `'port'`. If `'port'` does not exist, or if it is in use, you will not be able to connect the serial port object to the device. `'port'` object name will depend upon the platform that the serial port is on. The Instrument Control Toolbox function

```
instrhwinfo('serial')
```

provides a list of available serial ports. This list is an example of serial constructors on different platforms:

Platform	Serial Constructor
Linux 32 and 64-bit	<code>serial('/dev/ttyS0');</code>
Mac OS X and Mac OS X 64-bit	<code>serial('/dev/tty.KeySerial1');</code>
Microsoft Windows 32 and 64-bit	<code>serial('com1');</code>
Sun™ Solaris™ 64-bit	<code>serial('/dev/term/a');</code>

The serial port object `s` now exists in the MATLAB workspace. To display the class of `s`, use the `whos` command.

```
whos s
  Name      Size      Bytes  Class
```

```
s          1x1          512  serial object
Grand total is 11 elements using 512 bytes
```

Note: The first time you try to access a serial port in MATLAB using the `s = serial('port')` call, make sure that the port is free and is not already open in any other application. If the port is open in another application, MATLAB cannot access it. Once you have accessed in MATLAB, you can open the same port in other applications and MATLAB will continue to use it along with any other application that has it open as well.

Once the serial port object is created, the following properties are automatically assigned values. These general-purpose properties provide descriptive information about the serial port object based on the object type and the serial port.

Descriptive General Purpose Properties

Property Name	Description
Name	Specify a descriptive name for the serial port object
Port	Indicate the platform-specific serial port name
Type	Indicate the object type

Display the values of these properties for `s` with the `get` function. On a Windows platform, it will look like this:

```
get(s,{'Name','Port','Type'})
ans =
    'Serial-COM1'    'COM1'    'serial'
```

Configuring Properties During Object Creation

You can configure serial port properties during object creation. `serial` accepts property names and property values in the same format as the `set` function. For example, you can specify property name/property value pairs.

```
s = serial('port','BaudRate',4800,'Parity','even');
```

If you specify an invalid property name, the object is not created. However, if you specify an invalid value for some properties (for example, `BaudRate` is set to 50), the object

might be created but you are not informed of the invalid value until you connect the object to the device with the `fopen` function.

The Serial Port Object Display

The serial port object provides you with a convenient display that summarizes important configuration and state information. You can invoke the display summary these three ways:

- Type the serial port object variable name at the command line.
- Exclude the semicolon when creating a serial port object.
- Exclude the semicolon when configuring properties using the dot notation.

To display summary information using the Workspace browser, right-click an instrument object and select **Display Summary** from the context menu.

The display summary for the serial port object `s` on a Windows platform is:

```
Serial Port Object : Serial-COM1
```

Communication Settings

```
Port:          COM1
BaudRate:      9600
Terminator:    'LF'
```

Communication State

```
Status:        closed
RecordStatus:  off
```

Read/Write State

```
TransferStatus:  idle
BytesAvailable:  0
ValuesReceived:  0
ValuesSent:      0
```

Creating an Array of Serial Port Objects

In MATLAB, you create an array from existing variables by concatenating those variables together. The same is true for serial port objects. For example, suppose you create the serial port objects `s1` and `s2` on a Windows platform.

```
s1 = serial('COM1');
```



```
s2 = serial('COM2');
```

Create a serial port object array, consisting of `s1` and `s2`, using the usual MATLAB syntax. To create the row array `x`, enter:

```
x = [s1 s2]
```

Instrument Object Array

Index:	Type:	Status:	Name:
1	serial	closed	Serial-COM1
2	serial	closed	Serial-COM2

To create the column array `y`, enter:

```
y = [s1;s2];
```

Note that you cannot create a matrix of serial port objects. For example, you cannot create the matrix:

```
z = [s1 s2;s1 s2];
??? Error using ==> serial/vertcat
Only a row or column vector of instrument objects can be created.
```

Depending on your application, you might want to pass an array of serial port objects to a function. For example, to configure the baud rate and parity for `s1` and `s2` using one call to `set`:

```
set(x, 'BaudRate', 19200, 'Parity', 'even')
```

Connecting to the Device

Before using the serial port object to write or read data, you must connect it to your device via the serial port specified in the `serial` function. You connect a serial port object to the device with the `fopen` function.

```
fopen(s)
```


Some properties are read only while the serial port object is connected and must be configured before using `fopen`. Examples include the `InputBufferSize` and the `OutputBufferSize` properties. To determine when you can configure a property, see “Property Reference” on page 15-70.

Note: You can create any number of serial port objects, but you can connect only one serial port object per MATLAB session to a given serial port at a time. However, the serial port is not locked by the session, so other applications or other instances of MATLAB software can access the same serial port, which could result in a conflict, with unpredictable results.

To verify that the serial port object is connected to the device, examine the `Status` property.

```
s.Status
ans =
open
```

As shown in the following illustration, the connection between the serial port object and the device is complete; data is readable and writable.



Configuring Communication Settings

Before you can write or read data, both the serial port object and the device must have identical communication settings. Configuring serial port communications involves specifying values for properties that control the baud rate and the serial data format. The following table describes these properties.

Communication Properties

Property Name	Description
BaudRate	Specify the rate at which bits are transmitted
DataBits	Specify the number of data bits to transmit
Parity	Specify the type of parity checking
StopBits	Specify the number of bits used to indicate the end of a byte
Terminator	Specify the terminator character

Note: If the serial port object and the device communication settings are not identical, data is not readable or writable.

Refer to the device documentation for an explanation of its supported communication settings.

Writing and Reading Data

In this section...

“Before You Begin” on page 15-28

“Example — Introduction to Writing and Reading Data” on page 15-28

“Controlling Access to the MATLAB Command Line” on page 15-29

“Writing Data” on page 15-30

“Reading Data” on page 15-35

“Example — Writing and Reading Text Data” on page 15-41

“Example — Parsing Input Data Using textscan” on page 15-42

“Example — Reading Binary Data” on page 15-43

Before You Begin

For many serial port applications, there are three important questions that you should consider when writing or reading data:

- Will the read or write function block access to the MATLAB command line?
- Is the data to be transferred binary (numerical) or text?
- Under what conditions will the read or write operation complete?

For write operations, these questions are answered in “Writing Data” on page 15-30.

For read operations, these questions are answered in “Reading Data” on page 15-35.

Note: All the examples shown below are based on a Windows 32-bit platform. Refer to “Overview of a Serial Port Object” on page 15-22 section for information about other platforms.

Example — Introduction to Writing and Reading Data

Suppose you want to return identification information for a Tektronix TDS 210 two-channel oscilloscope connected to the serial port COM1 on a Windows platform. This requires writing the `*IDN?` command to the instrument using the `fprintf` function, and reading back the result of that command using the `fscanf` function.

```
s = serial('COM1');  
fopen(s)  
fprintf(s, '*IDN?')  
out = fscanf(s)
```

The resulting identification information is:

```
out =  
TEKTRONIX,TDS 210,0,CF:91.1CT FV:v1.16 TDS2CM:CMV:v1.04
```

End the serial port session.

```
fclose(s)  
delete(s)  
clear s
```

Controlling Access to the MATLAB Command Line

You control access to the MATLAB command line by specifying whether a read or write operation is *synchronous* or *asynchronous*.

A synchronous operation blocks access to the command line until the read or write function completes execution. An asynchronous operation does not block access to the command line, and you can issue additional commands while the read or write function executes in the background.

The terms *synchronous* and *asynchronous* are often used to describe how the serial port operates at the hardware level. The RS-232 standard supports an asynchronous communication protocol. Using this protocol, each device uses its own internal clock. The data transmission is synchronized using the start bit of the bytes, while one or more stop bits indicate the end of the byte. For more information on start bits and stop bits, see “Serial Data Format” on page 15-10. The RS-232 standard also supports a synchronous mode where all transmitted bits are synchronized to a common clock signal.

At the hardware level, most serial ports operate asynchronously. However, using the default behavior for many of the read and write functions, you can mimic the operation of a synchronous serial port.


Note: When used in this guide, the terms *synchronous* and *asynchronous* refer to whether read or write operations block access to the MATLAB command-line. In other

words, these terms describe how the software behaves, and not how the hardware behaves.

The two main advantages of writing or reading data asynchronously are:

- You can issue another command while the write or read function is executing.
- You can use all supported callback properties (see “Events and Callbacks” on page 15-46).

For example, because serial ports have separate read and write pins, you can simultaneously read and write data. This is illustrated in the following diagram.



Writing Data

This section describes writing data to your serial port device in three parts:

- “The Output Buffer and Data Flow” on page 15-31 describes the flow of data from MATLAB software to the device.
- “Writing Text Data” on page 15-32 describes how to write text data (string commands) to the device.
- “Writing Binary Data” on page 15-34 describes how to write binary (numerical) data to the device.

The following table shows the functions associated with writing data.

Functions Associated with Writing Data

Function Name	Description
<code>fprintf</code>	Write text to the device
<code>fwrite</code>	Write binary data to the device

Function Name	Description
stopasync	Stop asynchronous read and write operations

The following table shows the properties associated with writing data.

Properties Associated with Writing Data

Property Name	Description
BytesToOutput	Number of bytes currently in the output buffer
OutputBufferSize	Size of the output buffer in bytes
Timeout	Waiting time to complete a read or write operation
TransferStatus	Indicate if an asynchronous read or write operation is in progress
ValuesSent	Total number of values written to the device

The Output Buffer and Data Flow

The output buffer is computer memory allocated by the serial port object to store data that is to be written to the device. When writing data to your device, the data flow follows these two steps:


- 1 The data specified by the write function is sent to the output buffer.
- 2 The data in the output buffer is sent to the device.

The `OutputBufferSize` property specifies the maximum number of bytes that you can store in the output buffer. The `BytesToOutput` property indicates the number of bytes currently in the output buffer. The default values for these properties are:

```
s = serial('COM1');
get(s,{'OutputBufferSize','BytesToOutput'})
ans =
    [512]    [0]
```

If you attempt to write more data than can fit in the output buffer, an error is returned and no data is written.


For example, suppose you write the string command `*IDN?` to the TDS 210 oscilloscope using the `fprintf` function. As shown in the following diagram, the string is first written to the output buffer as six values.



- Bytes used during write
- Bytes unused during write

The `*IDN?` command consists of six values because the terminator is automatically written. Moreover, the default data format for the `fprintf` function specifies that one value corresponds to one byte. For more information about bytes and values, see “Bytes Versus Values” on page 15-10. `fprintf` and the terminator are discussed in “Writing Text Data” on page 15-32.

As shown in the following diagram, after the string is written to the output buffer, it is then written to the device via the serial port.



- Bytes used during write
- Bytes unused during write

Writing Text Data

You use the `fprintf` function to write text data to the device. For many devices, writing text data means writing string commands that change device settings, prepare the device to return data or status information, and so on.

For example, the `Display:Contrast` command changes the display contrast of the oscilloscope.


```
s = serial('COM1');
fopen(s)
fprintf(s, 'Display:Contrast 45')
```

By default, `fprintf` writes data using the `%s\n` format because many serial port devices accept only text-based commands. However, you can specify many other formats, as described in the `fprintf` reference pages.

To verify the number of values sent to the device, use the `ValuesSent` property.

```
s.ValuesSent
ans =
    20
```

Note that the `ValuesSent` property value includes the terminator because each occurrence of `\n` in the command sent to the device is replaced with the `Terminator` property value.

```
s.Terminator
ans =
LF
```

The default value of `Terminator` is the linefeed character. The terminator required by your device will be described in its documentation.

Synchronous Versus Asynchronous Write Operations

By default, `fprintf` operates synchronously and blocks the MATLAB command line until execution completes. To write text data asynchronously to the device, you must specify `async` as the last input argument to `fprintf`.

```
fprintf(s, 'Display:Contrast 45', 'async')
```

Asynchronous operations do not block access to the MATLAB command line. Additionally, while an asynchronous write operation is in progress, you can:

- Execute an asynchronous read operation because serial ports have separate pins for reading and writing
- Make use of all supported callback properties

To determine which asynchronous operations are in progress, use the `TransferStatus` property. If no asynchronous operations are in progress, `TransferStatus` is `idle`.

```
s.TransferStatus
```

```
ans =  
idle
```

Completing a Write Operation with `fprintf`

A synchronous or asynchronous write operation using `fprintf` completes when:

- The specified data is written.
- The time specified by the `Timeout` property passes.

Stop an asynchronous write operation with the `stopasync` function.

Rules for Writing the Terminator

The `Terminator` property value replaces all occurrences of `\n` in `cmd`. Therefore, when you use the default format `%s\n`, all commands written to the device end with this property value. Refer to your device documentation for the terminator required by your device.

Writing Binary Data

You use the `fwrite` function to write binary data to the device. Writing binary data means writing numerical values. A typical application for writing binary data involves writing calibration data to an instrument such as an arbitrary waveform generator.

Note: Some serial port devices accept only text-based commands. These commands might use the SCPI language or some other vendor-specific language. Therefore, you might need to use the `fprintf` function for all write operations.

By default, `fwrite` translates values using the `uchar` precision. However, you can specify many other precisions as described in the reference pages for this function.

By default, `fwrite` operates synchronously. To write binary data asynchronously to the device, you must specify `async` as the last input argument to `fwrite`. For more information about synchronous and asynchronous write operations, see “Writing Text Data” on page 15-32. For a description of the rules used by `fwrite` to complete a write operation, refer to its reference pages.

Troubleshooting Common Errors

Use this table to identify common `fprintf` errors.

Error	Occurs when	Troubleshooting
<p>??? Error using ==> serial.fwrite at 199 OBJ must be connected to the hardware with FOPEN.</p>	<p>You perform a write operation and the serial port object is not connected to the device.</p>	<p>Use <code>fopen</code> to establish a connection to the device.</p>
<p>??? Error using ==> serial.fwrite at 199 The number of bytes written must be less than or equal to <code>OutputBufferSize-BytesToOutput</code>.</p>	<p>The output buffer is not able to hold all the data to be written.</p>	<p>Specify the size of the output buffer with the <code>OutputBufferSize</code> property.</p>
<p>??? Error using ==> serial.fwrite at 192 FWRITE cannot be called. The <code>FlowControl</code> property is set to 'hardware' and the Clear To Send (CTS) pin is high. This could indicate that the serial device may not be turned on, may not be connected, or does not use hardware handshaking</p>	<ul style="list-style-type: none"> • You set the <code>flowcontrol</code> property on a serial object to <code>hardware</code>. • The device is either not connected or a connected device is not asserting that is ready to receive data. 	<p>Check your remote device status and flow control settings to see if hardware flow control is causing MATLAB errors.</p>

Reading Data

This section describes reading data from your serial port device in three parts:

- “The Input Buffer and Data Flow” on page 15-36 describes the flow of data from the device to MATLAB software.
- “Reading Text Data” on page 15-38 describes how to read from the device, and format the data as text.

- “Reading Binary Data” on page 15-40 describes how to read binary (numerical) data from the device.

The following table shows the functions associated with reading data.

Functions Associated with Reading Data

Function Name	Description
<code>fgetc</code>	Read one line of text from the device and discard the terminator
<code>fgets</code>	Read one line of text from the device and include the terminator
<code>fread</code>	Read binary data from the device
<code>fscanf</code>	Read data from the device and format as text
<code>readasync</code>	Read data asynchronously from the device
<code>stopasync</code>	Stop asynchronous read and write operations

The following table shows the properties associated with reading data.

Properties Associated with Reading Data

Property Name	Description
<code>BytesAvailable</code>	Number of bytes available in the input buffer
<code>InputBufferSize</code>	Size of the input buffer in bytes
<code>ReadAsyncMode</code>	Specify whether an asynchronous read operation is continuous or manual
<code>Timeout</code>	Waiting time to complete a read or write operation
<code>TransferStatus</code>	Indicate if an asynchronous read or write operation is in progress
<code>ValuesReceived</code>	Total number of values read from the device

The Input Buffer and Data Flow

The input buffer is computer memory allocated by the serial port object to store data that is to be read from the device. When reading data from your device, the data flow follows these two steps:


- 1 The data read from the device is stored in the input buffer.
- 2 The data in the input buffer is returned to the MATLAB variable specified by the read function.

The `InputBufferSize` property specifies the maximum number of bytes you can store in the input buffer. The `BytesAvailable` property indicates the number of bytes currently available to be read from the input buffer. The default values for these properties are:

```
s = serial('COM1');
get(s,{'InputBufferSize','BytesAvailable'})
ans =
    [512]    [0]
```


If you attempt to read more data than can fit in the input buffer, an error is returned and no data is read.

For example, suppose you use the `fscanf` function to read the text-based response of the `*IDN?` command previously written to the TDS 210 oscilloscope. As shown in the following diagram, the text data is first read into the input buffer via the serial port.



Note that for a given read operation, you might not know the number of bytes returned by the device. Therefore, you might need to preset the `InputBufferSize` property to a sufficiently large value before connecting the serial port object.

As shown in the following diagram, after the data is stored in the input buffer, it is then transferred to the output variable specified by `fscanf`.



- Bytes used during read
- Bytes unused during read

Reading Text Data

You use the `fgetl`, `fgets`, and `fscanf` functions to read data from the device, and format the data as text.

For example, suppose you want to return identification information for the oscilloscope. This requires writing the `*IDN?` command to the instrument, and then reading back the result of that command.

```
s = serial('COM1');
fopen(s)
fprintf(s, '*IDN?')
out = fscanf(s)
out =
TEKTRONIX,TDS 210,0,CF:91.1CT FV:v1.16 TDS2CM:CMV:v1.04
```

By default, `fscanf` reads data using the `%c` format because the data returned by many serial port devices is text based. However, you can specify many other formats as described in the `fscanf` reference pages.

To verify the number of values read from the device—including the terminator, use the `ValuesReceived` property.

```
s.ValuesReceived
ans =
    56
```

Synchronous Versus Asynchronous Read Operations

You specify whether read operations are synchronous or asynchronous with the `ReadAsyncMode` property. You can configure `ReadAsyncMode` to `continuous` or `manual`.

If `ReadAsyncMode` is `continuous` (the default value), the serial port object continuously queries the device to determine if data is available to be read. If data is available, it is asynchronously stored in the input buffer. To transfer the data from the input buffer to MATLAB, use one of the synchronous (blocking) read functions such as `fgetl` or `fscanf`. If data is available in the input buffer, these functions return quickly.

```
s.ReadAsyncMode = 'continuous';
fprintf(s, '*IDN?')
s.BytesAvailable
ans =
    56
out = fscanf(s);
```

If `ReadAsyncMode` is `manual`, the serial port object does not continuously query the device to determine if data is available to be read. To read data asynchronously, use the `readasync` function. Then use one of the synchronous read functions to transfer data from the input buffer to MATLAB.

```
s.ReadAsyncMode = 'manual';
fprintf(s, '*IDN?')
s.BytesAvailable
ans =
    0
readasync(s)
s.BytesAvailable
ans =
    56
out = fscanf(s);
```

Asynchronous operations do not block access to the MATLAB command line. Additionally, while an asynchronous read operation is in progress, you can:

- Execute an asynchronous write operation because serial ports have separate pins for reading and writing
- Make use of all supported callback properties

To determine which asynchronous operations are in progress, use the `TransferStatus` property. If no asynchronous operations are in progress, then `TransferStatus` is `idle`.

```
s.TransferStatus
ans =
idle
```

Rules for Completing a Read Operation with `fscanf`

A read operation with `fscanf` blocks access to the MATLAB command line until:

- The terminator specified by the `Terminator` property is read.
- The time specified by the `Timeout` property passes.
- The specified number of values specified is read.
- The input buffer is filled.

Reading Binary Data

You use the `fread` function to read binary data from the device. Reading binary data means that you return numerical values to MATLAB.

For example, suppose you want to return the cursor and display settings for the oscilloscope. This requires writing the `CURSOR?` and `DISPLAY?` commands to the instrument, and then reading back the results of those commands.

```
s = serial('COM1');  
fopen(s)  
fprintf(s, 'CURSOR?')  
fprintf(s, 'DISPLAY?')
```

Because the default value for the `ReadAsyncMode` property is `continuous`, data is asynchronously returned to the input buffer as soon as it is available from the device. To verify the number of values read, use the `BytesAvailable` property.

```
s.BytesAvailable  
ans =  
    69
```

To return the data to MATLAB, use any of the synchronous read functions. However, if you use `fgetl`, `fgets`, or `fscanf`, you must issue the function twice because there are two terminators stored in the input buffer. To return all the data to MATLAB in one function call, use `fread`.

```
out = fread(s,69);
```

By default, `fread` returns numerical values in double precision arrays. However, you can specify many other precisions as described in the `fread` reference pages. To convert the numerical data to text, use the MATLAB `char` function.


```

val = char(out) '
val =
HBARS;CH1;SECONDS;-1.0E-3;1.0E-3;VOLTS;-6.56E-1;6.24E-1
YT;DOTS;0;45

```

For more information about synchronous and asynchronous read operations, see “Reading Text Data” on page 15-38. For a description of the rules used by `fread` to complete a read operation, refer to its reference pages.

Example — Writing and Reading Text Data

This example illustrates how to communicate with a serial port instrument by writing and reading text data.

The instrument is a Tektronix TDS 210 two-channel oscilloscope connected to the COM1 port. Therefore, many of the following commands are specific to this instrument. A sine wave is input into channel 2 of the oscilloscope, and your job is to measure the peak-to-peak voltage of the input signal.

- 1 Create a serial port object — Create the serial port object `s` associated with serial port COM1.

```
s = serial('COM1');
```

- 2 Connect to the device — Connect `s` to the oscilloscope. Because the default value for the `ReadAsyncMode` property is `continuous`, data is asynchronously returned to the input buffer as soon as it is available from the instrument.

```
fopen(s)
```

- 3 Write and read data — Write the `*IDN?` command to the instrument using `fprintf`, and then read back the result of the command using `fscanf`.

```

fprintf(s,'*IDN?')
idn = fscanf(s)
idn =
TEKTRONIX,TDS 210,0,CF:91.1CT FV:v1.16 TDS2CM:CMV:v1.04

```

You need to determine the measurement source. Possible measurement sources include channel 1 and channel 2 of the oscilloscope.

```

fprintf(s,'MEASUREMENT:IMMED:SOURCE?')
source = fscanf(s)
source =

```

CH1

The scope is configured to return a measurement from channel 1. Because the input signal is connected to channel 2, you must configure the instrument to return a measurement from this channel.

```
fprintf(s, 'MEASUREMENT:IMMED:SOURCE CH2')
fprintf(s, 'MEASUREMENT:IMMED:SOURCE?')
source = fscanf(s)
source =
CH2
```

Configure the scope to return the peak-to-peak voltage, and then request the value of this measurement.

```
fprintf(s, 'MEASUREMENT:MEAS1:TYPE PK2PK')
fprintf(s, 'MEASUREMENT:MEAS1:VALUE?')
```

Transfer data from the input buffer to MATLAB using `fscanf`.

```
ptop = fscanf(s, '%g')
ptop =
2.0199999809E0
```

- 4 Disconnect and clean up — When you no longer need `s` disconnect it from the instrument and remove it from memory and from the MATLAB workspace.

```
fclose(s)
delete(s)
clear s
```

Example — Parsing Input Data Using `textscan`

This example illustrates how to use the `textscan` function to parse and format data that you read from a device. `textscan` is particularly useful when you want to parse a string into one or more variables, where each variable has its own specified format.

The instrument is a Tektronix TDS 210 two-channel oscilloscope connected to the serial port COM1.

- 1 Create a serial port object — Create the serial port object `s` associated with serial port COM1.

```
s = serial('COM1');
```

- 2 Connect to the device — Connect `s` to the oscilloscope. Because the default value for the `ReadAsyncMode` property is `continuous`, data is asynchronously returned to the input buffer as soon as it is available from the instrument.

```
fopen(s)
```

- 3 Write and read data — Write the `RS232?` command to the instrument using `fprintf`, and then read back the result of the command using `fscanf`. `RS232?` queries the RS-232 settings and returns the baud rate, the software flow control setting, the hardware flow control setting, the parity type, and the terminator.

```
fprintf(s, 'RS232?')
data = fscanf(s)
data =
9600;0;0;NONE;LF
```

Use the `textscan` function to parse and format the `data` variable into five new variables.

```
C = textscan(a, '%d%d%d%s', 'delimiter', '');
[br, sfc, hfc, par, tm] = deal(C{:});
br =
    9600
sfc =
     0
hfc =
     0
par =
    'NONE'
tm =
    'LF'
```

- 4 Disconnect and clean up — When you no longer need `s`, you should disconnect it from the instrument, and remove it from memory and from the MATLAB workspace.

```
fclose(s)
delete(s)
clear s
```

Example — Reading Binary Data

This example shows how you to download the TDS 210 oscilloscope screen display to MATLAB. The screen display data is transferred and saved to disk using the Windows bitmap format. This data provides a permanent record of your work, and is an easy way to document important signal and scope parameters.

Because the amount of data transferred is expected to be fairly large, it is asynchronously returned to the input buffer as soon as it is available from the instrument. This allows you to perform other tasks as the transfer progresses. Additionally, the scope is configured to its highest baud rate of 19,200.

- 1 Create a serial port object — Create the serial port object `s` associated with serial port COM1.

```
s = serial('COM1');
```

- 2 Configure property values — Configure the input buffer to accept a reasonably large number of bytes, and configure the baud rate to the highest value supported by the scope.

```
s.InputBufferSize = 50000;  
s.BaudRate = 19200;
```

- 3 Connect to the device — Connect `s` to the oscilloscope. Because the default value for the `ReadAsyncMode` property is `continuous`, data is asynchronously returned to the input buffer as soon as it is available from the instrument.

```
fopen(s)
```

- 4 Write and read data — Configure the scope to transfer the screen display as a bitmap.

```
fprintf(s, 'HARDCOPY:PORT RS232')  
fprintf(s, 'HARDCOPY:FORMAT BMP')  
fprintf(s, 'HARDCOPY START')
```

Wait until all the data is sent to the input buffer, and then transfer the data to the MATLAB workspace as unsigned 8-bit integers.

```
out = fread(s,s.BytesAvailable, 'uint8');
```

- 5 Disconnect and clean up — When you no longer need `s`, disconnect it from the instrument and remove it from memory and from the MATLAB workspace.

```
fclose(s)  
delete(s)  
clear s
```

Viewing the Bitmap Data

To view the bitmap data, follow these steps:

- 1 Open a disk file.

- 2 Write the data to the disk file.
- 3 Close the disk file.
- 4 Read the data into MATLAB using the `imread` function.
- 5 Scale and display the data using the `imagesc` function.


Note that the file I/O versions of the `fopen`, `fwrite`, and `fclose` functions are used.

```
fid = fopen('test1.bmp','w');
fwrite(fid,out,'uint8');
fclose(fid)
a = imread('test1.bmp','bmp');
imagesc(a)
```

Because the scope returns the screen display data using only two colors, an appropriate colormap is selected.

```
mymap = [0 0 0; 1 1 1];
colormap(mymap)
```

The following diagram shows the resulting bitmap image.



Events and Callbacks

In this section...

“Introduction” on page 15-46

“Example — Introduction to Events and Callbacks” on page 15-46

“Event Types and Callback Properties” on page 15-47

“Responding To Event Information” on page 15-49

“Creating and Executing Callback Functions” on page 15-51

“Enabling Callback Functions After They Error” on page 15-52

“Example — Using Events and Callbacks” on page 15-52

Introduction

You can enhance the power and flexibility of your serial port application by using *events*. An event occurs after a condition is met and might result in one or more callbacks.

While the serial port object is connected to the device, use events to display a message, display data, analyze data, and so on. Callbacks are controlled through *callback properties* and *callback functions*. All event types have an associated callback property. Callback functions are MATLAB functions that you construct to suit your specific application needs.

You execute a callback when a particular event occurs by specifying the name of the callback function as the value for the associated callback property.

Note: All examples in this section are based on a Windows 32-bit platform. For information about other platforms refer to “Overview of a Serial Port Object” on page 15-22.

Example — Introduction to Events and Callbacks

This example uses the callback function `instrcallback` to display a message to the command line when a bytes-available event occurs. The event is generated when the terminator is read.

```
s = serial('COM1');
```

```
fopen(s)
s.BytesAvailableFcnMode = 'terminator';
s.BytesAvailableFcn = @instrcallback;
fprintf(s, '*IDN?')
out = fscanf(s);
```

MATLAB displays:

```
BytesAvailable event occurred at 17:01:29 for the object:
Serial-COM1.
```

End the serial port session.

```
fclose(s)
delete(s)
clear s
```

To see the code for the built-in `instrcallback` function, use the `type` command.

Event Types and Callback Properties

The following table describes serial port event types and callback properties. This table has two columns and nine rows. In the first column (event type), the second item (bytes available) applies to rows 2 through 4. Also, in the first column the last item (timer) applies to rows 8 and 9.

Event Types and Callback Properties

Event Type	Associated Properties
Break interrupt	BreakInterruptFcn
Bytes available	BytesAvailableFcn
	BytesAvailableFcnCount
	BytesAvailableFcnMode
Error	ErrorFcn
Output empty	OutputEmptyFcn
Pin status	PinStatusFcn
Timer	TimerFcn
	TimerPeriod

Break-Interrupt Event

A break-interrupt event is generated immediately after a break interrupt is generated by the serial port. The serial port generates a break interrupt when the received data has been in an inactive state longer than the transmission time for one character.

This event executes the callback function specified for the `BreakInterruptFcn` property. It can be generated for both synchronous and asynchronous read and write operations.

Bytes-Available Event

A bytes-available event is generated immediately after a predetermined number of bytes are available in the input buffer or a terminator is read, as determined by the `BytesAvailableFcnMode` property.

If `BytesAvailableFcnMode` is `byte`, the bytes-available event executes the callback function specified for the `BytesAvailableFcn` property every time the number of bytes specified by `BytesAvailableFcnCount` is stored in the input buffer. If `BytesAvailableFcnMode` is `terminator`, the callback function executes every time the character specified by the `Terminator` property is read.

This event can be generated only during an asynchronous read operation.

Error Event

An error event is generated immediately after an error occurs.

This event executes the callback function specified for the `ErrorFcn` property. It can be generated only during an asynchronous read or write operation.

An error event is generated when a time-out occurs. A time-out occurs if a read or write operation does not successfully complete within the time specified by the `Timeout` property. An error event is not generated for configuration errors such as setting an invalid property value.

Output-Empty Event

An output-empty event is generated immediately after the output buffer is empty.

This event executes the callback function specified for the `OutputEmptyFcn` property. It can be generated only during an asynchronous write operation.

Pin Status Event

A pin status event is generated immediately after the state (pin value) changes for the CD, CTS, DSR, or RI pins. For a description of these pins, see “Serial Port Signals and Pin Assignments” on page 15-6.

This event executes the callback function specified for the `PinStatusFcn` property. It can be generated for both synchronous and asynchronous read and write operations.

Timer Event

A timer event is generated when the time specified by the `TimerPeriod` property passes. Time is measured relative to when the serial port object is connected to the device.

This event executes the callback function specified for the `TimerFcn` property. Note that some timer events might not be processed if your system is significantly slowed or if the `TimerPeriod` value is too small.

Responding To Event Information

You can respond to event information in a callback function or in a record file. Event information is stored in a callback function using two fields: `Type` and `Data`. The `Type` field contains the event type, while the `Data` field contains event-specific information. As described in “Creating and Executing Callback Functions” on page 15-51, these two fields are associated with a structure that you define in the callback function header. To learn about recording data and event information to a record file, see “Debugging: Recording Information to Disk” on page 15-60.

The following table shows event types and the values for the `Type` and `Data` fields. The table has three columns and 15 rows. Items in the first column (event type) span several rows, as follows:

Break interrupt: rows 1 and 2

Bytes available: rows 3 and 4

Error: rows 5 through 7

Output empty: rows 8 and 9

Pin status: rows 10 through 13

Timer: rows 14 and 15

Event Information

Event Type	Field	Field Value
Break interrupt	Type	BreakInterrupt
	Data.AbsTime	day-month-year hour:minute:second
Bytes available	Type	BytesAvailable
	Data.AbsTime	day-month-year hour:minute:second
Error	Type	Error
	Data.AbsTime	day-month-year hour:minute:second
	Data.Message	An error string
Output empty	Type	OutputEmpty
	Data.AbsTime	day-month-year hour:minute:second
Pin status	Type	PinStatus
	Data.AbsTime	day-month-year hour:minute:second
	Data.Pin	CarrierDetect, ClearToSend, DataSetReady, or RingIndicator
	Data.PinValue	on or off
Timer	Type	Timer
	Data.AbsTime	day-month-year hour:minute:second

The following topics describe the Data field values.

The AbsTime Field

The AbsTime field, defined for all events, is the absolute time the event occurred. The absolute time is returned using the `CLOCK` format: day-month-year hour:minute:second.

The Pin Field

The pin status event uses the `Pin` field to indicate if the CD, CTS, DSR, or RI pins changed state. For a description of these pins, see “Serial Port Signals and Pin Assignments” on page 15-6.

The PinValue Field

The pin status event uses the `PinValue` field to indicate the state of the CD, CTS, DSR, or RI pins. Possible values are `on` or `off`.

The Message Field

The error event uses the `Message` field to store the descriptive message that is generated when an error occurs.

Creating and Executing Callback Functions

To specify the callback function to be executed when a specific event type occurs, include the name of the file as the value for the associated callback property. You can specify the callback function as a function handle or as a string cell array element. Function handles are described in the `function_handle` reference pages.

For example, to execute the callback function `mycallback` every time the terminator is read from your device:

```
s.BytesAvailableFcnMode = 'terminator';
s.BytesAvailableFcn = @mycallback;
```

Alternatively, you can specify the callback function as a cell array.

```
s.BytesAvailableFcn = {'mycallback'};
```

Callback functions require at least two input arguments. The first argument is the serial port object. The second argument is a variable that captures the event information shown in the table, Event Information. This event information pertains only to the event that caused the callback function to execute. The function header for `mycallback` is:

```
function mycallback(obj,event)
```

You pass additional parameters to the callback function by including both the callback function and the parameters as elements of a cell array. For example, to pass the MATLAB variable `time` to `mycallback`:

```
time = datestr(now,0);
```

```
s.BytesAvailableFcnMode = 'terminator';  
s.BytesAvailableFcn = {@mycallback,time};
```

Alternatively, you can specify the callback function as a string in the cell array.

```
s.BytesAvailableFcn = {'mycallback',time};
```

The corresponding function header is:

```
function mycallback(obj,event,time)
```

If you pass additional parameters to the callback function, they must be included in the function header after the two required arguments.

Note: You can also specify the callback function as a string. In this case, the callback is evaluated in the MATLAB workspace and no requirements are made on the input arguments of the callback function.

Enabling Callback Functions After They Error

If an error occurs while a callback function is executing the following occurs:

- The callback function is automatically disabled.
- A warning is displayed at the command line, indicating that the callback function is disabled.

If you want to enable the same callback function, set the callback property to the same value or disconnect the object with the `fclose` function. If you want to use a different callback function, the callback is enabled when you configure the callback property to the new value.

Example — Using Events and Callbacks

This example uses the callback function `instrcallback` to display event-related information to the command line when a bytes-available event or an output-empty event occurs.

- 1 Create a serial port object — Create the serial port object `s` associated with serial port COM1.

```
s = serial('COM1');
```

- 2 Configure properties — Configure `s` to execute the callback function `instrcallback` when a bytes-available event or an output-empty event occurs. Because `instrcallback` requires the serial port object and event information to be passed as input arguments, the callback function is specified as a function handle.

```
s.BytesAvailableFcnMode = 'terminator';
s.BytesAvailableFcn = @instrcallback;
s.OutputEmptyFcn = @instrcallback;
```

- 3 Connect to the device — Connect `s` to the Tektronix TDS 210 oscilloscope. Because the default value for the `ReadAsyncMode` property is `continuous`, data is asynchronously returned to the input buffer as soon as it is available from the instrument.

```
fopen(s)
```

- 4 Write and read data — Write the `RS232?` command asynchronously to the oscilloscope. This command queries the RS-232 settings and returns the baud rate, the software flow control setting, the hardware flow control setting, the parity type, and the terminator.

```
fprintf(s, 'RS232?', 'async')
```

`instrcallback` is called after the `RS232?` command is sent, and when the terminator is read. The resulting displays are:

```
OutputEmpty event occurred at 17:37:21 for the object:
Serial-COM1.
```

```
BytesAvailable event occurred at 17:37:21 for the object:
Serial-COM1.
```

Read the data from the input buffer.

```
out = fscanf(s)
out =
9600;0;0;NONE;LF
```

- 5 Disconnect and clean up — When you no longer need `s`, disconnect it from the instrument and remove it from memory and from the MATLAB workspace.

```
fclose(s)
delete(s)
clear s
```

Using Control Pins

In this section...

“Properties of Serial Port Control Pins” on page 15-54

“Signaling the Presence of Connected Devices” on page 15-54

“Controlling the Flow of Data: Handshaking” on page 15-57

Properties of Serial Port Control Pins

As described in “Serial Port Signals and Pin Assignments” on page 15-6, 9-pin serial ports include six control pins. The following table shows properties associated with the serial port control pins.

Control Pin Properties

Property Name	Description
<code>DataTerminalReady</code>	State of the DTR pin
<code>FlowControl</code>	Data flow control method to use
<code>PinStatus</code>	State of the CD, CTS, DSR, and RI pins
<code>RequestToSend</code>	State of the RTS pin

Signaling the Presence of Connected Devices

DTEs and DCEs often use the CD, DSR, RI, and DTR pins to indicate whether a connection is established between serial port devices. Once the connection is established, you can begin to write or read data.

To monitor the state of the CD, DSR, and RI pins, use the `PinStatus` property. To specify or monitor the state of the DTR pin, use the `DataTerminalReady` property.

The following example illustrates how these pins are used when two modems are connected to each other.

Note: All examples in this section are based on a Windows 32-bit platform. For more information about other supported platforms, refer to “Overview of a Serial Port Object” on page 15-22.

Example — Connecting Two Modems

This example connects two modems to each other via the same computer, and illustrates how to monitor the communication status for the computer-modem connections, and for the modem-modem connection. The first modem is connected to COM1, while the second modem is connected to COM2.

- 1 Create the serial port objects — After the modems are powered on, the serial port object `s1` is created for the first modem, and the serial port object `s2` is created for the second modem.

```
s1 = serial('COM1');
s2 = serial('COM2');
```

- 2 Connect to the devices — `s1` and `s2` are connected to the modems. Because the default value for the `ReadAsyncMode` property is `continuous`, data is asynchronously returned to the input buffers as soon as it is available from the modems.

```
fopen(s1)
fopen(s2)
```

Because the default `DataTerminalReady` property value is `on`, the computer (data terminal) is now ready to exchange data with the modems. To verify that the modems (data sets) can communicate with the computer, examine the value of the `Data Set Ready` pin using the `PinStatus` property.

```
s1.Pinstatus
ans =
    CarrierDetect: 'off'
    ClearToSend: 'on'
    DataSetReady: 'on'
    RingIndicator: 'off'
```

The value of the `DataSetReady` field is `on` because both modems were powered on before they were connected to the objects.

- 3 Configure properties — Both modems are configured for a baud rate of 2400 bits per second and a carriage return (CR) terminator.

```
s1.BaudRate = 2400;
s1.Terminator = 'CR';
s2.BaudRate = 2400;
s2.Terminator = 'CR';
```

- 4 Write and read data — Write the `atd` command to the first modem. This command puts the modem “off the hook,” which is equivalent to manually lifting a phone receiver.

```
fprintf(s1, 'atd')
```

Write the `ata` command to the second modem. This command puts the modem in “answer mode,” which forces it to connect to the first modem.

```
fprintf(s2, 'ata')
```

After the two modems negotiate their connection, verify the connection status by examining the value of the Carrier Detect pin using the `PinStatus` property.

```
s1.PinStatus
ans =
    CarrierDetect: 'on'
      ClearToSend: 'on'
    DataSetReady: 'on'
    RingIndicator: 'off'
```

Verify the modem-modem connection by reading the descriptive message returned by the second modem.

```
s2.BytesAvailable
ans =
    25
out = fread(s2,25);
char(out) '
ans =
ata
CONNECT 2400/NONE
```

Now break the connection between the two modems by configuring the `DataTerminalReady` property to `off`. To verify the modems are disconnected, examine the Carrier Detect pin value.

```
s1.DataTerminalReady = 'off';
s1.PinStatus
ans =
    CarrierDetect: 'off'
      ClearToSend: 'on'
    DataSetReady: 'on'
    RingIndicator: 'off'
```


- 5 Disconnect and clean up — Disconnect the objects from the modems and remove the objects from memory and from the MATLAB workspace.

```
fclose([s1 s2])
delete([s1 s2])
clear s1 s2
```

Controlling the Flow of Data: Handshaking

Data flow control or *handshaking* is a method used for communicating between a DCE and a DTE to prevent data loss during transmission. For example, suppose your computer can receive only a limited amount of data before it must be processed. As this limit is reached, a handshaking signal is transmitted to the DCE to stop sending data. When the computer can accept more data, another handshaking signal is transmitted to the DCE to resume sending data.

If supported by your device, you can control data flow using one of these methods:

- Hardware handshaking
- Software handshaking

Note: Although you might be able to configure your device for both hardware handshaking and software handshaking at the same time, MATLAB does not support this behavior.

To specify the data flow control method, use the `FlowControl` property. If `FlowControl` is `hardware`, hardware handshaking is used to control data flow. If `FlowControl` is `software`, software handshaking is used to control data flow. If `FlowControl` is `none`, no handshaking is used.

Hardware Handshaking

Hardware handshaking uses specific serial port pins to control data flow. In most cases, these are the RTS and CTS pins. Hardware handshaking using these pins is described in “The RTS and CTS Pins” on page 15-8.

If `FlowControl` is `hardware`, the RTS and CTS pins are automatically managed by the DTE and DCE. To return the CTS pin value, use the `PinStatus` property. Configure or return the RTS pin value with the `RequestToSend` property.

Note: Some devices also use the DTR and DSR pins for handshaking. However, these pins are typically used to indicate that the system is ready for communication, and are not used to control data transmission. In MATLAB, hardware handshaking always uses the RTS and CTS pins.

If your device does not use hardware handshaking in the standard way, then you might need to manually configure the `RequestToSend` property. In this case, you should configure `FlowControl` to `none`. If `FlowControl` is hardware, then the `RequestToSend` value that you specify might not be honored. Refer to the device documentation to determine its specific pin behavior.

Software Handshaking

Software handshaking uses specific ASCII characters to control data flow. These characters, known as Xon and Xoff (or XON and XOFF), are described in the following table.

Software Handshaking Characters

Character	Integer Value	Description
Xon	17	Resume data transmission
Xoff	19	Pause data transmission

When using software handshaking, the control characters are sent over the transmission line the same way as regular data. Therefore, only the TD, RD, and GND pins are needed.

The main disadvantage of software handshaking is that Xon or Xoff characters are not writable while numerical data is being written to the device. This is because numerical data might contain a 17 or 19, which makes it impossible to distinguish between the control characters and the data. However, you can write Xon or Xoff while data is being asynchronously read from the device because you are using both the TD and RD pins.

Example: Using Software Handshaking

Suppose you want to use software flow control with the example described in “Example — Reading Binary Data” on page 15-43. To do this, you must configure the oscilloscope and serial port object for software flow control.

```
fprintf(s, 'RS232:SOFTF ON')
```

```
s.FlowControl = 'software';
```

To pause data transfer, write the numerical value **19** to the device.

```
fwrite(s,19)
```

To resume data transfer, write the numerical value **17** to the device.

```
fwrite(s,17)
```

Debugging: Recording Information to Disk

In this section...

“Introduction” on page 15-60

“Recording Properties” on page 15-60

“Example: Introduction to Recording Information” on page 15-61

“Creating Multiple Record Files” on page 15-61

“Specifying a Filename” on page 15-61

“The Record File Format” on page 15-62

“Example: Recording Information to Disk” on page 15-63

Introduction

Recording information to disk provides a permanent record of your serial port session, and is an easy way to debug your application. While the serial port object is connected to the device, you can record the following information to a disk file:

- The number of values written to the device, the number of values read from the device, and the data type of the values
- Data written to the device, and data read from the device
- Event information

Recording Properties

You record information to a disk file with the `record` function. The following table shows the properties associated with recording information to disk.

Recording Properties

Property Name	Description
RecordDetail	Amount of information saved to a record file
RecordMode	Specify whether data and event information is saved to one record file or to multiple record files
RecordName	Name of the record file
RecordStatus	Indicate if data and event information are saved to a record file

Note: All examples in this section are based on a Windows 32-bit platform. For more information about other supported platforms, refer to “Overview of a Serial Port Object” on page 15-22.

Example: Introduction to Recording Information

This example records the number of values written to and read from the device, and stores the information to the file `myfile.txt`.

```
s = serial('COM1');
fopen(s)
s.RecordName = 'myfile.txt';
record(s)
fprintf(s, '*IDN?')
idn = fscanf(s);
fprintf(s, 'RS232?')
rs232 = fscanf(s);
```

End the serial port session.

```
fclose(s)
delete(s)
clear s
```

To display `myfile.txt` at the command line, use the `type` command.

Creating Multiple Record Files

When you initiate recording with the `record` function, the `RecordMode` property determines if a new record file is created or if new information is appended to an existing record file.

You can configure `RecordMode` to `overwrite`, `append`, or `index`. If `RecordMode` is `overwrite`, the record file is overwritten each time recording is initiated. If `RecordMode` is `append`, the new information is appended to the file specified by `RecordName`. If `RecordMode` is `index`, a different disk file is created each time recording is initiated. The rules for specifying a record filename are discussed in the next section.

Specifying a Filename

You specify the name of the record file with the `RecordName` property. You can specify any value for `RecordName` — including a directory path — provided the filename is

supported by your operating system. Additionally, if `RecordMode` is `index`, the filename follows these rules:

- Indexed filenames are identified by a number. This number precedes the filename extension and is increased by 1 for successive record files.
- If no number is specified as part of the initial filename, the first record file does not have a number associated with it. For example, if `RecordName` is `myfile.txt`, `myfile.txt` is the name of the first record file, `myfile01.txt` is the name of the second record file, and so on.
- `RecordName` is updated after the record file is closed.
- If the specified filename already exists, the existing file is overwritten.

The Record File Format

The record file is an ASCII file that contains a record of one or more serial port sessions. You specify the amount of information saved to a record file with the `RecordDetail` property.

`RecordDetail` can be `compact` or `verbose`. A compact record file contains the number of values written to the device, the number of values read from the device, the data type of the values, and event information. A verbose record file contains the preceding information as well as the data transferred to and from the device.

Binary data with precision given by `uchar`, `schar`, `(u)int8`, `(u)int16`, or `(u)int32` is recorded using hexadecimal format. For example, if the integer value 255 is read from the instrument as a 16-bit integer, the hexadecimal value 00FF is saved in the record file. Single- and double-precision floating-point numbers are recorded as decimal values using the `%g` format, and as hexadecimal values using the format specified by the IEEE[®] Standard 754-1985 for Binary Floating-Point Arithmetic.

The IEEE floating-point format includes three components: the sign bit, the exponent field, and the significant field. Single-precision floating-point values consist of 32 bits. The value is given by

$$\text{value} = (-1)^{\text{sign}} (2^{\text{exp}-127})(1.\text{significand})$$

Double-precision floating-point values consist of 64 bits. The value is given by

$$\text{value} = (-1)^{\text{sign}} (2^{\text{exp}-1023})(1.\text{significand})$$

The floating-point format component, and the associated single-precision and double-precision bits are shown in the following table.

Component	Single-Precision Bits	Double-Precision Bits
sign	1	1
exp	2–9	2–12
significand	10–32	13–64

Bit 1 is the left-most bit as stored in the record file.

Example: Recording Information to Disk

This example illustrates how to record information transferred between a serial port object and a Tektronix TDS 210 oscilloscope. Additionally, the structure of the resulting record file is presented.

- 1 Create the serial port object — Create the serial port object `s` associated with the serial port `COM1`.


```
s = serial('COM1');
```
- 2 Connect to the device — Connect `s` to the oscilloscope. Because the default value for the `ReadAsyncMode` property is `continuous`, data is asynchronously returned the input buffer as soon as it is available from the instrument.


```
fopen(s)
```
- 3 Configure property values — Configure `s` to record information to multiple disk files using the verbose format. Recording is then initiated with the first disk file defined as `WaveForm1.txt`.


```
s.RecordMode = 'index';
s.RecordDetail = 'verbose';
s.RecordName = 'WaveForm1.txt';
record(s)
```
- 4 Write and read data — The commands written to the instrument, and the data read from the instrument are recorded in the record file. For an explanation of the oscilloscope commands, see “Example — Writing and Reading Text Data” on page 15-41.

```
fprintf(s, '*IDN?')
```

```
idn = fscanf(s);  
fprintf(s, 'MEASUREMENT:IMMED:SOURCE CH2')  
fprintf(s, 'MEASUREMENT:IMMED:SOURCE?')  
source = fscanf(s);
```

Read the peak-to-peak voltage with the `fread` function. Note that the data returned by `fread` is recorded using hex format.

```
fprintf(s, 'MEASUREMENT:MEAS1:TYPE PK2PK')  
fprintf(s, 'MEASUREMENT:MEAS1:VALUE?')  
ptop = fread(s,s.BytesAvailable);
```

Convert the peak-to-peak voltage to a character array.

```
char(ptop)'  
ans =  
2.0199999809E0
```

The recording state is toggled from `on` to `off`. Because the `RecordMode` value is `index`, the record filename is automatically updated.

```
record(s)  
s.RecordStatus  
ans =  
off  
s.RecordName  
ans =  
WaveForm2.txt
```

- 5 Disconnect and clean up — When you no longer need `s`, disconnect it from the instrument, and remove it from memory and from the MATLAB workspace.

```
fclose(s)  
delete(s)  
clear s
```

The Record File Contents

The contents of the `WaveForm1.txt` record file are shown below. Because the `RecordDetail` property was `verbose`, the number of values, commands, and data were recorded. Note that data returned by the `fread` function is in hex format.

```
type WaveForm1.txt
```

Legend:

* - An event occurred.


```
> - A write operation occurred.
< - A read operation occurred.
1   Recording on 22-Jan-2000 at 11:21:21.575. Binary data in...
2   > 6 ascii values.
    *IDN?
3   < 56 ascii values.
    TEKTRONIX,TDS 210,0,CF:91.1CT FV:v1.16 TDS2CM:CMV:v1.04
4   > 29 ascii values.
    MEASUREMENT:IMMED:SOURCE CH2
5   > 26 ascii values.
    MEASUREMENT:IMMED:SOURCE?
6   < 4 ascii values.
    CH2
7   > 27 ascii values.
    MEASUREMENT:MEAS1:TYPE PK2PK
8   > 25 ascii values.
    MEASUREMENT:MEAS1:VALUE?
9   < 15 uchar values.
    32 2e 30 31 39 39 39 39 38 30 39 45 30 0a
10  Recording off.
```

Saving and Loading

In this section...

“Using save and load” on page 15-66

“Using Serial Port Objects on Different Platforms” on page 15-66

Using save and load

Save serial port objects to a file, just as you would any workspace variable, using the `save` command. For example, suppose you create the serial port object `s` associated with the serial port COM1, configure several property values, and perform a write and read operation.

```
s = serial('COM1');
s.BaudRate = 19200;
s.Tag = 'My serial object';
fopen(s)
fprintf(s, '*IDN?')
out = fscanf(s);
```

To save the serial port object and the data read from the device to the file `myserial.mat`:

```
save myserial s out
```

Note: To save data and event information as text to a disk file, use the `record` function.

You can recreate `s` and `out` in the workspace using the `load` command.

```
load myserial
```

Values for read only properties are restored to their default values upon loading. For example, the `Status` property is restored to `closed`. Therefore, to use `s`, you must connect it to the device with the `fopen` function. To determine if a property is read only, examine its reference pages.

Using Serial Port Objects on Different Platforms

If you save a serial port object from one platform, and then load that object on a different platform having different serial port names, you need to modify the `Port` property value.

For example, suppose you create the serial port object `s` associated with the serial port COM1 on a Microsoft Windows platform. If you want to save `s` for eventual use on a Linux platform, configure `Port` to an appropriate value such as `ttyS0` after the object is loaded.

Disconnecting and Cleaning Up

In this section...

“Disconnecting a Serial Port Object” on page 15-68

“Cleaning Up the MATLAB Environment” on page 15-68

Disconnecting a Serial Port Object

When you no longer need to communicate with the device, disconnect it from the serial port object with the `fclose` function.

```
fclose(s)
```

Examine the `Status` property to verify that the serial port object and the device are disconnected.

```
s.Status  
ans =  
closed
```

After `fclose` is issued, the serial port associated with `s` is available. Now connect another serial port object to it using `fopen`.

Cleaning Up the MATLAB Environment

When the serial port object is no longer needed, remove it from memory with the `delete` function.

```
delete(s)
```

Before using `delete`, disconnect the serial port object from the device with the `fclose` function.

A deleted serial port object is *invalid*, which means that you cannot connect it to the device. In this case, remove the object from the MATLAB workspace. To remove serial port objects and other variables from the MATLAB workspace, use the `clear` command.

```
clear s
```

Use `clear` on a serial port object that is still connected to a device to remove the object from the workspace but leave it connected to the device. Restore cleared objects to MATLAB with the `instrfind` function.

Property Reference

In this section...
“The Property Reference Page Format” on page 15-70
“Serial Port Object Properties” on page 15-70

The Property Reference Page Format

Each serial port property description contains some or all of this information:

- The property name
- A description of the property
- The property characteristics, including:
 - Read only — The condition under which the property is read only

A property can be read-only always, never, while the serial port object is open, or while the serial port object is recording. You can configure a property value using the `set` function or dot notation. You can return the current property value using the `get` function or dot notation.

- Data type — the property data type

This is the data type you use when specifying a property value.

- Valid property values including the default value

When property values are given by a predefined list, the default value is usually indicated by `{}`.

- An example using the property
- Related properties and functions

Serial Port Object Properties

The serial port object properties are briefly described below, and organized into categories based on how they are used. Following this section the properties are listed alphabetically and described in detail.

Communications Properties	
BaudRate	Rate at which bits are transmitted
DataBits	Number of data bits to transmit
Parity	Type of parity checking
StopBits	Number of bits used to indicate the end of a byte
Terminator	Terminator character

Write Properties	
BytesToOutput	Number of bytes currently in the output buffer
OutputBufferSize	Size of the output buffer in bytes
Timeout	Waiting time to complete a read or write operation
TransferStatus	Indicate if an asynchronous read or write operation is in progress
ValuesSent	Total number of values written to the device

Read Properties	
BytesAvailable	Number of bytes available in the input buffer
InputBufferSize	Size of the input buffer in bytes
ReadAsyncMode	Specify whether an asynchronous read operation is continuous or manual
Timeout	Waiting time to complete a read or write operation
TransferStatus	Indicate if an asynchronous read or write operation is in progress
ValuesReceived	Total number of values read from the device

Callback Properties	
BreakInterruptFcn	Callback function to execute when a break-interrupt event occurs
BytesAvailableFcn	Callback function to execute when a specified number of bytes is available in the input buffer, or a terminator is read

Callback Properties	
BytesAvailableFcnCount	Number of bytes that must be available in the input buffer to generate a bytes-available event
BytesAvailableFcnMode	Specify if the bytes-available event is generated after a specified number of bytes is available in the input buffer, or after a terminator is read
ErrorFcn	Callback function to execute when an error event occurs
OutputEmptyFcn	Callback function to execute when the output buffer is empty
PinStatusFcn	Callback function to execute when the CD, CTS, DSR, or RI pins change state
TimerFcn	Callback function to execute when a predefined period of time passes
TimerPeriod	Period of time between timer events

Control Pin Properties	
DataTerminalReady	State of the DTR pin
FlowControl	Data flow control method to use
PinStatus	State of the CD, CTS, DSR, and RI pins
RequestToSend	State of the RTS pin

Recording Properties	
RecordDetail	Amount of information saved to a record file
RecordMode	Specify whether data and event information are saved to one record file or to multiple record files
RecordName	Name of the record file
RecordStatus	Indicate if data and event information are saved to a record file

General Purpose Properties	
ByteOrder	Order in which the device stores bytes
Name	Descriptive name for the serial port object

General Purpose Properties	
Port	Platform-specific serial port name
Status	Indicate if the serial port object is connected to the device
Tag	Label to associate with a serial port object
Type	Object type
UserData	Data you want to associate with a serial port object

Properties — Alphabetical List

BaudRate

Specify the rate at which bits are transmitted

Description

You configure **BaudRate** as bits per second. The transferred bits include the start bit, the data bits, the parity bit (if used), and the stop bits. However, only the data bits are stored.

The baud rate is the rate at which information is transferred in a communication channel. In the serial port context, “9600 baud” means that the serial port is capable of transferring a maximum of 9600 bits per second. If the information unit is one baud (one bit), the bit rate and the baud rate are identical. If one baud is given as 10 bits, (for example, eight data bits plus two framing bits), the bit rate is still 9600 but the baud rate is 9600/10, or 960. You always configure **BaudRate** as bits per second. Therefore, in the previous example, set **BaudRate** to 9600.

Note: Both the computer and the peripheral device must be configured to the same baud rate before you can successfully read or write data.

Standard baud rates include 110, 300, 600, 1200, 2400, 4800, 9600, 14400, 19200, 38400, 57600, 115200, 128000 and 256000 bits per second. To display the supported baud rates for the serial ports on your platform, see “Finding Serial Port Information for Your Platform” on page 15-13.

Characteristics

Read only	Never
Data type	Double

Values

The default value is **9600**.

See Also

Properties

DataBits, Parity, StopBits

BreakInterruptFcn

Specify the callback function to execute when a break-interrupt event occurs

Description

You configure `BreakInterruptFcn` to execute a callback function when a break-interrupt event occurs. A break-interrupt event is generated by the serial port when the received data is in an off (space) state longer than the transmission time for one byte.

Note: A break-interrupt event can be generated at any time during the serial port session.

If the `RecordStatus` property value is `on`, and a break-interrupt event occurs, the record file records this information:

- The event type as `BreakInterrupt`
- The time the event occurred using the format `day-month-year hour:minute:second:millisecond`

To learn how to create a callback function, see “Creating and Executing Callback Functions” on page 15-51.

Characteristics

Read only	Never
Data type	Callback function

Values

The default value is an empty string.

See Also

Functions

record

Properties

RecordStatus

ByteOrder

Specify the byte order of the device

Description

You configure `ByteOrder` to be `littleEndian` or `bigEndian`. If `ByteOrder` is `littleEndian`, the device stores the first byte in the first memory address. If `ByteOrder` is `bigEndian`, the device stores the last byte in the first memory address.

For example, suppose the hexadecimal value `4F52` is to be stored in device memory. Because this value consists of two bytes, `4F` and `52`, two memory locations are used. Using big-endian format, `4F` is stored first in the lower storage address. Using little-endian format, `52` is stored first in the lower storage address.

Note: Configure `ByteOrder` to the appropriate value for your device before performing a read or write operation. Refer to your device documentation for information about the order in which it stores bytes.

Characteristics

Read only	Never
Data type	String

Values

<code>{littleEndian}</code>	The byte order of the device is little-endian.
<code>bigEndian</code>	The byte order of the device is big-endian.

See Also

Properties

Status

BytesAvailable

Number of bytes available in the input buffer

Description

`BytesAvailable` indicates the number of bytes currently available to be read from the input buffer. The property value is continuously updated as the input buffer is filled, and is set to 0 after the `fopen` function is issued.

You can make use of `BytesAvailable` only when reading data asynchronously. This is because when reading data synchronously, control is returned to the MATLAB command line only after the input buffer is empty. Therefore, the `BytesAvailable` value is always 0. To learn how to read data asynchronously, see “Reading Text Data” on page 15-38.

The `BytesAvailable` value can range from zero to the size of the input buffer. Use the `InputBufferSize` property to specify the size of the input buffer. Use the `ValuesReceived` property to return the total number of values read.

Characteristics

Read only	Always
Data type	Double

Values

The default value is 0.

See Also

Functions

`fopen`

Properties

InputBufferSize, TransferStatus, ValuesReceived

BytesAvailableFcn

Specify the callback function to execute when a specified number of bytes is available in the input buffer, or a terminator is read

Description

You configure `BytesAvailableFcn` to execute a callback function when a bytes-available event occurs. A bytes-available event occurs when the number of bytes specified by the `BytesAvailableFcnCount` property is available in the input buffer, or after a terminator is read, as determined by the `BytesAvailableFcnMode` property.

Note: A bytes-available event can be generated only for asynchronous read operations.

If the `RecordStatus` property value is `on`, and a bytes-available event occurs, the record file records this information:

- The event type as `BytesAvailable`
- The time the event occurred using the format day-month-year hour:minute:second:millisecond

To learn how to create a callback function, see “Creating and Executing Callback Functions” on page 15-51.

Characteristics

Read only	Never
Data type	Callback function

Values

The default value is an empty string.

Example

Create the serial port object `s` for a Tektronix TDS 210 two-channel oscilloscope connected to the serial port COM1.

```
s = serial('COM1');
```

Configure `s` to execute the callback function `instrcallback` when 40 bytes are available in the input buffer.

```
s.BytesAvailableFcnCount = 40;  
s.BytesAvailableFcnMode = 'byte';  
s.BytesAvailableFcn = @instrcallback;
```

Connect `s` to the oscilloscope.

```
fopen(s)
```

Write the `*IDN?` command, which instructs the scope to return identification information. Because the default value for the `ReadAsyncMode` property is `continuous`, data is read as soon as it is available from the instrument.

```
fprintf(s, '*IDN?')
```

MATLAB displays:

```
BytesAvailable event occurred at 18:33:35 for the object:  
Serial-COM1.
```

56 bytes are read and `instrcallback` is called once. The resulting display is shown above.

```
s.BytesAvailable  
ans =  
    56
```

Suppose you remove 25 bytes from the input buffer and then issue the `MEASUREMENT?` command, which instructs the scope to return its measurement settings.

```
out = fscanf(s, '%c', 25);  
fprintf(s, 'MEASUREMENT?')
```

MATLAB displays:

```
BytesAvailable event occurred at 18:33:48 for the object:
```

Serial-COM1.

BytesAvailable event occurred at 18:33:48 for the object:
Serial-COM1.

There are now 102 bytes in the input buffer, 31 of which are left over from the *IDN? command. `instrcallback` is called twice—once when 40 bytes are available and once when 80 bytes are available.

```
s.BytesAvailable  
ans =  
    102
```

See Also

Functions

`record`

Properties

`BytesAvailableFcnCount`, `BytesAvailableFcnMode`, `RecordStatus`, `Terminator`, `TransferStatus`

BytesAvailableFcnCount

Specify the number of bytes that must be available in the input buffer to generate a bytes-available event

Description

You configure `BytesAvailableFcnCount` to the number of bytes that must be available in the input buffer before a bytes-available event is generated.

Use the `BytesAvailableFcnMode` property to specify whether the bytes-available event occurs after a certain number of bytes are available or after a terminator is read.

The bytes-available event executes the callback function specified for the `BytesAvailableFcn` property.

You can configure `BytesAvailableFcnCount` only when the object is disconnected from the device. You disconnect an object with the `fclose` function. A disconnected object has a `Status` property value of `closed`.

Characteristics

Read only	While open
Data type	Double

Values

The default value is 48.

See Also

Functions

`fclose`

Properties

BytesAvailableFcn, BytesAvailableFcnMode, Status

BytesAvailableFcnMode

Specify if the bytes-available event is generated after a specified number of bytes is available in the input buffer, or after a terminator is read

Description

You can configure `BytesAvailableFcnMode` to be `terminator` or `byte`. If `BytesAvailableFcnMode` is `terminator`, a bytes-available event occurs when the terminator specified by the `Terminator` property is reached. If `BytesAvailableFcnMode` is `byte`, a bytes-available event occurs when the number of bytes specified by the `BytesAvailableFcnCount` property is available.

The bytes-available event executes the callback function specified for the `BytesAvailableFcn` property.

You can configure `BytesAvailableFcnMode` only when the object is disconnected from the device. You disconnect an object with the `fclose` function. A disconnected object has a `Status` property value of `closed`.

Characteristics

Read only	While open
Data type	String

Values

<code>{terminator}</code>	A bytes-available event is generated when the terminator is read.
<code>byte</code>	A bytes-available event is generated when the specified number of bytes are available.

See Also

Functions

`fclose`

Properties

`BytesAvailableFcn`, `BytesAvailableFcnCount`, `Status`, `Terminator`

BytesToOutput

Number of bytes currently in the output buffer

Description

BytesToOutput indicates the number of bytes currently in the output buffer waiting to be written to the device. The property value is continuously updated as the output buffer is filled and emptied, and is set to 0 after the `fopen` function is issued.

You can make use of BytesToOutput only when writing data asynchronously. This is because when writing data synchronously, control is returned to the MATLAB command line only after the output buffer is empty. Therefore, the BytesToOutput value is always 0. To learn how to write data asynchronously, see “Writing Text Data” on page 15-32.

Use the ValuesSent property to return the total number of values written to the device.

Note: If you attempt to write out more data than can fit in the output buffer, an error is returned and BytesToOutput is 0. Specify the size of the output buffer with the OutputBufferSize property.

Characteristics

Read only	Always
Data type	Double

Values

The default value is 0.

See Also

Functions

fopen

Properties

OutputBufferSize, TransferStatus, ValuesSent

DataBits

Number of data bits to transmit

Description

You can configure **DataBits** to be 5, 6, 7, or 8. Data is transmitted as a series of five, six, seven, or eight bits with the least significant bit sent first. At least seven data bits are required to transmit ASCII characters. Eight bits are required to transmit binary data. Five and six bit data formats are used for specialized communications equipment.

Note: Both the computer and the peripheral device must be configured to transmit the same number of data bits.

In addition to the data bits, the serial data format consists of a start bit, one or two stop bits, and possibly a parity bit. You specify the number of stop bits with the **StopBits** property, and the type of parity checking with the **Parity** property.

To display the supported number of data bits for the serial ports on your platform, see “Finding Serial Port Information for Your Platform” on page 15-13.

Characteristics

Read only	Never
Data type	Double

Values

DataBits can be 5, 6, 7, or 8. The default value is 8.

See Also

Properties

Parity, StopBits

DataTerminalReady

State of the DTR pin

Description

You can configure `DataTerminalReady` to be on or off. If `DataTerminalReady` is on, the Data Terminal Ready (DTR) pin is asserted. If `DataTerminalReady` is off, the DTR pin is unasserted.

In normal usage, the DTR and Data Set Ready (DSR) pins work together, and are used to signal if devices are connected and powered. However, there is nothing in the RS-232 standard that states the DTR pin must be used in any specific way. For example, DTR and DSR might be used for handshaking. You should refer to your device documentation to determine its specific pin behavior.

You can return the value of the DSR pin with the `PinStatus` property. Handshaking is described in “Controlling the Flow of Data: Handshaking” on page 15-57.

Characteristics

Read only	Never
Data type	String

Values

{on}	The DTR pin is asserted.
off	The DTR pin is unasserted.

See Also

Properties

`FlowControl`, `PinStatus`

ErrorFcn

Specify the callback function to execute when an error event occurs

Description

You configure `ErrorFcn` to execute a callback function when an error event occurs.

Note: An error event is generated only for asynchronous read and write operations.

An error event is generated when a time-out occurs. A time-out occurs if a read or write operation does not successfully complete within the time specified by the `Timeout` property. An error event is not generated for configuration errors such as setting an invalid property value.

If the `RecordStatus` property value is `on`, and an error event occurs, the record file records this information:

- The event type as `Error`
- The error message
- The time the event occurred using the format `day-month-year hour:minute:second:millisecond`

To learn how to create a callback function, see “Creating and Executing Callback Functions” on page 15-51.

Characteristics

Read only	Never
Data type	Callback function

Values

The default value is an empty string.

See Also

Functions

record

Properties

RecordStatus, Timeout

FlowControl

Data flow control method to use

Description

You can configure `FlowControl` to be `none`, `hardware`, or `software`. If `FlowControl` is `none`, data flow control (handshaking) is not used. If `FlowControl` is `hardware`, hardware handshaking is used to control data flow. If `FlowControl` is `software`, software handshaking is used to control data flow.

Hardware handshaking typically utilizes the Request to Send (RTS) and Clear to Send (CTS) pins to control data flow. Software handshaking uses control characters (Xon and Xoff) to control data flow. For more information about handshaking, see “Controlling the Flow of Data: Handshaking” on page 15-57.

You can return the value of the CTS pin with the `PinStatus` property. You can specify the value of the RTS pin with the `RequestToSend` property. However, if `FlowControl` is `hardware`, and you specify a value for `RequestToSend`, that value might not be honored.

Note: Although you might be able to configure your device for both hardware handshaking and software handshaking at the same time, MATLAB does not support this behavior.

Characteristics

Read only	Never
Data type	String

Values

{none}	No flow control is used.
hardware	Hardware flow control is used.

software	Software flow control is used.
----------	--------------------------------

See Also

Properties

PinStatus, RequestToSend

InputBufferSize

Size of the input buffer in bytes

Description

You configure `InputBufferSize` as the total number of bytes that can be stored in the input buffer during a read operation.

A read operation is terminated if the amount of data stored in the input buffer equals the `InputBufferSize` value. You can read text data with the `fgetl`, `fget`, or `fscanf` functions. You can read binary data with the `fread` function.

You can configure `InputBufferSize` only when the serial port object is disconnected from the device. You disconnect an object with the `fclose` function. A disconnected object has a `Status` property value of `closed`.

If you configure `InputBufferSize` while there is data in the input buffer, that data is flushed.

Characteristics

Read only	While open
Data type	Double

Values

The default value is 512.

See Also

Functions

`fclose`, `fgetl`, `fgets`, `fopen`, `fread`, `fscanf`

Properties

Status

Name

Descriptive name for the serial port object

Description

You configure **Name** to be a descriptive name for the serial port object.

When you create a serial port object, a descriptive name is automatically generated and stored in **Name**. This name is given by concatenating the word “Serial” with the serial port specified in the `serial` function. However, you can change the value of **Name** at any time.

The serial port is given by the **Port** property. If you modify this property value, then **Name** is automatically updated to reflect that change.

Characteristics

Read only	Never
Data type	String

Values

Name is automatically defined when the serial port object is created.

Example

Suppose you create a serial port object associated with the serial port COM1.

```
s = serial('COM1');
```

s is automatically assigned a descriptive name.

```
s.Name  
ans =
```

Serial-COM1

See Also

Functions

serial

ObjectVisibility

Control access to serial port object

Description

The `ObjectVisibility` property provides a way for application developers to prevent end-user access to the serial port objects created by their applications. When an object's `ObjectVisibility` property is set to `off`, `instrfind` does not return or delete that object.

Objects that are not visible are still valid. If you have access to the object (for example, from within the file that creates it), you can set and get its properties and pass it to any function that operates on serial port objects.

Characteristics

Usage	Any serial port object
Read only	Never
Data type	String

Values

{on}	Object is visible to <code>instrfind</code> .
off	Object is not visible from the command line (except by <code>instrfindall</code>).

Examples

The following statement creates a serial port object with its `ObjectVisibility` property set to `off`:

```
s = serial('COM1', 'ObjectVisibility', 'off');
```

```
instrfind
ans =
     []
```

However, because the hidden object is in the workspace (**s**), you can access it.

```
get(s,'ObjectVisibility')
ans =
    off
```

See Also

Functions

`instrfind`, `instrfindall`

OutputBufferSize

Size of the output buffer in bytes

Description

You configure `OutputBufferSize` as the total number of bytes that can be stored in the output buffer during a write operation.

An error occurs if the output buffer cannot hold all the data to be written. You write text data with the `fprintf` function. You write binary data with the `fwrite` function.

You can configure `OutputBufferSize` only when the serial port object is disconnected from the device. You disconnect an object with the `fclose` function. A disconnected object has a `Status` property value of `closed`.

Characteristics

Read only	While open
Data type	Double

Values

The default value is 512.

See Also

Functions

`fprintf`, `fwrite`

Properties

`Status`

OutputEmptyFcn

Specify the callback function to execute when the output buffer is empty

Description

You configure OutputEmptyFcn to execute a callback function when an output-empty event occurs. An output-empty event is generated when the last byte is sent from the output buffer to the device.

Note: An output-empty event can be generated only for asynchronous write operations.

If the RecordStatus property value is on, and an output-empty event occurs, the record file records this information:

- The event type as **OutputEmpty**
- The time the event occurred using the format day-month-year
hour:minute:second:millisecond

To learn how to create a callback function, see “Creating and Executing Callback Functions” on page 15-51.

Characteristics

Read only	Never
Data type	Callback function

Values

The default value is an empty string.

See Also

Functions

record

Properties

RecordStatus

Parity

Specify the type of parity checking

Description

You can configure **Parity** to be **none**, **odd**, **even**, **mark**, or **space**. If **Parity** is **none**, parity checking is not performed and the parity bit is not transmitted. If **Parity** is **odd**, the number of mark bits (1s) in the data is counted, and the parity bit is asserted or unasserted to obtain an odd number of mark bits. If **Parity** is **even**, the number of mark bits in the data is counted, and the parity bit is asserted or unasserted to obtain an even number of mark bits. If **Parity** is **mark**, the parity bit is asserted. If **Parity** is **space**, the parity bit is unasserted.

Parity checking can detect errors of one bit only. An error in two bits might cause the data to have a seemingly valid parity, when in fact it is incorrect. For more information about parity checking, see “The Parity Bit” on page 15-12.

In addition to the parity bit, the serial data format consists of a start bit, between five and eight data bits, and one or two stop bits. You specify the number of data bits with the **DataBits** property, and the number of stop bits with the **StopBits** property.

Characteristics

Read only	Never
Data type	String

Values

{none}	No parity checking
odd	Odd parity checking
even	Even parity checking
mark	Mark parity checking

space	Space parity checking
-------	-----------------------

See Also

Properties

DataBits, StopBits

PinStatus

State of the CD, CTS, DSR, and RI pins

Description

`PinStatus` is a structure array that contains the fields `CarrierDetect`, `ClearToSend`, `DataSetReady` and `RingIndicator`. These fields indicate the state of the Carrier Detect (CD), Clear to Send (CTS), Data Set Ready (DSR) and Ring Indicator (RI) pins, respectively. For more information about these pins, see “Serial Port Signals and Pin Assignments” on page 15-6.

`PinStatus` can be `on` or `off` for any of these fields. A value of `on` indicates the associated pin is asserted. A value of `off` indicates the associated pin is unasserted. A pin status event occurs when any of these pins changes its state. A pin status event executes the call back function specified by `PinStatusFcn`.

In normal usage, the Data Terminal Ready (DTR) and DSR pins work together, while the Request to Send (RTS) and CTS pins work together. You can specify the state of the DTR pin with the `DataTerminalReady` property. You can specify the state of the RTS pin with the `RequestToSend` property.

For an example that uses `PinStatus`, see “Example — Connecting Two Modems” on page 15-55.

Characteristics

Read only	Always
Data type	Structure

Values

<code>off</code>	The associated pin is unasserted.
<code>on</code>	The associated pin is asserted.

The default value is device dependent.

See Also

Properties

`DataTerminalReady`, `PinStatusFcn`, `RequestToSend`

PinStatusFcn

Specify the callback function to execute when the CD, CTS, DSR, or RI pins change state

Description

You configure `PinStatusFcn` to execute a callback function when a pin status event occurs. A pin status event occurs when the Carrier Detect (CD), Clear to Send (CTS), Data Set Ready (DSR) or Ring Indicator (RI) pin changes state. A serial port pin changes state when it is asserted or unasserted. Information about the state of these pins is recorded in the `PinStatus` property.

Note: A pin status event can be generated at any time during the serial port session.

If the `RecordStatus` property value is `on`, and a pin status event occurs, the record file records this information:

- The event type as `PinStatus`
- The pin that changed its state, and the pin state as either `on` or `off`
- The time the event occurred using the format day-month-year hour:minute:second:millisecond

To learn how to create a callback function, see “Creating and Executing Callback Functions” on page 15-51.

Characteristics

Read only	Never
Data type	Callback function

Values

The default value is an empty string.

See Also

Functions

record

Properties

PinStatus, RecordStatus

Port

Specify the platform-specific serial port name

Description

You configure `Port` to be the name of a serial port on your platform. `Port` specifies the physical port associated with the object and the device.

When you create a serial port object, `Port` is automatically assigned the port name specified for the `serial` function.

You can configure `Port` only when the object is disconnected from the device. You disconnect an object with the `fclose` function. A disconnected object has a `Status` property value of `closed`.

Characteristics

Read only	While open
Data type	String

Values

The `Port` value is determined when the serial port object is created.

Example

Suppose you create a serial port object associated with serial port `COM1`.

```
s = serial('COM1');
```

The value of the `Port` property is `COM1`.

```
s.Port  
ans =
```

COM1

See Also

Functions

`fclose`, `serial`

Properties

`Name`, `Status`

ReadAsyncMode

Specify whether an asynchronous read operation is continuous or manual

Description

You can configure `ReadAsyncMode` to be `continuous` or `manual`. If `ReadAsyncMode` is `continuous`, the serial port object continuously queries the device to determine if data is available to be read. If data is available, it is automatically read and stored in the input buffer. If issued, the `readasync` function is ignored.

If `ReadAsyncMode` is `manual`, the object does not query the device to determine if data is available to be read. Instead, you must manually issue the `readasync` function to perform an asynchronous read operation. Because `readasync` checks for the terminator, this function can be slow. To increase speed, configure `ReadAsyncMode` to `continuous`.

Note: If the device is ready to transmit data, it will do so regardless of the `ReadAsyncMode` value. Therefore, if `ReadAsyncMode` is `manual` and a read operation is not in progress, data might be lost. To guarantee that all transmitted data is stored in the input buffer, you should configure `ReadAsyncMode` to `continuous`.

To determine the amount of data available in the input buffer, use the `BytesAvailable` property. For either `ReadAsyncMode` value, you can bring data into the MATLAB workspace with one of the synchronous read functions such as `fscanf`, `fgetl`, `fgets`, or `fread`.

Characteristics

Read only	Never
Data type	String

Values

{ <code>continuous</code> }	Continuously query the device to determine if data is available to be read.
-----------------------------	---

manual	Manually read data from the device using the <code>readasync</code> function.
--------	---

See Also

Functions

`fgetl`, `fgets`, `fread`, `fscanf`, `readasync`

Properties

`BytesAvailable`, `InputBufferSize`

RecordDetail

Specify the amount of information saved to a record file

Description

You can configure `RecordDetail` to be `compact` or `verbose`. If `RecordDetail` is `compact`, the number of values written to the device, the number of values read from the device, the data type of the values, and event information are saved to the record file. If `RecordDetail` is `verbose`, the data written to the device, and the data read from the device are also saved to the record file.

The event information saved to a record file is shown in the table, `Event Information`. The verbose record file structure is shown in “Example: Recording Information to Disk” on page 15-63.

Characteristics

Read only	Never
Data type	String

Values

<code>{compact}</code>	The number of values written to the device, the number of values read from the device, the data type of the values, and event information are saved to the record file.
<code>verbose</code>	The data written to the device, and the data read from the device are also saved to the record file.

See Also

Functions

`record`

Properties

RecordMode, RecordName, RecordStatus

RecordMode

Specify whether data and event information are saved to one record file or to multiple record files

Description

You can configure `RecordMode` to be `overwrite`, `append`, or `index`. If `RecordMode` is `overwrite`, the record file is overwritten each time recording is initiated. If `RecordMode` is `append`, data is appended to the record file each time recording is initiated. If `RecordMode` is `index`, a different record file is created each time recording is initiated, each with an indexed filename.

You can configure `RecordMode` only when the object is not recording. You terminate recording with the `record` function. A object that is not recording has a `RecordStatus` property value of `off`.

You specify the record filename with the `RecordName` property. The indexed filename follows a prescribed set of rules. For a description of these rules, see “Specifying a Filename” on page 15-61.

Characteristics

Read only	While recording
Data type	String

Values

<code>{overwrite}</code>	The record file is overwritten.
<code>append</code>	Data is appended to an existing record file.
<code>index</code>	A different record file is created, each with an indexed filename.

Example

Suppose you create the serial port object `s` associated with the serial port COM1.

```
s = serial('COM1');  
fopen(s)
```

Specify the record filename with the `RecordName` property, configure `RecordMode` to `index`, and initiate recording.

```
s.RecordName = 'MyRecord.txt';  
s.RecordMode = 'index';  
record(s)
```

The record filename is automatically updated with an indexed filename after recording is turned off.

```
record(s, 'off')  
s.RecordName  
ans =  
MyRecord01.txt
```

Disconnect `s` from the peripheral device, remove `s` from memory, and remove `s` from the MATLAB workspace.

```
fclose(s)  
delete(s)  
clear s
```

See Also

Functions

`record`

Properties

`RecordDetail`, `RecordName`, `RecordStatus`

RecordName

Name of the record file

Description

You configure `RecordName` to be the name of the record file. You can specify any value for `RecordName` - including a directory path - provided the file name is supported by your operating system.

MATLAB software supports any file name supported by your operating system. However, if you access the file with a MATLAB command, you might need to specify the file name using single quotes. For example, suppose you name the record file `My Record.txt`. To type this file at the MATLAB command line, you must include the name in quotes.

```
type('My Record.txt')
```

You can specify whether data and event information are saved to one disk file or to multiple disk files with the `RecordMode` property. If `RecordMode` is `index`, the filename follows a prescribed set of rules. For a description of these rules, see “Specifying a Filename” on page 15-61.

You can configure `RecordName` only when the object is not recording. You terminate recording with the `record` function. An object that is not recording has a `RecordStatus` property value of `off`.

Characteristics

Read only	While recording
Data type	String

Values

The default record filename is `record.txt`.

See Also

Functions

record

Properties

RecordDetail, RecordMode, RecordStatus

RecordStatus

Indicate if data and event information are saved to a record file

Description

You can configure `RecordStatus` to be `off` or `on` with the `record` function. If `RecordStatus` is `off`, then data and event information are not saved to a record file. If `RecordStatus` is `on`, then data and event information are saved to the record file specified by `RecordName`.

Use the `record` function to initiate or complete recording. `RecordStatus` is automatically configured to reflect the recording state.

For more information about recording to a disk file, see “Debugging: Recording Information to Disk” on page 15-60.

Characteristics

Read only	Always
Data type	String

Values

<code>{off}</code>	Data and event information are not written to a record file.
<code>on</code>	Data and event information are written to a record file.

See Also

Functions

`record`

Properties

RecordDetail, RecordMode, RecordName

RequestToSend

State of the RTS pin

Description

You can configure `RequestToSend` to be `on` or `off`. If `RequestToSend` is `on`, the Request to Send (RTS) pin is asserted. If `RequestToSend` is `off`, the RTS pin is unasserted.

In normal usage, the RTS and Clear to Send (CTS) pins work together, and are used as standard handshaking pins for data transfer. In this case, RTS and CTS are automatically managed by the DTE and DCE. However, there is nothing in the RS-232 standard that requires the RTS pin must be used in any specific way. Therefore, if you manually configure the `RequestToSend` value, it is probably for nonstandard operations.

If your device does not use hardware handshaking in the standard way, and you need to manually configure `RequestToSend`, configure the `FlowControl` property to `none`. Otherwise, the `RequestToSend` value that you specify might not be honored. Refer to your device documentation to determine its specific pin behavior.

You can return the value of the CTS pin with the `PinStatus` property. Handshaking is described in “Controlling the Flow of Data: Handshaking” on page 15-57.

Characteristics

Read only	Never
Data type	String

Values

<code>{on}</code>	The RTS pin is asserted.
<code>off</code>	The RTS pin is unasserted.

See Also

Properties

FlowControl, PinStatus

Status

Indicate if the serial port object is connected to the device

Description

Status can be `open` or `closed`. If Status is `closed`, the serial port object is not connected to the device. If Status is `open`, the serial port object is connected to the device.

Before you can write or read data, you must connect the serial port object to the device with the `fopen` function. Use the `fclose` function to disconnect a serial port object from the device.

Characteristics

Read only	Always
Data type	String

Values

<code>{closed}</code>	The serial port object is not connected to the device.
<code>open</code>	The serial port object is connected to the device.

See Also

Functions

`fclose`, `fopen`

StopBits

Number of bits used to indicate the end of a byte

Description

You can configure **StopBits** to be 1, 1.5, or 2. If **StopBits** is 1, one stop bit is used to indicate the end of data transmission. If **StopBits** is 2, two stop bits are used to indicate the end of data transmission. If **StopBits** is 1.5, the stop bit is transferred for 150% of the normal time used to transfer one bit.

Note: Both the computer and the peripheral device must be configured to transmit the same number of stop bits.

In addition to the stop bits, the serial data format consists of a start bit, between five and eight data bits, and possibly a parity bit. You specify the number of data bits with the **DataBits** property, and the type of parity checking with the **Parity** property.

Characteristics

Read only	Never
Data type	Double

Values

{1}	One stop bit is transmitted to indicate the end of a byte.
1.5	The stop bit is transferred for 150% of the normal time used to transfer one bit.
2	Two stop bits are transmitted to indicate the end of a byte.

See Also

Properties

DataBits, Parity

Tag

Label to associate with a serial port object

Description

You configure `Tag` to be a string value that uniquely identifies a serial port object.

`Tag` is particularly useful when constructing programs that would otherwise need to define the serial port object as a global variable, or pass the object as an argument between callback routines.

You can return the serial port object with the `instrfind` function by specifying the `Tag` property value.

Characteristics

Read only	Never
Data type	String

Values

The default value is an empty string.

Example

Suppose you create a serial port object associated with the serial port COM1.

```
s = serial('COM1');  
fopen(s)
```

You can assign `s` a unique label using `Tag`.

```
set(s, 'Tag', 'MySerialObj')
```

You can access `s` in the MATLAB workspace or in a file using the `instrfind` function and the `Tag` property value.

```
s1 = instrfind('Tag', 'MySerialObj');
```

See Also

Functions

`instrfind`

Terminator

Terminator character

Description

You can configure `Terminator` to an integer value ranging from 0 to 127, which represents the ASCII code for the character, or you can configure `Terminator` to the ASCII character. For example, to configure `Terminator` to a carriage return, specify the value to be `CR` or 13. To configure `Terminator` to a linefeed, specify the value to be `LF` or 10. You can also set `Terminator` to `CR/LF` or `LF/CR`. If `Terminator` is `CR/LF`, the terminator is a carriage return followed by a line feed. If `Terminator` is `LF/CR`, the terminator is a linefeed followed by a carriage return. Note that there are no integer equivalents for these two values. Additionally, you can set `Terminator` to a 1-by-2 cell array. The first element of the cell is the read terminator and the second element of the cell array is the write terminator.

When performing a write operation using the `fprintf` function, all occurrences of `\n` are replaced with the `Terminator` property value. Note that `%s\n` is the default format for `fprintf`. A read operation with `fgetl`, `fgets`, or `fscanf` completes when the `Terminator` value is read. The terminator is ignored for binary operations.

You can also use the terminator to generate a bytes-available event when the `BytesAvailableFcnMode` is set to `terminator`.

Characteristics

Read only	Never
Data type	String

Values

An integer value ranging from 0 to 127, or the equivalent ASCII character. `CR/LF` and `LF/CR` are also accepted values. You specify different read and write terminators as a 1-by-2 cell array.

See Also

Functions

fgetl, fgets, fprintf, fscanf

Properties

BytesAvailableFcnMode

Timeout

Waiting time to complete a read or write operation

Description

You configure `Timeout` to be the maximum time (in seconds) to wait to complete a read or write operation.

If a time-out occurs, the read or write operation aborts. Additionally, if a time-out occurs during an asynchronous read or write operation, then:

- An error event is generated.
- The callback function specified for `ErrorFcn` is executed.

Characteristics

Read only	Never
Data type	Double

Values

The default value is 10 seconds.

See Also

Properties

`ErrorFcn`

TimerFcn

Specify the callback function to execute when a predefined period of time passes.

Description

You configure `TimerFcn` to execute a callback function when a timer event occurs. A timer event occurs when the time specified by the `TimerPeriod` property passes. Time is measured relative to when the serial port object is connected to the device with `fopen`.

Note: A timer event can be generated at any time during the serial port session.

If the `RecordStatus` property value is `on`, and a timer event occurs, the record file records this information:

- The event type as `Timer`
- The time the event occurred using the format day-month-year hour:minute:second:millisecond

Some timer events might not be processed if your system is significantly slowed or if the `TimerPeriod` value is too small.

To learn how to create a callback function, see “Creating and Executing Callback Functions” on page 15-51.

Characteristics

Read only	Never
Data type	Callback function

Values

The default value is an empty string.

See Also

Functions

fopen, record

Properties

RecordStatus, TimerPeriod

TimerPeriod

Period of time between timer events

Description

TimerPeriod specifies the time, in seconds, that must pass before the callback function specified for `TimerFcn` is called. Time is measured relative to when the serial port object is connected to the device with `fopen`.

Some timer events might not be processed if your system is significantly slowed or if the TimerPeriod value is too small.

Characteristics

Read only	Never
Data type	Callback function

Values

The default value is 1 second. The minimum value is 0.01 second.

See Also

Functions

`fopen`

Properties

`TimerFcn`

TransferStatus

Indicate if an asynchronous read or write operation is in progress

Description

`TransferStatus` can be `idle`, `read`, `write`, or `read&write`. If `TransferStatus` is `idle`, no asynchronous read or write operations are in progress. If `TransferStatus` is `read`, an asynchronous read operation is in progress. If `TransferStatus` is `write`, an asynchronous write operation is in progress. If `TransferStatus` is `read&write`, both an asynchronous read and an asynchronous write operation are in progress.

You can write data asynchronously using the `fprintf` or `fwrite` functions. You can read data asynchronously using the `readasync` function, or by configuring the `ReadAsyncMode` property to `continuous`. While `readasync` is executing, `TransferStatus` might indicate that data is being read even though data is not filling the input buffer. If `ReadAsyncMode` is `continuous`, `TransferStatus` indicates that data is being read only when data is actually filling the input buffer.

You can execute an asynchronous read and an asynchronous write operation simultaneously because serial ports have separate read and write pins. For more information about synchronous and asynchronous read and write operations, see “Writing and Reading Data” on page 15-28.

Characteristics

Read only	Always
Data type	String

Values

<code>{idle}</code>	No asynchronous operations are in progress.
<code>read</code>	An asynchronous read operation is in progress.

write	An asynchronous write operation is in progress.
read&write	Asynchronous read and write operations are in progress.

See Also

Functions

fprintf, fwrite, readasync

Properties

ReadAsyncMode

Type

Object type

Description

Type indicates the type of the object. Type is automatically defined after the serial port object is created with the `serial` function. The Type value is always `serial`.

Characteristics

Read only	Always
Data type	String

Values

Type is always `serial`. This value is automatically defined when the serial port object is created.

Example

Suppose you create a serial port object associated with the serial port COM1.

```
s = serial('COM1');
```

The value of the Type property is `serial`, which is the object class.

```
s.Type  
ans =  
serial
```

You can also display the object class with the `whos` command.

```
Name      Size      Bytes  Class
```

s 1x1 644 serial object

Grand total is 18 elements using 644 bytes

See Also

Functions

serial

UserData

Data you want to associate with a serial port object

Description

You configure `UserData` to store data that you want to associate with a serial port object. The object does not use this data directly, but you can access it using the `get` function or the dot notation.

Characteristics

Read only	Never
Data type	Any type

Values

The default value is an empty vector.

Example

Suppose you create the serial port object associated with the serial port COM1.

```
s = serial('COM1');
```

You can associate data with `s` by storing it in `UserData`.

```
coeff.a = 1.0;  
coeff.b = -1.25;  
s.UserData = coeff;
```

ValuesReceived

Total number of values read from the device

Description

ValuesReceived indicates the total number of values read from the device. The value is updated after each successful read operation, and is set to 0 after the `fopen` function is issued. If the terminator is read from the device, then this value is reflected by ValuesReceived.

If you are reading data asynchronously, use the `BytesAvailable` property to return the number of bytes currently available in the input buffer.

When performing a read operation, the received data is represented by values rather than bytes. A value consists of one or more bytes. For example, one `uint32` value consists of four bytes. For more information about bytes and values, see “Bytes Versus Values” on page 15-10.

Characteristics

Read only	Always
Data type	Double

Values

The default value is 0.

Example

Suppose you create a serial port object associated with the serial port COM1.

```
s = serial('COM1');  
fopen(s)
```

If you write the `RS232?` command, and read back the response using `fscanf`, `ValuesReceived` is 17 because the instrument is configured to send the LF terminator.

```
fprintf(s, 'RS232?')
out = fscanf(s)
out =
9600;0;0;NONE;LF
s.ValuesReceived
ans =
    17
```

See Also

Functions

`fopen`

Properties

`BytesAvailable`

ValuesSent

Total number of values written to the device

Description

ValuesSent indicates the total number of values written to the device. The value is updated after each successful write operation, and is set to 0 after the `fopen` function is issued. If you are writing the terminator, ValuesSent reflects this value.

If you are writing data asynchronously, use the BytesToOutput property to return the number of bytes currently in the output buffer.

When performing a write operation, the transmitted data is represented by values rather than bytes. A value consists of one or more bytes. For example, one `uint32` value consists of four bytes. For more information about bytes and values, see “Bytes Versus Values” on page 15-10.

Characteristics

Read only	Always
Data type	Double

Values

The default value is 0.

Example

Suppose you create a serial port object associated with the serial port COM1.

```
s = serial('COM1');  
fopen(s)
```

If you write the `*IDN?` command using the `fprintf` function, `ValuesSent` is `6` because the default data format is `%s\n`, and the terminator was written.

```
fprintf(s, '*IDN?')
s.ValuesSent
ans =
     6
```

See Also

Functions

`fopen`

Properties

`BytesToOutput`

Hardware Support

- “Support Package Installation” on page 16-2
- “Support Package Installer Help” on page 16-5
- “MATLAB Supported Hardware” on page 16-19

Support Package Installation

In this section...

“What Is a Support Package?” on page 16-2

“Install Support Packages” on page 16-2

“Install Downloaded Support Package on Multiple Computers” on page 16-3

“Troubleshoot Timed Out Connections” on page 16-4

What Is a Support Package?

A *support package* is an add-on that enables you to use a MathWorks product with specific third-party hardware and software.

For example, support packages available for use with MATLAB include:

- Arduino® Hardware
- LEGO® MINDSTORMS® EV3 Hardware
- Raspberry Pi™ Hardware
- USB Webcam


For a complete list of available support packages, see Hardware Support.

Install Support Packages

You install support packages using *Support Package Installer*, a wizard that guides you through the installation process. You can also use Support Package Installer to update installed support package software or update the firmware on third-party hardware.

To start Support Package Installer:

- On the MATLAB **Home** tab, in the **Resources** section, click **Add-Ons > Get Hardware Support Packages**.



Install Downloaded Support Package on Multiple Computers

You can download a support package to one computer, and then install it on other computers. This allows you to:

- Install support packages on computers that are not connected to the Internet.
- Reduce the number of downloads you need to perform.

The computer you use for downloading must have the same base product license and platform as the computers upon which you are installing the support package. For example, suppose you want to install a Simulink support package on a group of computers that are running 64-bit Windows. To do so, you must first download the support package using a computer that has a Simulink license and is running 64-bit Windows.

To install a downloaded support package on multiple computers:

- 1 Download the support package, and place the folder in a shared network location.
- 2 Run Support Package Installer on the other computers.

- 3 On the **Install or update support package** screen, select the **Folder** option.
- 4 Follow the instructions provided by Support Package Installer to complete the installation process.

Note: Some support packages require you to install third-party software. If so, ensure that the third-party software is available for installation on each computer.

Troubleshoot Timed Out Connections

While you are installing a support package, Support Package Installer downloads software from the Internet. If downloading the software takes too long, Support Package Installer displays:

“Unable to download http:<url>. Connection timed out. Verify your network connection and proxy settings. If they are properly configured, retry the support package installation after 15 minutes. If the problem persists, contact MathWorks Technical Support.”

In some cases, antivirus software on the host computer causes this error by delaying or blocking the software download process. Consider pausing the antivirus software, or changing the antivirus software settings. Then, try installing the support package again.

See Also

supportPackageInstaller | targetupdater

External Web Sites

- [Hardware Support Catalog](#)

Support Package Installer Help

In this section...

“About Support Package Installer” on page 16-5

“Select an Action” on page 16-6

“Select Support Package to Install or Select Support Package to Download” on page 16-7

“Log In to MathWorks Account ” on page 16-10

“The MathWorks, Inc. Software License Agreement” on page 16-12

“Third-Party Software Licenses” on page 16-13

“Confirm Installation, Confirm Download, Confirm Uninstall” on page 16-14

“Install or Update Complete, Download Complete, Uninstall Complete” on page 16-15

“Set Up Support Package” on page 16-16

“Support Package Setup Complete” on page 16-18

“Special Instructions” on page 16-18


About Support Package Installer

Use Support Package Installer to add support for third-party products to your MathWorks software. When you complete the installation process, you can use the MathWorks software with those third-party products.

To start Support Package Installer, enter `supportPackageInstaller` in a MATLAB Command Window.

The following topics provide help for each screen in the Support Package Installer.

Select an Action




You can use **Select an action** to choose the action Support Package Installer performs:

- **Install from Internet:** Download a support package from the Internet and install it on the host computer.
- **Download from Internet:** Download a support package from the Internet without installing it.
- **Install from folder:** Install a previously downloaded support package.
- **Uninstall:** Uninstall a specific support package.

For instructions on using **Download from Internet** and **Install from Folder**, see “Install Downloaded Support Package on Multiple Computers” on page 16-3.

Select Support Package to Install or Select Support Package to Download



Support Package Installer installs those support package or packages that are currently visible in the right pane. In other words, it only installs support for one type of hardware at a time.

Use **Support for** to choose a specific group of support packages. Support Package Installer can only install or act upon one particular group of support packages at a time.

You can use **Show** to filter the support packages Support Package Installer displays:

- **All** displays support packages for all base products and host computer platforms.
- **Installable** displays support packages that you can install with the product licenses and platform on your host computer.
- **Installed** displays support packages that are installed on your host computer.
- **Updatable** displays installed support packages for which updates are available.

To install support packages in multiple groups, rerun Support Package Installer for each group.

Use **Support packages** to choose and review the status of specific support packages. Support Package Installer organizes the following support package information in columns:

- **Action** displays the action Support Package Installer can perform upon a support package. Select or clear the check box in to enable or disable Support Package Installer from performing that action: **Install, Reinstall, Update, None**.
- **Installed Version** displays the version of the installed support package. This entry is blank if the support package is not installed. If Latest Version and Installed Version are different, you can update the support package.
- **Latest Version** displays the version of the support package that is available for download. If Latest Version and Installed Version are different, you can update the support package. If your computer does not have access to the Internet, this value is empty.
- **Description** links to a web page where you can look or search for more information about the support package.
- **Required Base Product** displays the base product that is required in order to install the support package. If the base product is not licensed and installed, the support package is not downloadable or installable.
- **Supported Host Platforms** displays the host computer platforms required to install the support package. If the host computer is not one of the supported platforms, you cannot download or install the support package. **Win32** and **Win64** represent the 32- and 64-bit versions of Microsoft Windows. **Linux64** represents the 64-bit version of Linux. **Mac64** represents the 64-bit version of the Apple Mac platform.

The **Installation folder** parameter displays the path where Support Package Installer installs the support package. You must have write privileges for this folder. You can


enter a new path directly, or use the **Browse** button to select one. The installation process creates a `downloads` folder in this location.

If you choose the **Download from Internet** option, Support Package Installer displays the **Download folder** parameter instead of the **Installation folder** parameter. **Download folder** displays the path where Support Package Installer creates support package folders. You must have write privileges for this path. You can enter a new path directly, or use the **Browse** button to select one. By default, the **Download folder** is named `downloads`. After installing support packages, the **Download folder** contains subfolders for each support package.

The **Find more supported hardware** link opens a browser and displays the Hardware Support topic on the MathWorks website.


Note: Opening a support package installation file opens the **Select a Support Package to Install or Download** screen with a support package preselected. These files are available from MATLAB Central File Exchange, and have the file name extension:
`*.mlpkginstall`

Log In to MathWorks Account



Click **Log In**. In the **MathWorks Account Log In** dialog box, enter your MathWorks.com account email address and password. For more information, see <http://www.mathworks.com/support/solutions/en/data/1-172ME/index.html?solution=1-172ME>.

If you do not have an account, click [here](#) to create one.



MathWorks Account Log In

Don't have an account? [Create an account](#)


Email address:

Password:

Keep me logged on


[Forgot your password?](#)

The MathWorks, Inc. Software License Agreement



Review the text of the license agreement. If you agree, select the **I accept** check box, and then click **Next**.


Third-Party Software Licenses



Support packages that download third-party software as part of the installation process display this screen. Review the information and any license agreements.

To proceed, click **Install**. Otherwise, click **Back** or **Cancel**.

Confirm Installation, Confirm Download, Confirm Uninstall




This screen confirms the name of the support package you have chosen. To continue, click **Install**, **Download**, or **Uninstall**.

Support Package Installer displays a progress bar while it performs the specified action.

Note: If Support Package Installer instructs you to delete files, close the MATLAB software before removing the files. Then, restart MATLAB software and run Support Package Installer to complete the process.

Install or Update Complete, Download Complete, Uninstall Complete



Support Package Installer has finished installing or uninstalling the support package.

Some support packages require additional actions before you can use the support package:


- Replace or update the firmware on the target hardware.
- Install and validate required third-party software.

To perform these actions, click **Continue**. Otherwise, click **Finish**.

This screen displays the path of the support package folder within the **Download folder**. If you use the **Install from Folder** option in the future, you will specify the location of this support package folder.

If there are no additional actions, and the support package contains featured examples, Support Package Installer gives you the option to open the featured examples. These examples show you how to use the capabilities provided by the support package.

Set Up Support Package




This screen is only shown for support packages that provide additional post-installation steps. Use the **Support package for** parameter to identify the third-party hardware or software to set up. Then, click **Next**.

The subsequent screens guide you through the process of:

- Replacing or updating the firmware on the target hardware.
- Installing and validating required third-party software.

Note: To return to this screen without repeating preceding screens, enter `targetupdater` in a MATLAB Command Window.

Support Package Setup Complete



You have completed the set up process.

If you leave the **Show support package examples** check box selected and click **Finish**, Support Package Installer displays support package examples in a new window.

Special Instructions

This screen is unique to the support package you are installing. Carefully read and follow the instructions provided by the screen.

MATLAB Supported Hardware

For a complete list of support packages, see the Hardware Support Catalog.

In addition to these packages, MATLAB includes built-in support for:

- “Audio Recording and Playback”
- “Serial Port Devices”

