d01 - Quadrature d01sjc

NAG C Library Function Document

nag 1d quad gen 1 (d01sjc)

1 Purpose

nag_1d_quad_gen_1 (d01sjc) is a general purpose integrator which calculates an approximation to the integral of a function f(x) over a finite interval [a,b]:

$$I = \int_a^b f(x) \ dx.$$

2 Specification

3 Description

This function is based upon the QUADPACK routine QAGS (Piessens *et al.* (1983)). It is an adaptive function, using the Gauss 10-point and Kronrod 21-point rules. The algorithm, described by De Doncker (1978), incorporates a global acceptance criterion (as defined by Malcolm and Simpson (1976)) together with the ϵ -algorithm (Wynn (1956)) to perform extrapolation. The local error estimation is described by Piessens *et al.* (1983).

This function is suitable as a general purpose integrator, and can be used when the integrand has singularities, especially when these are of algebraic or logarithmic type.

This function requires the user to supply a function to evaluate the integrand at a single point.

4 Parameters

1: \mathbf{f} – function supplied by user

Function

The function \mathbf{f} , supplied by the user, must return the value of the integrand f at a given point. The specification of \mathbf{f} is:

double f(double x, Nag_User *comm)

1: \mathbf{x} – double Input

On entry: the point at which the integrand f must be evaluated.

2: **comm** – Nag User *

On entry/on exit: pointer to a structure of type Nag_User with the following member:

p – Pointer Input/Output

On entry/on exit: the pointer $comm \rightarrow p$ should be cast to the required type, e.g., struct user *s = (struct user *)comm->p, to obtain the original object's address with appropriate type. (See the argument **comm** below.)

[NP3491/6] d01sjc.1

a - double Input

On entry: the lower limit of integration, a.

3: \mathbf{b} - double Input

On entry: the upper limit of integration, b. It is not necessary that a < b.

4: **epsabs** – double *Input*

On entry: the absolute accuracy required. If **epsabs** is negative, the absolute value is used. See Section 6.1.

5: **epsrel** – double *Input*

On entry: the relative accuracy required. If **epsrel** is negative, the absolute value is used. See Section 6.1.

6: **max_num_subint** – Integer

Input

On entry: the upper bound on the number of sub-intervals into which the interval of integration may be divided by the function. The more difficult the integrand, the larger **max_num_subint** should be.

Suggested values: a value in the range 200 to 500 is adequate for most problems.

Constraint: $max_num_subint \ge 1$.

7: **result** – double * Output

On exit: the approximation to the integral I.

8: **abserr** – double * Output

On exit: an estimate of the modulus of the absolute error, which should be an upper bound for |I-result|.

9: **qp** – Nag_QuadProgress *

Pointer to structure of type Nag QuadProgress with the following members:

num_subint - Integer

Output

On exit: the actual number of sub-intervals used.

fun count – Integer Output

On exit: the number of function evaluations performed by nag_1d_quad_gen_1.

```
sub_int_be_pts_pts - double *Outputsub_int_end_pts - double *Outputsub_int_result - double *Outputsub_int_error - double *Output
```

On exit: these pointers are allocated memory internally with max_num_subint elements. If an error exit other than NE_INT_ARG_LT or NE_ALLOC_FAIL occurs, these arrays will contain information which may be useful. For details, see Section 6.

Before a subsequent call to nag_1d_quad_gen_1 is made, or when the information contained in these arrays is no longer useful, the user should free the storage allocated by these pointers using the NAG macro **NAG FREE**.

d01sjc.2 [NP3491/6]

d01 - Quadrature d01sjc

10: **comm** – Nag User *

On entry/on exit: pointer to a structure of type Nag User with the following member:

p – Pointer Input/Output

On entry/on exit: the pointer p, of type Pointer, allows the user to communicate information to and from the user-defined function f(). An object of the required type should be declared by the user, e.g., a structure, and its address assigned to the pointer p by means of a cast to Pointer in the calling program, e.g., comm.p = (Pointer)&s. The type Pointer is void *.

11: **fail** – NagError *

Input/Output

The NAG error parameter (see the Essential Introduction).

Users are recommended to declare and initialise fail and set fail.print = TRUE for this function.

5 Error Indicators and Warnings

NE INT ARG LT

On entry, max num subint must not be less than 1: max num subint = <value>.

NE ALLOC FAIL

Memory allocation failed.

NE_QUAD_MAX_SUBDIV

The maximum number of subdivisions has been reached: **max num subint** = $\langle value \rangle$.

The maximum number of subdivisions has been reached without the accuracy requirements being achieved. Look at the integrand in order to determine the integration difficulties. If the position of a local difficulty within the interval can be determined (e.g., a singularity of the integrand or its derivative, a peak, a discontinuity, etc.) you will probably gain from splitting up the interval at this point and calling the integrator on the sub-intervals. If necessary, another integrator, which is designed for handling the type of difficulty involved, must be used. Alternatively, consider relaxing the accuracy requirements specified by **epsabs** and **epsrel**, or increasing the value of **max num subint**.

NE QUAD ROUNDOFF TOL

Round-off error prevents the requested tolerance from being achieved: **epsabs** = <*value*>, **epsrel** = <*value*>.

The error may be underestimated. Consider relaxing the accuracy requirements specified by **epsabs** and **epsrel**.

NE_QUAD_BAD_SUBDIV

Extremely bad integrand behaviour occurs around the sub-interval (<value>, <value>).

The same advice applies as in the case of NE QUAD MAX SUBDIV.

NE QUAD ROUNDOFF EXTRAPL

Round-off error is detected during extrapolation.

The requested tolerance cannot be achieved, because the extrapolation does not increase the accuracy satisfactorily; the returned result is the best that can be obtained.

The same advice applies as in the case of NE_QUAD_MAX_SUBDIV.

NE QUAD NO CONV

The integral is probably divergent or slowly convergent.

Please note that divergence can occur with any error exit other than NE_INT_ARG_LT and NE_ALLOC_FAIL.

[NP3491/6] d01sjc.3

6 Further Comments

The time taken by nag 1d quad gen 1 depends on the integrand and the accuracy required.

If the function fails with an error exit other than **NE_INT_ARG_LT** or **NE_ALLOC_FAIL**, then the user may wish to examine the contents of the structure **qp**. These contain the end-points of the sub-intervals used by nag_ld_quad_gen_1 along with the integral contributions and error estimates over the sub-intervals.

Specifically, for i = 1, 2, ..., n, let r_i denote the approximation to the value of the integral over the sub-interval $[a_i, b_i]$ in the partition of [a, b] and e_i be the corresponding absolute error estimate.

Then, $\int_{a_i}^{b_i} f(x) dx \simeq r_i$ and **result** = $\sum_{i=1}^n r_i$ unless the function terminates while testing for divergence of the integral (see Section 3.4.3 of Piessens *et al.* (1983)). In this case, **result** (and **abserr**) are taken to be the values returned from the extrapolation process. The value of n is returned in **num_subint**, and the values a_i , b_i , r_i and e_i are stored in the structure **qp** as

```
a_i = \mathbf{sub\_int\_beg\_pts}[i-1],

b_i = \mathbf{sub\_int\_end\_pts}[i-1],

r_i = \mathbf{sub\_int\_result}[i-1] and e_i = \mathbf{sub\_int\_error}[i-1].
```

6.1 Accuracy

The function cannot guarantee, but in practice usually achieves, the following accuracy:

$$|I - \mathbf{result}| \le tol$$

where

$$tol = \max\{|\mathbf{epsabs}|, |\mathbf{epsrel}| \times |I|\}$$

and **epsabs** and **epsrel** are user-specified absolute and relative error tolerances. Moreover it returns the quantity **abserr** which, in normal circumstances, satisfies

$$|I - \mathbf{result}| \le \mathbf{abserr} \le tol.$$

6.2 References

De Doncker E (1978) An adaptive extrapolation algorithm for automatic integration *ACM SIGNUM Newsl.* **13 (2)** 12–18

Malcolm M A and Simpson R B (1976) Local versus global strategies for adaptive quadrature *ACM Trans. Math. Software* **1** 129–146

Piessens R, De Doncker-Kapenga E, Überhuber C and Kahaner D (1983) *QUADPACK, A Subroutine Package for Automatic Integration* Springer-Verlag

Wynn P (1956) On a device for computing the $e_m(S_n)$ transformation Math. Tables Aids Comput. 10 91–96

7 See Also

8 Example

To compute

$$\int_0^{2\pi} \frac{x \sin(30x)}{\sqrt{\left(1 - \left(\frac{x}{2\pi}\right)^2\right)}} \ dx.$$

d01sjc.4 [NP3491/6]

d01 - Quadrature d01sjc

8.1 Program Text

```
/* nag_1d_quad_gen_1(d01sjc) Example Program
 * Copyright 1998 Numerical Algorithms Group.
 * Mark 5, 1998.
 * Mark 6 revised, 2000.
#include <nag.h>
#include <stdio.h>
#include <nag_stdlib.h>
#include <math.h>
#include <nagd01.h>
#include <nagx01.h>
static double f(double x, Nag_User *comm);
main()
  double a, b;
  double epsabs, abserr, epsrel, result;
  Nag_QuadProgress qp;
  Integer max_num_subint;
  static NagError fail;
  double pi = X01AAC;
  Nag_User comm;
  Vprintf("d01sjc Example Program Results\n");
  epsabs = 0.0;
  epsrel = 0.0001;
  a = 0.0;
  b = pi*2.0;
  max_num_subint = 200;
  d01sjc(f, a, b, epsabs, epsrel, max_num_subint, &result, &abserr,
         &qp, &comm, &fail);
                - lower limit of integration = %10.4f\n", a);
  Vprintf("a
                  - upper limit of integration = %10.4f\n", b);
  Vprintf("b
  Vprintf("epsabs - absolute accuracy requested = %9.2e\n", epsabs);
  Vprintf("epsrel - relative accuracy requested = %9.2e\n\n", epsrel);
  if (fail.code != NE_NOERROR)
    Vprintf("%s\n", fail.message);
  if (fail.code != NE_INT_ARG_LT && fail.code != NE_ALLOC_FAIL)
      \label{eq:printf} Vprintf("result - approximation to the integral = \$9.5f\n", result);
      Vprintf("abserr - estimate of the absolute error = \$9.2e\n", abserr);
      Vprintf("qp.fun_count - number of function evaluations = %4ld\n",
              qp.fun_count);
      Vprintf("qp.num_subint - number of subintervals used = %4ld\n",
              qp.num_subint);
      /* Free memory used by qp */
      NAG_FREE(qp.sub_int_beg_pts);
      NAG_FREE(qp.sub_int_end_pts);
      NAG_FREE(qp.sub_int_result);
      NAG_FREE(qp.sub_int_error);
      exit(EXIT_SUCCESS);
    }
```

[NP3491/6] d01sjc.5

```
else
    exit(EXIT_FAILURE);
}

static double f(double x, Nag_User *comm)
{
    double pi = X01AAC;
    return (x*sin(x*30.0)/sqrt(1.0-x*x/(pi*pi*4.0)));
}
```

8.2 Program Data

None.

8.3 Program Results

```
d01sjc Example Program Results

a - lower limit of integration = 0.0000

b - upper limit of integration = 6.2832

epsabs - absolute accuracy requested = 0.00e+00

epsrel - relative accuracy requested = 1.00e-04

result - approximation to the integral = -2.54326

abserr - estimate of the absolute error = 1.28e-05

qp.fun_count - number of function evaluations = 777

qp.num_subint - number of subintervals used = 19
```

d01sjc.6 (last) [NP3491/6]