

G05DPF – NAG Fortran Library Routine Document

Note. Before using this routine, please read the Users' Note for your implementation to check the interpretation of bold italicised terms and other implementation-dependent details.

1 Purpose

G05DPF returns a pseudo-random real number taken from a two parameter Weibull distribution with shape parameter a and scale parameter b .

2 Specification

```
real FUNCTION G05DPF(A, B, IFAIL)
INTEGER           IFAIL
real             A, B
```

3 Description

The distribution has PDF (probability density function)

$$\begin{aligned} f(x) &= \frac{a}{b}x^{a-1}e^{-x^a/b} && \text{if } x > 0, \\ f(x) &= 0 && \text{otherwise.} \end{aligned}$$

The routine returns the value $(-b \ln y)^{1/a}$, where y is a pseudo-random number from a uniform distribution over $(0,1)$, generated by G05CAF.

4 References

- [1] Knuth D E (1981) *The Art of Computer Programming (Volume 2)* Addison–Wesley (2nd Edition)
- [2] Kendall M G and Stuart A (1969) *The Advanced Theory of Statistics (Volume 1)* Griffin (3rd Edition)

5 Parameters

- | | |
|---|---------------------|
| 1: A — <i>real</i> | <i>Input</i> |
| <i>On entry:</i> the shape parameter, a , of the distribution. | |
| <i>Constraint:</i> $A > 0.0$. | |
| 2: B — <i>real</i> | <i>Input</i> |
| <i>On entry:</i> the scale parameter, b , of the distribution. | |
| <i>Constraint:</i> $B > 0.0$. | |
| 3: IFAIL — INTEGER | <i>Input/Output</i> |
| <i>On entry:</i> IFAIL must be set to 0, -1 or 1. For users not familiar with this parameter (described in Chapter P01) the recommended value is 0. | |
| <i>On exit:</i> IFAIL = 0 unless the routine detects an error (see Section 6). | |

6 Error Indicators and Warnings

Errors detected by the routine:

IFAIL = 1

On entry, $A \leq 0.0$.

IFAIL = 2

On entry, $B \leq 0.0$.

7 Accuracy

Not applicable.

8 Further Comments

None.

9 Example

The example program prints out the first five pseudo-random real numbers from a Weibull distribution with shape parameter 1.0 and scale parameter 2.0, generated by G05DPF after initialisation by G05CBF.

The generator mechanism used is selected by an initial call to G05ZAF.

9.1 Program Text

Note. The listing of the example program presented below uses bold italicised terms to denote precision-dependent details. Please read the Users' Note for your implementation to check the interpretation of these terms. As explained in the Essential Introduction to this manual, the results produced may not be identical for all implementations.

```

*      G05DPF Example Program Text
*      NAG Fortran SMP Library, Release 2.  NAG Copyright 2000.
*      .. Parameters ..
    INTEGER          NOUT
    PARAMETER        (NOUT=6)
*      .. Local Scalars ..
    DOUBLE PRECISION X
    INTEGER          I, IFAIL
*      .. External Functions ..
    DOUBLE PRECISION G05DPF
    EXTERNAL         G05DPF
*      .. External Subroutines ..
    EXTERNAL         G05CBF, G05ZAF
*      .. Executable Statements ..
    CALL G05ZAF('0')
    WRITE (NOUT,*) 'G05DPF Example Program Results'
    WRITE (NOUT,*)
    CALL G05CBF(0)
    IFAIL = 0
    DO 20 I = 1, 5
*
        X = G05DPF(1.0D0,2.0D0,IFAIL)
*
        WRITE (NOUT,99999) X
20 CONTINUE
STOP

```

```
*  
99999 FORMAT (1X,F10.4)  
END
```

9.2 Program Data

None.

9.3 Program Results

G05DPF Example Program Results

```
0.4585  
2.9769  
1.9816  
2.9830  
0.2585
```
