D01 – Quadrature D01ALF

NAG Fortran Library Routine Document D01ALF

Note: before using this routine, please read the Users' Note for your implementation to check the interpretation of **bold italicised** terms and other implementation-dependent details.

1 Purpose

D01ALF is a general purpose integrator which calculates an approximation to the integral of a function f(x) over a finite interval [a, b]:

$$I = \int_{a}^{b} f(x) \, dx$$

where the integrand may have local singular behaviour at a finite number of points within the integration interval.

2 Specification

```
SUBROUTINE DO1ALF(F, A, B, NPTS, POINTS, EPSABS, EPSREL, RESULT, ABSERR,

W, LW, IW, LIW, IFAIL)

INTEGER

NPTS, LW, IW(LIW), LIW, IFAIL

real

F, A, B, POINTS(NPTS), EPSABS, EPSREL, RESULT, ABSERR,

W(LW)

EXTERNAL

F
```

3 Description

D01ALF is based upon the QUADPACK routine QAGP (Piessens *et al.* (1983)). It is very similar to D01AJF, but allows the user to supply 'break-points', points at which the function is known to be difficult. It is an adaptive routine, using the Gauss 10-point and Kronrod 21-point rules. The algorithm described by de Doncker (1978) incorporates a global acceptance criterion (as defined by Malcolm and Simpson (1976)) together with the ϵ -algorithm (Wynn (1956)) to perform extrapolation. The user-supplied 'break-points' always occur as the end-points of some sub-interval during the adaptive process. The local error estimation is described by Piessens *et al.* (1983).

4 References

de Doncker E (1978) An adaptive extrapolation algorithm for automatic integration *ACM SIGNUM Newsl.* **13 (2)** 12–18

Malcolm M A and Simpson R B (1976) Local versus global strategies for adaptive quadrature *ACM Trans. Math. Software* **1** 129–146

Piessens R, de Doncker-Kapenga E, Überhuber C and Kahaner D (1983) *QUADPACK, A Subroutine Package for Automatic Integration* Springer-Verlag

Wynn P (1956) On a device for computing the $e_m(S_n)$ transformation Math. Tables Aids Comput. 10 91–96

5 Parameters

1: F - real FUNCTION, supplied by the user.

External Procedure

F must return the value of the integrand f at a given point.

[NP3546/20A] D01ALF.1

Its specification is:

1: X - real Input

On entry: the point at which the integrand f must be evaluated.

F must be declared as EXTERNAL in the (sub)program from which D01ALF is called. Parameters denoted as *Input* must **not** be changed by this procedure.

2: A – **real** Input

On entry: the lower limit of integration, a.

3: B - real Input

On entry: the upper limit of integration, b. It is not necessary that a < b.

4: NPTS – INTEGER Input

On entry: the number of user-supplied break-points within the integration interval.

Constraint: NPTS ≥ 0 .

5: POINTS(NPTS) – *real* array

Input

On entry: the user-specified break-points.

Constraint: the break-points must all lie within the interval of integration (but may be supplied in any order).

6: EPSABS – real Input

On entry: the absolute accuracy required. If EPSABS is negative, the absolute value is used. See Section 7.

7: EPSREL – *real* Input

On entry: the relative accuracy required. If EPSREL is negative, the absolute value is used. See Section 7.

8: RESULT – real Output

On exit: the approximation to the integral I.

9: ABSERR – real Output

On exit: an estimate of the modulus of the absolute error, which should be an upper bound for |I - RESULT|.

10: W(LW) - real array Output

On exit: details of the computation, as described in Section 8.

11: LW – INTEGER Input

On entry: the dimension of the array W as declared in the (sub)program from which D01ALF is called. The value of LW (together with that of LIW below) imposes a bound on the number of sub-intervals into which the interval of integration may be divided by the routine. The number of sub-intervals cannot exceed $(LW - 2 \times NPTS - 4)/4$. The more difficult the integrand, the larger LW should be.

Suggested value: a value in the range 800 to 2000 is adequate for most problems.

D01ALF.2 [NP3546/20A]

D01 – Quadrature D01ALF

Constraint: LW $> 2 \times NPTS + 8$.

12: IW(LIW) – INTEGER array

Output

On exit: IW(1) contains the actual number of sub-intervals used. The rest of the array is used as workspace.

13: LIW – INTEGER Input

On entry: the dimension of the array IW as declared in the (sub)program from which D01ALF is called. The number of sub-intervals into which the interval of integration may be divided cannot exceed (LIW - NPTS - 2)/2.

Suggested value: LIW = LW/2.

Constraint: LIW \geq NPTS + 4.

14: IFAIL – INTEGER

Input/Output

On entry: IFAIL must be set to 0, -1 or 1. Users who are unfamiliar with this parameter should refer to Chapter P01 for details.

On exit: IFAIL = 0 unless the routine detects an error (see Section 6).

For environments where it might be inappropriate to halt program execution when an error is detected, the value -1 or 1 is recommended. If the output of error messages is undesirable, then the value 1 is recommended. Otherwise, because for this routine the values of the output parameters may be useful even if IFAIL $\neq 0$ on exit, the recommended value is -1. When the value -1 or 1 is used it is essential to test the value of IFAIL on exit.

6 Error Indicators and Warnings

If on entry IFAIL = 0 or -1, explanatory error messages are output on the current error message unit (as defined by X04AAF).

Errors or warnings detected by the routine:

IFAIL = 1

The maximum number of subdivisions allowed with the given workspace has been reached, without the accuracy requirements being achieved. Look at the integrand in order to determine the integration difficulties. If the position of a local difficulty within the interval can be determined (e.g., a singularity of the integrand or its derivative, a peak, a discontinuity, etc.) it should be supplied to the routine as an element of the vector POINTS. If necessary, another integrator should be used, which is designed for handling the type of difficulty involved. Alternatively, consider relaxing the accuracy requirements specified by EPSABS and EPSREL, or increasing the amount of workspace.

IFAIL = 2

Round-off error prevents the requested tolerance from being achieved. The error may be underestimated. Consider requesting less accuracy.

IFAIL = 3

Extremely bad local integrand behaviour causes a very strong subdivision around one (or more) points of the interval. The same advice applies as in the case of IFAIL = 1.

IFAIL = 4

The requested tolerance cannot be achieved, because the extrapolation does not increase the accuracy satisfactorily; the result returned is the best which can be obtained. The same advice applies as in the case IFAIL = 1.

[NP3546/20A] D01ALF.3

IFAIL = 5

The integral is probably divergent, or slowly convergent. Please note that divergence can also occur with any other non-zero value of IFAIL.

IFAIL = 6

The input is invalid: break-points are specified outside the integration range, NPTS > LIMIT or NPTS < 0. RESULT and ABSERR are set to zero.

IFAIL = 7

On entry,
$$LW < 2 \times NPTS + 8$$
, or $LIW < NPTS + 4$.

7 Accuracy

The routine cannot guarantee, but in practice usually achieves, the following accuracy:

$$|I - RESULT| \le tol$$
,

where

$$tol = \max\{|\text{EPSABS}|, |\text{EPSREL}| \times |I|\},$$

and EPSABS and EPSREL are user-specified absolute and relative error tolerances. Moreover, it returns the quantity ABSERR which, in normal circumstances, satisfies

$$|I - \text{RESULT}| \le \text{ABSERR} \le tol.$$

8 Further Comments

The time taken by the routine depends on the integrand and on the accuracy required.

If IFAIL $\neq 0$ on exit, then the user may wish to examine the contents of the array W, which contains the end-points of the sub-intervals used by D01ALF along with the integral contributions and error estimates over these sub-intervals.

Specifically, for i = 1, 2, ..., n, let r_i denote the approximation to the value of the integral over the sub-interval $[a_i, b_i]$ in the partition of [a, b] and e_i be the corresponding absolute error estimate. Then,

$$\int_{a_i}^{b_i} f(x) \, dx \simeq r_i \text{ and RESULT} = \sum_{i=1}^n r_i \text{ unless D01ALF terminates while testing for divergence of the}$$

integral (see Section 3.4.3 of Piessens *et al.* (1983)). In this case, RESULT (and ABSERR) are taken to be the values returned from the extrapolation process. The value of n is returned in IW(1), and the values a_i , b_i , e_i and r_i are stored consecutively in the array W, that is:

$$egin{aligned} a_i &= \mathsf{W}(i), \ b_i &= \mathsf{W}(n+i), \ e_i &= \mathsf{W}(2n+i) \ ext{and} \ r_i &= \mathsf{W}(3n+i). \end{aligned}$$

9 Example

To compute

$$\int_0^1 \frac{1}{\sqrt{|x-1/7|}} \, dx.$$

A break-point is specified at x = 1/7, at which point the integrand is infinite. (For definiteness the function FST returns the value 0.0 at this point.)

D01ALF.4 [NP3546/20A]

D01 – Quadrature D01ALF

9.1 Program Text

Note: the listing of the example program presented below uses **bold italicised** terms to denote precision-dependent details. Please read the Users' Note for your implementation to check the interpretation of these terms. As explained in the Essential Introduction to this manual, the results produced may not be identical for all implementations.

```
D01ALF Example Program Text
     Mark 14 Revised. NAG Copyright 1989.
      .. Parameters ..
                       NPTS, LW, LIW
      INTEGER
     PARAMETER
                       (NPTS=1,LW=800,LIW=LW/2)
      INTEGER
                       NOUT
     PARAMETER
                       (NOUT=6)
      .. Scalars in Common ..
      INTEGER
                      KOUNT
      .. Local Scalars ..
                      A, ABSERR, B, EPSABS, EPSREL, RESULT
      real
      INTEGER
                       IFAIL
      .. Local Arrays ..
                      POINTS(NPTS), W(LW)
      INTEGER
                       IW(LIW)
      .. External Functions ..
     real
                       FST
      EXTERNAL
                      FST
      .. External Subroutines ..
     EXTERNAL
                      D01ALF
      .. Common blocks ..
                       /TELNUM/KOUNT
      COMMON
      .. Executable Statements ..
      WRITE (NOUT,*) 'D01ALF Example Program Results'
     EPSABS = 0.0e0
     EPSREL = 1.0e-03
     A = 0.0e0
     B = 1.0e0
     POINTS(1) = 1.0e0/7.0e0
      KOUNT = 0
      IFAIL = -1
     CALL DO1ALF(FST,A,B,NPTS,POINTS,EPSABS,EPSREL,RESULT,ABSERR,W,LW,
                  IW,LIW,IFAIL)
     WRITE (NOUT, *)
     WRITE (NOUT,99999) 'A
                                 - lower limit of integration = ', A
      WRITE (NOUT, 99999) 'B
                                 - upper limit of integration = '
     WRITE (NOUT, 99998) 'EPSABS - absolute accuracy requested = ',
     + EPSABS
     WRITE (NOUT, 99998) 'EPSREL - relative accuracy requested = ',
     + EPSREL
     WRITE (NOUT, 99999) 'POINTS(1) - given break-point = ', POINTS(1)
     WRITE (NOUT, *)
     IF (IFAIL.NE.O) WRITE (NOUT, 99996) 'IFAIL = ', IFAIL
      IF (IFAIL.LE.5) THEN
         WRITE (NOUT, 99997)
          ' RESULT - approximation to the integral = ', RESULT
         WRITE (NOUT, 99998)
           ' ABSERR - estimate of the absolute error = ', ABSERR
         WRITE (NOUT, 99996)
          ' KOUNT - number of function evaluations = ', KOUNT
         WRITE (NOUT, 99996) 'IW(1) - number of subintervals used = ',
          IW(1)
     END IF
     STOP
99999 FORMAT (1X,A,F10.4)
99998 FORMAT (1X,A,e9.2)
99997 FORMAT (1X,A,F9.5)
99996 FORMAT (1X,A,I4)
     END
     real FUNCTION FST(X)
      .. Scalar Arguments ..
```

[NP3546/20A] D01ALF.5

9.2 Program Data

None.

9.3 Program Results

```
DO1ALF Example Program Results

A - lower limit of integration = 0.0000
B - upper limit of integration = 1.0000
EPSABS - absolute accuracy requested = 0.00E+00
EPSREL - relative accuracy requested = 0.10E-02
POINTS(1) - given break-point = 0.1429

RESULT - approximation to the integral = 2.60757
ABSERR - estimate of the absolute error = 0.60E-13
KOUNT - number of function evaluations = 462
IW(1) - number of subintervals used = 12
```

D01ALF.6 (last) [NP3546/20A]