# NAG Fortran Library Routine Document G05MKF

Note: before using this routine, please read the Users' Note for your implementation to check the interpretation of **bold italicised** terms and other implementation-dependent details.

## 1 Purpose

G05MKF generates a vector of pseudo-random integers from the discrete Poisson distribution with mean  $\lambda$ 

# 2 Specification

SUBROUTINE GO5MKF(MODE, LAMBDA, N, X, IGEN, ISEED, R, NR, IFAIL)

INTEGER MODE, N, X(N), IGEN, ISEED(4), NR, IFAIL

real LAMBDA, R(NR)

## 3 Description

G05MKF generates n integers  $x_i$  from a discrete Poisson distribution with mean  $\lambda$ , where the probability of  $x_i = I$  is

$$P(x_i = I) = \frac{\lambda^I \times e^{-\lambda}}{I!}, \quad I = 0, 1, \dots,$$

where  $0 \le \lambda$ .

The variates can be generated with or without using a search table and index. If a search table is used then it is stored with the index in a reference vector and subsequent calls to G05MKF with the same parameter values can then use this reference vector to generate further variates. The reference array is found using a recurrence relation if  $\lambda$  is less than 50 and by Stirling's formula otherwise.

One of the initialisation routines G05KBF (for a repeatable sequence if computed sequentially) or G05KCF (for a non-repeatable sequence) must be called prior to the first call to G05MKF.

## 4 References

Knuth D E (1981) *The Art of Computer Programming (Volume 2)* (2nd Edition) Addison-Wesley Kendall M G and Stuart A (1969) *The Advanced Theory of Statistics (Volume 1)* (3rd Edition) Griffin

# 5 Parameters

1: MODE – INTEGER Input

On entry: a code for selecting the operation to be performed by the routine:

MODE = 0

Set up reference vector only.

MODE = 1

Generate variates using reference vector set up in a prior call to G05MKF.

MODE = 2

Set up reference vector and generate variates.

MODE = 3

Generate variates without using the reference vector.

[NP3546/20A] G05MKF.1

*Constraint*:  $0 \le MODE \le 3$ .

#### 2: LAMBDA – real

Input

On entry: the mean  $\lambda$  of the Poisson distribution.

Constraint: LAMBDA > 0.0.

3: N - INTEGER

Input

On entry: the number, n, of pseudo-random numbers to be generated.

Constraint: N > 1.

4: X(N) - INTEGER array

Output

On exit: the n pseudo-random numbers from the specified Poisson distribution.

5: IGEN – INTEGER

Input

On entry: must contain the identification number for the generator to be used to return a pseudorandom number and should remain unchanged following initialisation by a prior call to one of the routines G05KBF or G05KCF.

6: ISEED(4) – INTEGER array

Input/Output

On entry: contains values which define the current state of the selected generator.

On exit: contains updated values defining the new state of the selected generator.

7: R(NR) - real array

Input/Output

On exit: the reference vector.

8: NR – INTEGER

Input

On entry: the dimension of the array R as declared in the (sub)program from which G05MKF is called.

Suggested value:  $22 + 20 \times \sqrt{LAMBDA}$ .

Constraints:

if MODE = 0 or 2, then

$$NR > (INT[LAMBDA + 7.15\sqrt{LAMBDA} + 8.5]$$

$$-\max(0, INT[LAMBDA - 7.15\sqrt{LAMBDA}]) + 6);$$

if MODE = 1, then NR should remain unchanged from the previous call to G05MKF;

if MODE = 3, then R is not referenced.

### 9: IFAIL – INTEGER

Input/Output

On entry: IFAIL must be set to 0, -1 or 1. Users who are unfamiliar with this parameter should refer to Chapter P01 for details.

On exit: IFAIL = 0 unless the routine detects an error (see Section 6).

For environments where it might be inappropriate to halt program execution when an error is detected, the value -1 or 1 is recommended. If the output of error messages is undesirable, then the value 1 is recommended. Otherwise, for users not familiar with this parameter the recommended value is 0. When the value -1 or 1 is used it is essential to test the value of IFAIL on exit.

G05MKF.2 [NP3546/20A]

# 6 Error Indicators and Warnings

If on entry IFAIL = 0 or -1, explanatory error messages are output on the current error message unit (as defined by X04AAF).

Errors or warnings detected by the routine:

```
IFAIL = 1 \\ On entry, \ N < 1.
IFAIL = 2 \\ On entry, \ NR \ is \ too \ small \ when \ MODE = 0 \ or \ 2 \ (see \ Section \ 5).
IFAIL = 3 \\ On \ entry, \ LAMBDA < 0.0.
IFAIL = 4 \\ On \ entry, \ MODE < 0 \\ or \ MODE > 3.
```

IFAIL = 5

MODE = 0 or 2 and LAMBDA is such that NR would have to be larger than the largest representable integer. Use MODE = 3 in this case.

IFAIL = 6

LAMBDA is not the same as when R was set up in a previous call with MODE = 0 or 2.

# 7 Accuracy

Not applicable.

### **8** Further Comments

None.

#### 9 Example

The example program prints 10 pseudo-random integers from a Poisson distribution with mean  $\lambda = 20$ , generated by a single call to G05MKF, after initialisation by G05KBF.

## 9.1 Program Text

**Note:** the listing of the example program presented below uses **bold italicised** terms to denote precision-dependent details. Please read the Users' Note for your implementation to check the interpretation of these terms. As explained in the Essential Introduction to this manual, the results produced may not be identical for all implementations.

```
GO5MKF Example Program Text
Mark 20 Release. NAG Copyright 2001.
.. Parameters ..
INTEGER
                 NOUT, N, NR
PARAMETER
                 (NOUT=6,N=10,NR=120)
.. Local Scalars ..
                 LAMBDA
real
                 I, IFAIL, IGEN
INTEGER
.. Local Arrays ..
real
                 R(NR)
INTEGER
                 ISEED(4), X(N)
.. External Subroutines ..
                 GO5KBF, GO5MKF
EXTERNAL
```

[NP3546/20A] G05MKF.3

```
.. Executable Statements ..
     WRITE (NOUT, *) 'G05MKF Example Program Results'
     WRITE (NOUT, *)
     Set the distribution parameter LAMBDA
     LAMBDA = 20.0e0
     Initialise the seed to a repeatable sequence
     ISEED(1) = 1762543
      ISEED(2) = 9324783
     ISEED(3) = 42344
     ISEED(4) = 742355
     IGEN identifies the stream.
     IGEN = 1
      CALL GO5KBF(IGEN, ISEED)
     IFAIL = 0
     Generate reference vector R
     CALL GO5MKF(O,LAMBDA,N,X,IGEN,ISEED,R,NR,IFAIL)
     Generate integers and store in X
     CALL GO5MKF(1,LAMBDA,N,X,IGEN,ISEED,R,NR,IFAIL)
     WRITE (NOUT, 99999) (X(I), I=1, N)
     STOP
99999 FORMAT (1X,I12)
     END
```

## 9.2 Program Data

None.

### 9.3 Program Results

```
G05MKF Example Program Results

14
28
19
23
28
19
21
19
21
19
18
26
```

G05MKF.4 (last) [NP3546/20A]