

NAG Fortran Library Routine Document

D01GCF

Note: before using this routine, please read the Users' Note for your implementation to check the interpretation of *bold italicised* terms and other implementation-dependent details.

1 Purpose

D01GCF calculates an approximation to a definite integral in up to 20 dimensions, using the Korobov–Conroy number theoretic method.

2 Specification

```

SUBROUTINE D01GCF(NDIM, FUNCTN, REGION, NPTS, VK, NRAND, ITRANS, RES,
1              ERR, IFAIL)
  INTEGER      NDIM, NPTS, NRAND, ITRANS, IFAIL
  real       FUNCTN, VK(NDIM), RES, ERR
  EXTERNAL    FUNCTN, REGION

```

3 Description

This routine calculates an approximation to the integral

$$I = \int_{c_1}^{d_1} dx_1, \dots, \int_{c_n}^{d_n} dx_n f(x_1, x_2, \dots, x_n) \quad (1)$$

using the Korobov–Conroy number theoretic method (Korobov (1957), Korobov (1963), Conroy (1967)). The region of integration defined in (1) is such that generally c_i and d_i may be functions of x_1, x_2, \dots, x_{i-1} , for $i = 2, 3, \dots, n$, with c_1 and d_1 constants. The integral is first of all transformed to an integral over the n -cube $[0, 1]^n$ by the change of variables

$$x_i = c_i + (d_i - c_i)y_i, \quad i = 1, 2, \dots, n.$$

The method then uses as its basis the number theoretic formula for the n -cube, $[0, 1]^n$:

$$\int_0^1 dx_1 \cdots \int_0^1 dx_n g(x_1, x_2, \dots, x_n) = \frac{1}{p} \sum_{k=1}^p g\left(\left\{k \frac{a_1}{p}\right\}, \dots, \left\{k \frac{a_n}{p}\right\}\right) - E \quad (2)$$

where $\{x\}$ denotes the fractional part of x , a_1, a_2, \dots, a_n are the so-called optimal coefficients, E is the error, and p is a prime integer. (It is strictly only necessary that p be relatively prime to all a_1, a_2, \dots, a_n and is in fact chosen to be even for some cases in Conroy (1967).) The method makes use of properties of the Fourier expansion of $g(x_1, x_2, \dots, x_n)$ which is assumed to have some degree of periodicity. Depending on the choice of a_1, a_2, \dots, a_n the contributions from certain groups of Fourier coefficients are eliminated from the error, E . Korobov shows that a_1, a_2, \dots, a_n can be chosen so that the error satisfies

$$E \leq CKp^{-\alpha} \ln^{\alpha\beta} p \quad (3)$$

where α and C are real numbers depending on the convergence rate of the Fourier series, β is a constant depending on n , and K is a constant depending on α and n . There are a number of procedures for calculating these optimal coefficients. Korobov imposes the constraint that

$$a_1 = 1 \quad \text{and} \quad a_i = a^{i-1} \pmod{p} \quad (4)$$

and gives a procedure for calculating the parameter, a , to satisfy the optimal conditions.

In this routine the periodisation is achieved by the simple transformation

$$x_i = y_i^2(3 - 2y_i), \quad i = 1, 2, \dots, n.$$

More sophisticated periodisation procedures are available but in practice the degree of periodisation does not appear to be a critical requirement of the method.

An easily calculable error estimate is not available apart from repetition with an increasing sequence of values of p which can yield erratic results. The difficulties have been studied by Cranley and Patterson (1976) who have proposed a Monte Carlo error estimate arising from converting (2) into a stochastic integration rule by the inclusion of a random origin shift which leaves the form of the error (3) unchanged; i.e., in the formula (2), $\left\{k\frac{a_i}{p}\right\}$ is replaced by $\left\{\alpha_i + k\frac{a_i}{p}\right\}$, for $i = 1, 2, \dots, n$, where each α_i is uniformly distributed over $[0, 1]$. Computing the integral for each of a sequence of random vectors α allows a 'standard error' to be estimated.

This routine provides built-in sets of optimal coefficients, corresponding to six different values of p . Alternatively the optimal coefficients may be supplied by the user. Routines D01GYF and D01GZF compute the optimal coefficients for the cases where p is a prime number or p is a product of 2 primes, respectively.

4 References

Korobov N M (1957) The approximate calculation of multiple integrals using number theoretic methods *Dokl. Acad. Nauk SSSR* **115** 1062–1065

Korobov N M (1963) *Number Theoretic Methods in Approximate Analysis* Fizmatgiz, Moscow

Conroy H (1967) Molecular Shroedinger equation VIII. A new method for evaluating multi-dimensional integrals *J. Chem. Phys.* **47** 5307–5318

Cranley R and Patterson T N L (1976) Randomisation of number theoretic methods for mulitple integration *SIAM J. Numer. Anal.* **13** 904–914

5 Parameters

1: NDIM – INTEGER *Input*

On entry: the number of dimensions of the integral, n .

Constraint: $1 \leq \text{NDIM} \leq 20$.

2: FUNCTN – *real* FUNCTION, supplied by the user. *External Procedure*

FUNCTN must return the value of the integrand f at a given point.

Its specification is:

<pre style="margin: 0;"> real FUNCTION FUNCTN(NDIM, X) INTEGER NDIM real X(NDIM) </pre>
<p>1: NDIM – INTEGER <i>Input</i></p> <p><i>On entry:</i> the number of dimensions of the integral, n.</p>
<p>2: X(NDIM) – <i>real</i> array <i>Input</i></p> <p><i>On entry:</i> the co-ordinates of the point at which the integrand must be evaluated.</p>

FUNCTN must be declared as EXTERNAL in the (sub)program from which D01GCF is called. Parameters denoted as *Input* must **not** be changed by this procedure.

- 3: REGION – SUBROUTINE, supplied by the user. *External Procedure*
 REGION must evaluate the limits of integration in any dimension.
 Its specification is:

<pre> SUBROUTINE REGION(NDIM, X, J, C, D) INTEGER NDIM, J real X(NDIM), C, D </pre>	
<p>1: NDIM – INTEGER <i>Input</i> <i>On entry:</i> the number of dimensions of the integral, n.</p>	
<p>2: X(NDIM) – real array <i>Input</i> <i>On entry:</i> X(1), ..., X($j - 1$) contain the current values of the first ($j - 1$) variables, which may be used if necessary in calculating c_j and d_j.</p>	
<p>3: J – INTEGER <i>Input</i> <i>On entry:</i> the index j for which the limits of the range of integration are required.</p>	
<p>4: C – real <i>Output</i> <i>On exit:</i> the lower limit c_j of the range of x_j.</p>	
<p>5: D – real <i>Output</i> <i>On exit:</i> the upper limit d_j of the range of x_j.</p>	

REGION must be declared as EXTERNAL in the (sub)program from which D01GCF is called. Parameters denoted as *Input* must **not** be changed by this procedure.

- 4: NPTS – INTEGER *Input*
On entry: the Korobov rule to be used. There are two alternatives depending on the value of NPTS.
- (a) $1 \leq \text{NPTS} \leq 6$.
 In this case one of six preset rules is chosen using 2129, 5003, 10007, 20011, 40009 or 80021 points depending on the respective value of NPTS being 1, 2, 3, 4, 5 or 6.
- (b) $\text{NPTS} > 6$.
 NPTS is the number of actual points to be used with corresponding optimal coefficients supplied in the array VK.
Constraint: $\text{NPTS} \geq 1$.
- 5: VK(NDIM) – **real** array *Input/Output*
On entry: if $\text{NPTS} > 6$, VK must contain the n optimal coefficients (which may be calculated using D01GYF or D01GZF); if $\text{NPTS} \leq 6$, VK need not be set.
On exit: if $\text{NPTS} > 6$, VK is unchanged; if $\text{NPTS} \leq 6$, VK contains the n optimal coefficients used by the preset rule.
- 6: NRAND – INTEGER *Input*
On entry: the number of random samples to be generated in the error estimation (generally a small value, say 3 to 5 is sufficient). The total number of integrand evaluations will be $\text{NRAND} \times \text{NPTS}$.
Constraint: $\text{NRAND} \geq 1$.

- 7: ITRANS – INTEGER *Input*
On entry: indicates whether the periodising transformation is to be used:
 if ITRANS = 0, the transformation is to be used;
 if ITRANS \neq 0, the transformation is to be suppressed (to cover cases where the integrand may already be periodic or where the user desires to specify a particular transformation in the definition of FUNCTN).
Suggested value: ITRANS = 0.
- 8: RES – *real* *Output*
On exit: an estimate of the value of the integral.
- 9: ERR – *real* *Output*
On exit: the standard error as computed from NRAND sample values. If NRAND = 1, then ERR contains zero.
- 10: IFAIL – INTEGER *Input/Output*
On entry: IFAIL must be set to 0, -1 or 1. Users who are unfamiliar with this parameter should refer to Chapter P01 for details.
On exit: IFAIL = 0 unless the routine detects an error (see Section 6).
 For environments where it might be inappropriate to halt program execution when an error is detected, the value -1 or 1 is recommended. If the output of error messages is undesirable, then the value 1 is recommended. Otherwise, for users not familiar with this parameter the recommended value is 0. **When the value -1 or 1 is used it is essential to test the value of IFAIL on exit.**

6 Error Indicators and Warnings

If on entry IFAIL = 0 or -1, explanatory error messages are output on the current error message unit (as defined by X04AAF).

Errors or warnings detected by the routine:

IFAIL = 1

On entry, NDIM < 1,
 or NDIM > 20.

IFAIL = 2

On entry, NPTS < 1.

IFAIL = 3

On entry, NRAND < 1.

7 Accuracy

An estimate of the absolute standard error is given by the value, on exit, of ERR.

8 Further Comments

The time taken by the routine will be approximately proportional to NRAND \times p , where p is the number of points used.

The exact values of RES and ERR returned by D01GCF will depend (within statistical limits) on the sequence of random numbers generated within the routine by calls to G05CAF. To ensure that the results

returned by D01GCF in separate runs are identical, users should call G05CBF immediately before calling D01GCF; to ensure that they are different, call G05CCF.

9 Example

This example calculates the integral

$$\int_0^1 \int_0^1 \int_0^1 \int_0^1 \cos(0.5 + 2(x_1 + x_2 + x_3 + x_4) - 4) dx_1 dx_2 dx_3 dx_4.$$

9.1 Program Text

Note: the listing of the example program presented below uses *bold italicised* terms to denote precision-dependent details. Please read the Users' Note for your implementation to check the interpretation of these terms. As explained in the Essential Introduction to this manual, the results produced may not be identical for all implementations.

```
*      D01GCF Example Program Text
*      Mark 14 Revised.  NAG Copyright 1989.
*      .. Parameters ..
INTEGER          NDIM
PARAMETER       (NDIM=4)
INTEGER          NOUT
PARAMETER       (NOUT=6)
*      .. Local Scalars ..
real           ERR, RES
INTEGER          IFAIL, ITRANS, NPTS, NRAND
*      .. Local Arrays ..
real           VK(NDIM)
*      .. External Functions ..
real           FUNCT
EXTERNAL         FUNCT
*      .. External Subroutines ..
EXTERNAL        D01GCF, REGION
*      .. Executable Statements ..
WRITE (NOUT,*) 'D01GCF Example Program Results'
NPTS = 2
ITRANS = 0
NRAND = 4
IFAIL = 0
*
CALL D01GCF(NDIM,FUNCT,REGION,NPTS,VK,NRAND,ITRANS,RES,ERR,IFAIL)
*
WRITE (NOUT,*)
WRITE (NOUT,99999) 'Result =', RES, ' Standard error =', ERR
STOP
*
99999 FORMAT (1X,A,F13.5,A,e10.2)
END
*
SUBROUTINE REGION(N,X,J,A,B)
*      .. Scalar Arguments ..
real           A, B
INTEGER          J, N
*      .. Array Arguments ..
real           X(N)
*      .. Executable Statements ..
A = 0.0e0
B = 1.0e0
RETURN
END
*
real FUNCTION FUNCT(NDIM,X)
*      .. Scalar Arguments ..
INTEGER          NDIM
*      .. Array Arguments ..
real           X(NDIM)
*      .. Local Scalars ..
real           SUM
INTEGER          J
```

```
*      .. Intrinsic Functions ..  
INTRINSIC          COS, real  
*      .. Executable Statements ..  
SUM = 0.0e0  
DO 20 J = 1, NDIM  
    SUM = SUM + X(J)  
20 CONTINUE  
FUNCT = COS(0.5e0+2.0e0*SUM-real(NDIM))  
RETURN  
END
```

9.2 Program Data

None.

9.3 Program Results

D01GCF Example Program Results

Result = 0.43999 Standard error = 0.18E-05
