

NAG Fortran Library Routine Document

D06CAF

Note: before using this routine, please read the Users' Note for your implementation to check the interpretation of *bold italicised* terms and other implementation-dependent details.

1 Purpose

D06CAF uses a barycentering technique to smooth a given mesh.

2 Specification

```

SUBROUTINE D06CAF (NV, NELT, NEDGE, COOR, EDGE, CONN, NVFIX, NUMFIX,
1 ITRACE, NQINT, IWORK, LIWORK, RWORK, LRWORK, IFAIL)
INTEGER NV, NELT, NEDGE, EDGE(3,NEDGE), CONN(3,NELT), NVFIX,
1 NUMFIX(*), ITRACE, NQINT, IWORK(LIWORK), LIWORK,
2 LRWORK, IFAIL
   double precision COOR(2,NV), RWORK(LRWORK)

```

3 Description

D06CAF uses a barycentering approach to improve the smoothness of a given mesh. The measure of quality used for a triangle K is

$$Q_K = \alpha \frac{h_K}{\rho_K};$$

where h_K is the diameter (length of the longest edge) of K , ρ_K is the radius of its inscribed circle and $\alpha = \frac{\sqrt{3}}{6}$ is a normalization factor chosen to give $Q_K = 1$ for an equilateral triangle. Q_K ranges from 1, for an equilateral triangle, to ∞ , for a totally flat triangle.

D06CAF makes small perturbation to vertices (using a barycenter formula) in order to give a reasonably good value of Q_K for all neighbouring triangles. Some vertices may optionally be excluded from this process.

For more details about the smoothing method, especially with regard to differing quality, consult the D06 Chapter Introduction as well as George and Borouchaki (1998).

This routine is derived from material in the MODULEF package from INRIA (Institut National de Recherche en Informatique et Automatique).

4 References

George P L and Borouchaki H (1998) *Delaunay Triangulation and Meshing: Application to Finite Elements* Editions HERMES, Paris

5 Parameters

- 1: NV – INTEGER *Input*
On entry: the total number of vertices in the input mesh.
Constraint: $NV \geq 3$.
- 2: NELT – INTEGER *Input*
On entry: the number of triangles in the input mesh.
Constraint: $NELT \leq 2 \times NV - 1$.

- 3: NEDGE – INTEGER *Input*
On entry: the number of the boundary and interface edges in the input mesh.
Constraint: NEDGE \geq 1.
- 4: COOR(2,NV) – *double precision* array *Input/Output*
On entry: COOR(1, *i*) contains the *x* co-ordinate of the *i*th input mesh vertex, for $i = 1, \dots, NV$; while COOR(2, *i*) contains the corresponding *y* co-ordinate.
On exit: COOR(1, *i*) will contain the *x* co-ordinate of the *i*th smoothed mesh vertex, for $i = 1, \dots, NV$; while COOR(2, *i*) will contain the corresponding *y* co-ordinate. Note that the co-ordinates of boundary and interface edge vertices, as well as those specified by you (see the description of NUMFIX), are unchanged by the process.
- 5: EDGE(3,NEDGE) – INTEGER array *Input*
On entry: the specification of the boundary or interface edges. EDGE(1, *j*) and EDGE(2, *j*) contain the vertex numbers of the two end points of the *j*th boundary edge. EDGE(3, *j*) is a user-supplied tag for the *j*th boundary or interface edge: EDGE(3, *j*) = 0 for an interior edge and has a non-zero tag otherwise.
Constraint: $1 \leq \text{EDGE}(i, j) \leq NV$ and $\text{EDGE}(1, j) \neq \text{EDGE}(2, j)$, for $i = 1, 2$ and $j = 1, 2, \dots, \text{NEDGE}$.
- 6: CONN(3,NELT) – INTEGER array *Input*
On entry: the connectivity of the mesh between triangles and vertices. For each triangle *j*, CONN(*i*, *j*) gives the indices of its three vertices (in anticlockwise order), for $i = 1, 2, 3$ and $j = 1, \dots, \text{NELT}$.
Constraint: $1 \leq \text{CONN}(i, j) \leq NV$ and $\text{CONN}(1, j) \neq \text{CONN}(2, j)$ and $\text{CONN}(1, j) \neq \text{CONN}(3, j)$ and $\text{CONN}(2, j) \neq \text{CONN}(3, j)$, for $i = 1, 2, 3$ and $j = 1, 2, \dots, \text{NELT}$.
- 7: NVFIX – INTEGER *Input*
On entry: the number of fixed vertices in the input mesh.
Constraint: $0 \leq \text{NVFIX} \leq NV$.
- 8: NUMFIX(*) – INTEGER array *Input*
Note: the dimension of the array NUMFIX must be at least $\max(1, \text{NVFIX})$.
On entry: the indices in COOR of fixed interior vertices of the input mesh.
Constraint: if $\text{NVFIX} > 0$, $1 \leq \text{NUMFIX}(i) \leq NV$, for $i = 1, 2, \dots, \text{NVFIX}$.
- 9: ITRACE – INTEGER *Input*
On entry: the level of trace information required from D06CAF.
 ITRACE \leq 0
 No output is generated.
 ITRACE = 1
 A histogram of the triangular element qualities is printed on the current advisory message unit (see X04ABF) before and after smoothing. This histogram gives the lowest and the highest triangle quality as well as the number of elements lying in each of the NQINT equal intervals between the extremes.
 ITRACE $>$ 1
 The output is similar to that produced when ITRACE = 1 but the connectivity between vertices and triangles (for each vertex, the list of triangles in which it appears) is given.

You are advised to set ITRACE = 0, unless you are experienced with finite element meshes.

- 10: NQINT – INTEGER *Input*
On entry: the number of intervals between the extreme quality values for the input and the smoothed mesh.
 If ITRACE = 0, NQINT is not referenced.
- 11: IWORK(LIWORK) – INTEGER array *Workspace*
 12: LIWORK – INTEGER *Input*
On entry: the dimension of the array IWORK as declared in the (sub)program from which D06CAF is called.
Constraint: $LIWORK \geq 8 \times NELT + 2 \times NV$.
- 13: RWORK(LRWORK) – *double precision* array *Workspace*
 14: LRWORK – INTEGER *Input*
On entry: the dimension of the array RWORK as declared in the (sub)program from which D06CAF is called.
Constraint: $LRWORK \geq 2 \times NV + NELT$.
- 15: IFAIL – INTEGER *Input/Output*
On entry: IFAIL must be set to 0, -1 or 1. If you are unfamiliar with this parameter you should refer to Chapter P01 for details.
On exit: IFAIL = 0 unless the routine detects an error (see Section 6).
 For environments where it might be inappropriate to halt program execution when an error is detected, the value -1 or 1 is recommended. If the output of error messages is undesirable, then the value 1 is recommended. Otherwise, if you are not familiar with this parameter the recommended value is 0. **When the value -1 or 1 is used it is essential to test the value of IFAIL on exit.**

6 Error Indicators and Warnings

If on entry IFAIL = 0 or -1, explanatory error messages are output on the current error message unit (as defined by X04AAF).

Errors or warnings detected by the routine:

IFAIL = 1

- On entry, $NV < 3$,
- or $NELT > 2 \times NV - 1$,
- or $NEDGE < 1$,
- or $EDGE(i,j) < 1$ or $EDGE(i,j) > NV$ for some $i = 1, 2$ and $j = 1, \dots, NEDGE$,
- or $EDGE(1,j) = EDGE(2,j)$ for some $j = 1, \dots, NEDGE$,
- or $CONN(i,j) < 1$ or $CONN(i,j) > NV$ for some $i = 1, 2, 3$ and $j = 1, \dots, NELT$,
- or $CONN(1,j) = CONN(2,j)$ or $CONN(1,j) = CONN(3,j)$ or $CONN(2,j) = CONN(3,j)$ for some $j = 1, \dots, NELT$,
- or $NVFIX < 0$ or $NVFIX > NV$,
- or $NUMFIX(i) < 1$ or $NUMFIX(i) > NV$ for some $i = 1, \dots, NVFIX$ if $NVFIX > 0$,
- or $LIWORK < 8 \times NELT + 2 \times NV$,
- or $LRWORK < 2 \times NV + NELT$.

IFAIL = 2

A serious error has occurred in an internal call to an auxiliary routine. Check the input mesh, especially the connectivity between triangles and vertices (the parameter CONN). Setting ITRACE > 1 may provide more information. If the problem persists, contact NAG.

7 Accuracy

Not applicable.

8 Further Comments

Not applicable.

9 Example

In this example, a uniform mesh on the unit square is randomly distorted using routines from Chapter G05 (see Figure 1). D06CAF is then used to smooth the distorted mesh and recover a uniform mesh (see Figure 2).

9.1 Program Text

```
*      D06CAF Example Program Text
*      Mark 20 Release. NAG Copyright 2001.
*      .. Parameters ..
      INTEGER          NIN, NOUT
      PARAMETER       (NIN=5,NOUT=6)
      INTEGER          NBEDMX, NVMAX, NELTMAX, NVFIXMX, LNUME, LIWORK,
+
      LRWORK
      PARAMETER       (NBEDMX=100,NVMAX=400,NELTMAX=2*NVMAX-1,
+
      NVFIXMX=20,LNUME=3*NELTMAX,
+
      LIWORK=2*NVMAX+5*NELTMAX+LNUME,
+
      LRWORK=2*NVMAX+NELTMAX)
*      .. Local Scalars ..
      DOUBLE PRECISION DELTA, HX, HY, PI, R, RAD, SK, THETA, X1, X2, X3,
+
      Y1, Y2, Y3
      INTEGER          I, IFAIL, IMAX, IND, ITRACE, J, JMAX, K, ME1,
+
      ME2, ME3, NEDGE, NELT, NQINT, NV, NVFIX, REFTK
      CHARACTER        PMESH
*      .. Local Arrays ..
      DOUBLE PRECISION COOR(2,NVMAX), RWORK(LRWORK)
      INTEGER          CONN(3,NELTMAX), EDGE(3,NBEDMX), IWORK(LIWORK),
+
      NUMFIX(NVFIXMX)
*      .. External Functions ..
      DOUBLE PRECISION GO5DAF
      EXTERNAL         GO5DAF
*      .. External Subroutines ..
      EXTERNAL         D06CAF, GO5CBF
*      .. Intrinsic Functions ..
*
      INTRINSIC        ATAN, COS, DBLE, MIN, SIN
*      .. Executable Statements ..
      WRITE (NOUT,*) 'D06CAF Example Program Results'
      WRITE (NOUT,*)

*
*      Skip heading in data file
*
      READ (NIN,*)

*
*      Read IMAX and JMAX, the number of vertices
*      in the x and y directions respectively.
*
      READ (NIN,*) IMAX, JMAX

*
*      Read distortion percentage and calculate radius
*      of distortion neighbourhood so that cross-over
```

```

*   can only occur at 100% or greater.
*
  READ (NIN,*) DELTA
*
  NV = IMAX*JMAX
  IF (NV.GT.NVMAX) THEN
    WRITE (NOUT,99999) 'Dimension problem NV MAX ', NV, NVMAX
    STOP
  END IF
*
  READ (NIN,*) PMESH
*
  HX = 1.DO/DBLE(IMAX-1)
  HY = 1.DO/DBLE(JMAX-1)
  RAD = 0.01D0*DELTA*MIN(HX,HY)/2.DO
  PI = 4.DO*ATAN(1.DO)
  CALL G05CBF(0)
  IND = 0
*
*   Generate a simple uniform mesh and then distort it
*   randomly within the distortion neighbourhood of each
*   node.
*
  DO 40 J = 1, JMAX
    DO 20 I = 1, IMAX

      R = G05DAF(0.DO,RAD)
      THETA = G05DAF(0.DO,2*PI)
      IF (I.EQ.1 .OR. I.EQ.IMAX .OR. J.EQ.1 .OR. J.EQ.JMAX)
+        R = 0.DO

      K = (J-1)*IMAX + I
      COOR(1,K) = DBLE(I-1)*HX + R*COS(THETA)
      COOR(2,K) = DBLE(J-1)*HY + R*SIN(THETA)

      IF (I.LT.IMAX .AND. J.LT.JMAX) THEN
        IND = IND + 1
        CONN(1,IND) = K
        CONN(2,IND) = K + 1
        CONN(3,IND) = K + IMAX + 1
        IND = IND + 1
        CONN(1,IND) = K
        CONN(2,IND) = K + IMAX + 1
        CONN(3,IND) = K + IMAX
      END IF
    20 CONTINUE
  40 CONTINUE
*
  NELT = IND
*
  IF (PMESH.EQ.'N') THEN
    WRITE (NOUT,*) 'The complete distorted mesh characteristics'
    WRITE (NOUT,99998) 'NV =', NV
    WRITE (NOUT,99998) 'NELT =', NELT
  ELSE IF (PMESH.EQ.'Y') THEN
*
*   Output the mesh to view it using the NAG Graphics Library
*
    WRITE (NOUT,99997) NV, NELT
    DO 60 I = 1, NV
      WRITE (NOUT,99996) COOR(1,I), COOR(2,I)
    60 CONTINUE
  ELSE
    WRITE (NOUT,*) 'Problem with the printing option Y or N'
    STOP
  END IF
*
  REFTK = 0
  DO 80 K = 1, NELT
    ME1 = CONN(1,K)
    ME2 = CONN(2,K)

```

```

      ME3 = CONN(3,K)
*
      X1 = COOR(1,ME1)
      X2 = COOR(1,ME2)
      X3 = COOR(1,ME3)
      Y1 = COOR(2,ME1)
      Y2 = COOR(2,ME2)
      Y3 = COOR(2,ME3)
*
      SK = ((X2-X1)*(Y3-Y1)-(Y2-Y1)*(X3-X1))/2.DO
      IF (SK.LT.0.DO) THEN
        WRITE (NOUT,*)
+       'Error the surface of the element is negative'
        WRITE (NOUT,99998) 'K = ', K
        WRITE (NOUT,99994) 'SK = ', SK
        STOP
      END IF
+     IF (PMESH.EQ.'Y') WRITE (NOUT,99995) CONN(1,K), CONN(2,K),
+     CONN(3,K), REFTK
80 CONTINUE
*
*   Boundary edges
*
      NEDGE = 0
      DO 100 I = 1, IMAX - 1
        NEDGE = NEDGE + 1
        EDGE(1,NEDGE) = I
        EDGE(2,NEDGE) = I + 1
        EDGE(3,NEDGE) = 0
100 CONTINUE
*
      DO 120 I = 1, JMAX - 1
        NEDGE = NEDGE + 1
        EDGE(1,NEDGE) = I*IMAX
        EDGE(2,NEDGE) = (I+1)*IMAX
        EDGE(3,NEDGE) = 0
120 CONTINUE
*
      DO 140 I = 1, IMAX - 1
        NEDGE = NEDGE + 1
        EDGE(1,NEDGE) = IMAX*JMAX - I + 1
        EDGE(2,NEDGE) = IMAX*JMAX - I
        EDGE(3,NEDGE) = 0
140 CONTINUE
*
      DO 160 I = 1, JMAX - 1
        NEDGE = NEDGE + 1
        EDGE(1,NEDGE) = (JMAX-I)*IMAX + 1
        EDGE(2,NEDGE) = (JMAX-I-1)*IMAX + 1
        EDGE(3,NEDGE) = 0
160 CONTINUE
*
      NVFIX = 0
      NUMFIX(1) = 0
      ITRACE = 1
      NQINT = 10
      IFAIL = 0
*
*   Call the smoothing routine
*
      CALL D06CAF(NV,NELT,NEDGE,COOR,EDGE,CONN,NVFIX,NUMFIX,ITRACE,
+      NQINT,IWORK,LIWORK,RWORK,LRWORK,IFAIL)
*
      IF (PMESH.EQ.'N') THEN
        WRITE (NOUT,*) 'The complete smoothed mesh characteristics'
        WRITE (NOUT,99998) 'NV = ', NV
        WRITE (NOUT,99998) 'NELT = ', NELT
      ELSE IF (PMESH.EQ.'Y') THEN
*
*   Output the mesh to view it using the NAG Graphics Library
*

```

```

        WRITE (NOUT,99997) NV, NELT
        DO 180 I = 1, NV
            WRITE (NOUT,99996) COOR(1,I), COOR(2,I)
180     CONTINUE
*
        REFTK = 0
        DO 200 K = 1, NELT
            WRITE (NOUT,99995) CONN(1,K), CONN(2,K), CONN(3,K), REFTK
200     CONTINUE
        END IF
*
        STOP
*
99999 FORMAT (1X,A,2I6)
99998 FORMAT (1X,A,I6)
99997 FORMAT (1X,2I10)
99996 FORMAT (2(2X,E12.6))
99995 FORMAT (1X,4I10)
99994 FORMAT (1X,A,E12.6)
        END

```

9.2 Program Data

D06CAF Example Program Data

```

20 20      :IMAX JMAX
87.0      :DELTA
'N'       :Printing option 'Y' or 'N'

```

9.3 Program Results

D06CAF Example Program Results

The complete distorted mesh characteristics

```

NV      = 400
NELT    = 722
BEFORE SMOOTHING
MINIMUM SMOOTHNESS MEASURE:      1.0048907
MINIMUM SMOOTHNESS MEASURE:      133.2110681
DISTRIBUTION
INTERVAL                                NUMBER OF ELEMENTS
1.0048907 - 14.2255084                720
14.2255084 - 27.4461262                0
27.4461262 - 40.6667439                0
40.6667439 - 53.8873616                0
53.8873616 - 67.1079794                0
67.1079794 - 80.3285971                0
80.3285971 - 93.5492149                0
93.5492149 - 106.7698326               0
106.7698326 - 119.9904504              0
119.9904504 - 133.2110681              1

```

```

AFTER SMOOTHING
MINIMUM SMOOTHNESS MEASURE:      1.3346259
MINIMUM SMOOTHNESS MEASURE:      1.4572261
DISTRIBUTION
INTERVAL                                NUMBER OF ELEMENTS
1.3346259 - 1.3468859                  10
1.3468859 - 1.3591459                  36
1.3591459 - 1.3714060                  46
1.3714060 - 1.3836660                  117
1.3836660 - 1.3959260                  186
1.3959260 - 1.4081860                  137
1.4081860 - 1.4204460                  106
1.4204460 - 1.4327061                  51
1.4327061 - 1.4449661                  28
1.4449661 - 1.4572261                  4

```

The complete smoothed mesh characteristics

```

NV      = 400
NELT    = 722

```




Figure 1
Distorted uniform mesh




Figure 2
After smoothing with D06CAF