



REFERENCE MANUAL | PUBLIC

SAP Adaptive Server Enterprise 16.0 SP03

Document Version: 1.0 – 2019-06-06

# Reference Manual: Commands

# Content

- 1 Commands. . . . . 14**
- 1.1 alter database. . . . . 14
  - alter database Restrictions. . . . . 29
  - Using alter database for Archive Databases. . . . . 30
  - Altering In-Memory and Relaxed Durability Databases. . . . . 30
  - Altering Databases for In-Memory Row Storage. . . . . 31
  - Backing Up master After Allocating More Space. . . . . 32
  - Placing the Log on a Separate Device. . . . . 32
  - Altering Databases for Compression. . . . . 33
  - In-row LOB Columns. . . . . 33
  - Shrinking Log Space. . . . . 33
  - Getting Help on Space Usage. . . . . 34
  - The system and default Segments. . . . . 34
  - Using alter database to Awaken Sleeping Processes. . . . . 34
  - Using the alter database for proxy\_update Parameter. . . . . 34
  - Fully Encrypting Databases. . . . . 35
- 1.2 alter encryption key. . . . . 35
- 1.3 alter index. . . . . 44
- 1.4 alter login. . . . . 47
- 1.5 alter login profile. . . . . 54
- 1.6 alter...modify owner. . . . . 58
- 1.7 alter precomputed result set. . . . . 63
- 1.8 alter role. . . . . 65
  - Changing Passwords for Roles. . . . . 69
  - Mutually Exclusive Roles. . . . . 70
- 1.9 alter table. . . . . 70
  - Restrictions for alter table. . . . . 92
  - alter table and Encrypted Columns. . . . . 94
  - Altering a Table's Compression. . . . . 96
  - Altering Tables for In-Memory Row Storage. . . . . 96
  - Interactions Between Compression and Other alter table Parameters. . . . . 98
  - Altering the Compression Level for a Table Using Large Objects. . . . . 100
  - Getting Information About Tables. . . . . 101
  - Specifying Ascending or Descending Ordering in Indexes. . . . . 101
  - Using Cross-Database Referential Integrity Constraints. . . . . 101
  - Changing Defaults. . . . . 102

	Setting Space Management Properties for Indexes. . . . .	103
	Conversion of max_rows_per_page to exp_row_size. . . . .	104
	Using reservepagegap. . . . .	104
	Partitioning Tables for Improved Performance. . . . .	105
	Using Computed Columns. . . . .	106
	Adding IDENTITY Columns. . . . .	106
	Altering Table Schema. . . . .	107
	Restrictions for Modifying a Table Schema. . . . .	108
	Restrictions for Modifying text and image Columns. . . . .	109
	Modifying Tables With Unitext Columns. . . . .	109
	Changing Locking Schemes. . . . .	110
	Adding Java-SQL Columns. . . . .	111
	Restrictions for Shared-Disk Clusters. . . . .	111
1.10	alter thread pool. . . . .	111
1.11	begin...end. . . . .	114
1.12	begin transaction. . . . .	116
1.13	break. . . . .	118
1.14	checkpoint . . . . .	120
1.15	close. . . . .	122
1.16	commit. . . . .	123
1.17	compute Clause. . . . .	125
	compute Clause Restrictions. . . . .	130
	compute Results Appear as a New Row or Rows. . . . .	131
	Case-Sensitivity. . . . .	132
1.18	connect to...disconnect. . . . .	133
1.19	continue. . . . .	136
1.20	create archive database. . . . .	137
1.21	create database. . . . .	140
	Restrictions for create database. . . . .	152
	Temporary Databases. . . . .	153
	Creating Compressed Databases. . . . .	154
	Creating Databases With In-Row LOBs. . . . .	154
	Creating In-Memory and Relaxed Durability Databases. . . . .	154
	Creating Databases for In-Memory Row Storage Caches. . . . .	155
	New Databases Created from model. . . . .	156
	Ensuring Database Recoverability. . . . .	157
	Using the for load Option. . . . .	157
	Getting Information About Databases. . . . .	158
	Using with default_location and for proxy_update. . . . .	158
1.22	create default. . . . .	158
	create default Restrictions. . . . .	162

	Datatype Compatibility. . . . .	162
	Getting Information about Defaults. . . . .	162
	Defaults and Rules. . . . .	162
	Defaults and Nulls. . . . .	163
	Specifying a Default Value in create table. . . . .	163
	Objects Dependent on Replaced Defaults. . . . .	163
1.23	create encryption key. . . . .	163
1.24	create existing table. . . . .	170
	Datatype Conversions. . . . .	174
	Changes by Server Class. . . . .	174
	Remote Procedures. . . . .	175
	Encrypted Columns. . . . .	176
1.25	create function. . . . .	176
	Objects Dependent on Replaced Functions. . . . .	184
1.26	create function (SQLJ). . . . .	185
1.27	create global temporary table. . . . .	189
1.28	create index. . . . .	192
	Creating Indexes Efficiently. . . . .	206
	Creating Clustered Indexes. . . . .	206
	Creating Indexes on Compressed Table. . . . .	207
	Creating Indexes on Encrypted Columns. . . . .	207
	Considerations for Creating Indexes on In-Memory Row Storage Tables. . . . .	208
	Specifying Ascending or Descending Ordering in Indexes. . . . .	209
	Space Requirements for Indexes. . . . .	209
	Duplicate Rows. . . . .	209
	Using Unique Constraints in Place of Indexes. . . . .	210
	Using the sorted_data Option to Speed Sorts. . . . .	211
	Specifying the Number of Histogram Steps. . . . .	212
	Space Management Properties. . . . .	212
	Index Options and Locking Modes. . . . .	213
	Using the sorted_data Option on Data-Only-Locked Tables. . . . .	213
	Getting Information About Tables and Indexes. . . . .	214
	Creating Indexes on Computed Columns. . . . .	214
	Creating Partitioned Indexes. . . . .	214
	Creating Function-Based Indexes. . . . .	215
	create index and Stored Procedures. . . . .	215
	Creating Indexes in Parallel. . . . .	215
1.29	create login. . . . .	216
1.30	create login profile. . . . .	220
1.31	create manifest file. . . . .	223
1.32	create plan. . . . .	225

1.33	create precomputed result set. . . . .	227
1.34	create procedure. . . . .	232
	create procedure Restrictions. . . . .	243
	execute as Stored Procedure. . . . .	244
	System Procedures. . . . .	244
	Nested Procedures. . . . .	245
	Procedure Return Status. . . . .	245
	Object Identifiers. . . . .	246
	Temporary Tables and Procedures. . . . .	247
	Setting Options in Procedures. . . . .	247
	Extended Stored Procedures. . . . .	247
	Objects Dependent on Replaced Procedures. . . . .	248
	Getting Information About Procedures. . . . .	248
1.35	create procedure (SQLJ). . . . .	248
1.36	create proxy_table. . . . .	253
1.37	create role. . . . .	257
1.38	create rule. . . . .	260
	create rule Restrictions. . . . .	264
	Binding Rules. . . . .	264
1.39	create schema. . . . .	265
1.40	create service. . . . .	268
1.41	create table. . . . .	273
	Restrictions for create table. . . . .	298
	Creating Compressed Tables. . . . .	301
	Restrictions for Compression. . . . .	302
	Using Indexes. . . . .	302
	Renaming a Table or Its Columns. . . . .	302
	Restrictions on Compressing Tables That Use Large Object (LOB) Data. . . . .	303
	Column Definitions. . . . .	303
	Temporary Tables. . . . .	304
	Defining Integrity Constraints. . . . .	305
	Unique and Primary-Key Constraints. . . . .	306
	Referential Integrity Constraints. . . . .	307
	Using Cross-Database Referential Integrity Constraints. . . . .	309
	check Constraints. . . . .	310
	IDENTITY Columns. . . . .	310
	Specifying a Locking Scheme. . . . .	311
	Getting Information About Tables. . . . .	311
	Creating Tables with Partitions. . . . .	312
	Creating Tables With Computed Columns. . . . .	312
	Creating Tables with Encrypted Columns. . . . .	313

	Limitations When Creating Virtually Hashed Tables. . . . .	313
	Creating Tables for In-Memory and Relaxed Durability Databases. . . . .	314
	Creating Tables for In-Memory Row Storage. . . . .	314
	Restrictions for Shared-Disk Clusters. . . . .	315
	Space Management Properties. . . . .	315
	Using reservepagegap. . . . .	316
	Java-SQL Columns. . . . .	317
	Determining Values for hash_factor. . . . .	318
1.42	create temporary precomputed result set. . . . .	318
1.43	create thread pool. . . . .	320
1.44	create trigger. . . . .	323
	Triggers and Referential Integrity. . . . .	331
	The deleted and inserted Logical Tables. . . . .	331
	Trigger Restrictions. . . . .	331
	Triggers and Performance. . . . .	332
	Setting Options Within Triggers. . . . .	332
	Dropping a Trigger. . . . .	332
	Actions That Do Not Cause Triggers to Fire. . . . .	332
	Nesting Triggers and Trigger Recursion. . . . .	333
	Restrictions for instead of. . . . .	334
	Getting Information About Triggers. . . . .	334
	Triggers and Transactions. . . . .	334
	Inserting and Updating Triggers. . . . .	335
	instead of and for Triggers. . . . .	336
1.45	create type. . . . .	337
1.46	create view. . . . .	338
	Restrictions on Views. . . . .	345
	View Resolution. . . . .	346
	Modifying Data Through Views. . . . .	346
	IDENTITY Columns and Views. . . . .	347
	group by Clauses and Views. . . . .	347
	distinct Clauses and Views. . . . .	347
	Creating Views from SQL-Derived Tables. . . . .	348
	Objects Dependent on Replaced Views. . . . .	348
1.47	dbcc. . . . .	349
	Using dbcc quorum (clusters only). . . . .	374
	Restrictions on dbcc checkstorage for Shared-Disk Clusters. . . . .	374
	Using dbcc complete_xact. . . . .	375
	Checking Performed by dbcc checkcatalog. . . . .	375
	Using dbcc checktable. . . . .	376
	Valid Options for dbcc imrs. . . . .	377

1.48	deallocate cursor. . . . .	379
1.49	deallocate locator. . . . .	381
1.50	declare. . . . .	382
1.51	declare cursor . . . . .	384
	Using Scrollable Cursors. . . . .	387
	Cursor select Statements. . . . .	387
	Cursor Scope. . . . .	388
	Result Set. . . . .	389
	Updatable Cursors. . . . .	389
	Releasing Locks at Cursor Close. . . . .	390
1.52	delete. . . . .	391
	delete Restrictions. . . . .	396
	Deleting All Rows from a Table. . . . .	396
	delete and Transactions. . . . .	397
	Using the where current of Parameter. . . . .	397
	Using readpast. . . . .	398
1.53	delete statistics. . . . .	398
1.54	disk init. . . . .	401
	Using dsync with disk init. . . . .	407
	Creating Devices for In-Memory and Relaxed Durability Databases. . . . .	408
	Creating Devices for In-Memory Row Storage Caches. . . . .	408
1.55	disk mirror . . . . .	409
1.56	disk refit. . . . .	413
1.57	disk reinit. . . . .	415
	Using dsync with Disk Reinit. . . . .	419
1.58	disk remirror. . . . .	420
1.59	disk resize. . . . .	423
1.60	disk unmirror. . . . .	425
1.61	drop database. . . . .	429
1.62	drop default. . . . .	431
1.63	drop encryption key. . . . .	433
1.64	drop function. . . . .	436
1.65	drop function (SQLJ). . . . .	438
1.66	drop index. . . . .	439
1.67	drop login. . . . .	442
1.68	drop login profile. . . . .	444
1.69	drop precomputed result set. . . . .	447
1.70	drop procedure. . . . .	448
1.71	drop role. . . . .	450
1.72	drop rule. . . . .	453
1.73	drop service. . . . .	455

1.74	drop table. . . . .	457
	Restrictions for drop table. . . . .	459
	Dropping Tables with Cross-Database Referential Integrity Constraints. . . . .	459
1.75	drop thread pool. . . . .	460
1.76	drop trigger. . . . .	462
1.77	drop type. . . . .	464
1.78	drop view. . . . .	466
1.79	dump configuration. . . . .	468
1.80	dump database. . . . .	470
	Commands and System Procedures Used to Back Up Databases. . . . .	481
	Scheduling Dumps. . . . .	482
	Specifying Dump Devices. . . . .	482
	Restrictions for dump database. . . . .	483
	Dumping Databases with Devices That Are Mirrored. . . . .	484
	Dumping the System Databases. . . . .	485
	Dump Files. . . . .	485
	Volume Names. . . . .	485
	Changing Dump Volumes. . . . .	486
	Appending to or Overwriting a Volume. . . . .	486
	File Names and Archive Names. . . . .	486
	dump database Performance. . . . .	488
	Compressed Dumps for an Archive Database. . . . .	488
	Compatibility Issues for a Compressed Dump . . . . .	489
	Encrypted Columns and dump database. . . . .	489
1.81	dump transaction. . . . .	490
	dump transaction Restrictions. . . . .	499
	Copying the Log After Device Failure. . . . .	501
	Dumping Databases Without Separate Log Segments. . . . .	501
	Dumping Only Complete Transactions. . . . .	501
	Dumping Without the Log. . . . .	502
	Scheduling Dumps. . . . .	502
	Using Thresholds to Automate dump transaction. . . . .	503
	Specifying Dump Devices. . . . .	503
	Determining Tape Device Characteristics. . . . .	503
	Backup Servers. . . . .	504
	Dump Files. . . . .	504
	Volume Names. . . . .	504
	Changing Dump Volumes. . . . .	505
	Appending To or Overwriting a Volume. . . . .	505
	Dumping Logs Stored on Mirrored Devices. . . . .	505
	Fully Recoverable DDL and dump transaction. . . . .	506



1.82	execute. . . . .	506
1.83	fetch. . . . .	513
	Status Information. . . . .	515
	fetch Restrictions. . . . .	516
	Using Scrollable Cursors with <code>fetch_direction</code> . . . . .	517
	Multiple Rows per Fetch. . . . .	517
	Rules for Positioning the Scrollable Cursor. . . . .	517
1.84	goto label. . . . .	519
1.85	grant. . . . .	520
	grant all Object Creation Privileges. . . . .	535
	Using the with grant option Parameter. . . . .	535
	Users and User Groups. . . . .	536
	Using the grant Command's granted by Option. . . . .	536
	Privileges for grant. . . . .	537
	Grant Access to Roles. . . . .	551
	Granting Default Permissions on System Tables. . . . .	552
	Granting Permissions for <code>update statistics</code> , <code>delete statistics</code> , and <code>truncate table</code> . . . . .	554
	Granting Proxies and Session Authorizations. . . . .	555
	Granting a Privilege to a Role. . . . .	555
1.86	grant role. . . . .	555
1.87	group by and having Clauses. . . . .	558
	How group by and having Queries with Aggregates Work. . . . .	562
	Standard group by and having Queries. . . . .	562
	Transact-SQL Extensions to <code>group by</code> and <code>having</code> . . . . .	563
	group by and having Clauses and Sort Orders. . . . .	568
	How group by Works With the Optimizer. . . . .	568
1.88	if...else. . . . .	569
1.89	insert. . . . .	572
	The Column List. . . . .	576
	Validating Column Values. . . . .	577
	Treatment of Blanks. . . . .	577
	Inserting Rows Selected from Another Table. . . . .	578
	Inserting Rows in Bulk. . . . .	578
	Transactions and <code>insert</code> . . . . .	579
	Inserting Values into IDENTITY Columns. . . . .	579
	Inserting Data Through Views. . . . .	580
	Partitioning Tables for Improved Insert Performance. . . . .	581
1.90	kill. . . . .	581
1.91	load database. . . . .	585
	Commands and System Procedures to Restore Databases. . . . .	596

	Restrictions for load database. . . . .	597
	Locking Out Users During Loads. . . . .	599
	Upgrading Database and Transaction Log Dumps. . . . .	599
	Specifying Dump Devices. . . . .	599
	Backup Servers. . . . .	600
	Volume Names. . . . .	600
	Changing Dump Volumes. . . . .	600
	Restoring the System Databases. . . . .	600
	Disk Mirroring. . . . .	600
	Materializing an Archive Database. . . . .	601
	Using load database with norecovery . . . . .	601
	Using Logical Devices with an Archive Database. . . . .	601
	load database Limitations with an Archive Database. . . . .	602
	load database and Encrypted Columns. . . . .	602
	Loading Compressed Data. . . . .	602
1.92	load transaction. . . . .	603
	load transaction Restrictions. . . . .	610
	Restoring a Database. . . . .	610
	Recovering a Database to a Specified Time. . . . .	611
	Locking Users Out During Loads. . . . .	611
	Upgrading Database and Transaction Log Dumps. . . . .	612
	Specifying Dump Devices. . . . .	612
	Backup Servers. . . . .	612
	Volume Names. . . . .	613
	Changing Dump Volumes. . . . .	613
	Disk Mirroring. . . . .	613
	Loading a Transaction Log into an Archive Database. . . . .	613
1.93	lock table. . . . .	614
1.94	merge. . . . .	617
1.95	mount. . . . .	620
1.96	online database. . . . .	625
1.97	open. . . . .	628
1.98	order by Clause. . . . .	630
	order by Clause Restrictions. . . . .	632
	Behavior of <code>order by</code> When Identical Table Column Name and Column Alias Name Exist. . . . .	633
	Collating Sequences. . . . .	634
	Sort Rules. . . . .	634
	Descending Scans. . . . .	635
1.99	prepare database. . . . .	636
1.100	prepare transaction. . . . .	639
1.101	print. . . . .	640

1.102	quiesce database. . . . .	643
	Encrypted Columns and quiesce database. . . . .	647
	quiesce database in a Clustered Environment. . . . .	648
1.103	raiserror. . . . .	648
1.104	readtext. . . . .	653
	Using the readpast Option. . . . .	656
	Using readtext with unitext Columns. . . . .	656
1.105	reconfigure. . . . .	657
1.106	refresh precomputed result set. . . . .	658
1.107	remove java. . . . .	659
1.108	reorg. . . . .	661
1.109	return. . . . .	669
1.110	revoke. . . . .	672
	Using the revoke Command's granted by Option. . . . .	683
	Revoking set proxy and set session authorization. . . . .	684
	Revoking Default Permissions on System Tables. . . . .	684
	Revoking Permissions for update statistics, delete statistics, and truncate table. . . . .	685
	Using the cascade Option. . . . .	686
1.111	revoke role. . . . .	687
1.112	rollback. . . . .	690
1.113	rollback trigger. . . . .	692
1.114	save transaction. . . . .	694
1.115	select . . . . .	696
	Using select into. . . . .	719
	Converting the NULL Properties of a Target Column with select...into. . . . .	720
	Specifying a Compression Level. . . . .	721
	Parameter Interactions with Data Compression. . . . .	721
	Using select for update. . . . .	721
	Specifying in-row LOB Columns. . . . .	722
	Specifying a Lock Scheme Using select...into. . . . .	722
	Specifying a Partition Strategy Using select...into. . . . .	722
	Using index, prefetch, and lru   mru. . . . .	723
	Using Encrypted Columns. . . . .	723
	Using parallel. . . . .	723
	Using readpast. . . . .	724
	Expanded select * Syntax. . . . .	725
	Using select with Variables, Global Variables, and Constants. . . . .	725
	Pagination Queries Using limit and offset. . . . .	726
	Using intersect and except. . . . .	727
1.116	set . . . . .	732
	set Options That Can Be Grouped Together. . . . .	776

	Compile-Time Changes for Some <code>set</code> Parameters. . . . .	776
	Aggregate Behavior. . . . .	778
	Comparison Behavior. . . . .	779
	Roles and <code>set</code> Options. . . . .	779
	In-Memory and Relaxed-Durability Databases. . . . .	780
	In-Memory Row Storage. . . . .	780
	Setting Compression for a Session. . . . .	781
	Using Predicated Privileges. . . . .	781
	Distributed Transactions, CIS, and <code>set</code> Options. . . . .	781
	Using Proxies. . . . .	782
	Using <code>lock wait</code> . . . . .	783
	Repeatable-Reads Transaction Isolation Level. . . . .	783
	Using Simulated Statistics. . . . .	784
	Global Variables Affected by <code>set</code> Options. . . . .	784
	Using <code>fipsflagger</code> with Java in the Database. . . . .	786
	Restrictions for <code>set tracefile</code> . . . . .	786
	<code>set</code> Options That Save Diagnostic Information to a Trace File. . . . .	787
	Restrictions for <code>show_sqltext</code> . . . . .	787
	Exporting <code>set</code> Options from a Login Trigger. . . . .	788
	Delimited Identifiers. . . . .	789
1.117	<code>setuser</code> . . . . .	790
1.118	<code>shutdown</code> . . . . .	792
	Specifying a Wait Time. . . . .	797
1.119	<code>transfer encryption key</code> . . . . .	797
1.120	<code>transfer table</code> . . . . .	799
1.121	<code>truncate lob</code> . . . . .	806
1.122	<code>truncate precomputed result set</code> . . . . .	807
1.123	<code>truncate table</code> . . . . .	809
1.124	<code>union operator</code> . . . . .	812
1.125	<code>unmount</code> . . . . .	816
1.126	<code>update</code> . . . . .	819
	Using <code>update</code> with Transactions. . . . .	825
	Using Joins in Updates. . . . .	825
	Using <code>update</code> with Character Data. . . . .	826
	Using <code>update</code> with Cursors. . . . .	826
	Updating IDENTITY Columns. . . . .	827
	Updating Data Through Views. . . . .	827
	Using <code>index</code> , <code>prefetch</code> , or <code>lru   mru</code> . . . . .	828
	Using <code>readpast</code> . . . . .	828
	Using Variables in <code>update</code> Statements. . . . .	829
1.127	<code>update all statistics</code> . . . . .	830

1.128	update index statistics. . . . .	834
1.129	update statistics. . . . .	839
	Types of Scans Performed During update statistics. . . . .	846
	update statistics and Sampling. . . . .	847
	create index and Stored Procedures. . . . .	848
	Using Hash-Based Statistics. . . . .	848
1.130	update table statistics. . . . .	848
1.131	use. . . . .	850
1.132	waitfor. . . . .	852
1.133	where Clause. . . . .	855
1.134	while. . . . .	863
1.135	writetext. . . . .	865
<b>2</b>	<b>Interactive SQL Commands. . . . .</b>	<b>869</b>
2.1	clear. . . . .	869
2.2	configure. . . . .	870
2.3	connect. . . . .	870
2.4	disconnect. . . . .	873
2.5	exit. . . . .	874
2.6	input. . . . .	875
2.7	output. . . . .	879
2.8	parameters. . . . .	883
2.9	read. . . . .	884
2.10	set connection. . . . .	886
2.11	start logging. . . . .	887
2.12	stop logging. . . . .	888
2.13	system. . . . .	889

# 1 Commands

SAP Adaptive Server Enterprise commands, clauses, and other elements are used to construct a Transact-SQL statement.

Permission checks for an SAP ASE command may differ based on the granular permissions setting. Check the Permission section for each command for details. See *Using Granular Permissions* in the *Security Administration Guide* for more information on granular permissions.

## 1.1 alter database

Increases the amount of space allocated to a database, as well as to the modified pages section of an archived database. Alters one or more database-wide properties such as data manipulation language (DML) logging level, defaults for compression, in-row large object (LOB) storage, and so on.

### Syntax

```
alter database <database_name>
  [on {default | <database_device>} [= <size>]
    [, <database_device> [= <size>]]...]
  [log on {default | <database_device>} [= <size>]
    [, <database_device> [= <size>]]...]
  [version storage {on <tempdb_name> | off}]
  [imrslog on <database_device> [= <size>] [, ...]]
  [ row storage on <cache_name>]
  row storage on | off [<cache_name>]
  set {[durability = {no_recovery | at_shutdown | full}]
    [[,] dml_logging = {full | minimal}]
    [[,] template = {<database_name> | NULL}]
    [[,] set_latch_free_index = {on | off} [for all tables]]]
  [, [no] async_init]
  [, compression = {none | row | page}]
  [, index_compression = {none | page}]
  [, lob_compression = {<compression_level> | off}]
  [[,] row_caching {on | off} [ for all tables ]]
  [[,] snapshot_isolation { on [ using version storage ] | off } [ for all
tables ]]
  [, inrow_lob_length = <value> [log off <database_device>
  [= size | [from <logical_page_number>] [to <logical_page_number>]]]
  [, <database_device>
  [= size | [from <logical_page_number>] [to <logical_page_number>]]]
  [, set_defer_index_recovery = {[parallel,] [auto | manual | none]]]
    | [with_nodfer_index_recovery]
  [with override]
  [for load]
  [for proxy_update]
```

Encrypts databases:

```
alter database <database_name>
{[encrypt with <key_name> | decrypt [<with key_name>]] [parallel
<degree_of_parallelism>]
| resume [encryption | decryption [parallel <degree_of_parallelism>]]
| suspend [encryption | decryption]
}
```

Shrinks databases:

```
alter database <database_name>
off database_device {=size | [from <page_number>] [to <page_number>]}
[, <database_device>...]
[with time='time']
[with check_only]
```

Syntax for cluster environments:

```
alter database <database_name> {
    [for single instance access] |
    [for clusterwide access]}
```

## Parameters

### <database\_name>

To fully encrypt and decrypt the name of the database. The database name can be a literal, a variable, or a stored procedure parameter.

### on

indicates a size and location for the database extension. If you have your log and data on separate device fragments, use `on` for the data device and `log on` for the log device.

### default

indicates that `alter database` can put the database extension on any default database devices (as shown by the `sp_helpdevice` stored procedure in *Reference Manual: Procedures*). To specify a size for the database extension without specifying the exact location, use:

```
on default = <size>
```

To change a database device's status to default, use `sp_diskdefault`.

### <database\_device>

is the name of the database device on which to locate the database extension. A database can occupy more than one database device with different amounts of space on each. Use `disk init` to add database devices to SAP Adaptive Server Enterprise.

### <size>

is the amount of space to allocate to the database extension. The following are example unit specifiers, using uppercase, lowercase, single and double quotes interchangeably: "k" or "K" (kilobytes), "m" or "M" (megabytes), "g" or "G" (gigabytes), and "t" or "T" (terabytes). You should always include a unit specifier. Quotes are optional if you do not

include a unit specifier. However, you must use quotes if you include a unit specifier. If you do not provide a unit specifier, the value provided is presumed to be in megabytes.

If you do not specify a value, `alter database` extends a database by 1 MB or 4 allocation unit, whichever is larger. Minimum amounts are:

Server's Logical Page Size	Database Extended By
2K	1 MB
4K	1 MB
8K	2 MB
16K	4 MB

#### `log on`

indicates that you want to specify additional space for the database's transaction logs. The `log on` clause uses the same defaults as the `on` clause.

#### `imrslog on`

extends the database on dedicated `imrslog` devices to provide storage space for on-disk row storage. This clause is needed only when a row storage cache is allocated to the database either as part of a current or future `alter` operation.

#### `row storage off` [`<cache_name>`]

disables row or version storage in the current database as an in-memory row storage facility. `<cache_name>` is the name of the row storage cache assigned to this database. Issuing `row storage off` removes version storage if it is enabled on this database.

#### **i** Note

`row storage off` detaches the currently-assigned row storage cache from the database, and makes the memory available as a row storage cache to another database. The now-detached row storage cache is no longer available to the in-memory row storage for any future table DDL operations. Before issuing `row storage off`, you must first alter all tables in the database to not use the in-memory row storage and persist existing data from the in-memory row storage to data page storage. However, the database itself must be enabled for in-memory row storage before issuing the `row storage off` parameter.

#### `row storage on` `<cache_name>`

specifies that the database is configured for the specified row storage cache. `<cache_name>` must be a previously configured cache of type `row_storage`. The row storage cache assigned to the database is available for other tables for row caching or snapshot isolation..

#### `durability`

determines the durability level of the database, and is one of:

- `full` – all transactions are written to disk. This is the default if you do not specify a durability level when you create the database, and ensures full recovery from a server failure. All system databases except `tempdb` use this durability level (the



traditional durability level for disk-resident databases). `tempdb` uses a durability level of `no_recovery`.

- `no_recovery` – transactions are durable only while the server is running. All durability is lost if the server fails or is shut down politely. For disk-resident databases with durability set to `no_recovery`, the SAP ASE server periodically writes data at runtime to the disk devices, but in an uncontrolled manner. After any shutdown (polite, impolite, or server failure and restart) a database created with `no_recovery` is not recovered, but is re-created from the `model` or, if defined, the template database.
- `at_shutdown` – transactions are durable while the server is running and after a polite shutdown. All durability is lost if the server fails.

**`latch_free_index = {on | off} [for all tables]`**

indicates the latch policy of tables in this database.

- `on` – all subsequent tables use latch-free indexes. Setting `latch_free_index` to `on` does not change the latch policy of existing tables and indexes.
- `off` – all subsequent tables use regular indexes. Setting `latch_free_index` to `off` does not change the latch policy of existing tables and indexes.
- `for all tables` – enables or disables latch-free indexes for all existing tables and indexes. It requires the database to be in single-user mode.

The `latch_free_index` option only affects DOL tables. APL tables that are created in a latch-free index-enabled database use regular indexes.

**`[no] async_init`**

Enables or disables asynchronous database initialization.

**`compression`**

indicates the level of compression `alter database` applies to newly created tables in this database.

- `none` – the data is not compressed.
- `row` – compresses one or more data items in an individual row. The SAP ASE server stores data in a `row`-compressed form only if the compressed form saves space compared to an uncompressed form.
- `page` – when the page fills, existing data rows that are `row`-compressed are then compressed using page-level compression to create page-level dictionary, index, and character-encoding entries.  
The SAP ASE server compresses data at the page level only after it has compressed data at the row level, so setting the compression to `page` implies both `page` and `row` compression.

**`index_compression = { none | page }`**

Indicates you are changing the compression level of an for all indexes on the database, where:

- `none` – the index is not compressed
- `page` – the index is compressed at the page level

**`lob_compression = off | <compression_level>`**

Determines the compression level for the newly created table. Selecting `off` means the table does not use LOB compression.

#### `<compression_level>`

table compression level:

- 0 – the lob column is not compressed.
- 1 through 9 – the SAP ASE server uses ZLib compression. Generally, the higher the compression number, the more the SAP ASE server compresses the LOB data, and the greater the ratio between compressed and uncompressed data (that is the greater the amount of space savings, in bytes, for the compressed data versus the size of the uncompressed data).  
However, the amount of compression depends on the LOB content, and the higher the compression level, the more CPU-intensive the process. That is, level 9 provides the highest compression ratio but also the heaviest CPU usage.
- 100 – the SAP ASE server uses FastLZ compression. The compression ratio that uses the least CPU usage; generally used for shorter data.
- 101 – the SAP ASE server uses FastLZ compression. A value of 101 uses slightly more CPU than a value of 100, but uses a better compression ratio than a value of 100.

#### `row_caching on | off [for all tables]`

specifies that the database's in-memory row storage cache is used to cache data rows for inserts, selects and updates for all user tables created in this database. One of:

- `on` – use the in-memory row storage cache to store all data rows for inserts, selects, and updates for all user tables created in this database. High-volume OLTP applications requiring high performance benefit from enabling row caching for hot tables.
- `off` – temporarily disables newly created tables from inheriting the `row_caching` property. Tables created while `row_caching` was enabled retain this configuration.
- `for all tables` – enables or disables the corresponding feature database-wide and applies this property to all existing user tables in the database. `for all tables` requires the table be in single-user mode.

#### `snapshot_isolation { on [ using version storage ] | off }`

determines whether the database uses snapshot isolation level semantics. One of:

- `on` – timestamp-based snapshot isolation level semantics are applied to all user tables created in this database, unless you explicitly override the option when you create a new table.
- `off` – (the default) snapshot isolation-level semantics are not enabled database-wide for newly created tables, even if you created the database with row storage cache.
- `using` – indicates you selecting row or version storage for this database.
- `version storage` – specifies that tables use a temporary database to hold older versions of rows. Cache specified as a database-wide cache to store the row version metadata information is stored in `sysversions` in the version-storage temporary database. Issuing `version storage off` disables version storage and the `imrs_cache` from this database.

#### `inrow_lob_length = <value>`

specifies the number of bytes for an in-row `text` or `image` LOB column, and the number of characters for an in-row `Unitext` LOB column.

**log off <database\_device>**

removes unwanted portions of the log for the database from the specified database device. Using `log off` decreases the amount of space allocated to the log of a database, as well as to the modified pages section of an archive database.

You cannot use `log off` with any other `alter database` parameter, including `log on`, `for load`, or `with override`.

**= <size>**

specifies the amount of space at the end of the device that the command should affect. For this purpose, the end of a device is the highest-numbered logical page used by this database on that device. This command specifies physical storage, removing every log page on the specified device from the database:

```
alter database sales_db log off mylogdev
```

Size specifications round up to fit an exact number of allocation units. In an installation using a 16KB logical page size, you remove 52MB, not 50, because each allocation unit on that server is 4MB. The only time the SAP ASE server removes less space than specified is when the database's log segment uses less than that much space on that device.

**from <logical\_page\_number>**

identifies the first page number affected by this command. The SAP ASE server automatically adjusts the number to indicate the allocation page's page ID. The default `from` location is the lowest numbered logical page on the device.

**to <logical\_page\_number>**

identifies the last page affected by the command. Only complete allocation units (multiples of 256 pages) can be removed, so the SAP ASE server automatically adjusts the page number upwards to the last page in the allocation unit. If `<logical_page_number>` is the exact page number of an allocation page (that is, it is divisible by 256), that allocation unit is unaffected. For example, `to 512` affects pages up to but not including page 512.

The default `to` location is the highest-numbered logical page on the device.

**dml\_logging {minimal | default}**

indicates the level of logging for `insert`, `update`, and `delete` commands. `full` (the default) records all changes to the log for a complete record of all transactions. If the database uses `minimal logging`, the SAP ASE server attempts to not log row or page changes to `syslogs`. However, the SAP ASE server may generate some in-memory logging activity to support run-time operations such as rolling back transactions.

**template**

determines the template the database uses. One of:

- `<database_name>` – user database that is disk-resident at full durability, and in a usable state.
- `NULL` – removes the binding to the current template database. The database uses `model` as its template database during subsequent server restarts.

**with override**

forces the SAP ASE server to accept your device specifications, even if they mix data and transaction logs on the same device, thereby endangering up-to-the-minute recoverability for your database. If you attempt to mix log and data on the same device without using this clause, the `alter database` command fails. If you mix log and data, and use `with override`, you are warned, but the command succeeds.

**for load**

is used only after `create database for load`, when you must re-create the space allocations and segment usage of the database being loaded from a dump.

**for proxy\_update**

forces the resynchronization of proxy tables within the proxy database.

**encrypt with <key\_name>**

instructs SAP ASE to fully encrypt the database. Specifically, the command retrieves the corresponding key ID from the `sysencryptkeys` system table in the master database and set the `enckeyid` column in its related `sysdatabases` row.

<key\_name> is the database encryption key you used to encrypt the database. If you do specify a different key name, the command fails and SAP ASE displays an error message.

SAP ASE fails to run `alter database` and displays an error message if the database is already:

- Encrypted with another key.
- Being encrypted.

If you run this command on a partially encrypted database that is not currently being encrypted, SAP ASE treats the command as if you specified the `resume encryption` option, as long as the key name is the same as the previously specified key.

**decrypt [with <key\_name>]**

instructs SAP ASE to decrypt the database. When decrypting a database, [with <key\_name>] is optional, as SAP ASE looks up the key ID in the `sysdatabases` system table. The command fails, however, if you specify <key\_name> with a different key name than what was used to encrypt the database.

**resume decryption**

instructs SAP ASE to resume the decryption process for the database in which an earlier decryption process was suspended. SAP ASE ignores this command if the <database\_name> is already completely decrypted.

**parallel <degree\_of\_parallelism>**

determines how many worker threads to initiate for the task. Create a thread for each database storage virtual device, as long as the number is equal to or fewer than "number of worker processes" configuration. The <degree\_of\_parallelism> number should be no larger than the number of database devices because additional worker threads do not improve encryption performance. If you do not specify <degree\_of\_parallelism>, SAP ASE internally defines the value based on the number of online engines, as well as how the database is distributed across various devices.

### **resume encryption**

resumes the encryption process from the page where encryption was previously suspended. The command fails if:

- There is an encryption process already running in SAP ASE.
- Encryption was never started on the database.
- The encryption process already completed.

You can use `parallel <degree_of_parallelism>` with `resume encrypt`. If you do not specify `parallel <degree_of_parallelism>`, SAP ASE determines the value based on how the database is distributed across various engines.

### **suspend encryption**

terminates all encryption worker threads that are encrypting data. SAP ASE records the progress of encryption so that `resume encryption` can restart encryption where the previous encryption process stopped. SAP ASE ignores this command if there is no encryption in progress.

### **off**

specifies the device from which you are releasing space for shrinking databases.

The following scenarios need the database to be in single-user mode when you shrink a database:

- Moving the logical pages 0–255 of a database to another device.
- Partially moving a fragment (represented by an entry in `sysusages`).

The `off` clause includes:

- `<database_device>` – is the name of the database device on which to locate the database extension. A database can occupy more than one database device with different amounts of space on each device.  
`<database_device>` includes either the `=<size>` parameter or the `from` or `to` parameters (not both). The default `from` page is 0 (zero). If you do not specify any modifiers with the `from` clause, SAP ASE releases all storage for this database on the indicated device.
- `<size>` – specifies the amount of space to be released from the database. `alter database` accepts a specific size, or a `from ... to` declaration:
  - Specific size – an integer. If you do not include a unit specifier, SAP ASE uses megabytes as the unit. You can also include "k" or "K" (kilobytes), "m" or "M" (megabytes), "g" or "G" (gigabytes), and "t" or "T" (terabytes). SAP ASE recommends that you always include a unit specifier. Quotes are optional if you do not include a unit specifier. However, you must use quotes if you include a unit specifier. If you do not provide a unit specifier, the value provided is presumed to be in megabytes. For example:
    - `alter database ... off mydev1 = 200` – removes 200 megabytes
    - `alter database ... off mydev1 = '2g'` – removes 2 gigabytes
  - `from ... to` declaration – unsigned integers. See below.

SAP ASE releases the highest-numbered logical pages of this database associated with the indicated device. SAP ASE rounds the value for `<size>` up, if needed, to indicate an even number of allocation units.

If you specify more space than is currently in use by this database on the indicated device, SAP ASE limits the specified size or page IDs to the amount of space available.

- `from <page_number>` – specifies the low end of the range of logical pages to be released. SAP ASE rounds the `from` value down, if needed, to represent the first page of the allocation unit containing the indicated page. The default value for `from` is 0 (zero).
- `to <page_number>` – specifies the high end of the range of logical pages to be released. SAP ASE rounds the `to` value up, if necessary, to represent the last page of the allocation unit containing the indicated page. The default value for `to` is the highest-numbered logical page in the database. However, if the `to` page is an allocation page itself (which is the starting page of an allocation unit) and is not the same as the `from` page, the `alter database ... off` command does not affect the allocation unit containing the specified `to` page. SAP ASE assumes that a user requesting a precise page range does not intend to affect the specified end page, so it decrements the end page rather than increasing it.

### Note

SAP ASE does not issue an error message if you indicate a `from` page value that is greater than the `to` page value. Instead, SAP ASE swaps the `from` and `to` values before applying the rounding logic.

- `with check_only` – checks for:
  - The expected results of shrinking the database rather than actually shrinking the database.
  - Tables with text columns that are not marked as having text back-linked to their owning rows. All text and image columns are required to have back-linked pointers to the home data row in the first text page.
  - Sufficient room in the remainder of the database to accommodate everything that must be moved. Any indication of a potential problem is reported.
  - And reports any potential problems where a significant amount of time could be spent sorting the index

When checking the indexes, if the results indicate that there could be enough duplicate key entries that the command will spend a significant amount of time sorting the index, the index is reported as a problem. The recommendation is that the index should be dropped before shrinking the database and the index be re-created after the database is shrunk.

Results of the checks being done by `with check_only` can be compromised by any other work being performed on in the database while the checks are running, or by work that was done after the checks are run but before the actual shrink is completed.

- `with time=<time>` – specifies the maximum length of time `alter database ... off` may run, and is specified as hours, minutes, and seconds (`<HH:MM:SS>`). If you do not include the full specification, `alter database` interprets the missing sections for `<time>` as:
  - `<XX:YY>` is interpreted as `<MM:SS>`.
  - `<XX>` is interpreted as minutes.

- Empty sections are treated as zero. For example, `alter database` interprets both `"::30"` and `":30"` as 30 seconds. However, `alter database` interprets `"1::"` as 1 hour, and `"2:"` as 2 minutes.

If `alter database ... off` does not finish within the specified period of time, work in progress is abandoned, and the command exits with an error message. Any completed work remains done.

### **i** Note

Use either `alter database off` or `alter database log off` to shrink the log segment. Both commands perform the same function.

#### **with nodefer\_index\_recovery**

indicates that you are removing the `defer_index_recovery` setting from the database.

#### **set defer\_index\_recovery**

enables you to defer the recovery of the index during load transaction recovery. Deferred recovery indexes are useful for (but not restricted to) queries that create indexes but don't need to retain the indexes. That is, the application needs only a temporary index and not a permanent index.

- `parallel` – defers recovery if the index was created in parallel. If you do not include the `parallel` parameter, SAP ASE defers the index recovery regardless of whether a serial or a parallel sort was used at run-time.
- `auto` – the index is re-created automatically during `online database` using the metadata in the system tables.
- `manual` – the index can be re-created manually any time after issuing `online database`. SAP ASE includes a warning in the error log saying that the index creation is deferred and must be created manually. Deferred recovery indexes are marked as suspect, ensuring that the optimizer does use them in any ad-hoc queries, and that stored procedures containing references to the index as part of the query tree are recompiled.
- `none` – `online database` removes the metadata for the index, dropping the index entirely. SAP ASE includes this as an informational message in the error log.

You cannot use deferred recovery indexes on:

- System tables
- System databases
- Clustered indexes

Additionally, SCC does not support re-creating and managing deferred recovery indexes

#### **for single instance access**

converts a regular cluster database to a single-instance database.

#### **for clusterwide access**

converts a single-instance database to a regular cluster database.

## Examples

### Add 3 MB to Database

Adds 3MB (1,536 pages) to a user database configured for 2K logical pages on a default database device:

```
alter database mydb
```

### Add 3 MB to Database on Device

Adds 3MB to the space allocated for the `pubs2` database on the database device named `newdata`:

```
alter database pubs2 on newdata = 3
```

### Add 10 MB for Data and 2 MB for Log

Adds 10MB of space for data on `userdata1` and 2MB for the log on `logdev` for a server configured for 2K logical pages:

```
alter database production
on userdata1 = "10M"
log on logdev = '2.5m'
```

### Change Durability Level

Changes the durability level of `pubs5_rddb`, a relaxed-durability database to change it to a regular database with full durability:

```
alter database pubs5_rddb
set durability = full
```

### Change Template

Alters the template for the `pubs3` database:

```
alter database pubs3
set template = new_pubs_template_db
```

### Change Durability Level of Disk-Resident Database

Changes the durability level of a disk-resident database with relaxed durability:

```
alter database pubs7 set durability=at_shutdown
```

### Change DML Logging Level

Changes the DML logging level for the `model` database, which is set to a durability level of full. Any databases created from `model` after this change inherit the minimal logging level property:

```
alter database model set dml_logging = minimal
```

### Alter Database to Use Row Storage Cache

Alter the `production` database to allocate space for the `imrslogsegment` on-disk row storage and enable the `prod_row_cache` row storage cache:

1. Create the `prod_odrs_dev1` and `prod_odrs_dev2` devices for the on-disk row storage:

```
disk init name = "prod_odrs_dev1",
physname = "/usr/u/SAP/BTrim/devices/prod_odrs_dev1.dat",
size = "200g",
type = imrslog
```



```
disk init name = "prod_odrs_dev2",
physname = "/usr/u/SAP/BTrim/devices/prod_odrs_dev2.dat",
size = "100g",
type = imrslog
```

2. Extend the `production` database to use the new devices:

```
alter database production
imrslog on prod_odrs_dev1 = "200g", prod_odrs_dev2 = "100g"
```

3. Create a named cache of type `row storage`, required for IMRS:

```
sp_cacheconfig "prod_row_cache", "50g", row_storage
```

4. Alter the `production` database to use the row storage cache and the newly created row storage cache as the in-memory row storage:

```
alter database production
row storage on prod_row_cache
```

### Disable Row-Storage Cache

Temporarily disabling the row-storage cache as the database-wide cache allows you to create new tables that do not use the row storage cache. This example enables the `new_orders_priv_customers` table to use the `prod_row_cache` row storage cache for high performance access while managing new orders for privileged customers:

```
alter database production set row_caching off
create table new_orders (...) lock datarows
alter database production set row_caching on
create table new_orders_priv_customers
...
lock datarows
```

### Remove Row Storage Cache

This example removes row storage and the `imrslog` from the `production` database (requires multiple commands):

```
alter database production row_storage off
go
alter database production
off prod_odrs_dev1, prod_odrs_dev2
go
```

You can enable row storage and the `imrslog` in a single command.

### Change Compression Level

This example changes `pubs2` database to page-level compression:

```
alter database pubs2
set compression = page
```

### Changes the Compression Level for All Indexes

Changes the `pubs2` database to use page-level compression:

```
alter database pubs2 set index_compression = page
```

### Change Database to LOB Compression

This example changes the `pubs2` database to use LOB compression:

```
alter database pubs2 set lob_compression = 100
```

### Modify Length of In-Row LOB Columns in Database

This example modifies the `pubs` database to change the length of its in-row LOB columns to 400 bytes:

```
alter database pubs
  set inrow_lob_length = 400
```

### Removes 50 MB of Database from Device

This example removes 50 MB of database `sales_db` from device `mylogdev`:

```
alter database sales_db log off mylogdev='50M'
```

This example removes the highest-numbered logical pages of `sales_db` that are on `mylogdev`, up to a maximum of 50MB.

### Specifies Pages to Remove

Removes space for database `sales_db` from device `mylogdev`, specifying exactly which pages are to be removed:

```
alter database sales_db log off mylogdev from 7168 to
  15360
```

Because logical page 15360 is an allocation page, this example affects all logical pages on `mydev` from 7168 through 15359. It does not, however, affect page 15360, nor does it affect any pages in the named range that are not physically located on `mylogdev`.

### Encrypt an Existing Database

This example alters an existing database called `existdb` for encryption using an encryption key called `dbkey`:

```
alter database existdb encrypt with dbkey
```

The example does not specify the parallel degree, leaving it up to SAP ASE to determine how many worker threads should be initiated to encrypt `existdb` in parallel.

### Suspend an Encryption of a Database

This example suspends an encryption operation on a database called `existdb`:

```
alter database existdb suspend encryption
```

### Resume Encrypting a Database

This example resumes a suspended encryption on a database called `existdb`:

```
alter database existdb resume encryption
```

### Defer Index Recovery

This example alters the `big_db` database to defer index recovery if the index was created in parallel:

```
alter database testdb set defer_index_recovery = parallel
```

### Remove Deferred Index Recovery

This example alters the "big\_db" database to no longer use deferred index recovery:

```
alter database testdb with nodefer_index_recovery
```

### Convert to a Single-instance Database

(Cluster Edition only) This example converts a regular cluster database called `tech` to a single-instance database:

```
alter database tech for single instance access
```

### Convert to a Regular Cluster Database

(Cluster Edition only) This example converts a single-instance database called `tech` to a regular database:

```
alter database tech for clusterwide access
```

### Add Version Storage to pubs2

This example alters the `pubs2` database for row storage on the `pubs2_row_cache`, enables snapshot isolation, and uses version storage:

```
alter database pubs2
row storage on pubs2_row_cache
set snapshot isolation on
using version storage
```

### Add Version Storage to pubs2\_temp Temporary Database

This example alters the `pubs2` database for version storage on the `pubs2_temp` temporary database:

```
alter database pubs2
version storage on pubs2_temp
set snapshot isolation on
using version storage
```

### Remove Version Storage from pubs2

This example removes the version storage for the `pubs2` database:

```
alter database pubs2
version storage off
```

### Change the Database's Latch Policy

This example alters the `pubs3` database to use latch-free indexes on new and existing tables and indexes:

```
alter database pubs3 set latch_free_index = on for all tables
```

## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

## Permissions

The permission checks for `alter database` differ based on your granular permissions settings.

Setting	Description
---------	-------------

<b>Enabled</b>	With granular permissions enabled, for <code>sybsecurity</code> , you must be the database owner or have any of these privileges:
----------------	---

`own database (on sybsecurity)` or `manage auditing`.

For all other databases, you must be database owner or have the `own database` privilege (on the database).

<b>Disabled</b>	With granular permissions disabled, you must be the database owner, a user with <code>sa_role</code> , or a user with <code>sso_role</code> (for <code>sybsecurity</code> ).
-----------------	--

## Auditing

You can enable `alter auditing` option to audit this command. Values in `event` and `extrainfo` columns from the `sysaudits` table are:

Information	Value
Audit option	<code>alter</code>
Event	2
Command or access audited	<code>alter database</code>
Information in <code>extrainfo</code>	<ul style="list-style-type: none"><li>• <b>Roles</b> – current active roles</li><li>• <b>Full command text</b> – full text of <code>alter database</code> command</li><li>• <b>Previous value</b> – NULL</li><li>• <b>Current value</b> – NULL</li><li>• <b>Other information</b> – NULL</li><li>• <b>Proxy information</b> – original login name, if <code>set proxy</code> is in effect</li></ul>

Full command text is included in `extrainfo` column. For example:

```
sa_role sso_role oper_role sybase_ts_role mon_role;  
alter database pubs2 on newdata = 3; ; ; ; sa/ase;
```

For more information about auditing, see *Security Administration Guide > Auditing*.

## Related Information

[create database \[page 140\]](#)

[disk init \[page 401\]](#)

[drop database \[page 429\]](#)

[load database \[page 585\]](#)

## 1.1.1 alter database Restrictions

Additional considerations for `alter database`.

Restrictions for using `alter database` are:

- Quotes are optional if you do not include a unit specifier. However, you must use quotes if you include a unit specifier.
- The maximum number of devices a database can use is 1269. `alter database` fails if you attempt to exceed this amount.
- The SAP ASE server reports an error if the total size of all fixed-length columns, plus the row overhead, is greater than the table's locking scheme and page size allows.
- The SAP ASE server allocates space for databases for `create database` and `alter database` rounding down the specified size to the nearest whole megabyte multiple of allocation units.
- You can specify the `<size>` as a `float` datatype, but it is rounded down to the nearest whole value. For example, if you specify a size of 3.75G, it is rounded down to 3G.
- Although the SAP ASE server does create tables in the following circumstances, you see errors about size limitations when you perform data manipulation language operations:
  - If the length of a single variable-length column exceeds the maximum column size.
  - For data-only locked tables, if the offset of any variable-length column other than the initial column exceeds the limit of 8191 bytes.
- If the SAP ASE server cannot allocate the requested space, it comes as close as possible per device and prints a message telling how much space has been allocated on each database device.
- You must be using the `master` database, or executing a stored procedure in the `master` database, to use `alter database`.
- You can expand the `master` database only on the master device. An attempt to use `alter database` to expand the `master` database to any other database device results in an error message. For example, use:

```
alter database master on master = 1
```

- Each time you allocate space on a database device with `create database` or `alter database`, that allocation represents a device fragment, and the allocation is entered as a row in `sysusages`.
- If you use `alter database` on a database that is being dumped, `alter database` cannot complete until the dump finishes. The SAP ASE server locks the in-memory map of database space use during a dump. If you issue `alter database` while this in-memory map is locked, the SAP ASE server updates the map from the disk after the dump completes. If you interrupt `alter database`, the SAP ASE server instructs you to run `sp_dbremap`. If you do not run `sp_dbremap`, the space you added does not become available to the SAP ASE server until you restart the server.
- You can use `alter database on database_device` on an offline database.

Restrictions for single-instance databases:

- The logical cluster must be a single instance logical cluster to change a database to a single-instance database.
- This single instance logical cluster must exist before issuing `alter database ... for single instance access`.

- After issuing `alter database ... for single instance access`, the database undergoes the following steps:
  1. Issue checkpoint.
  2. Drain logins (similar as in case of `quiesce db` or when issuing a polite shutdown).
  3. Shut down the database. Wait for user to add logical cluster association.
  4. Send a message to the base instance of the logical cluster to open `dbtable` and open up database for normal work in the cluster (or rather perform a routine similar to `dbs_dbrestart()` called for `DBCC DBREBOOT`)
  5. Recovery is minimal in case of polite shutdown of the database.
- `alter database ... to cluster database` converts the single instance database to a regular cluster database and removes the corresponding logical cluster associations.
- `alter database ... to cluster database` does not delete or drop the associated single-instance logical cluster or single-instance database.
- The database undergoes the following steps:
  1. Issue checkpoint.
  2. Drain logins (similar as in case of `quiesce db` or when issuing a polite shutdown).
  3. Remove logical cluster association.
  4. Shutdown database.
  5. Send a message to all the instances to open `dbtable` and open up database for normal work in the cluster.

See also `sp_addsegment`, `sp_dropsegment`, `sp_helpdb`, `sp_helpsegment`, `sp_logsdevice`, `sp_renamedb`, `sp_spaceused` in *Reference Manual: Procedures*.

## 1.1.2 Using alter database for Archive Databases

You can use `alter database` to add space to the modified pages section of an archive database at any time, not only when space runs out.

Increasing the space in the modified pages section allows a suspended command to resume operation. The syntax is:

```
alter database <database_name>
  [ on <database_device> [= <size>]
    [, <database_device> [= <size>]]...]
```

## 1.1.3 Altering In-Memory and Relaxed Durability Databases

Keep these in mind when using `alter database` for in-memory and relaxed-durability databases.

- You cannot set specify `model`, `master` or `sysystemdb` as the template database.
- Setting the database name in the `use template` clause to `NULL` removes the binding to any existing template database, and defines `model` as the template database.

- Altering the template definition of a database that appears earlier in the database recovery order sequence than its template database automatically reorders the recovery order so the new template database appears prior to its dependent database in the database recovery order when you restart the server.
- If you change the settings for `durability` or `dml_logging`, `alter database` automatically attempts to set the databases to single-user mode before executing the command. You can manually set the database to single-user mode before you issue `alter table`.
- Databases must be in single-user mode before you can change the durability level setting.
- You can increase the size of an in-memory database only on in-memory storage caches that already host the in-memory database.
- You cannot change the durability level of system, template, or local temporary databases.
- The load sequence is broken when you change the durability level of the database to `full`. For example, for a disk-resident database using full durability, if you:
  1. Dump a database.
  2. Perform a `dump transaction`.
  3. Perform a second `dump transaction`.
  4. Changed the durability to `no_recovery`.
  5. Changed the durability to `full`.
 You cannot perform a third `dump transaction`. Instead, you must perform a full `dump database`.

## 1.1.4 Altering Databases for In-Memory Row Storage

Altering databases for in-memory row storage includes some restrictions.

- You can alter a database to use a row storage cache—and use `imrsllog` devices to create the on-disk row store—that are:
  - User created databases
  - In single-user mode
  - Non-temporary
  - Disk-resident databases
  - Full durability
- Row storage caches are dedicated to a single database and cannot be shared across databases.
- The on-disk row storage must have sufficient space (either existing, or as part of the `alter database` command) on the `imrsllog` devices on which the database is being altered.
- When you issue `alter database` on devices of type `imrsllog`, the definition for `imrsllogsegment` is added to `syssegments` in that database. An unused segment ID starting from 31, searching downwards, is assigned to `imrsllogsegment`. If all segment IDs are in use, the database creation fails.
- You can combine the `row storage on` and `imrsllog on` clauses in a single command. However, you cannot issue the `row storage on` clause before creating the on-disk row store. The `row storage off` clause must be an exclusive command. That is, it cannot be combined with other clauses of the `alter database` command, such as `off`, `with`, and `so on`.
- You can use the `set row_caching` or `set snapshot_isolation` clauses on databases that were previously created or altered to use a row storage cache.
- You can combine the `alter database row storage on cache` subclause with other `alter database` subclauses that extend the database to use more physical space. However, you cannot combine these `row`

`storage on` subclause with the commands to shrink the database. SAP recommends that the row storage related subclauses be issued in separate commands.

- Use the `off <database_device>` parameter to shrink the database from all devices of type `imrslog`, and to eventually remove the on-disk row storage completely. You can remove the on-disk row storage once the allocated row storage is detached from the database using the `row storage off` clause. However, even after you drop the on-disk row storage from the database, the definitions for the `imrslogsegment` and the `sysimrslogs` system tables are retained, with a value of 0 page IDs for `sysimrslogs`, in case you decide to reactivate the in-memory row storage.
- Once you alter a database for snapshot isolation, all tables created in the database inherit the snapshot isolation property set. Use the `create table` or `alter table` commands to create or alter tables that use different snapshot isolation property than the database level option.

**Restrictions.** You cannot:

- Enable a database for both `imrslog` and version storage.
- Use the `for all tables` parameter to enable or disable snapshot isolation for existing tables in a database.
- Reduce the capacity of the row storage clause by specifying a smaller value for `<number> rows` if the cache already holds more rows than the value of `<number>`.
- Combine `alter database ... row storage off <cache_name>` with any other subcommands.

## 1.1.5 Backing Up master After Allocating More Space

Back up the `master` database with `dump database` after each use of `alter database`. This makes recovery easier and safer in case `master` becomes damaged.

If you use `alter database` and do not back up `master`, you may be able to recover the changes with `disk refit`.

## 1.1.6 Placing the Log on a Separate Device

To increase the amount of storage space allocated for the transaction log when you have used the `log on` extension to `create database`, include the name of the log's device in the `log on` clause when you issue `alter database`.

If you did not use the `log on` extension of `create database` to place your logs on a separate device, you may not be able to recover fully in case of a hard disk failure. In this case, you can extend your logs by using `alter database` with the `log on` clause, then using `sp_logdevice` to move the log to its own devices.



## 1.1.7 Altering Databases for Compression

`set compression` specifies the database-wide compression level, which applies only to newly created tables.

You can use `set lob_compression` by itself or with other `set` subclauses. However, other `set` subclauses require the database to be in single-user mode (for example, if you change the durability level of the database).

## 1.1.8 In-row LOB Columns

Use `inrow_lob_length` to increase or decrease the in-row LOB length database-wide.

The SAP ASE server uses in-row LOB compression if:

- The table is implicitly or explicitly row- or page-compressed, and,
- Any of the in-row large object columns in the table are implicitly or explicitly LOB compressed.

Changing the `inrow_lob_length` affects the creation of LOB columns in future `create table` or `alter table add column` commands. The valid values are within the range of 0 to the logical page size of the database.

## 1.1.9 Shrinking Log Space

Information about the `log off` variant of `alter database`.

- Although the `log off` option specifies the range of pages to be removed as logical pages, it is the associated physical pages that are actually removed. The logical pages remain in the database as unusable since they form a hole. A hole is one or more allocation units for which there is no associated physical storage.
- Information about which allocation units—space that is divided into units of 256 data pages when you create a database or add space to a database—exist on the devices that are available in the `master.dbo.sysusages` table, which lists disk pieces by database ID, starting logical page number, size in logical pages, device ID, and starting offset in the device.
- If the specified `to` page is less than the `from` page, the pages are switched—that is, the `to` page becomes the `from` page, and vice versa. If `from` and `to` name the same page, the command affects only the allocation unit containing that page. The command does not adjust the `to` page in a way that causes a command error.
- The entire device is affected if you do not provide any clauses. This is equivalent to `log off<device> from 0`. This command specifies physical storage, removing every log page on the specified device from the database:

```
alter database sales_db log off mylogdev
```

- If `alter database` detects an error, it does not execute, and returns a message indicating the reason, such as:
  - The database log becomes too small.
  - The fragments to be removed contain pages that are allocated to `syslogs`. That is, the active log occupies space in the log fragments to be removed.

- The amount of log free space after the fragment is removed is too small to accommodate the last chance threshold.

## 1.1.10 Getting Help on Space Usage

To see the names, sizes, and usage of device fragments already in use by a database, execute `sp_helpdb <dbname>`. To see how much space the current database is using, execute `sp_spaceused`.

## 1.1.11 The system and default Segments

The `system` and `default` segments are mapped to each new database device included in the `on` clause of an `alter database` command. To unmap these segments, use `sp_dropsegment`.

When you use `alter database` (without `override`) to extend a database on a device already in use by that database, the segments mapped to that device are also extended. If you use the `override` clause, all device fragments named in the `on` clause become system/default segments, and all device fragments named in the `log on` clause become log segments.

## 1.1.12 Using alter database to Awaken Sleeping Processes

If user processes are suspended because they have reached a last-chance threshold on a log segment, use `alter database` to add space to the log segment. The processes awaken when the amount of free space exceeds the last-chance threshold.

## 1.1.13 Using the alter database for proxy\_update Parameter

If you enter the `for proxy_update` clause with no other options, `alter database` does not extend the size of the database; instead, the proxy tables, if any, are dropped from the proxy database and re-created from the metadata obtained from the path name specified during `create database ... with default_location = 'pathname'`.

If you use `alter database` with other options to extend the size of the database, the proxy table synchronization is performed after the size extensions are made.

`for proxy_update` provides the database administrator with an easy-to-use, single-step operation with which to obtain an accurate and up-to-date proxy representation of all tables at a single remote site.

Resynchronization is supported for all external data sources, not just the primary server in a high availability-cluster environment. Also, a database need not have been created with the `for proxy_update` clause. If a default storage location has been specified, either through `create database` or with `sp_defaultloc`, the metadata contained within the database can be synchronized with the metadata at the remote storage location.

To make sure databases are synchronized correctly so that all the proxy tables have the correct schema to the content of the primary database you just reloaded, you may need to run the `for proxy_update` clause on the server hosting the proxy database.

## 1.1.14 Fully Encrypting Databases

Considerations when encrypting or decrypting databases.

- Database encryption occurs while the database is running. This means the database is accessible by other users while it is being encrypted; you need not put it into single-user mode.
- The encryption process does not interrupt user queries, updates, or insert operations on the database.
- You can suspend and resume database encryption, so that you can resume encrypting the database after restarting SAP ASE.
- The encryption operation is not transactional.
- You can alter both archive and temporary databases for encryption and decryption.
- SAP ASE records the encryption progress of a database and provides utilities to report its status.

The command fails if:

- You use it on a database that is already encrypted.
- You use it on a database that is being encrypted. If you use this command on a partially encrypted database, but there is no encryption process running in SAP ASE, the command resumes encryption from the location where it was last suspended as long as you use the same database encryption key name in your previous command to encrypt the database.

Restrictions:

- You cannot encrypt the `master` and `model` databases.
- You cannot decrypt a database that is being encrypted, or encrypt a database that is being decrypted.
- You cannot drop or unmount a database when it is being encrypted.
- You cannot load another database on top of a database that is being encrypted.
- You cannot back up (dump) a database while a database is being encrypted.

## 1.2 alter encryption key

Changes the current password, adds and drops a key copy, and regenerates an encryption key.

The sections that describe this command are:

- [Syntax \[page 36\]](#)
- [Parameters \[page 38\]](#)
- [Examples \[page 38\]](#)
- [Usage \[page 41\]](#)
- [Permissions \[page 42\]](#)
- [Auditing \[page 43\]](#)

## Syntax

Alters the master key:

```
alter encryption key [dual] master
  with char_string {add encryption
    {with passwd <char_string> for user <user_name> [for recovery]
    | for automatic_startup}
  | modify encryption {with passwd <char_string> [for recovery]
    | for automatic_startup}
  | drop encryption
    {for user <user_name> | for recovery | for automatic_startup}
  | regenerate key
    [with passwd <char_string>] | recovery encryption
    with passwd <char_string> | modify owner <user_name>}
```

Alters between a user password and an external HSM key to encrypt the master key:

```
alter encryption key master
  with {passwd <char_string> | external key}
  {modify encryption {with {passwd <char_string> | external key}}
  | regenerate key
  | modify owner <user_name>
  }
```

Alters the syb\_extpasswdkey service key:

```
alter encryption key syb_extpasswdkey
  [with {static key | master key}]
  {regenerate key [with {static key | master key}]
  | modify encryption [with {static key | master key}]}
```

Alters the column encryption key:

```
alter encryption key [[<database>.]<owner>.] <keyname>
  {[as | not default]
  [dual] master
  [with {static key | master key}]
  regenerate key
  [with {static key | master key [no] dual_control}] | [with passwd
  '<password>' | <system_encr_passwd> | <login_passwd> |
  '<base_key_password>']
  modify encryption
  [with {passwd {'password' | system_encr_passwd | login_passwd} | master
  key}]
  [[no] dual_control] for automatic startup
  add encryption [with passwd '<password>' | '<key_copy_password>']
  for user <user_name>
  [for [<login_aassociation> | recovery | automatic_startup]]
  drop encryption for {user <user_name> | recovery
  [for recovery] | [for automatic_startup]}
  | [with passwd '<password>']
  recover encryption with passwd '<password>'
  | modify owner <user_name>}
```

## Parameters

<keyname>

is the name for a column encryption key.

**as [not] default**

indicates that the database default property should be assigned to, or unassigned from, this key.

**[dual] master**

specifies the database-level keys used to encrypt other keys within the database in which they are defined. These keys are not used to encrypt data.

**static key | master key**

The first instance of the `with {static key | master key}` clause asserts how the `syb_extpasswdkey` is currently encrypted. Because the SAP ASE server knows how `syb_extpasswdkey` is currently encrypted, this clause is optional.

The second instance of `with {static key | master key}` clause following the `regenerate key` action allows the administrator to change the encryption on the regenerated key from static to dynamic, or vice versa. If the clause is omitted, the regenerated key is encrypted as it was prior to this command being issued.

The third instance of `with {static key | master key}` clause following the `modify encryption` action changes the protection on the existing key to use the static key or the master key as specified. If the clause is omitted, the static key is used by default.

**[no] dual\_control**

indicates whether dual control is used to create the master key.

**regenerate key**

indicates that you are regenerating the key

**with passwd ['<password>' | <system\_encr\_passwd> | <login\_password >  
'<base\_key\_password>']**

specifies the current password the SAP ASE server uses to decrypt the column encryption key, and a new password for one of the following purposes:

- Modify the encryption of a key or a key copy.
- Encrypt a newly added key copy. The key owner can add key copies for individual users that are accessible through a private password or a login password.
- Recover the encryption key after losing a password.

The SAP ASE server supports the following passwords for keys:

- `<password>` – a character string up to 255 bytes long.
- `<login_passwd>` – tells the SAP ASE server to use the session's login password.
- `<system_encr_passwd>` – system encryption password for the current database.
- `'<base_key_password>'` – the password used to encrypt the base key, and may be known only by the key custodian. The password can be up to 255 bytes long. The SAP ASE server uses the first password to decrypt the base column-encryption key.

If you do not specify `with passwd`, the default is `<system_encr_passwd>`.

**modify encryption**

indicates that you are modifying the encryption key or key copy.

**for automatic startup**

indicates that the key copy is to be used to access the master or dual master key after the server is restarted with automatic master key access enabled.

**add encryption**

adds an encrypted key copy for a designated user.

`<key_copy_password>` – the password used to encrypt the key copy. The password cannot be longer than 255 bytes. The SAP ASE server makes a copy of the decrypted base key, encrypts it with a key encryption key derived from the `<key_copy_password>`, and saves the encrypted base key copy as a new row in `sysencryptkeys`.

**for user <user\_name>**

specifies the user for whom you are adding or dropping a key copy.

**for login\_association**

indicates that the key copy being added later becomes encrypted by the assigned user's login password during that user's first access to this key.

**for recovery**

indicates that the key copy is to be used to recover the master key in case the password is lost.

**drop encryption**

indicates that you are dropping the key copy for the specified user.

**recover encryption**

makes the base key accessible through a new password. Does not apply to key copies.

**modify owner**

changes the key's owner to the specified user.

**external key**

assigns the use of an external Hardware Security Module (HSM) key to encrypt the existing master key. To assign the user password instead, use `passwd <char_string>`.

## Examples

### Example 1

Changes `my_key` to the default encryption key:

```
alter encryption key my_key as default
```

You must have the `sso_role` or `keycustodian_role` to change the default property of a key. If the command above is executed by:

- The system security officer (SSO), the SAP ASE server removes the default property unconditionally from the previous default key, if one exists.
- The key custodian, that key custodian must own `my_key`. The key custodian must own the previous default key, if one exists.

To remove the default property from `my_key`, the SSO or the key custodian, as owner of the key, executes:

```
alter encryption key my_key as not default
```

If `my_key` is not the default key, this command returns an error.

### Example 2

Changes the password on the `important_key` encryption key:

```
alter encryption key important_key
  with passwd 'oldpassword'
  modify encryption
  with passwd 'newpassword'
```

If this command is executed by:

- The key owner – the command reencrypts the base key
- The user assigned a key copy – the command reencrypts that key copy.

### Example 3

Changes the password on a key copy to the current session's login password (can be executed only by a user who has been assigned a key copy):

```
alter encryption key important_key
  modify encryption
  with passwd login_passwd
```

You can encrypt only key copies with a login password. the SAP ASE server returns an error if you attempt to encrypt the base key with a login password.

### Example 4

Changes the password for the `important_key` encryption key to the system password:

```
alter encryption key important_key
  with passwd 'ReallyBigSecret'
  modify encryption with passwd system_encr_passwd
```

Only the key owner or a user with `sso_role` can execute this command and if a key has no key copies. (Base keys with copies must be encrypted by a user-specified password.) This example modifies the encryption of the base key.

### Example 5

Changes the password for the `important_key` encryption key from the system encryption password to a new password. Because the system encryption password is the default password, it need not be specified in the statement:

```
alter encryption key important_key
  modify encryption
  with passwd 'ReallyNewPassword'
```

### Example 6

Adds encryption for user “ted” for the `important_key` encryption key with the password “just4now”:

```
alter encryption key important_key
  with passwd 'TopSecret'
  add encryption with passwd 'just4now'
```

```
for user 'ted'
```

Only a key owner or a user with the `sso_role` can execute this command. The SAP ASE server uses “TopSecret” to decrypt the base key, making a copy of the raw key and encrypting it for Ted using the password “just4now.”

#### Example 7

Modifies the encryption for Ted to use a new password. Only Ted can execute this command:

```
alter encryption key important_key
with passwd 'just4now'
modify encryption
with passwd 'TedsOwnPassword'
```

#### Example 8

Drops encryption for user “ted” for the `important_key` encryption key (only the `sso_role` or key owner can execute this command):

```
alter encryption key important_key
drop encryption for user 'ted'
```

#### Example 9

Modifies the owner of `important_key` to new owner, “tinnap” (only the `sso_role` or key owner can execute this command):

```
alter encryption key important_key modify owner tinnap
```

#### Example 10

Uses the master key to encrypt an existing CEK “k2”:

```
alter encryption key k2
with passwd 'goodbye'
modify encryption
with master key
```

#### Example 11

Re-encrypts an existing CEK “k3” that is currently encrypted by the master key, to use dual control:

```
alter encryption key k3
modify encryption
with master key
dual_control
```

#### Example 13

Sets up the recovery key copy and uses it for key recovery after losing a password.

1. The key custodian originally creates a new encryption key protected by a password:

```
create encryption key key1 for AES passwd 'loseitl8ter'
```

2. The key custodian adds a special encryption key recovery copy for `key1` for Charlie:

```
alter encryption key key1 with passwd 'loseitl8ter'
add encryption
with passwd 'temppasswd'
for user charlie
for recovery
```



3. Charlie assigns a different password to the recovery copy and saves this password in a locked drawer:

```
alter encryption key key1
  with passwd 'temppasswd'
  modify encryption
  with passwd 'finditl8ter'
  for recovery
```

4. If the key custodian loses the password for base key, he can obtain the password from Charlie and recover the base key from the recovery copy of the key using:

```
alter encryption key key1
  with passwd 'finditl8ter'
  recover encryption
  with passwd 'newpasswd'
```

#### Example 14

Switches the encryption of the master key from a user password to an external Hardware Security Module (HSM) key:

```
alter encryption key master
  with passwd 'its8Secret'
  modify encryption with external key
```

## Usage

- If the SSO issues `alter encryption key` to set the key as the database default, the specified key replaces any existing key as the default.
- If the key custodian issues `alter encryption key` to set a key as the database default, the specified key and the current default key (if it exists) must be owned by the key custodian.
- Keys are owned and managed by users with `keycustodian_role`, the `sso_role`, or by users who are explicitly granted permission for the `create encryption key` command. Keys are used by all users who have permissions to process and see the data from encrypted columns. How the SAP ASE server protects keys affects how they are accessed:
  1. The key owner creates the key for encryption by the system encryption password— when users access the encrypted data, the SAP ASE server decrypts the base key using the system encryption password. The key owner does not create individual key copies for users.
  2. The key custodian encrypts the base key with an explicit password – rather than create key copies, the key custodian shares this password with all users who process encrypted data. Users or applications must supply this password with the `set encryption passwd` command to access data. See `set encryption passwd`.
  3. The key custodian adds key copies for end users so that users do not have to share passwords. Users must enter their key copy's password using `set encryption passwd` to access encrypted columns. Alternatively, the key custodian can set up key copies for encryption by the key assignee's login password. This password does not have to be entered through `set encryption passwd`.
- When you create a key using `create encryption key`, the SAP ASE server saves the key in encrypted form, along with the key's properties, as a row in `sysencryptkeys`. This row represents the base key. The key owner can choose to allow access to encrypted data exclusively through the base key, or use `alter encryption key` to add key copies for individual users.

- If you do not include the `with passwd` parameter with `alter encryption`, the SAP ASE server uses the system encryption password.
- You cannot use the system encryption password to alter the base key of a key that has copies, and you cannot encrypt copies of keys with the system encryption password.
- Users assigned key copies modify only their own key copies.
- If you specify for `<login_association>`, the SAP ASE server temporarily encrypts the key copy with the system encryption password. The key copy is reencrypted by the copy owner's login password when he or she encrypts or decrypts data with that key.
- You cannot specify for `recovery` and `<login_association>` for the same key copy.

See also:

- `sp_encryption` in *Reference Manual: Procedures*
- *Encrypted Column Users Guide*

## Permissions

The permission checks for `alter encryption key` differ based on your granular permissions settings.

### Setting Description

**Enabled** With granular permissions enabled, you must be a user with `manage column encryption key` privilege to execute `alter encryption key` as default or not default.

You must be the key owner or have the following privilege depending the key type:

- column encryption key – `manage column encryption key`
- master key – `manage master key`
- service key – `manage service key`

to:

- Use `alter encryption key` to add or drop key copies, recover the key, and modify the key owner.
- Execute `alter encryption key` to modify the password of the base key.

### i Note

You must be the user assigned the key copy to modify the key copy password. You implicitly have permission to modify your own key copy's password.

**Disabled** With granular permissions disabled, you must be a user with `sso_role`, or `keycustodian_role` to execute `alter encryption key` as default or not default.

You must be the system security officer or the key owner to:

- Use `alter encryption key` to add or drop key copies, recover the key, and modify the key owner.
- Execute `alter encryption key` to modify the password of the base key.

## Setting Description

### Note

You must be the user assigned the key copy to modify the key copy password. You implicitly have permission to modify your own key copy's password.

## Auditing

Enable `encryption_key` audit option to monitor `alter encryption key` command. Values in `event` and `extrainfo` columns from the `sysaudits` table are:

Event	Command or access audited	Information in <code>extrainfo</code>
108	<code>alter encryption key..as   not default</code>	<ul style="list-style-type: none"><li>• <i>Roles</i> – current active roles</li><li>• <i>Full command text</i> – full text of <code>alter encryption key</code> command (sensitive parameters are obfuscated)</li></ul>
118	<code>alter encryption key..modify encryption</code>	<ul style="list-style-type: none"><li>• <i>Previous value</i> – NULL</li><li>• <i>Current value</i> – NULL</li></ul>
119	<code>alter encryption key..add encryption</code>	<ul style="list-style-type: none"><li>• <i>Other information</i> – NULL</li><li>• <i>Proxy information</i> – original login name, if <code>set proxy</code> is in effect</li></ul>
120	<code>alter encryption key..drop encryption</code>	
122	<code>alter encryption key..recover encryption</code>	
135	<code>alter encryption key..regenerate key</code>	

Full command text (with obfuscated sensitive parameters) is included in `extrainfo` column. For example:

```
sso_role; alter encryption key user1.key_udp with passwd ***** add encryption  
with passwd ***** for user user4; ; ; ; user1/ase;
```

`alter encryption key..modify owner` is audited under `alter audit` option (event 132), same as `alter..modify owner`. See Auditing section in [alter...modify owner \[page 58\]](#).

For more information about auditing, see *Security Administration Guide > Auditing*.

## Related Information

[create encryption key \[page 163\]](#)

## 1.3 alter index

Renames indexes in base or global temporary tables and foreign key role names of indexes and foreign keys explicitly created by a user.

### Syntax

```
alter index [[<database>.] [<owner>].] <table_name>.<index_name>
    set {index_compression = {none | page}
        | <modify_partition_clause>
        | [, latch_free_index = {on | off}]}
    | [, index_hash_caching = {on [, bucket_count = <number> ] | off
    | default}}
<modify_partition_clause> ::=
    modify partition <partition_name>[, <partition_name>]...
    set index_compression = {none | page | default}
```

### Parameters

**index\_compression = {none | page}**

changes the local index partition's compression state affects only index rows that are newly inserted or updated in the partition. Valid values are:

- none** The index page for the specified index is not compressed. Indexes that are specifically created with `index_compression = page` are compressed.
- page** When the page is full, existing index rows are compressed using the page prefix compression. When a row is added, a check is performed to determine whether the row is suitable for compression.

**latch\_free\_index = {on | off}**

indicates the latch policy of the index:

- on** Alters the index to be latch-free.
- off** Alters the latch-free index to a regular index.

**index\_hash\_caching = {on [, bucket\_count = <number> ] | off | default}**

enables or disables index hash caching:

- `on` – indicates that the index you are creating uses hash caching.
- `off` – indicates that the index you are creating does not use hash caching

- `default` – when the `HCB index auto tuning` configuration option is enabled, this allows SAP ASE to enable or disable index hash caching as needed on this index.

`bucket_count = <number>`

specifies the number of hash table buckets for each index partition. If you do not specify `bucket_count`, the server uses an internally calculated value for the number of hash buckets.

## Examples

### Example 1

Sets the compression state to on for the index `idx_char`:

```
alter index order_line.idx_char
set index_compression = page
```

### Example 2

Alters the `idx_char` index to be latch-free:

```
alter index order_line.idx_char
set latch_free_index = ON
```

## Usage

- You may only alter the latching policy on data-only locked tables.
- Latch-free indexes may help when an index becomes the bottleneck for a query. Use `alter index` to add the latch-free index attribute. However, latch-free indexes require additional memory when compared to regular indexes. Use `alter index` to remove a latch-free index if it is no longer required (for example, if the index is no longer a bottleneck to the query).
- You can issue `bucket_count = <number>` without including the `index_hash_caching` parameter to change the bucket count for unique indexes that already use hash caching. Note that the hash table is empty after the change completes.
- Issuing `index_hash_caching = ON` without the `bucket_count = <number>` parameter enables the hash caching property and prints a message enumerating the number of hash buckets used for the index partition.
- You can enable hash caches only on data-only locked tables.
- Disabling hash caching by specifying `index_hash_caching = off | default` reclaims the memory used by hash table, but the disk space associated with the BTree index remains untouched.
- The bucket number is automatically rounded up to  $2^n$ . For example, if you set the bucket count to a value of 1000, internally it will be changed to  $2^{10}$  – 1024.

## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

## Permissions

The permission checks for `alter index` differ based on your granular permissions settings.

Setting	Description
Enabled	With granular permissions enabled, you must be the table owner.
Disabled	With granular permissions disabled, you must be the table owner.

## Auditing

You can enable `alter` auditing option to audit this command. Values in `event` and `extrainfo` columns from the `sysaudits` table are:

Information	Value
Audit option	<code>alter</code>
Event	155
Command or access audited	<code>alter index</code>
Information in <code>extrainfo</code>	<ul style="list-style-type: none"><li>• <b>Roles</b> – current active roles</li><li>• <b>Keywords or options</b> – full text of <code>alter index</code> command</li><li>• <b>Previous value</b> – NULL</li><li>• <b>Current value</b> – NULL</li><li>• <b>Other information</b> – NULL</li><li>• <b>Proxy information</b> – original login name, if <code>set proxy</code> is in effect</li></ul>

Full command text is included in `extrainfo` column. For example:

```
sa_role sso_role oper_role sybase_ts_role mon_role;
alter index order_line.idx_char set index_compression =
page; ; ; ; ; sa/ase;
```

For more information about auditing, see *Security Administration Guide > Auditing*.

## 1.4 alter login

Changes the attributes of a login account.

The sections that describe this command are:

- [Syntax \[page 47\]](#)
- [Parameters \[page 47\]](#)
- [Examples \[page 50\]](#)
- [Usage \[page 52\]](#)
- [Standards \[page 52\]](#)
- [Permissions \[page 52\]](#)
- [Auditing \[page 53\]](#)

### Syntax

```
alter login <login_name>
  {[modify <attribute_value_pair_list>]
  | [add auto activated roles <role_name>[, <role_name_list>]]
  | [drop auto activated roles {ALL | <role_name>[, <role_name_list>]]}
  | [drop <attribute_name_list>]
  | [with password <caller_password>
  modify password [immediately] <new_login_name_password>]}
```

### Parameters

#### <login\_name>

specifies the name of the login account to be changed.

#### modify

changes attribute values to the new values specified if the attributes exist. If the attributes do not exist, the specified list of attributes and corresponding values are added to the login account. The <attribute\_value\_pair\_list> is an attribute name and a specified value. Specify one or more from the following:

**login profile**  
<login\_profile\_value>

Valid <login\_profile\_value> values are:

- <login\_profile\_name> – binds the specified login profile to the specified login account. If a login profile binding already exist, it becomes replaced with the specified login profile.
- ignore – eliminates any login profile binding. If a login profile binding exist, it gets removed. A default login profile is not be applicable and

attributes are applied as they were prior to release 15.7.

- `default` – default removes an existing login profile binding and associates the default login profile with the login account.  
If login profile `<login_profile_name>` is not specified and a default login profile exists, then the default login profile is associated with the login account.

<code>fullname &lt;name_value&gt;</code>	Full name of user who owns the login account. Adds a full name or modifies an existing name. The default is NULL.
<code>password expiration</code>	Password expiration interval.  The valid range is 0 to 32767 days. The default is 0, meaning the password never expires.
<code>min password length</code>	Minimum password length required.  The valid range is 0 to 30. The default is 6.
<code>max failed attempts</code>	Number of login attempts allowed, after which the login account is locked.  The valid range is -1 to 32767. -1 indicates the failed count is tracked but not locked. The default is 0, meaning the failed count is not tracked and the account is not locked due to failed login attempts.
<code>authenticate with &lt;authentication mechanism&gt;</code>	Specifies the mechanism used for authenticating the login account.  <code>&lt;authentication mechanism&gt;</code> values are ASE, LDAP, PAM, KERBEROS, ANY  When ANY is used, the SAP ASE server checks for a defined external authentication mechanism. If one is defined, the SAP ASE server uses the defined mechanism., otherwise the ASE mechanism is used.  If <code>authenticate with &lt;authentication mechanism&gt;</code> is not specified, ANY is used for the login account.
<code>default database &lt;default_database_name&gt;</code>	Specifies a database to be the default. The default is <code>master</code> .
<code>default language &lt;default_language&gt;</code>	Specifies a language to be the default. The default is <code>us_english</code>



**login script**  
**<login\_script\_name>** Specifies a valid stored procedure. Limited to 120 characters for a login script. The login script must be created in the master database.

**exempt inactive lock**  
**{TRUE | FALSE}** Specifies whether or not to exempt login accounts from being locked due to inactivity.  
  
Default is `FALSE`, which indicates account are not exempt.

#### **add auto activated roles**

specifies the previously granted, non-password protected user defined roles that must be automatically activated on login.

#### **drop auto activated roles**

specifies the previously granted user defined roles must not be automatically activated on login. `ALL` specifies all granted user defined roles.

#### **drop**

Drops specified attributes from the login account. Specify one or more of the following attributes to be dropped:

**login profile** Removes the login profile binding from the specified login account. If the `login profile ignore` parameter has been specified, the parameter is removed and existing default login profile is no longer ignored.

**fullname** Removes the name associated with the login account.

**password expiration** Removes any password expiration values.

**min password length** Removes any restrictions for a minimum password length.

**max failed attempts** Removes restrictions for the number of failed attempts allowed.

**authenticate with** Removes specifications for authentication mechanisms.

**default database** Removes specifications for a default database.

**default language** Removes specifications for a default languages.

**login script** Removes specifications to apply a login script.

**exempt inactive lock** Removes specifications indicating whether or not to lock login accounts due to inactivity. Sets the default value of `FALSE` where login accounts are not exempt.

**with password <caller\_password> modify <new\_login\_name\_password>**

changes the login password to the new specified password.

**immediately**

specifies whether a password immediately takes effect on users who are logged in. If you:

- Specify `immediately` – the password changes immediately in the `syslogins` table, and users who are logged in get their passwords updated while they are still logged in.
- Do not specify `immediately` – all users—with an exception to the caller—who are logged, in keep their old passwords until they reconnect.

## Examples

### Example 1

Binds the login profile `emp_lp` to the login account `ravi`.

```
alter login ravi modify login profile emp_lp
```

### Example 2

Adds a password ("Sybase123") to an `sa` login that currently has no password:

```
alter login sa with password NULL modify password Sybase123
```

### Example 3

Changes the password for user `ravi` to "Sap654321" by a user logged in as "sa" (specified using the `with password` parameter), not the password for user `ravi`:

```
alter login ravi with password Sybase123 modify password Sap654321
```

### Example 4

When `ignore` is specified, all login profiles are ignored, whether it is a login profile that has been bound to the `users_1` login account or a defined default login profile.

```
alter login users_1 modify login profile ignore
```

### Example 5

Creates two login profiles; the first is `general_lp`, which is a default login profile and the second is a login profile name `emp_lp`, which is defined for a specific group of employees. After the login profiles are created, attributes from both login profiles are applied to a login account.

```
create login profile general_lp as default
  with default database master default language us_english
  track lastlogin true authenticate with ASE
create login profile emp_lp with default database empdb authenticate with
LDAP
```

See *Applying Login Profile and Password Policy Attributes* in the *Security Administration Guide* for information about the order in which attributes are applied.

The following binds the login profile `emp_lp` to the login account `users_2`. The `default language` and `track lastlogin` are not defined in login profile `emp_lp` but are defined in the default login profile. Therefore, the `default language` and `track lastlogin` values are applied from `general_lp`.

```
alter login users_22 modify login profile emp_lp
```

#### Example 6

Creates two login profiles; the first is `newEmployee_lp` for new employees and the second is `default_lp` for existing employees:

```
create login profile newEmployee_lp with login script "newEmp_script"  
create login profile default_lp as default with login script "def_script"
```

The following applies the login script `newEmp_script` to `employee_new` upon login:

```
create login employee_new with password myPasswd33 login profile  
"newEmployee_lp"
```

The login profile `default_lp` is applied upon login to existing accounts that do not have a login script specified through a login profile.

#### Example 7

Shows how to enforce different roles that are granted and automatically activated for contract employees and full-time employees:

```
create login profile contractEmp_lp  
grant role access_role to contractEmp_lp  
alter login profile contractEmp_lp add auto activated roles access_role  
create login contractEmp_emp1 with password c_Emp43 login profile  
"contract_lp"  
create login contractEmp_emp2 with password c_Emp44 login profile  
"contract_lp"  
create login contractEmp_emp3 with password c_Emp44 login profile  
"contract_lp"
```

#### Example 8

Changes the default database for login `susan` to `master`.

```
alter login susan modify default database master
```

#### Example 9

Sets the default language for `susan` to French.

```
alter login susan modify default language french
```

#### Example 10

Changes the full name of login `susan` to Samuel Clemens.

```
alter login susan modify fullname "Samuel Clemens"
```

#### Example 11

Changes the maximum number of failed login attempts for login `susan` to 40.

```
alter login susan modify max failed attempts 40
```

## Example 12

A System Security Officer whose password is "2tomato" changes Victoria's password to "sesame1".

```
alter login victoria with password 2tomato modify password sesame1
```

## Usage

Precedence rules determine how login account attributes are applied when attributes are taken from different login profiles, or when values have been specified using `sp_passwordpolicy`.

For precedence rules, see *Applying Login Profile and Password Policy Attributes* in the *Security Administration Guide*.

See also:

- `create login`, `create login profile`, `alter login profile`, `drop login`, `drop login profile`
- For information about altering login accounts, see the *Security Administration Guide*.
- `lprofile_id`, `lprofile_name` in *Reference Manual: Building Blocks*
- `sp_passwordpolicy`, `sp_displaylogin`, `sp_displayroles`, `sp_locklogin` in *Reference Manual: Procedures*

## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

## Permissions

The permission checks for `alter login` differ based on your granular permissions settings.

Setting	Description
---------	-------------

<b>Enabled</b>	With granular permissions enabled, you must have the <code>manage any login</code> privilege to <code>alter login</code> accounts in general. To modify a login account's password, you must have the <code>change password</code> privilege or be the account owner. The account owner is allowed to modify the account's full name.
----------------	---

<b>Disabled</b>	With granular permissions disabled, you must have <code>sso_role</code> to <code>alter login</code> accounts in general. The account owner is allowed to modify the account's password and full name.
-----------------	---

## Auditing

You can enable `login_admin` and `login_admin` auditing options to audit this command. Values in `event` and `extrainfo` columns from the `sysaudits` table are:

Information	Value
Audit option	<code>login admin, security</code>
Event	138
Command or access audited	<code>alter login</code>
Information in <code>extrainfo</code>	<ul style="list-style-type: none"><li>• <b>Roles</b> – current active roles</li><li>• <b>Full command text</b> – full text of <code>alter login</code> command (password is obfuscated)</li><li>• <b>Previous value</b> – NULL</li><li>• <b>Current value</b> – NULL</li><li>• <b>Other information</b> – NULL</li><li>• <b>Proxy information</b> – original login name, if <code>set proxy</code> is in effect</li></ul>

Full command text with obfuscated password is included in `extrainfo` column. For example:

```
sa_role sso_role oper_role sybase_ts_role mon_role;
alter login test1 with passwd ***** modify passwd
*****; ; ; ; test1/ase;
```

For more information about auditing, see *Security Administration Guide > Auditing*.

## Related Information

[alter login profile \[page 54\]](#)

[create login \[page 216\]](#)

[create login profile \[page 220\]](#)

[drop login \[page 442\]](#)

[drop login profile \[page 444\]](#)

## 1.5 alter login profile

Changes the attributes of a login profile.

### Syntax

```
alter login profile <login_profile_name>
{ [as [not] default]
| [modify <attribute_value_pair_list>]
| [add auto activated roles <role_name>[, <role_name_list>]]
| [drop auto activated roles {ALL | <role_name>[, <role_name_list>]]}
| [drop <attribute_name_list>]}
```

### Parameters

#### **login\_profile\_name**

specifies the name of the login profile to be changed.

#### **as [not] default**

as default modifies the login profile to be the default login profile. as not default removes the default property of the specified login profile.

#### **modify <attribute\_value\_pair\_list>**

attribute values are changed to the new values specified if the attributes exist. If the attributes do not exist, the specified list of attributes and corresponding values are added to the specified login profile. The < attribute\_value\_pair\_list> is an attribute name and a specified value. Specify one or more of the following attributes:

Parameter	Parameter Value	Description
default database	<default_database_name>	Specifies a database in the SAP ASE server. The default is master.
default language	<default_language>	Specifies a language. The default is us_english
login script	<login_script_name>	Specifies a valid stored procedure. Limited to 120 characters for a login script. The login script must be created in the master database.

Parameter	Parameter Value	Description
<code>authenticate with</code>	Valid values: ASE, LDAP, PAM, KERBEROS, ANY	<p>Specifies the mechanism used for authenticating the login account.</p> <p>When <code>ANY</code> is used, the SAP ASE server checks for a defined external authentication mechanism. If one is defined, the SAP ASE server uses the defined mechanism., otherwise the ASE mechanism is used.</p> <p>If <code>authenticate with &lt;authentication mechanism&gt;</code> is not specified, <code>ANY</code> is used for the login account.</p>
<code>track lastlogin</code>	Valid values: TRUE, FALSE.	<p>Enables last login updates.</p> <p>The default is <code>TRUE</code>, which is to update.</p>
<code>stale period</code>	<p>1..32767 days.</p> <p>Duration: D (days), W (weeks), M (months), Y (years)</p>	<p>Indicates the duration a login account is allowed to remain inactive before it is locked due to inactivity. The default is D (days).</p>

#### **add auto activated roles**

specifies the previously granted non-password protected user defined roles that must be automatically activated on login. An error is generated if the role specified is not granted to the login. By default, user defined roles are not automatically activated on login.

#### **drop auto activated roles**

specifies the previously granted user defined roles must not be automatically activated on login. `ALL` specifies all granted user defined roles.

#### **drop <attribute\_name\_list>**

removes the following:

- `default database` – removes the default database specification.
- `default language` – removes the default languages specification.
- `login script` – removes specifications to apply a login script.
- `authenticate with` – removes specifications for authentication mechanisms that are associated with the account.
- `track last login` – removes specifications that enable last login updates.
- `stale period` – removes any restrictions that have been specified for the login account to remain inactive before it is locked.

## Examples

### Example 1

Configures `eng_lp` as the default login profile. If there is an existing default login profile, its default property is removed.

```
alter login profile eng_lp as default
```

### Example 2

Alters the login profile `mgr_lp` to automatically activate the previously granted `program_role`, `product_role`, and `admin_role`, roles on login if they are not password protected.

```
alter login profile mgr_lp add auto activated roles program _role,  
product_role, admin_role
```

### Example 3

Alters the login profile `mgr_lp` to remove the automatic activation of the previously granted role `admin_role` on login.

```
alter login profile mgr_lp drop auto activated roles admin_role
```

### Example 4

Alters the login profile `mgr_lp` to remove the `login_script` attribute. Once removed, a login account associated with `mgr_lp` uses the values of a default login script, if one is defined. If one is not defined, the login script attribute be set to the default value, which is no login script with be invoked on login.

```
alter login profile mgr_lp drop login script
```

## Usage

- Precedence rules determine how login account attributes are applied when attributes are taken from different login profiles or when values have been specified using `sp_passwordpolicy`. For precedence rules, see *Applying Login Profile and Password Policy Attributes* in the *Security Administration Guide*.
- You can specify a login script to be invoked at login. For more information, see *Invoking a Login Script* in the *Security Administration Guide*.

See also:

- `create login`, `create login profile`, `alter login`, `drop login`, `drop login profile`
- For information about altering login profiles, see the *Security Administration Guide*.
- `lprofile_id`, `lprofile_name` in *Reference Manual: Building Blocks*
- `sp_passwordpolicy`, `sp_displaylogin`, `sp_displayroles`, `sp_locklogin` in *Reference Manual: Procedures*



## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

## Permissions

The permission checks for `alter login profile` differ based on your granular permissions settings.

Setting	Description
---------	-------------

<b>Enabled</b>	With granular permissions enabled, you must have the <code>manage any login profile</code> privilege to execute <code>alter login profile</code> .
----------------	--

<b>Disabled</b>	With granular permissions disabled, you must have <code>sso_role</code> to execute <code>alter login profile</code> .
-----------------	---

## Auditing

You can enable `security_profile` and `security` auditing options to audit this command. Values in `event` and `extrainfo` columns from the `sysaudits` table are:

Information	Value
Audit option	<code>security_profile, security</code>
Event	140
Command or access audited	<code>alter login profile</code>
Information in <code>extrainfo</code>	<ul style="list-style-type: none"><li>• <b>Roles</b> – current active roles</li><li>• <i>Full command text</i> – full text of <code>alter login profile</code> command</li><li>• <b>Previous value</b> – NULL</li><li>• <b>Previous value</b> – NULL</li><li>• <b>Other information</b> – NULL</li><li>• <b>Proxy information</b> – original login name, if <code>set proxy</code> is in effect</li></ul>

Full command text is included in `extrainfo` column. For example:

```
sa_role sso_role oper_role sybase_ts_role mon_role;  
alter login profile vivekk_lp modify default database  
"sybsystemprocs"; ; ; ; ; sa/ase;
```

For more information about auditing, see *Security Administration Guide > Auditing*.

## Related Information

[alter login \[page 47\]](#)

[create login \[page 216\]](#)

[create login profile \[page 220\]](#)

[drop login \[page 442\]](#)

[drop login profile \[page 444\]](#)

## 1.6 alter...modify owner

Transfers the ownership of database objects from one owner to another.

### Syntax

```
alter {<object_type> | all} [<owner>.] {<object_name> | * }
    modify owner
    {<name_in_db> | loginname only <login_name >}
    [preserve_permissions]
```

### Parameters

#### <object\_type>

- `table` – user tables and proxy tables
- `view` – views
- `procedure` – stored procedures
- `function` – user-defined functions
- `default` – defaults defined separately from the creation of tables
- `rule` – rules
- `type` – user-defined datatypes
- `encryption key` – encryption keys

#### `all`

all permitted object types. When specified as `all <owner>.*`, the ownership of all permitted objects owned by the specified owner are transferred. When specified as `all <owner>.<object_name>`, the ownership of permitted objects with name `<object_name>` owned by the specified owner are transferred.

#### <owner> ,

indicates the current owner of the object, which is determined by the owner's database user ID (`uid`). Specifying `<owner>` is optional when the user is transferring the

ownership of objects owned by themselves. Ownership of objects in the `sysobjects` table are associated with the owner's login name and uid.

#### `<object_name>`

indicates the name of the object for which the ownership is to be transferred. An attempt to transfer the ownership of an object with `<object_name>` to the same owner results in an error message.

\*

all objects owned by `<owner>` and specified by `<object_type>`. When `<object_type>` is `all`, all objects owned by `<owner>` are transferred. When `<owner>` is the database owner, \* granular permissions settings. is not allowed.

#### `<name_in_db>`

differ based on the database user name of the new owner to whom the ownership transferred. The user specified by `<name_in_db>` must be an existing user and cannot be a guest, role, group, or an alias.

#### `loginame only <login_name>`

transfers only the `loginame` field in `sysobjects` of objects involved to `<login_name>`. `<login_name>` must be a valid login in the `syslogins` table.

#### `preserve permissions`

indicates whether or not to preserve explicitly granted or revoked permissions on the objects whose ownership are being transferred:

- When specified – all explicitly granted or revoked permissions on the objects are preserved and the `<grantor>` of the permissions is changed to the new owner. For example, Bill granted `select` permission on table `bill_table` to Mark with `grant` option. Mark then granted `select` permission on table `bill_table` to John. If the ownership of the table is then transferred to Eric with `preserve permissions` specified, Mark and John retain their permission on `bill_table`.
- When not specified – all existing explicitly granted and revoked permissions on the objects are removed from the system, and as a result, rows in the `sysprotects` table that correspond to the object are deleted.

Implicit permissions on objects are not preserved for previous owners. New owners acquire all implicit permissions.

For example, Bill is the owner of `bill_table` and possesses the implicit `alter`, `delete`, `insert`, `references`, `select`, and `update` permissions and explicit `decrypt` permission on `bill_table`. After an ownership transfer to Eric with `preserve permission` specified, Bill only retains `decrypt` permission on `bill_table`.

## Examples

### Example 1

Transfers ownership of the table named `bill.author` to Eric: the type of object whose ownership is to be explicitly transferred. Specify one of the following object types:

```
alter table bill.author
```

```
modify owner eric
```

### Example 2

Transfers ownership of the view named `bill.vw_author_in_ca` to eric without removing all existing explicitly granted permissions:

```
the type of object whose ownership is to be explicitly transferred. Specify
one of
alter view bill.vw_author_in_ca
  modify owner eric
  preserve permissions
```

### Example 3

Transfers ownership of all tables owned by Bill to Eric:

```
alter table bill.*
  modify owner eric
```

### Example 4

Transfers ownership of all objects owned by Bill to Eric:

```
alter all bill.*
  modify owner eric
```

### Example 5

The command fails when the new owner Cindy already owns an table named `cindy.publisher`.

```
alter table bill.publisher
  modify owner cindy
```

### Example 6

An error results when an attempt is made to transfer the ownership of `bill.publisher` to Cindy because `bill.publisher` is not a stored procedure.

```
alter procedure bill.publisher
  modify owner cindy
```

## Usage

The ownership of the following dependent objects is implicitly transferred when the ownership of the objects they depend on have been transferred:

- `trigger` – ownership of triggers are updated along with the dependent table when the owners are the same. The ownership of a DBO owned trigger cannot be altered if the trigger was created for a non DBO owned table or view.
- Declarative objects, which are defined during the table or view creation.
  - Defaults
  - Decrypt defaults
  - Check constraints
  - Reference constraints
  - Partition constraints

- Computer columns

When transferring ownership of objects:

- Use caution in the following system databases: `sybsecurity`, `sybssystemdb`, `model`, `sybssystemprocs`, `sybsyntax`, `dbccdb`, and `tempdb`.
- Do not transfer ownership of system objects supplied and managed by SAP, such as but not limited to, user tables with `spt_` prefix, system stored procedures with the `sp_` prefix, and monitor tables. Doing so can render the system database unusable.

When transferring encryption keys:

- To an owner who owns a copy of the key is not allowed and the command fails.
- Changing the owner of encryption keys does not effect the assignees of the encryption key copies.

You cannot use the `alter ... modify owner` command to change the owner of a precomputed result set. To change the owner, drop the precomputed result set and re-create with the new owner.

## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

## Permissions

The permission checks for `alter... modify owner`

### Setting Description

**Enabled** With granular permissions enabled, you must have the `alter any object owner` privilege for objects other than encryption key.

Only encryption key owners or user with the following privilege (based on encryption key type) can transfer the encryption key ownership:

- column encryption key – `manage column encryption key`
- master key – `manage master key`
- service key – `manage service key`

The database users (with `alter any object owner` privilege) who are explicitly or implicitly aliased to the database owner are not allowed to transfer the ownership of objects they concretely own. An object is identified as concretely owned by the database owner if it includes database owner user ID for the value of `sysobjects.uid`, and NULL or the database owner's login name for the value of `sysobjects.loginame`.

**Disabled** With granular permissions disabled:

- System security officer (SSO) users are allowed to use this command to transfer the ownership of objects.

**Setting**    **Description**

- Only SSO users and encryption key owners can transfer the encryption key ownership.
- Database owner (DBO) users and users who are explicitly or implicitly aliased to the DBO are allowed to transfer the ownership of objects with a type other than encryption keys with the following restrictions:
  - Database owners are not allowed to transfer the ownership of objects they concretely own. An object is identified as concretely owned by the database owner if it includes DBO\_UID for the value of `sysobjects.uid`, and NULL or the database owner's login name for the value of `sysobjects.loginame`.
  - The functionality of transferring the ownership of multiple objects in one command is disabled for safety reasons and the transfer of DBO objects must be in the form of `dbo.<object_name>`.

## Auditing

You can enable `alter` auditing option to audit this command. Values in `event` and `extrainfo` columns from the `sysaudits` table are:

<b>Information</b>	<b>Value</b>
<b>Audit option</b>	<code>alter</code>
<b>Event</b>	132
<b>Command or access audited</b>	<code>alter...modify owner</code>
<b>Information in extrainfo</b>	<ul style="list-style-type: none"><li>• <b>Roles</b> – current active roles</li><li>• <b>Full command text</b> – full text of <code>alter...modify owner</code> command</li><li>• <b>Previous value</b> – NULL</li><li>• <b>Current value</b> – NULL</li><li>• <b>Other information</b> – NULL</li><li>• <b>Proxy information</b> – original login name, if <code>set proxy</code> is in effect</li></ul>

Full command text is included in `extrainfo` column. For example:

```
sa_role sso_role oper_role sybase_ts_role mon_role;  
alter table bill.author modify owner eric; ; ; ; ; sa/ase;
```

For more information about auditing, see *Security Administration Guide > Auditing*.

## 1.7 alter precomputed result set

Alters the properties or policies of a precomputed result set.

### Syntax

```
alter {precomputed result set | materialized view}
    [<owner_name>.<prs_name>
    [{immediate | manual} refresh]
    [enable | disable]
    [{enable | disable} use in optimization]
```

### Parameters

#### **precomputed result set | materialized view**

alters a materialized view or precomputed result set.

#### **<prs\_name>**

name of the precomputed result set. A fully qualified `<prs_name>` cannot include the server or database name.

#### **{immediate | manual} refresh**

determines the refresh policy:

**immediate** (Default) the precomputed result set is updated during the same transaction that updates the base tables.

**manual** The precomputed result set is explicitly updated. When you use the `manual` parameter, updates to the base tables are not reflected in the precomputed result set until you explicitly issue `refresh`. Because precomputed result sets set to `manual` are not maintained, the SAP ASE server considers them to be stale, even after you issue the `refresh` parameter, and therefore the query processor selects this data for query rewrite only if the query accepts stale data.

#### **enable | disable**

specifies whether the precomputed result set is available for operations. This option overrides all other precomputed result set options.

**enable** (Default) the precomputed result set is available for operations. Only precomputed result sets configured for `enable` are maintained according to their refresh policy.

**disable** The precomputed result set is not available for operations. Disabled precomputed result sets are not considered for maintenance or query rewrites. If a precomputed result set is configured for `disable`, it is not:

- Used for the query rewrite during optimization, whether or not you specify `use in optimization`.
- Populated, whether or not you specify `with populate`.

#### **{enable | disable} use in optimization**

specifies whether to include a precomputed result set for query rewrite during optimization. `use in optimization` is enabled by default. Precomputed result sets are considered for query rewrite depending on how their `refresh` parameter is set:

<b>immediate</b>	Considered for all queries
<b>manual</b>	Considered only if the query accepts stale data.

## Examples

### Example 1

Alters the `authors_prs` from a manual to an immediate refresh policy:

```
alter precomputed result set authors_prs
    immediate refresh
```

## Usage

- Precomputed result sets are automatically refreshed when you change them from a `manual` to an `immediate` refresh policy.
- You must be the explicit owner of the precomputed result set to perform a `manual refresh`. The owner of a precomputed result set created for `manual refresh` has exclusive permissions for access, and these permissions cannot be granted to other users.
- If the base table or view on which the precomputed result set is based is dropped or altered, the precomputed result set is automatically altered to `disable`.

## Permissions

You must be the precomputed result set owner to execute the `alter` command.



## Auditing

This command is not audited.

## 1.8 alter role

Defines mutually exclusive relationships between roles; adds, drops, and changes passwords for roles; specifies the password expiration interval, the minimum password length, and the maximum number of failed logins allowed for a specified role. Also locks and unlocks roles.

### Syntax

```
alter role <role1> {add | drop} exclusive  
    {membership | activation} <role2>
```

```
alter role <role_name> [add passwd "<password>" |  
    drop passwd] [lock | unlock]
```

```
alter role {<role_name> | "all overrides"}  
    set {passwd expiration | min passwd length |  
    max failed_logins} <option_value>
```

### Parameters

**<role1>**

is one role in a mutually exclusive relationship.

**add**

adds a role in a mutually exclusive relationship; adds a password to a role.

**drop**

drops a role in a mutually exclusive relationship; drops a password from a role.

**exclusive**

makes both named roles mutually exclusive.

**membership**

does not allow you to grant users both roles at the same time.

**activation**

allows you to grant a user both roles at the same time, but does not allow the user to activate both roles at the same time.

**<role2>**

is the other role in a mutually exclusive relationship.

**<role\_name>**

is the name of the role for which you want to add, drop, or change a password.

**passwd**

adds or drops a password to a role.

**<password>**

is the password to add to a role. You cannot use variables for passwords. For rules on passwords, see *Managing Adaptive Server Logins and Database Users* in the *Security Administration Guide*.

**lock**

locks the specified role.

**unlock**

unlocks the specified role.

**all overrides**

applies the setting that follows to the entire server rather than to a specific role.

**set**

activates the option that follows it.

**passwd expiration**

specifies the password expiration interval in days. It can be any value between 0 – 32767, inclusive.

**min passwd length**

specifies the minimum length allowed for the specified password.

**max failed\_logins**

specifies the maximum number of failed login attempts allowed for the specified password.

**<option\_value>**

specifies the value for `passwd expiration`, `min passwd length`, or `max failed_logins`. To set `all overrides`, set the value of `<option_value>` to `-1`.

## Examples

### Example 1

Defines `intern_role` and `specialist_role` as mutually exclusive at the membership level:

```
alter role intern_role add exclusive membership
specialist_role
```

### Example 2

Defines roles as mutually exclusive at the membership level and at the activation level:

```
alter role specialist_role add exclusive membership
intern_role
```

```
alter role intern_role add exclusive activation
surgeon_role
```

### Example 3

Adds a password to an existing role:

```
alter role doctor_role add passwd "physician"
```

### Example 4

Drops a password from an existing role:

```
alter role doctor_role drop passwd
```

### Example 5

Locks `physician_role`:

```
alter role physician_role lock
```

### Example 6

Unlocks `physician_role`:

```
alter role physician_role unlock
```

### Example 7

Changes the maximum number of failed logins allowed for `physician_role` to 5:

```
alter role physician_role set max failed_logins 5
```

### Example 8

Sets the minimum password length for `physician_role`, an existing role, to five characters:

```
alter role physician_role set min passwd length 5
```

### Example 9

Overrides the minimum password length of all roles:

```
alter role "all overrides" set min passwd length -1
```

### Example 10

Removes the overrides for the maximum failed logins for all roles:

```
alter role "all overrides" set max failed_logins -1
```

## Usage

- The `alter role` command defines mutually exclusive relationships between roles, and adds, drops, and changes passwords for roles.
- The `all overrides` parameter removes the system overrides that were set using `sp_configure` with any of the following parameters:

- `passwd expiration`
- `max failed_logins`
- `min passwd length`

Dropping the role password removes the overrides for the password expiration and the maximum failed logins options.

Password complexity checks are set at the login level using `create login` or `alter login`. Set the options at the global level using `sp_passwordpolicy` or `sp_configure`. See *Manage Roles* in the *Security Administration Guide*.

- When you use `alter role` to lock or unlock roles, you set (or unset) the `locksuid`, `lockdate`, and `lockreason` columns that are added to `sysrvroles`.

See also:

- For more information on altering roles, see the *System Administration Guide*.
- `mut_excl_roles`, `proc_role`, `role_contain`, `role_id`, `role_name` in *Reference Manual: Building Block*
- `sp_activeroles`, `sp_displaylogin`, `sp_displayroles` in *Reference Manual: Procedures*

## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

## Permissions

The permission checks for `alter role` differ based on your granular permissions settings.

Setting	Description
Enabled	With granular permissions enabled, you must have the <code>manage roles</code> privilege.
Disabled	With granular permissions disabled, you must be a user with <code>sso_role</code> .

## Auditing

You can enable the following auditing options to audit this command. Values in `event` and `extrainfo` columns from the `sysaudits` table are:

Audit option	Event	Command or access audited	Information in <code>extrainfo</code> :
<code>alter,role,security</code>	85	<code>alter role</code>	<ul style="list-style-type: none"> <li>• <b>Roles</b> – current active roles</li> <li>• <b>Full command text</b> – full text of <code>alter role</code> command (password is obfuscated)</li> </ul>
<code>role_locked</code>	133	<code>alter role...lock</code>	

Audit option	Event	Command or access audited	Information in <code>extrainfo</code> :
password	134	alter role...add passwd	<ul style="list-style-type: none"> <li>• <b>Previous value</b> – NULL</li> <li>• <b>Current value</b> – NULL</li> <li>• <b>Other information</b> – NULL</li> </ul>
		alter role...drop passwd	<ul style="list-style-type: none"> <li>• <b>Proxy information</b> – original login name, if <code>set proxy</code> is in effect</li> </ul>

Full command text (with obfuscated password) is included in `extrainfo`. For example, after you enable `role` and `password`, then execute `alter role`, two events will be recorded:

```
select event, extrainfo from sybsecurity..sysaudits_01 where event in (85, 134)
go
event  extrainfo
-----
85     sa_role sso_role oper_role sybase_ts_role mon_role; alter role role1
      add passwd "*****"; ; ; ; ; sa/ase;
134    sa_role sso_role oper_role sybase_ts_role mon_role; alter role role1
      add passwd "*****"; ; ; ; ; sa/ase;
```

## Related Information

[create role \[page 257\]](#)

[drop role \[page 450\]](#)

[grant \[page 520\]](#)

[revoke \[page 672\]](#)

[set \[page 732\]](#)

### 1.8.1 Changing Passwords for Roles

To change the password for a role, first drop the existing password, then add the new password.

```
alter role doctor_role drop passwd
```

```
alter role doctor_role add passwd "physician"
```

#### **i** Note

Passwords that existed before SAP ASE version 12.x and that are attached to user-defined roles do not expire.

## 1.8.2 Mutually Exclusive Roles

Consideration for mutually exclusive roles.

- You need not use any particular order to specify the roles in a mutually exclusive relationship or role hierarchy.
- You can use mutual exclusivity with role hierarchy to impose constraints on user-defined roles.
- Mutually exclusive membership is a stronger restriction than mutually exclusive activation. If you define two roles as mutually exclusive at membership, they are implicitly mutually exclusive at activation.
- If you define two roles as mutually exclusive at membership, defining them as mutually exclusive at activation has no effect on the membership definitions. Mutual exclusivity at activation is added and dropped independently of mutual exclusivity at membership.
- You cannot define two roles as mutually exclusive property after granting both roles to users or roles. Revoke either granted role from existing grantees before attempting to define the roles as mutually exclusive at the membership level.
- If two roles are defined as mutually exclusive at activation, the system security officer can assign both roles to the same user, but the user cannot activate both roles at the same time.
- If the system security officer defines two roles as mutually exclusive at activation, and users have already activated both roles or, by default, have set both roles to activate at login, the SAP ASE server makes the roles mutually exclusive, but issues a warning message naming specific users with conflicting roles. The users' activated roles do not change.

## 1.9 alter table

Makes changes to existing tables.

- Adds new columns to a table; drops or modifies existing columns; adds, changes, or drops constraints; changes properties of an existing table; enables or disables triggers on a table; and changes the compression level of a table.
- Supports adding, dropping, and modifying of computed columns. The command also enables the materialized property, nullability, or definition of an existing computed column to be changed.
- Partitions and repartitions a table with a specified partition strategy, adds partitions to a table with existing partitions, and splits or merges existing partitions.

### Syntax

```
alter table [[<database>....)
  | modify partition {<owner>}.] <table_name>
  {add <column_name> <datatype>}
  [default {<constant_expression> | user | null}]
  {identity | null | not null [not materialized]}
  [off row | in row]
  [[constraint <constraint_name>]
  {{unique | primary key}
```

```

        [clustered | nonclustered]
        [asc | desc]
        [with {fillfactor = <pct>,
            max_rows_per_page = <num_rows>,
            reservepagegap = <num_pages>
            immediate_allocation}
        [on <segment_name>]
| references [[<database>.]<owner>].<ref_table>
    [(<ref_column>)]
    [match full]
| check (<search_condition>)]
[encrypt [with [[<database>.]<owner>].] <keyname>]
    [decrypt_default {constant_expression | null}]]
[compressed = <compression_level> | not compressed]
[, <next_column>]...
| add [constraint <constraint_name>]
    {unique | primary key}
    [clustered | nonclustered]
    (<column_name> [asc | desc][, <column_name> [asc | desc]...])
    [with {fillfactor = <pct>,
        max_rows_per_page = <num_rows>,
        reservepagegap = <num_pages>}]
    [on <segment_name>]
    | foreign key (<column_name>[{, <column_name>}...])
    references [[<database>.]<owner>].<ref_table>
    [(<ref_column>)[{, <ref_column>}...])
    [match full]
| add <lob-colname> {text | image | unitext}
    [null] [in row [(<length>)]]
| check (<search_condition>)}
| set {[dml_logging = {full | minimal | default}]
    | [, compression = {none | page | row | all}]
    | [, index_compression = {none | page}]
    | [, erase_residual_data {on | off}]
    | [, row_caching {on [ allow [<number> | default] ] | [for [ all |
default ] ] rows ] | off}]
    | [, snapshot_isolation { on [ using version storage ] | off}]
    }
    [lob_compression = off | <compression_level>]
| drop {<column_name> [, <column_name>]...
    | constraint <constraint_name>}
| modify <column_name>
    [<datatype> [null | not null]]
    [[encrypt [with <keyname>] [decrypt_default [<value>]]
    | decrypt
    ]
    [[not] compressed]
    [compressed = <compression_level> | not compressed]
    | modify <lob-column> [in row (<length>)]
    [, <next_column>]...
| replace column_name
    default {constant_expression | user | null}
    | decrypt_default {constant_expression | null}
    | drop decrypt_default
lock {allpages | datarows | datapages}}
row storage {off}
| with exp_row_size=num_bytes
    | transfer table [on | off]
    | no datacopy}
| partition <number_of_partitions>
| unpartition
| <partition_clause>
| <add_partition_clause>

```

Syntax for partitions:

```
<partition_clause> ::=
```

```

partition by range (<column_name>[, <column_name>]...)
  ([.]<partition_name>] values <= (<constant | MAX>
  [, {constant | MAX}] ...) [on <segment_name>]
  [<compression_clause>] [on <segment_name>]
  [, [<partition_name>] values <= (<constant | MAX>
  [, {constant | MAX}] ...) [on <segment_name>]]...)
| partition by hash (<column_name>[, <column_name>]...)
  {(<partition_name> [on <segment_name>]
  [, <partition_name> [on <segment_name>]]...)
  [<compression_clause>] [on <segment_name>]
  | <number_of_partitions>
  [on (<segment_name>[, <segment_name>] ...)]}
| partition by list (<column_name>)
  ([<partition_name>] values (constant[, constant] ...)
  [on <segment_name>]
  [<compression_clause>] [on <segment_name>]
  [, [<partition_name>] values (constant[, constant] ...)
  [on <segment_name>]] ...)
| partition by roundrobin
  {(<partition_name> [on <segment_name>]
  [, <partition_name> [on <segment_name>]]...)
  [<compression_clause>] [on <segment_name>]
  | <number_of_partitions>
  [on (<segment_name> [, <segment_name>]...)]}
<add_partition_clause>::=
add partition
  {([<partition_name>] values <= (<constant | MAX>
  [, {constant | MAX}]...)
  [on <segment_name>]
  [<compression_clause>] [on <segment_name>]
  [, [<partition_name>] values <= (<constant | MAX>
  [, {constant | MAX}] ...)
  [on <segment_name><partition_name> [, <partition_name> . . .]}
  set compression [= {default | none | row | page}]
  set index_compression [= {none | page}]
  | ([<partition_name>] values (constant[, constant] ...)
  [on <segment_name>]
  [, [<partition_name>] values (constant[, constant] ...)
  [on <segment_name>]] ...)})

```

Syntax for computed columns:

```

alter table
  add <column_name> {compute | as}
  <computed_column_expression>...
  [materialized | not materialized]
  drop <column_name>
  modify <column_name> {null | not null |
  {materialized | not materialized} [null | not null] |
  {compute | as} <computed_column_expression>
  [materialized | not materialized]
  [null | not null]}

```

Syntax for dropping, splitting, merging, and moving partitions:

```

alter table <table_name>
  drop partition <partition_name>[, <partition_name>] [with
  skip_global_index_rebuild]...
  split partition <partition_name>
  merge partition {<partition_name>[{, <partition_name>}...]}
  into <destination_partition_name> [on <segment_name>]
  move partition <partition_name>[{, <partition_name>}...]
  to <destination_segment_name>

```



## Parameters

### <table\_name>

is the name of the table to change. Specify the database name if the table is in another database, and specify the owner's name if more than one table of that name exists in the database. The default value for <owner> is the current user, and the default value for <database> is the current database.

### add

specifies the name of the column or constraint to add to the table. If CIS is See add for remote servers.

### <column\_name>

is the name of a column in that table. If Java is enabled in the database, the column can be a Java-SQL column. specifies the name of the column or constraint to add to the table. If CIS is enabled, you cannot use

### <datatype>

is any system datatype except `bit`, or any user-defined datatype except those based on `bit`.

If Java is enabled in the database, <datatype> *Java in Adaptive Server Enterprise*.

### default

can be the name of a specifies a default value for a column. If you specify a default and the user does not provide a value for this column when inserting data, the SAP ASE server inserts this value. The default can be a <constant\_expression>, `user` (to insert the name of the user who is inserting the data), or `null` (to insert the null value).

The SAP ASE server generates a name for the default in the form of <tablename\_colname\_objid>, where <tablename> is the first 10 characters of the table name, <colname> is the first five characters of the column name, and <objid> is the object ID number for the default. Setting the default to `null` drops the default.

If CIS is enabled, you cannot use `default` for remote servers.

### <constant\_expression>

is a constant expression to use as a default value for a column. It cannot include global variables, the name of any columns, or other database objects, but can include built-in functions. This default value must be compatible with the datatype of the column.

### user

specifies that the SAP ASE server should insert the user name as the default if the user does not supply a value. The datatype of the column must be `char(30)`, `varchar(30)`, or a type that the SAP ASE server implicitly converts to `char`; however, if the datatype is not `char(30)` or `varchar(30)`, truncation may occur.

### null | not null

specifies the SAP ASE server behavior during data insertion if no default exists.

`null` specifies that a column is added that allows nulls. The SAP ASE server assigns a null value during inserts if a user does not provide a value.

The properties of a bit-type column must always be `not null`.

`not null` specifies that a column is added that does not allow nulls. Users must provide a non-null value during inserts if no default exists.

If you do not specify `null` or `not null`, the SAP ASE server uses `not null` by default. However, you can switch this default using `sp_dboption` to make the default compatible with the SQL standards. If you specify (or imply) `not null` for the newly added column, a default clause is required. The default value is used for all existing rows of the newly added column, and applies to future inserts as well.

**materialized | not materialized**

indicates whether you are creating a materialized or nonmaterialized column.

**compressed = <compression\_level> | not compressed**

indicates if the data in the row is compressed and to what level.

<compression\_level> is the level of compression. The levels are:

- 0 – the row is not compressed.
- 1 through 9 – the SAP ASE server uses ZLib compression. Generally, the higher the compression number, the more the SAP ASE server compresses the LOB data, and the greater the ratio between compressed and uncompressed data (that is the greater the amount of space savings, in bytes, for the compressed data versus the size of the uncompressed data).  
However, the amount of compression depends on the LOB content, and the higher the compression level, the more CPU-intensive the process. That is, level 9 provides the highest compression ratio but also the heaviest CPU usage.
- 100 – the SAP ASE server uses FastLZ compression. The compression ratio that uses the least CPU usage; generally used for shorter data.
- 101 – the SAP ASE server uses FastLZ compression. A value of 101 uses slightly more CPU than a value of 100, but uses a better compression ratio than a value of 100.

The compression algorithm ignores rows that do not use LOB data.

**identity**

indicates that the column has the IDENTITY property. Each table in a database can have one IDENTITY column with a datatype of:

- Exact `numeric` and scale of 0, or
- Any of the integer datatypes, including signed or unsigned `bigint`, `int`, `smallint`, or `tinyint`.

IDENTITY columns are not updatable and do not allow nulls.

IDENTITY columns store sequential numbers, such as invoice numbers or employee numbers that are automatically generated by the SAP ASE server. The value of the IDENTITY column uniquely identifies each row in a table.

**off row | in row**

specifies whether the Java-SQL column is stored separately from the row, or in storage allocated directly in the row.

The storage for an `in row` column cannot exceed 16 KB, depending on the page size of the database server and other variables. The default value is `off row`.

## **constraint**

introduces the name of an integrity constraint. If CIS is enabled, you cannot use `constraint` for remote servers.

### **<constraint\_name>**

is the name of the constraint, which must conform to the rules for identifiers and be unique in the database. If you do not specify the name for a table-level constraint, the SAP ASE server generates a name in the form of `<tablename_colname_objectid>`, where `<tablename>` is the first 10 characters of the table name, `<colname>` is the first five characters of the column name, and `<objectid>` is the object ID number for the constraint. If you do not specify the name for a unique or primary key constraint, the SAP ASE server generates a name in the format `<tablename_colname_tabindid>`, where `<tabindid>` is a string concatenation of the table ID and index ID.

Constraints do not apply to the data that already exists in the table at the time the constraint is added.

## **unique**

constrains the values in the indicated column or columns so that no two rows can have the same non-null value. This constraint creates a unique index that can be dropped only if the constraint is dropped. You cannot use this option with the `null` option.

## **primary key**

constrains the values in the indicated column or columns so that no two rows can have the same value and so that the value cannot be NULL. This constraint creates a unique index that can be dropped only if the constraint is dropped.

## **clustered | nonclustered**

specifies that the index created by a `unique` or `primary key` constraint is a clustered or nonclustered index. `clustered` is the default (unless a clustered index already exists for the table) for primary key constraints; `nonclustered` is the default for unique constraints. There can be only one clustered index per table. See `create index` for more information.

## **asc | desc**

specifies whether the index is to be created in ascending (`asc`) or descending (`desc`) order. The default is ascending order.

## **with fillfactor=<pct>**

specifies how full to make each page when the SAP ASE server creates a new index on existing data, by indicating the percentage value in `<pct>` stands for percentage. The `fillfactor` percentage is relevant only when the index is created. As data changes, pages are not maintained at any particular level of fullness.

### **⚠ Caution**

Creating a clustered index with a `fillfactor` affects the amount of storage space your data occupies, since the SAP ASE server redistributes the data as it creates the clustered index.

The default for `fillfactor` is 0; this is used when you do not include `with fillfactor` in the `create index` statement (unless the value has been changed with `sp_configure`). When specifying a `fillfactor`, use a value between 1 and 100.

A `fillfactor` of 0 creates clustered indexes with completely full pages and nonclustered indexes with completely full leaf pages. It leaves a comfortable amount of space within the index B-tree in both clustered and nonclustered indexes. There is seldom a reason to change the `fillfactor`.

If the `fillfactor` is set to 100, the SAP ASE server creates both clustered and nonclustered indexes, with each page 100 percent full. A `fillfactor` of 100 makes sense only for read-only tables—tables to which no data is ever added.

`fillfactor` values smaller than 100 (except 0, which is a special case) cause the SAP ASE server to create new indexes with pages that are not completely full. A `fillfactor` of 10 might be a reasonable choice if you are creating an index on a table that eventually holds a great deal more data, but small `fillfactor` values cause each index (or index and data) to take more storage space.

#### **transfer table [on | off]**

alters a table's eligibility for incremental transfer. The default value is to make no change, whether the table is marked for transfer or not. If the `alter table` command specifies `set transfer table`, and the selection of `on` or `off` differs from the current value, the table's eligibility is changed.

#### **max\_rows\_per\_page = <num\_rows>**

limits the number of rows on data pages and the leaf-level pages of indexes. Unlike `fillfactor`, the `max_rows_per_page` value is maintained until it is changed with `sp_chgattribute`.

If you do not specify a value for `max_rows_per_page`, the SAP ASE server uses a value of 0 when creating the index. When specifying `max_rows_per_page` for data pages, use a value between 0 – 256. The maximum number of rows per page for nonclustered indexes depends on the size of the index key; the SAP ASE server returns an error message if the specified value is too high.

For indexes created by constraints, a `max_rows_per_page` setting of 0 creates clustered indexes with full pages, and nonclustered indexes with full leaf pages. A setting of 0 leaves a comfortable amount of space within the index B-tree in both clustered and nonclustered indexes.

If `max_rows_per_page` is set to 1, the SAP ASE server creates both clustered and nonclustered leaf index pages with one row per page at the leaf level. You can use this to reduce lock contention on frequently accessed data.

Low `max_rows_per_page` values cause the SAP ASE server to create new indexes with pages that are not completely full, use more storage space, and may cause more page splits.

#### **⚠ Caution**

Creating a clustered index with `max_rows_per_page` can affect the amount of storage space your data occupies, since the SAP ASE server redistributes the data as it creates the clustered index.

#### **reservepagegap = <num\_pages>**

specifies a ratio of filled pages to empty pages to be left during extent I/O allocation operations for the index created by the constraint. For each specified `<num_pages>`, an

empty page is left for future expansion of the table. Valid values are 0 – 255. The default value, 0, leaves no empty pages.

#### **immediate\_allocation**

explicitly create a table when you have enabled `sp_dboption 'deferred table allocation'`.

#### **on <segment\_name>**

specifies the segment on which the index exists or is to be placed. When using `on <segment_name>`, the logical device must already have been assigned to the database with `create database` or `alter database`, and the segment must have been created in the database with `sp_addsegment`. See your system administrator or use `sp_helpsegment` for a list of the segment names available in your database.

If you specify `clustered` and use the `on <segment_name>` option, the entire table migrates to the segment you specify, since the leaf level of the index contains the actual data pages.

For partitions, `on <segment_name>` specifies the segment on which to place the partition.

#### **references**

specifies a column list for a referential integrity constraint. You can specify only one column value for a column constraint. By including this constraint with a table that references another table, any data inserted into the *referencing* table must already exist in the *referenced* table.

To use this constraint, you must have `references` permission on the referenced table. The specified columns in the referenced table must be constrained by a unique index (created by either a `unique` constraint or a `create index` statement). If no columns are specified, there must be a `primary key` constraint on the appropriate columns in the referenced table. Also, the datatypes of the referencing table columns must exactly match the datatype of the referenced table columns.

If CIS is enabled, you cannot use `references` for remote servers.

#### **check**

specifies a `<search_condition>` constraint that the SAP ASE server enforces for all the rows in the table. If CIS is enabled, you cannot use `check` for remote servers.

#### **foreign key**

specifies that the listed columns are foreign keys in this table for which the matching primary keys are the columns listed in the `references` clause.

#### **<ref\_table>**

is the name of the table that contains the referenced columns. You can reference tables in another database. Constraints can reference as many as 192 user tables and internally generated worktables. Use `sp_helpconstraint` to check a table's referential constraints.

#### **<ref\_column>**

is the name of the column or columns in the referenced table.

#### **match full**

specifies that if all values in the referencing columns of a referencing row are:

- Null – the referential integrity condition is true.
- Non-null values – if there is a referenced row where each corresponding column is equal in the referenced table, then the referential integrity condition is true.

If they are neither, then the referential integrity condition is false when:

- All values are non-null and not equal, or
- Some of the values in the referencing columns of a referencing row are non-null values, while others are null.

#### **<search\_condition>**

is a Boolean expression that defines the `check` constraint on the column values. These constraints can include:

- A list of constant expressions introduced with `in`
  - A set of conditions, which may contain wildcard characters, introduced with `like`
- An expression can include arithmetic operations and Transact-SQL functions. The `<search_condition>` cannot contain subqueries, aggregate functions, parameters, or host variables.

#### **<next\_column>**

next column in the list.

#### **set dml\_logging**

determines the amount of logging for `insert`, `update`, and `delete` (DML) operations. One of:

- `full` – the SAP ASE server logs all transactions,
- `minimal` – the SAP ASE server does not log row or page changes
- `default` – logging is set to the table default.

#### **add <lob-colname> {text | image | unitext }**

adds the LOB column with the specified datatype.

#### **[null] [in row [(<length>)]]**

specifies the maximum length for the LOB column to remain in-row. If you do not specify length, the SAP ASE server applies the database-wide setting in effect for in-row length.

If you do not use `in row (<length>)`, and the database-wide setting is not in effect, the LOB column is added with off-row storage of the data.

#### **modify <lob-column> in row [(<length>)]**

changes only the property of the LOB column to in-row, up to the specified length. When you run this command, no data moves.

You can also use this option to increase the length of an in-row LOB column.

#### **i Note**

You cannot use this option to decrease the length of a LOB column, nor can you specify 0 as the length. Depending on the amount of space available on the page,

the off-row LOB data is moved in-row up to the specified in-row length during updates that occur after this modification.

#### **encrypt [with <keyname>]**

specifies an encrypted column and the key used to encrypt it.

<keyname> identifies a key created using `create encryption key`. The table owner must have `select` permission on <keyname>. If <keyname> is not supplied, the server looks for a default key created using `create encryption key` or `alter encryption key`.

See *Encrypting Data*, in *Database Encryption* for a list of supported datatypes.

#### **decrypt\_default <constant\_expression>**

specifies that this column returns a default value for users who do not have decrypt permissions, and <constant\_expression> is the value the SAP ASE server returns on `select` statements instead of the decrypted value. The value can be NULL on nullable columns only. If the `decrypt_value` cannot be converted to the column's datatype, the SAP ASE server catches the conversion error only when the query executes.

#### **decrypt**

decrypts the encrypted column.

#### **set compression**

indicates the level of compression to be applied to the table or partition. The new compression level applies to newly inserted or updated data:

- `default` – resets the compression level for the specified partitions to the compression level of the table.
- `none` – the data in this table or partition is not compressed. For partitions, `none` indicates that data in this partition remains uncompressed even if the table compression is altered to `row` or `page` compression.
- `page` – when the page fills, existing data rows that are row-compressed are then compressed using page-level compression to create page-level dictionary, index, and character-encoding entries. Set `page` compression at the partition or table level.  
The SAP ASE server compresses data at the page level only after it has compressed data at the row level, so setting the compression to `page` implies both `page` and `row` compression.
- `row` – compresses one or more data items in an individual row. The SAP ASE server stores data in a `row` compressed form only if the compressed form saves space compared to an uncompressed form. Set `row` compression at the partition or table level.

#### **set index\_compression**

specifies the index compression to be enabled or disabled to the table, index, or the local index partition. If the table is modified to be index compressed, newly created indexes are compressed.

- `NONE` – indexes on the specified table are not compressed.
- `PAGE` – all indexes on the specified table are compressed.

**set lob\_compression = <compression\_level>**

changes the compression level for a table that uses LOB datatypes.

**set "erase residual data" {on | off}**

specifies whether to remove residual data from deletions in SAP ASE.

**set latch\_free\_index**

indicates the latch policy of the table:

- **on** – all subsequent indexes on this table use latch-free indexes. Setting `latch_free_index` to `on` does not change the latch policy of existing indexes.
- **off** – all subsequent indexes on this table use regular indexes. Setting `latch_free_index` to `off` does not change the latch policy of existing indexes.

**drop**

specifies the name of a column or constraint to drop from the table. If CIS is enabled, you cannot use `drop` for remote servers.

**modify**

specifies the name of the column for which you are changing the datatype or nullability.

**[not] compressed**

indicates if the modified column is compressed.

**replace**

specifies the column for which to replace the default value with the new value specified by a following `default` clause. If CIS is enabled, you cannot use `replace` for remote servers.

**enable | disable trigger**

enables or disables a trigger. See the *Transact-SQL Users Guide* for information about triggers.

**lock datarows | datapages | allpages**

changes the locking scheme to be used for the table.

**row\_caching**

specifies whether the table uses row caching:

- **on** – enables the in-memory row storage cache to store all data rows for inserts, selects, and updates in this table or re-enables row caching after temporarily disabling it with the `row_caching off` parameter. New inserts performed in the row store that are frequently selected or updated rows are migrated from the data pages to the row store. High-volume OLTP applications requiring high performance benefit from enabling row caching for hot tables.
- **allow [<number> | default]** – sets the upper limit for the number of rows that can be brought into the IMRS in a single query.
  - **<number>** – indicates the value for the upper limit for the number of rows. The maximum value for the upper limit is 2147483646.
  - **default** – indicates that you are setting the upper limit for the number of rows to the default value of 100.
- **for [all | default]** – indicates that subsequent queries cache all the accessed rows to the IMRS.



- `all` – for all subsequent queries, all the accessed rows are moved to the IMRS whether they are qualified or not, or whether they fulfill the criteria of the ILM rules or not.
- `default` – for all subsequent queries, only the rows that are qualified and fulfill the criteria of the ILM rules are moved to the IMRS.
- `off` – disables row caching for this table, even if it was enabled database-wide. Subsequent inserts, updates, and deletes are performed directly in the data page store. Use `off` when individual tables do not require row caching.

**`snapshot_isolation { on [ using version storage ] | off }`**

determines whether the database uses snapshot isolation level semantics. One of:

- `on` – timestamp-based snapshot isolation-level semantics are applied to all user tables created in this database, unless you explicitly override the option when you create a new table.
- `off` – (default) snapshot isolation level semantics are not enabled database-wide for newly created tables, even if you created the database with row storage cache.
- `using` – specifies that you are selecting row or version storage for this database.
- `version storage` – specifies that tables use a temporary database to hold older versions of rows. Cache specified as a database-wide cache to store the row version metadata information is stored in `sysversions` in the version-storage temporary database. Issuing `using version storage off` disables version storage and the `imrs_cache` from this database.

**`with exp_row_size=<num_bytes>`**

specifies the expected row size. You can apply this parameter only:

- To datarows and datapages locking schemes.
- To tables with variable-length rows.
- When `alter table` performs a data copy, such as with `alter table add` or `modify`. You cannot use `with exp_row_size=<num_bytes>` with `alter table lock change` operations.

Valid values are 0, 1, and any value between the minimum and maximum row length for the table. The default value is 0, which means a server-wide setting is applied.

**`row storage {off [<cache_name>]}`**

disables the in-memory row storage for row caching. Before executing this, you must first issue `alter table ... set row_caching off` to prevent additional rows from being cached (existing rows in the cache remain in the cache). Once you issue `alter table ... row storage off`, existing rows in the in-memory row storage are drained and moved to the page store (making the memory available for other tables), or are returned to the system. You must disable `row_caching` before disabling `row storage`. Row caching cannot be performed while the row storage is being deactivated for the table. Once the deactivation is complete, all subsequent DMLs are done in the page-store. Issuing `row storage off` completely detaches the currently-assigned row storage cache from this table.. One of:

**`no datacopy`**

indicates that `alter table` drops columns without performing a data copy, preventing the `alter table... drop` command from blocking other commands running on the table while the `alter table` operation occurs.

**partition** `<number_of_partitions>`

adds (`<number_of_partitions> -1`) empty partitions to an unpartitioned table (round-robin-partitioned table with a single partition). Thus, the total number of partitions for the table becomes `<number_of_partitions>`. If Component Integration Services (CIS) is enabled, you cannot use `partition` for remote servers.

**unpartition**

changes a round-robin-partitioned table without indexes, to an unpartitioned table. If CIS is enabled, you cannot use `unpartition` for remote servers.

**partition by range**

specifies that records are to be partitioned according values in the partitioning column or columns. Each partitioning column value is compared with sets of user-supplied upper and lower bounds to determine partition assignment.

`<column_name>`

when used in the `<partition_clause>`, specifies a partition key column. A partition key column cannot be an encrypted column.

`<partition_name>`

specifies the name of a new partition on which table records are to stored. Partition names must be unique within the set of partitions on a table or index. Partition names can be delimited identifiers if `set quoted_identifier` is on. Otherwise, they must be valid identifiers.

If `<partition_name>` is omitted, the SAP ASE server creates a name in the form `<table_name>_<partition_id>`. The SAP ASE server truncates partition names that exceed the allowed maximum length.

**values** `<= <constant> | MAX`

specifies the inclusive upper bound of values for a named partition. Specifying a constant value for the highest partition bound imposes an implicit integrity constraint on the table. The keyword `MAX` specifies the maximum value in a given datatype.

**on** `<segment_name>`

when used in the `<partition_clause>`, specifies the segment on which the partition is to be placed. When using `on <segment_name>`, the logical device must already have been assigned to the database with `create database` or `alter database`, and the segment must have been created in the database with `sp_addsegment`. See your system administrator or use `sp_helpsegment` for a list of the segment names available in your database.

**partition by hash**

specifies that records are to be partitioned by a system-supplied hash function. The function computes the hash value of the partition keys that specify the partition to which records are assigned.

**partition by list**

specifies that records are to be partitioned according to literal values specified in the named column. The partition key contains only one column. You can list as many as 250 constants as the partition values for each list partition.

**partition by round-robin**

specifies that records are to be partitioned in a sequential manner. A round-robin-partitioned table has no partitioning key. Neither the user nor the optimizer knows in which partition a particular record resides.

**add partition**

applies only to range- or list-partitioned tables:

- For range-partitioned tables – add one or more partitions to the upper end of a range partitioned table.
- For list-partitioned tables – add one or more partitions with a new set of values.

**modify partition**

specifies the partitions for which you are modifying the compression level.

**compute | as**

adds or drops a new computed column. Follow the same rules defined for the `create table` command and the `alter table add` rules.

**<computed\_column\_expression>**

is any valid Transact-SQL expression that does not contain columns from other tables, local variables, aggregate functions, or subqueries. It can be one or a combination of column name, constant, function, global variable, or case expression, connected by one or more operators. You cannot cross-reference between computed columns, except when virtual computed columns reference materialize computed columns. You cannot reference encrypted column in a `<computed_column_expression>`.

**materialized | not materialized**

specifies whether a computer column is materialized or not. These are reserved keywords in the `modify` clause that specify whether the computed column is materialized, or physically stored in the table. By default, a computed column is `not materialized` (that is, not physically stored in the table). You can also use this parameter to change the definitions of existing virtual computed columns; that is, to materialize them.

**<table\_name> drop partition <partition\_name> [, <partition\_name>]...**

drops one or more list or range partitions. You cannot use `alter table` to drop a hash or round-robin partition.

For each partition you drop, the SAP ASE server:

- Deletes all data on the partition
- Deletes the partition definition from the system catalog
- Drops all corresponding local index partitions that refer to this data partition
- Regenerates the partition condition object of the base table and each local index
- Deletes all statistics information on this partition
- Rebuilds all global indexes

### i Note

If you attempt to drop a partition from a table that is referenced by another table, and the partition to be dropped and the referencing table are not empty, the command fails because of possible violations with the foreign-key constraint, and the SAP ASE server displays error message 13971.

#### **with skip\_global\_index\_rebuild**

when specified with `drop partition`, the command marks any participating global index as "suspect" and does not rebuild it. All global indexes are rebuilt when this qualifier is not specified (the default value).

Using this qualifier may speed up the completion of the command, at the expense of making an index unusable. To make an index usable again, drop and re-create the a suspect index.

#### **split partition <partition\_name> into <partition\_condition\_clause>**

redistributes partition data to two or more partitions.

#### **<partition\_condition\_clause>**

indicates conditions that specify how to split the source partition data. Typically, conditions are a numerical range or a data range. The partition conditions should cover all, and only, the data in the source partition.

`<partition_condition_clause>` may be on the same segment as the source partition, or on a new segment. If you do not specify destination partition segments, the SAP ASE server creates the new partitions on the segment on which the source partition resides.

#### **merge partition**

combine the data from two or more merge-compatible partitions into a single partition.

#### **<destination\_partition\_name>**

a new or existing partition. If `<destination_partition_name>` is an existing partition, it cannot be any of the source partitions you are merging. If you do not specify a destination partition name, a system-generated name is picked.

#### **move partition**

moves a partition (and its index) to a specified segment.

#### **<destination\_segment\_name>**

a new or existing segment to which you are moving the partition. You cannot specify "default" as the `<destination_segment_name>`.

## Examples

### Add Column to Table

This example adds a column to a table. For each existing row in the table, the SAP ASE server assigns a NULL column value:

```
alter table publishers
```

```
add manager_name varchar (40) null
```

### Add an IDENTITY Column to a Table

For each existing row in the table, the SAP ASE server assigns a unique, sequential column value. The IDENTITY column can be type `numeric` or `integer`, and have a scale of zero. The precision determines the maximum value ( $10^5 - 1$ , or 99,999) that can be inserted into the column:

```
alter table sales_daily
add ord_num numeric (5,0) identity
```

### Add a Primary Key Constraint to the authors Table

If there is an existing primary key or unique constraint on the table, you must drop the existing constraint first (see the next example. "Drops a Constraint"):

```
alter table authors
add constraint au_identification
primary key (au_id, au_lname, au_fname)
```

### Drop a Constraint

This example drops the `au_identification` constraint:

```
alter table titles
drop constraint au_identification
```

### Create an Index on Authors

This example includes an index that has a `reservepagegap` value of 16, leaving 1 empty page in the index for each 15 allocated pages:

```
alter table authors
add constraint au_identification
primary key (au_id, au_lname, au_fname)
with reservepagegap = 16
```

### Remove the Default Constraint

This example removes the default constraint on the `phone` column in the `authors` table. If the column allows NULL values, NULL is inserted if no column value is specified. If the column does not allow NULL values, an insert that does not specify a column value fails:

```
alter table authors
replace phone default null
```

### Modify the emp Table

This example modifies the `emp` table to encrypt the `ssn` column and specifies decrypt default:

```
alter table emp modify ssn encrypt with key1
decrypt_default '000-00-0000'
```

### Decrypt Data

Decrypts credit card data that is longer sensitive:

```
alter table stolen_ccards
modify ccard decrypt
```

If card was encrypted by a key protected by a user-defined password, precede this command with the `set encryption key` command.

### Add an Encrypted Column to an Existing Table

Since keyname is omitted, the SAP ASE server looks for the database default encryption key:

```
alter table sales_mgr
    add bonus money null encrypt
```

### Set a Password

This example sets the password for the `ssn_key` encryption key and encrypts the `ssn` column in the existing `employee` table.

```
set encryption passwd '4evermore' for key ssn_key
alter table employee modify ssn
    encrypt with ssn_key
```

If `ssn` in this example is an existing encrypted column encrypted by "key1" the alter table would cause the SAP ASE server to decrypt `ssn` using "key1" and reencrypt `ssn` using "ssn\_key".

### Add a Decrypt Default to a Column

This example adds a decrypt default to the `salary` column, which is already encrypted:

```
alter table employee replace salary
    decrypt_default $0.00
```

### Remove the Decrypt Default

This example removes the decrypt default for `salary` without removing the encryption property:

```
alter table employee replace salary drop
    decrypt_default
```

### Change an Unpartitioned Table

This example changes an unpartitioned table to a range-partitioned table with three partitions, each of which is on a different segment:

```
alter table titles partition by range (total_sales)
    (smallsales values <= (500) on seg1,
    mediumsales values <= (5000) on seg2,
    bigsales values <= (25000) on seg3)
```

### Add a Range Partition

This example adds another range partition to the `titles` table:

```
alter table titles add partition
    (vbigsales values <= (40000) on seg4)
```

### Alter a Table to Use Low-Level Compression

This example alters the `titles` table in the `pubs2` database to use row-level compression:

```
alter table titles set compression = row
```

### Change a Table to Use Page-Level Compression

This example changes the Y2009 partition of the `sales` table to use page-level compression:

```
alter table sales modify partition Y2009
    set compression = page
```

### Change the Compression State to NONE

This example alters the existing table `order_line`, changing the compression state to NONE:

```
alter table order_line set index_compression = NONE
```

### Change a Locking Scheme

This example changes the locking scheme for the `titles` table to `datarows` locking:

```
alter table titles lock datarows
```

### Add a Non-Null Column

This example adds the not-null column `author_type` to the `authors` table with a default of `primary_author`:

```
alter table authors
  add author_type varchar (20)
  default "primary_author" not null
```

### Drop Columns from a Table

This example drops the `advance`, `notes`, and `contract` columns from the `titles` table:

```
alter table titles
  drop advance, notes, contract
```

### Modify a Column with a Default of NULL

This example modifies the `city` column of the `authors` table to be a `varchar (30)` with a default of NULL:

```
alter table authors
  modify city varchar (30) null
```

### Modify a Column with a Default of NOT NULL

This example modifies the `stor_name` column of the `stores` table to be NOT NULL. Its datatype, `varchar (40)`, remains unchanged:

```
alter table stores
  modify stor_name not null
```

### Modify a Column and Change the Locking Scheme of a Table

This example modifies the `type` column of the `titles` table and changes the locking scheme of the `titles` table from `allpages` to `datarows`:

```
alter table titles
  modify type varchar (10)
  lock datarows
```

### Make Various Modifications to a Column

This example modifies the `notes` column of the `titles` table from `varchar (200)` to `varchar (150)`, changes the default value from NULL to NOT NULL, and specifies an `exp_row_size` of 40:

```
alter table titles
  modify notes varchar (150) not null
  with exp_row_size = 40
```

### Add an Incremental Transfer Attribute

This example adds the incremental transfer attribute to `mytable`:

```
alter table mytable set transfer table on
```

### Remove an Incremental Transfer Attribute

This example removes the incremental transfer attribute from `mytable`:

```
alter table mytable set transfer table off
```

### Add, Modify, or Drop a Column

This example adds, modifies, and drops a column, and then adds another column in one query. Alters the locking scheme and specifies the `exp_row_size` of the new column:

```
alter table titles
  add author_type varchar (30) null
  modify city varchar (30)
  drop notes
  add sec_advance money default 1000 not null
  lock datarows
  with exp_row_size = 40
```

### Modify a Column to Support In-Row LOB

This example modifies the `description` column of `mymsgs` table to support in-row LOB 400 bytes long:

```
alter table mymsgs modify description in row (400)
```

### Add a Virtual Computed Column

This example adds a virtual computed column:

```
alter table authors
  add fullname compute au_fname + ' ' + au_lname
```

### Change a Computed Column from Virtual to Materialized

This example changes a virtual computed column to a materialized computed column:

```
alter table authors modify fullname materialized
```

### Split a Partition in Two

This example splits the partition containing the `orders` table into two partitions:

```
alter table orders
  split partition P2
  into
  ( P5 values <= (25000) on seg2,
    P6 values <= (50000) on seg3)
```

### Merge Partitions into a Single Partition

This example merges the partitions containing the `sales` table into a single partition:

```
alter table sales
  merge partition Q1, Q2, Q3, Q4
  into Y2007
```



### Move Table to Another Segment

This example moves the `orders` table to the `seg4` segment:

```
alter table orders
  move partition P2 to seg4
```

### Drop a Column from a Table

This example drops the `total_sales` column from the `titles` table with a data copy:

```
alter table titles
  drop total_sales
  with no datacopy
```

### Change the Table's Latch Policy

This example alters the `order_line` table to use latch-free indexes:

```
alter table order_line set latch_free_index = on
```

### Enable Row Caching for Table

This example alters the `new_orders` table to enable row caching:

```
alter table new_orders set row_caching on
```

### Enable and Disable Row Caching over Time

This example shows how an in-memory table changes over time, and begins with enabling row caching for the warehouse table:

```
alter table warehouse set row_caching on
```

However, these rows get cached in the in-memory row storage as they are accessed from this table, and the server attempts to maintain these rows in the cache as long as memory is available. Issuing a `select` command to read all the rows from the data pages forces the server to cache the table in the in-memory row storage—the `index` clause forces a table scan, so the `count (*)` is not returned by merely scanning the index rows:

```
select count(*) from warehouse w (index warehouse) 19 where w.w_id != 0
```

As the table grows over time, or the demand for memory is too high while caching all the rows, you can temporarily disable row caching:

```
alter table warehouse set row_caching off
```

When appropriate, revert to row caching for the table:

```
alter table warehouse set row_caching on
```

### Disable Row Caching to Perform a Bulk Insert

This example temporarily disables row caching on the `new_orders` table before performing a bulk-insert of new data:

```
alter table new_orders set row_caching OFF
```

With row caching disabled, new inserts are made directly to the page store. Any caching properties that exists on the `new_orders` table before row caching are temporarily disabled. Perform the bulk insert:

```
insert new_orders select * ...
bcp-in new_orders ...
```

Reinstate the caching; this also reinstates the original caching properties:

```
alter table new_orders set row_caching on
```

## Usage

- If there are multiple triggers on a table, the table owner can disable any or all of the multiple triggers defined on that table.
- When you set the "erase residual data" option on a table, the operations for the table (`drop table`, `delete row`, `alter table`, `drop index`) that result in residual data automatically clean up deallocated space. The default is set to `off`.
- You cannot use `alter table` on a segment that includes a virtually hashed table. You cannot use `alter table` on a segment that includes the VHASH table, since a virtually hashed table must take only one exclusive segment, which cannot be shared by other tables or databases. Before you add, modify, or drop columns on a table, run `sp_depends` to see if there are any stored procedures that depend on the table you are changing. If such stored procedures exist, drop, then re-create the stored procedures as necessary after changing table schema.
- If stored procedures using `select *` reference an altered table, no new columns appear in the result set, even if you use the `with recompile` option. To include these new columns, drop and re-create the procedure. Otherwise, the wrong results may be caused by `insert into table1 select * from table2` in the procedure when the tables have been altered and new columns have been added to the tables.
- When the table owner uses `alter table`, the SAP ASE server disables access rules during the execution of the command and enables them upon completion of the command. The access rules are disabled to avoid filtering of the table data during `alter table`.
- If you specify `clustered` and use the `on <segment_name>` option, the entire table migrates to the segment you specify, since the leaf level of the index contains the actual data pages.
- `alter table. . . transfer table` involves data copy (similar to adding or removing a column); it is a very expensive command in terms of performance.
- `alter table` performs error checking for check constraints before it alters the table.
- When using `on <segment_name>` for partitions, the logical device must already have been assigned to the database with `create database` or `alter database`, and the segment must have been created in the database with `sp_addsegment`. See your system administrator or use `sp_helpsegment` for a list of the segment names available in your database.

See also `sp_chgattribute`, `sp_help`, `sp_helppartition`, `sp_rename` in *Reference Manual: Procedures*.

## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

See *System and User-Defined Datatypes* in *Reference Manual: Building Blocks* for datatype compliance information.

## Permissions

The permission checks for `alter table` differ based on your granular permissions settings.

Setting	Description
---------	-------------

<b>Enabled</b>	With granular permissions enabled, you must be the table owner or a user with <code>alter any table</code> privilege. A user with <code>setuser</code> privilege can impersonate the table owner by executing the <code>setuser</code> command. Requires <code>manage data cache</code> privilege to use the row storage cache for row caching or snapshot isolation.
----------------	---

<b>Disabled</b>	With granular permissions disabled, you must be the table owner or a user with <code>sa_role</code> . The database owner can impersonate the table owner by running the <code>setuser</code> command. Requires <code>sa_role</code> privilege to use the row storage cache for row caching or snapshot isolation.
-----------------	---

## Auditing

You can enable `alter` auditing option to audit this command. Values in `event` and `extrainfo` columns from the `sysaudits` table are:

Information	Value
Audit option	<code>alter</code>
Event	3
Command or access audited	<code>alter table</code>
Information in <code>extrainfo</code>	<ul style="list-style-type: none"><li>• <b>Roles</b> – current active roles</li><li>• <b>Full command text</b> – full text of <code>alter table</code> command</li><li>• <b>Previous value</b> – NULL</li><li>• <b>Current value</b> – NULL</li><li>• <b>Other information</b> – NULL</li><li>• <b>Proxy information</b> – original login name, if <code>set proxy</code> is in effect</li></ul>

Full command text is included in `extrainfo`. For example:

```
sa_role sso_role oper_role sybase_ts_role mon_role;
```

## Information

## Value

```
alter table publishers add manager_name varchar (40)
null; ; ; ; ; sa/ase;
```

For more information about auditing, see *Security Administration Guide > Auditing*.

## Related Information

[create index \[page 192\]](#)

[create table \[page 273\]](#)

[dbcc \[page 349\]](#)

[drop database \[page 429\]](#)

[dump transaction \[page 490\]](#)

[insert \[page 572\]](#)

[setuser \[page 790\]](#)

[select \[page 696\]](#)

[drop table \[page 457\]](#)

## 1.9.1 Restrictions for alter table

Restrictions that apply when using `alter table`.

- Do not alter the system tables.
- You cannot add a column of datatype `bit` to an existing table if you do not specify a default value. This default value must be 0 or 1.
- You cannot include the `alter table ... with online` parameter on IMRS-enabled databases.
- You cannot add a non-nullable LOB column.
- Online `alter table` commands are not supported on IMRS-enabled tables
- You cannot modify a nullable LOB column to be non-nullable.
- When you run `alter table drop column` against columns with large objects (LOB), the SAP ASE server drops any replication indexes if:
  - The table contains LOB columns, and
  - The table is marked for replication, and
  - The LOB column contains a replication indexConsequently, the SAP ASE server may require a long time to drop the replication index if the table is large.
- The maximum number of columns in a table is:
  - 1024 for fixed-length columns in both all-pages-locked (APL) and data-only-locked (DOL) tables
  - 254 for variable-length columns in an APL table
  - 1024 for variable-length columns in a DOL table
- `alter table` raises an error if the number of variable-length columns in an APL table exceeds 254.
- Drop, then re-create compiled objects after changing a table's lock schema.

- You cannot use the `no_datacopy` parameter on:
  - Materialized or virtual computed columns
  - Encrypted columns
  - XML columns
  - `timestamp` columns
  - `bit` columns
  - Java columns
- The maximum length for in-row Java columns is determined by the maximum size of a variable-length column for the table's schema, locking style, and page size.
- When converting a table to a different locking scheme, the data in the source table cannot violate the limits of the target table. For example, if you attempt to convert a DOL table with more than 254 variable-length columns to an APL table, `alter table` fails because an APL table is restricted to having no more than 254 variable-length columns.
- Columns with fixed-length data (for example `char`, `binary`, and so on) have the maximum sizes shown in these two tables. The following describes the maximum row and columns lengths for an APL table:

Page Size	Maximum Row Length	Maximum Column Length
2KB (2048 bytes)	1962	1960 bytes
4KB (4096 bytes)	4010	4008 bytes
8KB (8192 bytes)	8106	8104 bytes
16KB (16384 bytes)	16298	16296 bytes

The following describes the maximum row and columns lengths for a DOL table:

Page Size	Maximum Row Length	Maximum Column Length
2KB (2048 bytes)	1964	1958 bytes
4KB (4096 bytes)	4012	4006 bytes
8KB (8192 bytes)	8108	8102 bytes
16KB (16384 bytes)	16300	16294 bytes – if table does not include any variable length columns.
16KB (16384 bytes)	16300 (subject to a max start offset of <code>varlen = 8191</code> )	8191-6-2 = 8183 bytes – if table includes at least one variable-length column.  This size includes 6 bytes for the row overhead and 2 bytes for the row-length field.

- The maximum number of bytes of variable-length data per row depends on the locking scheme for the table. The following describes the maximum size columns for an APL table:

Page Size	Maximum Row Length	Maximum Column Length
2KB (2048 bytes)	1960	1960
4KB (4096 bytes)	4008	4008
8KB (8192 bytes)	8104	8157
16KB (16384 bytes)	16296	16227

The following describes the maximum size columns for a DOL table:

Page Size	Maximum Row Length	Maximum Column Length
2KB (2048 bytes)	1960	1958
4KB (4096 bytes)	4008	4006
8KB (8192 bytes)	8157	8102
16KB (16384 bytes)	16294	16294

- You cannot use `alter table` to add a declarative or check constraint and then insert data into the table in the same batch or procedure. Either separate the `alter` and `insert` statements into two different batches or procedures, or use `execute` to perform the actions separately.
- You cannot use the following variable in `alter table` statements that include defaults:

```
declare @a int
select @a = 2
alter table t2 add c3 int
default @a
```

Doing so results in error message 154; Variable is not allowed in default.

- SQL user-defined functions are not currently supported with `create proxy table`, `create table at remote server`, or `alter table`.

### **i** Note

The execution of SQL functions requires the syntax `username.functionname()`.

## 1.9.2 alter table and Encrypted Columns

Considerations for using encrypted columns.

- When used to add or modify an encrypted column, `alter table` may take a significant amount of time if the table contains a large number of rows.
- Modifying a column for encryption may cause the row size of the table to increase.

- You cannot use `alter table` to encrypt or decrypt a column:
  - If the column belongs to a clustered or placement index. To encrypt or decrypt such a column, drop the index, alter the column, and re-create the index.
  - If the table has a trigger defined. Drop the trigger before you modify the column. Afterwards, re-create the trigger:
- If you modify the type of an encrypted column belonging to a clustered or placement index, the index is out of order, and `alter table` displays an error. Drop the index before modifying the type. Afterwards, re-create the index.
- You can encrypt these datatypes:
  - `int`, `smallint`, `tinyint`
  - `unsigned int`, `unsigned smallint`, `unsigned tinyint`
  - `bigint`, `unsigned bigint`
  - `decimal` and `numeric`
  - `float4` and `float8`
  - `money`, `smallmoney`
  - `date`, `time`, `smalldatetime`, `datetime`, `bigdatetime`
  - `char` and `varchar`
  - `unichar`, `univarchar`
  - `binary` and `varbinary`
  - `bit`
- The underlying datatype of encrypted data on disk is `varbinary`. Null values are not encrypted.
- Modifying the datatype of the encrypted column belonging to a clustered or placement index results in the index being out of order, and `alter table` displays an error. Drop the index before modifying the type, after which you re-create the index.
- `alter table` reports an error if you:
  - Change a computed column to an encrypted column, or change an encrypted column to a computed column
  - Enable a column for encryption where the column is referenced in an expression used by a computed column
  - Change a computed column to reference an encrypted column.
  - Encrypt a column that is a member of a functional index
  - Specify an encrypted column as a partition key
  - Enable a column for encryption that is already used as a partition key

### **i** Note

Referential integrity between encrypted columns is supported when the columns are encrypted with the same key. For details, see *Encrypting Data* in the *Encrypted Columns Users Guide*.

## 1.9.3 Altering a Table's Compression

Considerations for altering table compression.

- Use `set compression` to change the compression level of the table for future data inserts or updates. `set compression` does not affect existing data rows and pages that are already compressed, but does require exclusive access to the table.
- You cannot change a partition's compression level in the same command in which you are altering a table's compression level. You must perform these operations as independent commands
- You may use `set compression` with other `set` parameters.
- Changing the table's compression level affects only those partitions that do not already have an explicitly defined compression level. All partitions without an explicitly defined compression level implicitly inherit the table's compression level. For example, if you modify a table's compression level from uncompressed to row-level compression, all partitions that had a compression level of `none` do not change, but partitions for which their compression level was undefined are changed to row-level compressed.
- Altering a table's compression level does not change the compression level for existing columns. For example, if `my_table` and its columns are uncompressed, when you alter the compression level of `my_table`, its columns initially remain uncompressed. However, the SAP ASE server compresses these columns individually when they fill with enough data to trigger the compression mechanism.
- The default behavior for newly added columns depends on the table's compression setting. For compressed tables, the column's datatype determines its compression level. For uncompressed tables, new columns are uncompressed.
- You may add compressed materialized computed columns to a table or compress them later.

## 1.9.4 Altering Tables for In-Memory Row Storage

Altering a table for in-memory row storage includes some restrictions.

- You can enable `row_caching` and `snapshot_isolation` simultaneously on the same table. However, the behavior is changed for some commands issued in this environment:

Command	Row-Caching Off	Row-Caching On	snapshot_isolation Enabled
<code>insert</code>	Inserted in the page store.	New rows are inserted into the in-memory row storage.	New rows are inserted into the in-memory row storage.
<code>select</code>	Returns the row from wherever it resides.	ILM may cache rows in the in-memory row storage.	Depends on the <code>row_caching</code> subclauses.
<code>update</code>	Page store rows are updated in the page store, without row migration. Rows already in in-memory row storage are updated there.	ILM may migrate row to the in-memory row storage.	Row from the page store are migrated to, and updated in, the in-memory row storage. Rows already in the in-memory row storage are updated there.
<code>delete</code>	Page store rows are deleted from the page store,	Rows in the page store are deleted from wherever the	Rows from the page store are migrated to, and



Command	Row-Caching Off	Row-Caching On	snapshot_isolation Enabled
	without row migration. Rows already in in-memory row storage are deleted from there.	row resides. Migrated rows are deleted from the in-memory row storage. Cached rows are discarded, and the page-store version of the row is deleted.	deleted from, the in-memory row storage. Rows already in in-memory row storage are deleted from there.

- Draining all snapshot isolation queries from the table disables snapshot isolation on the table.
- You cannot disable `row_caching` or `snapshot_isolation` on tables that have not been previously enabled for row caching or snapshot isolation, respectively.
- You can set `row_caching` or `snapshot_isolation` on:
  - User-created, nontemporary datarow-locked tables in nontemporary disk-resident user databases.
  - Any system tables.
- You cannot set `row_caching` on:
  - Proxy tables
  - Views
  - Monitoring tables
  - Tables created with the `for load` parameter
- Do not combine this parameter with other `alter table... set` parameters; `row storage off` may include data movement and run for a long time.
- Migrating existing rows from in-memory row storage to page storage requires an exclusive table lock.
- Enabling `row_caching` configures the server to perform new inserts in the row store and migrates frequently selected or updated rows from the data pages to the row store. Caching frequently selected or updated rows depends on the availability of memory in the cache and other internal heuristics that track data access life cycle patterns.
- Enabling `snapshot_isolation` configures the server to perform migrate row updates or deletes from the data page to the row store (new inserts are performed in the page store).
- You can enable `row_caching` and `snapshot_isolation` simultaneously on the same table.
- Use `row storage off` parameter to remove the table's footprint from the IMRS cache. Once disabled, existing rows in the in-memory row storage are drained and moved to the page-store, making the memory available to other tables, or returning it to the system. `row storage off` involves data movement from the in-memory row storage to the page-store and may update the indexes on the affected table. `row storage off` requires exclusive access to the table while the existing rows are migrated to the page-store. You must first disable `row_caching` and `snapshot_isolation` before executing `row storage off`. Doing so stops any further activity on this table in the in-memory row storage.
- Databases must be enabled for version link cache before using snapshot isolation for a table. Individual tables can use this cache as their version link storage cache.
- All data partitions in a partitioned table use the specified version link storage cache.
- The `snapshot isolation on` parameter specifies that timestamp-based snapshot isolation level semantics are applied to `select` statements from this table. The version link storage cache assigned to this table is used to create in-memory metadata versions of the row required to support timestamp based snapshot isolation scans.
- You must have already created or altered the database to use a version link storage cache to use the `version link storage on <cache_name>` parameter to name a version link cache.

- Issuing `snapshot_isolation off` temporarily disables snapshot isolation for this table. Draining all snapshot isolation queries from the table to complete disabling snapshot isolation.
- You cannot use the `version link storage off` parameter on a multi-version concurrency control-enabled (MVCC) table. You must first disable the MVCC feature with the `set` command.
- Usage information for hash-cache indexes:
  - You cannot use the `bucket_count` parameter with any `alter table` parameter other than `index_hash_caching`.
  - You can create hash-cached indexes only on data-only locked tables.
  - Define hash caching on a unique index. If you attempt to create a hash-cached index on a non-unique index, SAP ASE issues a warning message and creates a regular BTREE index. If hash caching is on, then bucket count could be defined. But when `bucket_count=<num>` is specified, specify `index_hash_caching`, or else the command aborts and displays an error message.
  - You can define `bucket_count` when hash caching is on, but if you specify `bucket_count1=<num>`, you also have to specify `index_hash_caching`. If not, the command aborts and displays an error message.

## 1.9.5 Interactions Between Compression and Other alter table Parameters

When a command requires data movement, the SAP ASE server compresses any uncompressed data rows in the source partitions if the target partition is compressed. When you include a compression clause, `alter table` includes these interactions between the parameters.

- `set – you:`
  - Cannot combine `set` with `add`, `drop`, or `modify` clauses.
  - Cannot combine the `modify partition set` clause with other `modify <column_name>` parameters.
  - Cannot use the `all` keyword with `modify partition` and include partition names in the clause.
- `add:`
  - You may add nullable and non-nullable compressed columns to existing tables. Adding non-nullable columns requires data movement.
  - Columns added to a compressed table use row compression if they are configured for an appropriate datatype.
  - Modifying a column's datatype to one that is eligible for row compression in a compressed table does not change the column's compression level.
  - If you do not specify `not compressed` for a new column, it inherits the table's compression level. For example, if the table is row-level compressed, any column you add to the table uses row-level compression as well.
- `drop:`
  - Dropping a compressed column causes data movement.
  - If the other columns in a table or partition are not compressed, or cannot be compressed, you must change the compression state to `none` before dropping the last compressed column.
- `modify:`
  - You can modify a compressed column in an existing table to `not compressed` and vice versa.

- You can change a column's datatype simultaneously with its compression level. However, the target datatype must be eligible for row compression. If the target datatype is not eligible for compression, the SAP ASE server ignores the request to compress it during the `modify` operation.
- The SAP ASE server issues an error if you attempt to modify the compression level of a column that you cannot create as a compressed column. For example, the SAP ASE server issues an error message if you attempt to compress a virtual computed column.
- Combining `add`, `drop`, and `modify`:
  - You can issue multiple `add`, `drop`, or `modify` parameters that include one or more compressed columns in a single `alter table` statement. The data movement for this `alter table` command is dictated by the data movement restrictions for the parameters.
  - If `alter table` requires data movement, the column's compression level remains unchanged for the columns not affected by the `add`, `drop`, or `modify` parameters.
- Repartitioning a table – if you do not specify the compression clause for new partitions, the SAP ASE server sets the compression level for the new partitions as:
  - Uncompressed if the source table and all of its partitions are uncompressed.
  - The same compression level as the source table, if all of its partitions are compressed with the same compression level.
  - Uncompressed if:
    - The table or the individual partitions are compressed differently, or,
    - The source table is not compressed, but some of its partitions are
 The SAP ASE server does not compress the new partitions because it may be difficult to uniquely map and migrate the compression attribute from the original compressed partitions to the new partitions. You must explicitly state the compression level as part of the `alter table` command to specify which target partitions must be compressed during the data copy.
- `add partition` – newly added partitions inherit the table's compression level if you do not specify a partition level in the `compression` clause.
- `drop partition` – dropping a table's only compressed partition does not change the table's compression level if the table includes multiple partitions.  
If a table has been defined for compression, it remains compressed after the partition is dropped, and the SAP ASE server automatically configures future partitions for compression.
- Changing the locking scheme – the SAP ASE server requires data movement if you change the locking scheme of a table from allpages-locked to data-only-locked, or vice-versa. You cannot simultaneously change the compression level of the table or individual partitions when you change the locking scheme. Instead, you must run the `set compression` command to specify the compression level before you change the locking scheme.
- Unpartitioning a table – if at least one source partition is compressed when you unpartition a table, the entire table is marked as compressed when you run `alter table`. The SAP ASE server issues a warning message if the table was initially uncompressed.
- Other commands – you cannot combine parameters that specify the default value of a column, enable or disable triggers, add or drop column-level or table-level constraints, and so on, with commands that specify column-level or partition-level compression or copy data.
- If `alter table` does not include data movement, existing data is not affected, and the SAP ASE server applies the table's compression level to data once it is inserted. If `alter table` includes data movement, existing data is compressed or decompressed according to the table's compression level.
- These `alter table` events include data movement:
  - Adding non-null columns
  - Dropping columns

- Modifying a column to increase its length (for example, from a `smallint` to an `int`, or from `char(3)` to `varchar(45)`)
- These `alter table` events do not include data movement:
  - Adding null column
  - Adding null text column (adding a non-null text column has restrictions)
  - Modifying a variable-length column to increase its length (for example, from `varchar(5)` to `varchar(20)` or from `varchar(20)` to `varchar(40)`)
- You cannot compress proxy tables or partitions or columns on proxy tables.

## 1.9.6 Altering the Compression Level for a Table Using Large Objects

Changing the table's large object (LOB) compression level affects only the LOB columns that do not have an explicitly defined compression level. Columns without an explicitly defined compression level implicitly inherit the table's compression level.

The default behavior for newly added LOB columns for which you have not specified a LOB compression clause depends on the table's LOB compression level. For LOB compressed tables, the SAP ASE server uses the table's LOB compression level for the columns. For LOB uncompressed tables, newly added LOB columns remain uncompressed.

Interactions between compression and other `alter table` parameters for tables with LOB data:

- `drop column` – if the table includes no compressed LOB columns after dropping columns, the table uses the table-level LOB column compression level.
- `add column`
  - You can add a nullable compressed LOB column, but you cannot add a non-nullable compressed LOB column.
  - For a table not set to LOB compression, by default, newly added LOB columns are not compressed. Newly added LOB columns with LOB compression subclauses can be compressed or not compressed as specified.
- `modify column`
  - You can uncompress an existing compressed LOB column. Although newly inserted data is uncompressed, existing data remains compressed.
  - You can change the compression level of an existing LOB column. Although newly inserted data assumes the new compression level, existing data retains the original compression level.
  - You can change an uncompressed LOB column to `compressed`.
  - You cannot modify a regular column to a LOB column (compressed or uncompressed).
  - You can modify a compressed LOB column to:
    - Compressed `text` columns using `<n>char`, `<n>varchar`, `unichar`, and `univarchar`
    - Compressed `image` columns using `varbinary` and `binary`
    - Compressed `unitext` columns using `<n>char`, `<n>varchar`, `unichar`, `univarchar`, `varbinary`, and `binary`

Compressed off-row `java` columns cannot be modified to regular columns.

The SAP ASE server decompresses the LOB data, truncating the data if necessary to fit the regular column length, and converting it to the regular datatype. The maximum length of the regular column is governed by the SAP ASE server page size.

- Combinations of `add`, `drop`, `modify`, and `set lob_compression`:
  - You can issue multiple `add`, `drop`, or `modify` subcommands in a single `alter table` command—or `set lob_compression` and `set compression` subclauses—that involves one or more compressed columns.
  - If you add a column to a LOB-compressed table and include `set lob_compression = 0` in the command, the newly added column is not compressed.
  - If you add a column to a regular, uncompressed table, and include `set lob_compression = <compression_level>` in the command, the newly added column is compressed.

Existing LOB data is not affected by `alter table` commands; only future DMLs are affected by the changed LOB compression attributes. Use `update` and `select into` to compress or uncompress existing LOB data.

## 1.9.7 Getting Information About Tables

To rename a table, execute `sp_rename` (do not rename the system tables). For information about a table and its columns, use `sp_help`. For information about integrity constraints (`unique`, `primary key`, `references`, and `check`) or the `default` clause, see `create table`.

## 1.9.8 Specifying Ascending or Descending Ordering in Indexes

Use the `asc` and `desc` keywords after index column names to specify the sort order for the index. Creating indexes so that columns are in the same order specified in the `order by` clause of queries eliminates the sorting step during query processing.

See *Indexing for Performance in Performance and Tuning Guide: Basics*.

## 1.9.9 Using Cross-Database Referential Integrity Constraints

When you create a cross-database constraint, the SAP ASE server stores information in the `sysreferences` table of each database.

Information Stored in <code>sysreferences</code>	Columns with Information About the Referenced Table	Columns with Information About the Referencing Table
Key column IDs	<code>refkey1</code> through <code>refkey16</code>	<code>fokey1</code> through <code>fokey16</code>
Table ID	<code>reftabid</code>	<code>tableid</code>
Database ID	<code>pmrydbid</code>	<code>frgndbid</code>

Information Stored in <code>sysreferences</code>	Columns with Information About the Referenced Table	Columns with Information About the Referencing Table
Database name	<code>pmrydbname</code>	<code>frgndbname</code>

When you drop a referencing table or its database, the SAP ASE server removes the foreign-key information from the referenced database.

Because the referencing table depends on information from the referenced table, the SAP ASE server does not allow you to:

- Drop the referenced table,
- Drop the external database that contains the referenced table, or
- Rename either database with `sp_renamedb`.

You must first use `alter table` to remove the cross-database constraint.

Each time you add or remove a cross-database constraint, or drop a table that contains a cross-database constraint, dump *both* the affected databases.

#### ⚠ Caution

Loading earlier dumps of these databases may cause database corruption.

The `sysreferences` system table stores the name and the ID number of the external database. The SAP ASE server cannot guarantee referential integrity if you use `load database` to change the database name or to load it onto a different server.

#### ⚠ Caution

Before dumping a database to load it with a different name or move it to another SAP ASE server, use `alter table` to drop all external referential integrity constraints.

## 1.9.10 Changing Defaults

You can create column defaults either by declaring the default as a column constraint in the `create table` or `alter table` statement, or by creating the default using the `create default` statement and binding it to a column using `sp_bindefault`.

- You cannot replace a user-defined default bound to the column with `sp_bindefault`. First use `sp_unbindefault` to unbind the default.
- If you declare a default column value with `create table` or `alter table`, you cannot bind a default to that column with `sp_bindefault`. Drop the default by altering it to NULL, then bind the user-defined default. Changing the default to NULL unbinds the default and deletes it from the `sysobjects` table.

## 1.9.11 Setting Space Management Properties for Indexes

The space management properties `fillfactor`, `max_rows_per_page`, and `reservepagegap` in the `alter table` statement apply to indexes that are created for `primary key` or `unique` constraints. The space management properties affect the data pages of the table if the constraint creates a clustered index on an `allpages-locked` table.

- Use `sp_chgattribute` to change `max_rows_per_page` or `reservepagegap` for a table or an index, to change the `exp_row_size` value for a table, or to store `fillfactor` values.
- Space management properties for indexes are applied when indexes are:
  - Re-created as a result of an `alter table` command that changes the locking scheme for a table from `allpages` locking to `data-only` locking or vice versa.
  - Automatically rebuilt as part of a `reorg rebuild` command.
- To see the space management properties currently in effect for a table, use `sp_help`. To see the space management properties currently in effect for an index, use `sp_helpindex`.
- The space management properties `fillfactor`, `max_rows_per_page`, and `reservepagegap` help manage space usage for tables and indexes in the following ways:
  - `fillfactor` leaves extra space on pages when indexes are created, but the `fillfactor` is not maintained over time. It applies to all locking schemes.
  - `max_rows_per_page` limits the number of rows on a data or index page. Its main use is to improve concurrency in `allpages-locked` tables.
  - `reservepagegap` specifies the ratio of empty pages to full pages to apply for commands that perform extent allocation. It applies to all locking schemes.

You can store space management properties for tables and indexes so that they are applied during `alter table` and `reorg rebuild` commands.

- This table shows the valid combinations of space management properties and locking schemes. If an `alter table` command changes the table so that the combination is not compatible, the values stored in the stored in system tables remain there, but are not applied during operations on the table. If the locking scheme for a table changes so that the properties become valid, then they are used.

Parameter	Allpages	Datapages	Datarows
<code>max_rows_per_page</code>	Yes	No	No
<code>reservepagegap</code>	Yes	Yes	Yes
<code>fillfactor</code>	Yes	Yes	Yes
<code>exp_row_size</code>	No	Yes	Yes

- This table shows the default values and the effects of using the default values for the space management properties.

Parameter	Default	Effect of Using the Default
<code>max_rows_per_page</code>	0	Fits as many rows as possible on the page, up to a maximum of 256

Parameter	Default	Effect of Using the Default
<code>reservepagegap</code>	0	Leaves no gaps
<code>fillfactor</code>	0	Fully packs leaf pages

## 1.9.12 Conversion of `max_rows_per_page` to `exp_row_size`

If a table has `max_rows_per_page` set, and the table is converted from allpages locking to data-only locking, the value is converted to an `exp_row_size` value before the `alter table...lock` command copies the table to its new location. The `exp_row_size` is enforced during the copy.

If <code>max_rows_per_page</code> is Set to	Set <code>exp_row_size</code> to
0	Percentage value set by default <code>exp_row_size percent</code>
255	1, that is, fully packed pages
1 – 254	The smaller of: <ul style="list-style-type: none"> <li>• Maximum row size</li> <li>• <math>2002/\text{max\_rows\_per\_page}</math> value</li> </ul>

## 1.9.13 Using `reservepagegap`

Commands that use large amounts of space allocate new space by allocating an extent rather than allocating single pages. The `reservepagegap` keyword causes these commands to leave empty pages so that future page allocations take place close to the page that is being split, or to the page from which a row is being forwarded.

The `reservepagegap` value for a table is stored in `sysindexes`, and is applied when the locking scheme for a table is changed from allpages locking to data-only locking, or vice versa. To change the stored value, use `sp_chgattribute` before running `alter table`.

`reservepagegap` specified with the `clustered` keyword on an allpages-locked table overwrites any value previously specified with `create table` or `alter table`.



## 1.9.14 Partitioning Tables for Improved Performance

Use the `partition by` clause to partition an unpartitioned table or repartition an already partitioned table. The task requires a data copy; all data rows are redistributed according to the specified partition criteria.

- You may run this task in parallel if the SAP ASE server is configured for parallel processing. You must set the `select into/bulkcopy/pllsort` option to true. If the table has indexes, you must drop the indexes before you can change:
  - An unpartitioned table into a semantic-partitioned table.
  - The partitioning type.
  - The partitioning key – you need not drop indexes to change other attributes of the partitions, such as number of partitions, partition bounds, or partition location; the indexes are built automatically.
- You can use the `add partition` clause to add empty partitions to list- or range-partitioned tables, but not to hash or round-robin-partitioned tables. For range-partitioned tables, you can add new partitions only to the high end of the partition conditions. If the last existing partition has the maximum boundary (`values <= (MAX)`), you cannot add new partitions.
- The `partition <number_of_partition>` and `unpartition` clauses are provided for compatibility with versions of SAP ASE earlier than 15.0. You can use `partition <number_of_partition>` only on unpartitioned tables to add (`<number_of_partition>-1`) empty round-robin partitions; existing data is placed on the first partition, with subsequent data distributed among all partitions. If the table has a global clustered index, the SAP ASE server places subsequent data rows in the first partition. To redistribute the data, drop and re-create the index.

### Note

These commands do not require data movement. However, because the SAP ASE server performs a number of internal steps, the commands, especially when executed on large tables, do not occur instantly. To avoid data corruption, do not interrupt the operation while you partition or unpartition a table.

You can use the `unpartition` clause only on round-robin-partitioned tables without indexes.

- You cannot partition system tables.
- You cannot partition remote proxy tables.
- You cannot issue the partition-related `alter table` commands within a user-defined transaction.
- You cannot change a table's partitioning properties using the `partition by` clause if there are active open cursors on the table.
- After using the `partition by` clause, you must perform a full database dump before you can use `dump transaction`.
- You cannot drop a column that is part of a partitioning key.
- Alter key columns with care. In some cases, modifying the datatype of a key column might redistribute data among partitions. See the *Transact-SQL Users Guide*.
- Changing a table's partitioning properties increments the schema count, which causes existing stored procedures that access this table to recompile the next time they are executed.

## 1.9.15 Using Computed Columns

Considerations when using computed columns.

- When you add a new computed column without specifying nullability and the materialization property, the default option is nullable and not materialized.
- When you add a new materialized computed column, the `<computed_column_expression>` is evaluated for each existing row in the table, and the result is stored in the table.
- You cannot add new computed columns and add or modify their base columns at the same time.
- You can modify the entire definition of an existing computed column. This is a quick way to drop the computed column and add a new one with the same name. Such a column behaves like a new computed column: its defaults are not materialized and nullable, if you do not specify these options.
- You can modify the materialization property of an existing computed column without changing its other properties, such as the expression that defines it or its nullability.
- When you modify a not-null, materialized computed column into a virtual column, you must specify "null" in the `modify` clause.
- When you modify a computed column that is not materialized, to materialize it, the `<computed_column_expression>` is evaluated for each existing row in the table, and the result is stored in the table.
- If you modify existing columns that are index keys, the index is rebuilt.
- You cannot modify a materialized computed column into a virtual column if it has been used as an index key; you must first drop the index.
- You cannot modify a regular column to become a computed column, or a computed column to become a regular column.
- You cannot modify or drop the base column referenced by a computed column.
- You cannot drop a computed column if it is used as an index key.

## 1.9.16 Adding IDENTITY Columns

Considerations for adding an IDENTITY column.

- When adding a `numeric` or integer IDENTITY column to a table, make sure the column precision is large enough to accommodate the number of existing rows. If the number of rows exceeds  $10^{\text{precision}} - 1$ , the SAP ASE server prints an error message and does not add the column.
- When adding an IDENTITY column to a table, the SAP ASE server:
  - Locks the table until all the IDENTITY column values have been generated. If a table contains a large number of rows, this process may be time-consuming.
  - Assigns each existing row a unique, sequential IDENTITY column value, beginning with 1.
  - Logs each insert operation into the table. Use `dump transaction` to clear the database's transaction log before adding an IDENTITY column to a table with a large number of rows.
- Each time you insert a row into the table, the SAP ASE server generates an IDENTITY column value that is one higher than the value. This value takes precedence over any defaults declared for the column in the `alter table` statement or bound to it with `sp_bindefault`.

## 1.9.17 Altering Table Schema

Considerations for altering the table schema.

- `add`, `drop`, `modify`, and `lock` subclauses are useful when changing an existing table's schema. A single statement can contain any number of these subclauses, in any order, as long as the same column name is not referenced more than once in the statement.
- If stored procedures using `select *` reference a table that has been altered, no new columns appear in the result set, even if you use the `with recompile` option. You must drop the procedure and re-create it to include these new columns.
- To ensure that triggers fire properly, drop and re-create all triggers on an altered table after you perform an `add`, `drop`, `modify`, or `lock` operation.
- The SAP ASE server issues an error message if you try to add a `not null` column without a default value. This rule has one exception: if you add a user-defined type column, and the type has a default bound to it, you need not specify a default clause.
- You cannot drop all the columns in a table. Also, you cannot drop the last remaining column from a table (for example, if you drop four columns from a five-column table, you cannot then drop the remaining column). To remove a table from the database, use `drop table`.
- A data copy is required:
  - To drop a column
  - To add a NOT NULL column
  - For most `alter table ... modify` commands

Use `set noexec on` and `showplan on` options to determine if a data copy is required for a particular `alter table` command.

- You can specify a change in the locking scheme for the modified table with other `alter table` commands (`add`, `drop`, or `modify`) when the other `alter table` command requires a data copy.
- If `alter table` performs a data copy, `select into /bulkcopy/pllsort` must be turned on in the database that includes the table whose schema you are changing.
- The modified table retains the existing space management properties (`max_rows_per_page`, `fillfactor`, and so on) and indexes of the table.
- `alter table` that requires a data copy does not fire any triggers.
- You can use `alter table` to change the schema of remote proxy tables created and maintained by CIS. See the *Component Integration Services Users Guide*.
- You cannot perform a data copy and add a table level or referential integrity constraint in the same statement.
- You cannot perform a data copy and create a clustered index in the same statement.
- You can always add, drop, or modify a column in allpages-locked tables. However, there are restrictions for adding, dropping, or modifying a column in a data-only-locked table, which are described in the following table:

Type of Index	All Pages Locked, Partitioned Table	All Pages Locked, Unpartitioned Table	Data-Only-Locked, Partitioned Table	Data-Only-Locked, Unpartitioned Table
Clustered	Yes	Yes	No	Yes
Nonclustered	Yes	Yes	Yes	Yes

If you need to add, drop, or modify a column in a data-only-locked table partitioned with a clustered index, you can:

1. Drop the clustered index.
  2. Alter the data-only-locked table.
  3. Re-create the clustered index.
- You cannot add a NOT NULL Java object as a column. By default, all Java columns always have a default value of NULL, and are stored as either `varbinary` strings or as `image` datatypes.
  - You cannot modify a partitioned table that contains a Java column if the modification requires a data copy. Instead, first unpartition the table, execute `alter table`, then repartition the table.
  - You cannot drop the key column from an index or a referential integrity constraint. To drop a key column, first drop the index or referential integrity constraint, then drop the key column. See the *Transact-SQL Users Guide*.
  - You can drop columns that have defaults or rules bound to them. Any column-specific defaults are also dropped when you drop the column. You cannot drop columns that have check constraints or referential constraints bound to them. Instead, first drop the check constraint or referential constraint, then drop the column. Use `sp_helpconstraint` to identify any constraints on a table, and use `sp_depends` to identify any column-level dependencies.
  - You cannot drop a column from a system table. Also, you cannot drop columns from user tables that are created and used by SAP-provided tools and stored procedures.
  - You can generally modify the datatype of an existing column to any other datatype if the table is empty. If the table is not empty, you can modify the datatype to any datatype that is explicitly convertible to the original datatype.
  - You can:
    - Add a new IDENTITY column.
    - Drop an existing IDENTITY column.
    - Modify the size of an existing IDENTITY.See the *Transact-SQL Users Guide* for more information.
  - Altering the schema of a table increments the schema count, causing existing stored procedures that access this table to be renormalized the next time they are executed. Changes in datatype-dependent stored procedures or views may fail with datatype normalization errors. Update these dependent objects so they refer to the modified schema of the table.

## 1.9.18 Restrictions for Modifying a Table Schema

Restrictions when modifying table schema.

- You cannot run `alter table` from inside a transaction.
- Altering a table's schema can invalidate backups that you made using `bcp`. These backups may use a table schema that is no longer compatible with the table's current schema.
- You can add NOT NULL columns with check constraints, however, the SAP ASE server does not validate the constraint against existing data.
- You cannot change the locking scheme of a table using the `alter table . . . add, drop, or modify` commands if the table has a clustered index and the operation requires a data copy. Instead you can
  1. Drop the clustered index.
  2. Alter the table's schema.

3. Re-create the clustered index.
- You cannot alter a table's schema if there are any active open cursors on the table.

## 1.9.19 Restrictions for Modifying text and image Columns

Restrictions that apply when you modify `text` and `image` columns.

- You can only add `text` or `image` columns that accept null values.  
To add a `text` or `image` column so it contains only non-null values, first add a column that only accepts null values and then update it to the non-null values.
- You can modify a column from `text` datatype only to the following datatypes:
  - `[n]char`
  - `[n]varchar`
  - `unichar`
  - `univarchar`
  - `nchar`
  - `nvarchar`
- You can modify a column from `image` datatype only to `binary` or `varbinary`.
- You cannot add a new `text` or `image` column and then drop an existing `text` or `image` column in the same statement.
- You cannot modify a column to either `text` or `image` datatype.

## 1.9.20 Modifying Tables With Unitext Columns

Restrictions that apply when you use `alter table` to modify `unitext` columns.

- You can add a new `unitext` column that accepts NULL values.
- You can modify a column from `unitext` only to the following datatypes:
  - `[n]char`
  - `[n]varchar`
  - `unichar`
  - `univarchar`
  - `binary`
  - `varbinary`
- You cannot modify a column to the `unitext` datatype.
- You cannot add a `unitext` column and drop an existing `unitext` column in the same statement.

## 1.9.21 Changing Locking Schemes

`alter table` supports changing from any locking scheme to any other locking scheme.

- You can change:
  - From allpages to datapages or vice versa
  - From allpages to datarows or vice versa
  - From datapages to datarows or vice versa
- Before you change from allpages locking to a data-only locking scheme, or vice versa, use `sp_dboption` to set the database option `select into/bulkcopy/pllsort` to true, then run `checkpoint` in the database if any of the tables are partitioned and the sorts for the indexes require a parallel sort.
- After changing the locking scheme from allpages-locking to data-only locking or vice versa, you cannot use the `dump transaction` command to back up the transaction log; you must first perform a full database dump.
- When you use `alter table...lock` to change the locking scheme for a table from allpages locking to data-only locking or vice versa, the SAP ASE server makes a copy of the table's data pages. There must be enough room on the segment where the table resides for a complete copy of the data pages. There must be space on the segment where the indexes reside to rebuild the indexes.  
Clustered indexes for data-only-locked tables have a leaf level above the data pages. If you are altering a table with a clustered index from allpages-locking to data-only-locking, the resulting clustered index requires more space. The additional space required depends on the size of the index keys.  
Use `sp_spaceused` to determine how much space is currently occupied by the table, and use `sp_helpsegment` to see the space available to store the table.
- When you change the locking scheme for a table from allpages locking to datapages locking or vice versa, the space management properties are applied to the tables, as the data rows are copied, and to the indexes, as they are re-created. When you change from one data-only locking scheme to another, the data pages are not copied, and the space management properties are not applied.
- If a table is partitioned, changing the locking scheme performs a partition-to-partition copy of the rows. It does not balance the data on the partitions during the copy.
- When you change the locking scheme for a table, the `alter table...lock` command acquires an exclusive lock on the table until the command completes.
- When you use `alter table...lock` to change from datapages locking to datarows locking, the command does not copy data pages or rebuild indexes. It updates only system tables.
- Changing the locking scheme while other users are active on the system may have the following effects on user activity:
  - Query plans in the procedure cache that access the table are recompiled the next time they are run.
  - Active multistatement procedures that use the table are recompiled before continuing with the next step.
  - Ad hoc batch transactions that use the table are terminated.

### ⚠ Caution

Changing the locking scheme for a table while a bulk-copy operation is active can cause table corruption. Bulk copy operates by first obtaining information about the table and does not hold a lock between the time it reads the table information and the time it starts sending rows, leaving a small window of time for an `alter table...lock` command to start.

## 1.9.22 Adding Java-SQL Columns

If Java is enabled in the database, you can add Java-SQL columns to a table.

The declared class (`<datatype>`) of the new Java-SQL column must implement either the `Serializable` or `Externalizable` interface.

When you add a Java-SQL column to a table, the Java-SQL column cannot be specified:

- As a foreign key
- In a references clause
- As having the `UNIQUE` property
- As the primary key

If you specify:

- `in row` – the value stored cannot exceed 16KB, depending on the page size of the data server.
- `loff row` – the column cannot be:
  - Referenced in a check constraint
  - Referenced in a `select` that specifies `distinct`
  - Specified in a comparison operator, in a predicate, or in a `group by` clause

See *Java in Adaptive Server Enterprise*.

## 1.9.23 Restrictions for Shared-Disk Clusters

A referential integrity constraint cannot reference a column on a local temporary database except from a table on the same local temporary database. `alter table` fails when it attempts to create a reference to a column on a local temporary database from a table in another database.

You cannot encrypt a column with an encryption key stored in a local temporary database unless the column's table resides on the same local temporary database. `alter table` fails if it attempts to encrypt a column with an encryption key on the local temporary database and the table is in another database.

## 1.10 alter thread pool

Alters a thread pool.

### Considerations for Process Mode

`alter thread pool` is not supported in process mode.

## Syntax

```
alter thread pool <pool_name> with {pool name = "<new_name>"
  thread count = <thread_count>,
  [pool description = "<description>"]}
[idle timeout = <time_period>]
[for instance <inst_name> | global]
```

## Parameters

**<pool\_name>**

name of the thread pool you are altering.

**pool name = "<new\_name>"**

new name for the pool you are altering.

**thread count = <thread\_count>**

new number of threads in the thread pool. Must be greater than or equal to 1.

**pool description = "<description>"**

describes the pool's purpose. Must be fewer than 256 characters.

**idle timeout = <time\_period>**

time, in microseconds, that threads look for work before going to sleep. A value of -1 means the threads never go to sleep, and continue to consume CPU if no work is available. A value of 0 indicates that threads immediately go to sleep if they find no work.

**for instance [<inst\_name> | global]**

is name of the instance, or global for all instances.

## Examples

### Example 1

Renames the `order_pool` thread pool to `sales_pool`:

```
alter thread pool order_pool with pool name = 'sales_pool'
```

### Example 2

Modifies the `sales_pool` thread pool to contain seven threads:

```
alter thread pool sales_pool with thread count = 7
```

### Example 3

Modifies the name and description for `sales_pool`:

```
alter thread pool sales_pool with pool name = "larger_sales_pool", pool
```



```
description = 'thread pool exclusive to sales group'
```

#### Example 4

Modify `sales_pool` so threads sleep if they find no work after 500 microseconds:

```
alter thread pool order_pool with idle timeout = 500
```

#### Example 5

Modify `sales_pool` so threads never go to sleep if they find no work:

```
alter thread pool order_pool with idle timeout = -1
```

## Usage

- `<thread_count>` must be greater than or equal to 1.
- When you reduce a thread count, the thread pool you specify must wait for currently running tasks to yield before it reduces the number of threads, which may cause a slight delay in the SAP ASE server shrinking the pool.
- You cannot rename system-created thread pools (which begin with `syb_`). However, you can use `alter thread pool` to change the number of threads or idle timeout in system-created thread pools.
- You cannot use Transact-SQL variables as parameters with `alter thread pool`.
- You can set `idle timeout` only for engine thread pools.
- You may issue `alter thread pool` with `execute immediate`.

## Standards

ANSI SQL – Compliance level: Transact-SQL extension

## Permissions

The permission checks for `alter thread pool` differ based on your granular permissions settings.

Setting	Description
---------	-------------

Enabled	With granular permissions enabled, you must have the <code>manage any thread pool</code> privilege.
---------	---

Disabled	With granular permissions disabled, you must have <code>sa_role</code> .
----------	--

`alter thread pool` permission is not included in the `grant all` command.

## Auditing

You can enable `thread_pool` auditing option to audit this command. Values in `event` and `extrainfo` columns from the `sysaudits` table are:

Information	Value
Audit option	<code>alter</code>
Event	143
Command or access audited	<code>thread_pool</code>
Information in <code>extrainfo</code>	<ul style="list-style-type: none"><li>• <b>Roles</b> – current active roles</li><li>• <b>Full command text</b> – full text of <code>alter thread pool</code> command</li><li>• <b>Previous value</b> – NULL</li><li>• <b>Current value</b> – NULL</li><li>• <b>Other information</b> – NULL</li><li>• <b>Proxy information</b> – original login name, if <code>set proxy</code> is in effect</li></ul>

Full command text is included in `extrainfo`. For example:

```
sa_role sybase_ts_role mon_role;
alter thread pool order_pool
with pool name = 'sales_pool'; ; ; ; user0/ase;
```

For more information about auditing, see *Security Administration Guide > Auditing*.

## Related Information

[create thread pool \[page 320\]](#)

[drop thread pool \[page 460\]](#)

## 1.11 begin...end

Encloses a series of SQL statements so that control-of-flow language, such as `if...else`, can affect the performance of the entire group.

### Syntax

```
begin
  <statement block>
end
```

## Parameters

### <statement block>

is a series of statements enclosed by `begin` and `end`.

## Examples

### Example 1

Without `begin` and `end`, the `if` condition would cause execution of only one SQL statement:

```
if (select avg (price) from titles) < $15
begin
  update titles
  set price = price * $2
  select title, price
  from titles
  where price > $28
end
```

### Example 2

Without `begin` and `end`, the `print` statement would not execute:

```
create trigger deltitle
on titles
for delete
as
if (select count (*) from deleted, salesdetail
  where salesdetail.title_id = deleted.title_id) > 0
  begin
    rollback transaction
    print "You can't delete a title with sales."
  end
else
  print "Deletion successful--no sales for this
  title."
```

## Usage

`begin...end` blocks can nest within other `begin...end` blocks.

## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

## Permissions

No permission is required to use `begin...end`.

## Auditing

This command is not audited.

## Related Information

[if...else \[page 569\]](#)

## 1.12 begin transaction

Marks the starting point of a user-defined transaction.

### Syntax

```
begin tran[saction] [<transaction_name>]
```

### Parameters

**<transaction\_name>**

is the name assigned to this transaction. Transaction names must conform to the rules for identifiers. Use transaction names only on the outermost pair of nested `begin transaction/commit` or `begin transaction/rollback` statements.

## Examples

### Example 1

Explicitly begins a transaction for the `insert` statement:

```
begin transaction
  insert into publishers (pub_id) values ("9999")
commit transaction
```

## Usage

- Define a transaction by enclosing SQL statements and system procedures within the phrases `begin transaction` and `commit`. If you set chained transaction mode, the SAP ASE server implicitly invokes a `begin transaction` before the following statements: `delete`, `insert`, `open`, `fetch`, `select`, and `update`. You must still explicitly close the transaction with a `commit`.
- To cancel all or part of a transaction, use the `rollback` command. The `rollback` command must appear within a transaction; you cannot roll back a transaction after it is committed.

## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

## Permissions

No permission is required to use `begin transaction`.

## Auditing

This command is not audited.

## Related Information

[commit \[page 123\]](#)

[delete \[page 391\]](#)

[insert \[page 572\]](#)

[open \[page 628\]](#)

[fetch \[page 513\]](#)  
[select \[page 696\]](#)  
[update \[page 819\]](#)  
[commit \[page 123\]](#)  
[rollback \[page 690\]](#)  
[save transaction \[page 694\]](#)

## 1.13 break

Causes an exit from a while loop. `break` is often activated by an `if` test.

### Syntax

```
while <logical_expression>
    <statement>
break
    <statement >
continue
```

### Parameters

#### <logical\_expression>

is an expression (a column name, constant, any combination of column names and constants connected by arithmetic or bitwise operators, or a subquery) that returns TRUE, FALSE, or NULL. If the logical expression contains a `select` statement, enclose the `select` statement in parentheses.

### Examples

#### Example 1

If the average price is less than \$30, double the prices. Then, select the maximum price; if it is less than or equal to \$50, restart the `while` loop and double the prices again. If the maximum price is more than \$50, exit the `while` loop and print a message:

```
while (select avg (price) from titles) < $30
begin
    update titles
    set price = price * 2
    select max (price) from titles
```

```
if (select max (price) from titles) > $50
    break
else
    continue
end
begin
    print "Too much for the market to bear"
end
```

## Usage

- `break` causes an exit from a `while` loop. Statements that appear after the keyword `end`, which marks the end of the loop, are then executed.
- If two or more `while` loops are nested, the inner `break` exits to the next outermost loop. First, all the statements after the end of the inner loop run; then, the next outermost loop restarts.

## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

## Permissions

No permission is required to use `break`.

## Auditing

This command is not audited.

## Related Information

[continue \[page 136\]](#)

[select \[page 696\]](#)

[while \[page 863\]](#)

## 1.14 checkpoint

Writes all dirty pages (that is, pages that have been updated since they were last written) to the database device.

### Syntax

```
checkpoint [all | [<dbname>[, <dbname>, <dbname>, ...]]
```

### Examples

#### Example 1

Writes all dirty pages in the current database to the database device, regardless of the system checkpoint schedule:

```
checkpoint
```

### Usage

There are additional considerations when using `checkpoint`:

- You can use `checkpoint` with an archive database, however, the checkpoint process does not automatically checkpoint an archive database.
- Use `checkpoint` only as a precautionary measure in special circumstances.
- `sp_dboption` automatically defaults to using `checkpoint` when you change a database option.
- You can specify one or more databases to run `checkpoint`.
- Issuing a `checkpoint` does not affect the contents of the row storage cache in an in-memory row storage-enabled database.

Automatic checkpoints:

- Checkpoints caused by the `checkpoint` command supplement automatic checkpoints, which occur at intervals calculated by the SAP ASE server on the basis of the configurable value for maximum acceptable recovery time.
- `checkpoint` shortens the automatic recovery process by identifying a point at which all completed transactions are guaranteed to have been written to the database device. A typical `checkpoint` takes about 1 second, although checkpoint time varies, depending on the amount of activity on the SAP ASE server.
- The automatic `checkpoint` interval is calculated by the SAP ASE server on the basis of system activity and the recovery interval value in the system table `syscurconfigs`. The recovery interval determines



`checkpoint` frequency by specifying the maximum amount of time it should take for the system to recover. Reset this value by executing `sp_configure`.

- You can configure the SAP ASE server with multiple checkpoint processes. This allows the SAP ASE server with multiple engines to checkpoint tasks more frequently, thereby shortening the automatic recovery process.
- If the housekeeper task can flush all active buffer pools in all configured caches during the server's idle time, it wakes up the checkpoint task. The checkpoint task determines whether it can checkpoint the database.

Checkpoints that occur as a result of the housekeeper task are known as free checkpoints. They do not involve writing many dirty pages to the database device, since the housekeeper task has already done this work. They may improve recovery speed for the database.

See also `sp_configure`, `sp_dboption` in .

## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

## Permissions

The permission checks for `checkpoint` differ based on your granular permissions settings. Reference Manual: Procedures

Setting	Description
---------	-------------

<b>Enabled</b>	With granular permissions enabled:
----------------	------------------------------------

- To execute `checkpoint` on a particular database, you must be the database owner or have either the `checkpoint` or `own database` (on the database) privilege.
- To execute `checkpoint all`, you must be the database owner of all applicable databases or have either the `checkpoint any database` privilege or `own and database` privilege. Otherwise, `checkpoint all` runs against those databases in which you have permission to run `checkpoint`.

<b>Disabled</b>	With granular permissions disabled:
-----------------	-------------------------------------

- To execute `checkpoint <database>`, you must be the database owner or be a user with `sa_role`, `replication_role`, or `oper_role`.
- To execute `checkpoint all`, you must be the database owners of all applicable databases or a user with either `sa_role` or `replication_role`. Otherwise, `checkpoint all` only runs against those database you own.

## Auditing

This command is not audited.

## 1.15 close

Deactivates a cursor.

### Syntax

```
close <cursor_name>
```

### Parameters

**<cursor\_name>**

is the name of the cursor to close.

### Examples

#### Example 1

Closes the cursor named `authors_crshr`:

```
close authors_crshr
```

### Usage

- The `close` command essentially removes the cursor's result set. The cursor position within the result set is undefined for a closed cursor.
- The SAP ASE server returns an error message if the cursor is already closed or does not exist.

## Standards

ANSI SQL – Compliance level: Entry-level compliant.

## Permissions

No permission is required to use `close`.

## Auditing

This command is not audited.

## Related Information

[deallocate cursor \[page 379\]](#)

[declare cursor \[page 384\]](#)

[fetch \[page 513\]](#)

[open \[page 628\]](#)

## 1.16 commit

Marks the ending point of a user-defined transaction.

## Syntax

```
commit [tran | transaction | work] [<transaction_name>]
```

## Parameters

**tran | transaction | work**

specifies that you want to commit the transaction or the work. If you specify `tran`, `transaction`, or `work`, you can also specify a is the name assigned to the transaction.

It must conform to the rules for identifiers. Use transaction names only on the outermost pair of nested `<transaction_name>`.

`<transaction_name>`

begin transaction/commit or begin transaction/rollback statements.

## Examples

### Example 1

After updating the `royaltyper` is the name assigned to the transaction. It must conform to the rules for entries for the two authors, insert the savepoint `percentchanged`, then determine how a 10 percent increase in the book's price would affect the authors' royalty earnings. The transaction is rolled back to the savepoint with the `rollback transaction` command:

```
begin transaction royalty_change
update titleauthor
  set royaltyper = 65 from titleauthor, titles
  where royaltyper = 75
  and titleauthor.title_id = titles.title_id
  and title = "The Gourmet Microwave"
update titleauthor
  set royaltyper = 35 from titleauthor, titles
  where royaltyper = 25
  and titleauthor.title_id = titles.title_id
  and title = "The Gourmet Microwave"
save transaction percentchanged
update titles
  set price = price * 1.1
  where title = "The Gourmet Microwave"

select (price * total_sales) * royaltyper
  from titles, titleauthor
  where title = "The Gourmet Microwave"
  and titles.title_id = titleauthor.title_id

rollback transaction percentchanged

commit transaction
```

## Usage

- Define a transaction by enclosing SQL statements and system procedures with the phrases `begin transaction` and `commit`. If you set the chained transaction mode, the SAP ASE server implicitly invokes a `begin transaction` before the following statements: `delete`, `insert`, `open`, `fetch`, `select`, and `update`. You must still explicitly enclose the transaction with a `commit`.
- To cancel all or part of an entire transaction, use the `rollback` command. The `begin transaction` command must appear within a transaction. You cannot roll back a transaction after the `commit` has been entered.
- If no transaction is currently active, the `commit` or `rollback` statement has no effect on the SAP ASE server.

## Standards

ANSI SQL – Compliance level: Entry-level compliant.

The `commit transaction` and `commit tran` forms of the statement are Transact-SQL extensions.

## Permissions

No permission is required to use `commit`.

## Auditing

This command is not audited.

## Related Information

[begin transaction \[page 116\]](#)

[delete \[page 391\]](#)

[insert \[page 572\]](#)

[open \[page 628\]](#)

[fetch \[page 513\]](#)

[select \[page 696\]](#)

[update \[page 819\]](#)

[rollback \[page 690\]](#)

[save transaction \[page 694\]](#)

## 1.17 compute Clause

Generates summary values that appear as additional rows in the query results.

The sections that describe this command are:

- [Syntax \[page 126\]](#)
- [Parameters \[page 126\]](#)
- [Examples \[page 126\]](#)
- [Usage \[page 129\]](#)
- [Standards \[page 130\]](#)
- [Auditing \[page 130\]](#)

## Syntax

```
<start_of_select_statement>  
compute <row_aggregate> (<column_name>  
[, row_aggregate (<column_name>)]...  
[by <column_name>[, <column_name>]...]
```

## Parameters

### <row\_aggregate>

is one of the following:

- `sum` – is the total of values in the (numeric) column.
- `avg` – is the average of values in the (numeric) column.
- `min` – is the lowest value in the column.
- `max` – is the highest value in the column.
- `count` – is the number of values in the column as an `integer`.
- `count` – is the number of values in the column as a `bigint`.

### <column\_name>

is the name of a column, which must be enclosed in parentheses. You can use numeric columns only with `sum` and `avg`. You can only use `integer`, `numeric`, and `decimal` columns with `sum` and `avg`.

### `by`

calculates the row aggregate values for subgroups. Whenever the value of the `by` item changes, row aggregate values are generated. If you use `by`, you must use `order by`.

Listing more than one item after `by` breaks a group into subgroups and applies a function at each level of grouping.

## Examples

### Example 1

Calculates the sum of the prices of each type of cookbook that costs more than \$12:

```
select type, price  
  from titles  
  where price > $12  
         and type like "%cook"  
         order by type, price  
  compute sum (price) by type
```

type	price
mod_cook	19.99
	sum

```

-----
type          price
-----
trad_cook    14.99
trad_cook    20.95
              sum
-----
              35.94
(5 rows affected)

```

### Example 2

Calculates the sum of the prices and advances for each type of cookbook that costs more than \$12, with one `compute` clause applying several aggregate functions to the same set of grouping columns:

```

select type, price, advance
  from titles
 where price > $12
   and type like "%cook"
 order by type, price
 compute sum (price), sum (advance) by type

```

```

type          price          advance
-----
mod_cook      19.99              0.00
              sum
-----
              19.99              0.00

type          price          advance
-----
trad_cook     14.99           8,000.00
trad_cook     20.95           7,000.00
              sum
-----
              35.94           15,000.00
(5 rows affected)

```

### Example 3

Calculates the sum of the prices and maximum advances of each type of cook book that costs more than \$12, with one `compute` clause applying several aggregate functions to the same set of grouping columns:

```

select type, price, advance
  from titles
 where price > $12
   and type like "%cook"
 order by type, price
 compute sum (price), max (advance) by type

```

```

type          price          advance
-----
mod_cook      19.99              0.00
              sum
-----
              19.99
              max
-----
              0.00

```

```

type          price          advance
-----
trad_cook     14.99           8,000.00
trad_cook     20.95           7,000.00
              sum

```

```

-----
          35.94
                max
                -----
                    8,000.00
(5 rows affected)

```

#### Example 4

Breaks on `type` and `pub_id` and calculates the sum of the prices of psychology books by a combination of type and publisher ID:

```

select type, pub_id, price
  from titles
 where price > $10
   and type = "psychology"
  order by type, pub_id, price
 compute sum (price) by type, pub_id
type      pub_id      price
-----
psychology 0736         10.95
psychology 0736         19.99
                sum
                -----
                    30.94

type      pub_id      price
-----
psychology 0877         21.59
                sum
                -----
                    21.59
(5 rows affected)

```

#### Example 5

Calculates the grand total of the prices of psychology books that cost more than \$10 in addition to calculating sums by `type` and `pub_id`, using more than one `compute` clause to create more than one group:

```

select type, pub_id, price
  from titles
 where price > $10
   and type = "psychology"
  order by type, pub_id, price
 compute sum (price) by type, pub_id
 compute sum (price) by type
type      pub_id      price
-----
psychology 0736         10.95
psychology 0736         19.99
                sum
                -----
                    30.94

type      pub_id      price
-----
psychology 0877         21.59
                sum
                -----
                    21.59
                sum
                -----
                    52.53
(6 rows affected)

```



### Example 6

Calculates the grand totals of the prices and advances of cook books that cost more than \$10:

```
select type, price, advance
  from titles
  where price > $10
        and type like "%cook"
  compute sum (price), sum (advance)
type           price           advance
-----
mod_cook       19.99             0.00
trad_cook      20.95           8,000.00
trad_cook      11.95           4,000.00
trad_cook      14.99           7,000.00
              sum           sum
-----
              67.88           19,000.00
(5 rows affected)
```

You can use `compute` without `by` to generate grand totals, grand counts, and so on. `order by` is optional if you use the `compute` keyword without `by`.

### Example 7

Calculates the sum of the price of cook books and the sum of the price used in an expression:

```
select type, price, price*2
  from titles
  where type like "%cook"
  compute sum (price), sum (price*2)
type           price
-----
mod_cook       19.99           39.98
mod_cook        2.99            5.98
trad_cook      20.95           41.90
trad_cook      11.95           23.90
trad_cook      14.99           29.98
              sum           sum
=====
              70.87           141.74
```

## Usage

- The `compute` clause allows you to see the detail and summary rows in one set of results. You can calculate summary values for subgroups, and you can calculate more than one aggregate for the same group.
- You can use `compute` without `by` to generate grand totals, grand counts, and so on. `order by` is optional if you use the `compute` keyword without `by`.
- If you use `compute`, you must also use an `order by` clause. The columns listed after `compute` must be identical to or a subset of those listed after `order by` and must be in the same left-to-right order, start with the same expression, and cannot skip any expressions. For example, if the `order by` clause is `order by a, b, c`, the `compute` clause can be any (or all) of these:

```
compute by a, b, c
compute by a
compute by a, b
```

See also `avg`, `count`, `max`, `min`, `sum` in *Reference Manual: Building Block*.

## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

## Auditing

The command is not audited.

## Related Information

[group by and having Clauses \[page 558\]](#)

[select \[page 696\]](#)

### 1.17.1 compute Clause Restrictions

Restrictions for the `compute` clause.

- You cannot use more than 127 aggregate columns in a `compute` clause.
- You cannot use a `compute` clause in a cursor declaration.
- You can compute summary values for both expressions and columns. Any expression or column that appears in the `compute` clause must appear in the `select` list.
- Aliases for column names are not allowed as arguments to the row aggregate in a `compute` clause, although you can use them in the `select` list, the `order by` clause, and the `by` clause of `compute`.
- In a `select` statement with a `compute` clause, the order of columns in the `select` list overrides the order of the aggregates in the `compute` clause. Open Client™, JDBC, and DB-Library™ programmers must be aware of this in order to put the aggregate results in the right place.
- You cannot use `select into` in the same statement as a `compute` clause, because statements that include `compute` do not generate normal tables.
- If a `compute` clause includes a `group by` clause:
  - The `compute` clause cannot contain more than 255 aggregates.
  - The `group by` clause cannot contain more than 255 columns.
- Columns included in a `compute` clause cannot be longer than 255 bytes.

## 1.17.2 compute Results Appear as a New Row or Rows

The aggregate functions ordinarily produce a single value for all the selected rows in the table or for each group, and these summary values are shown as new columns.

For example:

```
select type, sum (price), sum (advance)
from titles
where type like "%cook"
group by type
```

```
type
-----
mod_cook          22.98  15,000.00
trad_cook         47.89  19,000.00
(2 rows affected)
```

The compute clause allows you to retrieve detail and summary rows with one command. For example:

```
select type, price, advance
from titles
where type like "%cook"
order by type
compute sum (price), sum (advance) by type
```

```
type      price      advance
-----
mod_cook    2.99      15,000.00
mod_cook   19.99         0.00
Compute Result:
-----
                22.98      15,000.00
type      price      advance
-----
trad_cook   11.95      4,000.00
trad_cook   14.99      8,000.00
trad_cook   20.95      7,000.00
Compute Result:
-----
                47.89      19,000.00
(7 rows affected)
```

The output and grouping of different types of compute clauses are:

Clauses and Grouping	Output	Examples
One compute clause, same function	One detail row	1, 2, 4, 6, 7
One compute clause, different functions	One detail row per type of function	3
More than one compute clause, same grouping columns	One detail row per compute clause; detail rows together in the output	Same results as having one compute clause with different functions
More than one compute clause, different grouping columns	One detail row per compute clause; detail rows in different places, depending on the grouping	5

## 1.17.3 Case-Sensitivity

If your server has a case-insensitive sort order installed, `compute` ignores the case of the data in the columns you specify.

For example, given this data:

```
select * from groupdemo
```

lname	amount
Smith	10.00
smith	5.00
SMITH	7.00
Levi	9.00
Lévi	20.00

`compute` by on `lname` produces these results:

```
select lname, amount from groupdemo
order by lname
compute sum (amount) by lname
```

lname	amount
Levi	9.00
Compute Result:	
	9.00

lname	amount
Lévi	20.00
Compute Result:	
	20.00

lname	amount
smith	5.00
SMITH	7.00
Smith	10.00
Compute Result:	
	22.00

The same query on a case- and accent-insensitive server produces these results:

lname	amount
Levi	9.00
Lévi	20.00
Compute Result:	
	29.00

lname	amount
smith	5.00
SMITH	7.00
Smith	10.00
Compute Result:	
	22.00

## 1.18 connect to...disconnect

(Component Integration Services only) Connects to the specified server and disconnects the connected server.

### Syntax

This syntax is sent to the SAP ASE server verbatim. Use this syntax with CIS to create a passthru to a different server:

```
connect to <server_name>
disconnect
  [from ASE]
  [all]
  [<connection_name>]
```

This syntax opens a new JDBC-level connection to the SAP ASE server, and does not use CIS. You can specify the arguments in any order. If you do not include arguments, the SAP ASE server prompts you for connection parameters:

```
connect
  [to ASE <engine_name>]
  [database <database_name>]
  [as <connection_name>]
  [user <user_id>]
  [identified by password]]]
```

This syntax opens a new JDBC-level connection to the SAP ASE server. This syntax does not use CIS:

```
connect using <connect_string>
```

### Parameters

#### <server\_name>

is the server to which a pass through connection is required.

#### from ASE

disconnects from the current SAP ASE server.

#### all

disconnects from all SAP ASE servers.

#### <connection\_name>

disconnects from the specified connection.

#### <engine\_name>

connects to the specified engine.

#### <database\_name>

connects to the specified database.

**<connection\_name>**

connects to the configured connection.

**<user\_id>**

connects to the user with this ID.

**<connection\_string>**

connects using a predetermined connection string.

## Examples

### Example 1

Establishes a passthrough connection to the server named MYSERVER:

```
connect to MYSERVER
```

### Example 2

Disconnects the connected server:

```
disconnect
```

### Example 3

Disconnects from all servers:

```
disconnect all
```

## Usage

- `connect to` specifies the server to which a passthrough connection is required. Passthrough mode enables you to perform native operations on a remote server.
- `<server_name>` must be the name of a server in the `sys.servers` table, with its server class and network name defined.
- When establishing a connection to `<server_name>` on behalf of the user, CIS uses one of the following identifiers:
  - A remote login alias described in `sysattributes`, if present
  - The user's name and password

In either case, if the connection cannot be made to the specified server, the SAP ASE server returns an error message.

- After making a passthrough connection, CIS bypasses the Transact-SQL parser and compiler when subsequent language text is received. It passes statements directly to the specified server, and converts the results into a form that can be recognized by the Open Client interface and returned to the client program.
- To close the connection created by the `connect to` command, use the `disconnect` command. You can use this command only after the connection has been made using `connect to`.

- You can abbreviate the `disconnect` command to `disc`.
- The `disconnect` command returns an error unless `connect to` has been previously issued and the server is connected to a remote server.

See also `sp_addserver`, `sp_autoconnect`, `sp_helpserver`, `sp_passthru`, `sp_remotesql`, `sp_serveroption` in *Reference Manual: Procedures*.

## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

## Permissions

You must have the `connect` privilege to use the `connect to` command.

## Auditing

You can enable `security` auditing option to audit this command. Values in `event` and `extrainfo` columns from the `sysaudits` table are:

Information	Value
Audit option	<code>security</code>
Event	90
Command or access audited	<code>connect to</code>
Information in <code>extrainfo</code>	<ul style="list-style-type: none"> <li>• <b>Roles</b> – current active roles</li> <li>• <b>Full command text</b> – full text of <code>connect to</code> command</li> <li>• <b>Previous value</b> – NULL</li> <li>• <b>Current value</b> – NULL</li> <li>• <b>Other information</b> – NULL</li> <li>• <b>Proxy information</b> – original login name, if <code>set proxy</code> is in effect</li> </ul>

Full command text is included in `extrainfo`. For example:

```
sa_role sso_role oper_role sybase_ts_role mon_role;
connect to myserver; ; ; ; ; sa/ase;
```

For more information about auditing, see *Security Administration Guide > Auditing*.

## Related Information

[create existing table \[page 170\]](#)

[grant \[page 520\]](#)

## 1.19 continue

Restarts the `while` loop. `continue` is often activated by an `if` test.

### Syntax

```
while <boolean_expression>
    <statement>
    break
    <statement>
continue
```

### Examples

#### Example 1

If the average price is less than \$30, double the prices. Then, select the maximum price. If the maximum price is less than or equal to \$50, restart the `while` loop and double the prices again. If the maximum price is more than \$50, exit the `while` loop and print a message:

```
while (select avg (price) from titles) < $30
begin
    update titles
    set price = price * 2
    select max (price) from titles
    if (select max (price) from titles) > $50
        break
    else
        continue
end
begin
print "Too much for the market to bear"
end
```

### Usage

`continue` restarts the `while` loop, skipping any statements after `continue`.



## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

## Permissions

No permission is required to use `continue`.

## Auditing

This command is not audited.

## Related Information

[break](#) [page 118]

[while](#) [page 863]

## 1.20 create archive database

Creates an archive database.

### Syntax

```
create archive database <db_name>
  [encrypt with <key_name>]
  [on <db_device> [= <size>]
  [, <db_device> [= <size>]] ...]
  with scratch_database = <db_name>
```

### Parameters

**encrypt with** **<key\_name>**

creates an archive database that is encrypted, using the same key you used to encrypt the database you backed up (dumped).

**on <db\_device>**

specifies the modified pages section. The SAP ASE server requires traditional database storage to store modified pages. Use the `on` clause to specify the location and size of the modified pages section.

<db\_device> specifies the database device on which you want to create your modified pages section.

**<size>**

specifies the size of the modified pages section you want to create. If you omit <size>, 5120 pages are allocated.

**with scratch\_database**

(required if a scratch database does not already exist) specifies the name of an existing database in which information about the archive database is maintained. The `sysaltusages` system table, which maps logical pages in the archive database onto physical pages, is stored in the scratch database.

## Examples

### Example 1

This example could be a typical archive database command sequence:

1. Create the scratch database, if necessary:

```
create database scratchdb
  on datadev1 = 100
  log on logdev1 = 50
```

This creates a 150 MB traditional database called `scratchdb`.

2. Designate the database you just created as a scratch database:

```
sp_dboption "scratchdb", "scratch database", "true"
```

3. Create the archive database:

```
create archive database archivedb
  on datadev2 = 20
  with scratch_database = scratchdb
```

This creates an archive database called `archivedb`, with a 20 MB modified pages section.

4. Materialize the archive database:

```
load database archivedb
  from "/dev/dumps/050615/proddb_01.dmp"
  stripe on "/dev/dumps/050615/proddb_02.dmp"
```

5. Bring the database online:

```
online database archivedb
```

6. Check the consistency of the archive database using `dbcc` commands. For example:

```
dbcc checkdb(archivedb)
```

7. Load a transaction log dump, and restore objects from the archive database:

```
load tran archivedb
    from "/dev/dumps/050615/proddb1_log_01.dmp"
load tran archivedb
    from "/dev/dumps/050615/proddb1_log_02.dmp"
online database archivedb
select * into proddb.dbo.orders from archivedb.dbo.orders
load tran archivedb
    from "/dev/dumps/050615/proddb1_log_03.dmp"
online database archivedb
```

## Usage

- You can load dumps of the `master` database into an archive database.
- You cannot:
  - Use an in-memory database as an archive database. You should not use an in-memory database as a scratch database
  - Issue `create archive database` on an in-memory row storage-enabled database.
  - Load a cumulative dump to an archive database.
  - Load more than one transaction dump that was performed with the `enable delta tran` configuration parameter enabled.

## Permissions

There is no special permission to use the `encrypt` with option of the `create archive database` command. However, users need `select` permission on the database encryption key to be able to reference it as the `<key_name>`.

The permission checks for `create archive database` differ based on your granular permissions settings.

Setting	Description
---------	-------------

<b>Enabled</b>	With granular permissions enabled, you must have the <code>create database</code> privilege.
----------------	--

<b>Disabled</b>	With granular permissions disabled, you must be the system administrator or have <code>create database</code> privilege.
-----------------	--

## Auditing

This command is not audited.

## 1.21 create database

Creates a new database.

### Syntax

Syntax for nonclustered environments:

```
create [inmemory] [temporary] database <database_name>
  [use <database_name> as template]
  [on {default | <database_device>} [= <size>]
    [, <database_device> [= <size>]]...]
  [log on <database_device> [= <size>]
    [, <database_device> [= <size>]]...]
  [imrslog on <database_device> [= <size>] [, ...]]
    [ row storage on <cache_name>]
    [ version storage on <temporary_database>]
  [with {dbid = <number>, default_location = "<pathname>", override}]
    | [[,]durability = { no_recovery
      | at_shutdown
      | full} ]
    [ [,] row_caching { on | off }
      [ [,] snapshot_isolation { on [{ row | version} storage ] | off } ]
    [, [no] async_init]
    [ [,] compression = {none | row | page}}
    [ [,] lob_compression = {<compression_level> | off}}
    [ [,] index_compression = {none | page}
      [ [,] latch_free_index = {on | off}}
    [ [,] inrow_lob_length = <value> ]          }...
  [for {load | proxy_update}]
  [ encrypt with <key_name>]
```

Syntax for cluster environments:

```
create [ [ global | system ] temporary ] database <database_name>
  [for instance <instance_name> ]
  [on {default | <database_device>} [= <size>]
    [, <database_device> [= <size>]]...]
  [log on <database_device> [= <size>]
    [, <database_device> [= <size>]]...]
  [with {override | default_location = "pathname"}]
  [for {load | proxy_update}]

create [temporary] database <database_name>
  encrypt with <key_name>
  for single instance access
```

### Parameters

#### temporary

indicates that you are creating a temporary database.

#### inmemory

required for in-memory databases.

**<database\_name>**

is the name of the new database, which must conform to the rules for identifiers, and cannot be a variable.

**on**

indicates a location and size for the database.

**default**

indicates that `create database` can put the new database on any default database devices, as shown in `sysdevices.status`. To specify a size for the database without specifying a location, use:

```
on default = <size>
```

To change a database device's status to "default," use `sp_diskdefault`.

**<database\_device>**

is the logical name of the device on which to locate the database. A database can occupy different amounts of space on each of several database devices. To add database devices to an SAP ASE server, use `disk init`.

**size**

is the amount of space to allocate to the database extension. You can use the following unit specifiers, using uppercase, lowercase, single and double quotes interchangeably: 'k' or "K" (kilobytes), "m" or 'M' (megabytes), "g" or "G" (gigabytes), and 't' or 'T' (terabytes). You should always include a unit specifier. Quotes are optional if you do not include a unit specifier. However, you must use quotes if you include a unit specifier. If you do not provide a unit specifier, the value provided is presumed to be in megabytes.

**log on**

specifies the logical name of the device for the database logs. You can specify more than one device in the `log on` clause.

**imrslog on**

specifies the on-disk row store device name and the amount of space bound to `imrslogsegment`. Although the `imrslog on size =` parameter is optional, if you do not include this parameter, the size of the database fragment created on the device is the same as other device specifiers. Generally, you can create a database fragment that is smaller than the device. However, SAP recommends that you allocate the entire device to the database so that `imrslog` devices need not be shared across databases. Sharing `imrslog` devices across database is not restricted, but because they are a type of log device, sharing them across databases may lead to transaction logging performance implications for device I/O across high-volume transactional workloads.

**row storage on <cache\_name>**

specifies the database-wide cache used to store rows from tables enabled for in-memory row storage. `<cache_name>` specifies an existing row-storage cache. The entire row storage cache is assigned to the database to store rows in-memory.

**with**

can be specified in any order. You must specify at least one of the following options when you use the `with` clause:

- `with dbid = <number>` – specifies the `dbid` for the new database. If you do not explicitly specify the `dbid`, the server assigns an unused `dbid`.
- `with default_location` – specifies the storage location of new tables. If you also specify the `for proxy_update` clause, one proxy table for each remote table or view is automatically created from the specified location.
- `with override` – forces the SAP ASE server to accept your device specifications, even if they mix data and transaction logs on the same device, thereby endangering up-to-the-minute recoverability for your database. If you attempt to mix log and data on the same device without using this clause, the `create database` command fails. If you mix log and data, and use `with override`, you are warned, but the command succeeds.
- `durability =` – determines the durability level of the database:
  - `full` – all transactions are written to disk. This is the default if you do not specify a durability level when you create the database, and ensures full recovery from a server failure. All system databases use this durability level (the traditional durability level for disk-resident databases).
  - `no_recovery` – transactions are not durable to disk and all changes are lost if the server fails or is shut down. For disk-based databases, the SAP ASE server periodically writes data at runtime to the disk devices, but in an uncontrolled manner. After any shutdown (polite, impolite, or server failure and restart) a database created with `no_recovery` is not recovered, but is re-created from the `model` or `template` (if defined) database.
  - `at_shutdown` – transactions are durable while the server is running and after a polite shutdown. All durability is lost if the server fails.
- `row_caching on | off` – determines whether the database uses row caching. one of:
  - `on` – use the in-memory row storage cache to store all data rows for inserts, selects, and updates for all user tables created in this database. High-volume OLTP applications requiring high performance benefit from enabling row caching for hot tables.
  - `off` – (the default) row caching is not enabled database-wide for newly created tables, even if you created the database with row storage cache.

**`snapshot_isolation { on [ using { row | version} storage ] | off }`**

determines whether the database uses snapshot-isolation level semantics. One of:

- `on` – timestamp-based snapshot isolation level semantics are applied to all user tables created in this database, unless you explicitly override the option when you create a new table.
- `off` – (default) snapshot-isolation level semantics are not enabled database-wide for newly created tables, even if you created the database with row storage cache.
- `using` – uses the specified temporary database as the version storage repository for versions of rows.
- `row` – specifies you are creating a version-link storage cache as the database-wide cache to store row metadata from eligible tables. `<cache_name>` indicates a cache previously created of type `row_storage`.
- `version` – specifies that new row versions are created in the `sysversions` table of the version storage temporary database specified in the `version storage on`

parameter. The `create database` command fails if the version storage temporary database does not exist or is linked with another database. Cache specified as a database-wide cache to store the row version metadata information is stored in the `sysversions` of the version storage temporary database.

**[no] `async_init`**

enables or disables asynchronous database initialization.

**`compression`**

indicates the level of compression to be applied to newly created tables or partitions:

- `none` – data is not compressed.
- `row` – compresses one or more data items in an individual row. The SAP ASE server stores data in a row-compressed form only if the compressed form saves space compared to an uncompressed form.
- `page` – when the page fills, existing data rows that are row-compressed are then compressed using page-level compression to create page-level dictionary, index, and character-encoding entries.  
The SAP ASE server compresses data at the page level only after it has compressed data at the row level, so setting the compression to implies both `pagerow` compression.

**`lob_compression = off | <compression_level>`**

Determines the compression level for the newly created table. Selecting and `off` means the table does not use LOB compression.

The compression algorithm ignores rows that do not use LOB data.

Table compression level. The compression levels are:

- 0 – the row is not compressed.
- and1 through 9 – the SAP ASE server uses ZLib compression. Generally, the higher the compression number, the more the SAP ASE server compresses the LOB data, and the greater the ratio between compressed and uncompressed data (that is the greater the amount of space savings, in bytes, for the compressed data versus the size of the uncompressed data).  
However, the amount of compression depends on the LOB content, and the higher the compression level, the more CPU-intensive the process. That is, level 9 provides the highest compression ratio but also the heaviest CPU usage.
- 100 – the SAP ASE server uses FastLZ compression. The compression ratio that uses the least CPU usage; generally used for shorter data.
- 101 – the SAP ASE server uses FastLZ compression. A value of 101 uses slightly more CPU than a value of 100, but uses a better compression ratio than a value of 100.

**`index_compression = { none | page }`**

indicates you are creating a database that includes a compressed index, where:

- `none` – the index is not compressed
- `page` – the index is compressed at the page level

**`latch_free_index = {on | off}]`**

indicates that you are creating a database that uses latch-free indexes. Set to:

- `on` – all tables created in this database use latch-free indexes, except those you create explicitly with `latch_free_index` set to `off`.
- `off` – all tables created in this database use regular indexes, except those you create explicitly with `latch_free_index` set to `on`.

The `latch_free_index` option only affects DOL tables. APL tables that are created in a latch-free, index-enabled database use regular indexes.

**`inrow_lob_length = <value>`**

specifies the number of bytes. The range of valid values for `inrow_lob_length` is 0 through the logical page size of the database. A value of 0 turns off LOB specification database-wide, and all LOB columns without a specific `in row` clause are created as off-row LOB columns.

**`dml_logging`**

specifies the logging level for DML operations.

**`full | minimal`**

specifies either full logging or minimal logging of the DML operations.

**`for load`**

invokes a streamlined version of `create database` that you can use only for loading a database dump.

**`for proxy_update`**

automatically gets metadata from the remote location and creates proxy tables. You cannot use `for proxy_update` unless you also specify `with default_location`.

**`global temporary`**

indicates that you are creating a global temporary database.

**`system temporary`**

indicates that you are creating a local system temporary database.

**`temporary`**

indicates that you are creating a temporary database.

**`for instance <instance_name>`**

specifies the instance that is to own the local system temporary database or local temporary database you are creating. This parameter is not used when creating global temporary databases.

**i Note**

You must create a local user temporary database from the instance that is to own it. You can create a local system temporary database from any instance.

**`with defer_index_recovery`**

enables you to defer the recovery of the index during load transaction recovery. Deferred recovery indexes are useful for (but not restricted to) queries that create indexes but don't need to retain the indexes. That is, the application needs only a temporary index and not a permanent index.



- `parallel` – defers recovery if the index was created in parallel. If you do not include the `parallel` parameter, SAP ASE defers the index recovery regardless of whether a serial or a parallel sort was used at run-time.
- `auto` – the index is re-created automatically during `online database` using the metadata in the system tables.
- `manual` – the index can be re-created manually any time after issuing `online database`. SAP ASE includes a warning in the error log saying that the index creation is deferred and must be created manually. Deferred recovery indexes are marked as suspect, ensuring that the optimizer does use them in any ad-hoc queries, and that stored procedures containing references to the index as part of the query tree are recompiled.
- `none` – `online database` removes the metadata for the index, dropping the index entirely. SAP ASE includes this as an informational message in the error log.

You cannot use deferred recovery indexes on:

- System tables
- System databases
- Clustered indexes

Additionally, the SAP ASE cockpit does not support re-creating and managing deferred recovery indexes

**encrypt with** `<key_name>`

creates a fully encrypted database. `<key_name>` is the name of the database encryption key.

**for single instance access**

indicates that you are creating a database that is accessible from a single node of the cluster.

## Examples

### Example 1

Creates a database named `pubs`:

```
create database pubs
```

### Example 2

Creates a 4MB database named `pubs`:

```
create database pubs
on default = 4
```

If you do not provide a unit specifier for `<size>`, the value provided for `pubs` is presumed to be in megabytes.

### Example 3

Creates a database named `pubs` with 3MB on the `datadev` device and 2MB on the `moredatadev` device:

```
create database pubs
```

```
on datadev = "3M", moredatadev = '2.0m'
```

#### Example 4

Creates a database named `pubs` with 3MB of data on the `datadev` device and a 0.5GB log on the `logdev` device:

```
create database pubs
  on datadev='3m'
  log on logdev='0.5g'
```

#### Example 5

Creates a proxy database named `proxydb` but does not automatically create proxy tables:

```
create database proxydb
with default_location
"UNITEST.pubs.dbo."
```

#### Example 6

Creates a proxy database named `proxydb` and automatically creates proxy tables:

```
create database proxydb
on default = "4M"
with default_location
"UNITEST.pubs2.dbo."
for proxy_update
```

#### Example 7

Creates a proxy database named `proxydb`, and retrieves the metadata for all of the remote tables from a remote database:

```
create database proxydb
on default = 4
with default_location
"UNITEST.pubs2.."
for proxy_update
```

#### Example 8

Creates a database called `pubs` with `dbid 15`:

```
create database pubs with dbid = 15
```

#### Example 9

Creates a temporary database called `mytempdb1`, with 3MB of data on the `datadev` device and 1MB of log on the `logdev` device:

```
create temporary database mytempdb1
  on datadev = '3m' log on logdev = '1M'
```

#### Example 10

In a cluster environment, creates a local user temporary database on "ase1." Execute the following command from the owner instance ("ase1"):

```
create temporary database local_tempdb1 for instance
ase1
```

or:

```
create temporary database local_tempdb1
```

#### Example 11

In a cluster environment, creates a local system temporary database on "ase1." Execute this command from any instance in the cluster:

```
create system temporary database local_systemtempdb1 for
instance ase1
```

#### Example 12

In a cluster environment, creates a global temporary database:

```
create global temporary database global_tempdb1
```

#### Example 13

Creates an in-memory database on two different in-memory storage devices, `imdb_data_dev1` for the data and `imdb_logdev` for the log:

```
create inmemory database imdb2
on imdb_data_dev1 = '1.0g'
log on imdb_logdev = '0.5g'
with durability = no_recovery
```

#### Example 14

Creates an in-memory database on multiple in-memory storage devices. `imdb_data_dev1` and `imdb_data_dev2` contain all data, and `inmem_logdev` contains the log:

```
create inmemory database imdb3
on imdb_data_dev1 = '100m',
   imdb_data_dev2 = '200m'
log on inmem_logdev = '50m'
with durability=no_recovery
```

#### Example 15

Creates the `pubs5` database using the `pubs2` database as the template:

```
create inmemory database pubs5
use pubs2 as template
on imdb_duck1_cache = '5m'
log on imdb_duck_log = '5m'
with durability = no_recovery
```

#### Example 16

Creates a relaxed-durability database named `pubs5_rddb`:

```
create database pubs5_rddb on pubs5_dev = '6M'
log on pubs5_log = '2M'
with durability = at_shutdown
```

#### Example 17

Creates an in-memory storage cache dedicated to an in-memory temporary database:

1. Create the in-memory storage cache:

```
sp_cacheconfig inmem_tempdb_cache, "40m", inmemory_storage,
"none", "cache_partition=2"
```

2. Create an in-memory device to create temporary database:

```
disk init name = "inmem_dev"  
, physname = "inmem_tempdb_cache"  
, size = "40m"  
, type='inmemory'
```

3. Create the in-memory database:

```
create inmemory temporary database temp_imdb  
on inmem_dev = "20m"  
with durability = no_recovery
```

### Example 18

Creates the production database on the existing in-memory row storage cache, prod\_row\_cache:

1. Create devices (prod\_odrs\_dev1 and prod\_odrs\_dev2) for the on-disk row store:

```
disk init name = "prod_odrs_dev1",  
physname = "/usr/u/SAP/odrs/devices/prod_odrs_dev1.dat",  
size = "200g",  
type = imrslog  
disk init name = "prod_odrs_dev2",  
physname = "/usr/u/SAP/odrs/devices/prod_odrs_dev2.dat",  
size = "100g",  
type = imrslog
```

2. Create a named cache for in-memory row storage usage:

```
sp_cacheconfig "prod_row_cache", "50g", row_storage
```

3. Create a database for the on-disk row storage devices and assign the row storage cache to this database:

```
create database production  
on data_dev1 = "500g", data_dev2 = "500g"  
log on log_dev1 = "200g", log_dev2 = "150g"  
imrslog on prod_odrs_dev1 = "200g", prod_odrs_dev2 = "100g"  
row storage on prod_row_cache
```

Alternatively, create the same database and enable database-wide row caching for all tables created in this database:

```
create database production  
on data_dev1 = "500g", data_dev2 = "500g"  
log on log_dev1 = "200g", log_dev2 = "150g"  
imrslog on prod_odrs_dev1 = "200g",  
prod_odrs_dev2 = "100g"  
row storage on prod_row_cache  
with row_caching on
```

### Example 19

Creates a temporary database on an existing disk-device with durability set to no\_recovery:

```
create temporary database tempdb_rddb_norec  
on datadev = "5m" log on logdev = "5m"  
with durability = no_recovery
```

### Example 20

Creates the `emaildb` database, and configures it for page-level compression:

```
create database emaildb
on email_dev = '50M'
with compression = page
```

### Example 21

Creates the `email_lob_db` database and configures it for a LOB compression level of 101:

```
Create database email_lob_db
on email_lob_dev = '50M'
with lob_compression = 101
```

### Example 22

Creates a database names `pubs5` with index compression set to page:

```
create database pubs5 with index_compression = page
```

### Example 23

Creates a database called `pubs` that allows in-row LOB data with a length of 300 bytes:

```
create database pubs
with inrow_lob_length = 300
```

### Example 24

Creates an encrypted database called `demodb` with a log called `demodev` on a machine called `demologdev`, using an encryption key called `dbkey`:

```
create database demodb on demodev log on demologdev encrypt with dbkey
```

### Example 25

(Cluster Edition only) Creates a single instance database named `tech`:

```
create database tech for single instance access
```

### Example 26

Creates an on-disk MVCC version-storage database that uses snapshot isolation named `production` as the default for tables:

```
create database production
on data_dev1 = '500g', data_dev2 = '500g'
log on log_dev1 = '200g', log_dev2 = '150g',
row storage on version_link_cache
version storage on mytempdb
with snapshot_isolation on using version storage
```

### Example 27

Creates an IMRS database that uses snapshot isolation named `production_1` as the default for tables:

```
create database production_1
on data_dev2 = '500g', data_dev3 = '500g'
log on log_dev2 = '200g', log_dev3 = '150g',
imrslog on prod_odrs_dev2 = '200g'
row storage on prod_row_cache
```

```
with snapshot_isolation on
```

### Example 28

Creates a database named `pubs5` with latch-free indexes:

```
create database pubs5 with latch_free_index = on
```

## Usage

- Use `create database` from the master database.
- You can specify the `<size>` as a `float` datatype, but it is rounded down to the nearest whole value. For example, if you specify a size of 3.75G, it is rounded down to 3G.
- If you do not explicitly state the size of the database, the size is determined by the size of the `model` database. The minimum size that you can create a database is four allocation units.
- The SAP ASE server allocates space for databases for `create database` and `alter database` rounding down the specified size to the nearest whole megabyte multiple of allocation units.
- If you do not include a unit specifier, the SAP ASE server interprets the size in terms of megabytes of disk space, and this number is converted to the logical page size the server uses.
- If you do not specify a location and size for a database, the default location is any default database devices indicated in `master..sysdevices`. The default size is the larger of the size of the `model` database or the `default database size` parameter in `sysconfigures`.  
system administrators can increase the default size by using `sp_configure` to change the value of `default database size` and restarting the SAP ASE server. The `default database size` parameter must be at least as large as the `model` database. If you increase the size of the `model` database, you must also increase the default size.  
If the SAP ASE server cannot give you as much space as you want where you have requested it, it comes as close as possible, on a per-device basis, and prints a message telling how much space was allocated and where it was allocated. The maximum size of a database is system-dependent.
- If you create a proxy database using:

```
create database mydb on my_device  
with default_location = "<pathname>" for proxy_update
```

The presence of the device name is enough to bypass size calculation, and this command may fail if the default database size (the size of the `model` database) is not large enough to contain all of the proxy tables. To allow CIS to estimate database size, do not include any device name or other option with this command.

- Specify whether to encrypt a database when you create it, and all the data inserted into the database becomes encrypted automatically. The size of the database does not change when it is encrypted, and all storage access functions work identically whether a database is encrypted or not. The types of databases that support encryption are:
  - Normal user database
  - Temporary database
  - Archive database

You cannot encrypt an in-memory database.

See also `sp_changedbowner`, `sp_diskdefault`, `sp_helpdb`, `sp_logdevice`, `sp_renamedb`, `sp_spaceused` in *Reference Manual: Procedures*.

## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

## Permissions

The permission checks for `create database` differ based on your granular permissions settings.

### Setting Description

**Enabled** You must have the:

- `create database` privilege to create databases
- `manage auditing` privilege to create the `sybsecurity` database.
- `create database` privilege to create a database with the `imrslog` clause
- `manage resource` privilege to:
  - Create a database with `row storage` enabled
  - Allocate memory for the row-metadata object pool created to support the row storage cache

**Disabled** With granular permissions disabled, you must be system administrator or have `create database` privilege. If you are creating the `sybsecurity` database, you must be a system security officer.

You must have the

- `create database` or `sa_role` privilege create a database with the `imrslog` clause
- `sa_role` role to use the `ROW STORAGE ON` clause as this involves use of a system-wide resource, 15 i.e. the row storage cache.

Require `sa_role` privilege to use the `row storage` clause

## Auditing

You can enable `create` auditing option to audit this command. Values in `event` and `extrainfo` columns from the `sysaudits` table are:

Information	Value
Audit option	<code>create</code>
Event	9
Command or access audited	<code>create database</code>
Information in <code>extrainfo</code>	<ul style="list-style-type: none"><li>• <b>Roles</b> – current active roles</li><li>• <b>Full command text</b> – full text of <code>create database</code> command</li><li>• <b>Previous value</b> – NULL</li></ul>

## Information

## Value

- **Current value** – NULL
- **Other information** – NULL
- **Proxy information** – original login name, if `set proxy` is in effect

Full command text is included in `extrainfo`. For example:

```
sa_role sso_role oper_role sybase_ts_role mon_role;  
create database pubs; ; ; ; sa/ase;
```

For more information about auditing, see *Security Administration Guide > Auditing*.

## Related Information

[alter database \[page 14\]](#)

[disk init \[page 401\]](#)

[disk reinit \[page 415\]](#)

[drop database \[page 429\]](#)

[dump database \[page 470\]](#)

[load database \[page 585\]](#)

[online database \[page 625\]](#)

### 1.21.1 Restrictions for create database

The SAP ASE server can manage as many as 32,767 databases.

- The `dbid` should always be greater than zero and less than the maximum `dbid` of 32,767.
- The SAP ASE server can create only one database at a time. If two database creation requests collide, one user sees this message:

```
model database in use: cannot create new database
```

- Each time you allocate space on a database device with `create database` or `alter database`, that allocation represents a device fragment, and the allocation is entered as a row in `sysusages`.
- The maximum number of devices a database can use is 1269. `create database` fails if you attempt to exceed this amount.
- The maximum number of named segments for a database is 32. Segments are named subsets of database devices available to a particular SAP ASE server. For more information about segments, see the *System Administration Guide*.

Restrictions for creating single-instance databases:

- You can create single-instance databases without valid logical cluster bindings.
- Single-instance databases are instantiated and available after you bind them to a logical cluster with a running base instance.



For example, these commands instantiate, and then bring online, a single-instance database named SIDB1:

```
sp_cluster logical, 'create', 'LC1', 'for single instance access'
go
sp_cluster logical, 'add', 'LC1', 'instance', 'N1'
go
sp_cluster logical, 'add', 'LC1', 'failover', 'N2'
go
sp_cluster logical, 'add', 'LC1', 'database', 'SIDB1'
go
sp_cluster logical, 'online', 'LC1'
go
```

- A logical cluster can include a single single-instance database, and vice versa.
- You cannot associate regular cluster databases with the single-instance database.
- All databases must be available to the current cluster node during multidatabase transactions.

## 1.21.2 Temporary Databases

You cannot use either `with default_location` or `for proxy_update` parameters with the `create temporary database` command.

Doing so generates an error, such as the following two examples:

```
1> create temporary database tbl with default_location
    "remSERVER.mydb.."
```

```
Msg 102, Level 15, State 7:
Server 'ebi_SUS_AS125x_SUN32', Line 1:
Incorrect syntax near 'create temporary database'.
```

```
1> create temporary database tbl with default_location
    "remSERVER.mydb.." for proxy_update
```

```
Msg 102, Level 15, State 7:
Server 'ebi_SUS_AS125x_SUN32', Line 1:
Incorrect syntax near 'create temporary database'.
```

The temporary status of a database, which is set during the creation of the temporary database, is indicated by value 0x00000100 (256 decimal) of the `status3` field of a `sysdatabases` entry.

In addition to all options inherited from `model`, a temporary database, like the system `tempdb`, has the following database options set:

- `select into/bulkcopy`
- `trunc log on chkpt`

As with system `tempdb`, the guest user is added to the temporary database, and `create table` permission is granted to PUBLIC.

Unused pages are not cleared during creation of the temporary database, since a temporary database is re-created every time the server is restarted.

## 1.21.3 Creating Compressed Databases

Considerations that apply when creating compressed databases.

- The compression setting for `create table . . . with compression` overrides the `create database` compression setting.
- Temporary tables created with `select into` do not inherit the compression level from the database.
- The default setting for compression in the `model` database is `none` (data compression is off for all databases based on `model`).
- When you enable data compression in `tempdb` or other temporary databases, temporary tables created in a session or inside stored procedures do not inherit `tempdb`'s compression level.
- The database to which a task is bound determines the compression level of the temporary tables it creates.

## 1.21.4 Creating Databases With In-Row LOBs

The SAP ASE server uses in-row LOB compression if the table is implicitly or explicitly row- or page-compressed, and, any of the in-row large object columns in the table are implicitly or explicitly LOB compressed.

The in-row size can be as large as the maximum row size allowed in the database. The SAP ASE server lowers the limit on the size of individual column's in-row LOB storage during inserts and updates, based on the space available for storage in a single page, minus any page or row overheads.

When you create a table in a database where you have specified a valid in-row LOB length database-wide, all LOB columns in the table are created as in-row unless you specify `off row` in the syntax for the column's definition. The column's in-row length, in bytes, is specified by this database-wide setting.

The default value for `inrow_lob_length` setting is 0 bytes, which causes no changes in behavior to existing databases when you upgrade to SAP ASE version 15.7. Changing this default allows applications with different requirements on in-row storage to control how much LOB data is stored in-row.

The database-wide setting applies only to newly created tables or LOB columns added to existing tables after the database-wide setting is applied or changed. The in-row LOB length inherited by each LOB column when the table was initially created remains unchanged, even when the database-wide setting is altered. To change an individual LOB column's in-row length or in-row property, use `alter table modify column`.

To change the default length, use the `inrow_lob_length` parameter of `alter database`.

## 1.21.5 Creating In-Memory and Relaxed Durability Databases

The `<database_device>` you list for the in-memory database must be an in-memory storage device.

The `for load` parameter indicates that the database is created initially in a state waiting to be loaded using a `load database` command.

You cannot:

- Create an in-memory database on a default device.
- Use in-memory databases for system databases (other than `tempdb`).
- Use an in-memory database as an archive database. You should not use an in-memory database as a scratch database.
- Use the same name for the database you are creating and its template database.
- Specify system databases, including `model`, as the template database.
- Mix disk-based and cache-based storage devices. The SAP ASE server treats databases created entirely on in-memory storage cache as in-memory databases. You cannot use:
  - In-memory storage devices created on different in-memory storage caches for one in-memory database
  - In-memory storage devices created on one in-memory storage cache, either in full or in part, for different in-memory databases
- Use the `use as template` parameter with the `with default_location =` parameter.
- Use the `for load` and `for proxy update` parameters with the `use as template` parameter.

You can:

- Create in-memory databases on in-memory storage devices residing on named caches as long as all the in-memory storage devices are hosted by in-memory storage cache.
- Create mixed log-and-data in-memory databases on the same in-memory storage devices. However, mixed log-and-data in-memory databases must be on a single cache.

The `durability = no_recovery` parameter is required when you create an in-memory database. This parameter reinforces the behavior that in-memory databases are always re-created when you restart the server.

SAP ASE includes a 30-day trial period, during which you can try the in-memory database feature. However, if you use this feature, at the end of the trial period, you must:

- Purchase an in-memory license, or
- Purchase an SAP ASE license that does not include the in-memory feature. In this case, you must drop and recreate the user-defined temporary databases without using the explicit `durability` parameter.

## 1.21.6 Creating Databases for In-Memory Row Storage Caches

- The name of the row storage cache assigned to the database is stored in the `sysdatabases.imrscache` column in the master database.
- When you issue `create database` on devices of type `imrslog`, the definition for `imrslogsegment` is added to `syssegments` in that database. An unused segment ID starting from 31, searching downwards, is assigned to `imrslogsegment`. If all segment IDs are in use, the database creation fails.
- Unless you explicitly state otherwise, all datarow-locked user tables created in this database automatically use the in-memory row storage caches.
- The entire space in the in-memory row storage cache is reserved exclusively use for the database and cannot be shared across databases.
- You may include the `for load` clause when you create a database enabled with row storage.

- You may include the `encrypt with <key_name>` clause when you create a database enabled with row storage. SAP ASE applies database-wide encryption the same for data stored on databases enabled with row storage, but the data stored in the in-memory row storage cache remains unencrypted.
- Compression-related clauses only apply to data stored on-disk and not to the data rows stored in the in-memory row storage. Data rows are always stored in an uncompressed form in the in-memory row storage.
- Databases created with row storage caches must use full durability (required to support `load transaction` functionality).
- If you do not include the `using` parameter when enabling snapshot isolation, the server enables snapshot isolation by default.
- You must use `set {row_caching | snapshot_isolation} on` parameters on a database that was previously created or altered with the `version link storage cache` parameter.

In-memory row storage caches include these restrictions:

- You can include the `row_caching on` or `snapshot_isolation on` parameters only with the `row storage on` clause.
- The database specified for version storage must be a single database. That is, there is a one to one mapping between the version storage and the temporary database, and you cannot use a temporary database with multiple databases for the version storage.
- You cannot use the `version storage` parameter to create multiple databases. That is, each `create database ... version storage` command creates a single database.
- You cannot use a single temporary database as the version storage for multiple databases.
- You cannot:
  - Create a row storage database with an `imrslog` and version storage. These resources are mutually exclusive and only one can be enabled at a time.
  - Create database-wide row storage caches for temporary databases.
  - Define any in-memory databases created on in-memory cache devices to use database-wide row storage caches.
  - Define proxy databases with a row storage cache.
  - Use a row storage enabled disk-resident fully durable database as a template for another in-memory database
  - Use `imrslog` devices on:
    - Temporary user databases
    - In-memory databases
    - Proxy databases
    - Data devices (that is, created with the `on <device_name>` clause) or log devices (that is, created with the `log on <device_name>` clause).

## 1.21.7 New Databases Created from model

The SAP ASE server creates a new database by copying the `model` database.

You can customize `model` by adding tables, stored procedures, user-defined datatypes, and other objects, and by changing database option settings. New databases inherit these objects and settings from `model`.

To guarantee recoverability, `create database` must clear every page that was not initialized when the `model` database was copied. This may take several minutes, depending on the size of the database and the speed of your system.

If you are creating a database to load a database dump into it, you can use the `for load` option to skip the page-clearing step. This makes database creation considerably faster.

## 1.21.8 Ensuring Database Recoverability

Back up the `master` database each time you create a new database. This makes recovery easier and safer if `master` is damaged.

### i Note

If you create a database and fail to back up `master`, you may be able to recover the changes with `disk reinit`.

The `with override` clause allows you to mix log and data segments on a single device. However, for full recoverability, the device or devices specified in `log on` should be different from the physical device that stores the data. In the event of a hard-disk failure, you can recover the database from database dumps and transaction logs.

You can create a small database on a single device that is used to store both the transaction log and the data, but you *must* rely on the `dump database` command for backups.

The size of the device required for the transaction log varies according to the amount of update activity and the frequency of transaction log dumps. As a rule of thumb, allocate to the log device 10 – 25 percent of the space you allocate to the database itself. It is best to start small, since space allocated to a transaction log device cannot be reclaimed and cannot be used for storing data.

## 1.21.9 Using the for load Option

You can use the `for load` option for recovering from media failure or for moving a database from one machine to another, if you have not added to the database with `sp_addsegment`.

Use `alter database for load` to create a new database in the image of the database from which the database dump to be loaded was made. For a discussion of duplicating space allocation when loading a dump into a new database, see the *System Administration Guide*.

When you create a database using the `for load` option, you can run only the following commands in the new database before loading a database dump:

- `alter database for load`
- `drop database`
- `load database`

After you load the database dump into the new database, you can also use some `dbcc` diagnostic commands in the databases. After you issue the `online database` command, there are no restrictions on the commands you can use.

A database created with the `for load` option has a status of “don't recover” in `sp_helpdb` output.

## 1.21.10 Getting Information About Databases

To get a report on a database, execute `sp_helpdb`; for a report on the space used in a database, use `sp_spaceused`.

## 1.21.11 Using `with default_location` and `for proxy_update`

Without the `for proxy_update` clause, the behavior of the `with default_location` clause is the same as that provided by `sp_defaultloc`—a default storage location is established for new and existing table creation, but proxy table definitions are not automatically imported during the processing of `create database`.

If `for proxy_update` is specified with no `default_location`, an error is reported.

When a proxy database is created (using the `for proxy_update` option), CIS is called upon to:

- Provide an estimate of the database size required to contain all proxy tables representing the actual tables and views found in the primary server's database. This estimate is the number of database pages needed to contain all proxy tables and indexes. The estimate is used if no size is specified, and no database devices are specified.
- Create all proxy tables representing the actual tables and views found in the companion server's database.
- Grant all permissions on proxy tables to public.
- Add the `guest` user to the proxy database.
- The database status is set to indicate that this database “Is\_A\_Proxy”. This status is contained in `master.dbo.sysdatabases.status3`.

## 1.22 `create default`

Specifies a value to insert in a column (or in all columns of a user-defined datatype) if no value is explicitly supplied at insert time.

### Syntax

```
create default [or replace] [<owner>.]<default_name>  
as <constant_expression>
```

## Parameters

### `or replace`

if the default already exists, replaces the default definition with the new definition.

### `<default_name>`

is the name of the default, which must conform to the rules for identifiers and cannot be a variable. Specify the owner's name to create another default of the same name owned by a different user in the current database. The default value for `<owner>` is the current user.

When you use `or replace`, if the specified default name already exists, then it is replaced with the new default definition. The object name and ID remain the same.

### `<constant_expression>`

is an expression that does not include the names of any columns or other database objects. It can include global variables and built-in functions that do not reference database objects. Enclose character and date constants in quotes and use a "0x" prefix for binary constants.

When you use `or replace`, the definition of the default can be changed when the default is replaced. The new default value overrides the old default.

## Examples

### Example 1

Creates a default called D1 that uses the `<@@spid>` global variable:

```
create default D1 as @@spid
```

### Example 2

Defines a default value, then binds it to the appropriate column or user-defined datatype:

```
create default phonedflt as "UNKNOWN"
```

### Example 3

The default takes effect only if there is no entry in the `phone` column of the `authors` table:

```
sp_bindefault phonedflt, "authors.phone"
```

No entry is different from a null value entry. To get the default, issue an `insert` command with a column list that does not include the column that has the default.

### Example 4

Creates a default value, `today's_date`, that inserts the current date into the columns to which it is bound:

```
create default today's_date as getdate ()
```

## Example 5

This example first creates a default with a phone number defined as UNKNOWN:

```
create default phonedflt as "UNKNOWN"
select object_id("phonedflt")
-----
1001051571
```

This default replaces the previously created default using the `or replace` clause. The phone number is changed, but the object ID of the default remains the same:

```
create or replace default phonedflt as "999-999-9999"
select object_id("phonedflt")
-----
1001051571
```

## Usage

- Bind a default to a column or user-defined datatype—but not an SAP ASE server-supplied datatype—with `sp_bindefault`.
- You can bind a new default to a datatype without unbinding the old one. The new default overrides and unbinds the old one.
- `create default` performs error checking for check constraints before it creates the default.
- To hide the source text of a default, use `sp_hidetext`.

See also `sp_bindefault`, `sp_help`, `sp_helptext`, `sp_rename`, `sp_unbindefault` in *Reference Manual: Procedures*.

## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

Use the `default` clause of the `create table` statement to create ANSI SQL-compliant defaults.

## Permissions

The permission checks for `create default` differ based on your granular permissions settings.

Setting	Description
---------	-------------

Enabled	With granular permissions enabled, you must have the <code>create default</code> privilege to create a default. To create a default for another user, you must have the <code>create any default</code> privilege.
---------	--

To replace a default, you must be the default owner. Any user who impersonates the default owner through an alias or `setuser` cannot replace the default.



## Setting Description

**Disabled** With granular permissions disabled, you must be the database owner, a user with `sa_role`, or have the `create default` privilege to create a default. You must have `sa_role` to create a default for another user.

To replace the default, you must be the default owner, or have `sa_role`. Any user who impersonates the default owner through an alias or `setuser` cannot replace the default unless the user has `sa_role`.

## Auditing

You can enable `create` auditing option to audit this command. Values in `event` and `extrainfo` columns from the `sysaudits` table are:

Information	Value
Audit option	<code>create</code>
Event	14
Command or access audited	<code>create default</code>
Information in <code>extrainfo</code>	<ul style="list-style-type: none"><li>• <b>Roles</b> – current active roles</li><li>• <b>Full command text</b> – full text of <code>create default</code> command</li><li>• <b>Previous value</b> – NULL</li><li>• <b>Current value</b> – NULL</li><li>• <b>Other information</b> – NULL</li><li>• <b>Proxy information</b> – original login name, if <code>set proxy</code> is in effect</li></ul>

Full command text is included in `extrainfo`. For example:

```
sa_role sso_role oper_role sybase_ts_role mon_role;  
create default D1 as @@spid; ; ; ; sa/ase;
```

For more information about auditing, see *Security Administration Guide > Auditing*.

## Related Information

[alter table \[page 70\]](#)

[create table \[page 273\]](#)

[drop default \[page 431\]](#)

[drop rule \[page 453\]](#)

[insert \[page 572\]](#)

## 1.22.1 create default Restrictions

Restrictions for `create default`.

- You can create a default only in the current database.
- You cannot combine `create default` statements with other statements in a single batch.
- You must drop a default using `drop default` before you create a new one of the same name; you must unbind a default using `sp_unbinddefault`, before you drop it.

## 1.22.2 Datatype Compatibility

The SAP ASE server generates an error message when it attempts to insert a default value that is not compatible with the column's datatype.

For example, if you bind a character expression such as "N/A" to an `integer` column, any `insert` that does not specify the column value fails.

If a default value is too long for a character column, the SAP ASE server either truncates the string or generates an exception, depending on the setting of the `string_rtruncation` option. See the `set` command.

## 1.22.3 Getting Information about Defaults

Default definitions are stored in `syscomments`.

- After a default is bound to a column, its object ID is stored in `syscolumns`. After a default is bound to a user-defined datatype, its object ID is stored in `sysstypes`.
- To rename a default, use `sp_rename`.
- For a report on the text of a default, use `sp_helptext`.

## 1.22.4 Defaults and Rules

If a column has both a default and a rule associated with it, the default value must not violate the rule. A default that conflicts with a rule cannot be inserted. The SAP ASE server generates an error message each time it attempts to insert such a default.

## 1.22.5 Defaults and Nulls

If a column does not allow nulls, and you do not create a default for the column, when a user attempts to insert a row but does not include a value for that column, the insert fails and the SAP ASE server generates an error message.

This table shows the relationship between the existence of a default and the definition of a column as NULL or NOT NULL.

Column Null Type	No Entry, no Default	No Entry, Default Exists	Entry is Null, no Default	Entry is Null, Default Exists
NULL	Null inserted	Default value inserted	Null inserted	Null inserted
NOT NULL	Error, command fails	Default value inserted	Error, command fails	Error, command fails

## 1.22.6 Specifying a Default Value in create table

You can define column defaults using the `default` clause of the `create table` statement as an alternative to using `create default`.

However, these column defaults are specific to that table; you cannot bind them to other tables. See `create table` and `alter table` for information about integrity constraints.

## 1.22.7 Objects Dependent on Replaced Defaults

Considerations when using `or replace`.

- Many columns can be bound to a replaced default.
- User defined datatypes can be bound to the replaced defaults.

Procedures that access these columns are recompiled when the default is replaced and the procedure is executed.

## 1.23 create encryption key

Creates encryption keys. All the information related to keys and encryption is encapsulated by `create encryption key`, which allows you to specify the encryption algorithm and key size, the key's default property, an optional user-specified password to encrypt the key, as well as the use of an initialization vector or padding during the encryption process.

The SAP ASE server uses Security Builder Crypto for key generation and encryption.

## Syntax

Creates the master key:

```
create encryption key [dual] master
  [for AES]
  with {passwd char_literal | external key}
```

Creates the service key:

```
create encryption key [syb_extpasswdkey | syb_syscommkey]
  [ with { static key | master key } ]
```

Creates the column encryption key:

```
create encryption key [[<database>.]<owner>.]<keyname>
  [as default]
  [for <algorithm_name>]
  [with [{passwd {char_literal | system_encr_passwd} | master key}]
  [keylength <num_bits>]
  [init_vector {null | random}]
  [pad {null | random}]
  [[no] dual_control]]
```

Creates an encryption key for fully encrypted databases:

```
create encryption key <keyname>
  [for <algorithm_name>]
  for database encryption
  [with
    {[master key]
    [keylength 256]
    [init_vector random]
    [[no] dual_control]]
```

Creates an external HSM key:

```
create encryption key [owner.]keyname
  [for AES]
  on external keystore
  [with
    {[keylength 256]
    [init_vector random]
    [uuid_key_uuid_on_device]} ]
```

## Parameters

### <keyname>

must be unique in the user's table, view, and procedure name space in the current database. Specify the <database> name if the key is in another database; specify the <owner> name if you are creating a key for another user. The default value for <owner> is the current user, and the default value for <database> is the current database. Only the system security officer can create keys for other users.

### as default

allows the system security officer or the key custodian to create a database default key for encryption. The existence of a database default encryption key enables the table creator to specify encryption without using a keyname on `create table`, `alter table`, and `select into`. The SAP ASE server uses the default key from the same database. The default key may be changed. See `alter encryption key`.

**for <algorithm\_name>**

specifies the algorithm you are using. Advanced Encryption Standard (AES) is the only algorithm supported. AES supports key sizes of 128 bits, 192 bits, and 256 bits, and a block size of 16 bytes.

**for database encryption**

indicates that you are creating an encryption key to encrypt an entire database, rather than a column.

**for AES**

uses the Advanced Encryption Standard (AES) encryption algorithm to encrypt data.

**passwd char\_literal**

Indicates to create the master key encrypted with a password.

**external key**

Indicates to create the master key encrypted with an external key.

**syb\_extpasswdkey**

specifies that all external passwords in `sysattributes` are re-encrypted with the new key using strong encryption

**syb\_syscommkey**

specifies that any subsequent execution of `sp_hidetext` uses the new key with strong encryption. `sp_hidetext` must be executed on an existing database object for the object to be encrypted with the new key

**static key | master key**

indicates that you are creating an encryption key using a static or master key.

Specifying `master key` creates a master key in the `master` database, and indicates to SAP ASE to protect the database encryption key using that key. By default, SAP ASE uses this master key (if it exists) to protect database encryption keys.

**keylength <num\_bits>**

the size, in bits, of the key to be created. For AES, valid key lengths are 128, 192, and 256 bits. The default key length is 128 bits.

The only valid length for a database encryption key is 256; you see an error message if you use any other size.

**<password\_phrase>**

is a quoted alphanumeric string of up to 255 bytes in length that the SAP ASE server uses to generate the key used to encrypt the column encryption key (the key encryption key).

**init\_vector {null | random}**

specifies whether to use of an initialization vector during encryption. When an initialization vector is used by the encryption algorithm, the cipher text of two identical

pieces of plain text are different, which prevents a cryptanalyst from detecting patterns of data. Use an initialization vector to increase the security of your data.

An initialization vector has some performance implications. Index creation, and optimized joins and searches, can be performed only on a column for which the encryption key does not specify an initialization vector.

The default is to use an initialization vector, that is, `init_vector random`. Use of an initialization vector implies using a cipher-block chaining (CBC) mode of encryption; setting `init_vector null` omits the use of an initialization vector when encrypting, and implies the electronic codebook (ECB) mode. This makes the column suitable for supporting an index..

Database encryption enforces stronger security than column encryption; if you specify `init_vector null` for database encryption as you can for creating a column encryption key, SAP ASE returns an error.

#### **pad {null | random}**

allows you to specify whether to add or omit random padding of data:

- `null` (default) – omits random padding of data. You cannot use padding if the column must support an index.
- `random` – data is automatically padded with random bytes before encryption. You can use padding instead of an initialization vector to randomize the cipher text. Padding is suitable only for columns whose plaintext length is less than half the block length. For the AES algorithm, the block length is 16 bytes.

#### **[no] dual\_control**

indicates whether the new key must be encrypted using dual controls. By default, dual control is not configured. Both the master key and dual master key must exist in the `master` database to use `dual_control`.

#### **on external keystore**

creates the actual raw key on the external Hardware Security Module (HSM) keystore. You can create only one key as the HSM key with this clause in an SAP ASE instance. This clause is not applied to master key, database encryption key, or service key.

#### **<key\_uuid\_on\_device>**

specifies the ID of the HSM key referenced in the HSM device. SAP ASE reports an error if a key with a UUID does not exist in the HSM device. When this clause is not specified, then SAP ASE generates a new UUID for the key. This clause is useful when the same key present on the HSM device needs to be used on another ASE installation. The format of UUID can be:

- A 32 bytes UUID string without hyphens, such as `d078fff951944f8ea524-d2dcc60a8e52`.
- A 36 bytes UUID string with hyphens, such as `d078fff9-5194-4f8e-a524-d2dcc60a8e52`.

## Examples

### Example 1

Specifies a 256-bit key called "safe\_key" as the database default key. The system security officer enters:

```
create encryption key safe_key as default for AES with keylength 256
```

### Example 2

Creates a 128-bit key called "salary\_key" for encrypting columns using random padding:

```
create encryption key salary_key for AES with init_vector null pad random
```

### Example 3

Creates a 192-bit key named "mykey" for encrypting columns using an initialization vector:

```
create encryption key mykey for AES with keylength 192 init_vector random
```

### Example 4

Creates a key that is protected by a user-specified password:

```
create encryption key key1 with passwd 'Worlds1Biggest6Secret'
```

You must enter user-specified passwords that protect keys before accessing a column encrypted by the key. See `set`.

### Example 5

Specifies a 256-bit key called "safe\_key" as the database default key. Because the key does not specify a password, the SAP ASE server uses the database-level master key as the key encryption key for `safe_key`. If there is no master key, the SAP ASE server uses the system encryption password:

```
create encryption key safe_key as default for AES with keylength 256
```

### Example 6

Encrypts CEK k3 with a combination of the master key and "Whybother":

```
create encryption key k3 with passwd 'Whybother' dual_control
create encryption key k1 with keylength 192
```

### Example 7

Creates a master key to protect "testkey":

```
create encryption key testkey for database encryption
with master key
```

### Example 8

Creates a dual master key to protect "testkey":

```
create encryption key testkey for database encryption
with dual_control
```

### Example 9

Creates both a master key and dual master key to protect "testkey":

```
create encryption key testkey for database encryption
with master key dual_control
```

### Example 10

Creates a master key to protect "testkey" while explicitly excluding the dual master key:

```
create encryption key testkey for database encryption
with master key no dual_control
```

### Example 11

Creates a master key to protect "testkey" while explicitly excluding a dual master key:

```
create encryption key testkey for database encryption
with no dual control
```

### Example 12

```
sp_configure 'enable encrypted columns', 1
create encryption key master with passwd "testpassword"
set encryption passwd 'testpassword' for key master
create encryption key dbkey for database encryption
```

### Example 13

Creates a HSM key with a key length as 256 bits and uses the random initialization vector during encryption, specifying UUID to be used for the key in the HSM device:

```
create encryption key hsm_key
on external keystore
with keylength 256
init_vector random
uuid '89586e56c69d2b45fe89d2c68e520adc'
```

## Usage

The SAP ASE server does not save the user-specified password. It saves a string of validating bytes known as the "salt" in `sysencryptkeys.eksalt`, which allows the SAP ASE server to recognize whether a password used on a subsequent encryption or decryption operation is legitimate for a key. You must supply the password to the SAP ASE server before you can access any column encrypted by `keyname`.

For fully encrypted databases:

- The database encryption key does not support the `pad` option in `create encryption key` command.
- The database encryption key cannot be the default key for column encryption.
- Successfully created database encryption keys are stored in the `sysencryptkeys` table of the `master` database and are indicated by this key type:

```
#define EK_DBENCKEY          0x1000
```

For information about auditing, see *Auditing Encrypted Columns* in the *Encrypted Columns Users Guide*.



## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

## Permissions

The permission checks for `create encryption key` differ based on your granular permissions settings.

Setting	Description
---------	-------------

<b>Enabled</b>	With granular permissions enabled, you must have the following privilege or privileges based on the encryption key type:
----------------	--

- column encryption key – `create encryption key` or `manage column encryption key`
- master key – `manage master key`
- service key – `manage service key`
- database encryption key – `manage database encryption key`
- external HSM key – `manage master key`

You must have the `manage any encryption key` privilege to create an encryption key for another user.

<b>Disabled</b>	With granular permissions disabled, you must be a user with <code>sso_role</code> , <code>keycustodian_role</code> , or have <code>create encryption key</code> privilege to create an encryption key. You must have <code>sso_role</code> to create an encryption key for another user.
-----------------	--

### **i** Note

You must be a user with `sso_role` or `keycustodian_role` to create an HSM key, the `create encryption key` privilege does not work for creating an HSM key.

## Auditing

You can enable `encryption_key` auditing option to audit this command. Values in `event` and `extrainfo` columns from the `sysaudits` table are:

Information	Value
Audit option	<code>encryption_key</code>
Event	107
Command or access audited	<code>create encryption key</code>
Information in <code>extrainfo</code>	<ul style="list-style-type: none"><li>• <b>Roles</b> – current active roles</li></ul>

## Information

## Value

- **Full command text** – full text of `create encryption key` command
- **Previous value** – NULL
- **Current value** – NULL
- **Other information** – NULL
- **Proxy information** – original login name, if `set proxy` is in effect

Full command text (with obfuscated password) is included in `extrainfo`. For example:

```
sa_role sso_role oper_role sybase_ts_role mon_role;  
  create encryption key loginA_key with passwd  
*****; ; ; ; sa/ase;
```

For more information about auditing, see *Security Administration Guide > Auditing*.

## Related Information

[alter encryption key \[page 35\]](#)

[set \[page 732\]](#)

[drop encryption key \[page 433\]](#)

[grant \[page 520\]](#)

[revoke \[page 672\]](#)

## 1.24 create existing table

(Component Integration Services only) Creates a proxy table, then retrieves and stores metadata from a remote table and places the data into the proxy table. Allows you to map the proxy table to a table, view, or procedure at a remote location.

The preferred method of creating proxy tables is the `create proxy_table` command, which eliminates the need to define the column definitions.

## Syntax

```
create existing table <table_name> (<column_list>)  
  [on <segment_name>]  
  [[external {table | procedure | file | <connection_type>}] at <pathname>  
  [column delimiter "<string>"]]
```

## Parameters

### <table\_name>

specifies the name of the table for which you want to create a proxy table.

### <column\_list>

specifies the name of the column list that stores information about the remote table.

### on <segment\_name>

specifies the segment that contains the remote table.

### external

specifies that the object is a remote object.

### table

specifies that the remote object is a table or a view. The default is `external table`.

### procedure

specifies that the remote object is a stored procedure.

### file

specifies that the remote object is a file.

### <connection\_type>

determines whether a remote procedure call uses the current or a separate connection. The valid values are:

- `non_transactional` – is a separate connection is used to execute the RPC.
- `transactional` – is the existing connection is used to execute the RPC.

The default behavior is `transactional`.

### at <pathname>

specifies the location of the remote object. <pathname> takes the form:

<server\_name>.<dbname>.<owner>.<object>, where:

- <server\_name> (required) – is the name of the server that contains the remote object.
- <dbname > (optional) – is the name of the database managed by the remote server that contains this object.
- <owner> (optional) – is the name of the remote server user that owns the remote object.
- <object> (required) – is the name of the remote table, view, or procedure.

### column delimiter

used to separate fields within each record when accessing flat files. The column delimiter can be up to 16 bytes long.

### <string>

the column delimiter string can be any character sequencer, but if the string is longer than 16 bytes, only the first 16 bytes are used. The use of column delimiter for proxy tables mapped to anything but files results in a syntax error.

## Examples

### Example 1

Creates the proxy table authors:

```
create existing table authors
(
  au_id      id,
  au_lname   varchar (40)    NOT NULL,
  au_fname   varchar (20)    NOT NULL,
  phone      char (12),
  address    varchar (40)    NULL,
  city       varchar (20)    NULL,
  state      char (2)        NULL,
  zip        char (5)        NULL,
  contract   bit
)
at "nhserver.pubs2.dbo.authors"
```

### Example 2

Creates the proxy table syb\_columns:

```
create existing table syb_columns
(
  id          int,
  number      smallint,
  colid       tinyint,
  status      tinyint,
  type        tinyint,
  length      tinyint,
  offset      smallint,
  usertype    smallint,
  cdefault    int,
  domain      int,
  name        varchar (30),
  printfmt    varchar (255)  NULL,
  prec        tinyint        NULL,
  scale       tinyint        NULL
)
at "remotel.master.dbo.columns"
```

### Example 3

Creates a proxy table named blurbs for the blurbs table at the remote server SERVER\_A:

```
create existing table blurbs
(
  author_id   id      not null,
  copy        text    not null
)
at "SERVER_A.db1.joe.blurbs"
```

### Example 4

Creates a proxy table named rpc1 for the remote procedure named p1:

```
create existing table rpc1
(
  column_1    int,
  column_2    int
)
external procedure
```

```
at "SERVER_A.db1.joe.pl"
```

## Usage

- `create existing table` does not create a new table unless the remote object is a file. Instead, CIS checks the table mapping to confirm that the information in `<column_list>` matches the remote table, verifies the existence of the underlying object, and retrieves and stores metadata about the remote table.
- You cannot issue `create existing table` on an IMRS-enabled database if the remote, target SAP ASE table is a row caching-enabled table. You can, however, issue `create existing table` on an IMRS-enabled database if the remote, target SAP ASE table is not a row caching-enabled table.
- If the host data file or remote server object does not exist, the command is rejected with an error message.
- If the object exists, the system tables `sysobjects`, `syscolumns`, and `sysindexes` are updated. The verification operation requires these steps:
  1. The nature of the existing object is determined. For host data files, this requires determining file organization and record format. For remote server objects, this requires determining whether the object is a table, a view, or an RPC.
  2. For remote server objects (other than RPCs), column attributes obtained for the table or view are compared with those defined in the `column_list`.
  3. Index information from the host data file or remote server table is extracted and used to create rows for the `sysindexes` system table. This defines indexes and keys in the SAP ASE server terms and enables the query optimizer to consider any indexes that might exist on this table.
- The `on <segment_name>` clause is processed locally and is not passed to a remote server.
- After successfully defining an existing table, issue `update statistics` for the table. This allows the query optimizer to make intelligent choices regarding index selection and join order.
- CIS allows you to create a proxy table with a column defined as NOT NULL even though the remote column is defined as NULL. It displays a warning to notify you of the mismatch.
- The location information provided by the `at` keyword is the same information that is provided by `sp_addobjectdef`. The information is stored in the `sysattributes` table.
- CIS inserts or updates a record in the `sysabstats` catalog for each index of the remote table. Since detailed structural statistics are irrelevant for remote indexes, only a minimum number of columns are set in the `sysabstats` record—`id`, `indid`, and `rowcnt`.
- External files cannot be of datatypes `text`, `image`, or Java ADTs.

## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

## Permissions

`create existing table` permission defaults to the table owner and is not transferable.

## Auditing

This command is not audited.

## Related Information

[alter table \[page 70\]](#)

[create table \[page 273\]](#)

[create proxy\\_table \[page 253\]](#)

[drop index \[page 439\]](#)

[drop table \[page 457\]](#)

[insert \[page 572\]](#)

[order by Clause \[page 630\]](#)

[set \[page 732\]](#)

[update \[page 819\]](#)

## 1.24.1 Datatype Conversions

When using `create existing table`, you must specify all datatypes with recognized SAP ASE datatypes.

If the remote server tables reside on a class of server that is heterogeneous, the datatypes of the remote table are automatically converted into the specified SAP ASE types when the data is retrieved. If the conversion cannot be made, CIS does not allow the table to be defined.

The *Component Integration Services Users Guide* contains a section for each supported server class and identifies all possible datatype conversions that are implicitly performed by CIS.

## 1.24.2 Changes by Server Class

All server classes allow you to specify fewer columns than there are in the table on the remote server.

In addition, all server classes:

- Match the columns by name.
- Allow the column type to be any datatype that can be converted to and from the datatype of the column in the remote table.

## 1.24.3 Remote Procedures

When the proxy table is a procedure-type table, you must provide a column list that matches the description of the remote procedure's result set. `create existing table` does *not* verify the accuracy of this column list.

No indexes are created for procedures.

CIS treats the result set of a remote procedure as a virtual table that can be sorted, joined with other tables, or inserted into another table using `insert` or `select`. However, a procedure type table is considered read-only, which means you cannot issue the following commands against the table:

- `alter table`
- `create index`
- `delete`
- `insert`
- `truncate table`
- `update`

Begin the column name with an underscore (`_`) to specify that the column is not part of the remote procedure's result set. These columns are referred to as parameter columns. For example:

```
create existing table rpcl
(
  a          int,
  b          int,
  c          int,
  _p1       int null,
  _p2       int null
)
external procedure
at "SYBASE.sybssystemprocs.dbo.myproc"
```

In this example, the parameter columns `_p1` and `_p2` are input parameters. They are not expected in the result set, but can be referenced in the query:

```
select a, b, c from t1
where _p1 = 10 and _p2 = 20
```

CIS passes the search arguments to the remote procedure as parameters, using the names `@<p1>` and `@<p2>`.

Parameter-column definitions in a `create existing table` statement:

- Must allow a null value.
- Cannot precede regular result columns—they must appear at the end of the column list.

If a parameter column is included in a `select` list and is passed to the remote procedure as a parameter, the return value is assigned by the `where` clause.

If a parameter column is included in a `select` list, but does not appear in the `where` clause or cannot be passed to the remote procedure as a parameter, its value is `NULL`.

A parameter column can be passed to a remote procedure as a parameter if the SAP ASE query processor considers it a searchable argument. A parameter column is considered a searchable argument if it is not included in any `OR` predicates. For example, the `OR` predicate in the second line of the following query prevents the parameter columns from being used as parameters:

```
select a, b, c from t1
```

```
where _p1 = 10 or _p2 = 20
```

## 1.24.4 Encrypted Columns

`create existing table` automatically updates `syscolumns` with any encrypted column metadata from the remote table. You cannot include the `encrypt` keyword in the column list for a `create existing table` command.

## 1.25 create function

Creates a user-defined function, which is a saved Transact-SQL routine that returns a specified value.

### Syntax

```
create [or replace] function [<owner>.]<function_name>
    ([{@parameter_name} [as] <parameter_datatype>[ = default]]
    [,...n])
returns {<return_datatype> | table <table_type_definition>
        | <@return_variable> table <table_type_definition>}
[with recompile]
    [inline]
as
[begin]
<function_body>
return <scalar_expression>
[end]
```

### Parameters

#### **or replace**

redefines an existing function. Use this clause to change the definition of an existing user defined function without dropping, re-creating, and regrating object privileges previously granted on the function. If the function is redefined, it is recompiled when the function is used.

#### **<owner>**

is the name of the user ID that owns the user-defined function. Must be an existing user ID.

#### **<function\_name>**



is the name of the user-defined function. Function names must conform to the rules for identifiers and must be unique within the database and to its owner. Function names cannot be the same as other SAP ASE built-in functions.

When used with `or replace`, the name of the function remains the same, although its definition is changed.

### **i Note**

To reference or invoke a user-defined function, specify the `<owner.function_name>`, followed by parentheses (see the `bonus` function example below). Specify expressions as arguments for all the parameters within the parentheses. You cannot specify the parameter names in the argument list when you invoke a function. You must supply argument values for all of the parameters, and the argument values must be in the same sequence in which the parameters are defined in the `create function` statement. When a function's parameter has a default value, you must specify the keyword "default" when calling the function to get the default value.

### **<@parameter\_name>**

is the parameter in the user-defined function. You can declare one or more parameters in a `create function` statement.

A function can have up to 2,047 parameters. The user supplies the value of each declared parameter when the function is executed, unless you define a default for the parameter.

A table user-defined function can have up to 1,023 parameters.

Specify a parameter name using an "at" sign (@) as the first character. The parameter name must conform to the rules for identifiers. Parameters are local to the function. You can use the same parameter names in other functions.

If a parameter has a default value, the user must specify the keyword "default" when they call the function to get the default value. This behavior differs from parameters with default values in stored procedures in which omitting the parameter also implies the default value.

When used with `or replace`, you can alter the names and number of parameters.

### **<parameter\_datatype>**

is the datatype of the parameter. You can use all scalar datatypes, Java abstract datatypes (ADTs), and table types as a parameter for user-defined and table user-defined functions. However, user-defined functions do not support the `timestamp`, `text`, `image` and `unitext`.

When used with `or replace`, you can change the datatype of the parameter to the function.

**returns {<return\_datatype> | table <table\_type\_definition> | @<return\_variable>  
table <table\_type\_definition>}**

specifies what the function returns, depending on what type you are creating:

- `<return_datatype>` – is the return value of a scalar, user-defined function. `<return_datatype>` can be any of the scalar datatypes and Java abstract datatypes except `text`, `image`, `unitext`, and `timestamp`.  
When used with `or replace`, you can alter the return datatype of the function.
- `table <table_type_definition>` – specifies that you are creating an inline table user-defined function.
- `<@return_variable> table <table_type_definition>` – specifies that you are creating a multi-statement table-valued function, and includes column definitions. Using `<@return_variable>` allows you to declare a table as a variable, while `<table_type_definition>` is similar to the table definition, and is defined as (`<column_definition>[, ...<n>]`), where:
  - `<column_definition>` specifies a column definition.
  - `<n>` allows you to specify additional definitions and constraints.
- `<@return_variable> table<table_type_definition>` – specifies that you are creating a multi-statement table-valued function, and includes column definitions. Using `<@return_variable>` allows you to declare a table as a variable, while `<table_type_definition>` is similar to the table definition, and is defined as (`{ <column_definition> | <table_constraint> }[, ...<n>]`), where:
  - `<column_definition>` specifies a column definition.
  - `<table_constraint>` specifies a table constraint.
  - `<n>` allows you to specify additional definitions and constraints.

#### **with recompile**

indicates that the SAP ASE server never saves a plan for this function; instead, creates a new plan each time the function is referenced in a SQL statement. Use `with recompile` when you expect the execution of this function to be atypical, and to require a new plan.

When used with `or replace`, you can change the option to recompile, or not to recompile every time the function is replaced.

#### **inline**

indicates the system to change the table UDF to a parameterized view.

#### **<function\_body>**

specifies a series of Transact-SQL statements that together generates a set of rows that define the value of the function, but which together do not produce a side effect. Use `<function_body>` only in scalar functions and multistatement table-valued functions. In scalar functions, `<function_body>` is a series of Transact-SQL statements that evaluate to a scalar value.

When used with `or replace`, you can change the SQL statements that define the value of the function

#### **<scalar\_expression>**

specifies the scalar value the scalar function returns.

You can invoke scalar-valued functions where scalar expressions are used, including computed columns and `check` constraint definitions.

When used with `or replace`, you can change the value returned by the function.

#### <select\_statement>

The columns specified in the target list of the <select\_statement> should match <table\_type\_definition>.

## Examples

### Example 1

Creates a user-defined function named `BONUS`:

```
create function BONUS(@salary int, @grade int, @dept_id int)
returns int
as
begin
    declare @bonus int
    declare @cat int
    set @bonus = 0
    select @cat = dept_cat from department
        where dept_id = @dept_id
    if (@cat < 10)
        begin
            set @bonus = @salary *15/100
        end
    else
        begin
            set @bonus = @salary * 10/100
        end
    return @bonus
end
```

### Example 2

Defines a function which concatenates `firstname` and `lastname` strings.

```
create function fullname(
    @firstname char(30),
    @lastname char(30))
returns char(61)
as
begin
    declare @name char(61)
    set @name = @firstname|| ' ' ||@lastname
    return @name
end
select object_id("fullname")
-----
473049690
```

This function replaces the previously created `fullname` function using the `or replace` clause. After replacing the function, the local variable `@name` is removed. The object ID of the function remains the same.

```
create or replace function fullname(
    @firstname char(30),
    @lastname char(30))
returns char(61)
as
begin
```

```

return(@firstname|| ' ' ||@lastname)
end
select object_id("fullname")
-----
473049690

```

### Example 3

Creates an inline table-valued function using a table called `Emp_mails` with the following definition and data:

```

create table Emp_mails(emp_id int, name varchar(30), dept_id int,
email varchar(1000), WeekDay datetime)

```

```

Insert Emp_mails values (02993, 'Alex Kospar' , 14, ' ', getdate())
Insert Emp_mails values (02994, 'Ahmed ben Ahmed', 45, ' ', '2007-11-02')
Insert Emp_mails values (02995, 'Roger Mila', 43, ' ', '2007-10-30')
Insert Emp_mails values (02996, 'Amida Sountra', 45, ' ', '2007-10-30')
Insert Emp_mails values (02997, 'Sustra Cheng', 14, ' ', '2007-10-30')
Insert Emp_mails values (02998, 'Olive Presse', 56, ' ', '2007-10-29')
Insert Emp_mails values (03000, 'Yousri Kapa', 14, ' ', '2007-10-29')
Insert Emp_mails values (03001, 'Lynn Paris', 36, ' ', '2007-10-28')
Insert Emp_mails values (03002, 'Shella Labella', 87, ' ', '2007-10-28')

```

You then create a table-valued function to retrieve all email sent to a given department:

```

create function Emp_dept (@dptid int) returns table (emp_id int, name
varchar(30))
as
return select emp_id, name from Emp_mails where dept_id = @dptid

```

This function returns all the employees of a given department that sent an email.

#### Note

The rows are not sent to the user, but to the calling statement.

The calling statement can then use the function:

```

select * from Emp_dept(14)

```

The result of the calling statement is:

```

2993 Alex Kospar
2997 Sustra Cheng
3000 Yousri Kapa

```

The calling statement can also filter the result, such as:

```

select name from Emp_dept(14)
where emp_id >2995

```

The result is:

```

Sustra Cheng
Yousri Kapa

```

#### Example 4

Creates a multi-statement table-valued function for data integration using a table called `books` that contains `book_id` and book descriptions. These descriptions are in plain text and contain `authors`, `title`, `editor`, and `short_description` for each book. This description uses the format:

```
" authors : author_name <,list_of_authors>;
title : book_title; 15 editor : editor_name;
short_descr: short_description;"
```

The user shreds the contents of the description column and generates a rowset that contains (`book_id`, `author`, `title`, and `short_descr`), then writes a table user-defined function that reads the description and generates the rowset. Despite the lack of a sophisticated string manipulation built-in, the user can write small SQL functions that shred the description.

This writes a scalar SQL function that detects the string between two given keywords:

```
Create function get_substring(@str varchar(1000), @key_word
varchar(50)) returns varchar(500)
as
begin
    declare @substring_value varchar(500)
    declare @len int
    set @len = len(@str)
    select @substring_value = substring (@str,
        charindex (@key_word, @str), @len )
    select @substring_value = substring (@substring_value,
        charindex(':', @substring_value)+1 , @len)
    select @substring_value = substring (@substring_value, 1,
        charindex(';', @substring_value)-1)
    return @substring_value
end
```

This writes a table UDF that uses the previous scalar SQL function, and generates the rowsets:

```
create function get_authors (@str varchar(1000), @book_id int)
returns @table_authors table (book_id int, author varchar(50),
    title varchar(50), editor 4 varchar(50))
as
begin
    declare @editor varchar(500)
    declare @short_descr varchar(500)
    declare @title varchar(500)
    declare @authors varchar(500)
    declare @author varchar(50)
    declare @len int
    select @str = book_descr from books
    select @len = len(@str)
    /*Get the editor */
    select @editor = dbo.get_substring(@str, 'editor')
    /* Get the short description */
    select @short_descr = dbo.get_substring(@str, 'short_descr')
    /* Get the title */
    select @title = dbo.get_substring(@str, 'title')
    /* get authors */
    select @authors = dbo.get_substring(@str, 'authors')
    select @authors = @authors + ','
    select @len = len(@authors)
    while (@len > 0)
        begin
            select @author = substring
                (@authors, 1, charindex(',', @authors)-1)
            select @authors = substring(@authors, len(@author)+2, @len)
```

```

        select @len = len(@authors)
        insert @table_authors values (@book_id , @author, @title, 39 @editor)
    end
return
end

```

This calls this function to get the list of authors that wrote a given title:

```

select * from dbo.get_authors('authors :Alfredo Muzatti, Ali MacNamara,
Nouri Abdu; editor : Sci&tech; Title : The database world; short_descr:
It is all about the database;', 1)

```

The result is:

book_id	author	title	editor
1	Alfredo Muzatti	The database world	Sci&tech
1	Ali MacNamara	The database world	Sci&tech
1	Nouri Abdu	The database world	Sci&tech

Every row in books can also call the function:

```

select * from books b, dbo.get_authors(b.book_descr, b.book_id)

```

The result is:

book_id	author	title	editor
1	Alfredo Muzatti	The database world	Sci&tech
1	Ali MacNamara	The database world	Sci&tech
1	Nouri Abdu	The database world	Sci&tech

### Example 5

Creates an inlined table-valued UDF that will be changed internally into an equivalent parameterized view during execution:

```

create function getobj(@p1 int)
    returns table (id int, type char(2), name varchar(80))
    inline
    as return
    select id, type, name from sysobjects where id < @p1
go

```

## Usage

- If the owner of the user-defined function also owns all the database objects referenced inside, then all the other users who have `execute` permission on the function are automatically granted access permissions to all the referenced objects when they execute the function.
- When a function is created, the SAP ASE server checks to see if it is a SQL user-defined function or a SQLJ user-defined function. If it is the latter, the SAP ASE server checks for "sa" permissions. If it is a SQL function, the SAP ASE server checks for `create function` privileges.

If a function is referenced in a computed column or functional index, it cannot be replaced.

## Permissions

The permission checks for `create function` differ based on your granular permissions settings.

### Setting Description

**Enabled** With granular permissions enabled, you must have the `create function` privilege to create a function. To create a function for another user, you must have the `create any function` privilege.

To replace the function, you must be the function owner. Any user who impersonates the function owner through an alias or `setuser` cannot replace the function.

**Disabled** With granular permissions disabled, you must be the database owner, a user with `sa_role`, or have the `create function` privilege to create a function. To create a function for another user, you must have `sa_role`.

To replace the function, you must be the function owner, or have `sa_role`. Any user who impersonates the function owner through an alias or `setuser` cannot replace the function unless the user has `sa_role`.

Those with `sa_role` and the database owner (DBO) can grant `create function` permission to other logins by using this `grant` statement:

```
grant create function to <user_name>
```

Function owners have `execute` permission on their functions. Others do not, unless they have been granted explicit `execute` permission on the function. To grant the execution of a function by the owner to a given user, use:

```
grant execute on <function_name> to <username>
```

If an owner of a stored procedure also owns all the database objects referenced inside the stored procedure, then all the users who have `execute` permission on that procedure are automatically granted access permissions to all the referenced objects when they execute the procedure. This implicit grant rule also applies to table user-defined functions.

## Auditing

You can enable `create` auditing option to audit this command. Values in `event` and `extrainfo` columns from the `sysaudits` table are:

Information	Value
Audit option	<code>create</code>
Event	97
Command or access audited	<code>create function</code>

Information	Value
Information in <code>extrainfo</code>	<ul style="list-style-type: none"> <li>• <b>Roles</b> – current active roles</li> <li>• <b>Full command text</b> – full text of <code>create function</code> command</li> <li>• <b>Previous value</b> – NULL</li> <li>• <b>Current value</b> – NULL</li> <li>• <b>Other information</b> – NULL</li> <li>• <b>Proxy information</b> – original login name, if <code>set proxy</code> is in effect</li> </ul>

Full command text is included in `extrainfo`. For example:

```
sa_role sso_role oper_role sybase_ts_role mon_role;
create function testfun1 (@p1 int, @p2 int=2) returns int
as begin declare @retval int set @retval = @p1+@p2
return @retval end; ; ; ; ; sa/ase;
```

For more information about auditing, see *Security Administration Guide > Auditing*.

## 1.25.1 Objects Dependent on Replaced Functions

If a replaced function is called by another function, both functions are recompiled when called. If the interface of the replaced function does not match that in the calling function, then the calling function must be replaced, otherwise, the calling function raises an error. You can execute `sp_depends` on the replaced function to check for any calling objects.

For example, `testfun1` is replaced to have two parameters instead of one. The calling function, `testfun2`, must be replaced to account for the second parameter.

```
create function testfun1 (@para1 int)
returns int
as
begin
declare @retval int
set @retval = @para1
return @retval
end
create function testfun2 (@para int)
returns int
as
begin
declare @retval int
select @retval= dbo.testfun1 (@para)
return @retval
end
create or replace function testfun1 (@para1 int,@para2 int)
returns int
as
begin
declare @retval int
set @retval = @para1+@para2
return @retval
end
```



## 1.26 create function (SQLJ)

Creates a user-defined function by adding a SQL wrapper to a Java static method. Can return a value defined by the method.

### Syntax

```
create function [or replace] [<owner>.]<sql_function_name>
    ([< sql_parameter_name> <sql_datatype>
      [(<length>)| (<precision>[, <scale >])])
    [[, <sql_parameter_name> <sql_datatype>
      [(<length>)| (<precision>[, <scale>])]]
    ...]])
returns <sql_datatype>
    [(<length>)| (<precision>[, <scale>])]
[modifies sql data]
[returns null on null input |
  called on null input]
[deterministic | not deterministic]
[exportable]
language java
parameter style java
external name '<java_method_name>'
    [[(<java_datatype>[, <java_datatype>
      ...]])]
```

### Parameters

#### or replace

redefines an existing function. Use this clause to change the definition of an existing user defined SQLJ function without dropping, re-creating, and regrating object privileges previously granted on the function.

#### <sql\_function\_name>

is the Transact-SQL name of the function, must conform to the rules for identifiers, and cannot be a variable. The name remains the same even when you use `or replace`.

#### <sql\_parameter\_name>

is the name of an argument to the function. The value of each input parameter is supplied when the function is executed. Parameters are optional; a SQLJ function need not take arguments.

Parameter names must conform to the rules for identifiers. If the value of a parameter contains nonalphanumeric characters, it must be enclosed in quotes. This includes object names qualified by a database name or owner name, since they include a period. If the value of the parameter begins with a numeric character, it also must be enclosed in quotes.

Use `or replace` to change the names and the number of parameters.

**<sql\_datatype>** [(**<length>**) | (**<precision>** [, **<scale>**])]

is the Transact-SQL datatype of the parameter. See `create procedure` for more information about these parameters.

**<sql\_datatype>** is the SQL procedure signature.

Use `or replace` to change the Transact-SQL datatype of the parameter to the function.

**returns <sql\_datatype>**

specifies the result datatype of the function.

Use `or replace` to change result datatype of the function .

**modifies sql data**

indicates that the Java method invokes SQL operations, reads, and modifies SQL data in the database. This is the default and only implementation. It is included for syntactic compatibility with the ANSI standard.

**deterministic | not deterministic**

included for syntactic compatibility with the ANSI standard. Not currently implemented.

**exportable**

specifies that the procedure is to be run on a remote server using the SAP ASE OmniConnect feature. Both the procedure and the method it is built on must reside on the remote server.

**language java**

specifies that the external routine is written in Java. This is a required clause for SQLJ functions.

**parameter style java**

specifies that the parameters passed to the external routine at runtime are Java parameters. This is a required clause for SQLJ functions.

**external**

indicates that `create function` defines a SQL name for an external routine written in a programming language other than SQL.

**name**

specifies the name of the external routine (Java method). The specified name — '**<java\_method\_name>** [**< java\_datatype>** [{, **<java\_datatype>**} ...]]' — is a character-string literal and must be enclosed in single quotes.

Use `or replace` to change the name of the external routine.

**<java\_method\_name>**

specifies the name of the external Java method.

Use `or replace` to change the Java method.

**<java\_datatype>**

specifies a Java datatype that is mappable or result-set mappable. This is the Java method signature.

Use `or replace` to change the Java datatype.

## Examples

### Example 1

Creates a function `square_root` that invokes the `java.lang.Math.sqrt()` method:

```
create function square_root
  (input_number double precision) returns
  double precision
  language java parameter style java
  external name 'java.lang.Math.sqrt'
```

### Example 2

Creates a SQLJ function named `sqlj_testfun`.

```
create function sqlj_testfun (p1 int)
  returns int
  language java
  parameter style java
  external name 'UDFSample.sample(int)'
```

The following replaces the previously created SQLJ function using the `or replace` clause. Parameter `p2` is added and the external java method is changed but the object ID of the SQLJ function remains the same.

```
create or replace function sqlj_testfun (p1 int,p2 int)
  returns int
  language java
  parameter style java
  external name 'UDFSample.sample2(int,int)'
```

## Usage

- You cannot create a SQLJ function with the same name as an SAP ASE built-in function.
- You can create user-defined functions (based on Java static methods) and SQLJ functions with the same class and method names.

### Note

The SAP ASE server searching order ensures that the SQLJ function is always found first.

- You can include a maximum of 31 parameters in a `create function` statement.
- When a function is created, the SAP ASE server checks to see if it is a SQL user-defined function or a SQLJ user-defined function. If it is the latter, the SAP ASE server checks for “sa” permissions. If it is a SQL function the SAP ASE server checks for `create function` privileges.
- If the replaced SQLJ function is called by another function, both functions will be recompiled when called.
- If the interface of the replaced function does not match that in the calling function, then the calling function must be replaced, otherwise the calling function raises an error. You can execute `sp_depends` on the replaced function to check for any calling objects.

- If a function is referenced in a computed column or functional index, it cannot be replaced.

For objects dependent on replaced functions:

- If the replaced SQLJ function is called by another function, both functions will be recompiled when called.
- If the interface of the replaced function does not match that in the calling function, then the calling function must be replaced, otherwise the calling function raises an error. You can execute `sp_depends` on the replaced function to check for any calling objects.

See also:

- See *Java in Adaptive Server Enterprise* for more information about `create function`.
- `sp_depends`, `sp_help`, `sp_helpjava`, `sp_helprotect` in *Reference Manual: Procedures*

## Permissions

The permission checks for `create function (SQLJ)` differ based on your granular permissions settings.

### Setting Description

**Enabled** With granular permissions enabled, you must have the `create function` privilege to create a function (SQLJ). To create a function for another user, you must have the `create any function` privilege.

To replace the function, you must be the function owner. Any user who impersonates the function owner through an alias or `setuser` cannot replace the function.

**Disabled** With granular permissions disabled, you must be the database owner, a user with `sa_role`, or have the `create function` privilege to create a function (SQLJ). To create a function for another user, you must have `sa_role`.

To replace the function, you must be the function owner, or have `sa_role`. Any user who impersonates the function owner through an alias or `setuser` cannot replace the function unless the user has `sa_role`.

## Auditing

For information about auditing for `create function`, see [create function \[page 176\]](#).

For more information about auditing, see *Security Administration Guide > Auditing*.

## 1.27 create global temporary table

Creates a global temporary table, which has persistent metadata and private data per session. Global temporary tables have an entry in the system catalog so that all concurrent sessions can use their metadata. Data in the global temporary table is automatically deleted at the end of the session, even if the session ends unexpectedly.

### Syntax

```
create global temporary table <table_name>
  (<column_name datatype>[,{ <next_column> | <next_constraint>}]...)
  . . .
  [upon commit {preserve rows | delete rows}]
```

### Parameters

**<table\_name>**

is the name of the global temporary table you are creating.

**<column\_name datatype>**

specifies the name of the column and its datatypes.

**<next\_column>**

specifies the name of additional columns.

**<next\_constraint>**

specifies additional constraints for the column you are creating.

**upon commit**

indicates the state of data inserted upon session exit.

**preserve rows**

indicates that rows should be preserved until the end of the session. This is the default behavior.

**delete rows**

indicates that rows should be deleted after end of current transaction.

### Examples

#### Example 1

This example creates a global temporary table, inserts some values, then drops the table:

```
create global temporary table gt1(c1 int)
```

```

go
insert into gt1 values(12)
go
(1 row affected)
select * from gt1
go
c1
-----
12

```

### Example 2

This example creates a global temporary table where its rows are preserved until the end of the session:

```
create global temporary table gt2(a int) upon commit preserve rows
```

### Example 3

This example creates a global temporary table with rows that are deleted after end of the current transaction:

```
create global temporary table gt3(a int) upon commit delete rows
```

### Example 4

To delete a global temporary table, use the `drop table` command:

```
drop table gt1
```

## Usage

The characteristics of global temporary tables are:

- You can create a global temporary table template in any database.
- A global temporary table template is persistent and is visible to all connections.
- The data in a global temporary table is private, so that data inserted by a session can only be accessed by that session.
- The `select` command returns only the column name.
- The session-specific rows in a global temporary table can be preserved for the whole session, or just for the current transaction.
- Global temporary tables do not have logging or replication support.
- You can create indexes on global temporary tables.
- When no session is using the global temporary table, you can use the `drop` command to drop it.
- Any built-in function that calls on a global temporary table provides data or information only for the current session.
- You can use export and import utilities to transfer the global temporary table template definitions, but no data rows are processed.

## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

## Permissions

Any user can create temporary tables and new tables with logging disabled.

The following describes permission checks for `create global temporary table` that differ based on your granular permissions settings.

Setting	Description
---------	-------------

<b>Enabled</b>	With granular permissions enabled, you must have the <code>create table</code> privilege to create a table. To create a table for another user, you must have the <code>create any table</code> privilege. Requires <code>manage data cache privilege</code> to use the row storage cache for either row caching or snapshot isolation.
----------------	---

<b>Disabled</b>	With granular permissions disabled, you must be the database owner, a user with <code>sa_role</code> , or a user with the <code>create table</code> privilege to create a table. To create a table for another user, you must have <code>sa_role</code> . Requires the <code>sa_role</code> privilege to use the row storage cache for either row caching or snapshot isolation.
-----------------	--

## Auditing

You can enable the following auditing options to audit this command. Values in `event` and `extrainfo` columns from the `sysaudits` table are:

Audit option	Event	Command or access audited	Information in <code>extrainfo</code> :
<code>create</code>	10	<code>create table</code>	<ul style="list-style-type: none"> <li>• <i>Roles</i> – current active roles</li> </ul>
<code>reference</code>	91	<code>create table...references</code>	<ul style="list-style-type: none"> <li>• <i>Full command text</i> – full text of <code>create table</code> command</li> <li>• <i>Previous value</i> – NULL</li> <li>• <i>Current value</i> – NULL</li> <li>• <i>Other information</i> – NULL</li> <li>• <i>Proxy information</i> <code>set proxy</code> is in effect</li> </ul>

Full command text is included in `extrainfo`. For example: – original login name, if

```
sa_role sso_role oper_role sybase_ts_role mon_role; create table testab_tab9
(coll int) with transfer table off; ; ; ; sa/ase;
```

For more information about auditing, see *Security Administration Guide > Auditing*.

## 1.28 create index

Creates an index on one or more computed or noncomputed columns in a table. Creates partitioned indexes. Allows computed columns, like ordinary columns, to be index keys, and creates function-based indexes. A function-based index has one or more expressions as its index key.

The existing `create index` syntax can create indexes on computed columns, but function-based indexes require additional syntax.

The sections that describe this command are:

- [Syntax \[page 192\]](#)
- [Parameters \[page 193\]](#)
- [Examples \[page 199\]](#)
- [Usage \[page 204\]](#)
- [Standards \[page 205\]](#)
- [Permissions \[page 205\]](#)
- [Auditing \[page 205\]](#)

### Syntax

```
create [unique] [clustered | nonclustered] index <index_name>
  on [[<database>.]<owner>.]<table_name>
    (<column_expression> [asc | desc]
    [, <column_expression> [asc | desc]]...)
  [with {fillfactor = <pct>,
        online,
        latch_free_index = {on | off},
        index_compression = {none | page},
        index_hash_caching = {on [, bucket_count = <number> ] | off |
default}
        max_rows_per_page = <num_rows>,
        reservepagegap = <num_pages>,
        consumers = <x>, ignore_dup_key, sorted_data,
        [ignore_dup_row | allow_dup_row],
        [statistics using<num_steps> values]
        [, statistics <hash_option>]
        [, statistics max_resource_granularity = int]
        [, statistics histogram_tuning_factor = int]
        [, statistics print_progress = int}}]
  [on <segment_name>]
  [<index_partition_clause>]
  [<partial_index_clause>]
  for <data_partition_name> ...]]
  [defer_recovery = {[parallel], [auto | manual | none]]}]
```

Creates index partitions:

```
<index_partition_clause> ::=
  [local index [<partition_name>
  [with index_compression = {NONE | PAGE}][on <segment_name>]
  [, <partition_name> [on <segment_name>]
  [with index_compression = {NONE | PAGE}][on <segment_name>]...]]
```



Creates partial index:

```
<partial_index_clause>::=
  [partial index [<index_partition_name>]
    [on <segment_name>]
    for <data_partition_name>
    [, [<index_partition_name>] [on <segment_name>]
    for <data_partition_name> ...]]
```

Creates function-based indexes:

```
create [unique | nonclustered] index <index_name>
  on [[<database>.] [<owner>].] <table_name>
  (<column_expression> [asc | desc]
  [, <column_expression> [asc | desc]]...
```

## Parameters

### unique

prohibits duplicate index values (also called "key values"). The system checks for duplicate key values when the index is created (if data already exists), and each time data is added with an `insert` or `update`. If there is a duplicate key value or if more than one row contains a null value, the command fails, and the SAP ASE server prints an error message giving the duplicate entry.

#### ⚠ Caution

The SAP ASE server does not detect duplicate rows if a table contains any non-null `text`, `unitext`, or `image` columns.

`insert` and `update` commands, which generate duplicate key values, can succeed if you create your index using the `allow_dup_row` option.

Composite indexes (indexes in which the key value is composed of more than one column) can also be unique.

The default is nonunique. To create a nonunique clustered index on a table that contains duplicate rows, specify `allow_dup_row` or `allow_dup_row`.

When you create a unique local index on range-, list-, and hash-partitioned tables, the index key list is a superset of the partition-key list.

### clustered

means that the physical order of rows on the current database device is the same as the indexed order of the rows. The bottom, or leaf level, of the clustered index contains the actual data pages. A clustered index almost always retrieves data faster than a nonclustered index. Only one clustered index per table is permitted.

If `clustered` is not specified, `nonclustered` is assumed.

### nonclustered

means that the physical order of the rows is not the same as their indexed order. The leaf level of a nonclustered index contains pointers to rows on data pages. You can have as many as 249 nonclustered indexes per table.

#### <index\_name>

is the name of the index. Index names must be unique within a table, but need not be unique within a database.

#### <table\_name>

is the name of the table in which the indexed column or columns are located. Specify the database name if the table is in another database, and specify the owner's name if more than one table of that name exists in the database. The default value for <owner> is the current user, and the default value for <database> is the current database.

#### <column\_expression>

is a valid Transact-SQL expression that references at least one base column, and does not contain columns from other tables, local and global variables, aggregate functions, or subqueries.

#### i Note

<column\_expressions> replaces the <column\_name> variable used in SAP ASE versions earlier than 15.0.

#### asc | desc

specifies whether the index is to be created in ascending or descending order for the column specified. The default is ascending order.

#### fillfactor

specifies how full the SAP ASE server makes each page when it creates a new index on existing data. The `fillfactor` percentage is relevant only when the index is created. As data changes, the pages are not maintained at any particular level of fullness.

The value you specify is not saved in `sysindexes`. Use `sp_chgattribute` to create stored `fillfactor` values.

The default for `fillfactor` is 0; this is used when you do not include `with fillfactor` in the `create index` statement (unless the value has been changed with `sp_configure`). When specifying a `fillfactor`, use a value between 1 and 100.

A `fillfactor` of 0 creates clustered indexes with completely full pages and nonclustered indexes with completely full leaf pages. It leaves a comfortable amount of space within the index B-tree in both the clustered and nonclustered indexes. There is seldom a reason to change the `fillfactor`.

If the `fillfactor` is set to 100, the SAP ASE server creates both clustered and nonclustered indexes with each page 100 percent full. A `fillfactor` of 100 makes sense only for read-only, to which no data is ever added.

`fillfactor` values smaller than 100 (except 0, which is a special case) cause the SAP ASE server to create new indexes with pages that are not completely full. A `fillfactor` of 10 might be a reasonable choice if you are creating an index on a table that eventually holds a great deal more data, but small `fillfactor` values cause each index (or index and data) to occupy more storage space.

### ⚠ Caution

Creating a clustered index with a `fillfactor` affects the amount of storage space your data occupies, since the SAP ASE server redistributes the data as it creates the clustered index.

#### **max\_rows\_per\_page**

limits the number of rows on data pages and the leaf-level pages of indexes. Unlike `fillfactor`, the `max_rows_per_page` value is maintained until it is changed with `sp_chgattribute`.

If you do not specify a value for `max_rows_per_page`, the SAP ASE server uses a value of 0 when creating the table. Values for tables and clustered indexes range from 0 to 183K on a 2K page, to 0 to 1486 on a 16K page.

The maximum number of rows per page for nonclustered indexes depends on the size of the index key. The SAP ASE server returns an error message if the specified value is too high.

A `max_rows_per_page` value of 0 creates clustered indexes with full pages and nonclustered indexes with full leaf pages. It leaves a comfortable amount of space within the index B-tree in both clustered and nonclustered indexes.

If `max_rows_per_page` is set to 1, the SAP ASE server creates both clustered and nonclustered indexes with one row per page at the leaf level. Use low values to reduce lock contention on frequently accessed data. However, low `max_rows_per_page` values cause the SAP ASE server to create new indexes with pages that are not completely full, uses storage space, and may cause more page splits.

If CIS is enabled, you cannot use `max_rows_per_page` for remote servers.

### ⚠ Caution

Creating a clustered index with `max_rows_per_page` can affect the amount of storage space your data occupies, since the SAP ASE server redistributes the data as it creates the clustered index.

#### **with reservepagegap = <num\_pages>**

specifies a ratio of filled pages to empty pages to be left during extent I/O allocation operations. For each specified `<num_pages>`, an empty page is left for future expansion of the index. Valid values are 0 – 255. The default is 0.

#### **with consumers**

specifies the number of consumer processes that should perform the sort operation for creating the index. The actual number of consumer processes used to sort the index may be different from the specified number, depending on the number of worker processes available and the number of data partitions.

#### **ignore\_dup\_key**

cancels attempts of duplicate key entry into a table that has a unique index (clustered or nonclustered). The SAP ASE server cancels the attempted `insert` or `update` of a duplicate key with an informational message. After the cancellation, the transaction containing the duplicate key proceeds to completion.

You cannot create a unique index on a column that includes duplicate values or more than one null value, whether or not `ignore_dup_key` is set. If you attempt to do so, the SAP ASE server prints an error message that displays the first of the duplicate values. You must eliminate duplicates before the SAP ASE server can create a unique index on the column.

**ignore\_dup\_row**

allows you to create a new, nonunique clustered index on a table that includes duplicate rows. `allow_dup_row` deletes the duplicate rows from the table, and cancels any `insert` or `update` that would create a duplicate row, but does not roll back the entire transaction.

**allow\_dup\_row**

allows you to create a nonunique clustered index on a table that includes duplicate rows, and allows you to duplicate rows with `insert` and `update` statements.

**sorted\_data**

speeds creation of clustered indexes or unique nonclustered indexes when the data in the table is already in sorted order (for example, when you have used `bcop` to copy data that has already been sorted into an empty table).

**with statistics using <num\_steps> values**

specifies the number of steps to generate for the histogram used to optimize queries. If you omit this clause:

- The default value is 20, if no histogram is currently stored for the leading index column.
- The current number of steps is used, if a histogram for the leading column of the index column already exists.

If you specify 0 for `<num_steps>`, the index is re-created, but the statistics for the index are not overwritten in the system tables.

The actual number of steps may differ from the one you specify; if the histogram steps specified with `<num_steps>` is `<M>`, and the `histogram_tuning_factor` parameter is `<N>`, then the actual steps are between `<M>` and `<M*N>`, depending on the number of frequency cells that exist in the distribution.

**online**

creates indexes without blocking access to the data.

**latch\_free\_index**

indicates the latch policy of the index:

- on** Creates a latch-free indexes.
- off** Creates a regular index.

By default, if you do not specify a latch-free index, SAP ASE creates a regular, latched index.

**on <segment\_name>**

creates the index on the named segment. Before using the `on <segment_name>` option, initialize the device with `disk init`, and add the segment to the database using `sp_addsegment`. See your system administrator, or use `sp_helpsegment` to

generate a list of the segment names available in your database. There are two locations where you can use `on <segment_name>`:

- Immediately before the `<index_partition_clause>` – defines a global default which is used for all partitions where the segment is not explicitly defined in the `<index_partition_clause>`.
- Within that clause itself – allows you to specify a segment for each individual partition

See the examples section for an example that uses `on <segment_name>` in both locations.

#### `<hash_option>`

indicates whether to gather index statistics on tables:

- hashing** Statistics are gathered with hashing.
- new\_hashing** Enables hash-based gathering for minor attributed columns that have not had statistics previously gathered.
- no\_hashing** No hash-based statistics are gathered.

#### `with statistics hashing`

specifies:

- max\_resource\_granularity** Sets the maximum percentage of system resources a query can use.
- histogram\_tuning\_factor** Controls the number of steps that SAP ASE analyzes per histogram.
- print\_progress** Shows progress messages during gathering of statistics with hashing.

#### `local index`

specifies, for semantically partitioned tables, an index that is always equipartitioned with its base table; that is, the table and index share the same partitioning key and partitioning criteria. For round-robin-partitioned tables, a local index means that index keys in each of the tables' index partitions refer to data rows in one and only one table partition.

For both semantically partitioned tables and round-robin-partitioned tables, each table partition has only one corresponding index partition.

#### `<partition_name>`

specifies the name of a new partition on which indexes are to be stored. Partition names must be unique within the set of partitions on a table or index. Partition names can be delimited identifiers if `set quoted_identifier` is on. Otherwise, they must be valid identifiers.

If `<partition_name>` is omitted, the SAP ASE server creates a name in the form `<table_name_partition_id>`. The SAP ASE server truncates partition names that exceed the allowed maximum length.

#### `index_compression = {none | page}`

specifies whether to compress an index or index partition. Values are:

**NONE** The index page for the specified index is not compressed. Indexes that are specifically created with `index_compression = PAGE` are compressed.

**PAGE** When the page is full, existing index rows are compressed using the page prefix compression. When a row is added, a check determines whether the row suitable for compression.

`index_hash_caching = {on [, bucket_count = <number> ] | off | default}`

enables or disables index hash caching.

- `on` – indicates that the index you are creating uses hash caching.
- `off` – indicates that the index you are creating does not use hash caching
- `default` – when the `HCB index auto tuning` option is enabled, this allows SAP ASE to enable or disable index hash caching as needed.

`bucket_count = <number>`

specifies the number of hash table buckets for each index partition. If you do not specify `bucket_count`, the server uses an internally calculated value for the number of hash buckets.

**default**

allows utilities (for example, `dbcc` commands) to enable or disable index hash caching as needed.

**partial index**

indicates that you are creating a partial index on a partitioned table.

`<index_partition_name>`

name of the index partition. If you do not specify a name, SAP ASE generates one.

`<segment_name>`

name of the segment that holds the index partition.

`<data_partition_name>`

name of the data partition on which the index partition is based.

**with defer\_recovery**

enables you to defer the recovery of the index during load transaction recovery. Deferred recovery indexes are useful for (but not restricted to) queries that create indexes but don't need to retain the indexes. That is, the application needs only a temporary index and not a permanent index:

**parallel** Allows you to issue dump transaction commands after parallel sorts.

**auto** The index is re-created automatically during `online database` using the metadata in the system tables.

**manual** The index can be re-created manually any time after issuing `online database`. SAP ASE includes a warning in the error log saying that the index creation is deferred and must be created manually. Deferred recovery indexes are marked as suspect, ensuring that the optimizer does use them in any ad-hoc queries, and that stored procedures containing references to the index as part of the query tree are recompiled.

**none** online database removes the metadata for the index, dropping the index entirely. SAP ASE includes this as an informational message in the error log.

You cannot use deferred recovery indexes on:

- System tables
- System databases
- Clustered indexes

Additionally, SCC does not support re-creating and managing deferred recovery indexes

## Examples

### Example 1

Creates an index named `au_id_ind` on the `au_id` column of the `authors` table:

```
create index au_id_ind on authors (au_id)
```

### Example 2

Creates a unique clustered index named `au_id_ind` on the `au_id` column of the `authors` table:

```
create unique clustered index au_id_ind  
on authors (au_id)
```

### Example 3

Creates an index named `ind1` on the `au_id` and `title_id` columns of the `titleauthor` table:

```
create index ind1 on titleauthor (au_id, title_id)
```

### Example 4

Creates a nonclustered index named `zip_ind` on the `zip` column of the `authors` table, filling each index page one-quarter full and limiting the sort to 4 consumer processes:

```
create nonclustered index zip_ind  
on authors (postalcode)  
with fillfactor = 25, consumers = 4
```

### Example 5

Creates an index with ascending ordering on `pub_id` and descending order on `pubdate`:

```
create index pub_dates_ix  
on titles (pub_id asc, pubdate desc)
```

### Example 6

Creates an index on `title_id`, using 50 histogram steps for optimizer statistics and leaving 1 empty page out of every 40 pages in the index:

```
create index title_id_ix  
on titles (title_id)
```

```
with reservepagegap = 40,  
statistics using 50 values
```

### Example 7

Creates a local, clustered index on a partitioned `salesdetail` table. The `clust_idx` index inherits the partition strategy, partition key, and partition bounds of `salesdetail`.

```
create clustered index clust_idx  
on salesdetail (ord_num) local index
```

### Example 8

Creates a nonpartitioned, nonclustered global index on a partitioned `sales` table, which is partitioned by range on the `date` column.

```
create nonclustered index global_idx  
on sales (order_num)
```

### Example 9

First, creates a table, `pback_sales`, with three data partitions:

```
create table pback_sales (c1 int, c2 int,  
c3 varchar (20)) partition range (c1)  
(p1 c1 values <= (10),  
p2 c1 values <= (20),  
p3 c1 values <= (MAX))
```

Then, creates a local, function-based index on partition `p1`:

```
create index fc_idx on pback_sales (c1*c2) local index  
p1
```

### Example 10

`create index with sorted_data` selects a parallel query plan when an explicit `consumers =` clause is included. This example uses a parallel query plan for the first query, but uses a serial query plan for the second:

```
create index i1 on t1(c1) with sorted_data, consumers = N  
create index i1 on t1(c1) with sorted_data
```

### Example 11

Creates a function-based index:

```
create index sum_sales on mytitles (price * total_sales)
```

### Example 12

Specifies the `on <segment_name>` clause both before and after the partition name:

```
use tempdb  
go  
if not exists(select 1 from tempdb..syssegments where name = 'seg1')  
exec sp_addsegment seg1,tempdb,master  
go  
if not exists(select 1 from tempdb..syssegments where name = 'seg2')  
exec sp_addsegment seg2,tempdb,master  
go  
if not exists(select 1 from tempdb..syssegments where name = 'seg3')  
exec sp_addsegment seg3,tempdb,master  
go
```



```

if not exists(select 1 from tempdb..syssegments where name = 'seg4')
    exec sp_addsegment seg4,tempdb,master
go
if exists(select 1 from sysobjects where name = 't1')
    drop table t1
go
create table t1 (a int, b varchar(30)) partition by roundrobin (p1 on seg1,
p2 on seg2)
go
create index t1_i1 on t1 (a) local index
go
create index t1_i2 on t1 (a) on seg3 local index ip1 on seg4
go
sp_help t1
go

```

Provides the following output:

```

Name Owner Object_type Create_date
-----
t1    dbo    user table   Aug 7 2008 11:14AM
(1 row affected)
Column_name Type      Length Prec Scale Nulls Default_name Rule_name
Access_Rule_name Computed_Column_object Identity
-----
a      int      4  NULL  NULL  0  NULL  0  NULL
NULL
b      varchar 30  NULL  NULL  0  NULL  0  NULL
NULL
Object has the following indexes
index_name index_keys index_description index_max_rows_per_page
index_fillfactor index_reservepagegap index_created index_local
-----
t1_i1      a      nonclustered      0  Aug 7 2008 11:14AM Local Index
t1_i2      a      nonclustered      0  Aug 7 2008 11:14AM Local Index
(2 rows affected)
index_ptn_name index_ptn_seg
-----
t1_i1_952063116 default
t1_i1_968063173 default
ip1          seg4
t1_i2_1000063287 seg3
(4 rows affected)
No defined keys for this object.
name type      partition_type partitions partition_keys
-----
t1    base table roundrobin      2  NULL
(1 row affected)
partition_name partition_id pages row_count segment create_date
-----
p1          920063002  1  0  seg1  Aug 7 2008 11:14AM
p2          936063059  1  0  seg2  Aug 7 2008 11:14AM
Partition_Conditions
-----
NULL
Avg_pages Max_pages Min_pages Ratio (Max/Avg) Ratio (Min/Avg)
-----
1          1          1          1.000000  1.000000
Lock scheme Allpages
The attribute 'exp_row_size' is not applicable to tables with allpages lock
scheme.
The attribute 'concurrency_opt_threshold' is not applicable to tables with
allpages lock scheme.

```

```

exp_row_size reservepagegap fillfactor max_rows_per_page identity_gap
ascinserts
-----
0 0 0 0 0 0
(1 row affected)
concurrency_opt_threshold optimistic_index_lock dealloc_first_txtpg
-----
0 0 0
(1 row affected)
(return status = 0)

```

### Example 13

Creates a compressed index called `idx_order_line` on columns `ol_delivery_d` and `ol_dist_info`:

```

create index idx_order_line
  on order_line (ol_delivery_d, ol_dist_info)
with index_compression = page

```

If the index has an index row length that is too short to benefit from compression, a warning is raised indicating the index will not be compressed.

### Example 14

Creates a compressed index called `idx_sales`. The index contains local index partitions that can be compressed. Index prefix compression is applied to the local index partition. Page prefix compression is applied while the index page is full:

```

create index idx_sales
  on Sales(store_id, order_num)
  local index ip1 with index_compression = PAGE,
  ip2 with index_compression = PAGE,
  ip3

```

### Example 15

Creates a unique clustered index named `au_id_ind` on the `au_id` and `title_id` columns of the `authors` table. Statistics are gathered with hashing, counts 50 steps, and enables `print_progress` which shows progress messages:

```

create unique clustered index au_id_ind
  on authors(au_id, title_id)
with statistics hashing,
  statistics using 50 values,
  statistics print_progress = 1

```

### Example 16

Creates an index named `ind1` on the `au_id` and `title_id` columns of the `titleauthor` table. Statistics are gathered with hashing, counts 50 steps, and sets the percentage of system resources a query can use at 80 percent using the `max_resource_granularity` option:

```

create index ind1
  on titleauthor (au_id, title_id)
with statistics using 50 values,
  statistics hashing,
  statistics max_resource_granularity = 80

```

### Example 17

Creates a nonclustered index named `zip_ind` on the `postalcode` and `au_id` columns of the `authors` table. Each index page is filled one-quarter full and the sort is limited to 4 consumer processes. Statistics are gathered with hashing, counts 50 steps, and generates an intermediate 40-step histogram:

```
create nonclustered index zip_ind
  on authors(postalcode, au_id)
  with fillfactor = 25,
     consumers = 4,
     statistics using 50 values,
     statistics hashing,
     statistics histogram_tuning_factor = 40
```

### Example 18

Creates a unique clustered index named `au_id_ind` on the `au_id` and `title_id` columns of the `authors` table. Statistics are gathered with hashing for minor attributed columns that have not had statistics previously gathered:

```
create unique clustered index au_id_ind
  on authors(au_id, title_id)
  with statistics new_hashing
```

### Example 19

Creates a latch-free `idx_order_line` index on the `ol_delivery_d` and `ol_dist_info` columns:

```
create index idx_order_line
  on order_line (ol_delivery_d, ol_dist_info)
  with latch_free_index = on
```

### Example 20

Creates a `pub_dates_ix` index on the columns `pub_id` and `ascpubdate desc` of the `titles` table:

```
create index pub_dates_ix
  on titles (pub_id asc, pubdate desc)
  with online
```

The index is created without blocking access to the data.

### Example 21

Creates an index `t1` on the columns `c1` and `c3` of the `t1` table. The index is re-created automatically during online database using the metadata in the system tables.

```
create index i1
  on t1(c1, c3)
  with defer_recovery = auto
```

### Example 22

Creates an index `i1` on the columns `c1` and `c3` of the `t1` table. Three consumer processes will perform the sort operation for creating the index.

```
create index i1
  on t1(c1, c3)
  with consumers = 3
```

### Example 23

Creates a local index `i1` on the columns `c1` and `c3` of the `t1` table. Six consumer processes will perform the sort operation for creating the index.

```
create index i1
on t1(c1, c3)
with consumers = 3
local index
```

## Usage

- Periodically run `update statistics` if you add data to the table that changes the distribution of keys in the index. The query optimizer uses the information created by `update statistics` to select the best plan for running queries on the table.
- You can create non-clustered local index in parallel for partitioned tables that includes empty partitions.
- If the table contains data when you create a nonclustered index, the SAP ASE server runs `update statistics` on the new index. If the table contains data when you create a clustered index, the SAP ASE server runs `update statistics` on all the table's indexes.
- Index all columns that are regularly used in joins.
- When CIS is enabled, the `create index` command is reconstructed and passed directly to the SAP ASE associated with the table.
- You cannot use `create index` (clustered or unclustered) on the segment that includes the virtually hashed table, since a virtually hashed table must take only one exclusive segment, which cannot be shared by other tables or databases
- You can run `writetext` concurrently with the `online` parameter.
- `create index` allows you to create latch-free indexes only on data-only locked tables.
- Specifying the latch policy at the index level overrides the latch policy at the table level.
- You can compress latch-free indexes.

See also:

- `sp_addsegment`, `sp_chgattribute`, `sp_helpcomputedcolumn`, `sp_helpindex`, `sp_helpsegment`, `sp_spaceused` in *Reference Manual: Procedures*
- `optdiag` in the *Utility Guide*

Partial indexes must be:

- Created on a user-partitioned table that is not a proxy or deferred table
- Nonclustered local indexes

Partial indexes cannot be:

- Built on proxy databases
- Functional or replication indexes
- Online indexes

Partial indexes can be built in parallel.

## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

## Permissions

The permission checks for `create index` differ based on your granular permissions settings.

Setting	Description
---------	-------------

<b>Enabled</b>	With granular permissions enabled, you must be the table owner, or a user with the <code>create any index</code> privilege.
----------------	---

<b>Disabled</b>	With granular permissions disabled, you must be the table owner or a user with <code>sa_role.create index</code> permission defaults to the table owner and is not transferable.
-----------------	--

## Auditing

You can enable `create` auditing option to audit this command. Values in `event` and `extrainfo` columns from the `sysaudits` table are:

Information	Value
Audit option	<code>create</code>
Event	104
Command or access audited	<code>create index</code>

- Information in `extrainfo`
- **Roles** – current active roles.
  - **Full command text** – full text of `create index` command.
  - **Previous value** – NULL.
  - **Current value** – NULL.
  - **Other information** – NULL.
  - **Proxy information** – original login name, if `set proxy` is in effect.

Full command text is included in `extrainfo` column. For example:

```
sa_role sso_role oper_role sybase_ts_role mon_role;  
create index au_id_ind on authors (au_id); ; ; ; sa/ase;
```

For more information about auditing, see *Security Administration Guide > Auditing*.

## Related Information

[alter index \[page 44\]](#)

[alter table \[page 70\]](#)

[create table \[page 273\]](#)

[drop index \[page 439\]](#)

[insert \[page 572\]](#)

[order by Clause \[page 630\]](#)

[set \[page 732\]](#)

[update \[page 819\]](#)

[reorg \[page 661\]](#)

### 1.28.1 Creating Indexes Efficiently

Indexes speed data retrieval, but can slow data updates. For better performance, create a table on one segment and create its nonclustered indexes on another segment, when the segments are on separate physical devices.

The SAP ASE server can create indexes in parallel if a table is partitioned and the server is configured for parallelism. It can also use sort buffers to reduce the amount of I/O required during sorting. See *Parallel Sorting in Performance and Tuning Guide: Optimizer and Abstract Plans*.

Create a clustered index before creating any nonclustered indexes, since nonclustered indexes are automatically rebuilt when a clustered index is created.

When using parallel sort for data-only-locked tables, the number of worker processes must be equal or exceed the number of partitions, even for empty tables. The database option `select into/bulkcopy/pllsort` must also be enabled.

### 1.28.2 Creating Clustered Indexes

A table “follows” its clustered index. When you create a table, using the `on <segment_name>` extension to `create clustered index`, the table migrates to the segment where the index is created.

If you create a table on a specific segment, then create a clustered index without specifying a segment, the SAP ASE server moves the table to the default segment when it creates the clustered index there.

Because `text`, `unitext`, and `image` data is stored in a separate page chain, creating a clustered index with `on <segment_name>` does not move text and image columns.

To create a clustered index, the SAP ASE server duplicates the existing data; the server deletes the original data when the index is complete. Before creating a clustered index, use `sp_spaceused` to make sure that the database has at least 120 percent of the size of the table available as free space.

The clustered index is often created on the table’s primary key (the column or columns that uniquely identify the row). You can record the primary key in the database (for use by front-end programs and `sp_depends`) using `sp_primarykey`.

To allow duplicate rows in a clustered index, specify `allow_dup_row`.

### 1.28.3 Creating Indexes on Compressed Table

Considerations that apply when creating indexes on compressed tables.

- If a table requires sorting, the SAP ASE server compresses all rows that are available for compression during the data copy operation.
- The SAP ASE server does not perform a data copy if you create a clustered index using `sorted_data`, and does not compress any data rows while it builds the clustered index.
- The SAP ASE server does not compress index key values: It compresses only the values in the data rows.
- You may select index key columns and create unique indexes even if the key columns are compressed. To perform nonclustered uniqueness checks, examine the uncompressed index keys in an index page.
- The SAP ASE server uses the uncompressed index key and row formats to verify support for `ignore_dup_key`, `ignore_dup_row`, and `allow_dup_row`.
- The SAP ASE server applies the `fillfactor` parameter only for row-level compression.
- When it applies the `fillfactor` parameter to the data pages of an allpages-locked clustered index, the SAP ASE server considers the:
  - Final compressed row format
  - Space required for compressionThe SAP ASE server may additionally compress the page space used with subsequent page compression operations, resulting in lower `fillfactor` values.
- The SAP ASE server applies the `respagegap` parameter at the page level so it is not affected by compression.
- `max_rows_per_page` includes a page's data rows only, and not the hidden page-dictionary, index, and character-encoding entries.

### 1.28.4 Creating Indexes on Encrypted Columns

You can create an index on an encrypted column if you specify the encryption key without any initialization vector or random padding. Indexes on encrypted columns are useful for equality and nonequality matches, but cannot be used to match case-insensitive data, or to perform range searches of any data.

To improve performance on both equality and nonequality searches, and on joins, create indexes on encrypted columns.

`create index` reports an error if you create:

- A functional index using an expression that references an encrypted column
- An index on a column encrypted with initialization vector or random padding

#### i Note

You cannot use an encrypted column in an expression for a functional index.

## 1.28.5 Considerations for Creating Indexes on In-Memory Row Storage Tables

There are a number of items to consider when you create indexes for in-memory row storage tables.

- Generally, issuing `create index` does not move inserted rows from the in-memory row storage, but it may flush migrated rows to the page store. For example, building a clustered index requires sorting the rows in the page store, however, the sorting criteria does not apply to the rows in the in-memory row storage, and the migrated rows in the in-memory row storage are flushed to the page-store so subsequent sorts can consider them as well.

Once `create index` builds the placement index, the in-memory row storage contains inserted rows, but does not contain migrated or cached rows. However, building a nonclustered index does not move rows that already exist in the in-memory row storage (both inserted and migrated). `create index` builds the index directly on the rows in the in-memory row storage. Once the index is built, the in-memory row storage may contain inserted, migrated, and cached rows. The final state of the in-memory row storage may vary according to the `create index` command.

- You cannot include the `create index ... with online` parameter on IMRS-enabled databases.
- `create index` on in-memory row storage tables does not support:
  - `load transaction create index recovery` for all cases of serial `create index` on an in-memory row storage-enabled table.
  - Replication index
- Issuing parallel `create index`
  - On an unpartitioned table – runs utility-based parallelism if the `enable functionality group` configuration parameter is disabled, runs lava-based parallelism if the `enable functionality group` configuration parameter is enabled.
  - On partitioned tables – runs a utility-driven `create index` regardless of the `enable functionality group` setting.
  - With the `with consumers` parameter – may still generate a parallel plan even if you do not specify this parameter, depending on the data distribution across devices.
- Issuing `create index with sorted_data` fails if the table has any rows in the in-memory row storage. Instead you must reissue the command without the `with sorted_data` parameter (`create index` must scan rows from both stores and expects to receive rows in a sorted order). Instead, SAP recommends that you:
  1. Use `alter table row storage off` to pack the existing rows to the page store.
  2. Disable row caching for the table with `alter table set row_caching off` or `set row_caching off` (for the session).
  3. Load the externally sorted data directly into the page store.
  4. Build the index using `create index with sorted_data`.

This procedure may not work if the first step packs inserted rows to the page store. Instead, the rows may be stored in unsorted order, violating the requirements of the sorted-sort index build. Generally, these steps are largely inapplicable or not supportable for in-memory row storage tables.

- Creating a function based index:
  - Supported if the in-memory row storage-enabled table includes no rows.
  - Unsupported if the in-memory row storage-enabled table includes rows.
- When creating hash-cached indexes:
  - Hash-cached indexes are created only on data-only locked tables.



- Hash cached indexes must be defined on unique indexes. If the index is not unique, the `create index` command stops and aborts the process.
- You can specify a bucket count if hash caching is enabled. However, if you specify `bucket_count = <number>`, you must also specify `index_hash_caching`.
- If you specify a bucket number, the server rounds the number to  $2^n$ . If `index_hash_caching` is enabled, the server calculates a bucket number internally. Ideally, the hash bucket number is one to two times the total number of distinct data rows covered by the local index. The server chooses the larger value of:
  - 1.5 times the total number of distinct data rows
  - 100000
 Regardless, the bucket number is rounded up to  $2^n$ . For example, if users set bucket count as 1000, then internally it will be changed to  $2^{10}$ –1024.
- You can use the `index_hash_caching` parameter with other `create index` parameters. However, the other parameters apply only to the B-tree indexes in the page store.

## 1.28.6 Specifying Ascending or Descending Ordering in Indexes

Use the `asc` and `desc` keywords after index column names to specify the sorting order for the index keys.

Creating indexes so that columns are in the same order specified in the `order by` clause of queries eliminates the sorting step during query processing. See *Indexing for Performance* in *Performance and Tuning Guide: Locking*.

## 1.28.7 Space Requirements for Indexes

Space is allocated to tables and indexes in increments of one extent, or eight pages, at a time. Each time an extent is filled, another extent is allocated. Use `sp_spaceused` to display the amount of space allocated to and used by an index.

In some cases, using the `sorted_data` option allows the SAP ASE server to skip copying the data rows. In these cases, you need only enough additional space for the index structure itself. Depending on key size, this is usually about 20 percent of the size of the table.

## 1.28.8 Duplicate Rows

Considerations when using `ignore_dup_row` and `allow_dup_row` options.

- The `ignore_dup_row` and `allow_dup_row` options are irrelevant when you create a nonunique, nonclustered index. The SAP ASE server attaches a unique row identification number internally in each nonclustered index; duplicate rows are not a problem, even for identical data values.
- `ignore_dup_row` and `allow_dup_row` are mutually exclusive.

- In all-pages-locked tables, nonunique clustered indexes allows duplicate keys, but does not allow duplicate rows unless you specify `allow_dup_row`. This behavior differs for data-only-locked tables.
- `allow_dup_row` allows you to create a nonunique, clustered index on a table that includes duplicate rows. If a table has a nonunique, clustered index that was created without the `allow_dup_row` option, you cannot create new duplicate rows using the `insert` or `update` command. If any index in the table is unique, the requirement for uniqueness takes precedence over the `allow_dup_row` option. You cannot create an index with `allow_dup_row` if a unique index exists on any column in the table.
- The `ignore_dup_row` option is also used with a nonunique, clustered index. The `ignore_dup_row` option eliminates duplicates from a batch of data. In all-pages-locked tables, `ignore_dup_row` cancels any `insert` or `update` that would create a duplicate row, but does not roll back the entire transaction.
- This table illustrates how `allow_dup_row` and `ignore_dup_row` affect attempts to create a nonunique, clustered index on a table that includes duplicate rows and attempts to enter duplicate rows into a table.

Option Setting	Create an Index on a Table That Has Duplicate Rows	Insert Duplicate Rows into a Table With an Index
Neither option set	<code>create index</code> fails.	<code>insert</code> fails.
<code>allow_dup_row</code> set	<code>create index</code> completes.	<code>insert</code> completes.
<code>ignore_dup_row</code> set	Index is created, but duplicate rows are deleted; error message.	All rows are inserted, except duplicates; error message.

This table shows which index options you can use with the different types of indexes:

Index Type	Options
Clustered	<code>ignore_dup_row</code>   <code>allow_dup_row</code>
Unique, clustered	<code>ignore_dup_key</code>
Nonclustered	None
Unique, nonclustered	<code>ignore_dup_key</code>

## 1.28.9 Using Unique Constraints in Place of Indexes

As an alternative to `create index`, you can implicitly create unique indexes by specifying a unique constraint with the `create table` or `alter table` statement. The unique constraint creates a clustered or nonclustered unique index on the columns of a table. These *implicit* indexes are named after the constraint, and they follow the same rules for indexes created with `create index`.

You cannot drop indexes supporting unique constraints using the `drop index` statement. They are dropped when the constraints are dropped through an `alter table` statement or when the table is dropped. See `create table` for more information about unique constraints.

## 1.28.10 Using the `sorted_data` Option to Speed Sorts

The `sorted_data` option can reduce the time needed to create an index by skipping the sort step and by eliminating the need to copy the data rows to new pages in certain cases. The speed increase becomes significant on large tables, and increases to several times faster in tables larger than 1GB.

If `sorted_data` is specified, but data is not in sorted order, the SAP ASE server displays an error message, and the command fails.

The effects of `sorted_data` for creating a clustered index depend on whether the table is partitioned and whether certain other options are used in the `create index` command. Some options require data copying, if used at all, for nonpartitioned tables and sorts plus data copying for partitioned tables, while others require data copying only if you use:

- The `ignore_dup_row` option
- The `fillfactor` option
- The `on <segmentname>` clause to specify a segment that is different from the segment where the table data is located
- The `max_rows_per_page` clause to specify a value that is different from the value associated with the table

Creating a nonunique, nonclustered index succeeds, unless there are rows with duplicate keys. If there are rows with duplicate keys, the SAP ASE server displays an error message, and the command fails.

This table shows when the sort is required and when the table is copied for partitioned and nonpartitioned tables.

Options	Partitioned Table	Unpartitioned Table
No options specified	Parallel sort necessary only for creating a clustered index on a round-robin-partitioned table; copies data, distributing evenly on partitions; creates index tree.	Either parallel or nonparallel sort; copies data, creates index tree.
with <code>sorted_data</code> only or with <code>sorted_data on &lt;same_segment&gt;</code>	Creates index tree only. Does not perform the sort or copy data. Does not run in parallel.	Creates index tree only. Does not perform the sort or copy data. Does not run in parallel.
with <code>sorted_data</code> and <code>ignore_dup_row</code> or <code>fillfactor</code> or on <code>&lt;other_segment&gt;</code> or <code>max_rows_per_page</code>	Parallel sort; copies data, distributing evenly on partitions; creates index tree.	Copies data and creates the index tree. Does not perform the sort. Does not run in parallel.

## 1.28.11 Specifying the Number of Histogram Steps

Use the `with statistics` clause to specify the number of steps for a histogram for the leading column of an index. Histograms are used during query optimization to determine the number of rows that match search arguments for a column.

To re-create an index without updating the values in `sysstatistics` for a column, use 0 for the number of steps. This avoids overwriting statistics that have been changed with `optdiag`.

If you specify the `histogram_tuning_factor` parameter with a value, then `create index` uses anywhere between 20 and  $M*20$  steps, depending on the number of frequency cells that have been isolated. The default is 20, but you can specify a different number with the `using step values` option.

## 1.28.12 Space Management Properties

`fillfactor`, `max_rows_per_page`, and `reservepagegap` help manage space on index pages in different ways.

- `fillfactor` applies to indexes for all locking schemes. For clustered indexes on allpages-locked tables, it affects the data pages of the table. On all other indexes, it affects the leaf level of the index.
- `max_rows_per_page` applies only to index pages of allpages-locked tables.
- `reservepagegap` applies to tables and indexes for all locking schemes.

`reservepagegap` affects space usage in indexes when:

- The index is created.
- `reorg` commands on indexes are executed.
- Nonclustered indexes are rebuilt after creating a clustered index.

When a `reservepagegap` value is specified in a `create clustered index` command, it applies to:

- The data and index pages of allpages-locked tables
- Only the index pages of data-only-locked tables

The `<num_pages>` value specifies a ratio of filled pages to empty pages on the leaf level of the index so that indexes can allocate space close to existing pages, as new space is required. For example, a `reservepagegap` of 10 leaves 1 empty page for each 9 used pages.

`reservepagegap` specified along with `create clustered index` on an allpages-locked table overwrites any value previously specified with `create table` or `alter table`.

You can change the space management properties for an index with `sp_chgattribute`. Changing properties with `sp_chgattribute` does not immediately affect storage for indexes on the table. Future large scale allocations, such as `reorg rebuild`, use the `sp_chgattribute` value.

The `fillfactor` value set by `sp_chgattribute` is stored in the `fill_factor` column in `sysindexes`. The `fillfactor` is applied when an index is re-created as a result of an `alter table...lock` command or a `reorg rebuild` command.

## 1.28.13 Index Options and Locking Modes

Allpages-locked and data-only-locked tables are supported by certain index options. On data-only-locked tables, the `ignore_dup_row` and `allow_dup_row` options are enforced during `create index`, but are not enforced during `insert` and `update` operations.

Data-only-locked tables always allow the insertion of duplicate rows.

Index Type	Allpages-Locked Table	Data-Only-Locked Table	
		During Index Creation	During Inserts
Clustered	<code>allow_dup_row</code> , <code>ignore_dup_row</code>	<code>allow_dup_row</code> , <code>ignore_dup_row</code>	<code>allow_dup_row</code>
Unique clustered	<code>ignore_dup_key</code>	<code>ignore_dup_key</code>	<code>ignore_dup_key</code>
Nonclustered	None	None	None
Unique nonclustered	<code>ignore_dup_key</code>	<code>ignore_dup_key</code>	<code>ignore_dup_key</code>

This table shows the behavior of commands that attempt to insert duplicate rows into tables with clustered indexes, and when the clustered indexes are dropped and re-created.

Options	Allpages-Locked Table	Data-Only-Locked Table
No options specified	Insert fails with error message 2615. Re-creating the index succeeds.	Insert succeeds. Re-creating the index fails with error message 1508.
<code>allow_dup_row</code>	Insert and re-creating the index succeed.	Insert and re-creating the index succeed.
<code>ignore_dup_row</code>	Insert fails with "Duplicate row was ignored" message. Re-creating the index succeeds.	Insert succeeds. Re-creating the index deletes duplicate rows.

## 1.28.14 Using the `sorted_data` Option on Data-Only-Locked Tables

You can use the `sorted_data` option to `create index` only immediately following a bulk-copy operation into an empty table. Once data modifications to that table cause additional page allocations, you cannot use the `sorted_data` option.

Specifying different values for space management properties may override the sort suppression functionality of the `sorted_data`.

## 1.28.15 Getting Information About Tables and Indexes

Each index—including composite indexes—is represented by one row in `sysindexes`.

For information about the order of the data retrieved through indexes and the effects of an SAP ASE-installed sort order, see the `order by` clause.

For information about a table's indexes, execute `sp_helpindex`. For information about index partitions, you can also execute `sp_helppartitions`.

Each index partition and data partition is represented by one row in `syspartitions`.

## 1.28.16 Creating Indexes on Computed Columns

You can use materialized computed columns as index keys, as though they were regular columns.

To convert a virtual column to a materialized column and index it, use `alter table modify` with the `materialized` option before executing `create index`.

A computed column need not be deterministic to be used as an index key; however, you must be careful about the possible impact of a nondeterministic column on the queries that reference it.

## 1.28.17 Creating Partitioned Indexes

A local index inherits the partition strategies, partition columns, and partition bounds (for range and list partitions) of the base table.

The SAP ASE server maintains local indexes, rebuilding the local index if the base table is repartitioned with a different partition key.

The SAP ASE server supports:

Index Type	Table Type
Local clustered and nonclustered partitioned indexes	Partitioned tables
Global, clustered, unpartitioned indexes	Round-robin-partitioned tables
Global, nonclustered, unpartitioned indexes	All partitioned tables

For range-, hash-, and list-partitioned tables, clustered indexes are always local. The SAP ASE server creates a local clustered index whether or not "local index" is included in the syntax.

## 1.28.18 Creating Function-Based Indexes

Considerations for creating function-based indexes.

- You can create indexes directly on expressions.
- The expression must be deterministic.
- Since the SAP ASE server does not verify the deterministic property of the expression index key, the user must manually maintain the property. A change in this property can cause unexpected results.
- As a function-based index key must be deterministic, its result is preevaluated, and reused without reevaluation. The SAP ASE server assumes all function-based index keys to be deterministic and uses their pre-evaluated values when they are referenced in a query; they are reevaluated only when the values of their base columns are changed.
- An index can have multiple function-based index keys or a combination of function-based index keys and regular columns.
- Expressions used as index keys must be deterministic. An expression key is different from a computed column index key, which needs to be evaluated only once, and does not require the deterministic property. An expression, however, must be reevaluated upon each occurrence of the expression in a specified query, and must always return the same result.
- If a user-defined function that is referenced by a function-based index is dropped or becomes invalid, any operations that call that function fail.
- The SAP ASE server does not support clustered function-based indexes.
- You cannot create a function-based index with the `sorted_data` option.
- Once you create an index key on an expression, subsequent queries recognize the expression as an index key only if the expression is exactly the same as the expression used to create the index key.
- All `insert`, `delete`, and `update` operations on base columns cause the SAP ASE server to automatically update the value of function-based index keys.

## 1.28.19 create index and Stored Procedures

The SAP ASE server automatically recompiles stored procedures after executing `create index` statements. Although ad hoc queries that you start before executing `create index` continue to work, they do not take advantage of the new index. In SAP ASE versions 12.5 and earlier, `create index` was ignored by cached stored procedures.

## 1.28.20 Creating Indexes in Parallel

There are a number of items to consider when creating indexes in parallel

- If you do not specify the `with consumers` parameter, `create index` creates a parallel index when:
- If you specify a parallel `create index` using a lava query processor, the index is created when
  - Number of devices in the target table.
  - Size of the table.
  - `number of sort buffers` is configured for

- `max utility parallel degree` is set to
- The `with defer_recovery` parameter creates an index when `enforce dump tran sequence` is set to ??? and `select into/bulkcopy/pllsort` is set to ???.

## 1.29 create login

Creates a login account; specifies a password, a login profile for the account, and user-supplied parameters to be assigned to the account.

### Syntax

```
create login <login_name> with [encrypted]
    password <password>
    [<attribute_value_pair_list>]
```

### Parameters

#### <login\_name>

specifies the name of the login account to be created; it must start with an alphabetic character and cannot exceed 30 characters in length.

#### with encrypted

specifies an encrypted password for the new login account.

#### password <password\_value>

specifies a password for the new login account. See *Choose and Create a Password* in the *Security Administration Guide*.

#### <attribute\_value\_pair\_list>

list of attributes and corresponding values to be added to the login account. The `<attribute_value_pair_list>` is an attribute name and value. Specify one or more of the following attributes:

#### login profile

```
{<login_profile_name> |
ignore}
```

`<login_profile_name>` binds the specified login profile to the specified login account.

`ignore` eliminates any login profile binding. A default login profile is not applicable and attributes are applied as they were prior to release 15.7.

If `login profile` is not specified, a default login profile is applied. See *Applying Login Profile and*



*Password Policy Attributes in the Security Administration Guide.*

<b>suid</b>	By default, an suid is generated and automatically assigned to the login account upon creation.  Valid values: Unique value between [-32768, 2147483647] excluding [-2, -1, 0, 1, 2].
<b>fullname</b> <code>&lt;name_value&gt;</code>	Is the full name of user who owns the login account. The default is NULL.
<b>login script</b> <code>&lt;login_script_name&gt;</code>	Specifies a valid stored procedure. Limited to 120 characters for a login script.
<b>password expiration</b> <code>&lt;number&gt;</code>	Is the password expiration interval. The valid range: 0 to 32767 days. The default of 0 means the password never expires.
<b>min password length</b> <code>&lt;number&gt;</code>	The minimum password length required, the valid range: 0 to 30 (default is 6).
<b>max failed attempts</b> <code>&lt;number&gt;</code>	The number of login attempts allowed after which the login account is locked.  Valid range: -1 to 32767. -1 indicates the failed count is tracked but not locked.  The default is 0, meaning the failed count is not tracked and the account is not locked due to failed login attempts.
<b>default database</b> <code>&lt;default_database_name&gt;</code>	Specifies a database to be the default.  Default is <code>master</code> .
<b>default language</b> <code>&lt;default_language&gt;</code>	Specifies a language to be the default.  Default is <code>us_english</code>
<b>authenticate with</b> <code>&lt;authentication mechanism&gt;</code>	Specifies the mechanism used for authenticating the login account.  Valid values for <code>&lt;authentication mechanism&gt;</code> are: ASE, LDAP, PAM, KERBEROS, ANY  When <code>ANY</code> is used, the SAP ASE server checks for a defined external authentication mechanism. If one is defined, the SAP ASE server uses the defined mechanism., otherwise the <code>ASE</code> mechanism is used.

```
exempt inactive lock  
{true | false}
```

If `authenticate` with `<authentication mechanism>` is not specified, `ANY` is used for the login account.

Specifies whether or not to exempt login accounts from being locked due to inactivity.

Default is `FALSE`, which indicates accounts are not exempt.

## Examples

### Example 1

Creates a login account with password `itsA8ecret`, applies the login profile `emp_lp`, applies server user ID 7, and specifies that the account is not locked due to inactivity.

```
create login ravi with password itsA8ecret login profile  
emp_lp suid 7 exempt inactive lock true
```

### Example 2

Creates the login `susan` with the password `itsA8ecret` on the default database `test`.

```
create login susan with password itsA8ecret default database test
```

### Example 3

Creates the login `susan` with the password `itsA8ecret` on the default database `test` with English as the default language.

```
create login susan with password itsA8ecret default database test default  
language us_english
```

### Example 4

Creates the login `susan` with the password `itsA8ecret` on the default database `test`, and applies the full name "Susan B. Anthony."

```
create login susan with password itsA8ecret fullname "Susan B. Anthony"  
default database test
```

## Usage

- Precedence rules determine how login account attributes are applied when attributes are taken from different login profiles or when values have been specified using `sp_passwordpolicy`.
- For ease of management, it is strongly recommended that the SAP ASE login names of all users be the same as their operating system login names. This makes it easier to correlate audit data between the operating system and the SAP ASE server. Otherwise, keep a record of the correspondence between operating system and server login names.

See also:

- For more information about creating login accounts, see the *Security Administration Guide*. For precedence rules, see *Applying login profile and password policy attributes* in the *Security Administration Guide*.
- `lprofile_id`, `lprofile_name` in *Reference Manual: Building Blocks*
- `sp_passwordpolicy`, `sp_displaylogin`, `sp_displayroles`, `sp_locklogin` in *Reference Manual: Procedures*

## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

## Permissions

The permission checks for `create login` differ based on your granular permissions settings.

Setting	Description
Enabled	With granular permissions enabled, you must be a user with the <code>manage any login</code> privilege.
Disabled	With granular permissions disabled, you must be a user with <code>sso_role</code> .

## Auditing

Values in `event` and `extrainfo` columns of `sysaudits` are:

Information	Values
Event	103
Audit option	<code>login_admin</code> , <code>security</code>
Command or access audited	<code>create login</code>
Information in <code>extrainfo</code>	<ul style="list-style-type: none"><li>• <b>Roles</b> – current active roles</li><li>• <b>Full command text</b> – full text of <code>create login</code> command (password is obfuscated)</li><li>• <b>Previous value</b> – NULL</li><li>• <b>Current value</b> – NULL</li><li>• <b>Other information</b> – NULL</li><li>• <b>Proxy information</b> – original login name, if <code>set proxy</code> is in effect</li></ul>

## Information

## Values

Full command text with obfuscated password is included in `extrainfo` column. For example:

```
sa_role sso_role oper_role sybase_ts_role mon_role;
create login test4 with encrypted passwd '*****' default
database master; ; ; ; sa/ase;
```

For more information about auditing, see *Security Administration Guide > Auditing*.

## Related Information

[alter login \[page 47\]](#)

[alter login profile \[page 54\]](#)

[create login profile \[page 220\]](#)

[drop login \[page 442\]](#)

[drop login profile \[page 444\]](#)

## 1.30 create login profile

Creates a login profile with specified attributes.

## Syntax

```
create login profile <login_profile_name> [as default]
    [with {attributes from <login_name> | <attribute_value_pair_list>}]
```

## Parameters

**<login\_profile\_name>**

specifies the name of the login profile to be created.

**as default**

sets the created login profile as the default for all login accounts except `sa` and `probe`.

**with attributes from {<login\_name> | <attribute\_value\_pair\_list>}**

when `<login_name>` is specified, creates a login profile with attributes values taken from the specified login account. The `<attribute_value_pair_list>` specifies,

an attribute name and corresponding value. Specify one or more of the following attributes and value:

<b>default database</b> <b>&lt;default_database_name&gt;</b>	Specifies a default database. The default is <code>Master</code> .
<b>default language</b> <b>&lt;default_language&gt;</b>	Specifies a default language. The default is <code>us_english</code> .
<b>login script</b> <b>&lt;login_script_name&gt;</b>	Specifies a valid stored procedure. Limited to 120 characters for a login script.
<b>authenticate with</b> <b>&lt;authentication mechanism&gt;</b>	<p>Specifies the mechanism used for authenticating the login account. Valid values: <code>ASE</code>, <code>LDAP</code>, <code>PAM</code>, <code>KERBEROS</code>, <code>ANY</code>.</p> <p>When <code>ANY</code> is used, the SAP ASE server checks for a defined external authentication mechanism. If one is defined, the SAP ASE server uses the defined mechanism., otherwise the <code>ASE</code> mechanism is used.</p> <p>If <code>authenticate with &lt;authentication mechanism&gt;</code> is not specified, <code>ANY</code> is used for the login account.</p>
<b>track lastlogin {true   false}</b>	Enables last login updates. The default is <code>true</code> , which is to update.
<b>stale period &lt;number&gt;</b>	Indicates the duration a login account is allowed to remain inactive before it is locked due to inactivity. Valid values are 1 .. 32767 days. Duration: <code>D</code> (days), <code>w</code> (weeks), <code>M</code> (months), <code>Y</code> (years). The default is <code>D</code> (days).
<b>profile id</b>	<p>Shares the ID space with the server user ID (suid) of login accounts. By default, the login profile ID is generated and automatically assigned to the login profile upon creation</p> <p>Valid value is unique between login accounts and login profiles. Range: [-32768, 2147483647] Excluding: -2, -1, 0, 1, 2</p>

## Examples

### Example 1

Creates a login profile. Attribute values that are not set follow the precedence rules:

```
create login profile eng_lp
```

For information, see *Applying Login Profile and Password Policy Attributes* in the *Security Administration Guide*.

### Example 2

Creates a login profile and transfers the login attribute values from the login account `ravi` to the new login profile `ravi_lp`. Attribute values that are not set follow the precedence rules.

```
create login profile ravi_lp with attributes from ravi
```

### Example 3

Creates login profile `sa_login_profile` with the authentication method ASE:

```
create login profile sa_login_profile with authenticate
with ASE
```

## Usage

Precedence rules determine how login account attributes are applied when attributes are taken from different login profiles, or when values have been specified using `sp_passwordpolicy`.

See also:

- For information about creating login profiles, invoking a login script at login, and precedence rules, see the *Security Administration Guide*.
- `lprofile_id`, `lprofile_name` in *Reference Manual: Building Block*
- `sp_passwordpolicy`, `sp_displaylogin`, `sp_displayroles`, `sp_locklogin` in *Reference Manual: Procedures*

## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

## Permissions

The permission checks for `create login profile` differ based on your granular permissions settings.

Setting	Description
---------	-------------

Enabled	With granular permissions enabled, you must be a user with the <code>manage any login profile</code> privilege.
---------	---

Disabled	With granular permissions disabled, you must be a user with <code>sso_role</code> .
----------	---

## Auditing

You can enable the following auditing options to audit this command. Values in `event` and `extrainfo` columns from the `sysaudits` table are:

Information	Value
Audit option	<code>security_profile, security</code>
Event	137
Command or access audited	<code>create login profile</code>
Information in <code>extrainfo</code>	<ul style="list-style-type: none"><li>• <b>Roles</b> – current active roles</li><li>• <b>Full command text</b> – full text of <code>create login profile</code> command</li><li>• <b>Previous value</b> – NULL</li><li>• <b>Current value</b> – NULL</li><li>• <b>Other information</b> – NULL</li><li>• <b>Proxy information</b> – original login name, if <code>set proxy</code> is in effect</li></ul>

Full command text is included in `extrainfo` column. For example:

```
sa_role sso_role oper_role sybase_ts_role mon_role;  
create login profile vivekk_lp; ; ; ; sa/ase;
```

For more information about auditing, see *Security Administration Guide > Auditing*.

## Related Information

[alter login \[page 47\]](#)

[alter login profile \[page 54\]](#)

[create login \[page 216\]](#)

[drop login \[page 442\]](#)

[drop login profile \[page 444\]](#)

## 1.31 create manifest file

Creates a manifest file for one or more databases.

The manifest file is the binary file that describes the databases that are present on a set of database devices. It can be created only if the set of databases that occupy those devices are isolated, and self-contained on those devices. Use the `create manifest file` command to create a manifest file, which you need to run the `quiesce database` command for mounting and unmounting databases. For more information, see “Using mount and unmount commands” in the “Backup and Recovery Plan” chapter of the System Administration Guide, Volume 2.

## Syntax

```
create manifest file <database_list> to <manifest_file_name>
```

## Parameters

**database\_list**

is the list of databases for which you are creating a manifest file.

**manifest\_file\_name**

is the name of the manifest file you are creating. Enclose full path names in quotes.

## Examples

### Example 1

Creates a manifest file for the database `big_database` in the current directory:

```
create manifest file big_database to big_database_manifest
```

### Example 2

Creates a manifest file for the databases `big_database`, `medium_database`, and `small_database`:

```
create manifest file big_database, medium_database, small_database to  
'/sybase/data/database_manifest'
```

## Usage

- You cannot run `create manifest file` within a transaction.
- You cannot include system databases in the `<database_list>`.
- You cannot run `create manifest file` in a high availability system that is in a transient (failover or failback) state.
- You cannot include a database in the `<database_list>` that resides on a disk that is shared by another database that is not included in the manifest file list.
- You cannot create a manifest file for an archived database.

## Permissions

You must have the `sa_role` or `oper_role` to run `create manifest file`.



## Auditing

`create manifest file` is audited by audit event number 116.

## 1.32 create plan

Creates an abstract plan.

### Syntax

```
create plan <query> <plan>
    [into <group_name>]
    [and set @<new_id>]
```

### Parameters

**<query>**

is a string literal, parameter, or local variable containing the SQL text of a query.

**<plan>**

is a string literal, parameter, or local variable containing an abstract plan expression.

**into <group\_name>**

specifies the name of an abstract plan group.

**and set @<new\_id>**

returns the ID number of the abstract plan in the variable.

### Examples

#### Example 1

Creates an abstract plan for the specified query:

```
create plan "select * from titles where price > $20" " (t_scan titles)"
```

#### Example 2

Creates an abstract plan for the query in the `dev_plans` group, and returns the plan ID in the variable `@id`:

```
declare @id int
```

```
create plan "select au_fname, au_lname from authors where au_id =
'724-08-9931' "
" (i_scan au_id_ix authors)"
into dev_plans
and set @id
select @id
```

## Usage

- `create plan` saves the abstract plan in the group specified with `into`. If no group name is specified, the plan is saved in the currently active plan group.
- Queries and abstract plans specified with `create plan` are not checked for valid SQL syntax, and plans are not checked for valid abstract plan syntax. Also, the plan is not checked for compatibility with the SQL text. You should immediately check all plans created with `create plan` for correctness by running the query specified in the `create plan` statement.
- If another query plan in the group has the same SQL text, `replace` mode must be enabled with `set plan replace on`. Otherwise, the `create plan` command fails.
- You must declare `<@new_id>` before using it in the `and set` clause.
- The abstract plan group you specify with `into` must already exist.
- The SAP ASE server ignores any literal parameterization you specify when creating an abstract plan if you enable server-wide literal parameterization using the `sp_configure "enable literal autoparam", 1` system procedure.

See also:

- *Performance and Tuning Guide: Optimizer and Abstract Plans*.
- `sp_add_qpgroup`, `sp_configure "enable literal autoparam"`, `sp_find_qpplan`, `sp_help_qpplan`, `sp_set_qpplan` in *Reference Manual: Procedures*

## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

## Permissions

No permission is required to use `create plan`.

## Auditing

This command is not audited.

## Related Information

[set](#) [page 732]

## 1.33 create precomputed result set

Creates precomputed result sets and the policies required to maintain them.

### Syntax

```
create {precomputed result set | materialized view}
  [<owner_name>.]<prs_name> [(<alternative_column_name>
  [[constraint <constraint_name>]
  unique (<column_name>,...)]
  [{immediate | manual} refresh]
  [{populate | nopopulate}]
  [enable | disable]
  [{enable | disable} use in optimization]
  [lock { datarows | datapages | allpages}]
  [on <segment_name>]
  [<partition_clause>]
  as <query_expression>
```

### Syntax for Partitions

Use this syntax for partitions:

```
<partition_clause>::= partition by range (<column_name>[, <column_name>]...)
  ([<partition_name>] values <= ({constant | MAX}
  [, {constant | MAX}] ...)
  [<compression_clause>] [on <segment_name>]
  [, [<partition_name>] values <= ({constant | MAX}
  [, {constant | MAX}] ...)
  [<compression_clause>] [on <segment_name>]]...)
| partition by hash (<column_name>[, <column_name>]...)
  {(<partition_name>
  [<compression_clause>] [on <segment_name>]
  [, <partition_name>
  [<compression_clause>] [on <segment_name>]]...)
  | <number_of_partitions>
  [on (<segment_name>[, <segment_name>] ...)]}
| partition by list (<column_name>)
  ([<partition_name>] values (constant[, constant] ...)
  [<compression_clause>] [on <segment_name>]
  [, [<partition_name>] values (constant[, constant] ...)
  [<compression_clause>] [on <segment_name>]] ...)
| partition by roundrobin
  {(<partition_name> [on <segment_name>]
  [, <partition_name>
  [<compression_clause>] [on <segment_name>]]...)
  | <number_of_partitions>
  [on (<segment_name>[, <segment_name>]...)]}
```

## Parameters

### **precomputed result set | materialized view**

creates a materialized view or precomputed result set.

#### **<prs\_name>**

name of the precomputed result set. A fully qualified **<prs\_name>** cannot include the server or database name.

#### **<alternative\_column\_name>**

indicates the name for the precomputed result set column.

#### **constraint <constraint\_name>**

introduces the name of an integrity constraint, which must conform to the rules for identifiers and be unique in the database.

If you do not specify the name for a unique or primary-key constraint, the SAP ASE server generates a name in the format **<tablename\_colname\_tabindid>**, where **<tabindid>** is a string concatenation of the table ID and index ID.

#### **unique (<column\_name>,...)**

constrains the values in the indicated column or columns so that no two rows have the same value.

#### **{immediate | manual} refresh**

determines the refresh policy:

**immediate** (Default) updates the precomputed result set during the same transaction that updates the base tables.

**manual** Explicitly updates the precomputed result set. When you use the **manual** parameter, updates to the base tables are not reflected in the precomputed result set until you explicitly issue **refresh**. Because **manual** precomputed result sets are not maintained, the SAP ASE server considers them to be stale, even after you issue the **refresh** parameter. Therefore, the query processor selects this data for query rewrite only if the query accepts stale data.

#### **populate | nonpopulate**

specifies whether to populate the precomputed result set after it is created, or create it with only the metadata information, and populate it later:

**populate** `create` command.

**nonpopulate** Result set is not populated as part of the `create` command. If you specify **nonpopulate**, you cannot run the **enable** parameter on the precomputed result set. The SAP ASE server enables the precomputed result set the next time you issue the **refresh** command.

#### **enable | disable**

specifies whether the precomputed result set is available for operations. This option overrides all other precomputed result set options.

**enable** (Default) result set populated as part of the default is available for operations. Only precomputed result sets configured for `enable` are maintained according to their refresh policy.

**disable** Is not available for operations. Disabled precomputed result sets are not considered for maintenance or query rewrites. If a precomputed result set is configured for `disable`, it is not:

- Used for the query rewrite during optimization, whether or not you specify `use in optimization`.
- Populated, whether or not you specify `populate`.

#### **{enable | disable} use in optimization**

specifies whether to include a precomputed result set for query rewrite during optimization. The `use in optimization` option is enabled by default. Precomputed result sets are considered for query rewrite depending on how their `refresh` parameter is set:

- `immediate` – considered for all queries.
- `manual` – considered only if the query accepts with stale data.

#### **lock {datarows | datapages | allpages}**

indicates the level of locking the precomputed result set uses.

#### **ON <segment\_name>**

when used with the `constraint` option, specifies that the index is to be created on the named segment. Before the `on <segment_name>` option can be used, the device must be initialized with `disk init`, and the segment must be added to the database with `sp_addsegment`. See your system administrator or use `sp_helpsegment` for a list of the segment names available in your database.

If you specify `clustered` and use the `on <segment_name>` option, the entire table migrates to the segment you specify, since the leaf level of the index contains the actual data pages.

#### **<partition\_clause> ::=**

- `partition by range` – specifies that records are to be partitioned according to values in the partitioning column or columns. Each partitioning column value is compared with sets of user-supplied upper and lower bounds to determine partition assignment.
- `<column_name>` – when used in the `<partition_clause>`, specifies a partition key column.
- `<partition_name>` – specifies the name of a new partition on which table records are to be stored. Partition names must be unique within the set of partitions on a table or index. Partition names can be delimited identifiers if `set quoted_identifier` is on. Otherwise, they must be valid identifiers.

If `<partition_name>` is omitted, the SAP ASE server creates a name in the form `<table_name>_<partition_id>`. The SAP ASE server truncates partition names that exceed the allowed maximum length.

- `values <= <constant> | MAX` – specifies the inclusive upper bound of values for a named partition. Specifying a constant value for the highest partition bound imposes an implicit integrity constraint on the table. The keyword `MAX` specifies the maximum value in a given datatype.
- `on <segment_name>` – when used in the `<partition_clause>`, specifies the name of the segment on which to place the partition. When using `on <segment_name>`, the logical device must already have been assigned to the database with `create database` or `alter database`, and the segment must have been created in the database with `sp_addsegment`. See your system administrator or use `sp_helpsegment` for a list of the segment names available in your database.
- `partition by hash` – specifies that records are to be partitioned by a system-supplied hash function. The function computes the hash value of the partition keys that specify the partition to which records are assigned.
- `partition by list` – specifies records are to be partitioned according to literal values specified in the named column. The partition key contains only one column. You can list up to 250 constants as the partition values for each list partition.
- `partition by roundrobin` – specifies records are to be partitioned in a sequential manner. A round-robin-partitioned table has no partitioning key. Neither the user nor the optimizer knows in which partition a particular record resides.

## Examples

### Example 1

Creates the `prs_1` precomputed result set:

```
create precomputed result set prs_1 constraint prs_1_uniq unique(coll)
as select coll, col2 from test_table
```

### Example 2

Creates the `test_table_prs` precomputed result set on `test_table`, with manual refresh policy and lockscheme of `datarows`. Refresh this materialized view to reflect the base table values in a precomputed result set:

```
create materialized view test_table_prs manual refresh lock datarows as
select * from test_table
```

Specifying `lockscheme` creates a materialized view with the given `lockscheme`, in this case `datarows`, rather than the default `lockscheme`.

### Example 3

Creates precomputed result set `prs_1` on `test_table` with a unique constraint on column name `int_1` using the immediate refresh policy:

```
create precomputed result set prs_1 constraint prs1_const1 unique(int_1) as
select * from test_table
```

### Example 4

Creates a precomputed result set `prs_nop_manual` on `test_table` with manual refresh and `nopopulate` policy:

```
create materialized view prs_nop_manual manual refresh nopopulate as
select * from test_table
Warning: Precomputed result set is being created with NOPOPULATE option, so it
will not be ENABLED.
```

The `nopopulate` option prevents the precomputed result set from populating during creation; instead, population occurs only upon executing a manual refresh.

### Example 5

Creates materialized view `prs_enb_op` on `test_table`, specifying a manual refresh and exclude the precomputed result set for query rewrite during optimization:

```
create materialized view prs_enb_op manual refresh disable use in optimization
as select * from test_table
```

### Example 6

Creates precomputed result set `prs1` with `equijoin` of three tables specifying the unique constraint that updates during the same transaction that updates the base tables:

```
create precomputed result set prs1 constraint prs1_pkey unique (t1_int) as
select tbl1.int_1 t1_int, tbl2.char_2, tbl2.float_3, tbl3.int_1 t3_int from
t1 tbl1, t2 tbl2, t3 tbl3
where tbl1.int_1 = tbl2.int_1 and tbl1.int_1 = tbl3.int_1
```

### Example 7

Creates precomputed result set `seg_part_range` with range partition on a column of `test_table`, specifying the default immediate refresh policy on the default segment:

```
create materialized view seg_part_range constraint prs1_constraint1 unique
(int_1) on 'default'
partition by range(int_1)
(p1 values <= (500), p2 values <= (1000), p3 values <= (MAX))
as select * from test_table
```

## Usage

- Set these `set` parameters before you create or alter precomputed result sets:
  - `set ansinull on`
  - `set arithabort on`
  - `set arithignore off`

- `set string_truncation on`
- You cannot include a `like` clause with `create precomputed result sets` or `create materialized view` that includes an `immediate refresh` parameter.
- You must be the explicit owner of the precomputed result set to perform a `manual refresh`. The owner of a precomputed result set created for `manual refresh` has exclusive permissions for access, and these permissions cannot be granted to other users.

## Standards

The `create precomputed result set` command is a Transact-SQL extension and is not covered by the SQL standard.

## Permissions

You must have `create table` and `create view` privileges to create precomputed result sets.

## Auditing

This command is not audited.

## 1.34 create procedure

Creates or replaces a stored procedure or an extended stored procedure (ESP) that can take one or more user-supplied parameters.

The sections that describe this command are:

- [Syntax \[page 233\]](#)
- [Parameters \[page 233\]](#)
- [Examples \[page 236\]](#)
- [Usage \[page 240\]](#)
- [Standards \[page 241\]](#)
- [Permissions \[page 241\]](#)
- [Auditing \[page 242\]](#)

For syntax and usage information about the SQLJ command for creating procedures, see [create procedure \(SQLJ\) \[page 248\]](#).



## Syntax

```
[<owner>].create [or replace] procedure [<procedure_name>[;<number>create [or  
replace]  
[[(@<parameter_name> <datatype> [(<length>) | (<precision>[, <scale>]])]  
[= <default>][output]  
[, @<parameter_name> <datatype> [(<length>) | (<precision>[, <scale>]])]  
[=< default>][output]]...]]]  
[with {recompile | execute as {owner | caller}} ]  
as {<SQL_statements> | external name <dll_name>}
```

## Parameters

### **create**

creates a new procedure.

### **or replace**

if the specified procedure does not exist, a new procedure is created. If the procedure does exist, the procedure definition is changed; existing permissions, auditing options, transaction mode, permission checking mode for dynamic SQL in stored procedures, and replication attributes are preserved.

### **<procedure\_name>**

is the name of the procedure. It must conform to the rules for identifiers and cannot be a variable. Specify the owner's name to create another procedure of the same name owned by a different user in the current database. The default value for **<owner>** is the current user.

If the procedure is being replaced, the name of the procedure remains the same and the object identifier of the procedure in all the respective catalogs remains the same.

### **;<number>**

(optional) is an integer used to group procedures that share the same name so they can be dropped together with a single `drop procedure` statement. Procedures used in the same application are often grouped this way. For example, if the procedures used with the application named `orders` are named `orderproc;1`, `orderproc;2`, and so on, the following statement drops the entire group:

```
drop proc orderproc
```

Once procedures have been grouped, individual procedures within the group cannot be dropped. For example, the following statement is not allowed:

```
drop procedure orderproc;2
```

You cannot group procedures if you are running SAP ASE in the evaluated configuration. The evaluated configuration requires that you disallow procedure grouping so that every stored procedure has a unique object identifier and can be dropped individually. To disallow procedure grouping, a system security officer uses `sp_configure` to reset `allow procedure grouping`. For more information about the evaluated configuration, see the *System Administration Guide*.

If `or replace` is not specified and the procedure exists, SAP ASE raises an error that the procedure has already been created with that group number, and you must create the procedure with a different group number. If `or replace`

#### **<parameter\_name>**

clause is specified, but the group number is not, but the procedure is the name of an argument to the procedure. The value of each parameter is supplied when the procedure is executed. Parameter names are optional in `create procedure` statements — a procedure is not required to take any arguments.

Parameter names must be preceded by the @ sign and conform to the rules for identifiers. A parameter name, including the @ sign, can be a maximum of 30 characters, and larger for identifiers. Parameters are local to the procedure: the same parameter names can be used in other procedures.

If the value of a parameter contains nonalphanumeric characters, it must be enclosed in quotes. This includes object names qualified by a database name or owner name, since they include a period. If the value of a character parameter begins with a numeric character, it also must be enclosed in quotes.

You can change the name and number of parameters when the procedure definition is replaced.

#### **<datatype>[(<length>) | (<precision >[, <scale>])]**

is the datatype of the parameter. See *Reference Manual: Building Blocks > User-Defined Datatypes*. Stored procedure parameters cannot have a datatype of `text`, `unitext`, or `image` or a user-defined datatype whose underlying type is `text`, `unitext`, or `image`.

The `char`, `varchar`, `unichar`, `univarchar`, `nchar`, `nvarchar`, `binary`, and `varbinary` datatypes should include a `<length>` in parentheses. If you omit the length, the SAP ASE server truncates the parameter value to 1 character.

The `float` datatype expects a binary `<precision>` in parentheses. If you omit the precision, the SAP ASE server uses the default precision for your platform.

The `numeric` and `decimal` datatypes expect a `<precision>` and `<scale>`, enclosed in parentheses and separated by a comma. If you omit the precision and scale, the SAP ASE server uses a default precision of 18 and a scale of 0.

You can use `or replace` to change the type, length, precision and scale of the parameters.

#### **<default>**

defines a default value for the procedure's parameter. If a default is defined, a user can execute the procedure without giving a parameter value. The default must be a constant. It can include the wildcard characters (`%`, `_`, `[ ]`, and `[^]`) if the procedure uses the parameter name with the keyword `like` (see the example showing when no parameter supplied).

The default can be NULL. The procedure definition can specify that some action be taken if the parameter value is NULL (see example using NULL parameter).

You can use `or replace` to change the default to NULL for the parameters, or set a different value when the procedure is replaced.

#### **output**

indicates that the parameter is a return parameter. Its value can be returned to the `execute` command that called this procedure. Use return parameters to return information to the calling procedure.

To return a parameter value through several levels of nested procedures, each procedure must include the `output` option with the parameter name, including the `execute` command that calls the highest level procedure.

The `output` keyword can be abbreviated to `out`.

You can use `or replace` to change the return parameter of the procedure.

#### **with recompile**

allows you to recompile individual statements in a procedure. SAP ASE creates a new plan each time the procedure is executed. Use this optional clause when you expect that the execution of a procedure is atypical—that is, when you need a new plan. The `with recompile` clause has no impact on the execution of an extended stored procedure.

If an existing procedure has been created with this option, it can then be changed using the `or replace` clause so that SAP ASE does not create a new plan each time the procedure is executed. If the existing procedure has not been created using `with recompile`, then it can be replaced with the new definition so that the plan is created each time the procedure is executed.

#### **with execute as**

specifies whether to execute the procedure as the owner or the caller. When executed as the owner, all actions in the procedure are checked against the privileges of the procedure owner. When executed as the caller, all actions in the procedure are checked against the privileges of the procedure caller.

An existing procedure's `with execute as` clause can be changed from owner to caller and vice versa. You can also re-create a procedure without the `with execute as` clause using the `or replace` clause.

#### **owner**

checks runtime permissions, executes DDL, and resolves objects names on behalf of the procedure owner. `execute as definer` is also supported as an alternative syntax.

#### **caller**

checks runtime permissions, executes DDL, and resolves objects names on behalf of the procedure caller. `execute as invoker` is also supported as an alternative syntax.

#### **<SQL\_statements>**

specifies the actions the procedure is to take. You can include any number and kind of SQL statements, with the exception of `create view`, `create default`, `create rule`, `create procedure`, `create trigger`, and `use`.

`create procedure` SQL statements often include control-of-flow language, including one or more of the following: `declare`; `if...else`; `while`; `break`; `continue`; `begin...end`; `goto label`; `return`; `waitfor`; `/* <comment> */`. They can also refer to parameters defined for the procedure.

The SQL statements can reference objects in another database, as long as they are properly qualified.

You can change the body of the procedure to contain statements different from those in the existing procedure.

#### **as external name**

creates an extended stored procedure. You cannot use the `<number>` parameter with `as external name`.

Extended stored procedures can also be replaced.

#### **<dll\_name>**

specifies the name of the dynamic link library (DLL) or shared library containing the functions that implement the extended stored procedure. The `<dll_name>` can be specified with no extension or with a platform-specific extension, such as `.dll` on Windows NT or `.so` on Solaris. If you specify the extension, enclose the entire `<dll_name>` in quotation marks.

The name of the dynamic linked library that implements the extended stored procedures can be changed.

When creating system extended stored procedures, you can only specify `sybsyesp.so` for `<dll_name>` if you are the database owner in the `sybsystemprocs` database.

## Examples

### Example of showind

Given a table name, the procedure `showind` displays its name and the names and identification numbers of any indexes on any of its columns:

```
create procedure showind @tablename varchar (30)
as
select sysobjects.name, sysindexes.name, indid
from sysindexes, sysobjects
where sysobjects.name = @tablename
and sysobjects.id = sysindexes.id
```

Here are the acceptable syntax forms for executing `showind`:

```
execute showind titles
```

```
execute showind @tablename = "titles"
```

Or, if this is the first statement in a file or batch:

```
showind titles
```

### Example when no parameter supplied

Displays information about the system tables if the user does not supply a parameter:

```
create procedure
showsysind @table varchar (30) = "sys%"
```

```

as
  select sysobjects.name, sysindexes.name, indid
  from sysindexes, sysobjects
  where sysobjects.name like @table
  and sysobjects.id = sysindexes.id

```

### Example with NULL parameter

Specifies an action to be taken if the parameter is NULL (that is, if the user does not give a parameter):

```

create procedure
showindnew @table varchar (30) = null
as
  if @table is null
    print "Please give a table name"
  else
    select sysobjects.name, sysindexes.name, indid
    from sysindexes, sysobjects
    where sysobjects.name = @table
    and sysobjects.id = sysindexes.id

```

### Example using @result

Multiplies two integer parameters and returns the product in the output parameter, @result:

```

create procedure mathtutor @mult1 int, @mult2 int,
  @result int output
as
select @result = @mult1 * @mult2

```

If the procedure is executed by passing it three integers, the `select` statement performs the multiplication and assigns the values, but does not print the return parameter:

```

mathtutor 5, 6, 32
(return status 0)

```

### Example using execute

Both the procedure and the `execute` statement include `output` with a parameter name so that the procedure can return a value to the caller:

```

declare @guess int
select @guess = 32
exec mathtutor 5, 6, @result = @guess output
(1 row affected)
(return status = 0)

```

Return parameters:

```

@result
-----
      30

```

The output parameter and any subsequent parameters in the `execute` statement, `<@result>`, must be passed as:

```
<@parameter> = <value>
```

- The value of the return parameter is always reported, whether or not its value has changed.
- `@result` does not need to be declared in the calling batch because it is the name of a parameter to be passed to `mathtutor`.

- Although the changed value of `@result` is returned to the caller in the variable assigned in the `execute` statement (in this case, `@guess`), it appears under its own heading (`@result`).

### Example using `@guess`

You can use return parameters in additional SQL statements in the batch or calling procedure. This example shows how to use the value of `@guess` in conditional clauses after the `execute` statement by storing it in another variable name, `@store`, during the procedure call. When return parameters are used in an `execute` statement that is part of a SQL batch, the return values are printed with a heading before subsequent statements in the batch are executed.

```

declare @guess int
declare @store int
select @guess = 32
select @store = @guess
execute mathtutor 5, 6, @result = @guess output
select Your_answer = @store, Right_answer = @guess
if @guess = @store
    print "Right-o"
else
    print "Wrong, wrong, wrong!"
(1 row affected)
(return status = 0)
Return parameters:

@result
-----
          30
Your_answer Right_answer
-----
          32          30
(1 row affected)
Wrong, wrong, wrong!

```

### Example of `xp_echo`

Creates an extended stored procedure named `xp_echo`, which takes an input parameter, `@in`, and echoes it to an output parameter, `@out`. The code for the procedure is in a function named `xp_echo`, which is compiled and linked into a DLL named `sqlsrvdll.dll`:

```

create procedure xp_echo @in varchar (255),
    @out varchar (255) output
as external name "sqlsrvdll.dll"

```

### Example using `execute as caller`

Creates a procedure using the `execute as caller` clause. Jane creates the procedure and Bill requires `execute` permission to run the procedure. Jane owns both `p_emp` and `jane.employee`. Bill requires `select` permission on `jane.employee`. The table `emp_interim` is created and owned by Bill. Bill must have `create table` permission:

```

create procedure p_emp
    with execute as caller as
    select * into emp_interim
    from jane.employee
grant execute on p_emp to bill

```

### Second example using `execute as caller`

Creates a procedure using the `execute as caller` clause with references to an object with an unqualified name. Jane creates the procedure and Bill executes the procedure. The SAP ASE server

searches for a table named `t1` owned by Bill. If `bill.t1` does not exist, the SAP ASE server looks for `dbo.t1`. If the SAP ASE server resolves `t1` to `dbo.t1`, permission to insert into `t1` must have been granted to Bill:

```
create procedure insert p
  with execute as caller as
  insert t1 (c1) values (100)
grant execute on insert p to bill
```

### Third example using execute as caller

Creates a procedure using the `execute as caller` clause that invokes a nested procedure in another database with a fully qualified name. Jane creates the procedure and Bill executes the procedure. The login associated with Bill resolves to user Bill in `otherdb`. The SAP ASE server checks that user Bill in `otherdb` has `execute` permission on `jim.p_child`. If `jim.p_child` has been created with `execute as owner` then `p_child` is executed on behalf of Jim. If `jim.p_child` has been created with `execute as caller` or without the `execute as` clause, then `p_child` is executed on behalf of Bill:

```
create procedure p master
  with execute as caller
  as exec otherdb.jim.p_child
grant execute on p master to bill
```

### Example of execute as owner

Creates a procedure using the `execute as owner` clause. Jane creates the procedure and Bill requires only `execute` permission to run the procedure. The table `emp_interim` is created and owned by Jane. If Jane does not have `create table` permission, the procedure fails:

```
create procedure p_emp
  with execute as owner as
  select * into emp_interim
  from jane.employee
grant execute on p_emp to bill
```

### Second example using execute as owner

Creates a procedure using the `execute as owner` clause with references to an object with an unqualified name. Jane creates the procedure and Bill executes the procedure. The SAP ASE server searches for a table named `t1` owned by Jane. If `jane.t1` does not exist, the SAP ASE server looks for `dbo.t1`. If the SAP ASE server resolves `t1` to `dbo.t1`, permission to insert into `t1` must have been granted to Jane:

```
create procedure insert p
  with execute as owner as
  insert t1 (c1) values (100)
grant execute on insert p to bill
```

### Third example using execute as owner

Creates a procedure using the `execute as owner` clause that invokes a nested procedure in another database with a fully qualified name. Jane creates the procedure and Bill executes the procedure. The login associated with Jane resolves to user Jane in `otherdb`. The SAP ASE server checks that user Jane in `otherdb` has `execute` permission on `jim.p_child`. If `jim.p_child` has been created with `execute as owner` then `p_child` is executed on behalf of Jim. If `jim.p_child` has been created with `execute as caller` or without the `execute as` clause, then `p_child` is executed on behalf of Jane:

```
create procedure p master
  with execute as owner
```

```
as exec otherdb.jim.p_child
grant execute p master to bill
```

### Example based on information about products

Based on a table of information about products, which is defined as:

```
create table Products (
    ProductID int,
    ProductName varchar(30),
    Discontinued varchar(10))
create procedure ProductType
    @product_ID int,
    @type char(10) output
as
declare @prod_name char(20)
select @prod_name = ProductName, @type =
    case @prod_name
        when 'Tee Shirt' then 'Shirt'
        when 'Sweatshirt' then 'Shirt'
        when 'Baseball Cap' then 'Hat'
        when 'Visor' then 'Hat'
        when 'Shorts' then 'Shorts'
        else 'UNKNOWN'
    end
from Products
where ProductID = @product_ID
select object_id("ProductType")
-----
425049519
```

This next command replaces the `ProductType` procedure using the `or replace` clause. The parameters for `Tee Shirt` and `Sweatshirt` are updated, but the object ID of the procedure remains the same.

```
create or replace procedure ProductType
    @product_ID int,
    @type char(10) output
as
declare @prod_name char(20)
select @prod_name = ProductName, @type =
    case @prod_name
        when 'Tee Shirt' then 'T Shirt'
        when 'Sweatshirt' then 'Long Sleeve Shirt'
        when 'Baseball Cap' then 'Hat'
        when 'Visor' then 'Hat'
        when 'Shorts' then 'Shorts'
        else 'UNKNOWN'
    end
from Products
where ProductID = @product_ID
select object_id("ProductType")
-----
425049519
```

## Usage

- To avoid seeing unexpected results due to changes in settings, run `set rowcount 0` as your initial statement before executing `create procedure`. The scope of `set` is limited to the `create procedure` command, and resets to your previous setting once the procedure exits.



- After a procedure is created, you can run it by issuing the `execute` command along with the procedure's name and any parameters. If a procedure is the first statement in a batch, you can give its name without the keyword `execute`.
- You can use `sp_hidetext` to hide the source text for a procedure, which is stored in `syscomments`.
- When a stored procedure batch executes successfully, the SAP ASE server sets the `@@error` global variable to 0.
- A procedure that calls a replaced procedure is recompiled when it executes. If replacing the procedure changed the number or type of parameters, the calling procedure must be replaced. You can run `sp_depends` on the replaced procedure to verify whether there are calling procedures that are affected by the changed definition.
- You cannot use the `setuser` command:
  - When you create a new procedure using the `with execute as owner` option.
  - With an existing stored procedure, or a stored procedure that was upgraded from an earlier version of SAP ASE, that includes `with execute as owner`.

## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

## Permissions

When you create a procedure, no permission checks are made on objects, such as tables and views, that are referenced by the procedure. Therefore, you can create a procedure successfully even though you do not have access to its objects. All permission checks occur when a user executes the procedure.

The creation of system extended stored procedures (ESPs) can only be performed by the DBO in `sybtempprocs`.

When the procedure is executed, permission checks on objects depend upon whether the procedure and all referenced objects are owned by the same user.

- If the procedure's objects are owned by different users, the invoker must have been granted direct access to the objects. For example, if the procedure performs a select from a table that the user cannot access, the procedure execution fails.
- If a procedure and its objects are owned by the same user, special rules apply. The invoker automatically has "implicit permission" to access the procedure's objects even though the invoker could not access them directly. Without having to grant users direct access to your tables and views, you can give them restricted access with a stored procedure. In this way, a stored procedure can be a security mechanism. For example, invokers of the procedure might be able to access only certain rows and columns of your table. See *Using Stored Procedures as Security Mechanisms* in the *Security Administration Guide*.

The following describes permission checks for `create procedure` that differ based on your granular permissions settings.

**Setting**    **Description**

**Enabled**    When granular permissions is enabled, you must have the `create procedure` privilege to create a procedure. To create a procedure for another user, you must have the `create any procedure` privilege.

To replace a procedure, you must be the procedure owner. Any user who impersonates the procedure owner through an alias or `setuser` cannot replace the procedure. To replace the object, you must be the object owner. Any user who impersonates the object owner through an alias or `setuser` cannot replace the object.

**Disabled**    With granular permissions disabled, you must be the database owner, a user with `sa_role`, or have the `create procedure` privilege to create a procedure. To create a procedure for another user, you must have `sa_role`.

To replace a procedure, you must be the procedure owner, or have `sa_role`. Any user who impersonates the procedure owner through an alias or `setuser` cannot replace the procedure unless the user has `sa_role`. To replace the object, you must be the object owner, or have `sa_role`. Any user who impersonates the object owner through an alias or `setuser` cannot replace the object unless the user has `sa_role`.

**Setting**    **Description**

**Enabled**    The following describes permission checks for creating an extended stored procedure (ESP)When granular permissions is enabled, you must have the `manage any esp` privilege to create an extended stored procedure, including when you create an extended stored procedure for another user.

To replace an extended stored procedure, you must be the procedure owner. Any user who impersonates the procedure owner through an alias or `setuser` cannot replace the procedure.

**Disabled**    With granular permissions disabled, you must have `sa_role`. To create an extended stored procedure for another user, you must also have `sa_role`.

To replace an extended stored procedure, you must be the procedure owner, or have `sa_role`. Any user who impersonates the procedure owner through an alias or `setuser` cannot replace the procedure unless the user has `sa_role`.

## Auditing

You can enable `create` auditing option to audit this command. Values in `event` and `extrainfo` columns from the `sysaudits` table are:

Information	Values
Audit option	<code>create</code>
Event	11

Information	Values
Command or access audited	<code>create procedure</code>
Information in <code>extrainfo</code>	<ul style="list-style-type: none"> <li>• <b>Roles</b> – current active roles</li> <li>• <b>Full command text</b> – full text of <code>create procedure</code> command</li> <li>• <b>Previous value</b> – NULL</li> <li>• <b>Current value</b> – NULL</li> <li>• <b>Other information</b> – NULL</li> <li>• <b>Proxy information</b> – original login name, if <code>set proxy</code> is in effect</li> </ul>

Full command text is included in `extrainfo`. For example:

```
sa_role sso_role oper_role sybase_ts_role mon_role;
create proc testproc1 @p1 varchar(20) with recompile
as select coll from testtbl; ; ; ; sa/ase;
```

For more information about auditing, see *Security Administration Guide > Auditing*.

## 1.34.1 create procedure Restrictions

Restrictions for `create procedure`.

- The maximum number of parameters that a stored procedure can have is 2048.
- The maximum number of local and global variables in a procedure is limited only by available memory.
- The maximum amount of text in a stored procedure is 16MB.
- You cannot combine a `create procedure` statement with other statements in a single batch.
- You can create a stored procedure only in the current database, although the procedure can reference objects from other databases. Most objects referenced in a procedure must exist at the time you create the procedure. However, you can include statements like `drop table`, `create index`, or `truncate table`. These are allowed in a `create procedure` statement even if the underlying object does not exist when you create the procedure.  
You can create an object within a procedure, then reference it, provided the object is created before it is referenced.  
You cannot use `alter table` in a procedure to add a column and then refer to that column within the procedure.
- If you use `select *` in your `create procedure` statement, the procedure (even if you use the `with recompile` option to `execute`) does not pick up any new columns you may have added to the table. You must `drop` the procedure and re-create it. Otherwise, the wrong results can be caused by the `insert...select` statement of `insert into table1 select * from table2` in the procedure when new columns have been added to both tables.
- Within a stored procedure, you cannot create an object (including a temporary table), drop it, then create a new object with the same name. The SAP ASE server creates the objects defined in a stored procedure when the procedure is executed, not when it is compiled.

### ⚠ Caution

Certain changes to databases, such as dropping and re-creating indexes, can cause object IDs to change. When object IDs change, stored procedures recompile automatically, and can increase slightly in size. Leave some space for this increase.

## 1.34.2 `execute as` Stored Procedure

You cannot use the `set session authorization` statement inside an `execute as owner` stored procedure even if the statement is embedded in nested procedure defined with or without the `execute as` clause.

The `execute as` clause is not supported for SQLJ procedures.

Plans in the procedure cache for the same procedure created with `execute as caller` are not shared across users as the objects in the procedure must be resolved to the user executing the procedure. Because of this, procedure cache usage may increase if many users are executing the procedure. The plan for a particular user is reused when the user executes the procedure again.

For information about the `execute as` stored procedure, see *Managing User Permissions* in the *Security Administration Guide*.

## 1.34.3 System Procedures

System administrators can create new system procedures in the `sybssystemprocs` database.

System procedure names must begin with the characters “`sp_`”. You can execute these procedures from any database by specifying the procedure name; you need not qualify it with the `sybssystemprocs` database name. For more information about creating system procedures, see the *System Administration Guide*.

System procedure results may vary, depending on the context in which they are executed. For example, `sp_foo`, which executes the `db_name ()` system function, returns the name of the database from which it is executed. When executed from the `pubs2` database, it returns the value “`pubs2`”:

```
use pubs2
sp_foo
```

```
-----
pubs2
```

When executed from `sybssystemprocs`, it returns the value “`sybssystemprocs`”:

```
use sybssystemprocs
sp_foo
```

```
-----
sybssystemprocs
```

## 1.34.4 Nested Procedures

Procedure nesting occurs when one stored procedure calls another.

- If you execute a procedure that calls another procedure, the called procedure can access objects created by the calling procedure.
- The nesting level increments when the called procedure begins execution, and decrements when the called procedure completes execution. Exceeding the maximum of 16 levels of nesting causes the transaction to fail.
- You can call another procedure by name or by a variable name in place of the actual procedure name.
- The current nesting level is stored in the @@<nestlevel> global variable.
- `execute as` procedures can be nested with the nested procedures being created with or without the `execute as` clause

## 1.34.5 Procedure Return Status

Stored procedures can return an integer value called a return status. The return status either indicates that the procedure executed successfully or specifies the type of error that occurred.

When you execute a stored procedure, it automatically returns the appropriate status code. The SAP ASE server currently returns these status codes:

Code	Meaning
0	Procedure executed without error
-1	Missing object
-2	Datatype error
-3	Process was chosen as deadlock victim
-4	Permission error
-5	Syntax error
-6	Miscellaneous user error
-7	Resource error, such as out of space
-8	Nonfatal internal problem
-9	System limit was reached
-10	Fatal internal inconsistency
-11	Fatal internal inconsistency
-12	Table or index is corrupt

Code	Meaning
-13	Database is corrupt
-14	Hardware error

Codes -15 through -99 are reserved for future use.

Users can generate a user-defined return status with the `return` statement. The status can be any integer other than 0 through -99. The following example returns 1 when a book has a valid contract and 2 in all other cases:

```
create proc checkcontract @titleid tid
as
if (select contract from titles where
    title_id = @titleid) = 1
    return 1
else
    return 2
```

```
checkcontract @titleid = "BU1111"
```

```
(return status = 1)
```

```
checkcontract @titleid = "MC3026"
```

```
(return status = 2)
```

If more than one error occurs during execution, the code with the highest absolute value is returned. User-defined return values take precedence over system-defined values.

## 1.34.6 Object Identifiers

Consideration for working with object identifiers.

- To change the name of a stored procedure, use `sp_rename`.
- To change the name of an extended stored procedure, drop the procedure, rename and recompile the supporting function, then re-create the procedure.
- If a procedure references table names, column names, or view names that are not valid identifiers, you must set `quoted_identifier` on before the `create procedure` command and enclose each such name in double quotes. The `quoted_identifier` option does not need to be on when you execute the procedure.
- You can replace the procedure if any of the objects it references have been renamed..
- Inside a stored procedure, object names used with the `create table` and `dbcc` commands must be qualified with the object owner's name if other users are to make use of the stored procedure. For example, user "mary," who owns the table `marytab`, should qualify the name of her table inside a stored procedure (when it is used with these commands) if she wants other users to be able to execute it. This is because the object names are resolved when the procedure is run. When another user tries to execute the procedure,

the SAP ASE server looks for a table called `marytab` owned by the user "mary" and not a table called `marytab` owned by the user executing the stored procedure.

Thus, if `marytab` is not qualified, and user "john" tries to execute the procedure, the SAP ASE server looks for a table called `marytab` owned by the owner of the procedure ("mary," in this case) or by the database owner if the user table does not exist. For example, if the table `mary.marytab` is dropped, the procedure references `dbo.marytab`.

Object names used with other statements (for example, `select` or `insert`) inside a stored procedure need not be qualified because the names are resolved when the procedure is compiled.

## 1.34.7 Temporary Tables and Procedures

You can create a procedure to reference a temporary table if the temporary table is created in the current session. A temporary table created within a procedure is removed when the procedure exits.

System procedures such as `sp_help` work on temporary tables, but only if you use them from `tempdb`.

See the *Transact-SQL Users Guide*.

## 1.34.8 Setting Options in Procedures

You can use the `set` command inside a stored procedure. Most `set` options remain in effect during the execution of the procedure, then revert to their former settings.

However, if you use a `set` option (such as `identity_insert`) which requires the user to be the object owner, a user who is not the object owner cannot execute the stored procedure.

## 1.34.9 Extended Stored Procedures

If you use the `as <external name>` syntax, `create procedure` registers an extended stored procedure (ESP). Extended stored procedures execute procedural language functions rather than Transact-SQL commands.

(Windows) An ESP function should not call a C runtime signal routine. This can cause XP Server to fail, because Open Server™ does not support signal handling on Windows NT.

To support multithreading, ESP functions should use the Open Server `srv_yield` function, which suspends and reschedules the XP Server thread to allow another thread of the same or higher priority to execute.

The DLL search mechanism is platform-dependent. On Windows NT, the sequence of a DLL file name search:

1. The directory from which the application is loaded
2. The current directory
3. The system directory (SYSTEM32)
4. Directories listed in the PATH environment variable

If the DLL is not in the first three directories, set the PATH to include the directory in which it is located.

On UNIX platforms, the search method varies with the particular platform. If it fails to find the DLL or shared library, it searches `$SYBASE/lib`.

Absolute path names are not supported.

## 1.34.10 Objects Dependent on Replaced Procedures

If a replaced procedure is called by another procedure, both procedures are recompiled when called. If the interface of the replaced procedure does not match that in the calling procedure, then the calling procedure must be replaced, otherwise, the calling procedure raises an error. You can execute `sp_depends` on the replaced procedure to check for any calling objects.

## 1.34.11 Getting Information About Procedures

You can get information about the objects referenced by a procedure, display the text of a procedure, or generate a list of ESPs and supporting DLLs.

- For a report on the objects referenced by a procedure, use `sp_depends`.
- To display the text of a `create procedure` statement, which is stored in `syscomments`, use `sp_helptext` with the procedure name as the parameter. You must be using the database where the procedure resides when you use `sp_helptext`. To display the text of a system procedure, execute `sp_helptext` from the `sybsystemprocs` database.
- To see a list of system extended stored procedures and their supporting DLLs, use `sp_helpextendedproc` from the `sybsystemprocs` database.

## 1.35 create procedure (SQLJ)

Creates or replaces a SQLJ stored procedure by adding a SQL wrapper to a Java static method. Accepts user-supplied parameters and return result sets and output parameters.

### i Note

For syntax and usage information about the Transact-SQL command for creating procedures, see `create procedure`.

### Syntax

```
create [or replace] procedure [<owner>.]<sql_procedure_name>  
  ([[in | out | inout] <sql_parameter_name>  
    <sql_datatype> [(<length>)] |
```



```

    (<precision>[, <scale>]])
    [=<default>]
    ...))
[, [in | out | inout] <sql_parameter_name>
    <sql_datatype> [(<length>) |
    (<precision>[, <scale>])]]
    [=<default>]
    ...))
[modifies sql data]
[dynamic result sets <integer>]
[deterministic | not deterministic]
language java
parameter style java
external name '<java_method_name>
    [( [<java_datatype>[, <java_datatype>
    ...]])]'

```

## Parameters

### **create**

creates a new SQLJ procedure.

### **or replace**

if the specified SQLJ procedure does not exist, a new SQLJ procedure is created. If the SQLJ procedure does exist, the definition is changed.

### **<sql\_procedure\_name>**

is the Transact-SQL name of the procedure, which must conform to the rules for identifiers and cannot be a variable. Specify the owner's name to create another procedure of the same name owned by a different user in the current database. The default value for **<owner>** is the current user.

Use **or replace** to change the name and number of parameters.

### **in | out | inout**

specifies the mode of the listed parameter. **in** indicates an input parameter; **out** indicates an output parameter; and **inout** indicates a parameter that is both an input and an output parameter. The default mode is **in**.

Use **or replace** to change the mode of the listed parameter.

### **<sql\_parameter\_name>**

is the name of an argument to the procedure. The value of each input parameter is supplied when the procedure is executed. Parameters are optional; a SQLJ stored procedure need not take arguments.

Parameter names must conform to the rules for identifiers. If the value of a parameter contains nonalphanumeric characters, it must be enclosed in quotes. This includes object names qualified by a database name or owner name, since they include a period. If the value of the parameter begins with a numeric character, it also must be enclosed in quotes.

### **<sql\_datatype> [( <length>) | (<precision> [, <scale>])]**

is the Transact-SQL datatype of the parameter.

`<sql_datatype>` is the SQL procedure signature.

Use `or replace` to change the type, length, precision, and scale of the parameters.

#### **`<default>`**

defines a default value for the procedure's parameter. If a default is defined, you can execute the procedure without a parameter value. The default must be a constant. It can include wildcard characters (`%`, `_`, `[ ]`, and `^`) if the procedure uses the parameter name with the keyword `like`.

The default can be NULL. The procedure definition can specify some action to be taken if the parameter value is NULL.

Use `or replace` to change the default to NULL for the parameters, or set a different value when the procedure is changed.

#### **`modifies sql data`**

indicates that the Java method invokes SQL operations, reads, and modifies SQL data in the database. This is the default and only implementation. It is included for syntactic compatibility with the ANSI standard.

#### **`dynamic result sets <integer>`**

specifies that the Java method can return SQL result sets. `<integer>` specifies the maximum number of result sets the method can return. This value is implementation-defined.

#### **`deterministic | not deterministic`**

this syntax is supported for compatibility with other SQLJ-compliant vendors.

Use `or replace` to change the deterministic value.

#### **`language java`**

specifies that the external routine is written in Java. This is a required clause for SQLJ stored procedures.

#### **`parameter style java`**

specifies that the parameters passed to the external routine at runtime are Java parameters. This is a required clause for SQLJ stored procedures.

#### **`external`**

indicates that `create procedure` defines a SQL name for an external routine written in a programming language other than SQL.

Use `or replace` to change the name of the external routine.

#### **`name`**

specifies the name of the external routine (Java method). The specified name is a character-string literal and must be enclosed in single quotes:

```
'<java_method_name> [< java_datatype>
                    [{, <java_datatype>} ...]'
```

#### **`<java_method_name>`**

specifies the name of the external Java method.

Use `or replace` to change the Java method name.

### <java\_datatype>

specifies a Java datatype that is mappable or result-set mappable. This is the Java method signature.

Use `or replace` to change the Java datatype.

## Examples

### Example 1

Creates the SQLJ procedure `java_multiply`, which multiplies two integers and returns an integer:

```
create procedure java_multiply (param1 integer,
    param2 integer, out result integer)
language java parameter style java
external name 'MathProc.multiply'
```

### Example 2

Returns values that are always larger than 10:

```
create procedure my_max (a int = 10, b int = 10)
language java parameter style java
external name 'java.lang.Math.max'
exec my_max
    (return status = 10)
exec my_max 8
    (return status = 10)
```

See also the examples for Transact-SQL `create procedure`.

### Example 3

Creates a SQLJ procedure named `proc_name`.

```
create procedure sqlj_proc (param int)
    language java
    parameter style java
    external name 'UDFSample.sample(int)'
```

This procedure replaces the previously created SQLJ procedure using the `or replace` clause. Parameter `p2` is added and the external java method is changed but the object ID of the SQLJ procedure remains the same.

```
create or replace procedure sqlj_proc (p1 int, p2 int)
    language java
    parameter style java
    external name 'UDFSample.add(int,int)'
```

## Usage

- The SQLJ `create procedure` syntax differs from the Transact-SQL `create procedure` syntax for compatibility with the SQLJ ANSI standard. The SAP ASE server executes each type of stored procedure in the same way.

- To avoid seeing unexpected results due to changes in settings, run `set rowcount 0` as your initial statement before executing `create procedure`. The scope of `set` is limited to just your `create procedure` command, and resets to your previous setting once the procedure exits.
- You can include a maximum of 31 `in`, `inout`, and `out` parameters in a `create procedure` statement.
- To comply with the ANSI standard, do not precede parameter names with the `@` sign. When executing a SQLJ stored procedure from `isql` or other non-Java client, however, you must precede parameter names with the `@` sign, which preserves the naming order.
- A Transact-SQL procedure that calls a replaced SQLJ procedure is recompiled when it executes. If replacing the SQLJ procedure changed the number or type of parameters, the calling procedure must be replaced. You can run `sp_depends` on the replaced procedure to verify whether there are calling procedures that are affected by the changed definition.

See also `sp_depends`, `sp_help`, `sp_helpjava`, `sp_helpprotect` in *Reference Manual: Procedures*.

## Permissions

When you create a procedure, no permission checks are made on objects, such as tables and views, that are referenced by the procedure. Therefore, you can successfully create a procedure without having access to its objects. All permission checks occur when a user executes the procedure.

When the procedure is executed, permission checks on objects depend upon whether the procedure and all referenced objects are owned by the same user.

- If the procedure's objects are owned by different users, the invoker must have been granted direct access to the objects. For example, if the procedure performs a select from a table that the user cannot access, the procedure execution fails.
- If a procedure and its objects are owned by the same user, special rules apply. The invoker automatically has "implicit permission" to access the procedure's objects even though the invoker could not access them directly. Without having to grant users direct access to your tables and views, you can give them restricted access with a stored procedure. In this way, a stored procedure can be a security mechanism. For example, invokers of the procedure might be able to access only certain rows and columns of your table.

The following describes permission checks for `create procedure` that differ based on your granular permissions settings.

### Setting Description

**Enabled** When granular permissions is enabled, you must have the `create procedure` privilege to create a procedure (SQLJ). To create a procedure for another user, you must have the `create any procedure` privilege.

To replace a procedure, you must be the procedure owner. Any user who impersonates the procedure owner through an alias or `setuser` cannot replace the procedure.

**Disabled** With granular permissions disabled, you must be the database owner, a user with `sa_role`, or have the `create procedure` privilege to create a procedure (SQLJ). To create a procedure for another user, you must have `sa_role`.

Setting	Description
---------	-------------

	To replace a procedure, you must be the procedure owner, or have <code>sa_role</code> . Any user who impersonates the procedure owner through an alias or <code>setuser</code> cannot replace the procedure unless the user has <code>sa_role</code> .
--	--

## Auditing

For information about auditing for `create procedure`, see [create procedure \[page 232\]](#).

For more information about auditing, see *Security Administration Guide > Auditing*.

## Related Information

[drop procedure \[page 448\]](#)

## 1.36 create proxy\_table

(Component Integration Services only) Creates a proxy table without specifying a column list. CIS derives the column list from the metadata it obtains from the remote table.

## Syntax

```
create proxy_table <table_name>
    [external [table | directory | file]]
    at <pathname>
```

## Parameters

### <table\_name>

specifies the local proxy table name to be used by subsequent statements. `<table_name>` takes the form `<dbname.owner.object>`, where `<dbname>` and `<owner>` are optional and represent the local database and owner name. If `<dbname>` is not specified, the table is created in the current database; if `<owner>` is not specified, the table is owned by the current user. If either `<dbname>` or `<owner>` is specified, enclose the entire `<table_name>` in quotes. If only `<dbname>` is present, a placeholder is required for `<owner>`.

### **external table**

specifies that the object is a remote table or view. `external table` is the default, so this clause is optional.

### **external directory**

specifies that the object is a directory with a path in the format `/tmp/directory_name [;R]`, where `R` indicates "recursive."

### **external file**

specifies that the object is a file with a path in the format `/tmp/filename`.

### **at <pathname>**

specifies the location of the remote object. `<pathname>` takes the form `<server_name.dbname.owner.object>`, where:

- <server\_name>** The name of the server that contains the remote object.
- <dbname>** (Optional) the name of the database managed by the remote server that contains this object.
- <owner>** (Optional) the name of the remote server user that owns the remote object.
- <object>** The name of the remote table or view.

## **Examples**

### **Example 1**

Creates a proxy table named `t1` that is mapped to the remote table `t1`. CIS derives the column list from the remote table:

```
create proxy_table t1
    at "SERVER_A.db1.joe.t1"
```

## **Usage**

- `create proxy_table` is a variant of the `create existing table` command. You use `create proxy_table` to create a proxy table, but (unlike `create existing table`) you do not specify a column list. CIS derives the column list from the metadata it obtains from the remote table.
- Column defaults and rules are not imported by `create proxy_table`; use `create existing table` instead, where column properties can be defined.
- The location information provided by the `at` keyword is the same information that is provided by `sp_addobjectdef`. The information is stored in the `sysattributes` table.
- If the remote server object does not exist, the command is rejected with an error message.
- If the object exists, the local system tables are updated. Every column is used. Columns and their attributes are obtained for the table or view.

- CIS automatically converts the datatype of the column into an SAP ASE datatype. If the conversion cannot be made, the `create proxy_table` command does not allow the table to be defined.
- Index information from the remote server table is extracted and used to create rows for the system table `sysindexes`. This defines indexes and keys in SAP ASE terms and enables the query optimizer to consider any indexes that may exist on the table.
- After defining the proxy table, issue an `update statistics` command for the table. This allows the query optimizer to make intelligent choices regarding join order.
- When executing `create proxy_table <table_name> at <pathname>`, the table and column names assumes the same case as `<table_name>`, if the server identified by `<pathname>` is case-insensitive (such as DB2 and Oracle).  
The columns returned by a case-insensitive server (typically in uppercase), is stored in SAP ASE as lowercase, if `<table_name>` is lowercase. If `<table_name>` is uppercase, then the column names is stored as uppercase values. If `<table_name>` is in mixed case, all column names are stored as received from the remote site.
- `create proxy_table` is not supported with temporary tables.
- You cannot combine `create proxy_table` statement with other statements in a single batch.
- A proxy table stores only metadata. As such, the only space used is the result of making entries in system catalogs. It is estimated that a hundred proxy tables consume about 1MB of space, assuming an average of two indexes per table.
- SQL user-defined functions are not currently supported with `create proxy table`, `create table at <remote server>`, or `alter table`.

### Note

The execution of SQL functions requires the syntax `<username.function_name>`.

- If the remote SAP ASE table has one or more encrypted columns, CIS updates the proxy table's metadata in `syscolumns` to reflect the column's encryption properties and its key ID.
- You cannot issue `create proxy table` on an IMRS-enabled database if the remote, target SAP ASE table is a row caching-enabled table. You can, however, issue `create proxy table` on an IMRS-enabled database if the remote, target SAP ASE table is not a row caching-enabled table

## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

## Permissions

`create proxy_table` permission defaults to the table owner and is not transferable.

## Auditing

You can enable `create` auditing option to audit this command. Values in `event` and `extrainfo` columns from the `sysaudits` table are:

Information	Value
Audit option	<code>create</code>
Event	10
Command or access audited	<code>create proxy_table</code>
Information in <code>extrainfo</code>	<ul style="list-style-type: none"><li>• <b>Roles</b> – current active roles</li><li>• <b>Full command text</b> – full text of <code>create table</code> command</li><li>• <b>Previous value</b> – NULL</li><li>• <b>Current value</b> – NULL</li><li>• <b>Other information</b> – NULL</li><li>• <b>Proxy information</b> – original login name, if <code>set proxy</code> is in effect</li></ul>

Full command text is included in `extrainfo` column. For example:

```
sa_role sso_role oper_role sybase_ts_role mon_role;  
create proxy_table t1 at "SERVER_A.db1.joe.t1"; ; ; ; sa/  
ase;
```

For more information about auditing, see *Security Administration Guide > Auditing*.

## Related Information

[create existing table \[page 170\]](#)

[create table \[page 273\]](#)

[update statistics \[page 839\]](#)



## 1.37 create role

Creates a user-defined role; specifies the password expiration interval, the minimum password length, and the maximum number of failed logins allowed for a specified role at creation. You can also associate a password with the role at the time that the role is created.

### Syntax

```
create role <role_name> [with passwd "<password>"
    [, {passwd expiration <expiration_interval>
    | min passwd length <length_value>|
    max failed_logins <login_attempts>}]
```

### Parameters

#### <role\_name>

is the name of the new role, which must be unique to the server and conform to the rules for identifiers. <role\_name> cannot be a variable.

#### with passwd "<password>"

attaches a password the user must enter to activate the role.

<password> is the password to attach to the role. Passwords must be at least 6 characters in length and must conform to the rules for identifiers. You cannot use variables for passwords.

#### passwd expiration <expiration\_interval>

specifies the password expiration interval in days. It can be any value between 0 and 32767, inclusive. For example, if you create a new login on August 1, 2007 at 10:30 a.m., with a password expiration interval of 30 days, the password expires on August 31, 2007 at 10:30 a.m.

#### min passwd length <length\_value>

specifies the minimum password length required for the specified role.

#### max failed\_logins <login\_attempts>

specifies the number of allowable failed login attempts for the specified login.

## Examples

### Example 1

Creates a role named `doctor_role`:

```
create role doctor_role
```

### Example 2

Creates a role named `doctor_role` with the password "physician":

```
create role doctor_role with passwd "physician"
```

### Example 3

Sets `passwd expiration` to seen days. The password for the role expires at the time of day that the password was last changed after the specified period has passed (in this example, seen days):

```
create role intern_role with passwd "temp244",  
passwd expiration 7
```

### Example 4

Sets the maximum number of failed logins allowed for `intern_role`:

```
create role intern_role with passwd "temp244"  
max failed_logins 20
```

### Example 5

Sets the minimum password length for `intern_role`:

```
create role intern_role with passwd "temp244",  
min passwd length 0
```

## Usage

- Use `create role` from the master database.
- If you attach a password to the role, the user granted this role must specify the password to activate the role.

For information on adding a password to a role after creation, see the `alter role` command.

### Note

Passwords created in versions before 12.x that are attached to user-defined roles do not expire.

- Role names must be unique to the server.
- Role names cannot be the same as user names. You can create a role with the same name as a user, but when you grant privileges, SAP ASE resolves naming conflicts by making the grant to the user instead of the role.

For more information on naming conflicts, see the `grant role` command.

The restrictions for `create role` are:

- The maximum number of roles that can be created per server session is 1024. However, 32 roles are reserved for system roles, such as sa\_role and sso\_role. Also, a special user-defined role, sa\_serverprivs\_role was created by SAP ASE. Therefore, the maximum number of user-defined roles that can be created per server session is 991.
- If you create a role with an attached password, a user cannot activate that role by default at login. Do not create a role with an attached password if the user to whom you grant that role needs to activate the role by default at login.

See also `sp_activeroles`, `sp_displaylogin`, `sp_displayroles`, `sp_helprotect` in *Reference Manual: Procedures*.

## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

## Permissions

The permission checks for `create role` differ based on your granular permissions settings.

Setting	Description
<b>Enabled</b>	With granular permissions enabled, you must be a user with the <code>manage roles</code> privilege.
<b>Disabled</b>	With granular permissions disabled, you must be a user with <code>sso_role</code> .

## Auditing

You can enable the following auditing options to audit this command. Values in `event` and `extrainfo` columns from the `sysaudits` table are:

Audit option	Event	Command or access audited	Information in <code>extrainfo</code> :
<code>create,role,security</code>	85	<code>create role</code>	<ul style="list-style-type: none"> <li>• <b>Roles</b> – current active roles</li> <li>• <b>Full command text</b> – full text of <code>create role</code> command (for <code>create role...with passwd</code>, password is obfuscated)</li> </ul>
<code>password</code>	134	<code>create role...with passwd</code>	<ul style="list-style-type: none"> <li>• <b>Previous value</b> – NULL</li> <li>• <b>Current value</b> – NULL</li> <li>• <b>Other information</b> – NULL</li> <li>• <b>Proxy information</b> – original login name, if <code>set proxy</code> is in effect</li> </ul>

Full command text (with obfuscated password) is included in `extrainfo`. For example:

```
sa_role sso_role oper_role sybase_ts_role mon_role; create role doctor_role
with passwd *****; ; ; ; sa/ase;
```

For more information about auditing, see *Security Administration Guide > Auditing*.

## Related Information

[alter role \[page 65\]](#)

[drop role \[page 450\]](#)

[grant \[page 520\]](#)

[revoke \[page 672\]](#)

[set \[page 732\]](#)

## 1.38 create rule

Specifies the domain of acceptable values for a particular column or for any column of a user-defined datatype, and creates access rules.

### Syntax

```
create [or replace] [{and | or} access]] rule
  [<owner>.]<rule_name>
  as <condition_expression>
```

### Parameters

#### create

creates a rule if one does not already exist.

#### or replace

if the rule already exists, replaces the rule definition with the new definition.

#### access

specifies that you are creating an access rule. An access rule can be changed from an “and” rule to an “or” rule, and vice versa. Access rules cannot be replaced with a domain rule of the same name, and vice versa.

See *Managing User Permissions* in the *System Administration Guide*.

### <rule\_name>

is the name of the new rule, which must conform to the rules for identifiers and cannot be a variable. Specify the owner's name to create another rule of the same name owned by a different user in the current database. The default value for <owner> is the current user.

If the specified rule name already exists, it is replaced with the new rule definition, but the name is preserved.

### <condition\_expression>

specifies the conditions that define the rule. It can be any expression that is valid in a where clause, and can include arithmetic operators, relational operators, `in`, `like`, `between`, and so on. However, <condition\_expression> cannot reference a column or any other database object. Built-in functions that do not reference database objects can be included.

A <condition\_expression> takes one argument, which must be prefixed by the @ sign and refers to the value that is entered via the `update` or `insert` command. You can use any name or symbol to represent the value when you write the rule. Enclose character and date constants in quotes, and precede binary constants with "0x".

You can change the definition of the rule when the rule is replaced. The new rule value overrides the old rule value.

## Examples

### Example 1

Creates a rule named `limit`, which limits the value of `advance` to less than \$1000:

```
create rule limit
as @advance < $1000
```

### Example 2

Creates a rule named `pubid_rule`, which restricts the values of `pub_id` to 1389, 0736, or 0877:

```
create rule pubid_rule
as @pub_id in ('1389', '0736', '0877')
```

### Example 3

Creates a rule named `picture`, which restricts the value of `value` to always begin with the indicated characters:

```
create rule picture
as @value like '_-%[0-9]'
```

### Example 4

Creates a rule named `limit`, which limits the value of `advance` to \$1000:

```
create rule limit
as @advance < $1000
select object_id("limit")
```

```
-----  
1017051628
```

This next command replaces the created rule. The limit is changed using the `or replace` clause. The object ID of the rule remains the same.

```
create or replace rule limit  
as @advance < $2000  
select object_id("limit")  
-----  
1017051628
```

### Example 5

The table owner creates an AND access rule called `uname_acc_rule`:

```
create access rule uname_acc_rule  
as @username = suser_name()  
select object_id("uname_acc_rule")  
-----  
1033051685
```

Replace `uname_acc_rule` with an OR access rule:

```
create or replace or access rule uname_acc_rule  
as @username = suser_name()  
select object_id("uname_acc_rule")  
-----  
1033051685
```

## Usage

- To hide the text of a rule, use `sp_hidetext`.
- To rename a rule, use `sp_rename`.

Objects that are dependent on replaced rules:

- Columns from many tables can be bound to the replaced rules.
- User defined datatypes can be bound to the replaced rules.

Procedures that access these columns will be recompiled when the rule is replaced and the procedure is executed.

See also `sp_bindrule`, `sp_help`, `sp_helptext`, `sp_hidetext`, `sp_rename`, `sp_unbindrule` in *Reference Manual: Procedures*

## Standards

ANSI SQL – Compliance level: Entry-level compliant.

To create rules using ANSI SQL-compliant syntax, use the `check` clause of the `create table` statement.

## Permissions

The permission checks for `create rule` differ based on your granular permissions settings.

Setting	Description
---------	-------------

- |                 |   |
|-----------------|---|
| <b>Enabled</b>  | With granular permissions enabled, you must have the <code>create rule</code> privilege to create a rule. To create a rule for another user, you must have the <code>create any rule</code> privilege.<br><br>To replace the rule, you must be the rule owner. Any user who impersonates the rule owner through an alias or <code>setuser</code> cannot replace the rule.   |
| <b>Disabled</b> | With granular permissions disabled, you must be the database owner, a user with <code>sa_role</code> , or have the <code>create rule</code> privilege to create a rule. To create a rule for another user, you must have <code>sa_role</code> .<br><br>To replace a rule, you must be the rule owner, or have <code>sa_role</code> . Any user who impersonates the rule owner through an alias or <code>setuser</code> cannot replace the rule unless the user has <code>sa_role</code> . |

## Auditing

You can enable `create` auditing option to audit this command. Values in `event` and `extrainfo` columns from the `sysaudits` table are:

Audit option	Event	Command or access audited	Information in <code>extrainfo</code> :
<code>create</code>	13	<code>create rule</code>	<ul style="list-style-type: none"><li>• <i>Roles</i> – current active roles</li><li>• <i>Full command text</i> – full text of <code>create rule</code> command</li><li>• <i>Previous value</i> – NULL</li><li>• <i>Current value</i> – NULL</li><li>• <i>Other information</i> – NULL</li><li>• <i>Proxy information</i> – original login name, if <code>set proxy</code> is in effect</li></ul>

Full command text is included in `extrainfo`. For example:

```
sa_role sso_role oper_role sybase_ts_role mon_role; create rule limit
as @advance < $1000; ; ; ; sa/ase;
```

For more information about auditing, see *Security Administration Guide > Auditing*.

## Related Information

[alter table \[page 70\]](#)

[create default \[page 158\]](#)

[create table \[page 273\]](#)

[drop rule \[page 453\]](#)

[drop table \[page 457\]](#)

[insert \[page 572\]](#)

[update \[page 819\]](#)

## 1.38.1 create rule Restrictions

Restrictions for `create rule`.

- You can create a rule only in the current database.
- Rules do not apply to the data that already exists in the database at the time the rules are created.
- `create rule` statements cannot be combined with other statements in a single batch.
- You cannot bind a rule to an Adaptive-Server-supplied datatype or to a column of type `text`, `unitext`, `image`, or `timestamp`.
- You must drop a rule before you create a new one of the same name, and you must unbind a rule before you drop it. Use:

```
sp_unbindrule <objname> [, futureonly]
```

## 1.38.2 Binding Rules

Use `sp_bindrule` to bind a rule to a column or user-defined datatype.

- `sp_bindrule <rulename>, <objname> [, futureonly]`
- A rule that is bound to a user-defined datatype is activated when you insert a value into, or update, a column of that type. Rules do not test values inserted into variables of that type.
- The rule must be compatible with the datatype of the column. For example, you cannot use the following as a rule for an exact or approximate numeric column:

```
@value like A%
```

If the rule is not compatible with the column to which it is bound, SAP ASE generates an error message when it tries to insert a value, not when you bind it.

- You can bind a rule to a column or datatype without unbinding an existing rule.
- Rules bound to columns always take precedence over rules bound to user-defined datatypes, regardless of which rule was most recently bound. This table indicates the precedence when binding rules to columns and user-defined datatypes where rules already exist:

New Rule Bound to	Old Rule Bound to User-Defined Datatype	Old Rule Bound to Column
User-defined datatype	New rule replaces old	No change



New Rule Bound to	Old Rule Bound to User-Defined Datatype	Old Rule Bound to Column
Column	New rule replaces old	New rule replaces old

- Rules do not override column definitions. If a rule is bound to a column that allows null values, you can insert NULL into the column, implicitly or explicitly, even though NULL is not included in the text of the rule. For example, if you create a rule specifying “@val in (1,2,3)” or “@amount > 10000”, and bind this rule to a table column that allows null values, you can still insert NULL into that column. The column definition overrides the rule.
- If a column has both a default and a rule associated with it, the default must fall within the domain defined by the rule. A default that conflicts with a rule is never inserted. The SAP ASE server generates an error message each time it attempts to insert the default.
- You can define rules using `check` with the `create table` statement, which creates integrity constraints. However, these constraints are specific for that table; you cannot bind them to other tables. See `create table` and `alter table` for information about integrity constraints.
- To get a report on a rule, use `sp_help`.
- To display the text of a rule, which is stored in the `syscomments` system table, execute `sp_helptext` with the rule name as the parameter.
- After a rule is bound to a particular column or user-defined datatype, its ID is stored in the `syscolumns` or `systypes` system tables.

## 1.39 create schema

Creates a new collection of tables, views, and permissions for a database user.

### i Note

The `create schema` command, which allows you to create two types of objects (tables and views) and grant permission on them for a particular user, differs from the SAP HANA `CREATE SCHEMA` command, which creates a schema object in SQLScript databases.

## Syntax

```
create schema authorization <authorization_name>
  <create_object_statement>
  [<create_object_statement> ...]
  [<permission_statement> ...]
```

## Parameters

<authorization\_name>

is the name of the current user in the database.

#### <create\_object\_statement>

is a `create table` or `create view` statement.

#### <permission\_statement>

is a `grant` or `revoke` command.

## Examples

### Example 1

Creates the `newtitles`, `newauthors`, `newtitleauthors` tables, the `tit_auth_view` view, and the corresponding permissions:

```
create schema authorization pogo
  create table newtitles (
    title_id tid not null,
    title varchar (30) not null)
```

```
create table newauthors (
  au_id id not null,
  au_lname varchar (40) not null,
  au_fname varchar (20) not null)
```

```
create view tit_auth_view
  as
  select au_lname, au_fname
    from newtitles, newauthors,
         newtitleauthors
  where
    newtitleauthors.au_id = newauthors.au_id
  and
    newtitleauthors.title_id =
      newtitles.title_id
```

```
grant select on tit_auth_view to public
revoke select on tit_auth_view from churchy
```

## Usage

- Schemas can be created only in the current database.
- The <authorization\_name>, also called the schema authorization identifier, must be the name of the current user.
- The user must have the correct command permissions (`create table` and `create view`). If the user creates a view on tables owned by another database user, permissions on the view are checked when a user attempts to access data through the view, not when the view is created.
- The `create schema authorization` command is terminated by:
  - The regular command terminator ("`go`" is the default in `isql`).

- Any statement other than `create table`, `create view`, `grant`, or `revoke`.
- If any of the statements within a `create schema authorization` statement fail, the entire command is rolled back as a unit, and none of the commands take effect.
- `create schema authorization` adds information about tables, views, and permissions to the system tables. Use the appropriate drop command (`drop table` or `drop view`) to drop objects created with `create schema authorization`. You cannot change permissions granted or revoked in a schema with the standard `grant` and `revoke` commands outside the schema creation statement.
- Clusters only – you cannot include a referential integrity constraint that references a column on a local temporary database unless it is from a table on the same local temporary database. `create schema authorization` fails when it attempts to create a reference to a column on a local temporary database from a table in another database.

See also `isql` in the *Utility Guide*.

## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

## Permissions

`create schema authorization` can be executed by any user of a database. The user must have permission to create the objects specified in the schema; that is, `create table` and `create view` permission.

## Auditing

This command is not audited.

## Related Information

[create table \[page 273\]](#)

[drop table \[page 457\]](#)

[drop view \[page 466\]](#)

[grant \[page 520\]](#)

[revoke \[page 672\]](#)

## 1.40 create service

Wraps the supplied SQL statement in a stored procedure with the specified name and parameters.

### Syntax

```
create service <service_name> [secure <security_options>]
  [, userpath <path>][, alias <alias_name>]
  type {xml | raw | soap}
  [[(@<parameter_name> datatype [(length) | (precision [, scale])]
    [= default][output]
  [, @<parameter_name> datatype [(length) | (precision [, scale])]
    [= default][output]]...[.])]
  as <SQL_statements>
```

```
<security_options> ::= (<security_option_item> [<security_option_item>])
```

### Parameters

#### <service\_name>

is the name for the user-defined Web service. This name can be any name that is valid for a stored procedure. When the `drop service` command is invoked with this service name, the corresponding stored procedure is dropped. If you specify the name of an existing service, an exception results.

#### secure <security\_options>

Values for <security\_option\_item> are:

- `clear` – indicates that HTTP is used to access this Web service.
- `ssl` – indicates HTTPS is used to access this Web service.

#### <path>

is a character-string literal specifying the user-defined path to be appended to the URL accessing the Web service. By default, <path> is null.

#### <alias-name>

is a character-string-literal specifying the user-defined Web service alias.

#### <parameter\_name>

is the name of an argument to the user-defined Web service. The value of this parameter is supplied when the Web service is executed. Parameter names must be preceded by the @ sign and conform to the rules for identifiers. These conditions are the same as for the <parameter\_name> parameter of the `create procedure` command.

#### <SQL\_statements>

are the actions the user-defined Web service is to take. Any number and type of SQL statements can be included, with the exception of `create view`, `create default`, `create rule`, `create procedure`, `create trigger`, and `use`.

#### type

- soap** Implies an HTTP `POST` request and must be compliant with all the SOAP rules. The data is returned in SQL/XML format.
- raw** Indicates that the output is to be sent without any alteration or reformatting. This implies an HTTP `GET` request. The invoked stored procedure can specify the exact output.
- xml** Indicates that the result set output is returned in SQL/XML format. This implies an HTTP `GET` request.

#### i Note

For datatype mappings between SAP ASE stored procedures and SOAP user-defined Web services, see the *Web Services Users Guide*.

## Examples

### Example 1

A user-defined Web service, `rawservice`, of type `raw` is created to return the version of the current database. The `create service` command is entered from the `isql` command line for the `pubs2` database:

```
1> use pubs2
2> go
1> create service rawservice type raw as select '<html><h1>' + @@version + '</
h1></html>'
2> go
```

The newly created user-defined Web service is then deployed:

```
1> sp_webservices 'deploy', 'all'
2> go
```

The Web Service Definition Language for the newly created user-defined Web service is at `http://myhost:8181/services/pubs2?wsdl`.

The newly created user-defined Web service is available at the following URL, where `bob` and `bob123` are the user ID and password of the creator of the user-defined Web service:

```
http://myhost:8181/services/pubs2?
method=rawservice&username=bob&password=bob123
```

The output, an SAP ASE version string, appears in an HTML `<h1>` tag in the browser window.

## Example 2

A user-defined Web service, `xmlservice`, of type `xml` is created to return the version of the current database. The `create service` command is entered from the `isql` command line for the `pubs2` database:

```
1> use pubs2
2> go
1> create service xmlservice userpath "testing" type xml as select @@version
2> go
```

The newly created user-defined Web service is then deployed:

```
1> sp_webservices 'deploy', 'xmlservice'
2> go
```

### i Note

For details on the `deploy` option, see `sp_webservices` in *Reference Manual: Procedures*.

The WSDL for user-defined Web service is at:

```
http://myhost:8181/services/pubs2/testing?wsdl
```

You can invoke the user-defined Web service from a browser at the following URL, where `bob` and `bob123` are the user ID and password of the creator of the user-defined Web service:

```
http://myhost:8181/services/pubs2/testing?method=xmlservice&
username=bob&password=bob123
```

The output appears as XML in the browser window.

## Example 3

A user-defined Web service is made available to a SOAP client to execute the stored procedure `sp_who`. One argument is supplied, and the optional `userpath` token is specified:

```
create service sp_who_service userpath
'myservices/args' type soap @loginname varchar(30) as
exec sp_who @loginname
```

The Web service is created as `sp_who_service` in the `pubs2` database and, after being deployed it is accessible at:

```
http://localhost:8181/pubs2/myservices/args/sp_who_service
```

The WSDL for the service is available at:

```
http://localhost:8181/pubs2/myservices/args?wsdl
```

The signature for the Web method, described in the WSDL file, is:

```
DataReturn[] sp_who_service (xsd:string username,
xsd:string password, xsd:string loginname)
```

The new service is invoked by a SOAP client with one parameter, `loginname`, of type `varchar (30)`.

## Usage

Except for the following differences, the resulting stored procedure behaves the same as a stored procedure created with the `create procedure` command, following existing stored procedure rules for execution, replication, `sp_helptext`, and recompilation, and is executable from `isql`:

- The resulting stored procedure can be dropped only with the `drop service` command, not the `drop procedure` command.
- The `syscomments` table is populated with DDL necessary to re-create the `create service` command.
- The specified service name cannot create a stored procedure group.

### i Note

To make a user-defined Web service available through the SAP ASE Web Services engine, you must use the `deploy` option of `sp_webservices`. However, the stored procedure for a user-defined Web service is accessible from `isql`, even if it has not been deployed.

## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

## Permissions

To use a Web service, you must be granted `execute` permission explicitly:

Permissions on Objects at	Description
---------------------------	-------------

<b>Service creation</b>	When you create a Web service, SAP ASE makes no permission checks on objects, such as tables and views, that are referenced by the service. Therefore, you can successfully create a Web service even though you do not have access to its objects. All permission checks occur when a user executes the Web service.
-------------------------	---

<b>Web service execution</b>	When the Web service is executed, permission checks on objects depend on whether the Web service and all referenced objects are owned by the same user. <ul style="list-style-type: none"><li>• If the Web service's objects are owned by different users, the invoker must have been granted direct access to the objects. For example, if the Web service performs a <code>select</code> from a table that the user cannot access, the Web service execution fails.</li><li>• If a Web service and its objects are owned by the same user, however, special rules apply. The invoker automatically has "implicit permission" to access the Web service's objects even though the invoker could not access them directly. Without having to grant users direct access to your tables and views, you can give them restricted access with a stored procedure. In this way, a stored procedure can be a security mechanism. For</li></ul>
------------------------------	--

## Permissions on Objects at Description

example, invokers of the Web service might be able to access only certain rows and columns of your table.  
A detailed description of the rules for implicit permissions is discussed in the *System Administration Guide*.

The following describes permission checks for `create service` that differ based on your granular permissions settings.

### Setting Description

**Enabled** With granular permissions enabled, you must have the `create procedure` privilege. You must have `create any procedure` privilege to use `create service` for other users.

**Disabled** With granular permissions disabled, you must have the `create procedure` privilege, be the database owner, or a user with `sa_role`.

You must be a user with `sa_role` to use `create rule` for other users.

## Auditing

You can enable `create` auditing option to audit this command. Values in `event` and `extrainfo` columns from the `sysaudits` table are:

Information	Value
Audit option	<code>create</code>
Event	11
Command or access audited	<code>create service</code>
Information in <code>extrainfo</code>	<ul style="list-style-type: none"><li>• <b>Roles</b> – current active roles</li><li>• <b>Full command text</b> – full text of <code>create service</code> command</li><li>• <b>Previous value</b> – NULL</li><li>• <b>Current value</b> – NULL</li><li>• <b>Other information</b> – NULL</li><li>• <b>Proxy information</b> – original login name, if <code>set proxy</code> is in effect</li></ul>

Full command text is included in `extrainfo`. For example:

```
sa_role sso_role oper_role sybase_ts_role mon_role; create service s1
type raw as select '<html><h1>' + @@version + '</h1></html>';
; ; ; sa/ase;
```

For more information about auditing, see *Security Administration Guide > Auditing*.



## 1.41 create table

Creates new tables and optional integrity constraints, defines computed columns and table, row, index, and partition compression levels. Defines encrypted columns, decrypt defaults, and partition properties. Removes residual data from deletions.

The sections that describe this command are:

- [Syntax \[page 273\]](#)
- [Syntax\\_for\\_Partitions \[page 274\]](#)
- [Parameters \[page 275\]](#)
- [Examples \[page 285\]](#)
- [Usage \[page 296\]](#)
- [Standards \[page 296\]](#)
- [Permissions \[page 297\]](#)
- [Auditing \[page 297\]](#)

### Syntax

```
create table [[<database>.<owner>].]<table_name> (<column_name> <datatype>
  [default {<constant_expression> | user | null}]
  [{identity | null | not null}]
  [ in row [(<length>)] | off row]
  [[constraint <constraint_name>]
  {unique | primary key}
  [clustered | nonclustered] [asc | desc]
  [with {fillfactor = <pct>,
        max_rows_per_page = <num_rows>,&
        reservepagegap = <num_pages>}
  dml_logging = {full | minimal}
  [deferred_allocation | immediate_allocation]]
  [on <segment_name>]
  | references [[<database>.<owner>].<ref_table>
  [(<ref_column>)]
  [match full]
  | check (<search_condition>)]}]
  [[encrypt [with [<database>.<owner>].<key_name>]
  [decrypt_default <constant_expression> | null]]
  [not compressed]
  [compressed = {<compression_level> | not compressed}]
  [[constraint [[<database>.<owner>].<key_name>]
  {unique | primary key}
  [clustered | nonclustered]
  (<column_name> [asc | desc]
  [{, <column_name> [asc | desc]}...])
  [with {fillfactor = <pct>
        max_rows_per_page = <num_rows>,
        reservepagegap = <num_pages>}}]
  [on <segment_name>]
  | foreign key (<column_name> [{, <column_name>}...])
  references [[<database>.<owner>].<ref_table>
  [(<ref_column> [{, <ref_column>}...])]
  [match full]
  | check (<search_condition>) ...]
  [{, {<next_column> | <next_constraint>}}...]]
  [lock {datarows | datapages | allpages}]
```

```

[with {max_rows_per_page = <num_rows>,
      exp_row_size = <num_bytes>,
      reservepagegap = <num_pages>,
      identity_gap = <value>
      transfer table [on | off],
      dml_logging = {full | minimal},
      compression = {none | page | row},
      erase residual data {on | off}},
      lob_compression = off | <compression_level>,
      index_compression [= {none | page}
      latch_free_index [= {on | off}]
      row_caching {on [ allow [<number> | default] ] | [for [ all |
default ] ] rows ] | off}
      ]}
[on <segment_name>]
[<partition_clause>]
[[external table] at <pathname>]
[for load]
<compression_clause>::=
  with compression = {none | page | row}

```

Syntax for computed columns:

```

create table [[<database>.<owner>].] <table_name>
  (<column_name> {compute | as}
   <computed_column_expression>
   [[materialized] [not compressed]] | [not materialized])

```

Syntax to create a virtually hashed tables:

```

create table [database.[owner].]<table_name>
  . . .
  | {unique | primary key}
  using clustered
  (<column_name> [asc | desc][[, <column_name> [asc | desc]]...])=
  (hash_factor[[, hash_factor]...])
  with max num_hash_values key

```

## Syntax for Partitions

```

<partition_clause>::=
  partition by range (<column_name>[, <column_name>]...)
  ([[<partition_name>] values <= ({{constant | MAX}
  [, {constant | MAX}] ...)
  [<compression_clause>] [on <segment_name>]
  [, [<partition_name>] values <= ({{constant | MAX}
  [, {constant | MAX}] ...)
  [<compression_clause>] [on <segment_name>]]...))
| partition by hash (<column_name>[, <column_name>]...)
  {(<partition_name>
  [<compression_clause>] [on <segment_name>]
  [, <partition_name>
  [<compression_clause>] [on <segment_name>]]...))
| <number_of_partitions>
  [on (<segment_name>[, <segment_name>] ...)]}
| partition by list (<column_name>)
  ([[<partition_name>] values (constant[, constant] ...)
  [<compression_clause>] [on <segment_name>]
  [, [<partition_name>] values (constant[, constant] ...)
  [<compression_clause>] [on <segment_name>]] ...))
| partition by roundrobin
  {(<partition_name> [on <segment_name>]
  [, <partition_name>
  [<compression_clause>] [on <segment_name>]]...))
  | <number_of_partitions>
  [on (<segment_name>[, <segment_name>]...)]}

```

## Parameters

### <table\_name>

is the explicit name of the new table. Specify the database name if the table is in another database, and specify the owner's name if more than one table of that name exists in the database. The default value for <owner> is the current user, and the default value for <database> is the current database.

You cannot use a variable for the table name. The table name must be unique within the database and to the owner. If you have `set quoted_identifier on`, you can use a delimited identifier for the table name. Otherwise, it must conform to the rules for identifiers. For more information about valid table names, see *Identifiers in Reference Manual: Building Blocks*.

You can create a temporary table by preceding the table name with either a pound sign (#) or "tempdb.". See *Tables Beginning with # (Temporary Tables) in Reference Manual: Building Blocks*.

You can create a table in a different database, as long as you are listed in the `sysusers` table and have `create table` permission for that database. For example, you can use either of the following to create a table called `newtable` in the database `otherdb`:

```
create table otherdb..newtable
```

```
create table otherdb.yourname.newtable
```

### <column\_name>

is the name of the column in the table. It must be unique in the table. If you have `set quoted_identifier on`, you can use a delimited identifier for the column. Otherwise, it must conform to the rules for identifiers. For more information about valid column names, see *Expressions, Identifiers, and Wildcard Characters in Reference Manual: Building Blocks*.

### <datatype>

is the datatype of the column. System or user-defined datatypes are acceptable. Certain datatypes expect a length, <n>, in parentheses:

```
<datatype> (<n>)
```

Others expect a precision, <p>, and scale, <s>:

```
<datatype> (<p>,<s>)
```

See *System and User-Defined Datatypes in Reference Manual: Building Blocks* for more information.

If Java is enabled in the database, <datatype> can be the name of a Java class, either a system class or a user-defined class, that has been installed in the database. See *Java in Adaptive Server Enterprise* for more information.

### default

specifies a default value for a column. If you specify a default, and the user does not provide a value for the column when inserting data, the SAP ASE server inserts the

default value. The default can be a constant expression or a built-in, to insert the name of the user who is performing the insert, or `null`, to insert the null value. The SAP ASE server generates a name for the default in the form of `<tablename_colname_objid>`, where `<tablename>` is the first 10 characters of the table name, `<colname>` is the first 5 characters of the column name, and `<objid>` is the object ID number for the default. Defaults declared for columns with the IDENTITY property have no effect on column values.

You can reference global variables in the `default` section of `create table` statements that do not reference database objects. You cannot, however, use global variables in the `check` section of `create table`.

#### **<constant\_expression>**

is a constant expression to use as a default value for the column. It cannot include global variables, the name of any columns, or other database objects, but can include built-in functions that do not reference database objects. This default value must be compatible with the datatype of the column, or the SAP ASE server generates a datatype conversion error when attempting to insert the default.

#### **user | null**

specifies that the SAP ASE server should insert the user name or the null value as the default if the user does not supply a value. For `user`, the datatype of the column must be either `char (30)` or `varchar (30)`. For `null`, the column must allow null values.

#### **identity**

indicates that the column has the IDENTITY property. Each table in a database can have one IDENTITY column with a datatype of:

- Exact `numeric` and a scale of 0; or
- Any of the integer datatypes, including signed or unsigned `bigint`, `int`, `smallint`, or `tinyint`.

IDENTITY columns are not updatable and do not allow nulls.

IDENTITY columns are used to store sequential numbers—such as invoice numbers or employee numbers — that are generated automatically by the SAP ASE server. The value of the IDENTITY column uniquely identifies each row in a table.

#### **null | not null**

specifies SAP ASE server behavior during data insertion if no default exists.

`null` specifies that the SAP ASE server assigns a null value if a user does not provide a value.

`not null` specifies that a user must provide a non-null value if no default exists.

The properties of a bit-type column must always be `not null`.

If you do not specify `null` or `not null`, the SAP ASE server uses `not null` by default. However, you can switch this default using `sp_dboption` to make the default compatible with the SQL standards.

#### **in row**

instructs the SAP ASE server to store data in the LOB column as in-row whenever there is enough space in the data page. The LOB column's data is stored either fully as in-row or fully off-row.

#### **<length>**

(optional) specifies the maximum size at which LOB column data can be stored as in-row. Anything larger than this value is stored off-row, while anything equal to or less than **<length>** is stored as in-row, as long as there is enough space on the page.

When you do not specify **<length>**, the SAP ASE server uses the database-wide setting for in-row length.

#### **off row | in row**

specifies whether a Java-SQL column is stored separate from the row (**off row**) or in storage allocated directly in the row (**in row**).

**off row** provides the default behavior for storing LOB columns off-row. The SAP ASE server assumes this behavior for your new table unless you specify **in row**. If you do not specify the **off row** clause and you set the database-wide in-row length, **create table** creates the LOB column as an in-row LOB column.

The default value is **off row**. See *Java in Adaptive Server Enterprise*.

#### **<size\_in\_bytes>**

specifies the maximum size of the in-row column. An object stored in-row can occupy up to approximately 16K bytes, depending on the page size of the database server and other variables. The default value is 255 bytes.

#### **constraint <constraint\_name>**

introduces the name of an integrity constraint.

**<constraint\_name>** is the name of the constraint. It must conform to the rules for identifiers and be unique in the database. If you do not specify the name for a referential or check constraint, the SAP ASE server generates a name in the form **<tablename\_colname\_objectid>** where:

- **<tablename>** – is the first 10 characters of the table name
- **<colname>** – is the first 5 characters of the column name
- **<objectid>** – is the object ID number for the constraint

If you do not specify the name for a unique or primary key constraint, the SAP ASE server generates a name in the format **<tablename\_colname\_tabindid>**, where **<tabindid>** is a string concatenation of the table ID and index ID.

#### **unique**

constrains the values in the indicated column or columns so that no two rows have the same value. This constraint creates a unique index that can be dropped only if the constraint is dropped using **alter table**.

#### **primary key**

constrains the values in the indicated column or columns so that no two rows have the same value, and so that the value cannot be NULL. This constraint creates a unique index that can be dropped only if the constraint is dropped using **alter table**.

#### **clustered | nonclustered**

specifies that the index created by a `unique` or `primary` key constraint is a clustered or nonclustered index. `clustered` is the default for primary key constraints; `nonclustered` is the default for unique constraints. There can be only one clustered index per table. See `create index` for more information.

#### **asc | desc**

specifies whether the index created for a constraint is to be created in ascending or descending order for each column. The default is ascending order.

#### **fillfactor**

specifies how full the SAP ASE server makes each page when it creates a new index on existing data. The `fillfactor` percentage is relevant only when the index is created. As the data changes, the pages are not maintained at any particular level of fullness.

The default for `fillfactor` is 0; this is used when you do not include `with fillfactor` in the `create index` statement (unless the value has been changed with `sp_configure`). When specifying a `fillfactor`, use a value between 1 and 100.

A `fillfactor` of 0 creates clustered indexes with completely full pages and nonclustered indexes with completely full leaf pages. It leaves a comfortable amount of space within the index B-tree in both the clustered and nonclustered indexes. There is seldom a reason to change the `fillfactor`.

If the `fillfactor` is set to 100, the SAP ASE server creates both clustered and nonclustered indexes with each page 100 percent full. A `fillfactor` of 100 makes sense only for read-only tables—tables to which no data is ever added.

`fillfactor` values smaller than 100 (except 0, which is a special case) cause the SAP ASE server to create new indexes with pages that are not completely full. A `fillfactor` of 10 might be a reasonable choice if you are creating an index on a table that eventually holds a great deal more data, but small `fillfactor` values cause each index (or index and data) to take more storage space.

If CIS is enabled, you cannot use `fillfactor` for remote servers.

#### **⚠ Caution**

Creating a clustered index with a `fillfactor` affects the amount of storage space your data occupies, since the SAP ASE server redistributes the data as it creates the clustered index.

`decrypt_default` allows the sso to specify a value to be returned to users who do not have `decrypt` permissions on the encrypted column. Decrypt default values are substituted for text, image, or unitext columns retrieved through the `select` statement.

#### **max\_rows\_per\_page**

limits the number of rows on data pages and the leaf-level pages of indexes. Unlike `fillfactor`, the `max_rows_per_page` value is maintained when data is inserted or deleted.

If you do not specify a value for `max_rows_per_page`, the SAP ASE server uses a value of 0 when creating the table. Values for tables and clustered indexes are between 0 and 256. The maximum number of rows per page for nonclustered indexes depends on the

size of the index key; the SAP ASE server returns an error message if the specified value is too high.

A `max_rows_per_page` of 0 creates clustered indexes with full data pages and nonclustered indexes with full leaf pages. It leaves a comfortable amount of space within the index B-tree in both clustered and nonclustered indexes.

Using low values for `max_rows_per_page` reduces lock contention on frequently accessed data. However, using low values also causes the SAP ASE server to create new indexes with pages that are not completely full, uses more storage space, and may cause more page splits.

If CIS is enabled, and you create a proxy table, then `max_rows_per_page` is ignored. Proxy tables do not contain any data. If `max_rows_per_page` is used to create a table, and later a proxy table is created to reference that table, then the `max_rows_per_page` limits apply when you `insert` or `delete` through the proxy table.

**`reservepagegap = <num_pages>`**

specifies the ratio of filled pages to empty pages that are to be left during extent I/O allocation operations. For each specified `<num_pages>`, an empty page is left for future expansion of the table. Valid values are 0 – 255. The default value is 0.

**`deferred_allocation`**

defers a table or index's creation until the table is needed. Deferred tables are created at the first `insert`.

**`immediate_allocation`**

Explicitly creates a table when you have enabled `sp_dboption 'deferred table allocation'`.

**`on <segment_name>`**

when used with the `constraint` option, specifies that the index is to be created on the named segment. Before the `on <segment_name>` option can be used, the device must be initialized with `disk init`, and the segment must be added to the database with `sp_addsegment`. See your system administrator or use `sp_helpsegment` for a list of the segment names available in your database.

If you specify `clustered` and use the `on <segment_name>` option, the entire table migrates to the segment you specify, since the leaf level of the index contains the actual data pages.

**`references`**

specifies a column list for a referential integrity constraint. You can specify only one column value for a column constraint. By including this constraint with a table that references another table, any data inserted into the **referencing** table must already exist in the **referenced** table.

To use this constraint, you must have `references` permission on the referenced table. The specified columns in the referenced table must be constrained by a unique index (created by either a `unique` constraint or a `create index` statement). If no columns are specified, there must be a `primary key` constraint on the appropriate columns in the referenced table. Also, the datatypes of the referencing table columns must match the datatype of the referenced table columns.

#### `<ref_table>`

is the name of the table that contains the referenced columns. You can reference tables in another database. Constraints can reference as many as 192 user tables and internally generated worktables.

#### `<ref_column>`

is the name of the column or columns in the referenced table.

#### `match full`

specifies that if all values in the referencing columns of a referencing row are:

- Null – the referential integrity condition is true.
- Non-null values – if there is a referenced row where each corresponding column is equal in the referenced table, then the referential integrity condition is true.

If they are neither, then the referential integrity condition is false when:

- All values are non-null and not equal, or
- Some of the values in the referencing columns of a referencing row are non-null values, while others are null.

#### `check (<search_condition>)`

specifies the `check` constraint on the column values and a `<search_condition>` constraint that the SAP ASE server enforces for all the rows in the table. You can specify `check` constraints as table or column constraints; `create table` allows multiple `check` constraints in a column definition.

Although you can reference global variables in the `default` section of `create table` statements, you cannot use them in the `check` section.

The constraints can include:

- A list of constant expressions introduced with `in`
- A set of conditions introduced with `like`, which may contain wildcard characters

Column and table check constraints can reference any columns in the table.

An expression can include arithmetic operators and functions. The `<search_condition>` cannot contain subqueries, aggregate functions, host variables, or parameters.

#### `encrypt [with <key_name>]`

creates an encrypted column. Specify the database name if the key is in another database. Specify the owner's name if `<key_name>` is not unique to the database. The default value for `<owner>` is the current user, and the default value for `<database>` is the current database.

The table creator must have `select` permission on the key. If you do not supply `<key_name>`, the SAP ASE server looks for a default key in the database.

`<keyname>` identifies a key created using `create encryption key`. The creator of the table must have `select` permission on `<keyname>`. If `<keyname>` is not supplied, the SAP ASE server looks for a default key created using the `as default` clause on `create encryption key` or `alter encryption key`.



See *Encrypting Data* in the *Encrypted Columns Users Guide* for a list of supported datatypes.

**decrypt\_default** <constant\_expression>

specifies that this column returns a default value for users who do not have decrypt permissions, and <constant\_expression> is the constant value the SAP ASE server returns on `select` statements instead of the decrypted value. The value can be NULL on nullable columns only. If the decrypt default value cannot be converted to the column's datatype, the SAP ASE server catches the conversion error only when it executes the query.

**compression** = <compression\_level> | not compressed

indicates if the data in the row is compressed and to what level.

<compression\_level>

Table compression level. The compression levels are:

- 0 – the row is not compressed.
- 1 through 9 – the SAP ASE server uses ZLib compression. Generally, the higher the compression number, the more the SAP ASE server compresses the LOB data, and the greater the ratio between compressed and uncompressed data (that is the greater the amount of space savings, in bytes, for the compressed data versus the size of the uncompressed data).  
However, the amount of compression depends on the LOB content, and the higher the compression level, the more CPU-intensive the process. That is, level 9 provides the highest compression ratio but also the heaviest CPU usage.
- 100 – the SAP ASE server uses FastLZ compression. The compression ratio that uses the least CPU usage; generally used for shorter data.
- 101 – the SAP ASE server uses FastLZ compression. A value of 101 uses slightly more CPU than a value of 100, but uses a better compression ratio than a value of 100.

The compression algorithm ignores rows that do not use LOB data.

**foreign key**

specifies that the listed columns are foreign keys in this table whose target keys are the columns listed in the following *references*:

<next\_column> | clause. The foreign-key syntax is permitted only for table-level constraints, not for column-level constraints.<next\_constraint>

indicates that you can include additional column definitions or table constraints (separated by commas) using the same syntax described for a column definition or table constraint definition.

**lock datarows** | **datapages** | **allpages**

specifies the locking scheme to be used for the table. The default is the server-wide setting for the configuration parameter `lock scheme`.

**exp\_row\_size** = <num\_bytes>

specifies the expected row size; applies only to `datarows` and `datapages` locking schemes, and only to tables with variable-length rows. Valid values are 0, 1, and any value between the minimum and maximum row length for the table. The default value is 0, which means a server-wide setting is applied.

**identity\_gap <value>**

specifies the identity gap for the table. This value overrides the system identity gap setting for this table only.

<value> is the identity gap amount.

**transfer table [on | off]**

marks the table for incremental transfer. The default value of this parameter is `off`.

**dml\_logging = {full | minimal}**

determines the amount of logging for `insert`, `update` and `delete` operations, and for some forms of bulk inserts. One of:

- `full` – the SAP ASE server logs all transactions
- `minimal` – SAP ASE does not log row or page changes

**compression**

indicates the level of compression at the table or the partition level. Specifying the compression level for the partition overrides the compression level for the table. The SAP ASE server compresses individual columns only in partitions that are configured for compression.

- `none` – the data in this table or partition is not compressed. For partitions, `none` clause. The indicates that data in this partition remains uncompressed even if the table compression is altered to `row` or `page` compression.
- `row` – compresses one or more data items in an individual row. The SAP ASE server stores data in a row compressed form only if the compressed form saves space compared to an uncompressed form. Set `row` compression at the partition or table level.
- `page` – when the page fills, existing data rows that are row-compressed are then compressed using page-level compression to create page-level dictionary, index, and character-encoding entries. Set `page` compression at the partition or table level.  
The SAP ASE server compresses data at the page level only after it has compressed data at the row level, so setting the compression-level to `page` implies both `page` and `row` compression.

**erase residual data {on | off}**

Supports the ability to remove residual data from deletions in SAP ASE.

**lob\_compression = off | <compression\_level>**

Determines the compression level for the table. The table has no LOB compression if you select `off`.

**index\_compression [= {NONE | PAGE}]**

indicates the type of compression the index uses. One of:

- `NONE` – indexes on the specified table are not compressed. Indexes that are specifically created with `index_compression = PAGE` are compressed.
- `PAGE` – all indexes on the specified table are compressed. Indexes that are specifically created with `index_compression = NONE` are not compressed.

**latch\_free\_index**

indicates that you are creating a table that uses latch-free indexes. Set to:

- `on` – all indexes on this table use latch-free indexes, except those you create explicitly with `latch_free_index` set to `off`.
- `off` – all indexes on this table use regular indexes, except those you create explicitly with `latch_free_index` set to `on`.

By default, if you do not specify a latch-free b-tree index, SAP ASE creates a regular, latched b-tree index.

#### **row\_caching**

specifies whether the table uses row caching:

- `on` – enables the in-memory row storage cache to store all data rows for inserts, selects, and updates in this table or re-enables row caching after temporarily disabling it with the `row_caching off` parameter. New inserts performed in the row store that are frequently selected or updated rows are migrated from the data pages to the row store. High-volume OLTP applications requiring high performance benefit from enabling row caching for hot tables.
- `allow [<number> | default]` – sets the upper limit for the number of rows that can be brought into the IMRS in a single query.
  - `<number>` – indicates the value for the upper limit for the number of rows. The maximum value for the upper limit is 2147483646.
  - `default` – indicates that you are setting the upper limit for the number of rows to the default value of 100.
- `for [all | default]` – indicates that subsequent queries cache all the accessed rows to the IMRS.
  - `default` – for all subsequent queries, only the rows that are qualified and fulfill the criteria of the ILM rules are moved to the IMRS.
  - `all` – for all subsequent queries, all the accessed rows are moved to the IMRS whether they are qualified or not, or whether they fulfill the criteria of the ILM rules or not.
- `off` – disables row caching for this table, even if it was enabled database-wide. Subsequent inserts, updates, and deletes are performed directly in the data page store. Use `off` when individual tables do not require row caching.

#### **on <segment\_name>**

specifies the name of the segment on which to place the table. When using `on <segment_name>`, the logical device must already have been assigned to the database with `create database` or `alter database`, and the segment must have been created in the database with `sp_addsegment`. See your system administrator or use `sp_helpsegment` for a list of the segment names available in your database.

When used for partitions, specifies the segment on which to place the partition.

#### **external table**

specifies that the object is a remote table or view. `external table` is the default, so specifying this is optional.

#### **for load**

creates a table available only to `bcp in` and `alter table unpartition` operations. You can use `row_count()` on a table you create using `for load`.

**partition by range**

specifies records are to be partitioned according to specified ranges of values in the partitioning column or columns.

**<column\_name>**

when used in the <partition\_clause>, specifies a partition key column.

**<partition\_name>**

specifies the name of a new partition on which table records are stored. Partition names must be unique within the set of partitions on a table or index. Partition names can be delimited identifiers if `set quoted_identifier` is on. Otherwise, they must be valid identifiers.

If <partition\_name> is omitted, the SAP ASE server creates a name in the form <table\_name\_partition\_id>. The SAP ASE server truncates partition names that exceed the allowed maximum length.

**on <segment\_name>**

when used in the <partition\_clause>, specifies the segment on which the partition is to be placed. Before the `on <segment_name>` option can be used, the device must be initialized with `disk init`, and the segment must be added to the database using the `sp_addsegment` system procedure. See your system administrator or use `sp_helpsegment` for a list of the segment names available in your database.

**values <= constant | MAX**

specifies the inclusive upper bound of values for a named partition. Specifying a constant value for the highest partition bound imposes an implicit integrity constraint on the table. The keyword `MAX` specifies the maximum value in a given datatype.

**partition by hash**

specifies records are to be partitioned by a system-supplied hash function. The function computes the hash value of the partition keys that specify the partition to which records are assigned.

**partition by list**

specifies records are to be partitioned according to literal values specified in the named column. Only one column can partition a list-partitioned table. You can specify up to 250 distinct list values for each partition.

**partition by round-robin**

specifies records are to be partitioned in a sequential manner. A round-robin-partitioned table has no partitioning key. Neither the user nor the optimizer knows the partition of a particular record.

**at <pathname>**

specifies the location of the remote object. Using the `at <pathname>` clause results in the creation of a proxy table.

<pathname> takes the form <server\_name.dbname.owner.object;aux1.aux2>, where:

- <server\_name > – (required) is the name of the server that contains the remote object.

- `<dbname>` – (optional) is the name of the database managed by the remote server that contains this object.
- `<owner >` – (optional) is the name of the remote server user that owns the remote object.
- `<object >` – (required) is the name of the remote table or view.
- `<aux1.aux2 >` – (optional) is a string of characters that is passed to the remote server during a `create table` or `create index` command. This string is used only if the server is class `db2`. `aux1` is the DB2 database in which to place the table, and `aux2` is the DB2 tablespace in which to place the table.

#### **{compute | as}**

reserved keywords that you can use interchangeably to indicate that a column is a computed column.

#### **<computed\_column\_expression>**

is any valid T-SQL expression that does not contain columns from other tables, local variables, aggregate functions, or subqueries. It can be one or a combination of column name, constant, function, global variable, or case expression, connected by one or more operators. You cannot cross-reference between computed columns except when virtual computed columns reference materialize computed columns.

#### **materialized | not materialized**

specifies whether or not the computed column is materialized and physically stored in the table. If neither keyword is specified, a computed column by default is `not materialized`, and thus not physically stored in the table.

#### **using clustered**

indicates you are creating a virtually hashed table. The list of columns are treated as key columns for this table.

#### **<column\_name> [asc | desc]**

you cannot use `[asc | desc ]` for the hash region because the rows are placed based on their hash function. If you provide an order for the key columns of virtually hashed tables, it is used only in the overflow clustered region.

#### **<hash\_factor>**

is required for the hash function for virtually hashed tables. For the hash function, a hash factor is required for every key column. These factors are used with key values to generate hash value for a particular row.

#### **with max <num\_hash\_values> key**

the maximum number of hash values that you can use. Defines the upper bound on the output of this hash function.

## Examples

### Example 1

Creates the `foo` table using the `<@@spid>` global variable with the default parameter:

```
create table foo (
```

```

        a      int
    , b      int      default @@spid
)

```

### Example 2

Creates the `titles` table:

```

create table titles (
    title_id      tid      not null
    , title       varchar (80) not null
    , type        char (12)  not null
    , pub_id      char (4)   null
    , price       money      null
    , advance     money      null
    , total_sales int        null
    , notes       varchar (200) null
    , pubdate     datetime   not null
    , contract    bit        not null
)

```

### Example 3

Creates a table `mytable` using `for load`:

```

create table mytable (
    col1      int
    , col2     int
    , col3     (char 50)
)
partitioned by roundrobin 3 for load

```

Unpartition the new table so that it can be available for any user activity:

1. Load the data into `mytable`, using `bcp in`.
2. Unpartition `mytable`.

The table is now available for any user activities.

### Example 4

Creates the `compute` table. The table name and the column names, `max` and `min`, are enclosed in double quotes because they are reserved words. The `total score` column name is enclosed in double quotes because it contains an embedded blank. Before creating this table, you must set `quoted_identifier` on:

```

create table "compute" (
    "max"      int
    , "min"     int
    , "total score" int
)

```

### Example 5

Creates the `sales` table and a clustered index in one step with a unique constraint. (In the `pubs2` database installation script, there are separate `create table` and `create index` statements):

```

create table sales (
    stor_id      char (4)      not null
    , ord_num     varchar (20) not null
    , date        datetime     not null
    , unique clustered (stor_id, ord_num)
)

```

### Example 6

Creates the `salesdetail` table with two referential integrity constraints and one default value. There is a table-level, referential integrity constraint named `salesdet_constr` and a column-level, referential integrity constraint on the `title_id` column without a specified name. Both constraints specify columns that have unique indexes in the referenced tables (`titles` and `sales`). The `default` clause with the `qty` column specifies 0 as its default value:

```
create table salesdetail (
  stor_id char (4) not null
, ord_num varchar (20) not null
, title_id tid not null
  references titles (title_id)
, qty smallint default 0 not null
, discount float not null,
constraint salesdet_constr
foreign key (stor_id, ord_num)
references sales (stor_id, ord_num)
)
```

### Example 7

Creates the table `publishers` with a check constraint on the `pub_id` column. This column-level constraint can be used in place of the `pub_idrule` included in the `pubs2` database:

```
create rule pub_idrule
as @pub_id in ("1389", "0736", "0877", "1622", "1756")
or @pub_id like "99[0-9][0-9]"
```

```
create table publishers (
  pub_id char (4) not null
  check (pub_id in ("1389", "0736", "0877", "1622",
    "1756")
  or pub_id like "99[0-9][0-9]")
, pub_name varchar (40) null
, city varchar (20) null
, state char (2) null
)
```

### Example 8

Specifies the `ord_num` column as the `IDENTITY` column for the `sales_daily` table. The first time you insert a row into the table, the SAP ASE server assigns a value of 1 to the `IDENTITY` column. On each subsequent insert, the value of the column increments by 1:

```
create table sales_daily (
  stor_id char (4) not null
, ord_num numeric (10,0) identity
, ord_amt money null
)
```

### Example 9

Specifies the datapages locking scheme for the `new_titles` table and an expected row size of 200:

```
create table new_titles (
  title_id tid
, title varchar (80) not null
, type char (12)
, pub_id char (4) null
, price money null
, advance money null
)
```

```

, total_sales    int           null
, notes         varchar (200)  null
, pubdate       datetime
, contract      bit
)
lock datapages
with exp_row_size = 200

```

#### Example 10

Specifies the `datarows` locking scheme and sets a `reservepagegap` value of 16 so that extent I/O operations leave 1 blank page for each 15 filled pages:

```

create table new_publishers (
  pub_id      char (4)      not null
, pub_name   varchar (40)   null
, city       varchar (20)   null
, state      char (2)      null
)
lock datarows
with reservepagegap = 16

```

#### Example 11

Creates a table named `big_sales` with minimal logging:

```

create table big_sales (
  storid      char(4)       not null
, ord_num    varchar(20)    not null
, order_date  datetime      not null
)
with dml_logging = minimal

```

#### Example 12

Creates a deferred table named `im_not_here_yet`:

```

create table im_not_here_yet (
  col_1 int,
  col_2 varchar(20)
)
with deferred_allocation

```

#### Example 13

Creates a table named `mytable`, that uses the locking scheme `datarows`, and permits incremental transfer:

```

create table mytable (
  f1 int
, f2 bigint not null
, f3 varchar (255) null
)
lock datarows
with transfer table on

```

#### Example 14

Creates a table named `genre` with row-level compression:

```

create table genre (
  mystery    varchar(50)    not null
, novel      varchar(50)    not null
, psych      varchar(50)    not null
, history    varchar(50)    not null
)

```



```

, art          varchar(50)    not null
, science     varchar(50)    not null
, children    varchar(50)    not null
, cooking     varchar(50)    not null
, gardening   varchar(50)    not null
, poetry      varchar(50)    not null
)
with compression = row

```

### Example 15

Creates a table named `sales` on segments `seg1`, `seg2`, and `seg3`, with compression on `seg1`:

```

create table sales (
  store_id      int      not null
, order_num    int      not null
, date         datetime not null
)
partition by range (date)
( Y2008 values <= ('12/31/2008')
  with compression = page on seg1,
  Y2009 values <= ('12/31/2009') on seg2,
  Y2010 values <= ('12/31/2010') on seg3)

```

### Example 16

Creates the `email` table, which uses a LOB compression level of 5:

```

create table email (
  user_name     char (10)
, mailtxt      text
, photo        image
, reply_mails  text)
with lob_compression = 5

```

### Example 17

Creates a constraint supported by a unique clustered index; the index order is ascending for `stor_id` and descending for `ord_num`:

```

create table sales_south (
  stor_id      char (4)      not null
, ord_num     varchar (20)  not null
, date        datetime      not null
, unique clustered (stor_id asc, ord_num desc)
)

```

### Example 18

Creates a table named `t1` at the remote server `SERVER_A` and creates a proxy table named `t1` that is mapped to the remote table:

```

create table t1 (
  a      int
, b      char (10)
)
at "SERVER_A.db1.joe.t1"

```

### Example 19

Creates a table named `employees`. `name` is of type `varchar`, `home_addr` is a Java-SQL column of type `Address`, and `mailing_addr` is a Java-SQL column of type `Address2Line`. Both `Address` and `Address2Line` are Java classes installed in the database:

```
create table employees (
    name          varchar (30)
    , home_addr   Address
    , mailing_addr Address2Line
)
```

### Example 20

Creates a table named `mytable` with an `identity` column. The identity gap is set to 10, which means ID numbers are allocated in memory in blocks of ten. If the server fails or is shut down with no wait, the maximum gap between the last ID number assigned to a row and the next ID number assigned to a row is 10 numbers:

```
create table mytable (
    IdNum        numeric (12,0)    identity
)
with identity_gap = 10
```

### Example 21

Creates a table `my_publishers`, which is partitioned by list according to values in the `state` column. See the *Transact-SQL Users Guide* for more information about creating table partitions:

```
create table my_publishers (
    pub_id      char (4)          not null
    , pub_name   varchar (40)     null
    , city       varchar (20)     null
    , state      char (2)         null
)
partition by list (state) (
    west values ('CA', 'OR', 'WA') on seg1
    , east values ('NY', 'MA') on seg2
)
```

### Example 22

Creates the table `fictionsales`, which is partitioned by range according to values in the `date` column:

```
create table fictionsales (
    store_id    int              not null
    , order_num int              not null
    , date       datetime        not null
)
partition by range (date) (
    q1 values <= ("3/31/2005") on seg1
    , q2 values <= ("6/30/2005") on seg2
    , q3 values <= ("9/30/2005") on seg3
    , q4 values <= ("12/31/2005") on seg4
)
```

### Example 23

Creates the table `currentpublishers`, which is partitioned by round-robin:

```
create table currentpublishers (
    pub_id      char (4)          not null
    , pub_name   varchar (40)     null
)
```

```

, city      varchar (20)    null
, state     char (2)        null
)
partition by roundrobin 3 on (seg1)

```

#### Example 24

Creates the table `mysalesdetail`, which is partitioned by hash according to values in the `ord_num` column:

```

create table mysalesdetail (
  store_id   char (4)        not null
, ord_num    varchar (20)    not null
, title_id   tid            not null
, qty        smallint       not null
, discount   float          not null
)
partition by hash (ord_num) (
  p1 on seg1
, p2 on seg2
, p3 on seg3
)

```

#### Example 25

Creates a table called `mytitles` with one materialized computed column:

```

create table mytitles (
  title_id   tid            not null
, title      varchar (80)    not null
, type       char (12)       not null
, pub_id     char (4)        null
, price      money          null
, advance    money          null
, total_sales int          null
, notes      varchar (200)   null
, pubdate    datetime       not null
, sum_sales  compute price * total_sales
              materialized
)

```

#### Example 26

Creates an employee table with a nullable encrypted column. The SAP ASE server uses the database default encryption key to encrypt the `ssn` data:

```

create table employee_table (
  ssn        char(15)        null
, encrypt name char(50)
, deptid     int
)

```

#### Example 27

Creates a customer table with an encrypted column for credit card data:

```

create table customer (
  ccard char(16) unique
, encrypt with cc_key
, decrypt_default 'XXXXXXXXXXXXXXXXXX', name char(30)
)

```

The `ccard` column has a unique constraint and uses `cc_key` for encryption. Because of the `decrypt_default` specifier, the SAP ASE server returns the value 'XXXXXXXXXXXXXXXXXX' instead of the actual data when a user without decrypt permission selects the `ccard` column.

### Example 28

Creates a table that specifies `description` as an in-row LOB column 300 bytes long, `notes` as an in-row LOB column without a specified length (inheriting the size of the off-row storage), and the `reviews` column as stored off-row regardless of condition:

```
create table new_titles (
  title_id      tid          not null
, title        varchar (80)  not null
, type         char (12)     null
, price        money         null
, pubdate      datetime     not null
, description   text         in row (300)
, notes        text         in row
, reviews      text         off row
)
```


### Example 29

Creates a virtually hashed table named `orders` on the `pubs2` database on the `order_seg` segment:

```
create table orders (
  id      int
, age     int
, primary key using clustered (id,age) = (10,1) with max 1000 key
)
on order_seg
```

The layout for the data is:

- The `order_seg` segment starts on page ID 51200.
- The ID for the first data object allocation map (OAM) page is 51201.
- The maximum rows per page is 168.
- The row size is 10.
- The root index page of the overflow clustered region is 51217.




### Example 30

Creates a virtually hashed table named `orders` on the `pubs2` database on the `order_seg` segment:

```
create table orders (  
  id    int default NULL  
  , age  int  
  , primary key using  
        clustered (id,age) = (10,1) with max 100 key  
  , name varchar(30)  
)  
on order_seg
```

The layout for the data is:

- The `order_seg` segment starts on page ID 51200.
- The ID for the first data OAM page is 51201.
- The maximum rows per page is 42.
- The row size is 45.
- The root index page of the overflow clustered region is 51217.



### Example 31

The removal of residual data is set at the database level for these two scenarios by using this setting:

```
sp_dboption <dbname>, "erase residual data", true
```

The following scenarios use these two tables:

- `create table t1 (col1 int) with erase residual data on`
- `create table t2 (col1 int) with erase residual data off`

#### i Note

The `sp_dboption` procedure requires quote marks for "erase residual data", but `create table ... with erase residual data on | off` does not. Using quote marks in `create table` causes a syntax error.

### Scenario 1

The option to erase residual data is turned on for table `t1` because it is set at the database level, so that both the `drop table` and `truncate table` commands for `t1` result in the cleanup of all residual data from its pages.

Table `t2`, however, was created with the `erase residual data off` clause, so that residual data is not removed, even though the `sp_dboption` procedure's "erase residual data" option is set to `true` at the database level. As a result, residual data remains, even after running `drop table` and `truncate table` on `t2`:

```
create database db1
go
sp_dboption db1, "erase residual data", true
go
use db1
go
create table t1 (col int)
go
insert t1 values ...
go
create table t2 (col1 int, col2 char(10)) with erase residual data off
go
truncate table t1
go
drop table t1
go
truncate table t2
go
drop table t2
go
```

## Scenario 2

This scenario uses the following:

```
create database db1
go
use db1
go
create table t1 (col int)
go
sp_dboption db1, "erase residual data", true
go
create table t2 (col1 int, col2 char(10))
go
create table t3 (col1 int, col2 char(10)) with "erase residual data" off
go
truncate table t1
go
truncate table t2
go
truncate table t3
go
```

- Table `t1` does not have `erase residual data off` set explicitly, but does have it set at the database level, resulting in the removal of residual data from `t1` when you run `truncate table t1`.
- Table `t2` is set to erase residual data because the option was set at the database level. This results in the removal of residual data from `t2` when you run `truncate table t2`.
- Table `t3` is marked with "erase residual data off" explicitly, so that even though `sp_dboption` sets "erase residual data" to `true`, residual data is not removed when SAP ASE runs `truncate table t3`.

### Scenario 3

In this example:

- Although both t1 and t2 tables had the "erase residual data" option not set by default, because "erase\_residual\_data" was turned on at the session level just before the truncate table command was executed, the residual data is removed on both t1 and t2.
- Although table t3 has the "erase residual data" option explicitly set to off, residual data is still removed when the truncate command is executed, because the "erase\_residual\_data" option is set at the session level.

```
create database db1
go
use db1
go
create table t1(col int)
go
create table t2 (col1 int, col2 char(10))
go
create table t3 (col1 int, col2 char(10)) with "erase residual data" off
go
set erase_residual_data on
go
truncate table t1
go
truncate table t2
go
truncate table t3
go
```

### Example 32

Creates the index compressed table `order_line` with columns `ol_delivery_d` and `ol_dist_info` compressed and using page-level compression:

```
create table order_line (
    ol_o_id      int,
    ol_d_id      tinyint,
    ol_w_id      smallint,
    ol_number    tinyint,
    ol_i_id      int,
    ol_supply_w_id smallint,
    ol_delivery_d datetime,
    ol_quantity  smallint,
    ol_amount    float,
    ol_dist_info char(24) )
lock datapages
with index_compression = page
```

By default, indexes created on this table are compressed by default. However, if an index has an index row length that is too short to benefit from compression, a warning is raised, indicating that the index will not be compressed.

### Example 33

Create the `order_line` table, which specifies that any new indexes are latch-free:

```
create table order_line (
    ol_o_id      int,
    ol_d_id      tinyint,
    ol_w_id      smallint,
    ol_number    tinyint,
    ol_i_id      int,
```

```

    ol_supply_w_id  smallint,
    ol_delivery_d   datetime with compression,
    ol_quantity     smallint,
    ol_amount       float,
    ol_dist_info    char(24)  with compression
) lock datapages
with latch_free_index = on

```

Creates latch-free index on the `ol_dist_info` column:

```
create index idx_char on order_line(ol_dist_info)
```

## Usage

- `create table` creates a table and optional integrity constraints. The table is created in the currently open database unless you specify a different database in the `create table` statement. You can create a table or index in another database, if you are listed in the `sysusers` table and have `create table` permission in the database.
- `create table` allows you to create latch-free indexes only on data-only locked tables.
- Space is allocated to tables and indexes in increments of one extent, or eight pages, at a time. Each time an extent is filled, another extent is allocated. To see the amount of space allocated and used by a table, use `sp_spaceused`.
- The maximum length for in-row Java columns is determined by the maximum size of a variable-length column for the table's schema, locking style, and page size.
- `create table` performs error checking for check constraints before it creates the table.
- When using `create table` from CIS with a column defined as `char (<n>) NULL`, CIS creates the column as `varchar (<n>)` on the remote server.
- Use the `asc` and `desc` keywords after index column names to specify the sort order for the index. Creating indexes so that columns are in the same order specified in the `order by` clause of queries eliminates the sorting step during query processing.
- If an application inserts short rows into a data-only-locked table and updates them later so that their length increases, use `exp_row_size` to reduce the number of times that rows in data-only-locked tables are forwarded to new locations.
- The location information provided by the `at` keyword is the same information that is provided by `sp_addobjectdef`. The information is stored in the `sysattributes` table.
- When you set this option on a table, the operations for the table (`drop table`, `delete row`, `alter table`, `drop index`) that result in residual data automatically clean up deallocated space.

See also `sp_addmessage`, `sp_addsegment`, `sp_addtype`, `sp_bindmsg`, `sp_chgattribute`, `sp_commonkey`, `sp_depends`, `sp_foreignkey`, `sp_help`, `sp_helpjoins`, `sp_helpsegment`, `sp_primarykey`, `sp_rename`, `sp_spaceused` in *Reference Manual: Procedures*.

## Standards

ANSI SQL – Compliance level: Entry-level compliant.



Transact-SQL extensions include:

- Use of a database name to qualify a table or column name
- IDENTITY columns
- The `not null` column default
- The `asc` and `desc` options
- The `reservepagegap` option
- The `lock` clause
- The `on <segment_name>` clause

See *System and User-Defined Datatypes* in *Reference Manual: Building Blocks* for datatype compliance information.

## Permissions

Any user can create temporary tables and new tables with logging disabled.

The following describes permission checks for `create table` that differ based on your granular permissions settings.

Setting	Description
---------	-------------

<b>Enabled</b>	With granular permissions enabled, you must have the <code>create table</code> privilege to create a table. To create a table for another user, you must have the <code>create any table</code> privilege. Requires <code>manage data cache privilege</code> to use the row storage cache for either row caching or snapshot isolation.
----------------	---

<b>Disabled</b>	With granular permissions disabled, you must be the database owner, a user with <code>sa_role</code> , or a user with the <code>create table</code> privilege to create a table. To create a table for another user, you must have <code>sa_role</code> . Requires the <code>sa_role</code> privilege to use the row storage cache for either row caching or snapshot isolation.
-----------------	--

## Auditing

You can enable the following auditing options to audit this command. Values in `event` and `extrainfo` columns from the `sysaudits` table are:

Audit option	Event	Command or access audited	Information in <code>extrainfo</code> :
<code>create</code>	10	<code>create table</code>	<ul style="list-style-type: none"><li>• <i>Roles</i> – current active roles</li><li>• <i>Full command text</i> – full text of <code>create table</code> command</li><li>• <i>Previous value</i> – NULL</li><li>• <i>Current value</i> – NULL</li><li>• <i>Other information</i> – NULL</li></ul>

Audit option	Event	Command or access audited	Information in <code>extrainfo</code> :
reference	91	create table...references	<ul style="list-style-type: none"> <li>• <i>Proxy information</i> – original login name, if set proxy is in effect</li> </ul>

Full command text is included in `extrainfo`. For example:

```
sa_role sso_role oper_role sybase_ts_role mon_role; create table testab_tab9
(coll int) with transfer table off; ; ; ; sa/ase;
```

For more information about auditing, see *Security Administration Guide > Auditing*.

## Related Information

[alter database \[page 14\]](#)  
[alter table \[page 70\]](#)  
[create database \[page 140\]](#)  
[create default \[page 158\]](#)  
[create existing table \[page 170\]](#)  
[create index \[page 192\]](#)  
[create schema \[page 265\]](#)  
[disk init \[page 401\]](#)  
[drop index \[page 439\]](#)  
[drop rule \[page 453\]](#)  
[drop table \[page 457\]](#)  
[execute \[page 506\]](#)  
[grant \[page 520\]](#)  
[if...else \[page 569\]](#)  
[load database \[page 585\]](#)  
[select \[page 696\]](#)  
[while \[page 863\]](#)

### 1.41.1 Restrictions for create table

Restrictions for using `create table`.

- The maximum number of columns in a table depends on the width of the columns and the server's logical page size:
  - The sum of the columns' sizes cannot exceed the server's logical page size.
  - The maximum number of columns per table cannot exceed 1024.
  - The maximum number of variable-length columns for an all-pages lock table is 254.

For example, if your server uses a 2K logical page size and includes a table of integer columns, the maximum number of columns in the table is far fewer than 1024. (1024 \* 4 bytes exceeds a 2K logical page size.)

You can mix variable- and fixed-length columns in a single table as long as the maximum number of columns does not exceed 1024. For example, if your server uses a 8K logical page size, a table configured for APL can have 254 nullable integer columns (these are variable-length columns) and 770 non-nullable integers, for a total of 1024 columns.

- There can be as many as 2,000,000,000 tables per database and 1024 user-defined columns per table. The number of rows per table is limited only by available storage.
- Although the SAP ASE server does create tables in the following circumstances, you receive errors about size limitations when you perform DML operations:
  - If the total row size for rows with variable-length columns exceeds the maximum column size
  - If the length of a single variable-length column exceeds the maximum column size
  - For data-only-locked tables, if the offset of any variable-length column other than the initial column exceeds the limit of 8191 bytes
- The SAP ASE server reports an error if the total size of all fixed-length columns, plus the row overhead, is greater than the table's locking scheme and page size allows. These limits are for APL tables are:

Page Size	Maximum Row Length	Maximum Column Length
2K (2048 bytes)	1962 bytes	1960 bytes
4K (4096 bytes)	4010 bytes	4008 bytes
8K (8192 bytes)	8106 bytes	8104 bytes
16K (16384 bytes)	16298 bytes	16296 bytes

The limits for DOL tables are:

Page Size	Maximum Row Length	Maximum Column Length
2K (2048 bytes)	1964 bytes	1958 bytes
4K (4096 bytes)	4012 bytes	4006 bytes
8K (8192 bytes)	8108 bytes	8102 bytes
16K (16384 bytes)	16300 bytes	16294 bytes If table does not include any variable-length columns
16K (16384 bytes)	16300 (subject to a max start offset of varlen = 8191)	8191-6-2 = 8183 bytes If table includes at least one variable-length column. This size includes six bytes for the row overhead and two bytes for the row length field

- The maximum number of bytes of variable length data per row depends on the locking scheme for the table:

Page Size	Maximum Row Length	Maximum Column Length
2K (2048 bytes)	1962	1960
4K (4096 bytes)	4010	4008
8K (8192 bytes)	8096	8104
16K (16384 bytes)	16298	16296

The maximum size of columns for a DOL table:

Page Size	Maximum Row Length	Maximum Column Length
2K (2048 bytes)	1964	1958
4K (4096 bytes)	4012	4006
8K (8192 bytes)	8108	8102
16K (16384 bytes)	16300	16294

- If you create a DOL table with a variable-length column that exceeds a 8191-byte offset, you cannot add any rows to the column.
- If you create tables with `varchar`, `nvarchar`, `univarchar`, or `varbinary` columns for which total defined width is greater than the maximum allowed row size, a warning message appears, but the table is created. If you try to insert more than the maximum number bytes into such a row, or to `update` a row so that its total row size is greater than the maximum length, the SAP ASE server produces an error message, and the command fails.
- When a `create table` command occurs within an `if...else` block or a `while` loop, the SAP ASE server creates the schema for the table before determining whether the condition is true. This may lead to errors if the table already exists. To avoid this situation, either make sure a view with the same name does not already exist in the database or use an `execute` statement, as follows:

```
if not exists
  (select * from sysobjects where name="my table")
begin
  execute "create table mytable (x int)"
end
```

- You cannot issue `create table` with a declarative default or check constraint and then insert data into the table in the same batch or procedure. Either separate the create and insert statements into two different batches or procedures, or use `execute` to perform the actions separately.
- You cannot use the following variable in `create table` statements that include defaults:

```
declare @p int
select @p = 2
create table t1 (c1 int default @p, c2 int)
```

Doing so results in error message 154: "Variable is not allowed in default."

- Virtually-hashed tables have these restrictions:  
SQL user-defined functions are not currently supported with `create proxy table`, `create table at remote server`, or `alter table`.

### Note

The execution of SQL functions requires the syntax `username.functionname()`.

- - Virtually-hashed tables must have unique rows. Virtually hashed tables do not allow multiple rows with the same key-column values because the SAP ASE server cannot keep one row in the hash region and another with the same key-column value in the overflow clustered region.
  - You must create each virtually-hashed table on an exclusive segment.

## 1.41.2 Creating Compressed Tables

Considerations for creating compressed tables.

- Unless you state otherwise, the SAP ASE server:
  - Sets data compression to NULL when you create a table.
  - Preserves the existing compression level when you modify a table.
  - Sets all partitions to the compression level specified in the `create table` clause.
- You can create a table with table-level compression but leave some partitions uncompressed, which allows you to maintain uncompressed data in an active partitions format, and to periodically compress the data when appropriate.
- The SAP ASE server supports partition-level compression for all forms of partitioning except round-robin partitions.
- Columns marked as `not compressed` are not selected for row or page compression. However, in-row columns (including materialized computed columns) are eligible for compression:
  - All fixed-length data smaller than 4 bytes is ineligible for row compression. However, the SAP ASE server may compress these datatypes during page-index compression.
  - All data, fixed or with a variable length of 4 bytes or larger, is eligible for row compression.
- By default, the SAP ASE server creates uncompressed nonmaterialized computed columns.
- The SAP ASE server first compresses the columns eligible for compression at the row level. If the compressed row is longer than the uncompressed row, the SAP ASE server discards the compressed row and stores the uncompressed row on disk, ensuring that compression does not waste space.
- Data pages may simultaneously contain compressed and uncompressed data rows.
- You may compress fixed-length columns.
- You can use the `with exp_row_size` clause to create compressed data-only-locked (DOL) tables only for fixed-length rows. You cannot use the `with exp_row_size` clause on allpages-locked (APL) tables.
- If you specify an expected row size, but the uncompressed row length is smaller than the expected row size, the SAP ASE server does not compress the row.
- After you enable compression for a table, all `bcp` and DML operations that are executed on the table compress the data.
- Compression may allow you to store more rows on a page, but it does not change the maximum row size of a table. However, it can change the effective minimum row size of a table.

- Use `not compressed` for columns that could be row- or page-index compressed, but for which the nature of the column makes compression inapplicable or meaningless (for example, columns that use the `bit` datatype, encryption, or a timestamp column).
- Compressing a table does not compress its indexes.

### 1.41.3 Restrictions for Compression

Restrictions for using compression.

- You cannot compress:
  - System tables
  - Worktables
  - Nonmaterialized computed columns
  - IDENTITY columns
  - Timestamps added for data transfer
  - All datatypes; see the *Compression Users Guide* for a list of unsupported datatypes
  - Encrypted columns
- You cannot create a table for compression if the minimum row size exceeds the size of the maximum user data row for the configured locking scheme and page size combination. For example, you cannot create a data-only-locked table with a 2K page size that includes column `c1` with a `char(2007)` datatype because it exceeds the maximum user data row size. For row and page compression, the SAP ASE server performs the same row size check as for a new table.
- You cannot create a table for row or page compression that has only short, fixed-length columns smaller than 4 bytes.

### 1.41.4 Using Indexes

A table “follows” its clustered index. If you create a table on one segment, then create its clustered index on another segment, the table migrates to the segment where the index is created.

You can make inserts, updates, and selects faster by creating a table on one segment and its nonclustered indexes on another segment, if the segments are on separate physical devices. See *Using Clustered or Nonclustered Indexes in Transact-SQL Users Guide*.

### 1.41.5 Renaming a Table or Its Columns

Use `sp_rename` to rename a table or column.

After renaming a table or any of its columns, use `sp_depends` to determine which procedures, triggers, and views depend on the table, and redefine these objects.

### ⚠ Caution

If you do not redefine these dependent objects, they no longer work after the SAP ASE server recompiles them.

## 1.41.6 Restrictions on Compressing Tables That Use Large Object (LOB) Data

Restrictions for compressing data on LOB tables.

You cannot:

- Compress computed text columns
- Issue LOB compression clauses (for example, `lob_compression =`) on regular columns, XML data
- Use LOB compression for system and worktables

## 1.41.7 Column Definitions

Considerations for creating a column from a user-defined datatype.

- You cannot change the length, precision, or scale.
- You can use a NULL type to create a NOT NULL column, but not to create an IDENTITY column.
- You can use a NOT NULL type to create a NULL column or an IDENTITY column.
- You can use an IDENTITY type to create a NOT NULL column, but the column inherits the IDENTITY property. You cannot use an IDENTITY type to create a NULL column.

Only columns with variable-length datatypes can store null values. When you create a NULL column with a fixed-length datatype, the SAP ASE server automatically converts it to the corresponding variable-length datatype. The SAP ASE server does not inform the user of the type change.

This table lists the fixed-length datatypes and the variable-length datatypes to which they are converted. Certain variable-length datatypes, such as `moneyn`, are reserved types that cannot be used to create columns, variables, or parameters:

Table 1: Variable-Length Datatypes Used to Store Nulls

Original Fixed-Length Datatype	Converted to
<code>char</code>	<code>varchar</code>
<code>nchar</code>	<code>nvarchar</code>
<code>binary</code>	<code>varbinary</code>
<code>datetime</code>	<code>datetime</code>

Original Fixed-Length Datatype	Converted to
float	floatn
bigint, int, smallint, tinyint	intn
unsigned bigint, unsigned int, unsigned smallint	uintn
decimal	decimaln
numeric	numericn
money and smallmoney	moneyn

For a report on a table and its columns, execute the system procedure `sp_help`.

You can create column defaults in two ways: by declaring the default as a column constraint in the `create table` or `alter table` statement, or by creating the default using the `create default` statement and binding it to a column using `sp_bindefault`.

## 1.41.8 Temporary Tables

Usage information for temporary tables.

- Temporary tables are stored in the temporary database, `tempdb`.
- The first 13 characters of a temporary table name must be unique per session. Such tables can be accessed only by the current SAP ASE server session. They are stored in `tempdb..objects` by their names plus a system-supplied numeric suffix, and they disappear at the end of the current session or when they are explicitly dropped.
- Temporary tables created with the "`tempdb..`" prefix are shareable among SAP ASE server user sessions. Create temporary tables with the "`tempdb..`" prefix from inside a stored procedure only if you intend to share the table among users and sessions. To avoid inadvertent sharing of temporary tables, use the "#" prefix when creating and dropping temporary tables in stored procedures.
- Temporary tables can be used by multiple users during an the SAP ASE server session. However, the specific user session usually cannot be identified because temporary tables are created with the "guest" user ID of 2. If more than one user runs the process that creates the temporary table, each user is a "guest" user, so the `uid` values are all identical. Therefore, there is no way to know which user session in the temporary table is for a specific user. The system administrator can add the user to the temporary table using `create login`, in which case the individual `uid` is available for that user's session in the temporary table.
- You can associate rules, defaults, and indexes with temporary tables, but you cannot create views on temporary tables or associate triggers with them.
- When you create a temporary table, you can use a user-defined datatype only if the type is in `tempdb..systypes`. To add a user-defined datatype to `tempdb` for only the current session, execute `sp_addtype` while using `tempdb`. To add the datatype permanently, execute `sp_addtype` while using `model`, then restart the SAP ASE server so that `model` is copied to `tempdb`.



## 1.41.9 Defining Integrity Constraints

The `create table` statement helps control a database's integrity through a series of integrity constraints as defined by the SQL standards.

- These integrity constraint clauses restrict the data that users can insert into a table. You can also use defaults, rules, indexes, and triggers to enforce database integrity. Integrity constraints offer the advantages of defining integrity controls in one step during the table creation process and of simplifying the creation of those integrity controls. However, integrity constraints are more limited in scope and less comprehensive than defaults, rules, indexes, and triggers.

- You must declare constraints that operate on more than one column as table-level constraints; declare constraints that operate on only one column as column-level constraints. Although the difference is rarely noticed by users, column-level constraints are checked only if a value in the column is being modified, while the table-level constraints are checked if there is any modification to a row, regardless of whether or not it changes the column in question.

Place column-level constraints after the column name and datatype, before the delimiting comma. Enter table-level constraints as separate comma-delimited clauses. The SAP ASE server treats table-level and column-level constraints the same way; neither way is more efficient than the other.

- You can create the following types of constraints at the table level or the column level:
  - A `unique` constraint does not allow two rows in a table to have the same values in the specified columns. In addition, a `primary key` constraint disallows null values in the column.
  - A referential integrity (`references`) constraint requires that the data being inserted or updated in specific columns has matching data in the specified table and columns.
  - A `check` constraint limits the values of the data inserted into the columns.

You can also enforce data integrity by restricting the use of null values in a column (using the `null` or `not null` keywords) and by providing default values for columns (using the `default` clause).

- You can use `sp_primarykey`, `sp_foreignkey`, and `sp_commonkey` to save information in system tables, which can help clarify the relationships between tables in a database. These system procedures do not enforce key relationships or duplicate the functions of the `primary key` and `foreign key` keywords in a `create table` statement. For a report on keys that have been defined, use `sp_helpkey`. For a report on frequently used joins, execute `sp_helpjoins`.
- Transact-SQL provides several mechanisms for integrity enforcement. In addition to the constraints you can declare as part of `create table`, you can create rules, defaults, indexes, and triggers. This table summarizes the integrity constraints and describes the other methods of integrity enforcement:

In create table	Other Methods
unique constraint	<code>create unique index</code> (on a column that allows null values)
primary key constraint	<code>create unique index</code> (on a column that does not allow null values)
references constraint	<code>create trigger</code>
check constraint (table level)	<code>create trigger</code>
check constraint (column level)	<code>create trigger</code> or <code>create rule</code> and <code>sp_bindrule</code>

## In create table

## Other Methods

default clause

create default and sp\_bindefault

The method you choose depends on your requirements. For example, triggers provide more complex handling of referential integrity (such as referencing other columns or objects) than those declared in `create table`. Also, the constraints defined in a `create table` statement are specific for that table; unlike rules and defaults, you cannot bind them to other tables, and you can only drop or change them using `alter table`. Constraints cannot contain subqueries or aggregate functions, even on the same table.

- `create table` can include many constraints, with these limitations:
  - The number of `unique` constraints is limited by the number of indexes that a table can have.
  - A table can have only one `primary key` constraint.
  - You can include only one `default` clause per column in a table, but you can define different constraints on the same column.

For example:

```
create table discount_titles
(title_id varchar(6) default "PS7777" not null
 unique clustered
 references titles (title_id)
 check (title_id like "PS%"),
 new_price money)
```

Column `title_id` of the new table `discount_titles` is defined with each integrity constraint.

- You can create error messages and bind them to referential integrity and `check` constraints. Create messages with `sp_addmessage` and bind them to the constraints with `sp_bindmsg`.
- The SAP ASE server evaluates `check` constraints before enforcing the referential constraints, and evaluates triggers after enforcing all the integrity constraints. If any constraint fails, the SAP ASE server cancels the data modification statement; any associated triggers do not execute. However, a constraint violation *does not* roll back the current transaction.
- In a referenced table, you cannot update column values or delete rows that match values in a referencing table. Update or delete from the referencing table first, then try updating or deleting from the referenced table.
- You must drop the referencing table before you drop the referenced table; otherwise, a constraint violation occurs.
- For information about constraints defined for a table, use `sp_helpconstraint`.

## 1.41.10 Unique and Primary-Key Constraints

Considerations when using unique and primary-key constraints.

- You can declare `unique` constraints at the column level or the table level. `unique` constraints require that all values in the specified columns be unique. No two rows in the table can have the same value in the specified column.
- A `primary key` constraint is a more restrictive form of `unique` constraint. Columns with `primary key` constraints cannot contain null values.

## i Note

The `create table` statement's `unique` and `primary key` constraints create indexes that define unique or primary key attributes of columns. `sp_primarykey`, `sp_foreignkey`, and `sp_commonkey` define logical relationships between columns. These relationships must be enforced using indexes and triggers.

- Table-level `unique` or `primary key` constraints appear in the `create table` statement as separate items and must include the names of one or more columns from the table being created.
- `unique` or `primary key` constraints create a unique index on the specified columns. The `unique` constraint in Example 3 creates a unique, clustered index, as does:

```
create unique clustered index salesind
  on sales (stor_id, ord_num)
```

The only difference is the index name, which you could set to `salesind` by naming the constraint.

- The definition of `unique` constraints in the SQL standard specifies that the column definition cannot allow null values. By default, the SAP ASE server defines the column as not allowing null values (if you have not changed this using `sp_dboption`) when you omit `null` or `not null` in the column definition. In Transact-SQL, you can define the column to allow null values along with the `unique` constraint, since the unique index used to enforce the constraint allows you to insert a null value.
- `unique` constraints create unique, nonclustered indexes by default; `primary key` constraints create unique, clustered indexes by default. There can be only one clustered index on a table, so you can specify only one `unique clustered` or `primary key clustered` constraint.
- The `unique` and `primary key` constraints of `create table` offer a simpler alternative to the `create index` statement. However:
  - You cannot create nonunique indexes.
  - You cannot use all the options provided by `create index`.
  - You must drop these indexes using `alter table drop constraint`.

## 1.41.11 Referential Integrity Constraints

Referential integrity constraints require that data inserted into a *referencing* table that defines the constraint must have matching values in a *referenced* table.

- A referential integrity constraint is satisfied for either of the following conditions:
  - The data in the constrained columns of the referencing table contains a null value.
  - The data in the constrained columns of the referencing table matches data values in the corresponding columns of the referenced table.

Using the `pubs2` database as an example, a row inserted into the `salesdetail` table (which records the sale of books) must have a valid `title_id` in the `titles` table. `salesdetail` is the referencing table and `titles` table is the referenced table. Currently, `pubs2` enforces this referential integrity using a trigger. However, the `salesdetail` table could include this column definition and referential integrity constraint to accomplish the same task:

```
title_id tid
references titles (title_id)
```

- The maximum number of table references allowed for a query is 192. Use `sp_helpconstraint` to check a table's referential constraints.
- A table can include a referential integrity constraint on itself. For example, the `store_employees` table in `pubs3`, which lists employees and their managers, has the following self-reference between the `emp_id` and `mgr_id` columns:

```
emp_id id primary key,
mgr_id id null
      references store_employees (emp_id),
```

This constraint ensures that all managers are also employees, and that all employees have been assigned a valid manager.

- You cannot drop a referenced table until the referencing table is dropped or the referential integrity constraint is removed (unless it includes only a referential integrity constraint on itself).
- SAP ASE does not allow referential integrity constraints on temporary tables.
- To create a table that references another user's table, you must have `references` permission on the referenced table. For information about assigning `references` permissions, see the `grant` command.
- Table-level, referential integrity constraints appear in the `create table` statement as separate items. They must include the `foreign key` clause and a list of one or more column names. Column names in the `references` clause are optional only if the columns in the referenced table are designated as a primary key through a `primary key` constraint. The referenced columns must be constrained by a unique index in that referenced table. You can create that unique index using either the `unique` constraint or the `create index` statement.
- The datatypes of the referencing table columns must match the datatypes of the referenced table columns. For example, the datatype of `col1` in the referencing table (`test_type`) matches the datatype of `pub_id` in the referenced table (`publishers`):

```
create table test_type
  (col1 char (4) not null
   references publishers (pub_id),
  col2 varchar (20) not null)
```

- The referenced table must exist when you define the referential integrity constraint. For tables that cross-reference one another, use the `create schema` statement to define both tables simultaneously. As an alternative, create one table without the constraint and add it later using `alter table`. See `create schema` or `alter table` for more information.
- The `create table` referential integrity constraints offer a simple way to enforce data integrity. Unlike triggers, constraints cannot:
  - Cascade changes through related tables in the database
  - Enforce complex restrictions by referencing other columns or database objects
  - Perform "what-if" analysis

Referential integrity constraints do not roll back transactions when a data modification violates the constraint. Triggers allow you to choose whether to roll back or continue the transaction depending on how you handle referential integrity.

### **i** Note

The SAP ASE server checks referential integrity constraints before it checks any triggers, so a data modification statement that violates the constraint does not also fire the trigger.

## 1.41.12 Using Cross-Database Referential Integrity Constraints

Usage considerations for cross-database referential integrity constraints.

- When you create a cross-database constraint, the SAP ASE server stores the following information in the `sysreferences` system table of each database:

Table 2: Information Stored for Referential Integrity Constraints

Information Stored in <code>sysreferences</code>	Columns with Information About the Referenced Table	Columns with Information About the Referencing Table
Key column IDs	<code>refkey1</code> through <code>refkey16</code>	<code>fokey1</code> through <code>fokey16</code>
Table ID	<code>reftabid</code>	<code>tableid</code>
Database ID	<code>pmrydbid</code>	<code>frgndbid</code>
Database name	<code>pmrydbname</code>	<code>frgndbname</code>

- You can drop the referencing table or its database. The SAP ASE server automatically removes the foreign-key information from the referenced database.
- Because the referencing table depends on information from the referenced table, the SAP ASE server does not allow you to:
  - Drop the referenced table,
  - Drop the external database that contains the referenced table, or
  - Use `sp_renamedb` to rename either database.

You must use `alter table` to remove the cross-database constraint before you can do any of these actions.

- Each time you add or remove a cross-database constraint, or drop a table that contains a cross-database constraint, dump *both* of the affected databases.

### ⚠ Caution

Loading earlier dumps of databases containing cross-database constraints may cause database corruption.

- The `sysreferences` system table stores the name and the ID number of the external database. The SAP ASE server cannot guarantee referential integrity if you use `load database` to change the database name or to load it onto a different server.

### ⚠ Caution

Before dumping a database to load it with a different name or move it to another SAP ASE server, use `alter table` to drop all external referential integrity constraints.

## 1.41.13 check Constraints

A `check` constraint limits the values a user can insert into a column in a table.

- A `check` constraint specifies a `<search_condition>` that any non-null value must pass before it is inserted into the table. A `<search_condition>` can include:
  - A list of constant expressions introduced with `in`
  - A range of constant expressions introduced with `between`
  - A set of conditions introduced with `like`, which can contain wildcard characters

An expression can include arithmetic operators and Transact-SQL built-in functions. The `<search_condition>` cannot contain subqueries, aggregate functions, or a host variable or parameter. The SAP ASE server does not enforce `check` constraints for temporary tables.

- A column-level `check` constraint can reference only the column in which it is defined; it cannot reference other columns in the table. Table-level `check` constraints can reference any column in the table.
- `create table` allows multiple `check` constraints in a column definition.
- `check` integrity constraints offer an alternative to using rules and triggers. They are specific to the table in which they are created, and cannot be bound to columns in other tables or to user-defined datatypes.
- `check` constraints do not override column definitions. If you declare a `check` constraint on a column that allows null values, you can insert NULL into the column, implicitly or explicitly, even though NULL is not included in the `<search_condition>`. For example, if you create a `check` constraint specifying “pub\_id in (“1389”, “0736”, “0877”, “1622”, “1756”)” or “@amount > 10000” in a table column that allows null values, you can still insert NULL into that column. The column definition overrides the `check` constraint.

## 1.41.14 IDENTITY Columns

Information about using IDENTITY columns.

- The first time you insert a row into the table, the SAP ASE server assigns the IDENTITY column a value of 1. Each new row gets a column value that is 1 higher than the last value. This value takes precedence over any defaults declared for the column in the `create table` statement or bound to the column with `sp_bindefault`.  
The maximum value that can be inserted into an IDENTITY column is  $10^{\text{precision}} - 1$  for a numeric. For integer identities, it is the maximum permissible value of its type (such as 255 for `tinyint`, 32767 for `smallint`).  
See *System and User-Defined Datatypes in Reference Manual: Building Blocks* for more information about identifiers.
- Inserting a value into the IDENTITY column allows you to specify a seed value for the column or to restore a row that was deleted in error. The table owner, database owner, or system administrator can explicitly insert a value into an IDENTITY column after using `set identity_insert <table_name>` on for the base table. Unless you have created a unique index on the IDENTITY column, the SAP ASE server does not verify the uniqueness of the value. You can insert any positive integer.
- You can reference an IDENTITY column using the `syb_identity` keyword, qualified by the table name where necessary, instead of using the actual column name.

- System administrators can use the `auto identity` database option to automatically include a 10-digit IDENTITY column in new tables. To turn on this feature in a database, use:

```
sp_dboption <database_name>, "auto identity", "true"
```

Each time a user creates a table in the database without specifying a `primary key`, a `unique constraint`, or an IDENTITY column, the SAP ASE server automatically defines an IDENTITY column. This column, `SYB_IDENTITY_COL`, is not visible when you retrieve columns with the `select *` statement. You must explicitly include the column name in the select list.

- Server failures can create gaps in IDENTITY column values. Gaps can also occur due to transaction rollbacks, the deletion of rows, or the manual insertion of data into the IDENTITY column. The maximum size of the gap depends on the setting of the `identity burning set factor` and `identity grab size` configuration parameters, or the `identity_gap` value given in the `create table` or `select into` statement. See *Managing Identity Gaps in Tables* in the *Transact-SQL Users Guide*.

## 1.41.15 Specifying a Locking Scheme

To specify the locking scheme for a table, use the keyword `lock` and one of: `allpages locking`, `datapages locking`, `datarows locking`.

- `Allpages locking` – locks data pages and the indexes affected by queries.
- `Datapages locking` – locks only data pages.
- `Datarows locking` – locks only data rows.

If you do not specify a locking scheme, the default locking scheme for the server is used. The server-wide default is set with the configuration parameter `lock scheme`.

You can use `alter table` to change the locking scheme for a table.

## 1.41.16 Getting Information About Tables

There are several system procedures you can use to obtain information about tables.

- `sp_help` displays information about tables, listing any attributes (such as cache bindings) assigned to the specified table and its indexes, giving the attribute's class, name, integer value, character value, and comments.
- `sp_depends` displays information about the views, triggers, and procedures in the database that depend on a table.
- `sp_helpindex` reports information about the indexes created on a table.
- `sp_helppartition` reports information about the table's partition properties.

## 1.41.17 Creating Tables with Partitions

Considerations for creating tables with partitions.

- Before you create a table with partitions, you must prepare the disk devices and segments that you are using for the partitions.
- Range partitioning is dependent on sort order. If the sort order is changed, you must repartition the table for the new sort order.
- Range-partition bounds must be in ascending order according to the order in which the partitions are created.
- A column of `text`, `unitext`, `image`, or `bit`, Java datatype, or computed column cannot be part of a partition key, but a partitioned table can include columns with these datatypes. A composite partition key can contain up to 31 columns.
- For range and hash partitions, the partition key can be a composite key with as many as 31 columns. In general, however, a table with more than four partition columns becomes hard to manage and is not useful.
- Bound values for range and list partitions must be compatible with the corresponding partition key datatype. If a bound value is specified in a compatible but different datatype, the SAP ASE server converts the bound value to the partition key's datatype. The SAP ASE server does not support:
  - Explicit conversions.
  - Implicit conversions that result in data loss.
  - NULL as a boundary in a range-partitioned table.
  - Conversions from nonbinary datatypes to `binary` or `varbinary` datatypes.
- You can use NULL in a value list for list-partitioned tables.
- You can partition a table that contains `text` and `image` columns, but partitioning has no effect on the way the SAP ASE server stores the `text` and `image` columns because they reside on their own partition.
- You cannot partition remote tables.
- The SAP ASE server considers NULL to be lower than any other partition key value for a given partition key column.

## 1.41.18 Creating Tables With Computed Columns

Take these into consideration when creating tables with computed columns.

- `<computed_column_expression>` can reference only columns in the same table.
- The deterministic property of `<computed_column_expression>` significantly affects data operations. See *Deterministic Property* in the *Transact-SQL Users Guide*.
- Computed columns cannot have default values, and cannot be `identity` or `timestamp` columns.
- You can specify nullability only for materialized computed columns. If you do not specify nullability, all computed columns are, by default, nullable. Virtual computed columns are always nullable.
- Triggers and constraints, such as `check`, `rule`, `unique`, `primary key`, or `foreign key`) support only materialized computed columns. You cannot use them with virtual computed columns.
- If a user-defined function in a computed column definition is dropped or becomes invalid, any computed column operations that call that function fail.



## 1.41.19 Creating Tables with Encrypted Columns

Considerations for creating tables with encrypted columns.

You can encrypt these datatypes:

- `int`, `smallint`, `tinyint`
- `unsigned int`, `unsigned smallint`, `unsigned tinyint`
- `bigint`, `unsigned bigint`
- `decimal`, `numeric`
- `float4`, `float8`
- `money`, `smallmoney`
- `date`, `time`, `smalldatetime`, `datetime`, `bigdatetime`
- `char`, `varchar`
- `unichar`, `univarchar`
- `binary`, `varbinary`
- `bit`

The underlying datatype of encrypted data on disk is `varbinary`. Null values are not encrypted.

`create table` displays an error if you:

- Specify a computed column based on an expression that references one or more encrypted columns.
- Use the `encrypt` and `compute` parameters on the same column.
- List an encrypted column in the `partition` clause

During `create table`, `alter table`, and `select into` operations, the SAP ASE server calculates the maximum internal length of the encrypted column. The database owner must know the maximum length of the encrypted columns before he or she can make decisions about schema arrangements and page sizes.

You can create an index on an encrypted column if you specify the encryption key without any initialization vector or random padding. The SAP ASE server issues an error if you execute `create index` on an encrypted column with an initialization vector or random padding.

You can define referential integrity constraints on encrypted columns when:

- Both referencing and referenced columns are encrypted.
- The key you use to encrypt the columns specifies `init_vector null` and you have not specified `pad random`.

You cannot encrypt a computed column, and an encrypted column cannot appear in the expression defining a computed column. You cannot specify an encrypted column in the `<partition_clause>` of `create table`.

See *Encrypted Data* in the *Encrypted Columns Users Guide*.

## 1.41.20 Limitations When Creating Virtually Hashed Tables

Limitations for creating virtually hashed tables.

- You cannot use `create table` on the segment that includes a virtually hashed table, since a virtually hashed table must take only one exclusive segment, which cannot be shared by other tables or databases.

- Virtually hashed tables must have unique rows. Virtually hashed tables do not allow multiple rows with the same key column values because the SAP ASE server cannot keep one row in the hash region and another with the same key column value in the overflow clustered region.
- `truncate table` is not supported. Use `delete from <table_name>` instead.
- SQL92 does not allow two unique constraints on a relation to have the same key columns. However, the primary key clause for a virtually hashed table is not a standard unique constraint, so you can declare a separate unique constraint with the same key columns as the virtually hashed keys.
- Because you cannot create a virtually hashed clustered index after you create a table, you also cannot drop a virtually hashed clustered index.
- You must create a virtually hashed table on an exclusive segment. You cannot share disk devices you assign to the segments for creating a virtually hashed table with other segments.
- You cannot create two virtually hashed tables on the same exclusive segment. The SAP ASE server supports 32 different segments per database. Three segments are reserved for the default, system, and log segments, so the maximum number of virtually-hashed tables per database is 29.
- You cannot use the `alter table` or `drop clustered index` commands on virtually hashed tables.
- Virtually hashed tables must use all-pages locking.
- The key columns and hash factors of a virtually hashed table must use the `int` datatype.
- You cannot include `text` or `image` columns in virtually hashed tables, or columns with datatypes based on the `text` or `image` datatypes.
- You cannot create a partitioned virtually hashed table.

## 1.41.21 Creating Tables for In-Memory and Relaxed Durability Databases

Table-level logging settings defined by `create table` also apply to tables created via `select into`.

Although you can create tables with minimal logging in databases using full durability, the databases do not use minimal logging for these tables. The SAP ASE server allows you to set these tables to minimal logging so you can use these databases as templates for other databases with durability set to `no_recovery`, where minimal logging takes effect in the dependent database.

## 1.41.22 Creating Tables for In-Memory Row Storage

Creating tables for in-memory row storage includes some restrictions.

- The database must be enabled for database-wide row storage cache to use row caching or snapshot isolation for a table. This row-storage cache is available for individual tables as their in-memory row storage cache.
- The specified row storage cache is used for all data partitions in a partitioned table.
- Row storage usage for row caching and snapshot isolation is supported for datarows locked user tables in a nontemporary disk-resident user databases that use full durability.
- You can enable `row_caching` and `snapshot_isolation` simultaneously for a table, but any memory limit you specify for `row_caching` applies to all rows for this table residing in the in-memory row storage.

Because this is a soft limit, any updates or deletes to rows residing in the data page may cause these rows to migrate to the in-memory row storage.

- Specifying the `snapshot_isolation off` parameter for a table disables snapshot isolation for this table if this feature was already enabled database-wide. `snapshot_isolation off` is required when individual tables need not support snapshot isolation scan semantics, which may otherwise require extra memory for in-memory versioning.
- Compression for compressed tables applies to only the data that is page-resident. Data rows stored in the row storage cache remain uncompressed until the data is migrated back to the page storage. The server applies the appropriate row or page-level compression when the data from the cache is persisted to pages in the database. Although the data for compressed tables is stored uncompressed in the row storage cache, any specified memory limits apply to the uncompressed form of the row in the cache.
- `create table` fails when you specify `row_caching` or `snapshot_isolation`, but the database is not enabled for a database-wide row storage cache.
- The `erase_residual_data` parameter applies to only database space for disk-resident rows. The server recycles memory (and does not attempt to cleanse the row's data from the freed memory) when you delete rows residing in the in-memory row storage.
- You cannot specify row storage cache for:
  - External (proxy) tables
  - Tables created with the `for load` option

## 1.41.23 Restrictions for Shared-Disk Clusters

Restrictions for working with shared-disk clusters.

- You cannot include a referential integrity constraint that references a column on a local temporary database unless it is from a table on the same local temporary database. `create table` fails if it attempts to create a reference to a column on a local temporary database from a table in another database.
- You cannot encrypt a column with an encryption key stored in a local temporary database unless the column's table resides on the same local temporary database. `alter table` fails if it attempts to encrypt a column with an encryption key on the local temporary database and the table is in another database.

## 1.41.24 Space Management Properties

The space management properties `fillfactor`, `max_rows_per_page`, `exp_row_size`, and `reservepagegap` help manage space usage for tables.

- `fillfactor` leaves extra space on pages when indexes are created, but the `fillfactor` is not maintained over time.
- `max_rows_per_page` limits the number of rows on a data or index page. Its main use is to improve concurrency in allpages-locked tables, since reducing the number of rows can reduce lock contention. If you specify a `max_rows_per_page` value and `datapages` or `datarows` locking, a warning message is printed. The table is created, and the value is stored in `sysindexes`, but it is applied only if the locking scheme is changed later to `allpages`.

- `exp_row_size` specifies the expected size of a data row. It applies only to data rows, not to indexes, and applies only to data-only-locked tables that have variable-length columns. It is used to reduce the number of forwarded rows in data-only-locked tables. It is needed mainly for tables where rows have null or short columns when first inserted, but increase in size as a result of subsequent updates. `exp_row_size` reserves space on the data page for the row to grow to the specified size. If you specify `exp_row_size` when you create an allpages-locked table, a warning message is printed. The table is created, and the value is stored in `sysindexes`, but it is applied only if the locking scheme is changed later to `datapages` or `datarows`.
- `reservepagegap` specifies the ratio of empty pages to full pages to apply for commands that perform extent allocation. It applies to both data and index pages, in all locking schemes.

This table shows the valid combinations of space management properties and locking scheme. If a `create table` command includes incompatible combinations, a warning message is printed and the table is created. The values are stored in system tables, but are not applied. If the locking scheme for a table changes so that the properties become valid, then they are used.

Property	allpages	datapages	datarows
<code>max_rows_per_page</code>	Yes	No	No
<code>exp_row_size</code>	No	Yes	Yes
<code>reservepagegap</code>	Yes	Yes	Yes
<code>fillfactor</code>	Yes	Yes	Yes

This table shows the default values and the effects of using default values for the space management properties.

Property	Default	Effect of Using the Default
<code>max_rows_per_page</code>	0	Fits as many rows as possible on the page, up to a maximum of 255
<code>exp_row_size</code>	0	Uses the server-wide default value, which is set with the configuration parameter <code>default exp_row_size percent</code>
<code>reservepagegap</code>	0	Leaves no empty pages during extent allocations
<code>fillfactor</code>	0	Fully packs leaf pages, with space left on index pages

## 1.41.25 Using `reservepagegap`

Commands that use large amounts of space allocate new space by allocating an extent rather than allocating single pages. The `reservepagegap` keyword causes these commands to leave empty pages so that

subsequent page allocations occur close to the page being split or close to the page from which a row is being forwarded.

This table shows when `reservepagegap` is applied:

Command	Applies to data pages	Applies to index pages
<code>Fast bcp</code>	Yes	Fast bcp is not used if indexes exist
<code>Slow bcp</code>	Only for heap tables, not for tables with a clustered index	Extent allocation not performed
<code>select into</code>	Yes	No indexes exist on the target table
<code>create index or alter table...constraint</code>	Yes, for clustered indexes	Yes
<code>reorg rebuild</code>	Yes	Yes
<code>alter table...lock</code>	Yes	Yes

(For allpages-locking to data-only locking, or vice versa)

## 1.41.26 Java-SQL Columns

If Java is enabled in the database, you can create tables with Java-SQL columns.

The declared class (`<datatype>`) of the Java-SQL column must implement either the `Serializable` or `Externalizable` interface.

When you create a table, you cannot specify a Java-SQL column:

- As a foreign key
- In a references clause
- As having the `UNIQUE` property
- As the primary key

If `in row` is specified, the value stored cannot exceed 16K bytes, depending on the page size of the database server and other variables.

If `off row` is specified:

- The column cannot be referenced in a check constraint.
- The column cannot be referenced in a `select` that specifies `distinct`.
- The column cannot be specified in a comparison operator, in a predicate, or in a `group by` clause.

Refer to *Java in Adaptive Server Enterprise*.

## 1.41.27 Determining Values for hash\_factor

You can keep the hash factor for the first key as 1. The hash factor for all the remaining key columns is greater than the maximum value of the previous key allowed in the hash region multiplied by its hash factor.

The SAP ASE server allows tables with hash factors greater than 1 for the first key column to have fewer rows on a page. For example, if a table has a hash factor of 5 for the first key column, after every row in a page, space for the next four rows is kept empty. To support this, the SAP ASE server requires five times the amount of table space.

If the value of a key column is greater than or equal to the hash factor of the next key column, the current row is inserted in the overflow clustered region to avoid collisions in the hash region.

For example, `t` is a virtually hashed table with key columns `id` and `age`, and corresponding hash factors of (10,1). Because the hash value for rows (5, 5) and (2, 35) is 55, this may result in a hash collision.

However, because the value 35 is greater than or equal to 10 (the hash factor for the next key column, `id`), the SAP ASE server stores the second row in the overflow clustered region, avoiding collisions in the hash region.

In another example, if `u` is a virtually hashed table with a primary index and hash factors of (id1, id2, id3) = (125, 25, 5) and a `<max hash_value>` of 200:

- Row (1,1,1) has a hash value of 155 and is stored in the hash region.
- Row (2,0,0) has a hash value 250 and is stored in overflow clustered region.
- Row (0,0,6) has a hash factor of 6 x 5, which is greater than or equal to 25, so it is stored in the overflow clustered region.
- Row (0,7,0) has a hash factor of 7 x 25, which is greater than or equal to 125, so it is stored in the overflow clustered region

## 1.42 create temporary precomputed result set

Creates temporary precomputed result sets and the policies required to maintain them.

### Syntax

```
create {precomputed result set | materialized view}
  [<owner_name>.]<prs_name>
  [temporary refresh]
  as <query_expression>
```

### Parameters

**precomputed result set | materialized view**

creates a materialized view or precomputed result set.

**<prs\_name>**

name of the precomputed result set. A fully qualified **<prs\_name>** cannot include the server or database name.

**temporary refresh**

creates a temporary precomputed result set to store query redundant views that are used multiple times by the same query or by other frequently executed queries.

**<query\_expression>**

can only be `select * from <view_name>` and cannot include `where` clauses.

## Examples

### Example 1

Creates the `TITLES_VIEW_PRS` temporary precomputed result set:

```
create precomputed result set TITLES_VIEW_PRS temporary refresh
as
select * from TITLES_VIEW
go
```

## Standards

The `create temporary precomputed result set` command is a Transact-SQL extension and is not covered by the SQL standard.

## Permissions

You must have `create table` and `create view` privileges to create temporary precomputed result sets.

## Auditing

This command is not audited.

## 1.43 create thread pool

Creates a user-defined thread pool.

### Considerations for Process Mode

`create thread pool` is not supported in process mode.

### Syntax

```
create thread pool <pool_name> with thread count = <count>
  [, pool description = <description>]
  [idle timeout = <time_period>]
  [for instance <inst_name> | global]
```

### Parameters

**<pool\_name>**

is the name of the pool you are creating.

**thread count = <count>**

is the number of threads in the pool. Must be greater than or equal to 1.

**pool description = <description>**

(Optional) describes the pool's purpose. Must be fewer than 256 characters.

**idle timeout = <time\_period>**

time, in microseconds, that threads look for work before going to sleep. The default is 100 microseconds. A value of -1 means the threads never go to sleep, and continue to consume CPU if no work is available. A value of 0 indicates that threads immediately go to sleep if they find no work.

**for instance [<inst\_name> | global]**

is name of the instance, or global for all instances.



## Examples

### Example 1

Creates a thread pool named `sales_pool` with 10 threads:

```
create thread pool sales_pool with thread count = 10
```

### Example 2

Creates a thread pool named `order_pool`, which includes a description:

```
create thread pool order_pool with thread count = 10,  
pool description = 'used for handling order entry users'
```

### Example 3

Creates a thread pool named `order_pool` with 2 threads and an `idle timeout` of 500 microseconds:

```
create thread pool order_pool with thread count = 2,  
idle timeout = 500
```

## Usage

- Use `sp_addexecclass` to associate workload with a user-created thread pool.
- The SAP ASE server must have a sufficient number of free engines to bring online all threads (specified by `<count>`) in an engine pool. The value for `max online engines` determines the total number of engines. The total number of active threads in all engine pools cannot exceed the value of `max online engines`.
- `<pool_name>` cannot start with `syb_`, which is reserved for SAP-created thread pools.
- You cannot use Transact-SQL variables as parameters to `create thread pool`.
- `idle timeout 0` indicates that threads immediately go to sleep if they find no work.
- A value of `-1` for `idle timeout 0` indicates that threads never go to sleep, and continue to consume CPU if no work is available.
- You can issue `create thread pool` with `execute immediate`.

When using the `for instance` clause:

- If you do not specify the `for instance` clause, `create thread pool`
- You can only create instance-specific pools from the same instance.
- The instance-specific attribute has precedence over global attributes.
- To create thread pools with the same name but with different attributes, create a thread pool on first instance, then use `alter thread pool` on the other instances.
- Rename and description are global operations; for example, both `<pool_name>` and `<description>` are same for all instances.

## Standards

ANSI SQL – Compliance level: Transact-SQL extension

## Permissions

The permission checks for `create thread pool` differ based on your granular permissions settings.

Setting	Description
---------	-------------

<b>Enabled</b>	With granular permissions enabled, you must be a user with the <code>manage any thread pool</code> privilege.
----------------	---

<b>Disabled</b>	With granular permissions disabled, you must be a user with <code>sa_role</code> .
-----------------	--

## Auditing

You can enable `thread_pool` auditing option to audit this command. Values in `event` and `extrainfo` columns from the `sysaudits` table are:

Information	Value
Audit option	<code>thread_pool</code>
Event	142
Command or access audited	<code>create thread pool</code>
Information in <code>extrainfo</code>	<ul style="list-style-type: none"><li>• <b>Roles</b> – current active roles</li><li>• <b>Full command text</b> – full text of <code>create thread pool</code> command</li><li>• <b>Previous value</b> – NULL</li><li>• <b>Current value</b> – NULL</li><li>• <b>Other information</b> – NULL</li><li>• <b>Proxy information</b> – original login name, if <code>set proxy</code> is in effect</li></ul>

Full command text is included in `extrainfo`. For example:

```
sa_role sybase_ts_role mon_role; create thread pool mythreadpool1
with thread count = 2; ; ; ; user0/ase;
```

For more information about auditing, see *Security Administration Guide > Auditing*.

## Related Information

[alter thread pool \[page 111\]](#)

[drop thread pool \[page 460\]](#)

## 1.44 create trigger

Creates one or more new triggers, or re-creates an existing trigger. A trigger is a type of stored procedure that is often used to enforce integrity constraints, executing automatically when a user attempts a specified data modification statement on a specified table.

### Syntax

```
create [or replace] trigger [<owner>.<trigger_name>]
on [<owner>.<table_name>]
{for {insert, update} | instead of {insert, update, delete}}
[order <integer>]
[as
  [if update (<column_name>)
    [{and | or} update (<column_name>)]...]
  <SQL_statements>
  [if update (<column_name>)
    [{and | or} update (<column_name>)]...]
  <SQL_statements>]...]
```

### Parameters

#### **create**

creates a trigger if one does not already exist.

#### **or replace**

re-creates an existing trigger. Use this clause to change the definition of a trigger. When specifying `or replace`, auditing options on the trigger are not dropped. If there is no existing trigger with the name you enter, a new one is created and the old trigger remains. This is in conjunction with multiple triggers.

#### **<trigger\_name>**

is the name of the trigger, which must conform to the rules for identifiers and be unique in the database. Specify the owner's name to create another trigger of the same name owned by a different user in the current database. The default value for `<owner>` is the current user. If you use an owner name to qualify a trigger, you must explicitly qualify the table name the same way.

You cannot use a variable for a trigger name.

The name of the trigger is not changed when the trigger definition is replaced. The name of the new trigger definition must match the old name to be replaced. If the trigger name differs from any existing trigger, a new trigger is created and the old trigger is not dropped.

#### **<table\_name>**

is the name of the table on which to create the trigger. If more than one table of the same name exists in the database, specify the owner's name. The default value for `<owner>` is the current user.

You cannot change the name of the table when a trigger is replaced. If an existing trigger is modified to associate the trigger with another table, then an error is raised indicating that the trigger already exists on another table and cannot be replaced.

#### **for | instead of**

`for` – used before `insert`, `delete`, or `update` to indicate what you are creating the trigger for.

`instead of` – creates and fills the inserted and deleted pseudo tables, which are used in the trigger to examine the rows that would have been modified by the original `insert`, `delete`, or `update` query.

You cannot change an "instead of" trigger to a "for" trigger, and vice versa.

#### **insert, update, delete**

can be included in any combination. `delete` cannot be used with the `if update` clause.

You can change these actions when you use the `or replace` clause. For example, if the old trigger definition specifies all clauses, the replacement definition can specify all clauses, or a combination of the actions.

#### **order <integer>**

specifies a partial or full ordering of trigger firing:

- Full ordering occurs when you create all the triggers using the `order` clause.
- Partial ordering occurs if you do not specify the `order` clause on some of the triggers. Triggers without the `order` clause implicitly take order number 0 and do not have a defined order, except that they fire after those triggers created using `order`.

#### **<SQL\_statements>**

specifies trigger conditions and trigger actions. Trigger conditions determine whether the attempted `insert`, `update`, or `delete` causes the trigger actions to be carried out. The SQL statements often include a subquery preceded by the keyword `if`. In Example 2, below, the subquery that follows the keyword `if` is the trigger condition.

Trigger actions take effect when the user action (`insert`, `update`, or `delete`) is attempted. If multiple trigger actions are specified, they are grouped with `begin` and `end`.

You can change trigger conditions and actions when the trigger definition is replaced.

#### **if update**

tests whether the specified column is included in the `set` list of an `update` statement or is affected by an `insert`. `if update` allows specified trigger actions to be associated with updates to specified columns (see Example 3). More than one column can be specified, and you can use more than one `if update` statement in a `create trigger` statement.

You can drop or add the `if update` and change the column name referenced by this clause.

**order** *<integer>*

the order of the trigger firing can also be changed when the trigger definition is replaced.

## Examples

### Example 1

Prints a message when anyone tries to add data or change data in the `titles` table:

```
create trigger reminder
on titles
for insert, update as
print "Don't forget to print a report for accounting."
```

### Example 2

Prevents insertion of a new row into `titleauthor` if there is no corresponding `title_id` in the `titles` table:

```
create trigger t1
on titleauthor
for insert as
if (select count (*)
    from titles, inserted
    where titles.title_id = inserted.title_id) = 0
begin
print "Please put the book's title_id in the
      titles table first."
rollback transaction
end
```

### Example 3

If the `pub_id` column of the `publishers` table is changed, make the corresponding change in the `titles` table:

```
create trigger t2
on publishers
for update as
if update (pub_id) and @@rowcount = 1
begin
update titles
set titles.pub_id = inserted.pub_id
from titles, deleted, inserted
where deleted.pub_id = titles.pub_id
end
```

### Example 4

Deletes title from the `titles` table if any row is deleted from `titleauthor`. If the book was written by more than one author, other references to it in `titleauthor` are also deleted:

```
create trigger t3
on titleauthor
for delete as
```

```

begin
  delete titles
  from titles, deleted
  where deleted.title_id = titles.title_id
  delete titleauthor
  from titleauthor, deleted
  where deleted.title_id = titleauthor.title_id
  print "All references to this title have been
  deleted from titles and titleauthor."
end

```

### Example 5

Prevents updates to the primary key on weekends. Prevents updates to the price or advance of a title unless the total revenue amount for that title surpasses its advance amount:

```

create trigger stopupdatetrig
on titles
for update
as
if update (title_id)
  and datename (dw, getdate ())
  in ("Saturday", "Sunday")
  begin
    rollback transaction
    print "We don't allow changes to"
    print "primary keys on the weekend!"
  end
if update (price) or update (advance)
  if (select count (*) from inserted
  where (inserted.price * inserted.total_sales)
  < inserted.advance) > 0
  begin
    rollback transaction
    print "We don't allow changes to price or"
    print "advance for a title until its total"
    print "revenue exceeds its latest advance."
  end
end

```

### Example 6

Uses `instead of` triggers to update union views:

```

create table EmployeeWest (
  empid          int primary key,
  empname        varchar(30),
  empdob         datetime,
  region         char(5)
  constraint region_chk
  check (region='West'))
create table EmployeeEast (
  empid          int primary key,
  empname        varchar(30),
  empdob         datetime,
  region         char(5)
  constraint region_chk
  check (region='East'))
create view Employees as
  select * from EmployeeEast
  union all
  select * from EmployeeWest
create trigger EmployeesInsertTrig on Employees
instead of insert as
begin
  insert into EmployeeEast select * from inserted where region = "East"
end

```

```

insert into EmployeeWest select * from inserted where region = "West"
end
--will insert the data into the EmployeeEast table
insert into Employees values (10, 'Jane Doe', '11/11/1967', 'East')
--will insert the data into the EmployeeWest table
insert into Employees values (11, 'John Smith', '01/12/1977', 'West')
--will insert multiple rows into EmployeeEast and
--EmployeeWest tables. Employee2 table includes employees
--from both East and West.
insert into Employees select * from Employee2

```

### Example 7

Uses `instead of` triggers to implement encrypted column support, storing data in the database in encrypted form without changing applications (the user-defined functions, `my_encrypt` and `my_decrypt`, perform the encryption and decryption operations on the data):

```

CREATE TABLE Employee_t (id int PRIMARY KEY, name varchar(20),
                        salary binary (64))
--where the id and name columns are stored unencrypted, salary is
--encrypted and id is a primary key.
create view employee_v as select id, name, my_decrypt (salary)
from employee_t
CREATE TRIGGER EmployeeInsert
ON employee_v
INSTEAD OF INSERT
AS
BEGIN
    INSERT employee_t SELECT id, name, my_encrypt (salary)
    FROM inserted
END
CREATE TRIGGER employeeUpdate
ON employee_v
INSTEAD OF UPDATE
AS
BEGIN
    DELETE FROM employee_t WHERE id IN (SELECT id FROM deleted)
    INSERT employee_t SELECT id, name, my_encrypt (salary)
    FROM inserted
END
CREATE TRIGGER employeeDelete
ON employee_v
INSTEAD OF DELETE
AS
BEGIN
    DELETE FROM employee_t WHERE id IN (SELECT id FROM deleted)
END

```

### Example 8

Creates a trigger that prints a message when anyone tries to insert or update data in the `titles` table:

```

create trigger reminder
on titles
for insert, update as
print "Don't forget to print a report for accounting."
select object_id("reminder")
-----
1312004674

```

The next command changes the message of the printed trigger when anyone tries to update data in the `titles` table using the `or replace` clause:

```

create or replace trigger reminder
on titles

```

```
for update as
print "Don't forget to give a report to accounting."
select object_id("reminder")
-----
1312004674
```

## Usage

- To avoid seeing unexpected results due to changes in settings, run `set rowcount 0` as your initial statement before executing `create trigger`. The scope of `set` is limited to only the `create trigger` command, and resets to your previous setting once the procedure exits.
- A trigger fires only once per data modification statement. A complex query containing a `while` loop may repeat an `update` or `insert` many times, and the trigger is fired each time.
- In versions earlier than SAP ASE 16.0, consecutive `create trigger` commands dropped the old trigger and replaced it with a new trigger definition. However, the auditing options for the trigger were also dropped. Using the optional `or replace` clause, the definition is replaced, and auditing options are preserved.
- In SAP ASE version 16.0 and later, when there are multiple triggers, specifying `create` without `or replace` raises an error if the trigger name is same. If you specify a different trigger name, a new trigger is created and the old trigger remains.
- In versions of SAP ASE earlier than 16.0, if an existing trigger was replaced with the new trigger definition by specifying `create` without `or replace`, the name of the new trigger did not need to be same as the name of the old trigger name.
- You can only use the `order <integer>` clause with `for {insert | update | delete}`; you cannot use it with `instead of {insert | update | delete} triggers`.
- If you use a duplicate number for `order`, SAP ASE reports an error. `order` numbers need not be consecutive; in fact, nonconsecutive numbers might be preferable, as they allow you to insert new triggers into the middle of an order.

See also `sp_commonkey`, `sp_configure`, `sp_depends`, `sp_foreignkey`, `sp_help`, `sp_helptext`, `sp_primarykey`, `sp_rename`, `sp_spaceused` in *Reference Manual: Procedures*.

## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

## Permissions

Permissions on objects at trigger creation – when you create a trigger, the SAP ASE server makes no permission checks on objects such as tables or views that the trigger references. Therefore, you can successfully create a trigger, even though you do not have access to its objects. All permission checks occur when the trigger fires.



Permissions on objects at trigger execution – when the trigger executes, permission checks on its objects depend on whether the trigger and its objects are owned by the same user.

- If the trigger and its objects are not owned by the same user, the user who caused the trigger to fire must have been granted direct access to the objects. For example, if the trigger performs a select from a table the user cannot access, the trigger execution fails. In addition, the data modification that caused the trigger to fire is rolled back.
- If a trigger and its objects are owned by the same user, special rules apply. The user automatically has implicit permission to access the trigger's objects, even though the user cannot access them directly. See the detailed description of the rules for implicit permissions in the *System Administration Guide*.

Permissions for `instead of` and for triggers `instead of` – `instead of` triggers have the same permission requirements as `for` triggers: to create a view with `instead of` triggers, permission for `insert/update/delete` for the view, not the underlying tables, must be granted to the user.

The following describes permission checks for `create trigger` that differ based on your granular permissions settings.

Setting	Description
---------	-------------

<b>Enabled</b>	With granular permissions enabled, you must be the table owner and the <code>create trigger</code> privilege must not have been revoked to create a trigger. To create a trigger for another user's table, you must have the <code>create any trigger</code> privilege.
----------------	---

To replace the trigger, you must be the trigger owner. Any user who impersonates the trigger owner through an alias or `setuser` cannot replace the trigger.

<b>Disabled</b>	With granular permissions disabled, only a system security officer can grant or revoke permissions to create triggers. A user with <code>sa_role</code> has implicit permission to create a trigger on any user table. Users can create triggers only on tables that they own.
-----------------	--

To replace the trigger, you must be the trigger owner, or have `sa_role`. Any user who impersonates the trigger owner through an alias or `setuser` cannot replace the trigger unless the user has `sa_role`.

The system security officer may revoke user permission to create triggers. Revoking permission to create triggers affects only the database in which the systems security officer issues the `revoke` command. Permission to run the `create trigger` command is restored to the users whose permission was revoked when the system security officer explicitly grants them `create trigger` privilege.

## Auditing

You can enable `create` auditing option to audit this command. Values in `event` and `extrainfo` columns from the `sysaudits` table are:

Information	Value
Audit option	<code>create</code>
Event	12

Information	Value
Command or access audited	<code>create trigger</code>
Information in <code>extrainfo</code>	<ul style="list-style-type: none"> <li>• <b>Roles</b> – current active roles</li> <li>• <b>Full command text</b> – full text of <code>create trigger</code> command</li> <li>• <b>Previous value</b> – NULL</li> <li>• <b>Current value</b> – NULL</li> <li>• <b>Other information</b> – NULL</li> <li>• <b>Proxy information</b> – original login name, if <code>set proxy</code> is in effect</li> </ul>

Full command text is included in `extrainfo`. For example:

```
sa_role sso_role oper_role sybase_ts_role mon_role; create trigger t1
on dom1 for insert as print "Test"; ; ; ; sa/ase;
```

For more information about auditing, see *Security Administration Guide > Auditing*.

## Related Information

[alter database \[page 14\]](#)  
[alter table \[page 70\]](#)  
[create database \[page 140\]](#)  
[create default \[page 158\]](#)  
[create index \[page 192\]](#)  
[create table \[page 273\]](#)  
[disk init \[page 401\]](#)  
[disk refit \[page 413\]](#)  
[disk reinit \[page 415\]](#)  
[disk remirror \[page 420\]](#)  
[disk unmirror \[page 425\]](#)  
[drop trigger \[page 462\]](#)  
[grant \[page 520\]](#)  
[load database \[page 585\]](#)  
[load transaction \[page 603\]](#)  
[revoke \[page 672\]](#)  
[rollback trigger \[page 692\]](#)  
[select \[page 696\]](#)  
[set \[page 732\]](#)  
[truncate table \[page 809\]](#)  
[update statistics \[page 839\]](#)

## 1.44.1 Triggers and Referential Integrity

Triggers are commonly used to enforce referential integrity (integrity rules about relationships between the primary and foreign keys of tables or views), and to supply cascading deletes and updates.

A trigger fires only after the data modification statement has completed and the SAP ASE server has checked for any datatype, rule, or integrity constraint violations. The trigger and the statement that fires it are treated as a single transaction that can be rolled back from within the trigger. If a severe error is detected, the entire transaction is rolled back.

You can also enforce referential integrity using constraints defined with the `create table` statement as an alternative to using `create trigger`. See `create table` and `alter table` for information about integrity constraints.

## 1.44.2 The deleted and inserted Logical Tables

`deleted` and `inserted` are logical (conceptual) tables. They are structurally identical to the table for which the trigger is defined—that is, the table on which the user action is attempted—and hold the old values or new values of the rows that would be changed by the user action.

### i Note

Both `inserted` and `deleted` tables appear as views on the transaction log, but they are fake tables on `syslogs`.

`deleted` and `inserted` tables can be examined by the trigger to determine whether or how the trigger action should be carried out, but the tables themselves cannot be altered by the trigger's actions.

`deleted` tables are used with `delete` and `update`; `inserted` tables, with `insert` and `update`. An update is a `delete` followed by an `insert`: it affects the `deleted` table first, and then the `inserted` table.

## 1.44.3 Trigger Restrictions

Restrictions for using triggers.

- You can create a trigger only in the current database. If you use an owner name to qualify a trigger, you must explicitly qualify the table name the same way. A trigger can reference objects outside the current database.
- A trigger cannot apply to more than one table. However, the same trigger action can be defined for more than one user action (for example, `insert` and `update`) in the same `create trigger` statement. A table can have a maximum of three triggers—one each for `insert`, `update`, and `delete`.
- Each new trigger in a table or column for the same operation (`insert`, `update`, or `delete`) overwrites the previous one. No warning message appears before the previous trigger is overwritten.
- You cannot create a trigger on a session-specific temporary table.
- You cannot create a trigger on a view.

- You cannot create a trigger on a system table.
- You cannot use triggers that select from a `text`, `unitext`, or `image` column of the inserted or deleted table.
- Triggers should not include `select` statements that return results to the user, since special handling that allows modifications to the trigger table must be written into every application program for the returned results.
- If a trigger references table names, column names, or view names that are not valid identifiers, you must `set quoted_identifier on` before the `create trigger` command, and enclose each such name in double quotes. The `quoted_identifier` option does not need to be on when the trigger fires.

## 1.44.4 Triggers and Performance

In performance terms, trigger overhead is usually very low. The time involved in running a trigger is spent mostly in referencing other tables, which are either in memory or on the database device.

The `deleted` and `inserted` tables often referenced by triggers are always in memory rather than on the database device, because they are logical tables. The location of other tables referenced by the trigger determines the amount of time the operation takes.

## 1.44.5 Setting Options Within Triggers

You can use the `set` command inside a trigger. The `set` option you invoke remains in effect during the execution of the trigger, then reverts to its former setting. In particular, you can use the `self_recursion` option inside a trigger so that data modifications by the trigger itself can cause the trigger to fire again.

## 1.44.6 Dropping a Trigger

You must drop and re-create the trigger if you rename any of the objects referenced by the trigger.

You can rename a trigger with `sp_rename`.

When you drop a table, any triggers associated with it are also dropped.

## 1.44.7 Actions That Do Not Cause Triggers to Fire

A `truncate table` command is not caught by a `delete` trigger.

Although a `truncate table` statement is, in effect, like a `delete` without a `where` clause (it removes all rows), changes to the data rows are not logged, and so cannot fire a trigger.

Since permission for the `truncate table` command defaults to the table owner and is not transferable, only the table owner need worry about inadvertently circumventing a `delete` trigger with a `truncate table` statement.

The `writetext` command, whether logged or unlogged, does not cause a trigger to fire.

## 1.44.8 Nesting Triggers and Trigger Recursion

By default, the SAP ASE server allows nested triggers.

- To prevent triggers from nesting, use `sp_configure` to set the `allow nested triggers` option to 0 (off):

```
sp_configure "allow nested triggers", 0
```

- Triggers can be nested to a depth of 16 levels. If a trigger changes a table on which there is another trigger, the second trigger fires and can then call a third trigger, and so forth. If any trigger in the chain sets off an infinite loop, the nesting level is exceeded and the trigger aborts, rolling back the transaction that contains the trigger query.

### Note

Since triggers are put into a transaction, a failure at any level of a set of nested triggers cancels the entire transaction: all data modifications are rolled back. Supply your triggers with messages and other error handling and debugging aids to determine where the failure occurred.

- The global variable `<@@nestlevel>` contains the nesting level of the current execution. Each time a stored procedure or trigger calls another stored procedure or trigger, the nesting level is incremented. The nesting level is also incremented by one when a cached statement is created. If the maximum of 16 is exceeded, the transaction aborts.
- If a trigger calls a stored procedure that performs actions that would cause the trigger to fire again, the trigger is reactivated only if nested triggers are enabled. Unless there are conditions within the trigger that limit the number of recursions, this causes a nesting-level overflow.  
For example, if an update trigger calls a stored procedure that performs an update, the trigger and stored procedure execute once if `allow nested triggers` is off. If `allow nested triggers` is on, and the number of updates is not limited by a condition in the trigger or procedure, the procedure or trigger loop continues until it exceeds the 16-level maximum nesting value.
- By default, a trigger does not call itself in response to a second data modification to the same table within the trigger, regardless of the setting of the `allow nested triggers` configuration parameter. A `set` option, `self_recursion`, enables a trigger to fire again as a result of a data modification within the trigger. For example, if an update trigger on one column of a table results in an update to another column, the update trigger fires only once when `self_recursion` is disabled, but it can fire up to 16 times if `self_recursion` is set on. The `allow nested triggers` configuration parameter must also be enabled in order for self-recursion to take place.

## 1.44.9 Restrictions for instead of

Restrictions for using `instead of` triggers.

- If a trigger references table names, column names, or view names that are not valid identifiers, you must set `quoted_identifier` on before the `create trigger` command, and enclose each such name in double quotation marks. The `quoted_identifier` option does not need to be on when the trigger fires; bracketed identifiers also work.
- Using the `set cursor rows` command with client cursors, cursors declared through Open Client calls, or Embedded SQL™, may prevent positioned `delete` and `update` from firing an `instead of` trigger. A positioned update statement is a SQL `update` statement that contains the `where current of <<cursorname>>` clause to update only the row upon which the cursor, `<<cursorname>>`, is currently positioned.
- Joins are not allowed in searched `delete` and `update` statements that would fire an `instead of` trigger.
- positioned `delete` and `update` on cursors defined with joins does not fire an `instead of` trigger. A positioned `delete` (or positioned `update`) is a SQL `delete` (or `update`) statement containing a `where current of <<cursorname>>` clause to delete (or update) only the row upon which the cursor, `<<cursorname>>`, is currently positioned.
- For positioned `delete` and `update` statements that fire an `instead of` trigger, the `instead of` trigger must exist when the cursor is declared.

## 1.44.10 Getting Information About Triggers

Get information about working with triggers.

- The execution plan for a trigger is stored in `sysprocedures`.
- Each trigger is assigned an identification number, which is stored as a new row in `sysobjects` with the object ID for the table to which it applies in the `deltrig` column, and also as an entry in the `deltrig`, `instrig`, and `updtrig` columns of the `sysobjects` row for the table to which it applies.
- Use `sp_helptext` to display the text of a trigger, which is stored in `syscomments`. If the system security officer has reset the `allow select on syscomments.text` column parameter with `sp_configure` (as required to run the SAP ASE server in the evaluated configuration), you must be the creator of the trigger or a system administrator to view the text of the trigger through `sp_helptext`.
- For a report on a trigger, use `sp_help`.
- For a report on the tables and views that are referenced by a trigger, use `sp_depends`.

## 1.44.11 Triggers and Transactions

When a trigger is defined, the action it specifies on the table to which it applies is always implicitly part of a transaction, along with the trigger itself.

Triggers are often used to roll back an entire transaction if an error is detected, or they can be used to roll back the effects of a specific data modification:

- When the trigger contains the `rollback transaction` command, the rollback aborts the entire batch, and any subsequent statements in the batch are not executed.
- When the trigger contains the `rollback trigger`, the rollback affects only the data modification that caused the trigger to fire. The `rollback trigger` command can include a `raiserror` statement. Subsequent statements in the batch are executed.

Since triggers execute as part of a transaction, the following statements and system procedures are not allowed in a trigger:

- All `create` commands, including `create database`, `create default`, `create index`, `create procedure`, `create rule`, `create table`, `create trigger`, and `create view`
- All `drop` commands
- `alter database` and `alter table`
- `truncate table`
- `grant` and `revoke`
- `update statistics`
- `sp_configure`
- `load database` and `load transaction`
- `disk init`, `disk refit`, `disk reinit`, `disk remirror`, `disk unmirror`
- `select into`

If a desired result (such as a summary value) depends on the number of rows affected by a data modification, use `<@@rowcount>` to test for multirow data modifications (an `insert`, `delete`, or `update` based on a `select` statement), and take appropriate actions. Any Transact-SQL statement that does not return rows (such as an `if` statement) sets `<@@rowcount>` to 0, so the test of `<@@rowcount>` should occur at the beginning of the trigger.

## 1.44.12 Inserting and Updating Triggers

When an `insert` or `update` command executes, the SAP ASE server simultaneously adds rows to both the trigger table and the inserted table. The rows in the inserted table are always duplicates of one or more rows in the trigger table.

An `update` or `insert` trigger can use the `if update` command to determine whether the `update` or `insert` changed a particular column. `if update (<column_name>)` is true for an `insert` statement whenever the column is assigned a value in the `select` list or in the `values` clause. An explicit `NULL` or a default assigns a value to a column and thus activates the trigger. An implicit `NULL`, however, does not.

For example, if you create the following table and trigger:

```
create table junk
  (aaa int null,
   bbb int not null)
```

```
create trigger trigtest on junk
for insert as
if update (aaa)
  print "aaa updated"
if update (bbb)
  print "bbb updated"
```

Inserting values into either column or into both columns fires the trigger for both column `aaa` and column `bbb`:

```
insert junk (aaa, bbb)
values (1, 2)
```

```
aaa updated
bbb updated
```

Inserting an explicit `NULL` into column `aaa` also fires the trigger:

```
insert junk
values (NULL, 2)
```

```
aaa updated
bbb updated
```

If there was a default for column `aaa`, the trigger would also fire.

However, with no default for column `aaa` and no value explicitly inserted, the SAP ASE server generates an implicit `NULL` and the trigger does not fire:

```
insert junk (bbb)
values (2)
```

```
bbb updated
```

`if update` is never true for a `delete` statement.

## 1.44.13 `instead of` and `for` Triggers

You can interleave nesting `instead of` and `for` triggers.

For example, an `update` statement on a view with an `instead of update` trigger causes the trigger to execute. If the trigger contains a SQL statement updating a table with a `for` trigger defined on it, that trigger fires. The `for` trigger may contain a SQL statement that updates another view with an `instead of` trigger that then executes, and so forth.

`instead of` and `for` triggers have different recursive behaviors. `for` triggers support recursion, while `instead of` triggers do not. If an `instead of` trigger references the same view on which the trigger was fired, the trigger is not called recursively. Rather, the triggering statement applies directly to the view; in other words, the statement is resolved as modifications against the base tables underlying the view. In this case, the view definition must meet all restrictions for an updatable view. If the view is not updatable, an error is raised.

For example, if a trigger is defined as an `instead of update` trigger for a view, the `update` statement executed against the same view within the `instead of` trigger does not cause the trigger to execute again. The update exercised by the trigger is processed against the view, as though the view did not have an `instead of` trigger. The columns changed by the update must be resolved to a single base table.



## 1.45 create type

Creates a user-defined table type.

Use `drop type` to remove a table type. See [drop type \[page 464\]](#).

### Syntax

```
create type <type_name> as table ( {<column_name> <datatype> [{ null | not  
null }]} [ ,...n ] )
```

### Parameters

#### <type\_name>

is the name of the user-defined table type. Type names:

- Must conform to the rules for identifiers.
- Must be unique for each database. Since structurally a type object is table, type name cannot be the same as a name of an existing table.
- Cannot start with @ or #.
- Must be 255 characters or less.

#### <column\_name>

is the name of a column in the table type. It must be unique for a given table type.

#### <datatype>

is the datatype of the column. System or user-defined datatypes are acceptable, with an exception of the "table type" datatype. Note that certain datatypes expect a length or precision and scale, in parentheses. See "Datatypes" in *Transact-SQL Users Guide*.

### Examples

#### Example 1

Declares two variables and prints strings according to the values in the variables:

```
CREATE TYPE tab_type AS TABLE (c1 INT, c2 VARCHAR)  
CREATE PROCEDURE test_table (@tab tab_type)  
AS  
BEGIN  
SELECT * FROM @tab  
END  
DECLARE @tab1 tab_type  
INSERT INTO @tab1 VALUES (1, 'a')  
exec test_table @tab1
```

```
go
(1 row affected)
c1          c2
-----
          1 a
(1 row affected)
```

## Usage

- You cannot run DML statements on a table type object.
- You cannot define a regular table using `create type`.
- You cannot create an execute statement that includes output with a table type parameter or table variable.

## Permissions

`create type` command is available to all users. Permission checks do not differ based on the granular permissions settings.

## Auditing

This command is not audited.

## Related Information

[drop type \[page 464\]](#)

[drop type \[page 464\]](#)

## 1.46 create view

Creates or replaces a view, which is an alternative way to look at the data in one or more tables.

## Syntax

```
create [or replace] view [<owner>.<view_name>
[(<column_name>[, <column_name>]...)]
```

```
as
select [distinct] <select_statement>
[with check option]
```

## Parameters

### **create**

creates a view if one does not already exist.

### **or replace**

replaces an existing view definition without changing any of a view's security attributes.

### **<view\_name>**

is the name of the view. The name cannot include the database name. If you have `set quoted_identifier on`, you can use a delimited identifier. Otherwise, the view name cannot be a variable and must conform to the rules for identifiers. Specify the owner's name to create another view of the same name owned by a different user in the current database. The default value for `<owner>` is the current user.

Only an existing view can be replaced. The object name and ID remain the same.

### **<column\_name>**

specifies names to be used as headings for the columns in the view. If you have `set quoted_identifier on`, you can use a delimited identifier. Otherwise, the column name must conform to the rules for identifiers.

You can always supply column names, but they are required only on:

- A column is derived from an arithmetic expression, function, string concatenation, or constant
- Two or more columns have the same name (usually because of a join)
- You want to give a column in a view a different name than the column from which it is derived (see Example 3)

Column names can also be assigned in the `select` statement (see Example 4). If no column names are specified, the view columns acquire the same names as the columns in the `select` statement.

With the `or replace` clause, you can change column names for the view as follows:

- If the previous definition of the view contained headings for column names, then the new definition of the view can omit the headings, or have different headings for column names.
- If the previous definition of the view did not contain headings for column names, the new definition can contain headings for the view column names.
- You can change the number of column headings according to the column names in the `select_statement`.

### **select**

begins the `select` statement that defines the view.

### **distinct**

specifies that the view cannot contain duplicate rows.

If the original definition of the view did not specify `distinct` clause, you can change this parameter so the new view cannot contain duplicate rows.

#### <select\_statement>

completes the `select` statement that defines the view. The `select` statement can use more than one table, and other views.

The columns specified in the target list of the `select_statement` of the replaced view can be changed to drop or add columns.

#### with check option

indicates that all data modification statements are validated against the view selection criteria. All rows inserted or updated through the view must remain visible through the view. If you create a view using `with check option`:

- Each row that is inserted or updated through the view must meet the selection criteria of the view.
- All views derived from the "base" view must satisfy its check option. Each row inserted or updated through the derived view must remain visible through the base view.

A view created with the `with check option` clause can be replaced without this clause, and vice versa.

## Examples

### Example 1

Creates a view derived from the `title`, `type`, `price`, and `pubdate` columns of the base table `titles`:

```
create view titles_view
as select title, type, price, pubdate
from titles
```

### Example 2

Creates "new view" from "old view." Both columns are renamed in the new view. All view and column names that include embedded blanks are enclosed in double quotation marks. Before creating the view, you must use `set quoted_identifier on`.

```
create view "new view" ("column 1", "column 2")
as select col1, col2 from "old view"
```

### Example 3

Creates a view that contains the titles, advances, and amounts due for books that have a price less than \$5.00:

```
create view accounts (title, advance, amt_due)
as select title, advance, price * total_sales
from titles
where price > $5
```

#### Example 4

Creates a view derived from two base tables, `authors` and `publishers`. The view contains the names and cities of authors who live in a city in which there is a publisher:

```
create view cities
  (authorname, acity, publishername, pcity)
as select au_lname, authors.city, pub_name,
publishers.city
from authors, publishers
where authors.city = publishers.city
```

#### Example 5

Creates a view with the same definition as in the previous example, but with column headings included in the `select` statement:

```
create view cities2
as select authorname = au_lname,
acity = authors.city, publishername = pub_name, pcity = publishers.city
from authors, publishers
where authors.city = publishers.city
```

#### Example 6

Creates a view, `author_codes`, derived from `titleauthor` that lists the unique author identification codes:

```
create view author_codes
as select distinct au_id
from titleauthor
```

#### Example 7

Creates a view, `price_list`, derived from `titles` that lists the unique book prices:

```
create view price_list (price)
as select distinct price
from titles
```

#### Example 8

Creates a view of the `stores` table that excludes information about stores outside of California. The `with check option` clause validates each inserted or updated row against the view's selection criteria. Rows for which `state` has a value other than "CA" are rejected:

```
create view stores_cal
as select * from stores
where state = "CA"
with check option
```

#### Example 9

Creates a view, `stores_cal30`, which is derived from `stores_cal`. The new view inherits the `check option` from `stores_cal`. All rows inserted or updated through `stores_cal30` must have a `state` value of "CA". Because `stores_cal30` has no `with check option` clause, you can insert or update rows through `stores_cal30` for which `payterms` has a value other than "Net 30":

```
create view stores_cal30
as select * from stores_cal
where payterms = "Net 30"
```

### Example 10

Creates a view, `stores_cal30_check`, derived from `stores_cal`. The new view inherits the check option from `stores_cal`. It also has a `with check option` clause of its own. Each row that is inserted or updated through `stores_cal30_check` is validated against the selection criteria of both `stores_cal` and `stores_cal30_check`. Rows with a `state` value other than "CA" or a `payterms` value other than "Net 30" are rejected:

```
create view stores_cal30_check
as select * from stores_cal
where payterms = "Net 30"
with check option
```

### Example 11

Uses a SQL-derived table in creating a view:

```
create view psych_titles as
select *
from (select * from titles
      where type = "psychology") dt_psych
```

### Example 12

Based on the view `Current_Product_List`, which lists all active products from the table `Products`. The view is defined as:

```
create view Current_Product_List as
select ProductID, ProductName
from Products
where Discontinued = "No"
select object_id("Current_Product_List")
-----
889051172
```

This next command adds the `Category` column to `Current_Product_list` using the `or replace` clause. The object ID of the view remains the same:

```
create or replace view Current_Product_List as
select ProductID, ProductName, Category
from Products
where Discontinued = "No"
select object_id("Current_Product_List")
-----
889051172
```

### Example 13

Replaces `V1`—a view that has dependent objects:

```
create table T1(C1 int, C2 int)
create table T2(C1 int, C2 int)

create view V1 as select * from T1
create view V2 as select * from V1

create function fool
returns int
as
begin
    declare @number int
    select @number = C1 from V2
end
```

```
return @number
select object_id("V1")
-----
985051514
```

```
create or replace V1 as select * from T2
select * from V2
select dbo.foo1()
select object_id("V1")
-----
985051514
```

The replaced version of `V1` references `T2` instead of `T1`. Both `V2` and `foo1` will be recompiled. `select * from V2` recompiles `V2`, but not `foo1`, which is recompiled when the UDF is invoked.

## Usage

- You can use views as security mechanisms by granting permission on a view, but not on its underlying tables.
- You can use `sp_rename` to rename a view.
- When you query through a view, the SAP ASE server checks to make sure that all the database objects referenced anywhere in the statement exist, that they are valid in the context of the statement, and that data update commands do not violate data integrity rules. If any of these checks fail, you see an error message. If the checks are successful, `create view` "translates" the view into an action on the underlying tables.
- For more information about views, see the *Transact-SQL Users Guide*.

For getting information about views:

- To create a report of the tables or views on which a view depends, and of objects that depend on a view, execute `sp_depends`.
- To display the text of a view, which is stored in `syscomments`, execute `sp_helptext` with the view name as the parameter.

See also:

- *Identifiers in Reference Manual: Building Blocks*
- `sp_depends`, `sp_help`, `sp_helptext`, `sp_rename` in *Reference Manual: Procedures*

## Standards

ANSI SQL – Compliance level: Entry-level compliant.

The use of more than one `distinct` keyword and the use of "`<column_heading> = <column_name>`" in the `select` list are Transact-SQL extensions.

## Permissions

When you create a view, the SAP ASE server makes no permission checks on objects, such as tables and views, that are referenced by the view. Therefore, you can create successfully a view even if you do not have access to its objects. All permission checks occur when a user invokes the view.

When a view is invoked, permission checks on its objects depend on whether the view and all referenced objects are owned by the same user.

- If the view and its objects are not owned by the same user, the invoker must have been granted direct access to the objects. For example, if the view performs a `select` from a table the invoker cannot access, the `select` statement fails.
- If the view and its objects are owned by the same user, special rules apply. The invoker automatically has implicit permission to access the view's objects even though the invoker could not access them directly. Without having to grant users direct access to your tables, you can give them restricted access with a view. In this way, a view can be a security mechanism. For example, invokers of the view might be able to access only certain rows and columns of your table. A detailed description of the rules for implicit permissions is discussed in the *System Administration Guide*.
- If a column in the table is encrypted, you must have decrypt permission to select from the view. If the view and its objects are not owned by the same user, you must have decrypt permission on the encrypted column in the table to select from the view. If the view and its objects are owned by the same user, it is sufficient to grant decrypt permission to the user who must select from the view on the view column that corresponds to the encrypted column in the table.

Setting	Description
---------	-------------

<b>Enabled</b>	With granular permission enabled, you must have the <code>create view</code> privilege to create a view. To create a view for another user, you must have the <code>create any view</code> privilege.
----------------	---

To replace the view, you must be the view owner. Any user who impersonates the view owner through an alias or `setuser` cannot replace the view.

<b>Disabled</b>	With granular permissions disabled, you must be the database owner, a user with <code>sa_role</code> , or have the <code>create view</code> privilege to create a view. To create a view for another user, you must have <code>sa_role</code> .
-----------------	---

To replace the view, you must be the view owner, or have `sa_role`. Any user who impersonates the view owner through an alias or `setuser` cannot replace the view unless the user has `sa_role`.

## Auditing

You can enable `create` auditing option to audit this command. Values in `event` and `extrainfo` columns from the `sysaudits` table are:

Information	Value
Audit option	<code>create</code>
Event	16



Information	Value
Command or access audited	<code>create view</code>
Information in <code>extrainfo</code>	<ul style="list-style-type: none"> <li>• <b>Roles</b> – current active roles</li> <li>• <b>Full command text</b> – full text of <code>create view</code> command</li> <li>• <b>Previous value</b> – NULL</li> <li>• <b>Current value</b> – NULL</li> <li>• <b>Other information</b> – NULL</li> <li>• <b>Proxy information</b> – original login name, if <code>set proxy</code> is in effect</li> </ul>

Full command text is included in `extrainfo`. For example:

```
sa_role sso_role oper_role sybase_ts_role mon_role;
create view titles_view as select title, type, price,
pubdate from titles; ; ; ; ; sa/ase;
```

For more information about auditing, see *Security Administration Guide > Auditing*.

## Related Information

[create schema \[page 265\]](#)

[drop view \[page 466\]](#)

[group by and having Clauses \[page 558\]](#)

[select \[page 696\]](#)

[set \[page 732\]](#)

[update \[page 819\]](#)

### 1.46.1 Restrictions on Views

Restrictions for using views.

- You can create a view only in the current database.
- The number of columns referenced by a view cannot exceed 1024.
- You cannot create a view on a temporary table.
- You cannot create a trigger or build an index on a view.
- You cannot use `readtext` or `writetext` on `text`, `unitext`, or `image` columns in views.
- You cannot include `order by`, `compute` clauses, or the keyword `into` in the `select` statements that define views.
- You cannot update, insert, or delete from a view with `select` statements that include the `union` operator.
- If you create a view using a local or a global variable, the SAP ASE server issues error message 7351: "Local or global variables not allowed in view definition."
- You can combine `create view` statements with other SQL statements in a single batch.

### ⚠ Caution

When a `create view` command occurs within an `if...else` block or a `while` loop, the SAP ASE server creates the schema for the view before determining whether the condition is true. This may lead to errors if the view already exists. To avoid this, verify that a view with the same name does not already exist in the database or use an `execute` statement, as follows:

```
if not exists
    (select * from sysobjects where name="mytable")
begin
    execute ("create table mytable (x int)")
end
```

## 1.46.2 View Resolution

If you alter the structure of a view's underlying tables by adding or deleting columns, the new columns do not appear in a view that is defined using the `select *` clause unless you drop, and then redefine the view. The asterisk shorthand is interpreted and expanded when the view is first created.

If a view depends on a table or view that has been dropped, the SAP ASE server produces an error message when anyone tries to use the view. If a new table or view with the same name and schema is created to replace the one that has been dropped, the view again becomes usable.

You can redefine a view without redefining other views that depend on it, unless the redefinition makes it impossible for the SAP ASE server to translate any dependent views.

## 1.46.3 Modifying Data Through Views

Usage information for modifying data through views.

- `delete` statements are not allowed on multitable views.
- `insert` statements are not allowed unless all `not null` columns in the underlying table or view are included in the view through which you are inserting new rows. The SAP ASE server cannot supply values for `not null` columns in the underlying table or view.
- You cannot insert directly to a computed column through a view. The value of computed columns can only be generated internally by the SAP ASE server.
- `insert` statements are not allowed on join views created with `distinct` or with `check option`.
- `update` statements are allowed on join views with `check option`. The update fails if any of the affected columns appear in the `where` clause, in an expression that includes columns from more than one table.
- If you insert or update a row through a join view, all affected columns must belong to the same base table.
- You cannot update or insert into a view defined with the `distinct` clause.
- Data update statements cannot change any column in a view that is a computation, and cannot change a view that includes aggregates.

## 1.46.4 IDENTITY Columns and Views

To insert an explicit value into an IDENTITY column, the table owner, database owner, or system administrator must set `identity_insert <table_name> on` for the column's base table, not through the view through which it is being inserted.

You cannot use the `<column_name> = identity (<precision>)` syntax to add a new IDENTITY column to a view.

## 1.46.5 group by Clauses and Views

When creating a view for security reasons, be careful when using aggregate functions and the `group by` clause.

A Transact-SQL extension allows you to name columns that do not appear in the `group by` clause. If you name a column that is not in the `group by` clause, the SAP ASE server returns detailed data rows for the column. For example, this Transact-SQL extended column query returns a row for every 18 rows—more data than you might intend:

```
select title_id, type, sum (total_sales)
from titles
group by type
```

While this ANSI-compliant query returns one row for each type (6 rows):

```
select type, sum (total_sales)
from titles
group by type
```

## 1.46.6 distinct Clauses and Views

The `distinct` clause defines a view as a database object that contains no duplicate rows. A row is defined to be a duplicate of another row if all of its column values match the same column values in another row. Null values are considered to be duplicates of other null values.

Querying a subset of a view's columns can result in what appear to be duplicate rows. If you select a subset of columns, some of which contain the same values, the results appear to contain duplicate rows. However, the underlying rows in the view are still unique. The SAP ASE server applies the `distinct` requirement to the view's definition when it accesses the view for the first time (before it does any projection and selection) so that all the view's rows are distinct from each other.

You can specify `distinct` more than once in the view definition's `select` statement to eliminate duplicate rows, as part of an aggregate function or a `group by` clause. For example:

```
select distinct count (distinct title_id), price
from titles
```

The scope of `distinct` applies only for that view; it does not cover any new views derived from the `distinct` view.

## 1.46.7 Creating Views from SQL-Derived Tables

To create a view using a SQL-derived table, add the derived table expression in the `from` clause of the `select` part of the `create view` statement.

A view created using a SQL-derived table can be updated if the derived table expression can be updated. The update rules for the derived table expression follow the update rules for the `select` part of the `create view` statement.

Data can be inserted through a view that contains a SQL-derived table if the `insert` rules and permission settings for the derived table expression follow the `insert` rules and permission settings for the `select` part of the `create view` statement.

Temporary tables and local variables are not permitted in a derived table expression that is part of a `create view` statement.

SQL-derived tables cannot have unnamed columns.

For more information about derived table expressions, see the *Transact-SQL Users Guide*.

## 1.46.8 Objects Dependent on Replaced Views

Views can be contained in other object definitions.

- If the view that is replaced is contained in another view, the parent view is automatically recompiled when it is accessed.
- If the number of columns in a view changes due to replacing, you may need to fix the definitions of other views and procedures that reference this view.

In this situation, the owner has replaced `v1` with different number of columns and column names. `P` must also be replaced.

```
create view V1 as select C1 from T1
create procedure P as select * from V1
```

```
create or replace V1 as select C1, C2 from T1
```

In this next situation, the owner has replaced `V2` by removing `C2` from the definition. When `P` is executed, an error is raised, as `C2` is no longer part of `V2`. Because of this, `P` must be replaced.

```
create view V2 as select C1, C2 from T2
create procedure P as select C2 from V2
```

```
create or replace V2 as select C1 from T2
```

Before you replace a view, run `sp_depends` to determine if there are any stored procedures or parent views that depend on the view you are replacing. If such stored procedures or parent views exist, replace the stored procedures or parent views as necessary after replacing the view.

- `Instead of` triggers defined on the view are dropped when the view is replaced
- Any PRS that are dependent on the replaced view will require a full refresh to restore them to a usable state. You can neither refresh them, nor use them for query rewrite until they are recompiled.

## 1.47 dbcc

Database consistency checker (`dbcc`) checks the logical and physical consistency of a database and provides statistics, planning, and repair functionality.

Certain `dbcc` commands apply only to shared-disk clusters. See the separately listed `dbcc` syntax for clusters.

The sections that describe this command are:

- [Syntax \[page 349\]](#)
- [Parameters \[page 351\]](#)
- [Examples \[page 361\]](#)
- [Usage \[page 369\]](#)
- [Standards \[page 371\]](#)
- [Permissions \[page 371\]](#)
- [Auditing \[page 373\]](#)

### Syntax

- `dbcc addtempdb (<dbid> | <database_name>)`
- `dbcc checkalloc [( <database_name> [, fix | nofix | fixdbid ] )]`
- `dbcc checkcatalog [( <database_name> [, fix ] )]`
- `dbcc checkdb [( <dbid> | <database_name> [, "skip_tables_with_no_text" ] )]`
- `dbcc checkindex ( { <table_name> | <table_id> } , <index_id> [, bottom_up [, <partition_name> | <partition_id> ] ] )`
- `dbcc checkstorage [( <database_name> )]`
- `dbcc checktable ( <table_name> | <table_id> [, skip_ncindex | fix_spacebits | "check spacebits" | bottom_up | NULL [, <partition_name> | <partition_id> ] )`
- `dbcc checkverify ( <dbname> [, <tblname> [, <ignore_exclusions> ] ] )`
- `dbcc complete_xact ( <xid> , { [ "commit", "lpc" ] | "rollback" } )`
- `dbcc dbrepair ( <database_name> , dropdb, flushthreshold, redo_shrink )`
- `dbcc engine ( { offline, [ <enginenum> ] | "online" } )`
- `dbcc fix_text ( { <table_name> | <table_id> } )`
- `dbcc forget_xact ( <xid> )`
- `dbcc hcb ( <action> [, <component> , [ <database_ID> | <database_name> ] [, <option> [, <parameter> , <parameter> , <parameter> , <parameter> ] ] ] )`

- `dbcc hotbufs([<cache_ID>] [,<count>] [,<order>] [,<level>])`
- `dbcc indexalloc (<table_name> | <table_id>, <index_id>  
[, optimized | fast | NULL [, fix | nofix | NULL  
[, <partition_name> | <partition_id>]]])`
- `dbcc monitor ((increment | decrement | reset), <group_name>)`
- `dbcc pravailabletempdbs`
- `dbcc purgelobvers(<dbname> | <database_ID> [, <object_name> | <object_ID> [,  
<mode> ]])`
- `dbcc rebuild_text (<table_name> | <table_id><text_page>  
[, <data_partition_name> | <data_partition_id>]]])`
- `dbcc reindex ((<table_name> | <table_id>))`
- `dbcc serverlimits`
- `dbcc showrecovery('database_name')`
- `dbcc shrinkdb_setup(<dbname>[, <object_name>[, force [, verbose]])`
- `dbcc stackused`
- `dbcc tablealloc (<table_name> | <table_id>  
[, full | optimized | fast | NULL [, fix | nofix | NULL [,  
<data_partition_name> | <data_partition_id> | "all" ]]])`
- `dbcc textalloc ("ALL" | <table_name> | <table_id>  
[, full | optimized | fast | NULL[, fix | nofix | NULL]])`
- `dbcc textalloc (<table_name> | <table_id>  
[, full | optimized | fast | NULL[, fix | nofix | NULL  
[, <data_partition_name> | <data_partition_id>]]])`
- `dbcc {traceon | traceoff} (<flag >[, flag ...])`
- `dbcc tune ({ascinserts, {0 | 1}, <table_name> | cleanup, {0 | 1}  
| cpuaffinity, <start_cpu>{, on | off} | des_greedyalloc, <dbid>,  
<object_name>, "{on | off}" | deviochar vdevno, "<batch_size>"  
| des_bind, <dbid>, <object_name>  
des_unbind, <dbid>, <object_name>  
doneinproc {0 | 1}})`
- `dbcc upgrade_object [(<dbid> | <dbname>  
[, [<database>.[<owner>].<compiled_object_name>' |  
'check' | 'default' | 'procedure' | 'rule' | 'trigger' | 'view'  
[, 'force' | 'check']])`
- `dbcc zapdefraginfo(<dbid> | <dbname>, <objid> | <objname>  
[, <indexid> | <indexname>[, <ptnid> | <ptnname> | 0, ['print' | 'zap'  
| 'zap_no_log']]])`

dbcc syntax for clusters only:

- `dbcc nodetraceon(<trace_flag_number>)`

- `dbcc nodetraceoff(<trace_flag_number>)`
- `dbcc set_scope_in_cluster("cluster" | "instance" | "scope")`
- `dbcc quorum`

## Parameters

### **addtempdb**

adds a temporary database to the global list of available temporary databases. If the database does not exist or is not a temporary database, an error is generated. If the database is already a member of the list, an informational message prints.

#### **<dbid>**

is the database ID.

#### **<database\_name>**

is the name of the database to check. If no database name is given, `dbcc` uses the current database.

### **checkalloc**

checks the specified database to see that all pages are correctly allocated and that no page that is allocated is not used. If no database name is given, `checkalloc` checks the current database. It always uses the `optimized` report option (see `tablealloc`).

`checkalloc` reports on the amount of space allocated and used.

#### **fix | nofix**

determines whether `dbcc` fixes the allocation errors found. The default mode for `checkalloc` is `nofix`. You must put the database into single-user mode to use the `fix` option. For details on page allocation in SAP ASE servers, see the *System Administration Guide*. `fix` is not supported for IMRS-enabled databases.

### **fixdbid**

runs a minimal check in the database and fixes any mismatch of database IDs. The database ID is stored in the allocation pages of the database and remains unchanged if you change the `dbid` of the database when you mount it onto a server. The `fixdbid` option runs a check on the database and will fix any possible database ID mismatch for all allocation pages.

### **checkcatalog**

checks for consistency in and between system tables. For example, `checkcatalog` makes sure that every type in `syscolumns` has a matching entry in `sysypes`, that every table and view in `sysobjects` has at least one column in `syscolumns`, and that the last checkpoint in `syslogs` is valid. You can use `checkcatalog` in an archive database, but not the `fix` version of `checkcatalog`.

`checkcatalog` also reports on any segments that have been defined. If no database name is given, `checkcatalog` checks the current database.

### **fix**

determines whether `dbcc` fixes the `sysindexes` errors it finds. The default mode for `checkcatalog` is to not fix the errors. You must put the database into singleuser mode to use the `fix` option. The new `sysindexes` checks may result in new errors, not raised by `dbcc checkcatalog`, in SAP ASE servers earlier than version 12.5.2.

#### **checkdb**

runs the same checks as `checktable`, but on each table, including `syslogs`, in the specified database. If no database name is given, `checkdb` checks the current database. You can use `checkdb` in an archive database.

#### **skip\_ncindex**

causes `dbcc checktable` or `dbcc checkdb` to skip checking the nonclustered indexes on user tables. The default is to check all indexes.

#### **skip\_tables\_with\_no\_text**

causes `dbcc checkdb` skips checking on tables that do not have text, unitext, or image columns. Only tables that have text and image columns are checked.

#### **checkindex**

runs the same checks as `checktable`, but only on the specified index. You can use `checkindex` in an archive database.

#### **bottom\_up**

(data-only-locked tables only) checks indexes in a bottom-up order when specifying this option with `checkindex`. The `bottom_up` check involves verifying whether each data row has a corresponding index row.

#### **<partition\_name> | <partition\_id>**

is the name or ID of the data partition to check. If you specify a partition, `dbcc` skips global indexes.

#### **checkstorage**

checks the specified database for allocation, object allocation map (OAM) page entries, page consistency, text valued columns, allocation of text valued columns, and text column chains. The results of each `dbcc checkstorage` operation are stored in the `dbccdb` database. `dbcc checkstorage` is not supported on in-memory row storage (IMRS)-enabled databases. For details on using `dbcc checkstorage`, and on creating, maintaining, and generating reports from `dbccdb`, see the *System Administration Guide: Volume 2 > Checking Database Consistency*.

#### **checktable**

checks the specified table to see that index and data pages are correctly linked, that indexes are in properly sorted order, that all pointers are consistent, that the data information on each page is reasonable, and that page offsets are reasonable. You can use `checktable` in an archive database.

Certain changes to `dbcc checktable` refer to virtually hashed tables. In addition to the regular checks it performs, `checktable` verifies that the layout of data and OAM pages in the hash region is correct:

- Data pages are not allocated in an extent reserved for OAM pages as per the layout.
- The OAM pages are allocated only in the first extent of an allocation unit.

#### **<table\_name> | <table\_id>**



is the name or object ID of the table to check.

#### **fix\_spacebits**

is for tables that use datapages or datarows locking, and checks for the validity of space bits and fixes any invalid space bits. Space bits are stored per page and indicate the room available in a page for new inserts.

#### **check\_spacebits**

checks space bits for tables that use datapages or datarows locking tables. If you specify `check_spacebits`, `dbcc` does not check nonclustered indexes.

#### **checkverify**

verifies the results of the most recent run of `dbcc checkstorage` for the specified database. `dbcc checkverify` is not supported on IMRS-enabled databases. For details on using `dbcc checkverify`, see the *System Administration Guide: Volume 2 > Checking Database Consistency*.

#### **<ignore\_exclusions>**

enables or disables the exclusion list. Value is either 0, the default (enables the exclusion list), or 1 (disables the exclusion list).

#### **complete\_xact**

heuristically completes a transaction by either committing or rolling back its work. The SAP ASE server retains information about all heuristically completed transactions in the `master.dbo.systransactions` table, so that the external transaction coordinator may have some knowledge of how the transaction was completed.

#### **⚠ Caution**

Heuristically completing a transaction in the prepared state can cause inconsistent results for an entire distributed transaction. The system administrator's decision to heuristically commit or roll back a transaction may contradict the decision made by the coordinating SAP ASE server or protocol.

#### **<xid>**

is a transaction name from the `systransactions.xactname` column. You can also determine valid `xid` values using `sp_transactions`.

#### **lpc**

heuristically completes a transaction that was subject to a one-phase commit protocol optimization—instead of the regular two-phase commit protocol—by the external transaction manager that was coordinating its completion. This option allows the heuristic commit of a transaction that was not in the prepared state.

#### **dbrepair (<database\_name>, dropdb, flushthreshold, redo\_shrink)**

- `<database_name>` – is the name of the database you are checking.
- `dropdb` – drops a damaged database (the `drop database` command does not work on a damaged database)
- `flushthreshold` – flushes the current value for the last-chance threshold to the `systhresholds` table
- `redo_shrink` – indicates that you are repairing a database that suffered an uncontrolled halt

No one can use the database being dropped when this `dbcc` statement is issued (including the user issuing the statement).

#### **engine**

takes the SAP ASE engines offline or brings them online. If `<enginenum>` is not specified, `dbcc engine (offline)` takes the highest-numbered engine offline. See *Managing Multiprocessor Servers* in the *System Administration Guide: Volume 2*.

#### **fix\_text**

upgrades `text` values after an SAP ASE character set has been changed from any character set to a new multibyte character set.

Changing to a multibyte character set makes the internal management of `text` data more complicated. Since a `text` value can be large enough to cover several pages, the SAP ASE server must be able to handle characters that span page boundaries. To do so, the server requires additional information on each of the `text` pages. The system administrator or table owner must run `dbcc fix_text` on each table that has `text` data to calculate the new values needed. See the *System Administration Guide: Volume 2 > Checking Database Consistency*.

#### **forget\_xact**

removes the completion status of a heuristically completed transaction from `master.dbo.systransactions`. `forget_xact` can be used when the system administrator does not want the coordinating service to have knowledge that a transaction was heuristically completed, or when an external coordinator is not available to clear commit status in `systransactions`.

#### **⚠ Caution**

Do not use `dbcc forget_xact` in a normal DTP environment, since the external transaction coordinator should be permitted to detect heuristically-completed transactions. X/Open XA-compliant transaction managers and the SAP ASE server transaction coordination services automatically clear the commit status in `systransactions`.

`hcb (<action> [, <component>, [<database_ID> | <database_name>][, <option> [, <parameter>, <parameter>, <parameter>, <parameter>]]]`

displays hash caching-related information.

- `<action>` – action to perform. One of:
  - `print` – displays information based on the `<component>` or `<option>` selections.
  - `help` – displays the `dbcc hcb` syntax.
  - `set` – changes values based on the `<component>` or `<option>` selections.
- `<component>` is one of:
  - `gc` – manages system hash cache B-tree index garbage collection tasks for the specific database, including displaying the information of garbage collection tasks, changing the number of garbage collection tasks, and so on.
  - `bucket` – prints hash-cache B-tree hash buckets, based on the object ID, index ID, partition ID and bucket number.

- `tune` – prints hash cache B-tree index auto tuning statistics and tuning decisions.
- `<database_ID> | <database_name>` – is the ID or name of the database you are investigating.
- `<option>` – specifies the valid option for the action-component combination. `<option>`'s validity depends on which `<action>` it is used with. One of:
  - `verbose` – displays full information about the index
  - `brief` – displays reduced information about the index
  - `task` – displays information about tasks, such as the HCB garbage collector tasks.
  - `queue` – displays information about queues, such as HCB garbage collection queues.
  - `diag` – displays diagnostic information.
- `<parameter>` – a combination of the `<component>` and `<action>` parameters.

### hotbufs

lists pages in the cache with high contention. `dbcc hotbufs` detects cache spinlock or buffer level spinlock contention based on which option you include. By default, `dbcc hotbufs` prints the top ten pages in contention.

```
dbcc hotbufs (<cache_ID>, <count>, <order> <level>)
```

#### <cache\_ID>

ID of the cache you are investigating. By default, `dbcc hotbufs` uses the default data cache (cache ID of 0).

#### <count>

number of hot buffers that are printed. The default is 10. The maximum number of hot buffers printed is 50.

#### <order>

order used for the result set: 0 for descending, 1 for ascending.

#### <level>

determines the level to print the buffers: 0 for cache-level, 1 for buffer-level.

### indexalloc

checks the specified index to see that all pages are correctly allocated and that no page that is allocated is not used. This is a smaller version of `checkalloc`, providing the same integrity checks on an individual index. You can use `indexalloc` in an archive database.

`indexalloc` produces the same three types of reports as `tablealloc`: `full`, `optimized`, and `fast`. If no type is indicated, or if you use `null`, the SAP ASE server uses `optimized`. The `fix | nofix` option functions the same with `indexalloc` as with `tablealloc`.

#### i Note

You can specify `fix` or `nofix` only if you include a value for the type of report (`full`, `optimized`, `fast`, or `null`).

**<table\_name> | <table\_id>**

is the table's name or the table's object ID.

**<indid>**

is the ID of the index that is checked during `dbcc indexalloc`.

**fix\_spacebits**

is for tables of type `datapages` or `datarows` lockscheme, and checks for the validity of space bits and fixes any invalid space bits. Space bits are stored per page and indicate the room available in a page for new inserts.

**check\_spacebits**

checks space bits for `datapages` or `datarows` locked tables. If you specify `check spacebits`, `dbcc` does not check nonclustered indexes.

**full**

reports all types of allocation errors.

**optimized**

produces a report based on the allocation pages listed in the object allocation map (OAM) pages for the index. It does not report and cannot fix unreferenced extents on allocation pages that are not listed in the OAM pages. The `optimized` option is the default.

**fast**

does not produce an allocation report, but produces an exception report of pages that are referenced but not allocated in the extent (2521-level errors).

**fix | nofix**

determines whether `indexalloc` fixes the allocation errors found in the table. The default is `fix` for all indexes except indexes on system tables, for which the default is `nofix`. To use the `fix` option with system tables, you must first put the database in single-user mode.

You can specify `fix` or `nofix` only if you include a value for the type of report (`full`, `optimized`, `fast`, or `null`).

**<partition\_name> | <partition\_id>**

if you specify a partition ID, allocation checks are performed on the partition identified by (`indid`, `partition id`).

**monitor increment, <group name>**

The `increment` and `decrement` commands increase and decrease, by 1, the usage counts for the monitor counters in the specified group. The `reset` command sets the usage count for the monitor counters in the specified group to zero. This turns off collection of monitoring data for this group.

`<group name>` can be one of the following:

- `'all'` – determine usage count for the `all` group, which comprises most of the monitor counters, by selecting the `<@@monitors_active>` global variable.
- `spinlock_s` – usage counts for `spinlock_s` reported by the `dbcc resource` command.
- `appl` – usage counts for `appl` reported by the `dbcc resource` command.

### **pravailabletempdbs**

prints the global list of available temporary databases.

**purgelobvers** (<dbname> | <database\_ID> [, <object\_name> | <object\_ID> [, <mode> ]])

runs the garbage-collection tasks to find existing LOB versions of MVCC-enabled tables.

mode determines the mode in which purgelobvers runs. One of:

- *fast* – locates old LOB versions saved in the on-disk queue and runs the garbage collector against them.
- *full* – scans the TEXT partition of the table to locate old LOB versions and runs the garbage collector against them.

### **rebuild\_text**

rebuilds or creates an internal SAP ASE version 12.0 or later data structure for text, or unitext, image data. This data structure enables the SAP ASE server to perform random access and asynchronous prefetch during data queries. You can run rebuild\_text on all tables in a database, a single table, or a data partition.

<table\_name> | <table\_id> | "all"

is the table's name or the table's object ID, or all the objects in the database.

<column>

is the ID or name of the column of the text column. dbcc rebuild\_text rebuilds the internal data structure of each text value of this column.

<text\_page>

is the logical page number of the first text page. dbcc rebuild\_text rebuilds the internal data structure of this text page.

<data\_partition\_name> | <data\_partition\_id>

is name or ID of the data partition. If you specify <text\_page>, <data\_partition\_name> (or <data\_partition\_id>) is ignored.

### **reindex**

checks the integrity of indexes on user tables by running a fast version of dbcc checktable. It can be used with the table name or the table's object ID (the id column from sysobjects). reindex prints a message when it discovers the first index-related error, then drops and re-creates the suspect indexes. The system administrator or table owner must run dbcc reindex after the SAP ASE sort order has been changed and indexes have been marked "suspect" by the SAP ASE server.

When dbcc finds corrupt indexes, it drops and re-creates the appropriate indexes. If the indexes for a table are already correct, or if the table has no indexes, dbcc reindex does not rebuild the index, but prints an informational message instead.

dbcc reindex aborts if a table is suspected of containing corrupt data. When that happens, an error message instructs the user to run dbcc checktable. dbcc reindex does not allow reindexing of system tables. System indexes are checked and rebuilt, if necessary, as an automatic part of recovery after the SAP ASE server is restarted following a sort order change.

### **dbcc showrecovery('database\_name')**

displays diagnostic information about in-memory row storage (IMRS)-enabled databases. If there is an active thread performing recovery, it displays current pass information along with the imrslog recovery diagnostics until the pass completes. If there are not active threads performing recovery, it displays previously completed recovery diagnostics.

### **serverlimits**

displays the limits the SAP ASE server enforces on various entities, including the lengths of identifiers and the maximum number of different objects such as number of columns in a table, number of indexes on a table, page sizes, row-overheads, and so on. Use the information to determine the various sizing characteristics of the SAP ASE server process.

### **shrinkdb\_setup**

checks whether backlink pointers exist for each partition of a table in the database. If the backlink pointers do not exist, `shrinkdb_setup` creates them.

- `<dbname>` – is the name of the database you are checking.
- `<object_name>` – is the name of the object you are checking.
- `<force>` – is:
  - `true` – forcefully check and set the backlink pointers for the object, regardless of whether or not backlink pointers are already set.
  - `false` – (the default) setup backlink pointers for the object if they are not already set.
- `verbose` – print messages at the beginning of each check (on by default).

#### **i Note**

`shrinkdb_setup` works only on tables that contain text columns, and issues a silent return if you execute it on a table that does not contain text columns.

### **stackused**

reports the maximum amount of stack memory used since the server first started.

### **tablealloc**

checks the specified table or data partition to see that all pages are correctly allocated, and that no page that is allocated is not used. This is a smaller version of `checkalloc`, providing the same integrity checks on an individual table. It can be used with the table name or the table's object ID (the `id` column from `sysobjects`). You can use `tablealloc` in an archive database. For an example of `tablealloc` output, see the *System Administration Guide*.

Three types of reports can be generated with `tablealloc`: `full`, `optimized`, and `fast`. If no type is indicated, or if you use `null`, the SAP ASE server uses `optimized`.

### **textalloc**

checks the allocation integrity of `text` or `image` pages in a database. You can use `dbcc textalloc` with an archive database.

### **"ALL"**

checks each table in the current database that has a text or image column.

**full**

is equivalent to `checkalloc` at a table level; it reports all types of allocation errors.

**optimized**

produces a report based on the allocation pages listed in the object allocation map (OAM) pages for the table. It does not report and cannot fix unreferenced extents on allocation pages that are not listed in the OAM pages. The `optimized` option is the default.

**fast**

does not produce an allocation report, but produces an exception report of pages that are referenced but not allocated in the extent (2521-level errors).

**fix | nofix**

determines whether or not `tablealloc` fixes the allocation errors found in the table. The default is `fix` for all tables except system tables, for which the default is `nofix`. To use the `fix` option with system tables, you must first put the database in single-user mode.

You can specify `fix` or `nofix` only if you include a value for the type of report (`full`, `optimized`, `fast`, or `null`).

**<data\_partition\_name> | <data\_partition\_id>**

is name or ID of the data partition to check. If you specify a partition, `dbcc tablealloc` skips global indexes.

**traceon | traceoff**

toggles the printing of diagnostics during query optimization. Values 3604 and 3605 toggle, sending trace output to the user session and to the error log, respectively.

**tune**

enables or disables tuning flags for special performance situations. You must re-issue `dbcc tune` each time you restart the SAP ASE server. For more information on the individual options, see *Performance and Tuning Guide: Basics*.

**upgrade\_object**

upgrades a compiled object from the text stored in the `syscomments` table. The `upgrade_object` parameters are:

- <dbid>** Specifies the database ID. If you do not specify `<dbid>`, all compiled objects in the current database are upgraded.
- <dbname>** Specifies the database name. If you do not specify `<dbname>`, all compiled objects in the current database are upgraded.
- <compiled\_object\_name>** Is the name of a specific compiled object you want to upgrade. If you use the fully qualified name, `<dbname>` and `<database>` must match, and you must enclose the fully qualified name in quotes. If the database contains more than one compiled object of the same

name, use the fully qualified name. Otherwise, all objects with the same name are parsed, and if no errors are found, upgraded.

<b>check</b>	Upgrades all check constraints and rules. Referential constraints are not compiled objects and do not require upgrading.
<b>default</b>	Upgrades all declarative defaults and the defaults created with the <code>create default</code> command.
<b>procedure</b>	Upgrades all stored procedures.
<b>rule</b>	Upgrades all rules and check constraints.
<b>trigger</b>	Upgrades all triggers.
<b>view</b>	Upgrades all views.

The keywords `check`, `default`, `procedure`, `rule`, `trigger`, and `view` specify the classes of compiled objects to be upgraded. When you specify a class, all objects in that class, in the specified database, are upgraded, provided that `dbcc upgrade_object` finds no errors or potential problem areas.

<b>force</b>	<p>forces an upgrade of the object from <code>syscomments</code> even if an upgrade is not required. Errors are raised if the source text contains errors, as well as for other non-syntax errors including normalization issues such as ambiguous object references (error 209). <code>dbcc upgrade_object</code> requires the traceflag 3604 to be set to on to send output to the client.</p> <p><code>force</code> specifies that you want to upgrade the specified object even if it contains a <code>select *</code> clause. Do not use <code>force</code> unless you have confirmed that the <code>select *</code> statement is not returning unexpected results. The <code>force</code> option does not upgrade objects that contain reserved words, contain truncated or missing source text, refer to nonexistent temporary tables, or do not match the quoted identifier setting. You must fix these objects before they can be upgraded.</p>
--------------	--

<b>check</b>	checks syntax for the specified compiled object in <code>syscomments</code> in the specified database. Does not raise errors on occurrences of <code>select</code> .
--------------	--

## **zapdefraginfo**



deletes rows that are stored in `sysattributes`. For every data partition undergoing incremental reorganization, a row is stored in `sysattributes`. Use `zapdefraginfo` to delete this information before performing a downgrade.

In a running server, if the rows with defragmentation information for a specific object are accidentally lost from `sysattributes`, use `zapdefraginfo` to reset the extent version information for the specific object so that a later `reorg defrag` will not fail to consider all the extents of the object.

#### **zap**

deletes the extent version information for the specified object or partition.

#### **zap\_no\_log**

deletes the extent version information for the specified object without logging the changes involved.

#### **<trace\_flag\_number>**

is the number of the trace flag you are enabling or disabling.

#### **cluster**

sets the `dbcc` command scope to the cluster. Subsequent `dbcc` commands have a cluster-wide effect.

#### **instance**

sets the `dbcc` command scope to the current instance. Subsequent `dbcc` commands affect only the local instance.

#### **scope**

displays the current scope of the `dbcc` command, either `cluster` or `instance`.

## Examples

### Example 1

Checks `pubs2` for page allocation errors:

```
dbcc checkalloc (pubs2)
```

### Example 2

Checks database consistency for `pubs2` and places the information in the `dbccdb` database:

```
dbcc checkstorage (pubs2)
```

### Example 3

Checks the `salesdetail` table:

```
dbcc checktable (salesdetail)
```

```
Checking salesdetail
The total number of pages in partition 1 is 3.
The total number of pages in partition 2 is 1.
The total number of pages in partition 3 is 1.
The total number of pages in partition 4 is 1.
```

```
The total number of data pages in this table is 10.  
Table has 116 data rows.  
DBCC execution completed. If DBCC printed error  
messages, contact a user with system administrator (SA)  
role.
```

#### Example 4

Heuristically aborts the transaction "distributedxact1:"

```
dbcc complete_xact (distributedxact1, "rollback")
```

#### Example 5

Upgrades text values for `blurbs` after a character set change:

```
dbcc fix_text (blurbs)
```

#### Example 6

Runs `checkverify` on the table `tab`, with exclusion list disabled, in the database `my_db`:

```
dbcc checkverify(my_db, tab)
```

#### Example 7

Runs `dbcc checkverify` on table `tab`, in database `my_db`, with the exclusion list enabled:

```
dbcc checkverify (my_db, tab, 0)
```

#### Example 8

Runs `dbcc checkverify` on table `tab`, in database `my_db`, with the exclusion list disabled, enter:

```
dbcc checkverify (my_db, tab, 1)
```

#### Example 9

Removes information for the transaction "distributedxact1" from `master.dbo.systransactions`:

```
dbcc forget_xact (distributedxact1)
```

#### Example 10

Returns a full report of allocation for the index with an `indid` of 2 on the `titleauthor` table and fixes any allocation errors:

```
dbcc indexalloc ("pubs..titleauthor", 2, full)
```

#### Example 11

Prints the global list of available temporary databases:

```
dbcc pravailabletempdbs
```

```
Available temporary databases are:  
Dbid: 2  
Dbid: 4  
Dbid: 5  
Dbid: 6  
Dbid: 7  
DBCC execution completed. If DBCC printed error  
messages, contact a user with system administrator (SA) role.
```

### Example 12

Rebuilds or creates an internal SAP ASE data structure for all `text` and `image` columns in the `blurbs` table:

```
dbcc rebuild_text (blurbs)
```

### Example 13

Checks part of the `titles` table that resides on the `smallsales` partition (which contains all booksales less than 5000)

```
dbcc checktable (titles, NULL, "smallsales")
```

### Example 14

`dbcc reindex` Discovers one or more corrupt indexes in the `titles` table:

```
dbcc reindex (titles)
```

```
One or more indexes are corrupt. They will be rebuilt.
```

### Example 15

Checks the maximum amount of stack memory used since the SAP ASE server started:

```
dbcc stackused
```

### Example 16

Upgrades all stored procedures in the `listdb` database:

```
dbcc upgrade_object(listdb, 'procedure')
```

### Example 17

Upgrades all rules and check constraints in the `listdb` database. Double quotes are used around `rule` because `set quoted identifiers is off`.

```
dbcc upgrade_object(listdb, list_proc)
```

### Example 18

Displays an abridged output showing various forms of limits in your SAP ASE server:

```
dbcc serverlimits
```

```
To show a complete listing of limits in the server, executeLimits independent
of page size:To show a complete listing of limits in the server, execute
=====
```

```
Server-wide, Database-specific limits and sizes
Max engines per server : 128
Max number of logins per server : 2147516416
Max number of users per database : 2146484223
Max number of groups per database : 1032193
=====
```

```
Max number of user-defined roles per server : 1024
Server-wide, Database-specific limits and sizes
Max number of user-defined roles per (user) session : 127
Max engines per server : 128
```

```

Min database page size : 2048
Max
Max database page size : 16384 number of logins per server : 2147516416
...
Max number of users per database : 2146484223
Database page-specific limits
Max number of groups per database : 1032193
APL page header size : 32
Max number of user-defined roles per server : 1024
DOL page header size : 44
Max number of user-defined roles per (user) session : 127
Max reserved page gap : 255
Max fill factor : 100
Min database page size : 2048
Table, Index related limits
Max database page size : 16384
Max number of columns in a table/view : 1024
...
Max number of indexes on a table : 250
Database page-specific limits
Max number of user-keys in a single index on an unpartitioned table : 31
APL page header size : 32
Max number of user-keys in a single local index on a partitioned table : 31
DOL page header size : 44
...
Max reserved page gap : 255
General SQL related
Max fill factor : 100
Max size of character literals, sproc parameters : 16384
Table, Index related limits
Max size of local @variables in T-SQL : 16384
Max number of columns in a table/view : 1024
Max number of arguments to stored procedures : 2048
Max number of arguments to dynamic SQL : 2048
Max number of aggregates in a COMPUTE clause : 254
...
Maximum lengths of different Identifiers
Max length of server name : 30
Max length of host name : 30
Max length of login name : 30
Max length of user name : 30
...
Limits as a function of the page size:
Max number of indexes on a table : 250
=====
Max number of user-keys in a single index on an unpartitioned table : 31
Item dependent on page size : 2048    4096    8192    16384
Max number of user-keys in a single local index on a partitioned table : 31
-----
...
Server-wide, Database-specific limits and sizes
General SQL related
Min number of virtual pages in master device      : 11780 22532 45060 90116
Max size of character literals, sproc parameters : 16384
Default number of virtual pages in master device : 23556 45060 90116 180228
Max size of local @variables in T-SQL : 16384
Min number of logical pages in master device      : 11776 11264 11264 11264
Max number of arguments to stored procedures : 2048
Min number of logical pages in tempdb              : 2048 1536 1536 1536
Max number of arguments to dynamic SQL : 2048
Table-specific row-size limits
Max number of aggregates in a COMPUTE clause : 254
Max possible size of a log-record row on APL log page : 2014 4062 8158 16350
...
Physical Max size of an APL data row, incl row-overheads : 1962 4010 8106
16298
Maximum lengths of different Identifiers
Physical Max size of a DOL data row, incl row-overheads : 1964 4012 8108 16300

```

```

Max length of server name : 30
Max user-visible size o
Max length of host name : 30f an APL data row : 1960 4008 8104 16296
Max user-visible size of a DOL data row : 1958 4006 8102 16294
Max user-visible size of a fixed-length column in an APL table :
Max length of login name : 30
    1960 4008 8104 16296
Max length of user name : 30
Max user-visible size of a fixed-length column in a DOL table :
...
    1958 4006 8102 16294
Limits as a function of the page size:
...

```

## i Note

`dbcc traceon (3604)` to get the output to the client session.

### Example 19

Returns an optimized report of allocation for this table, but does not fix any allocation errors:

```
dbcc tablealloc (publishers, null, nofix)
```

### Example 20

Performs allocation checks on the `smallsales` partition. All the local indexes on `smallsales` are included in the check, while the global indexes are excluded:

```
dbcc tablealloc (titles, null, null, smallsales)
```

### Example 21

Uses `sp_transactions` to determine the name of a one-phase commit transaction that did not heuristically commit because it was not in a "prepared" state. The example then explains how to use the `lpc` parameter to successfully commit the transaction:

```
sp_transactions
```

```

xactkey          type   coordinator starttime
state            connection dbid spid loid failover   srvnname namelen
xactname
-----
0xbc0500000b00000030c316480100 External XA          Feb 2 2004 1:07PM
Done-Detached Detached          1    0 2099 Resident Tx NULL      88
28_u7dAc31Wc38000000000000000000000000000000000001HFpfSxkDM000FU_00003M00
00Y_:SYBBEV0A_LRM
(1 row affected)
(return status = 0)

```

If you try to commit this transaction, the SAP ASE server issues an error message:

```

dbcc complete_xact

("28_u7dAc31Wc38000000000000000000000000000000000001HFpfSxkDM000FU_00003M0000Y_
:SYBBEV0A_LRM", "commit")

```

The error message the SAP ASE server issues:

```
Msg 3947, Level 16, State 1:
```

```
Server 'PISSARRO_1251_P', Line 1:
A heuristic completion related operation failed. Please see errorlog
for more details.
DBCC execution completed. If DBCC printed error messages, contact
a user with system administrator (SA) role.
```

Because the transaction is in a "done" state, you can use a one-phase commit protocol optimization to heuristically complete the transaction after verifying the transaction was committed. You can commit this transaction using the `dbcc complete_xact ("1pc")` parameter:

```
dbcc complete_xact
("28_u7dAc31Wc380000000000000000000000000000000000000000000000001HFpfSxkDM000FU_00003M0000Y_
SYBBEV0A_LRM", "commit", "1pc")
```

```
DBCC execution completed. If DBCC printed error messages,
contact a user with system administrator (SA) role.
```

You can remove the transaction from `systransactions` with the `dbcc forget_xact` command:

```
dbcc forget_xact
("28_u7dAc31Wc38000000000000000000000000000000000000000000000001HFpfSxkDM0
00FU_00003M0000Y_ :SYBBEV0A_LRM")
DBCC execution completed. If DBCC printed error messages, contact
a user with system administrator (SA) role.
```

If you run `sp_transactions` again, the previous transaction does not appear:

```
sp_transactions
```

```
xactkey type coordinator starttime state connection dbid spid
      loid failover srvname namelen xactname
-----
(0 row affected)
```

#### Example 22

Enables trace flag 3604:

```
dbcc nodetraceoff(3604)
```

```
DBCC execution completed. If DBCC printed error messages,
contact a user with system administrator (SA) role.
```

#### Example 23

Sets the `dbcc` scope to the cluster:

```
dbcc set_scope_in_cluster('cluster')
```

#### Example 24

Sets the `dbcc` scope to the instance:

```
dbcc set_scope_in_cluster('instance')
```

### Example 25

Displays the current scope for dbcc commands:

```
dbcc set_scope_in_cluster('scope')
```

### Example 26

adds the store\_zips table to an IMRS-enabled version of the pubs2 database, creates the zip1 hash-cached BTree index, and uses dbcc hcb to view hash caching information:

1. Create the store\_zips table:

```
create table store_zips(ID int, ZIP varchar(5)) lock datarows with
row_caching on
```

2. Create the hash-cached BTree index:

```
create unique index zip1 on store_zips(ID) with index_hash_caching= on
```

3. Add content to the table:

```
insert into tbl values(10, '96777')
. . .
```

4. Determine the index structure of the table. The values dbcc hcb requires are the index\_name and index\_ptn\_name (in bold):

```
sp_helpindex store_zips
Object has the following indexes
  index_name          index_keys

index_description
  index_max_rows_per_page
  index_fillfactor
  index_reservepagegap
  index_created              index_local
-----
-----
-----
-----
-----
-----
-----
zip1          ID
nonclustered, unique, defer_recovery auto, index hash
caching
              0
              0
              0
Feb 16 2017 10:52AM              Global Index
(1 row affected)
index_ptn_name          index_ptn_seg
  index_ptn_comp
-----
zip1_1552005529          default
  inherit from index
(1 row affected)
name      attribute_class      attribute
  int_value      char_value      comments
-----
zip1      hcb index              bucket number
```

```

131072          NULL          NULL
go
dbcc hcb('print', 'bucket', tdb1, 'verbose', tb1, idx1, idx1_1168004161)

```

5. Enable trace flags 3604 and 1410:

```
dbcc traceon(3604, 1410)
```

6. Determine the table's hash cached information:

```

PDES_HCB at 0x150dc99e0
phcb_objid = 1552005529 phcb_indid = 2 phcb_ptnid = 1552005529
phcb_ts = 0 phcb_stats = 0 phcb_mem_err_printed = 1356634720
phcb_next = 0x(nil) phcb_bucket_number = 131072
phcb_buckets = (nil) phcb_buckets2 = 0x150dc9b40
This hash table has 131072 buckets
=====
Printing bucket 0 starting from 0x0x150e49c00
HCB_NODE at 0x0x150e49c00
hcbn_scannext = 0x0x150e49c60 hcbn_gcnext = 0x(nil)
hcbn_ts = 0 hcbn_stat = 0x(nil) hcbn_hashcode = 1173468484
RID = (953, 1)
HCB_NODE at 0x0x150e49c60
hcbn_scannext = 0x0x150dc9b80 hcbn_gcnext = 0x(nil)
hcbn_ts = 0 hcbn_stat = 0x(nil) hcbn_hashcode = 3138382297
RID = (953, 2)
HCB_NODE at 0x0x150dc9b80
hcbn_scannext = 0x(nil) hcbn_gcnext = 0x(nil)
hcbn_ts = 0 hcbn_stat = 0x(nil) hcbn_hashcode = 3792428981
RID = (953, 0)
=====
Totally 1 buckets are not empty. 3 nodes in all, avg 3.00 nodes per bucket
chain.
=====
DBCC execution completed. If DBCC printed error messages, contact a user
with
System Administrator (SA) role.

```

The `brief` parameter reduces the output:

```

dbcc hcb('print', 'bucket', pubs2, 'brief', store_zips, zip1,
'zip1_1552005529')
PDES_HCB at 0x150dc99e0
phcb_objid = 1552005529 phcb_indid = 2 phcb_ptnid = 1552005529
phcb_ts = 0 phcb_stats = 0 phcb_mem_err_printed = 1356634720
phcb_next = 0x(nil) phcb_bucket_number = 131072
phcb_buckets = (nil) phcb_buckets2 = 0x150dc9b40
This hash table has 131072 buckets
=====
Totally 1 buckets are not empty. 3 nodes in all, avg 3.00 nodes per bucket
chain.
=====
DBCC execution completed. If DBCC printed error messages, contact a user
with
System Administrator (SA) role.

```

### Example 27

checks for backlink pointers in the `pubs2` database:

```
dbcc shrinkdb_setup (pubs2, NULL, true)
DBCC: checking database 'pubs2'.
```



```

DBCC: checking table 'sysxtypes'.
DBCC: checking partition 'sysxtypes_25'.
DBCC: checking table 'sysjars'.
DBCC: checking partition 'sysjars_26'.
DBCC: checking table 'sysattributes'.
DBCC: checking partition 'sysattributes_21'.
DBCC: checking table 'au_pix'.
DBCC: checking partition 'au_pix_880003135'.
DBCC: checking table 'blurbs'.
DBCC: checking partition 'blurbs_912003249'.
DBCC execution completed. If DBCC printed error messages, contact a user with
System Administrator (SA) role.

```

This checks for backlink pointers in the blurbs table:

```

dbcc shrinkdb_setup (pubs2, blurbs, true)
DBCC: checking table 'blurbs'.
DBCC: checking partition 'blurbs_912003249'.
DBCC execution completed. If DBCC printed error messages, contact a user with
System Administrator (SA) role.

```

## Usage

- `dbcc checkstorage` reports a soft fault if any data page that is not the first data page is empty for nonhashed tables. However, `dbcc checkstorage` does not report this soft fault for the hashed region of a virtually hashed table. Any data page in the hashed region of a virtually hashed table can be empty.
- You can run `dbcc` while the database is active, except for the `dbrepair (<database_name>, dropdb)` option and `dbcc checkalloc` with the `fix` option.
- `dbcc` locks database objects as it checks them. For information on minimizing performance problems while using `dbcc`, see the `dbcc` discussion in the *System Administration Guide*.
- When `dbcc` commands are executing, users cannot access an archive database. If you attempt to access an archive database while `dbcc` commands are being performed, you receive a message saying that the database is in single-user mode.
- Most `dbcc` commands work with in-memory and relaxed durability databases.
- You cannot lock a table on which you previously executed the `dbcc tune(des_bind...)` command because the SAP ASE server does not allow shared or exclusive table locks on hot objects. For example, the SAP ASE server issues warning number 8242 if you:
  - Create a table
  - Run `dbcc tune (des_bin...)`. For example:

```
dbcc tune(des_bin, 4, new_table)
```

- Attempt to lock the table:

```
begin tran
lock table new_table in exclusive mode
go
```

```
Msg 8242, Level 16, State 1:
Server 'server01', Line 2:
The table 'new_table' in database 'big_db' is bound to metadata cache
memory.
Unbind the table and retry the query later.
```

- You can use variants of the `dbcc` commands on an archive database that is online or offline. However, you can use `dbcc` with a `fix` option only on an online archive database.
- To qualify a table or an index name with a user name or database name, enclose the qualified name in single or double quotation marks. For example:

```
dbcc tablealloc ("pubs2.pogo.testtable")
```

- You cannot run `dbcc reindex` within a user-defined transaction.
- `dbcc fix_text` can generate a large number of log records, which may fill up the transaction log. `dbcc fix_text` is designed so that updates are performed in a series of small transactions: in case of a log space failure, only a small amount of work is lost. If you run out of log space, clear your log and restart `dbcc fix_text` using the same table that was being upgraded when the original `dbcc fix_text` failed.
- If you are using a replicated database and need to load a dump from an earlier version of the SAP ASE server to the current version, use `dbcc dbrepair`. For example:
  - Load a dump from a production system of the earlier version of the SAP ASE server into a test system of the current version SAP ASE server, or
  - In a warm standby application, initialize a standby database of the current version of the SAP ASE server with a database dump from an active database of the earlier version of the SAP ASE server.
- If you attempt to use `select`, `readtext`, or `writetext` on `text` values after changing to a multibyte character set, and you have not run `dbcc fix_text`, the command fails, and an error message instructs you to run `dbcc fix_text` on the table. However, you can delete `text` rows after changing character sets without running `dbcc fix_text`.
- `dbcc` output is sent as messages or errors, rather than as result rows. Client programs and scripts should check the appropriate error handlers.
- If a table is partitioned, `dbcc checktable` returns information about each partition.
- `text` and `image` data that has been upgraded to SAP ASE version 12.x or later is not automatically upgraded from its original storage format. To improve query performance and enable prefetch for this data, use the `rebuild_text` keyword against the upgraded `text` and `image` columns.
- The amount of stack memory used in the past is only an indication of possible future needs. The SAP ASE server may require more stack memory than it used in the past. Periodically run `dbcc stackused` to find your current stack memory usage.
- `dbcc upgrade_object_check` is used to detect `syscomments` text corruption caused by SAP ASE defects that occurred before you upgraded the SAP ASE server. This `syscomments` text corruption is serious because it causes the upgrade process to fail.
- If any error is reported by `dbcc upgrade_object_check`, you must drop and re-create the `<compiled_object>`.
- Running `dbcc shrinkdb_setup` invalidates, but does not drop, text indexes. Subsequent DML operations run on the affected table will report that it contains a suspect index. SAP recommends that you drop indexes that `shrinkdb_setup` invalidates.
- After you run `dbcc shrinkdb_setup`:
  - Mark any large object columns that include replication indexes as "suspect" to ensure that Replication Server uses the backlink pointers on these LOB columns.
  - Databases are marked to indicate that `dbcc shrinkdb_setup` has configured backlink pointers for `text` and `image` columns. You cannot run a `use index` command to create replication indexes.
- (Cluster Edition only) `dbcc traceon` and `dbcc traceoff` apply trace flags for the entire cluster, while `dbcc nodetraceoff` and `dbcc nodetraceon` apply trace flags locally.
- See also `sp_configure`, `sp_helpdb` in *Reference Manual: Procedures*.

## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

## Permissions

The permission checks for `dbcc` commands differ based on your granular permissions settings. This table shows the permission requirement for each `dbcc` command.

### i Note

You can run a `dbcc` command if you have any one of the requirements (privileges or ownership) listed in the table for that command.

Table 3: Permissions Requirement for `dbcc` Command

DBCC Command Name	Permission Requirement	
	Granular Permissions Disabled	Granular Permissions Enabled
<code>addtempdb</code>	<ul style="list-style-type: none"><li>• Database owner</li><li>• <code>sa_role</code></li></ul>	<ul style="list-style-type: none"><li>• Database owner</li><li>• <code>own database</code></li></ul>
<code>checkalloc</code>	<ul style="list-style-type: none"><li>• <code>dbcc checkalloc</code></li><li>• Database owner</li><li>• <code>sa_role</code></li></ul>	<ul style="list-style-type: none"><li>• <code>dbcc checkalloc</code></li></ul>
<code>checkcatalog</code>	<ul style="list-style-type: none"><li>• <code>dbcc checkcatalog</code></li><li>• Database owner</li><li>• <code>sa_role</code></li></ul>	<ul style="list-style-type: none"><li>• <code>dbcc checkcatalog</code></li></ul>
<code>checkdb</code>	<ul style="list-style-type: none"><li>• <code>dbcc checkdb</code></li><li>• Database owner</li><li>• <code>sa_role</code></li></ul>	<ul style="list-style-type: none"><li>• <code>dbcc checkdb</code></li></ul>
<code>checkindex</code>	<ul style="list-style-type: none"><li>• <code>dbcc checkindex</code></li><li>• Table owner</li><li>• <code>sa_role</code></li></ul>	<ul style="list-style-type: none"><li>• <code>dbcc checkindex</code></li><li>• Table owner</li></ul>
<code>checkstorage</code>	<ul style="list-style-type: none"><li>• <code>dbcc checkstorage</code></li><li>• Database owner</li><li>• <code>sa_role</code></li></ul>	<ul style="list-style-type: none"><li>• <code>dbcc checkstorage</code></li></ul>
<code>checktable</code>	<ul style="list-style-type: none"><li>• <code>dbcc checktable</code></li><li>• Table owner</li><li>• <code>sa_role</code></li></ul>	<ul style="list-style-type: none"><li>• <code>dbcc checktable</code></li><li>• Table owner</li></ul>

DBCC Command Name	Permission Requirement	
	Granular Permissions Disabled	Granular Permissions Enabled
checkverify	<ul style="list-style-type: none"> <li>• dbcc checkverify</li> <li>• Database owner</li> <li>• sa_role</li> </ul>	<ul style="list-style-type: none"> <li>• dbcc checkverify</li> </ul>
cis showcaps	<ul style="list-style-type: none"> <li>• sa_role</li> </ul>	<ul style="list-style-type: none"> <li>• manage server</li> </ul>
cis remcon	<ul style="list-style-type: none"> <li>• sa_role</li> </ul>	<ul style="list-style-type: none"> <li>• manage server</li> </ul>
complete_xact	<ul style="list-style-type: none"> <li>• sa_role</li> </ul>	<ul style="list-style-type: none"> <li>• manage server</li> </ul>
dbrepair dropdb	<ul style="list-style-type: none"> <li>• Database owner</li> <li>• sa_role</li> </ul>	<ul style="list-style-type: none"> <li>• Database owner</li> <li>• own database</li> </ul>
engine	<ul style="list-style-type: none"> <li>• sa_role</li> </ul>	<ul style="list-style-type: none"> <li>• manage server</li> </ul>
fix_text	<ul style="list-style-type: none"> <li>• dbcc fix_text</li> <li>• Object owner</li> <li>• sa_role</li> </ul>	<ul style="list-style-type: none"> <li>• dbcc fix_text</li> <li>• Object owner</li> </ul>
forget_xact	<ul style="list-style-type: none"> <li>• sa_role</li> </ul>	<ul style="list-style-type: none"> <li>• manage server</li> </ul>
indexalloc	<ul style="list-style-type: none"> <li>• dbcc indexalloc</li> <li>• Table owner</li> <li>• sa_role</li> </ul>	<ul style="list-style-type: none"> <li>• dbcc indexalloc</li> <li>• Table owner</li> </ul>
monitor	<ul style="list-style-type: none"> <li>• sa_role</li> </ul>	<ul style="list-style-type: none"> <li>• manage server</li> </ul>
pravailabletempdbs	<ul style="list-style-type: none"> <li>• sa_role</li> </ul>	<ul style="list-style-type: none"> <li>• manage server</li> </ul>
quorum	<ul style="list-style-type: none"> <li>• sa_role</li> </ul>	<ul style="list-style-type: none"> <li>• manage cluster</li> </ul>
rebuild_text	<ul style="list-style-type: none"> <li>• Table owner</li> <li>• sa_role</li> </ul>	<ul style="list-style-type: none"> <li>• Table owner</li> <li>• manage database</li> </ul>
reindex	<ul style="list-style-type: none"> <li>• dbcc reindex</li> <li>• Table owner</li> <li>• sa_role</li> </ul>	<ul style="list-style-type: none"> <li>• dbcc reindex</li> <li>• Table owner</li> </ul>
serverlimits	<ul style="list-style-type: none"> <li>• sa_role</li> </ul>	<ul style="list-style-type: none"> <li>• manager server</li> </ul>
set_scope_in_cluster	<ul style="list-style-type: none"> <li>• sa_role</li> </ul>	<ul style="list-style-type: none"> <li>• manage cluster</li> </ul>
stackused	<ul style="list-style-type: none"> <li>• sa_role</li> </ul>	<ul style="list-style-type: none"> <li>• manager server</li> </ul>

DBCC Command Name	Permission Requirement	
	Granular Permissions Disabled	Granular Permissions Enabled
tablealloc	<ul style="list-style-type: none"> <li>• dbcc tablealloc</li> <li>• Table owner</li> <li>• sa_role</li> </ul>	<ul style="list-style-type: none"> <li>• dbcc tablealloc</li> <li>• Table owner</li> </ul>
textalloc	<ul style="list-style-type: none"> <li>• dbcc textalloc</li> <li>• Table owner</li> <li>• sa_role</li> </ul>	<ul style="list-style-type: none"> <li>• dbcc textalloc</li> <li>• Table owner</li> </ul>
trace flags 3604, 3605	<ul style="list-style-type: none"> <li>• sa_role</li> </ul>	<ul style="list-style-type: none"> <li>• set tracing</li> <li>• monitor qp performance</li> <li>• set switch</li> </ul>
all other trace flags	<ul style="list-style-type: none"> <li>• sa_role</li> </ul>	<ul style="list-style-type: none"> <li>• set switch</li> </ul>
tune ascinserts	<ul style="list-style-type: none"> <li>• dbcc tune</li> <li>• Table owner</li> <li>• sa_role</li> </ul>	<ul style="list-style-type: none"> <li>• dbcc tune</li> <li>• Table owner</li> </ul>
tune all other parameters	<ul style="list-style-type: none"> <li>• dbcc tune</li> <li>• sa_role</li> </ul>	<ul style="list-style-type: none"> <li>• dbcc tune</li> </ul>
upgrade_object	<ul style="list-style-type: none"> <li>• object owner</li> <li>• Database owner</li> <li>• sa_role</li> </ul>	<ul style="list-style-type: none"> <li>• manage database</li> <li>• Object owner</li> </ul>

## Auditing

You can enable `dbcc` auditing option to audit this command. Values in `event` and `extrainfo` columns from the `sysaudits` table are:

Information	Value
Audit option	dbcc
Event	81
Command or access audited	dbcc
Information in <code>extrainfo</code>	<ul style="list-style-type: none"> <li>• <b>Roles</b> – current active roles</li> <li>• <b>Full command text</b> – full text of <code>dbcc</code> command</li> <li>• <b>Previous value</b> – NULL</li> <li>• <b>Current value</b> – NULL</li> </ul>

## Information

## Value

- **Other information** – NULL
- **Proxy information** – original login name, if `set proxy` is in effect

Full command text is included in `extrainfo`. For example:

```
sa_role sso_role oper_role sybase_ts_role mon_role;  
dbcc checktable('master.dbo.t1'); ; ; ; sa/ase;
```

For more information about auditing, see *Security Administration Guide > Auditing*.

## Related Information

[drop database \[page 429\]](#)

### 1.47.1 Using dbcc quorum (clusters only)

Usage information for `dbcc quorum`.

- `dbcc quorum` output goes to:
  - By default, terminal that started the SAP ASE server
  - The client session if trace flag 3604 or 3605 is on
- `dbcc quorum` accepts an integer parameter for the number of view records to print. For example, to print the 20 most recently view records, use:

```
dbcc quorum(20)
```

- If you do not include a parameter `dbcc quorum` prints the 10 most recent view records.
- Issue `dbcc quorum (-1)` to view all records.

### 1.47.2 Restrictions on dbcc checkstorage for Shared-Disk Clusters

Restrictions for using `dbcc checkstorage` on shared-disk clusters.

- You cannot include instance-only named caches with `dbcc checkstorage`. `dbcc checkstorage` issues this error message if you do so:

```
The cache %1! cannot be used because it is an instance only cache
```

- To run `dbcc checkstorage` against a local temporary database, you must run the command from the same instance that owns the local temporary database.
- For performance reasons, `dbcc checkstorage` in the Cluster Edition may not query the latest version of a page in the cluster. This may cause the Cluster Edition to report more soft faults than other versions.

For well-partitioned applications where a single instance updates a database, `dbcc checkstorage` behaves as earlier non-Cluster Edition SAP ASE versions.

## 1.47.3 Using `dbcc complete_xact`

`dbcc complete_xact` enables a system administrator to commit or roll back a distributed transaction in circumstances where the external transaction coordinator cannot.

In versions of SAP ASE earlier than 15.0, a transaction could not heuristically committed unless it was in the “prepare” state, and the transaction coordinator used a two-phase commit protocol to commit the transaction. However, in some cases, a transaction coordinator may want to use a one-phase commit protocol as an optimization to commit the transaction.

`1pc` heuristically completes a transaction that was subject to a one-phase commit protocol optimization—instead of the regular two-phase commit protocol—by the external transaction manager that was coordinating its completion. Heuristically committing such a transaction requires that the transaction be in a “done” state (as reported by `sp_transactions`).

### i Note

Before heuristically completing the transaction, the system administrator should make every effort to determine whether the coordinating transaction manager committed or rolled back the distributed transaction.

## 1.47.4 Checking Performed by `dbcc checkcatalog`

`dbcc checkcatalog` checks and reports on a variety of issues.

- For each row in `sysindexes` that maps to a range-, hash-, or list-partitioned table, there exists one row in `sysobjects` where `sysindexes.conditionid equals sysobjects.id`. `dbcc checkcatalog` also performs this check for each row in `sysindexes` that maps to a round-robin-partitioned table that has a partition condition.
- For each row in `sysindexes` that maps to a range-, hash-, or list-partitioned table, there exists one or more rows in `sysprocedures` where `sysindexes.conditionid equals sysprocedures.id`. `dbcc checkcatalog` also performs this check for each row in `sysindexes` that maps to a round-robin-partitioned table that has a partition condition.
- For each row in `sysindexes` that maps to a range-, hash-, or list-partitioned table, there exists one row in `syspartitionkeys` where the following conditions are true: `sysindexes.id equals syspartitionkeys.id` and `sysindexes.indid equals syspartitionkeys.indid`. `dbcc checkcatalog` also performs this check for each row in `sysindexes` that maps to a round-robin-partitioned table that has a partition condition.
- For each row in `sysindexes`, there exists one or more rows in `syspartitions` where both of the following conditions are true: `sysindexes.id equals syspartitions.id` and `sysindexes.indid equals syspartitions.indid`.
- For each row in `sysobjects` where `type` is N, there exists one row in `sysindexes` where `sysindexes.conditionid equals sysobjects.id`.

- For each row in `syspartitions`, there exists a row in `sysindexes` where the following conditions are true: `syspartitions.id equals sysindexes.id` and `syspartitions.indid equals sysindexes.indid`.
- For each row in `syspartitionkeys`, there exists a row in `sysindexes` where the following conditions are true: `syspartitionkeys.id equals sysindexes.id` and `syspartitionkeys.indid equals sysindexes.indid`.
- For each row in `syspartitions`, there exists one row in `syssegments` where the following condition is true: `syspartitions.segments equals syssegments.segment`.
- For each row in `systabstats`, there exists a row in `syspartitions` where the following conditions are true: `syspartitions.id equals systabstats.id`, `syspartitions.indid equals systabstats.indid` and `syspartitions.partitionid equals systabstats.partitionid`. Text indexes (`indid=255`) do not have entries in `systabstats`.
- For each row in `sysstatistics`, there exists a row in `sysobjects` where the following condition is true: `sysstatistics.id equals sysobjects.id`.
- For each encryption key row in `sysobjects`, the SAP ASE server checks `sysencryptkeys` for a row defining that key.
- For each column in `syscolumns` marked for encryption, the SAP ASE server verifies that a key-in `sysobjects` and `sysencryptkeys`.
- `dbcc checkcatalog` ensures that:
  - The corresponding base key is present in `sysencryptkeys` for every key copy in `sysencryptkeys`. If the base key is not present, the SAP ASE server issues an error.
  - For every key copy, the corresponding `uid` is present in `sysusers`. If the `uid` is not present, the SAP ASE server issues an error.
  - For every decrypt default defined on a column, that the corresponding decrypt default is present in `sysobjects` and `sysattributes`. If the corresponding decrypt default is not present, the SAP ASE server issues an error.

## 1.47.5 Using dbcc checktable

If the log segment is on its own device, running `dbcc checktable` on the `syslogs` table reports the logs used and free space.

For example:

```
Checking syslogs
The total number of data pages in this table is 1.
*** NOTICE: Space used on the log segment is 0.20 Mbytes, 0.13%.
*** NOTICE: Space free on the log segment is 153.4 Mbytes, 99.87%.DBCC execution
completed. If dbcc printed error messages, see your system administrator.
```

If the log segment is not on its own device, the following message appears:

```
*** NOTICE: Notification of log space used/free cannot be reported because the
log segment is not on its own device.
```

In addition to the regular checks it performs, `checktable` verifies that the preallocation performed during table creation is correct:



- The number of pages preallocated matches the total number of data pages that must be allocated for the specified `<max hash key>` value.
- The data pages are not preallocated in an extent where the preallocation scheme specifies that only object allocation map (OAM) pages are allowed.
- The OAM pages are allocated only in the first extent of an allocation unit.

## 1.47.6 Valid Options for `dbcc imrs`

Valid `<option>` parameters for the `dbcc imrs` command depend on the combination of `<action>` and `<component>` parameters you include with it.

The syntax is:

```
dbcc imrs(<action> [, <component>, <database_ID> | <database_name>, <option>,
<parameter>, <parameter>, <parameter>, ...] )
```

The `<option>` parameters include:

- `all` – valid for syntax that includes:
- `brief` – valid for syntax that includes:
  - `(print, rows)`
  - `(print, inserted_rows)`
  - `(print, migrated_rows)`
  - `(print, cached_rows)`
  - `(print, this_row)`
  - `(print_queue, ilm)`
  - `(print, lobgcq)`
- `diag` – valid for syntax that includes:
  - `(print, gc)`
- `fast` – valid for syntax that includes:
  - `(purge, lovers)`
- `fragment_chain_back` – valid for syntax that includes:
  - `(print, imrslog)`
- `full` – valid for syntax that includes:
  - `(check, ridmap)`
  - `(purge, lovers)`
- `fullycommitxact` – valid for syntax that includes:
  - `(print, imrslog)`
  - `(set, imrslog)`
- `get_pageids` – valid for syntax that includes:
  - `(print, imrslog)`
- `inserted_rows` – valid for syntax that includes:
  - `(print, ridmap)`
  - `(print, qrow)`

- `isallocated` – valid for syntax that includes:
  - `(print, imrslog)`
- `lastlr` – valid for syntax that includes:
  - `(print, imrslog)`
  - `(set, imrslog)`
- `migrated_rows` – valid for syntax that includes:
  - `(print, ridmap)`
  - `(print, qrow)`
- `no_truncate` – valid for syntax that includes:
  - `(drop, imrslog)`
- `null` – valid for syntax that includes:
  - `(check, ridmap)`
  - `(check, imoam)`
  - `(check, this_row)`
  - `(drop, imrslog)`
  - `(print, statement)`
  - `(print, imoam)`
  - `(check_queue, ilm)`
- `oldestinsxact` – valid for syntax that includes:
  - `(print, imrslog)`
  - `(set, imrslog)`
- `pack` – valid for syntax that includes:
- `page_chain` – valid for syntax that includes:
  - `(print, imrslog)`
- `prevfullycommitxact` – valid for syntax that includes:
  - `(print, imrslog)`
  - `(set, imrslog)`
- `ptnfirst` – valid for syntax that includes:
  - `(print, imrslog)`
  - `(set, imrslog)`
- `ptnroot` – valid for syntax that includes:
  - `(print, imrslog)`
  - `(set, imrslog)`
- `records` – valid for syntax that includes:
  - `(print, imrslog)`
- `summary` – valid for syntax that includes:
  - `(print, rows)`
  - `(print, inserted_rows)`
  - `(print, migrated_rows)`
  - `(print, cached_rows)`
  - `(print, this_row)`
  - `(print_queue, ilm)`
  - `(print, cache)`

- `tasks` – valid for syntax that includes:
  - `(print, gc)`
  - `(set, gc)`
- `threshold` – valid for syntax that includes:
- `verbose` – valid for syntax that includes:
  - `(print, ridmap)`
  - `(print, statement)`
  - `(print, rows)`
  - `(print, inserted_rows)`
  - `(print, migrated_rows)`
  - `(print, cached_rows)`
  - `(print, this_row)`
  - `(print, lobgcq)`
  - `(print_queue, ilm)`
  - `(print, qrow)`
  - `(print, cache)`

## 1.48 deallocate cursor

Makes a cursor inaccessible and releases all memory resources that are committed to that cursor.

### Syntax

```
deallocate [cursor] <cursor_name>
```

### Parameters

<cursor\_name>

is the name of the cursor to deallocate.

### Examples

#### Example 1

Deallocates the cursor named "authors\_crshr":

```
deallocate cursor authors_crshr
```

## Example 2

Also deallocates the cursor named "authors\_crsr," but omits `cursor` from the syntax:

```
deallocate authors_crsr
```

## Usage

- You can use `deallocate cursor` with an archive database.
- The SAP ASE server returns an error message if the cursor does not exist.
- You must deallocate a cursor before you can use its cursor name as part of another `declare cursor` statement.
- `deallocate cursor` has no effect on memory resource usage when specified in a stored procedure or trigger.
- You can deallocate a cursor whether it is open or closed.

## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

## Permissions

No permission is required to use `deallocate cursor`.

## Auditing

This command is not audited.

## Related Information

[close \[page 122\]](#)

[declare cursor \[page 384\]](#)

## 1.49 deallocate locator

Deletes a large object (LOB) stored in memory and invalidates its LOB locator.

### Syntax

```
deallocate locator <locator_descriptor>
```

### Parameters

<locator\_descriptor>

is a valid representation of a LOB locator: a host variable, a local variable, or the literal binary value of a locator.

### Examples

#### Example 1

Deallocates the LOB referenced by <@v>:

```
deallocate locator @v
```

### Usage

- Use `deallocate locator` within a transaction. The SAP ASE server automatically deallocates each locator at the end of a transaction.
- `deallocate locator` can conserve memory. When many LOB locators are created within a transaction, use `deallocate locator` to remove individual LOBs and locators when they are no longer needed.

See also `locator_literal`, `locator_valid`, `return_lob`, `create_locator` in *Reference Manual: Building Blocks*.

### Permissions

Any user can execute `deallocate locator`.

## Auditing

This command is not audited.

## Related Information

[truncate lob \[page 806\]](#)

## 1.50 declare

Declares the name and type of local variables for a batch or procedure.

## Syntax

Variable declaration:

```
declare @<variable_name> <datatype>
        [, @<variable_name> <datatype>]...
```

Variable assignment:

```
select @<variable> = {<expression> | <select_statement>}
        [, @<variable> = {<expression> | <select_statement>} ...]
        [from <table_list>]
        [where <search_conditions>]
        [group by <group_by_list>]
        [having <search_conditions>]
        [order by <order_by_list>]
        [compute <function_list> [by <by_list>]]
```

## Parameters

**@<variable\_name>**

must begin with @ and must conform to the rules for identifiers.

**<datatype>**

can be either a system datatype or a user-defined datatype.

## Examples

### Example 1

Declares two variables and prints strings according to the values in the variables:

```
declare @one varchar (18), @two varchar (18)
select @one = "this is one", @two = "this is two"
if @one = "this is one"
    print "you got one"
if @two = "this is two"
    print "you got two"
else print "nope"
```

```
you got one
you got two
```

### Example 2

Prints "Ouch!" if the maximum book price in the `titles` table is more than \$20.00:

```
declare @veryhigh money
select @veryhigh = max (price)
    from titles
if @veryhigh > $20
    print "Ouch!"
```

## Usage

- Assign values to local variables with a `select` statement.
- The maximum number of parameters in a procedure is 2048. The number of local or global variables is limited only by available memory. The `@` sign denotes a variable name.
- Local variables are often used as counters for `while` loops or `if...else` blocks. In stored procedures, they are declared for automatic, noninteractive use by the procedure when it executes. Local variables must be used in the batch or procedure in which they are declared.
- The `select` statement that assigns a value to the local variable usually returns a single value. If there is more than one value to return, the variable is assigned the last one. The `select` statement that assigns values to variables cannot be used to retrieve data in the same statement.
- The `print` and `raiserror` commands can take local variables as arguments.
- Users cannot create global variables and cannot update the value of global variables directly in a `select` statement.

## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

## Permissions

No permission is required to use `declare`.

## Auditing

This command is not audited.

## Related Information

[print](#) [page 640]

[raiserror](#) [page 648]

[select](#) [page 696]

[while](#) [page 863]

## 1.51 declare cursor

Defines a cursor, by associating a `select` statement with a cursor name. You can use `declare cursor` with an archive database.

### Syntax

```
declare <cursor_name>
[semi_sensitive | insensitive] [scroll | no scroll] [release_locks_on_close]
  cursor for <select_statement>
  [for {read only | update [of <column_name_list>]}]
```

### Parameters

**<cursor\_name>**

is the name of the cursor being defined.

**<select\_statement>**

is the query that defines the cursor result set. See `select` for more information.

**semi\_sensitive**



specifies that the data changes made independently of the cursor may be visible to the cursor result set. The visibility of the dependent data changes depends on the query plan chosen by the optimizer. If there is no worktable created in the plan, the data changes are visible to the result set. The default is `semi_sensitive`.

**insensitive**

specifies that the data changes made independently of the cursor are not visible to the cursor result set. If you do not specify this argument, the default is `semi_sensitive`. You cannot update an insensitive cursor.

**scroll | no scroll**

specifies whether the declared cursor is scrollable. Scrollable cursors allowing you fetch the cursor result set nonsequentially, allowing you to scan the cursor back and forth. You cannot update a scrollable cursor.

**release\_locks\_on\_close**

allows you to configure the lock-releasing behavior of each cursor so that the shared locks can be released when the cursor is closed, even if the transaction is active. This option applies to cursors of all types.

**for read only**

specifies that the cursor result set cannot be updated.

**for update**

specifies that the cursor result set is updatable.

**of <column\_name\_list>**

is the list of columns from the cursor result set (specified by the `<select_statement>`) defined as updatable. The SAP ASE server also allows you to include columns that are not specified in the list of columns of the cursor's `<select_statement>` (and excluded from the result set), but that are part of the tables specified in the `<select_statement>`.

## Examples

### Example 1

Defines a result set for the `authors_crshr` cursor that contains all authors from the `authors` table who do not reside in California:

```
declare authors_crshr cursor
for select au_id, au_lname, au_fname
from authors
where state != 'CA'
```

### Example 2

Defines a read-only result set for the `titles_crshr` cursor that contains the business-type books from the `titles` table:

```
declare titles_crshr cursor
for select title, title_id from titles
where title_id like "BU%"
for read only
```

### Example 3

Defines an updatable result set for the `pubs_crshr` cursor that contains all of the rows from the `publishers` table. It defines the address of each publisher (`city` and `state` columns) for update:

```
declare pubs_crshr cursor
for select pub_name, city, state
from publishers
for update of city, state
```

### Example 4

Defines an insensitive scrollable result set for the `stores_scrollcrshr` that contains the book stores in California:

```
declare stores_scrollcrshr insensitive scroll cursor
for select stor_id, stor_name
from stores where state = 'CA'
```

### Example 5

Defines an insensitive nonscrollable result set for the `stores_scrollcrshr` that contains the book stores in California:

```
declare stores_scrollcrshr insensitive no scroll cursor
for select stor_id, stor_name
from stores where state = 'CA'
```

## Usage

- A `declare cursor` statement must precede any `open` statement for that cursor.
- You cannot include other statements with `declare cursor` in the same Transact-SQL batch.
- You can include up to 1024 columns in an `update` clause of a client's `declare cursor` statement.
- `<cursor_name>` must be a valid SAP ASE identifier containing no more than 30 characters.
- You cannot include encrypted columns in the `for update` clause of a `declare cursor` statement.
- You cannot update a scrollable cursor.
- You cannot update an insensitive cursor.
- Because `open cursor` requires exclusive locks on qualifying rows to make sure it is using a consistent snapshot, `open cursor` can take longer than conventional cursors (or subsequent fetches) for `update` or `delete cursor` commands that include snapshot isolation levels. However, subsequent fetches return only the qualified rows, because the rows contain no additional updates or changes.

## Standards

ANSI SQL – Compliance level: Entry-level compliant.

## Permissions

No permission is required to use `declare cursor`.

## Auditing

This command is not audited.

## Related Information

[open \[page 628\]](#)

### 1.51.1 Using Scrollable Cursors

Usage information for scrollable cursors.

- If you do specify `insensitive` or `semi_sensitive` when you execute `declare cursor`, the default sensitivity is implicit, so that the cursor's sensitivity depends on the query plan chosen by the optimizer. If the query plan has any worktable created, the cursor becomes insensitive.
- If you specify the cursor's sensitivity to be semisensitive, sensitivity also depends on the query plan.
- If you specify `insensitive`, the cursor is `<read_only>`. You cannot use a `for update` clause in a cursor declaration.
- If you do not specify the cursor's scrollability, `no scroll` is implied.
- All scrollable cursors are read-only. You cannot use a `for update` clause in a cursor declaration.

### 1.51.2 Cursor select Statements

Consider the following when using `cursor select` statements.

- `<select_statement>` can use the full syntax and semantics of a Transact-SQL `select` statement, with these restrictions:
  - Must contain a `from` clause
  - Cannot contain a `compute`, `for browse`, or `into` clause
  - Can contain the `holdlock` keyword
- The `<select_statement>` can contain references to Transact-SQL parameter names or Transact-SQL local variables (for all cursor types except `language`). The names must reference the Transact-SQL parameters and local variables defined in the procedure, trigger, or statement batch that contains the `declare cursor` statement.

The parameters and local variables referenced in the `declare cursor` statement do not have to contain valid values until the cursor is opened.

- The `<select_statement>` can contain references to the `inserted` and `deleted` temporary tables that are used in triggers.


### 1.51.3 Cursor Scope

A cursor's existence depends on its scope. The scope refers to the context in which the cursor is used, that is, within a user session, within a stored procedure, or within a trigger.

Within a user session, the cursor exists only until the user ends the session. The cursor does not exist for any additional sessions started by other users. After the user logs off, the SAP ASE server deallocates the cursors created in that session.

If a `declare cursor` statement is part of a stored procedure or trigger, the cursor created within it applies to stored procedure or trigger scope and to the scope that launched the stored procedure or trigger. Cursors declared inside a trigger on an `inserted` or a `deleted` table are not accessible to any nested stored procedures or triggers. However, cursors declared inside a trigger on an `inserted` or a `deleted` table are accessible within the scope of the trigger. Once the stored procedure or trigger completes, the SAP ASE server deallocates the cursors created within it.

This shows how cursors operate between scopes:



A cursor name must be unique within a given scope. The SAP ASE server detects name conflicts within a particular scope only during runtime. A stored procedure or trigger can define two cursors with the same name if only one is executed. For example, the following stored procedure works because only one `names_crshr` cursor is defined in its scope:

```
create procedure proc2 @flag int
as
if @flag > 0
    declare names_crshr cursor
    for select au_fname from authors
else
    declare names_crshr cursor
    for select au_lname from authors
return
```

## 1.51.4 Result Set

A cursor result set is generated as the rows are returned through a `fetch` of that cursor. This means that a cursor `select` query is processed like a normal `select` query. This process, known as a cursor scan, provides a faster turnaround time and eliminates the need to read rows that are not required by the application.

Cursor result set rows may not reflect the values in the actual base table rows. For example, a cursor declared with an `order by` clause usually requires the creation of an internal table to order the rows for the cursor result set. The SAP ASE server does not lock the rows in the base table that correspond to the rows in the internal table, which permits other clients to update these base table rows. In this case, the rows returned to the client from the cursor result set are not in sync with the base table rows.

A restriction of cursor scans is that they can only use the unique indexes of a table. However, if none of the base tables referenced by the cursor result set are updated by another process in the same lock space as the cursor, the restriction is unnecessary. The SAP ASE server allows the declaration of cursors on tables without unique indexes, but any attempt to update those tables in the same lock space closes all cursors on the tables.

## 1.51.5 Updatable Cursors

After defining a cursor using `declare cursor`, the SAP ASE server determines whether the cursor is updatable or read-only.

If:

- A cursor is updatable – you can update or delete rows through the cursor; that is, use `<cursor_name>` to do a position `update` or `delete`.
- A cursor is read-only – you cannot use `<cursor_name>` to perform a position `update` or `delete`.

Use the `for update` or `for read only` clause to explicitly define a cursor as updatable or read-only. You cannot define an updatable cursor if its `<select_statement>` contains one of the following constructs:

- `distinct` option
- `group by` clause
- Aggregate function
- Subquery
- `union` operator
- `at isolation read uncommitted` clause

If you do not specify either the `for update` or the `read only` clause, the SAP ASE server checks to see whether the cursor is updatable.

The SAP ASE server also defines a cursor as read-only if you declare a language- or server-type cursor that includes an `order by` clause as part of its `<select_statement>`. The SAP ASE server handles updates differently for client- and execute-type cursors, thereby eliminating this restriction.

When using updatable cursors and allpages locking:

- If you do not specify a `<column_name_list>` with the `for update` clause, all the specified columns in the query are updatable. The SAP ASE server attempts to use unique indexes for updatable cursors when scanning the base table. For cursors, the SAP ASE server considers an index containing an `IDENTITY` column to be unique, even if it is not so declared.

- If you do not specify the `for update` clause, the SAP ASE server chooses any unique index, although it can also use other indexes or table scans if no unique index exists for the specified table columns. However, when you specify the `for update` clause, the SAP ASE server must use a unique index defined for one or more of the columns to scan the base table. If none exists, it returns an error.
- In most cases, include only columns to be updated in the `<column_name_list>` of the `for update` clause. If the table has only one unique index, you do not need to include its column in the `for update <column_name_list>`; the SAP ASE server finds it when it performs the cursor scan. If the table has more than one unique index, do not include any of them in the `for update <column_name_list>`. This allows the SAP ASE server to use that unique index for its cursor scan, which helps prevent an update anomaly called the Halloween problem. Another way to prevent the Halloween problem is to create tables with the `unique auto_identity index` database option. See the *System Administration Guide*. The Halloween problem occurs when a client updates a column of a cursor result set row that defines the order in which the rows are returned from the base tables. For example, if the SAP ASE server accesses a base table using an index, and the index key is updated by the client, the updated index row can move within the index and be read again by the cursor. This is a result of an updatable cursor only logically creating a cursor result set. The cursor result set is actually the base tables that derive the cursor.

If you specify the `read only` option, you cannot update the cursor result set using the cursor name to perform update or delete.

## 1.51.6 Releasing Locks at Cursor Close

`release_locks_on_close` has no effect if the cursor scan occurs at isolation level 1.

The default behavior at isolation levels 2 and 3 if the transaction is committed or rolled back before the cursor is closed is for the SAP ASE server to release the shared locks acquired by the cursor until that point, with the exception of the lock on the last fetched row. If you use `release_on_locks_close`, the shared locks acquired by the cursor exist until the cursor is closed.

Use `sp_cursorinfo` to determine if a cursor was declared with the `release_on_locks_close` parameter:

```
1) sp_cursorinfo
2> go
```

```
Cursor name 'c' is declared at nesting level '0'.
The cursor is declared as NON-SCROLLABLE
RELEASE_LOCKS_ON_CLOSE cursor.
The cursor id is 917505.
The cursor has been successfully opened 0 times.
The cursor will remain open when a transaction is
committed or rolled back.
```

## 1.52 delete

Removes rows from a table.

### Syntax

```
delete
  [top <unsigned_integer>]
  [from [[<database>.<owner>.]<table_name> | <view_name>]
  [where <search_conditions>]
  [plan "<abstract plan>"]
```

```
delete [[<database>.<owner>.]<table_name> | <view_name>]
  [from [[<database>.<owner>.]<table_name> | <view_name> [readpast]
        [(index {<index_name> | <table_name>}
          [prefetch <size>][lru|mru])]]
        [readpast]
  [, [[<database>.<owner>.]<table_name> | <view_name> [readpast]]
     [(index {<index_name> | <table_name>}
       [prefetch <size>][lru|mru])
     [readpast]] ...]
  [where <search_conditions>]]
  [plan "<abstract plan>"]
```

```
delete [from] [[<database>.<owner>.]<table_name> | <view_name>]
  where current of <cursor_name>
```

### Parameters

#### top <unsigned\_integer>

Is used to limit the number of rows to the number of rows specified by <unsigned\_integer>.

#### from

When used:

- After `delete` – is an optional keyword used for compatibility with other versions of SQL.
- After <table\_name> or <view\_name> – lets you name more than one table or view to use with a `where` clause when specifying which rows to delete. This `from` clause allows you to delete rows from one table based on data stored in other tables, giving you much of the power of an embedded `select` statement.

#### <table\_name> | <view\_name>

is the name of the table or view from which to remove rows. Specify the database name if the view or table is in another database, and specify the owner's name if more than one view or table of that name exists in the database. The default value for <owner> is the current user, and the default value for <database> is the current database.

**where**

is a standard `where` clause.

**readpast**

specifies that the `delete` command skip all pages or rows on which incompatible locks are held, without waiting for locks or timing out. For datapages-locked tables, `<readpast>` skips all rows on pages on which incompatible locks are held; for datarows-locked tables, it skips all rows on which incompatible locks are held.

**index <index\_name>**

specifies an index to use for accessing `<table_name>`. You cannot use this option when you delete from a view.

**prefetch <size>**

specifies the I/O size, in kilobytes, for tables that are bound to caches with large I/Os configured. You cannot use `prefetch` when you delete from a view. `sp_helpcache` shows the valid sizes for the cache an object is bound to, or for the default cache.

When using `prefetch` and designating the prefetch size (`<size>`), the minimum is 2K and any power of two on the logical page size up to 16K. `prefetch` size options, in kilobytes, are:

Logical Page Size	Prefetch Size Options
2	2, 4, 8 16
4	4, 8, 16, 32
8	8, 16, 32, 64
16	16, 32, 64, 128

The `prefetch` size specified in the query is only a suggestion. To allow the size specification, configure the data cache at that size. If you do not configure the data cache to a specific size, the default `prefetch` size is used.

To configure the data cache size, use `sp_cacheconfigure`.

**i Note**

You cannot use `prefetch` for remote servers if you enable CIS.

**lru | mru**

specifies the buffer replacement strategy to use for the table. Use `lru` to force the optimizer to read the table into the cache on the MRU/LRU (most recently used/least recently used) chain. Use `mru` to discard the buffer from cache, and replace it with the next buffer for the table. You cannot use this option when you delete from a view.

**plan "<abstract plan>"**

specifies the abstract plan to use to optimize the query. It can be a full or partial plan, specified in the abstract plan language. See *Creating and Using Abstract Plans* in the *Performance and Tuning Guide: Optimizer and Abstract Plans*.

**where current of <cursor\_name>**



causes the SAP ASE server to delete the row of the table or view indicated by the current cursor position for `<cursor_name>`.

## Examples

### Example 1

Deletes all rows from the `authors` table:

```
delete authors
```

### Example 2

Deletes a row or rows from the `authors` table:

```
delete from authors where au_lname = "McBadden"
```

### Example 3

Deletes rows for books written by Bennet from the `titles` table:

```
delete titles
from titles, authors, titleauthor
where authors.au_lname = 'Bennet'
      and authors.au_id = titleauthor.au_id
      and titleauthor.title_id = titles.title_id
```

The `pubs2` database includes a trigger (`deltitle`) that prevents the deletion of the titles recorded in the `sales` table; drop this trigger for this example to work.

### Example 4

Deletes a row from the `titles` table currently indicated by the cursor `title_crshr`:

```
delete titles where current of title_crshr
```

### Example 5

Determines which row has a value of 4 for the `IDENTITY` column and deletes it from the `authors` table. Note the use of the `syb_identity` keyword instead of the actual name of the `IDENTITY` column:

```
delete authors where syb_identity = 4
```

### Example 6

Deletes rows from `authors`, skipping any locked rows:

```
delete from authors from authors readpast
where state = "CA"
```

### Example 7

Deletes rows from `stores`, skipping any locked rows. If any rows in `authors` are locked, the query blocks on these rows, waiting for the locks to be released:

```
delete stores from stores readpast, authors
where stores.city = authors.city
```

## Example 8

```
create table t1 (c1 int, c2 int)
create index idx on t1(c1)
create procedure test_p_delete @var1 INT, @var2 INT as
begin
    delete from t1 where c1=@var1 with recompile
end
```

## Usage

Queries that use `update` and `delete` on views with a `union all` clause are always resolved using worktables in `tempdb`.

The `index`, `prefetch`, and `lru | mru` options override the choices made by the SAP ASE optimizer. Use these options with caution, and always check the performance impact with `set statistics io on`. See *Using the set statistics Command* in *Performance and Tuning Guide: Monitoring and Analyzing*.

You can define a trigger to take a specified action when a `delete` command is issued on a specified table.

## Standards

ANSI SQL – Compliance level: Entry-level compliant. The use of more than one table in the `from` clause and qualification of table name with database name are Transact-SQL extensions.

`readpast` is a Transact-SQL extension.

## Permissions

If `set ansi_permissions` is on, you must have `select` permission on all columns appearing in the `where` clause, in addition to the regular permissions required for `delete` statements. By default, `ansi_permissions` is off.

The following describes permission checks for `delete` that differ based on your granular permissions settings.

Setting	Description
---------	-------------

<b>Enabled</b>	With granular permissions enabled, you must be the table or view owner, or a user with <code>delete</code> permission, or a user with <code>delete any table</code> permission.
----------------	---

<b>Disabled</b>	With granular permissions disabled, you must have <code>delete</code> permission, be the table owner, or a user with <code>sa_role</code> .
-----------------	---

## Auditing

Enable object-specific `delete` auditing option to audit deletes from a specific table or view. Enable user-specific `table_access` or `view_access` auditing options to audit table or view access by a specific user.

Values in `event` and `extrainfo` columns from the `sysaudits` table are:

Audit option	Event	Command or access audited	Information in <code>extrainfo</code> :
<code>delete</code> <code>table_access</code>	18	<code>delete</code> from a table	<ul style="list-style-type: none"><li>• <b>Roles</b> – current active roles</li><li>• <b>Full command text</b> – full text of <code>delete</code> command</li></ul>
<code>delete</code> <code>view_access</code>	19	<code>delete</code> from a view	<ul style="list-style-type: none"><li>• <b>Previous value</b> – NULL</li><li>• <b>Current value</b> – NULL</li><li>• <b>Other information</b> – a list of parameter name value pairs</li><li>• <b>Proxy information</b> – original login name, if a <code>set proxy</code> is in effect</li></ul>

Full command text and parameter names/values are included in `extrainfo`. For example:

```
sa_role sso_role oper_role sybase_ts_role mon_role; delete * from t1
  where c1 = @val1 and c2 = @val2; ; ; @val1=10, @val2 = 20; ;
sa/ase;
```

For more information about auditing, see *Security Administration Guide > Auditing*.

## Related Information

[commit \[page 123\]](#)

[declare cursor \[page 384\]](#)

[drop table \[page 457\]](#)

[drop trigger \[page 462\]](#)

[fetch \[page 513\]](#)

[insert \[page 572\]](#)

[open \[page 628\]](#)

[rollback \[page 690\]](#)

[select \[page 696\]](#)

[truncate table \[page 809\]](#)

[update \[page 819\]](#)

[where Clause \[page 855\]](#)

## 1.52.1 delete Restrictions

Restrictions for using `delete`

- You cannot use `delete` with a multitable view (one whose `from` clause names more than one table), even though you may be able to use `update` or `insert` on that same view. Deleting a row through a multitable view changes multiple tables, which is not permitted. `insert` and `update` statements that affect only one base table of the view are permitted.
- The SAP ASE server treats two different designations for the same table in a `delete` as two tables. For example, the following `delete` issued in `pubs2` specifies `discounts` as two tables (`discounts` and `pubs2..discounts`):

```
delete discounts
from pubs2..discounts, pubs2..stores
where pubs2..discounts.stor_id =
      pubs2..stores.stor_id
```

In this case, the join does not include `discounts`, so the `where` condition remains true for every row; the SAP ASE server deletes all rows in `discounts` (which is not the desired result). To avoid this problem, use the same designation for a table throughout the statement.

- If you are deleting a row from a table that is referenced from other tables via referential constraints, the SAP ASE server checks all the referencing tables before permitting the delete. If the row you are attempting to delete contains a primary key that is being used as a foreign key by one of the referencing tables, the delete is not allowed.

## 1.52.2 Deleting All Rows from a Table

Considerations for deleting all rows from a table.

- If you do not use a `where` clause, all rows in the table named after `delete [from]` are removed. The table, though empty of data, continues to exist until you issue a `drop table` command.
- `truncate table` and `delete` without a row specification are functionally equivalent, but `truncate table` is faster. `delete` removes rows one at a time and logs these transactions. `truncate table` removes entire data pages, and the rows are not logged. Both `delete` and `truncate table` reclaim the space occupied by the data and its associated indexes.
- You cannot use the `truncate table` command on a partitioned table. To remove all rows from a partitioned table, either use the `delete` command without a `where` clause, or unpartition the table before issuing `truncate table`.

## 1.52.3 delete and Transactions

In chained transaction mode, each `delete` statement implicitly begins a new transaction if no transaction is currently active.

Use `commit` to complete any deletes, or use `rollback` to undo the changes. For example:

```
delete from sales where date < '01/01/06'
if exists (select stor_id
          from stores
          where stor_id not in
              (select stor_id from sales))
    rollback transaction
else
    commit transaction
```

This batch begins a transaction (using the chained transaction mode) and deletes rows with dates earlier than Jan. 1, 2006 from the `sales` table. If it deletes all sales entries associated with a store, it rolls back all the changes to `sales` and ends the transaction. Otherwise, it commits the deletions and ends the transaction. For more information about the chained mode, see the *Transact-SQL Users Guide*.

## 1.52.4 Using the where current of Parameter

Use the clause `where current of` with cursors.

- Before deleting rows using the clause `where current of`, first define the cursor with `declare cursor` and open it using the `open` statement. Use one or more `fetch` statements to position the cursor on the row to delete. The cursor name cannot be a Transact-SQL parameter or local variable. The cursor must be an updatable cursor, or the SAP ASE server returns an error. Any deletion to the cursor result set also affects the base table row from which the cursor row is derived. You can delete only one row at a time using the cursor.
- You cannot delete rows in a cursor result set if the cursor's `select` statement contains a join clause, even though the cursor is considered updatable. The `<table_name>` or `<view_name>` specified with a `delete...where current of` must be the table or view specified in the first `from` clause of the `select` statement that defines the cursor.
- After the deletion of a row from the cursor's result set, the cursor is positioned before the next row in the cursor's result set. You must issue a `fetch` to access the next row. If the deleted row is the last row of the cursor result set, the cursor is positioned after the last row of the result set. The following describes the position and behavior of open cursors affected by a `delete`:
  - If a client deletes a row (using another cursor or a regular `delete`) and that row represents the current cursor position of other opened cursors owned by the same client, the position of each affected cursor is implicitly set to precede the next available row. However, one client cannot delete a row representing the current cursor position of another client's cursor.
  - If a client deletes a row that represents the current cursor position of another cursor defined by a join operation and owned by the same client, the SAP ASE server accepts the `delete` statement. However, it implicitly closes the cursor defined by the join.

## 1.52.5 Using readpast

Considerations for using `readpast`.

- `readpast` allows `delete` commands on data-only-locked tables to proceed without being blocked by incompatible locks held by other tasks.
  - On datarows-locked tables, `readpast` skips all rows on which shared, update, or exclusive locks are held by another task.
  - On datapages-locked tables, `readpast` skips all pages on which shared, update, or exclusive locks are held by another task.
- Commands specifying `readpast` block if there is an exclusive table lock.
- If the `readpast` option is specified for an allpages-locked table, it is ignored. The command blocks as soon as it finds an incompatible lock.
- If the session-wide isolation level is 3, the `readpast` option is silently ignored. The command executes at level 3. The command blocks on any rows or pages with incompatible locks.
- If the transaction isolation level for a session is 0, a `delete` command using `readpast` does not issue warning messages. For datapages-locked tables, `delete` with `readpast` modifies all rows on all pages that are not locked with incompatible locks. For datarows-locked tables, it affects all rows that are not locked with incompatible locks.
- If the `delete` command applies to a row with two or more text columns, and any text column has an incompatible lock on it, `readpast` locking skips the row.

## 1.53 delete statistics

Removes statistics from the `sysstatistics` system table.

### Syntax

```
delete [shared] statistics <table_name>
      [partition <data_partition_name>]
      [(<column_name>[, <column_name>] ...)]
```

### Parameters

#### **shared**

removes simulated statistics information from `sysstatistics` in the master database.

#### **<table\_name>**

removes statistics for all columns in the table.

`<data_partition_name>`

deletes all statistics for the data partition. Global statistics are not deleted.

`<column_name>`

removes statistics for the specified column.

## Examples

### Example 1

Deletes the densities, selectivities, and histograms for all columns in the `titles` table:

```
delete statistics titles
```

### Example 2

Deletes densities, selectivities, and histograms for the `pub_id` column in the `titles` table:

```
delete statistics titles (pub_id)
```

### Example 3

Deletes densities, selectivities, and histograms for the `smallsales` partition of the `titles` table:

```
delete statistics titles partition smallsales
```

### Example 4

Deletes densities, selectivities, and histograms for `pub_id`, `pubdate`, without affecting statistics on the single-column `pub_id` or the single-column `pubdate`:

```
delete statistics titles (pub_id, pubdate)
```

### Example 5

Deletes densities, selectivities, and histograms for the column `pub_id` and for the data partition `smallsales`:

```
delete statistics titles partition smallsales (pub_id)
```

## Usage

- `delete statistics` does not affect statistics in the `systabstats` table.
- `delete statistics` on a data partition does not delete global statistics.
- When you issue the `drop table` command, the corresponding rows in `sysstatistics` are dropped. When you use `drop index`, the rows in `sysstatistics` are not deleted. This allows the query optimizer to continue to use index statistics without incurring the overhead of maintaining the index on the table.

### ⚠ Caution

Densities, selectivities, and histograms are essential to good query optimization. The `delete statistics` command is provided as a tool to remove statistics not used by the optimizer. If you

inadvertently delete statistics needed for query optimization, run `update statistics` on the table, index, or column.

- Loading simulated statistics with the `optdiag` utility command adds a small number of rows to `master..sysstatistics` table. If the simulated statistics are no longer in use, use the `delete shared statistic` command to drop the information in `master..sysstatistics`.

See also `optdiag` in the *Utility Guide*.

## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

## Permissions

The permission checks for `delete statistics` differ based on your granular permissions settings.

Setting	Description
---------	-------------

Enabled	With granular permissions enabled, you must be the table owner, or a user with <code>delete statistics</code> permission.
---------	---

Disabled	With granular permissions disabled, you must be the table owner, a user with <code>sa_role</code> , or a user with <code>delete statistics</code> permission.
----------	---

`delete statistics` permission can be granted or transferred to anyone by the table owner or system administrator.

## Auditing

This command is not audited.

## Related Information

[create index \[page 192\]](#)

[drop index \[page 439\]](#)

[drop table \[page 457\]](#)

[grant \[page 520\]](#)

[revoke \[page 672\]](#)

[update \[page 819\]](#)

[update statistics \[page 839\]](#)



## 1.54 disk init

Makes a physical device or file usable by the SAP ASE server.

### Syntax

```
disk init
  name = "<device_name>",
  physname = {'<physical_name>' | '<cache_name>'}
  skip_alloc = {true | false},
  [vdevno = <virtual_device_number>],
  size = <number_of_blocks>
  [, type = 'inmemory' | 'imrslog' | 'nvcache']
  [, vstart = <virtual_address>
    , cntrltype = <controller_number>]
  [, dsync = {true | false}]
  [, directio = {true | false}]
  [, instance = "<instance_name>"]
```

### Parameters

#### <device\_name>

is the name of the database device or file. The name must conform to the rules for identifiers and must be enclosed in single or double quotes. This name is used in the `create database` and `alter database` commands.

#### physname = {'<physical\_name>' | '<cache\_name>'}

specifies the full specification of the database device or cache. This name must be enclosed in single or double quotes. When the physical device path is relative, `disk init` returns a warning.

<cache\_name> is the name of the cache on which you are creating the disk.

#### skip\_alloc = {true | false}

is a Boolean parameter for the `disk init` command. It is supported for devices created on non-Windows file systems and on Windows raw systems. When `skip_alloc` is set to `true`, users can avoid initialization of pages with zeros. The default of `skip_alloc` is `false`.

#### vdevno = <virtual\_device\_number>

specifies the virtual device number, which must be unique among the database devices associated with the SAP ASE server. The device number 0 is reserved for the master device. Otherwise, valid device numbers must be between 1 and 2,147,483,647.

To determine the virtual device number, look at the `device_number` column of the `sp_helpdevice` report, and use the next unused integer.

#### size = <number\_of\_blocks>

is the amount of space to allocate to the new device. The following are example unit specifiers, using uppercase, lowercase, and single and double quotes interchangeably: 'k' or "K" (kilobytes), "m" or 'M' (megabytes), "g" or "G" (gigabytes), and 't' or 'T' (terabytes). You should always include a unit specifier. Quotes are optional if you do not include a unit specifier. However, you must use quotes if you include a unit specifier. Acceptable values are:

- 5120 = 10 MB
- "5120" = 10 MB
- "10M" = 10 MB

**type = 'inmemory' | 'imrslog' | 'nvcache'**

allows you to specify the type of device you are creating

- `inmemory` – an in-memory device
- `imrslog` – a device to hold the `sysimrslogs` system table
- `nvcache` – a device for non-volatile cache

The `sysimrslogs` system table contains the on-disk row store log. The on-disk row store log is a persistent log that contains changes to the in-memory row store.

**vstart = <virtual\_address>**

is the starting virtual address, or the offset, for the SAP ASE server to begin using the database device. The following are example unit specifiers, using uppercase, lowercase, and single and double quotes interchangeably: 'k' or "K" (kilobytes), "m" or 'M' (megabytes), "g" or "G" (gigabytes), and 't' or 'T' (terabytes). You should always include a unit specifier. Quotes are optional if you do not include a unit specifier. However, you must use quotes if you include a unit specifier.

The size of the offset depends on how you enter the value for `vstart`.

- If you do not specify a unit size, `vstart` uses 2K pages for its starting address. For example, if you specify `vstart = 13`, the SAP ASE server uses 13 \* 2K pages as the offset for the starting address.
- If you specify a unit value, `vstart` uses the unit value as the starting address. For example, if you specify `vstart = "13M"`, the SAP ASE server sets the starting address offset at 13 MB.

The default value (and usually the preferred value) of `vstart` is 0. If the specified device does not have the sum of `vstart + size` blocks available, the `disk init` command fails. If you are running the Logical Volume Manager on an AIX operating system, `vstart` should be 2. Specify `vstart` only if instructed to do so by SAP Technical Support.

**cntrltype = <controller\_number>**

specifies the disk controller. Its default value is 0. Reset `cntrltype` only if instructed to do so by SAP Technical Support.

**dsync = {true | false}**

specifies whether writes to the database device are flushed to the storage media, or are buffered only when using operating system files. This option is meaningful only when you are initializing an operating system file; it has no effect when initializing devices on

a raw partition. By default, all operating system files are initialized with `dsync` set to `true`.

**directio = {true | false}**

allows you to configure the SAP ASE server to transfer data directly to disk, bypassing the operating system buffer cache. The SAP ASE server passes the device options to Backup Server, which enables Backup Server to access the database device with the appropriate `directio` option.

`directio` is a static parameter that requires a restart of the SAP ASE server to take effect.

By default, `directio` is set to `true` for clustered and nonclustered servers.

The `directio` parameter is ignored for raw devices.

**instance = "<instance\_name>"**

(clusters only) specifies the device as private and sets its owning instance to `<instance_name>`.

## Examples

### Example 1

Does not initialize pages with zeros:

```
disk init name="d2",
physname="/usr/sybase/devices/d3.dat",
skip_alloc="true",
size="10G"
```

SAP ASE servers do not allocate space during disk initialization if `skip_alloc` is set to `true`.

### Example 2

Initializes 10 MB of a disk on a UNIX system:

```
disk init
name = "user_disk",
physname = "/dev/rxy1a",
vdevno = 2, size = 5120
```

### Example 3

Initializes 10 MB of a disk on a UNIX operating system file. The SAP ASE server opens the device file with the `dsync` setting, and writes to the file are guaranteed to take place directly on the storage media:

```
disk init
name = "user_file",
physname = "/usr/u/sybase/data/userfile1.dat",
vdevno = 2, size = 5120, dsync = true
```

### Example 4

Creates a device named "user\_disk" that uses `directio` to write data directly to disk:

```
disk init
name = "user_disk",
```

```
physname = "/usr/u/sybase/data/userfile1.dat",
size = 5120,
directio= true
```

### Example 5

Creates a device named `inmemory_dev`:

```
disk init
name = inmemory_dev,
physname = 'imdb_cache',
size = '3G',
type = 'inmemory'
```

### Example 6

Creates a device of type `imrslog` to be used for `sysimrslogs` catalog:

```
disk init
name = "imrslogdev1",
physname = "/usr/u/sybase/devices/imrslogdev1.dat",
size = "200g", type = imrslog
```

### Example 7

Creates a 30 MB device of type `nvcache` for use with non-volatile cache:

```
disk init name = "nv1",
physname="/usr/u/sybase/data/nv1.dat",
size="30M",
type="nvcache"
```

See `sp_nvcacheconfig` in *Reference Manual: Procedures*, and *System Administration Guide : Volume 2 > Configuring Data Caches > Non-Volatile Cache Management* for details on how to creating and managing non-volatile cache.

## Usage

- Generally, SAP recommends that you create databases on character-based devices (also known as raw devices). SAP ASE versions 15.0 and later allow you to create them on block devices if you have `dsync` or `directio I/O` set. `dsync` or `directio I/O` guarantee data consistency on block devices. That is, a write is successful only when data is on disk.
- Use `skip_alloc` to expedite crash recovery on non-NT file systems and on NT raw systems. Also, using `skip_alloc` with the `directio` feature creates devices faster and improves durability of updates. Regardless of space availability, `skip_alloc` always prints a warning message about making sure the SAP ASE server has the required space for future use.
- The master device is initialized by the installation program; you need not initialize this device with `disk init`.
- Devices created with `disk init` have restricted permissions.
- To successfully complete disk initialization, the "sybase" user must have the appropriate operating system permissions on the device that is being initialized.
- You can specify the `<size>` as a `float` datatype, but it is rounded down to the nearest whole value.
- If you do not use a unit specifier for size, `disk init` uses the virtual page size of 2K.

- The minimum size of a disk piece that you can initialize using `disk init` is the larger of:
  - One megabyte
  - One allocation unit of the server's logical page size
- `directio` and `dsync` are mutually exclusive. If a device has `dsync` set to true, you cannot set `directio` to true for this device. To enable `directio` for a device, you must first reset `dsync` to false.
- `directio` is not available on all platforms. If you issue `disk init` with the `directio` parameter on a platform on which it is not supported, the SAP ASE server issues the message `No such parameter: 'directio'`.
- Use `disk init` for each new database device. Each time `disk init` is issued, a row is added to `master..sysdevices`. A new database device does not automatically become part of the pool of default database storage. Use `sp_diskdefault` to assign default status to a database device.
- Back up the `master` database with the `dump database` or `dump transaction` command after each use of `disk init`. This makes recovery easier and safer in case `master` is damaged. If you add a device with `disk init` and fail to back up `master`, you may be able to recover the changes by using `disk reinit`, then stopping and restarting the SAP ASE server.
- Assign user databases to database devices using the `on` clause of the `create database` or `alter database` command.
- The preferred method for placing a database's transaction log (the system table `syslogs`) on a different device than the one on which the rest of the database is stored is to use the `log on` extension to `create database`. Alternatively, you can name at least two devices when you create the database, then execute `sp_logdevice`. You can also use `alter database` to extend the database onto a second device, then run `sp_logdevice`. The `log on` extension immediately moves the entire log to a separate device. The `sp_logdevice` method retains part of the system log on the original database device until transaction activity causes the migration to become complete.
- For a report on all SAP ASE devices on your system (both database and dump devices), execute `sp_helpdevice`.
- Use `sp_dropdevice` to remove a database device. You must first drop all existing databases on that device.

See also `sp_diskdefault`, `sp_dropdevice`, `sp_helpdevice`, `sp_logdevice` in *Reference Manual: Procedures*.

## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

## Permissions

The permission checks for `disk init` differ based on your granular permissions settings. You must be using the `master` database to use `disk init`.

Setting	Description
Enabled	With granular permissions enabled, you must be a user with <code>manage disk</code> privilege.
Disabled	With granular permissions disabled, you must be a user with <code>sa_role</code> . <code>disk init</code> permission is not transferable.

## Auditing

You can enable `disk` auditing option to audit this command. Values in `event` and `extrainfo` columns from the `sysaudits` table are:

Information	Values
Audit option	<code>disk</code>
Event	20
Command or access audited	<code>disk init</code>
Information in <code>extrainfo</code>	<ul style="list-style-type: none"> <li>• <b>Roles</b> – current active roles</li> <li>• <b>Full command text</b> – full text of <code>disk init</code> command</li> <li>• <b>Previous value</b> – NULL</li> <li>• <b>Current value</b> – NULL</li> <li>• <b>Other information</b> – a list of parameter names and values</li> <li>• <b>Proxy information</b> – original login name, if <code>set proxy</code> is in effect</li> </ul>

Full command text and parameters are included in `extrainfo`. For example:

```
sa_role sybase_ts_role; disk init name=@p_name, physname=@p_physname,
vdevno=@p_vdevno, size=@p_dsize; ; ; @p_name = test_db_dev,
@p_physname = /lnxbarr02_tst2/quasrspace/pd20355885/d8.dbs,
@p_vdevno = 9, @p_dsize = 32m; ; user0/ase;;
```

For more information about auditing, see *Security Administration Guide > Auditing*.

## Related Information

- [alter database \[page 14\]](#)
- [create database \[page 140\]](#)
- [disk refit \[page 413\]](#)
- [disk mirror \[page 409\]](#)
- [disk reinit \[page 415\]](#)
- [disk remirror \[page 420\]](#)
- [disk resize \[page 423\]](#)

[disk unmirror \[page 425\]](#)

[dump database \[page 470\]](#)

[dump transaction \[page 490\]](#)

[load database \[page 585\]](#)

[load transaction \[page 603\]](#)

## 1.54.1 Using `dsync` with `disk init`

Considerations for using `dsync`.

### i Note

Do not set `dsync` to `false` for any device that stores critical data. The only exception is `tempdb`, which can safely be stored on devices for which `dsync` is set to `false`.

- (UNIX only) On raw devices, you cannot:
  - Set `directio` or `dsync` to `true`
  - Set `directio` or `dsync` via the `sp_deviceattr` stored procedure to `true`.

### i Note

For HPUX, only the `dsync` option applies.

Doing so returns a message such as:

```
You cannot set option dsync for raw device 'dev/raw/raw235'
```

or:

```
You cannot set attribute dsync for raw device 'myrawdisk1'
```

- When `dsync` is on, writes to the database device are guaranteed to take place on the physical storage media, and the SAP ASE server can recover data on the device in the event of a system failure.
- When `dsync` is off, writes to the database device may be buffered by the UNIX file system. The UNIX file system may mark an update as being completed, even though the physical media has not yet been modified. In the event of a system failure, there is no guarantee that data updates have ever taken place on the physical media, and the SAP ASE server may be unable to recover the database.
- `dsync` is always on for the master device file.
- Turn off the `dsync` value only when databases on the device need not be recovered after a system failure. For example, you may consider turning `dsync` off for a device that stores only the `tempdb` database.
- The SAP ASE server ignores the `dsync` setting for devices stored on raw partitions—writes to those device are guaranteed to take place on the physical storage media, regardless of the `dsync` setting.
- `disk reinit` ensures that `master..sysdevices` is correct if the `master` database has been damaged or if devices have been added since the last dump of `master`.

## 1.54.2 Creating Devices for In-Memory and Relaxed Durability Databases

Considerations for creating devices for in-memory and relaxed durability databases.

- The logical name of the in-memory device cannot be the same as the name of the cache on which a device is created.
- In-memory devices are reserved for the first in-memory database you assign to it.
- You must use the physical device name as the logical name of the in-memory device.
- The logical name of the in-memory device must be unique across all devices.
- You cannot:
  - Use these parameters when you create an in-memory device: `vstart`, `cntrltype`, `dsync`, `directio`, and `skip_alloc`.
  - Create an in-memory device that is larger than the cache on which it is created.
  - Create an in-memory device from a regular named cache, including the default data cache.
  - Increase the size of an in-memory device once it is created. However, you can use `sp_cacheconfig` to increase the size of the in-memory cache, and use `disk_init` to create new in-memory devices.
  - Use these commands against in-memory devices: `disk_resize`, `disk_mirror`, `disk_remirror`, `disk_unmirror`, `disk_refit`, and `disk_reinit`.
  - Use the `sp_deviceattr` and `sp_diskdefault` system procedures on disk devices.

## 1.54.3 Creating Devices for In-Memory Row Storage Caches

- Devices of type `imrslog` are created on the `imrslogsegment` segment, and cannot be shared across other segments.
- `imrslog` devices are log-only. That is, they cannot be mixed log-and data devices.
- The `imrslog` device are dedicated to the `imrslogsegment`. The server never considers `imrslog` devices for space allocation to other user or system objects.
- You can use operating system files or raw devices for `imrslog` devices. However, you cannot use in-memory storage cache devices for the on-disk row store log.
- You can use `disk_resize` to expand `imrslog` devices, and you can use `sp_dbextend` to increase space on `imrslogsegment` to ensure that transactional activity is not impeded by insufficient space on `imrslog`.
- You can use the `skip_alloc`, `dsync`, `directio`, and so on database options on `imrslog` similarly as other devices. SAP ASE chooses these parameters as the defaults for non-recoverable devices for enhanced performance (you can alter these parameters according to your site requirements):
  - `skip_alloc` set to `false` – Improves performance for creating `imrslog` devices (initialized when you run `create` or `alter database`). The default `skip_alloc` setting for other devices is `false`.
  - `dsync` set to `true` for file-system devices – The objects created on segments to which these non-recoverable devices are bound are themselves non-recoverable objects. Not requiring a synchronous write through the file-system buffer cache for `imrslog` devices improves performance. The default setting for `dsync` for other devices is `true`, which allows for reliable crash recovery even when you use file-system devices.



- `directio` is set to false for file-system devices – Improves the performance of I/O to `imrslog` devices. The I/O goes through the file-system buffer cache instead of writing directly to the physical device. The default setting for `directio` for other devices is false.
- Use `sp_helpdevice` and the `monDeviceIO` and `monDeviceSpaceUsage` monitoring tables to report information about in-memory row caches (be aware that the data reported in these monitoring tables is adjusted to reflect the I/O characteristics of these devices).

You cannot use:

- `sp_addsegment` or `sp_extendsegment` to assign `imrslog` devices to an existing user-defined segment.
- `sp_diskdefault` to make `imrslog` devices the default database device.
- A cache name for the `disk init ... physname` clause when creating `imrslog.imrslog` devices must be physical disk devices, not in-memory cache devices.
- Some device I/O-related `sp_dboption` parameters with `imrslog` devices. For such devices, SAP ASE supports these parameters for `imrslog` devices:
  - `skip_alloc` must be set to false (the default)
  - `dsync` must be set to true for physical file-system `imrslog` devices. (the default for file-system devices.)
  - `directio` must be set to true on file system devices even on SMP installations (the default is false for file system devices on non-clustered installations)
- These disk device related commands with `imrslog` devices:
  - `disk mirror`
  - `disk remirror`
  - `disk unmirror`
  - `disk refit`
  - `disk reinit`

## 1.55 disk mirror

Creates a software mirror that immediately takes over when the primary device fails.

### Syntax

```
disk mirror
  name = "<device_name>",
  mirror = "<physicalname>"
  [, writes = {serial | noserial}]
  [clear = {TRUE | FALSE}]
```

## Parameters

**name = "<device\_name>"**

specifies the name of the database device to mirror. This is recorded in the `name` column of the `sysdevices` table. The name must be enclosed in single or double quotes.

**mirror = "<physicalname>"**

specifies the full path name of the database mirror device that is to be your secondary device. It must be enclosed in single or double quotes. If the secondary device is a file, `<physicalname>` should be a path specification that clearly identifies the file, which the SAP ASE server creates. The value of `<physicalname>` cannot be an existing file.

**writes = {serial | noserial}**

allows you to choose whether to enforce serial writes to the devices. In the default case (`serial`), the write to the primary database device is guaranteed to finish before the write to the secondary device begins. If the primary and secondary devices are on different physical devices, serial writes can ensure that at least one of the disks is unaffected in the event of a power failure. `serial` writes are generally slower than `noserial` writes.

**clear = {TRUE | FALSE}**

initializes the mirror device with zeros to guarantee that the underlying filesystem has reserved space for the mirror device. The default value, `FALSE`, does not clear the mirror, and executing a write to the device might fail through lack of space on the file system. If you specify `TRUE`, the mirror is cleared, forcing the file system to reserve space for the device.

## Examples

### Example 1

`tranlog` is the logical device name for a raw device. The `tranlog` device was initialized with `disk init` and is being used as a transaction log device (as in `create database ... log on<tranlog>`). The following command mirrors the transaction log device:

```
disk mirror
  name = "tranlog",
  mirror = "/dev/rxyle"
```

### Example 2

Creates a software mirror for the database device `user_disk` on the file `mirror.dat`:

```
disk mirror
  name = "user_disk",
  mirror = "/server/data/mirror.dat"
```

## Usage

- Disk mirroring creates a software mirror of a user database device, the master database device, or a database device used for user database transaction logs. If a database device fails, its mirror immediately takes over.  
Disk mirroring does not interfere with ongoing activities in the database. You can mirror or unmirror database devices without shutting down the SAP ASE server.
- You cannot configure `imrsllog` devices for disk mirroring.
- Use `dump database` to back up the `master` database after each use of `disk mirror`. This makes recovery easier and safer in case `master` is damaged.
- When a read or write to a mirrored device is unsuccessful, the SAP ASE server unmirrors the bad device and prints error messages. The SAP ASE server continues to run, unmirrored. The system administrator must use the `disk remirror` command to restart mirroring.
- The `clear` option in this command has no effect when used on the NT platform.
- You can mirror the master device, devices that store data, and devices that store transaction logs. However, you cannot mirror dump devices.
- Devices are mirrored; databases are not.
- A device and its mirror constitute one logical device. The SAP ASE server stores the physical name of the mirror device in the `mirrorname` column of the `sysdevices` table. It does not require a separate entry in `sysdevices` and should not be initialized with `disk init`.
- To retain use of asynchronous I/O, always mirror devices that are capable of asynchronous I/O to other devices capable of asynchronous I/O. In most cases, this means mirroring raw devices to raw devices and operating system files to operating system files.  
If the operating system cannot perform asynchronous I/O on files, mirroring a raw device to a regular file produces an error message. Mirroring a regular file to a raw device works, but does not use asynchronous I/O.
- On systems that support asynchronous I/O, the `writes` option allows you to specify whether writes to the first device must finish before writes to the second device begin (`serial`) or whether both I/O requests are to be queued immediately, one to each side of the mirror (`noserial`). In either case, if a write cannot be completed, the I/O error causes the bad device to become unmirrored.
- Mirror all default database devices so that you are still protected if a `create database` or `alter database` command affects a database device in the default list.
- For greater protection, mirror the database device used for transaction logs.
- Always put user database transaction logs on a separate database device. To put a database's transaction log (that is, the system table `syslogs`) on a device other than the one on which the rest of the database is stored, name the database device and the log device when you create the database. Alternatively, use `alter database` to extend the database onto a second device, then run `sp_logdevice`.
- If you mirror the database device for the `master` database, you can use the `-r` option and the name of the mirror for UNIX, when you restart the SAP ASE server with the `dataserver` utility program. Add this to the `RUN_servername` file for that server so that the `startserver` utility program knows about it. For example, to start a master device named `master.dat` and its mirror, `mirror.dat` enter:

```
dataserver -dmaster.dat -rmirror.dat
```

See `dataserver` and `startserver` in the *Utility Guide*.

- If you mirror a database device that has unallocated space (room for additional `create database` and `alter database` statements to allocate part of the device), `disk mirror` begins mirroring these allocations when they are made, not when the `disk mirror` command is issued.
- For a report on all SAP ASE devices on your system (user database devices and their mirrors, as well as dump devices), execute `sp_helpdevice`.

See also:

- `sp_diskdefault`, `sp_helpdevice`, `sp_logdevice` in *Reference Manual: Procedures*
- `dataserver`, `startserver` in the *Utility Guide*

## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

## Permissions

The permission checks for `disk mirror` differ based on your granular permissions settings. You must be using the `master` database to use `disk mirror`.

### Setting Description

**Enabled** With granular permissions enabled, you must be a user with `manage disk` privilege.

**Disabled** With granular permissions disabled, you must be a user with `sa_role`. `disk mirror` permission is not transferable.

## Auditing

You can enable `disk` auditing option to audit this command. Values in `event` and `extrainfo` columns from the `sysaudits` table are:

Information	Values
Audit option	<code>disk</code>
Event	23
Command or access audited	<code>disk mirror</code>
Information in <code>extrainfo</code>	<ul style="list-style-type: none"> <li>• <b>Roles</b> – current active roles</li> <li>• <b>Full command text</b> – full text of <code>disk mirror</code> command</li> <li>• <b>Previous value</b> – NULL</li> </ul>

## Information

## Values

- **Current value** – NULL
- **Other information** – a list of parameter names and values
- **Proxy information** – original login name, if `set proxy` is in effect

Full command text is included in `extrainfo`. For example:

```
sa_role sso_role oper_role sybase_ts_role mon_role; disk mirror name = "tranlog",  
physname = "/dev/rxyle"; ; ; ; ; sa/ase;
```

For more information about auditing, see *Security Administration Guide > Auditing*.

## Related Information

[alter database \[page 14\]](#)

[create database \[page 140\]](#)

[disk init \[page 401\]](#)

[disk refit \[page 413\]](#)

[disk reinit \[page 415\]](#)

[disk remirror \[page 420\]](#)

[disk unmirror \[page 425\]](#)

[dump database \[page 470\]](#)

[dump transaction \[page 490\]](#)

[load database \[page 585\]](#)

[load transaction \[page 603\]](#)

## 1.56 disk refit

Rebuilds the `master` database's `sysusages` and `sysdatabases` system tables from information contained in `sysdevices`.

## Syntax

```
disk refit
```

## Usage

The SAP ASE server automatically shuts down after `disk refit` rebuilds the system tables.

Use `disk refit` after `disk reinit` as part of the procedure to restore the master database.

### i Note

You must start the SAP ASE server with trace flag 3608 before you run `disk refit`. However, make sure you read the information in the *Troubleshooting and Error Messages Guide* before you start the SAP ASE server with any trace flag.

See also:

- *System Administration Guide*.
- `sp_addumpdevice`, `sp_helpdevice` in *Reference Manual: Procedures*
- `disk refit` is not supported for `imrslog` devices or for in-memory row storage-enabled databases. However, `disk refit` is supported for all other devices and databases on SAP ASE installations that include an in-memory row storage-enabled database.

## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

## Permissions

The permission checks for `disk refit` differ based on your granular permissions settings. You must be using the master database to use `disk refit`.

Setting	Description
---------	-------------

<b>Enabled</b>	With granular permissions enabled, you must be a user with <code>manage disk</code> privilege.
----------------	--

<b>Disabled</b>	With granular permissions disabled, you must be a user with <code>sa_role</code> . <code>disk refit</code> permission is not transferable.
-----------------	--

## Auditing

You can enable `disk` auditing option to audit this command. Values in `event` and `extrainfo` columns from the `sysaudits` table are:

Information	Values
Audit option	<code>disk</code>

Information	Values
Event	21
Command or access audited	disk refit
Information in <code>extrainfo</code>	<ul style="list-style-type: none"> <li>• <b>Roles</b> – current active roles</li> <li>• <b>Full command text</b> – full text of <code>disk refit</code> command</li> <li>• <b>Previous value</b> – NULL</li> <li>• <b>Current value</b> – NULL</li> <li>• <b>Other information</b> – a list of parameter names and values</li> <li>• <b>Proxy information</b> – original login name, if <code>set proxy</code> is in effect</li> </ul>

Full command text is included in `extrainfo`. For example:

```
sa_role sso_role oper_role sybase_ts_role mon_role; disk refit; ; ; ; sa/ase;
```

For more information about auditing, see *Security Administration Guide > Auditing*.

## Related Information

[disk init \[page 401\]](#)

[disk reinit \[page 415\]](#)

## 1.57 disk reinit

Rebuilds the `master` database's `sysdevices` system table. Use `disk reinit` as part of the procedure to restore the `master` database.

### Syntax

```
disk reinit
  name = "<device_name>",
  physname = "<physicalname>",
  [vdevno = <virtual_device_number>],
  size = <number_of_blocks>
  [, vstart = <virtual_address>
    , cntrltype = <controller_number>]
  [, dsync = {true | false}]
  [, directio = {true | false}]
  [, instance = "<instance_name>"]
```

## Parameters

**name = "<device\_name>"**

specifies the name of the database device, which must conform to the rules for identifiers, and must be enclosed in single or double quotes. This name is used in the `create database` and `alter database` commands.

**physname = "<physicalname>"**

specifies the name of the database device. The physical name must be enclosed in single or double quotes.

**vdevno = <virtual\_device\_number>**

specifies the virtual device number, which must be unique among the database devices associated with the SAP ASE server. The device number 0 is reserved for the master device. Otherwise, valid device numbers are between 1 and 2,147,483,647.

To determine the virtual device number, look at the `device_number` column of the `sp_helpdevice` report, and use the next unused integer.

**size = <number\_of\_blocks>**

specifies the current size of the device being reinitialized. The following are example unit specifiers, using uppercase, lowercase, and single and double quotes interchangeably: 'k' or "K" (kilobytes), "m" or 'M' (megabytes), "g" or "G" (gigabytes), and 't' or 'T' (terabytes). You should always include a unit specifier. Quotes are optional if you do not include a unit specifier. However, you must use quotes if you include a unit specifier.

**vstart = <virtual\_address>**

specifies the starting virtual address, or the offset, for the SAP ASE server to begin using the database device. The following are example unit specifiers, using uppercase, lowercase, and single and double quotes interchangeably: 'k' or "K" (kilobytes), "m" or 'M' (megabytes), "g" or "G" (gigabytes), and 't' or 'T' (terabytes). You should always include a unit specifier. Quotes are optional if you do not include a unit specifier. However, you must use quotes if you include a unit specifier. If you do not provide a unit specifier, the value provided is presumed to be in megabytes. The size of the offset depends on how you enter the value for `vstart`.

- If you do not specify a unit size, `vstart` uses 2K pages for its starting address. For example, if you specify `vstart = 13`, the SAP ASE server uses 13 \* 2K pages as the offset for the starting address.
- If you specify a unit value, `vstart` uses it as the starting address. For example, if you specify `vstart = "13M"`, the SAP ASE server sets the starting address offset at 13 MB.

The default value (and usually the preferred value) of `vstart` is 0. If the specified device does not have the sum of `vstart + size` blocks available, `disk reinit` fails.

### i Note

If you are running the Logical Volume Manager on an AIX operating system, `vstart` should be 2.

Specify `vstart` only if instructed to do so by SAP Product Support.



**cntrltype = <controller\_number>**

specifies the disk controller. Its default value is 0. Reset it only if instructed to do so by SAP Product Support.

**dsync = {true | false}**

specifies whether writes to the database device are flushed to the storage media, or are buffered only when using operating system files. This option is meaningful only when you are initializing an operating system file; it has no effect when initializing devices on a raw partition. By default, all operating system files are initialized with `dsync` set to `true`.

**directio = {true | false}**

allows you to configure the SAP ASE server to transfer data directly to disk, bypassing the operating system buffer cache. The SAP ASE server passes the device options to Backup Server, which enables Backup Server to access the database device with the appropriate `directio` option.

`directio` is a static parameter that requires a restart of the SAP ASE server to take effect.

By default, `directio` is set to `true` for clustered and nonclustered servers.

The `directio` parameter is ignored for raw devices.

**instance = "<instance\_name>"**

(clusters only) specifies the device as private and sets its owning instance to `<instance_name>`.

If you do not include the physical device, `disk reinit` succeeds only after SAP ASE has restarted at least once since the device was deleted from the operating system.

## Examples

### Example 1

Adds a new row to the `sysdevices` table. This new row contains the characteristics of the existing device currently being reinitialized:

```
disk reinit
name = "user_file",
physname = "/usr/u/sybase/data/userfile1.dat",
vdevno = 2, size = 5120, dsync = true
```

### Example 2

Adds a new row to the `sysdevices` table, with the data transferred directly to disk. This new row contains the characteristics of the existing device currently being reinitialized:

```
disk reinit
name = "user_disk",
physname = "/usr/u/sybase/data/userfile1.dat",
size = 5120, directio= true
```

## Usage

- Generally, SAP recommends that you create databases on character-based devices (also known as raw devices). SAP ASE versions 15.0 and later allow you to create them on block devices if you have `dsync` or `directio I/O set.dsync` or `directio I/O` guarantee data consistency on block devices. That is, a write is successful only when data is on disk.
- `disk reinit` is not supported for `imrslog` devices or for in-memory row storage-enabled databases. However, `disk reinit` is supported for all other devices and databases on SAP ASE installations that include an in-memory row storage-enabled database.
- `disk reinit` ensures that `master..sysdevices` is correct if the master database has been damaged or if devices have been added since the last dump of `master`.
- `disk reinit` is similar to `disk init`, but does not initialize the database device.
- You can specify the `<size>` as a `float`, but the size is rounded down to the nearest multiple of 2K.
- If you do not use a unit specifier for `<size>`, `disk reinit` uses the virtual page size of 2K.
- By default, the `directio` option is set to `false` (off) for all platforms.
- For complete information on restoring the `master` database, see the *System Administration Guide*.

See also `sp_addumpdevice`, `sp_helpdevice` in *Reference Manual: Procedures*.

## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

## Permissions

The permission checks for `disk reinit` differ based on your granular permissions settings. You must be using the `master` database to use `disk reinit`.

Setting	Description
---------	-------------

<b>Enabled</b>	With granular permissions enabled, you must be a user with <code>manage disk</code> privilege.
----------------	--

<b>Disabled</b>	With granular permissions disabled, you must be a user with <code>sa_role</code> . <code>disk reinit</code> permission is not transferable.
-----------------	---

## Auditing

You can enable `disk` auditing option to audit this command. Values in `event` and `extrainfo` columns from the `sysaudits` table are:

Information	Values
Audit option	disk
Event	22
Command or access audited	disk reinit
Information in <code>extrainfo</code>	<ul style="list-style-type: none"> <li>• <b>Roles</b> – current active roles</li> <li>• <b>Full command text</b> – full text of <code>disk reinit</code> command</li> <li>• <b>Previous value</b> – NULL</li> <li>• <b>Current value</b> – NULL</li> <li>• <b>Other information</b> – a list of parameter names and values</li> <li>• <b>Proxy information</b> – original login name, if <code>set proxy</code> is in effect</li> </ul>

Full command text is included in `extrainfo`. For example:

```
sa_role sso_role oper_role sybase_ts_role mon_role; disk reinit name =
"user_file",
physname = "/usr/u/sybase/data/userfile1.dat", vdevno = 2, size = 5120,
dsync = true; ; ; ; sa/ase;
```

For more information about auditing, see *Security Administration Guide > Auditing*.

## Related Information

[alter database \[page 14\]](#)

[create database \[page 140\]](#)

[dbcc \[page 349\]](#)

[disk init \[page 401\]](#)

[disk refit \[page 413\]](#)

### 1.57.1 Using `dsync` with Disk Reinit

Usage information for `dsync`.

#### Note

Do not set `dsync` to false for any device that stores critical data. The only exception is `tempdb`, which can safely be stored on devices for which `dsync` is set to false.

- When `dsync` is on, writes to the database device are guaranteed to take place on the physical storage media, and the SAP ASE server can recover data on the device in the event of a system failure.
- `directio` and `dsync` are mutually exclusive. If a device has `dsync` set to true, you cannot set `directio` to true for this device. To enable `directio` for a device, you must first reset `dsync` to false.

- When `dsync` is off, writes to the database device may be buffered by the UNIX file system. The UNIX file system may mark an update as being completed, even though the physical media has not yet been modified. In the event of a system failure, there is no guarantee that data updates have ever taken place on the physical media, and the SAP ASE server may be unable to recover the database.
- `dsync` is always on for the master device file.
- Turn off the `dsync` value only when databases on the device need not be recovered after a system failure. For example, you may consider turning `dsync` off for a device that stores only the `tempdb` database.
- The SAP ASE server ignores the `dsync` setting for devices stored on raw partitions—writes to those device are guaranteed to take place on the physical storage media, regardless of the `dsync` setting.
- The `dsync` setting is not used on the Windows NT platform.
- `disk_reinit` ensures that `master..sysdevices` is correct if the `master` database has been damaged or if devices have been added since the last dump of `master`.

## 1.58 disk remirror

Restarts disk mirroring after it is stopped by failure of a mirrored device, or temporarily disabled by the `disk unmirror` command.

### Syntax

```
disk remirror
  name = "<device_name>"
```

### Parameters

`name = "<device_name>"`

specifies the name of the database device that you want to remirror, which is recorded in the `name` column of the `sysdevices` table, and must be enclosed in single or double quotes.

### Examples

#### Example 1

Resumes software mirroring on the database device `user_disk`:

```
disk remirror
  name = "user_disk"
```

## Usage

- Disk mirroring creates a software mirror of a user database device, the master database device, or a database device used for user database transaction logs. If a database device fails, its mirror immediately takes over.

Use the `disk remirror` command to reestablish mirroring after it has been temporarily stopped by failure of a mirrored device, or temporarily disabled with the `mode = retain` option of the `disk unmirror` command. The `disk remirror` command copies data on the retained disk to the mirror.

- You cannot configure `imrslog` devices for disk mirroring.
- Back up the `master` database with the `dump database` command after each use of `disk remirror`. This makes recovery easier and safer in case `master` is damaged.
- If mirroring was permanently disabled with the `mode = remove` option, you must remove the operating system file that contains the mirror before using `disk remirror`.
- Database devices, not databases, are mirrored.
- You can mirror, remirror, or unmirror database devices without shutting down the SAP ASE server. Disk mirroring does not interfere with ongoing activities in the database.
- When a read or write to a mirrored device is unsuccessful, the SAP ASE server unmirrors the bad device and prints error messages. The SAP ASE server continues to run, unmirrored. The system administrator must use `disk remirror` to restart mirroring.
- In addition to mirroring user database devices, always put user database transaction logs on a separate database device. The database device used for transaction logs can also be mirrored for even greater protection. To put a database's transaction log (that is, the system table `syslogs`) on a different device than the one on which the rest of the database is stored, name the database device and the log device when you create the database. Alternatively, use `alter database` to point to a second device, then run `sp_logdevice`.
- If you mirror the database device for the `master` database, you can use the `-r` option and the name of the mirror for UNIX, when you restart the SAP ASE server with the `dataserver` utility program. Add this option to the `RUN_servername` file for that server so that the `startserver` utility program knows about it. For example, the following command starts a master device named `master.dat` and its mirror, `mirror.dat`:

```
dataserver -dmaster.dat -rmirror.dat
```

See `dataserver` and `startserver` in the *Utility Guide*.

- For a report on all SAP ASE devices on your system (user database devices and their mirrors, as well as dump devices), execute `sp_helpdevice`.

See also:

- `sp_diskdefault`, `sp_helpdevice`, `sp_logdevice` in *Reference Manual: Procedures*
- `dataserver`, `startserver` in the *Utility Guide*

## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

## Permissions

The permission checks for `disk remirror` differ based on your granular permissions settings. You must be using the `master` database to use `disk remirror`.

Setting	Description
---------	-------------

<b>Enabled</b>	With granular permissions enabled, you must be a user with <code>manage disk</code> privilege.
----------------	--

<b>Disabled</b>	With granular permissions disabled, you must be a user with <code>sa_role.disk remirror</code> permission is not transferable.
-----------------	--

## Auditing

You can enable `disk` auditing option to audit this command. Values in `event` and `extrainfo` columns from the `sysaudits` table are:

Information	Values
Audit option	<code>disk</code>
Event	25
Command or access audited	<code>disk remirror</code>
Information in <code>extrainfo</code>	<ul style="list-style-type: none"><li>• <b>Roles</b> – current active roles</li><li>• <b>Full command text</b> – full text of <code>disk remirror</code> command</li><li>• <b>Previous value</b> – NULL</li><li>• <b>Current value</b> – NULL</li><li>• <b>Other information</b> – a list of parameter names and values</li><li>• <b>Proxy information</b> – original login name, if <code>set proxy</code> is in effect</li></ul>

Full command text is included in `extrainfo`. For example:

```
sa_role sso_role oper_role sybase_ts_role mon_role;  
disk remirror name = "user_disk"; ; ; ; sa/ase;
```

For more information about auditing, see *Security Administration Guide > Auditing*.

## Related Information

[alter database \[page 14\]](#)

[create database \[page 140\]](#)

[disk init \[page 401\]](#)

[disk mirror \[page 409\]](#)

[disk refit \[page 413\]](#)

[disk reinit \[page 415\]](#)

[disk unmirror \[page 425\]](#)

[dump database \[page 470\]](#)

[dump transaction \[page 490\]](#)

[load database \[page 585\]](#)

[load transaction \[page 603\]](#)

## 1.59 disk resize

Dynamically increases the size of the device used by the SAP ASE server.

### Syntax

```
disk resize
  name = "<device_name>",
  size = <additional_space>
```

### Parameters

**<name>**

is the name of the device for which you are increasing the size.

**<additional\_space>**

is the amount of additional space you are adding to the device.

### Examples

#### Example 1

Increase the size of `testdev` by 4 MB:

```
disk resize
  name = "test_dev",
  size = "4M"
```

## Usage

- The `disk resize` command allows you to dynamically increase the size of your disks.
- After you resize a device, dump the master device, which maintains the size of the device in the `sysdevices` table. If you attempt a recovery from an old dump of the master device, the information stored in `sysdevices` is not current.
- Any properties that are set on the device continue to be set after you increase its size.
- During the physical initialization of the disk, if any error occurs due to insufficient disk space, `disk resize` extends the database device to the point before the error occurs.  
For example, on a server that uses 4K logical pages, if you try to increase the size of the device by 40 MB, but only 39.5 MB is available, then the device is extended only by 39.5 MB. From the extended size (39.5 MB), only 39 MB is used by the SAP ASE server. The last 0.5 MB is allocated but not used, as 4K servers configure devices in one MB minimums.  
To utilize the last 0.5 MB, make sure that there is at least another 1.5 MB available for the device, then re-run `disk resize`, specifying 1.5 MB as the incremental size.
- You cannot use `disk resize` to decrease the size of the device.
- `<device_name>` must have a valid identifier. The device is initialized using the `disk init` command and, it must refer to a valid SAP ASE device, not a dump or load device.
- The following are example unit specifiers, using uppercase, lowercase, and single and double quotes interchangeably: 'k' or "K" (kilobytes), "m" or 'M' (megabytes), "g" or "G" (gigabytes), and 't' or 'T' (terabytes). You should always include a unit specifier. Although it is optional, you should always include the unit specifier with the `disk resize` command to avoid confusion in the actual number of pages allocated.  
You must enclose the unit specifier in single or double quotes. If you do not use a unit specifier, the size defaults to the number of disk pages.
- Permanently disable mirroring while the resize operation is in progress. You can reestablish mirroring when the resize operation is completed.

See also `sp_addsegment`, `sp_dropsegment`, `sp_helpdb`, `sp_helpsegment`, `sp_logdevice`, `sp_renamedb`, `sp_spaceused` in *Reference Manual: Procedures*.

## Standards

ANSI SQL – compliance level: Transact-SQL extension.

## Permissions

The permission checks for `disk resize` differ based on your granular permissions settings.

Setting	Description
Enabled	With granular permissions enabled, you must be a user with <code>manage disk</code> privilege.
Disabled	With granular permissions disabled, you must be a user with <code>sa_role</code> .



## Auditing

You can enable `disk` auditing option to audit this command. Values in `event` and `extrainfo` columns from the `sysaudits` table are:

Information	Values
Audit option	<code>disk</code>
Event	100
Command or access audited	<code>disk resize</code>
Information in <code>extrainfo</code>	<ul style="list-style-type: none"><li>• <b>Roles</b> – current active roles</li><li>• <b>Full command text</b> – full text of <code>disk resize</code> command</li><li>• <b>Previous value</b> – NULL</li><li>• <b>Current value</b> – NULL</li><li>• <b>Other information</b> – a list of parameter names and values</li><li>• <b>Proxy information</b> – original login name, if <code>set proxy</code> is in effect</li></ul>

Full command text and parameters are included in `extrainfo`. For example:

```
sa_role sybase_ts_role; disk resize name = @p_name, size = @p_dsize; ; ;
    @p_name = test_db_dev, @p_dsize = 32m; ; user0/ase;
```

For more information about auditing, see *Security Administration Guide > Auditing*.

## Related Information

[create database \[page 140\]](#)

[disk init \[page 401\]](#)

[drop database \[page 429\]](#)

[load database \[page 585\]](#)

## 1.60 disk unmirror

Suspends disk mirroring initiated with the `disk mirror` command to allow hardware maintenance or the changing of a hardware device.

## Syntax

```
disk unmirror
```

```
name = "<device_name>"
[, side = {"primary" | secondary}]
[, mode = {retain | remove}]
```

## Parameters

**name = "<device\_name>"**

specifies the name of the database device to unmirror. The name must be enclosed in single or double quotes.

**side = {"primary" | secondary}**

specifies whether to disable the `primary` device or the `secondary` device (the mirror). By default, the secondary device is unmirrored.

**mode = {retain | remove}**

determines whether the unmirroring is temporary (`retain`) or permanent (`remove`). By default, unmirroring is temporary.

Specify `retain` when you plan to remirror the database device later in the same configuration. This option mimics what happens when the primary device fails:

- I/O is directed only at the device **not** being unmirrored.
- The `status` column of `sysdevices` indicates that mirroring is deactivated. `remove` eliminates all `sysdevices` references to a mirror device.
- The `status` column indicates that the mirroring feature is ignored.
- The `phyname` column is replaced by the name of the secondary device in the `mirrorname` column if the primary device is the one being deactivated.
- The `mirrorname` column is set to NULL.

## Examples

### Example 1

Suspends software mirroring for the database device `user_disk`:

```
disk unmirror
name = "user_disk"
```

### Example 2

Suspends software mirroring for the database device `user_disk` on the secondary side:

```
disk unmirror name = "user_disk", side = secondary
```

### Example 3

Suspends software mirroring for the database device `user_disk` and removes all device references to the mirror device:

```
disk unmirror name = "user_disk", mode = remove
```

## Usage

- Disk mirroring creates a software mirror of a user database device, the master database device, or a database device used for user database transaction logs. If a database device fails, its mirror immediately takes over.  
`disk unmirror` disables either the original database device or the mirror, either permanently or temporarily, so that the device is no longer available to the SAP ASE server for reads or writes. It does not remove the associated file from the operating system.
- Disk unmirroring alters the `sysdevices` table in the `master` database. Back up the `master` database with the `dump database` command after each use of `disk unmirror`. This makes recovery easier and safer in case `master` is damaged.
- You can unmirror a database device while it is in use.
- You cannot unmirror any of a database's devices while a `dump database`, `load database`, or `load transaction` is in progress. The SAP ASE server displays a message asking whether to abort the dump or load or to defer the `disk unmirror` until after the dump or load completes.
- You cannot unmirror a database's log device while a `dump transaction` is in progress. The SAP ASE server displays a message asking whether to abort the dump or defer the `disk unmirror` until after the dump completes.

### Note

`dump transaction` with `truncate_only` and `dump transaction` with `no_log` are not affected when a log device is unmirrored.

- Mirror all the default database devices so that you are still protected if a `create` or `alter database` command affects a database device in the default list.
- When a read or write to a mirrored device is unsuccessful, the SAP ASE server automatically unmirrors the bad device and prints error messages. The SAP ASE server continues to run, unmirrored. A system administrator must restart mirroring with the `disk remirror` command.
- For a report on all SAP ASE devices on your system (user database devices and their mirrors, as well as dump devices), execute `sp_helpdevice`.
- Use `disk remirror` to reestablish mirroring after it is temporarily stopped with the `mode = retain` option of the `disk unmirror` command. If mirroring is permanently disabled with the `mode = remove` option, you must remove the operating system file that contains the mirror before using `disk remirror`.

See also:

- `sp_diskdefault`, `sp_helpdevice`, `sp_logdevice` in *Reference Manual: Procedures*
- `dataserver`, `startserver` in the *Utility Guide*

## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

## Permissions

The permission checks for `disk unmirror` differ based on your granular permissions settings. You must be using the `master` database to use `disk unmirror`.

Setting	Description
---------	-------------

<b>Enabled</b>	With granular permissions enabled, you must be a user with <code>manage disk</code> privilege.
----------------	--

<b>Disabled</b>	With granular permissions disabled, you must be a user with <code>sa_role.disk unmirror</code> permission is not transferable.
-----------------	--

## Auditing

You can enable `disk` auditing option to audit this command. Values in `event` and `extrainfo` columns from the `sysaudits` table are:

Information	Values
Audit option	<code>disk</code>
Event	24
Command or access audited	<code>disk unmirror</code>
Information in <code>extrainfo</code>	<ul style="list-style-type: none"><li>• <b>Roles</b> – current active roles</li><li>• <b>Full command text</b> – full text of <code>disk unmirror</code> command</li><li>• <b>Previous value</b> – NULL</li><li>• <b>Current value</b> – NULL</li><li>• <b>Other information</b> – a list of parameter names and values</li><li>• <b>Proxy information</b> – original login name, if <code>set proxy</code> is in effect</li></ul>

Full command text is included in `extrainfo`. For example:

```
sa_role sso_role oper_role sybase_ts_role mon_role;  
disk unmirror name = "user_disk"; ; ; ; sa/ase;
```

For more information about auditing, see *Security Administration Guide > Auditing*.

## Related Information

[alter database \[page 14\]](#)

[create database \[page 140\]](#)

[dump database \[page 470\]](#)

[dump transaction \[page 490\]](#)

[disk init \[page 401\]](#)

[disk mirror \[page 409\]](#)  
[disk refit \[page 413\]](#)  
[disk reinit \[page 415\]](#)  
[disk remirror \[page 420\]](#)  
[load database \[page 585\]](#)  
[load transaction \[page 603\]](#)

## 1.61 drop database

Removes one or more databases, including archive databases, from the SAP ASE server.

### Syntax

```
drop database <database_name >[, <database_name>] ...
```

### Parameters

**<database\_name>**

is the name of a database to remove. Use `sp_helpdb` to get a list of databases.

### Examples

#### Example 1

Removes the `publishing` database and all its contents:

```
drop database publishing
```

#### Example 2

`key_db` is the database where the encryption key resides and `col_db` is the database containing the encrypted columns. The SAP ASE server raises an error and fails to drop `key_db`. The drop of `col_db` succeeds. To drop both databases, drop `col_db` first:

```
drop database col_db, key_db
```

## Usage

- When dropping an archive database, all the rows for that database are deleted from the `sysaltusages` table in the `scratch` database. This requires log space in the `scratch` database.
- Removing a database deletes the database and all its objects, frees its storage allocation, and erases its entries from the `sysdatabases` and `sysusages` system tables in the `master` database.
- `drop database` clears the suspect page entries pertaining to the dropped database from `master..sysattributes`.

When using encrypted columns and `drop database`, to prevent accidental loss of keys, `drop database` fails if the database contains keys currently used to encrypt columns in other databases. To drop a database:

- Use `alter table` to decrypt the columns, or modify the columns for encryption using a different key.
- Drop the table or database containing the encrypted columns.

See also `sp_changedbowner`, `sp_helpdb`, `sp_renamedb`, `sp_spaceused` in *Reference Manual: Procedures*.

## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

## Permissions

The permission checks for `drop database` differ based on your granular permissions settings.

Setting	Description
---------	-------------

<b>Enabled</b>	<code>own database</code> privilege on the database. To drop With granular permissions enabled, you must be the database owner or have the <code>sybsecurity</code> , you must be the database owner or have the <code>manage auditing</code> privilege.
----------------	--

<b>Disabled</b>	With granular permissions disabled, you must be the database owner, a user with <code>sa_role</code> , or for <code>sybsecurity</code> , a user with <code>sso_role</code> .
-----------------	--

## Auditing

You can enable `drop` auditing option to audit this command. Values in `event` and `extrainfo` columns from the `sysaudits` table are:

Information	Values
Audit option	<code>drop</code>
Event	26

Information	Values
Command or access audited	drop database
Information in <code>extrainfo</code>	<ul style="list-style-type: none"> <li>• <b>Roles</b> – current active roles</li> <li>• <b>Full command text</b> – full text of <code>drop database</code> command</li> <li>• <b>Previous value</b> – NULL</li> <li>• <b>Current value</b> – NULL</li> <li>• <b>Other information</b> – a list of parameter names and values</li> <li>• <b>Proxy information</b> – original login name, if <code>set proxy</code> is in effect</li> </ul>

For more information about auditing, see *Security Administration Guide > Auditing*.

## Related Information

[alter database \[page 14\]](#)

[create database \[page 140\]](#)

[dbcc \[page 349\]](#)

[use \[page 850\]](#)

## 1.62 drop default

Removes a user-defined default.

### Syntax

```
drop default [<owner>.<default_name>
[, [<owner>.<default_name>] ...
```

### Parameters

**<default\_name>**

is the name of an existing default. Execute `sp_help` to display a list of existing defaults. Specify the owner's name to drop a default of the same name owned by a different user in the current database. The default value for `<owner>` is the current user.

## Examples

### Example 1

Removes the user-defined default `datedefault` from the database:

```
drop default datedefault
```

## Usage

- You cannot drop a default that is currently bound to a column or to a user-defined datatype. Use `sp_unbindefault` to unbind the default before you drop it.
- You can bind a new default to a column or user-defined datatype without unbinding its current default. The new default overrides the old one.
- When you drop a default for a NULL column, NULL becomes the column's default value. When you drop a default for a NOT NULL column, an error message appears if users do not explicitly enter a value for that column when inserting data.

See also `sp_help`, `sp_helptext`, `sp_unbindefault` in *Reference Manual: Procedures*.

## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

## Permissions

The permission checks for `drop default` differ based on your granular permissions settings.

Setting	Description
---------	-------------

<b>Enabled</b>	With granular permissions enabled, you must be the default owner or a user with <code>drop any default</code> privilege.
----------------	--

<b>Disabled</b>	With granular permissions disabled, you must be the default owner or a user with <code>sa_role</code> .
-----------------	---

`drop default` permission defaults to the owner of the default and is not transferable.

## Auditing

You can enable `drop` auditing option to audit this command. Values in `event` and `extrainfo` columns from the `sysaudits` table are:



Information	Value
Audit option	drop
Event	31
Command or access audited	drop default
Information in <code>extrainfo</code>	<ul style="list-style-type: none"> <li>• <b>Roles</b> – current active roles</li> <li>• <b>Full command text</b> – full text of <code>drop default</code> command</li> <li>• <b>Previous value</b> – NULL</li> <li>• <b>Current value</b> – NULL</li> <li>• <b>Other information</b> – NULL</li> <li>• <b>Proxy information</b> – original login name, if <code>set proxy</code> is in effect.</li> </ul>

Full command text is included in `extrainfo`. For example:

```
sa_role sso_role oper_role sybase_ts_role mon_role;
drop default datedefault; ; ; ; sa/ase;
```

For more information about auditing, see *Security Administration Guide > Auditing*.

## Related Information

[alter table \[page 70\]](#)

## 1.63 drop encryption key

Allows key owners to drop the named encryption key, including database encryption keys used for fully encrypted databases.

### Syntax

```
drop encryption key [[<database>.] [<owner>].] <keyname>
```

Explicitly drops an external login password service key:

```
drop encryption key syb_extpasswdkey
with password encryption downgrade
```

Explicitly drops a hidden text service key:

```
drop encryption key syb_syscommkey_ddddd
```

Or:

```
drop encryption key syb_syscommkey with text encryption downgrade
```

Explicitly drops an external HSM key:

```
drop encryption key [owner.]<keyname> [cascade]
```

## Parameters

**<database>**

is the name of the database.

**<owner>**

is the owner.

**<keyname>**

is the name of the key.

**syb\_extpasswdkey**

is the name of the service key

When you specify `with password encryption downgrade`, the SAP ASE server resets external login passwords with the algorithm used in versions earlier than 15.7, and the Replication Agent password, and the CIS and RTMS external login passwords are reset to an invalid value.

After the key is dropped, the administrator must reenter the passwords manually to resume using the corresponding services.

**syb\_syscommkey\_ddddddd**

is the explicit name of an individual syscomments service key to be dropped.

**syb\_syscommkey with text encryption downgrade**

the SAP ASE server reencrypts all the hidden text in syscomments with the algorithm used in versions earlier than 15.7.

**cascade**

drops the key from the HSM device as well. If not, only the entry in SAP ASE is dropped.

## Examples

### Example 1

Drops the encryption key `cc_key`:

```
drop encryption key cust.dbo.cc_key
```

## Usage

- If the key has key copies, the copies are dropped along with the base key.
- The command fails if:
  - Any column in any database is encrypted using the key.
  - The database encryption key you are dropping is still used to encrypt any database.
- `drop encryption key` cannot check databases that are archived, suspect, offline, unrecovered, or currently being loaded for columns encrypted by the key. The command issues a warning message naming the unavailable database, but does not fail. When the database is brought online, any tables with columns that were encrypted with the dropped key are not usable. To restore the key, the system administrator must load a dump of the dropped key's database from a time that precedes when the key was dropped.

See also `sp_encryption` and `sp_help` in *Reference Manual: Procedures*.

## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

## Permissions

The permission checks for `drop encryption key` differ based on your granular permissions settings.

Setting	Description
---------	-------------

<b>Enabled</b>	With granular permissions enabled, you must be the key owner or a user with <code>manage any encryption key</code> privilege.
----------------	---

For fully encrypted databases, SAP ASE creates a new permission called "`manage database encryption key`." You must have this permission to create a database encryption key.

You must have the `manage master key` permissions to drop the external HSM key.

<b>Disabled</b>	With granular permissions disabled, you must be the key owner or a user with <code>sso_role</code> .
-----------------	--

For fully encrypted databases, you must be a user with `sso_role`, `keycustodian_role`, or have `create encryption key` privilege.

### **i** Note

You must be a user with `sso_role` or `keycustodian_role` to drop an HSM key, the `create encryption key` privilege does not work for dropping an HSM key.

## Auditing

You can enable `encryption_key` auditing option to audit this command. Values in `event` and `extrainfo` columns from the `sysaudits` table are:

Information	Value
Audit option	<code>encryption_key</code>
Event	109
Command or access audited	<code>drop encryption key</code>
Information in <code>extrainfo</code>	<ul style="list-style-type: none"><li>• <b>Roles</b> – current active roles</li><li>• <b>Full command text</b> – full text of <code>drop encryption key</code> command</li><li>• <b>Previous value</b> – NULL</li><li>• <b>Current value</b> – NULL</li><li>• <b>Other information</b> – NULL</li><li>• <b>Proxy information</b> – original login name, if <code>set proxy</code> is in effect.</li></ul>

Full command text is included in `extrainfo`. For example:

```
sa_role sso_role oper_role sybase_ts_role mon_role;  
drop encryption key loginA_key; ; ; ; sa/ase;
```

For more information about auditing, see *Security Administration Guide > Auditing*.

## Related Information

[create encryption key \[page 163\]](#)

[alter encryption key \[page 35\]](#)

## 1.64 drop function

Removes one or more user-defined functions from the current database.

### Syntax

```
drop function { [<owner_name>.] <function_name> } [, ...n ]
```

## Parameters

**<owner\_name>**

is the name of the user ID that owns the user-defined function. Must be an existing user ID.

**<function\_name>**

is name of the user-defined function to be removed. Specifying the owner name is optional; the server name and database name cannot be specified.

## Examples

### Example 1

Drops the `bonus` function:

```
drop function bonus
```

## Usage

`drop function` drops scalar SQL user-defined functions from your current database.

## Permissions

The permission checks for `drop function` differ based on your granular permissions settings.

Setting	Description
---------	-------------

<b>Enabled</b>	With granular permissions enabled, you must be the function owner or a user with <code>drop any function</code> privilege.
----------------	--

<b>Disabled</b>	With granular permissions disabled, you must be the function owner or a user with <code>sa_role</code> .
-----------------	--

## Auditing

You can enable `drop` auditing option to audit this command. Values in `event` and `extrainfo` columns from the `sysaudits` table are:

Information	Value
<b>Audit option</b>	<code>drop</code>

Information	Value
Event	98
Command or access audited	drop function
Information in <code>extrainfo</code>	<ul style="list-style-type: none"> <li>• <b>Roles</b> – current active roles</li> <li>• <b>Full command text</b> – full text of <code>drop function</code> command</li> <li>• <b>Previous value</b> – NULL</li> <li>• <b>Current value</b> – NULL</li> <li>• <b>Other information</b> – NULL</li> <li>• <b>Proxy information</b> – original login name, if <code>set proxy</code> is in effect.</li> </ul>

Full command text is included in `extrainfo`. For example:

```
sa_role sso_role oper_role sybase_ts_role mon_role;
drop function bonus; ; ; ; sa/ase;
```

For more information about auditing, see *Security Administration Guide > Auditing*.

## 1.65 drop function (SQLJ)

Removes a SQLJ function.

### Syntax

```
drop func[tion] [<owner>.<function_name>
[, [<owner>.<function_name >] ...
```

### Parameters

`<owner>.<function_name>`

is the SQL name of a SQLJ function.

### Examples

#### Example 1

removes the SQLJ function `square_root`:

```
drop function square_root
```

## Usage

`drop function`

See also *Java in Adaptive Server Enterprise* for more information about SQLJ functions.

## Permissions

The permission checks for `drop function` differ based on your granular permissions settings.

Setting	Description
---------	-------------

<b>Enabled</b>	With granular permissions enabled, you must be the function owner or a user with <code>drop any function</code> privilege.
----------------	--

<b>Disabled</b>	With granular permissions disabled, you must be the function owner or a user with <code>sa_role</code> . Permissions are not transferable.
-----------------	--

## Auditing

For information about auditing for `drop function`, see [drop function \[page 436\]](#).

For more information about auditing, see *Security Administration Guide > Auditing*.

## 1.66 drop index

Removes an index from a table in the current database.

## Syntax

```
drop index <table_name.index_name>  
[, <table_name.index_name>] [with nowait]...
```

## Parameters

**<table\_name>**

is the table in which the indexed column is located. The table must be in the current database.

### <index\_name>

is the index to drop. In Transact-SQL, index names need not be unique in a database, though they must be unique within a table.

### <with nowait>

returns the `drop index` command instantly. The `<with nowait>` option performs the dropping of the index and index page deallocation tasks in the background therefore you can continue to run DML or DDL operations on the table.

## Examples

### Example 1

Removes `au_id_ind` from the `authors` table:

```
drop index authors.au_id_ind
```

### Example 2

Removes `au_id_ind` from the `authors` table and returns immediately:

```
drop index authors.au_id_ind with nowait
```

## Usage

- Once the `drop index` command is issued, you regain all the space that was previously occupied by the index. This space can be used for any database objects.
- You cannot use `drop index` on system tables.
- `drop index` cannot remove indexes that support unique constraints. To drop such indexes, drop the constraints through `alter table` or drop the table. See `create table` for more information about unique constraint indexes.
- You cannot drop indexes that are currently used by any open cursor. For information about which cursors are open and what indexes they use, use `sp_cursorinfo`.
- To get information about what indexes exist on a table, use the following, where `objname` is the name of the table:

```
sp_helpindex <objname>
```

- You can use the `drop index with nowait` command only on user tables in the user database.
- `drop index with nowait` command separates the index from the table immediately and deletes all related index system catalogs. However, the page deallocations are deferred to the daemon thread.
- Once the system catalogs are deleted, the `drop index with nowait` command returns and you can input other commands.
- After dropping the indexes and deleting the system catalogs, the `drop index with nowait` command cannot roll back.
- The daemon thread starts with the `drop index with nowait` command and exits after dropping the indexes.



- You cannot use the `drop index with nowait` command to drop clustered and functional indexes instantly.

See also `sp_cursorinfo`, `sp_helpindex`, `sp_spaceused` in *Reference Manual: Procedures*.

## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

## Permissions

You must be a table owner to use `drop index`.

## Auditing

You can enable `drop` auditing option to audit this command. Values in `event` and `extrainfo` columns from the `sysaudits` table are:

Information	Value
Audit option	<code>drop</code>
Event	105
Command or access audited	<code>drop index</code>

### Information in `extrainfo`

- **Roles** – current active roles
- **Full command text** – full text of `drop index` command
- **Previous value** – NULL
- **Current value** – NULL
- **Other information** – NULL
- **Proxy information** – original login name, if `set proxy` is in effect.

Full command text is included in `extrainfo`. For example:

```
sa_role sso_role oper_role sybase_ts_role mon_role; drop index
authors.au_id_ind; ; ; ; sa/ase;
```

For more information about auditing, see *Security Administration Guide > Auditing*.

## Related Information

[create index \[page 192\]](#)

[setuser \[page 790\]](#)

## 1.67 drop login

Drops a login account or list of accounts.

### Syntax

```
drop login <login_name>[, <login_name_list>] [with override]
```

### Parameters

**login\_name**

specifies the name of login account to be dropped.

**login\_name\_list**

specifies a list of login accounts to be dropped.

**with override**

drops the login even if there are non-available databases that cannot be checked for login references.

### Examples

#### Example 1

Drops the login accounts "ravi" and "vinod".

```
drop login ravi, vinod
```

### Usage

- Executing `drop login` removes a user login from the SAP ASE server, deleting the user's entry from `master.dbo.syslogins`.

- The SAP ASE server reuses a dropped login's server user ID, which compromises accountability. You can avoid dropping accounts entirely and, instead, use `sp_locklogin` to lock any accounts that are no longer used.
- If you need to drop logins, be sure to audit these events (using `sp_audit`) so that you have a record of them.
- `drop login` deletes all resource limits associated with the dropped login.
- `drop login` fails if the login to be dropped is a user in any database on the server. Use `sp_dropuser` to drop the user from a database. You cannot drop a user from a database if that user owns any objects in the database.
- If the login to be dropped is a System Security Officer, `drop login` verifies that at least one other unlocked System Security Officer's account exists. If not, `drop login` fails. Similarly, `drop login` ensures that there is always at least one unlocked system administrator account.

See also:

- For more information about dropping login accounts, see the *Security Administration Guide*.
- `lprofile_id`, `lprofile_name` in *Reference Manual: Building Blocks*
- `sp_passwordpolicy`, `sp_displaylogin`, `sp_displayroles`, `sp_locklogin` in *Reference Manual: Procedures*

## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

## Permissions

The permission checks for `drop login` differ based on your granular permissions settings.

Setting	Description
<b>Enabled</b>	With granular permissions enabled, you must be a user with <code>manage any login</code> privilege.
<b>Disabled</b>	With granular permissions disabled, you must be a user with <code>sso_role</code> .

## Auditing

You can enable the following auditing options to audit this command. Values in `event` and `extrainfo` columns from the `sysaudits` table are:

Information	Value
<b>Audit option</b>	<code>login_admin, security</code>
<b>Event</b>	139

Information	Value
Command or access audited	drop login
Information in <code>extrainfo</code>	<ul style="list-style-type: none"> <li>• <b>Roles</b> – current active roles</li> <li>• <b>Full command text</b> – full text of drop login command</li> <li>• <b>Previous value</b> – NULL</li> <li>• <b>Current value</b> – NULL</li> <li>• <b>Other information</b> – NULL</li> <li>• <b>Proxy information</b> – original login name, if set proxy is in effect.</li> </ul>

Full command text is included in `extrainfo` column. For example:

```
sa_role sso_role oper_role sybase_ts_role mon_role;
drop login vivekk_lp; ; ; ; sa/ase;
```

For more information about auditing, see *Security Administration Guide > Auditing*.

## Related Information

[alter login \[page 47\]](#)

[alter login profile \[page 54\]](#)

[create login \[page 216\]](#)

[create login profile \[page 220\]](#)

[drop login profile \[page 444\]](#)

## 1.68 drop login profile

Drops a login profile or list of login profiles.

### Syntax

```
drop login profile <login_profile_name>[, <login_profile_name_list>]
[with override]
```

### Parameters

**login\_profile\_name**

specifies the name of the login profile to be dropped.

### **login\_profile\_name\_list**

specifies a list of login profiles to be dropped.

### **with override**

forcefully drops login profiles that are bound to login accounts. The login accounts associated with the dropped login profile are associated with the default login profile.

## **Examples**

### **Example 1**

Drops the login profile `group1_login_profile` if it is not bound to one or more login accounts:

```
drop login profile group1_login_profile
```

### **Example 2**

Generates an error because the `sa_login_profile` being bound to one or more login accounts:

```
drop login profile sa_login_profile
Msg 11193, Level 16, State 1:
Line 1:
The specified login profile is the default login profile
and/or associated with one or more login accounts.
Remove the default property and/or associations or use
the WITH OVERRIDE clause to drop the login profile.
```

### **Example 3**

Drops the `sa_login_profile` even though it is bound to one or more login accounts:

```
drop login profile sa_login_profile with override
```

## **Usage**

- The command `drop loginprofile` removes the login profile if it is not bound to a login account.
- Use `drop login profile with override` to forcefully remove a login profile that is bound to a login account. If the login profile is bound to a login account, the login account is bound to the default login account, if one exist. If the default login profile is also not present, precedence rules prior to SAP ASE version 15.7 are observed for the login account.

See also:

- For more information about dropping login profiles, see the *Security Administration Guide*.
- `lprofile_id`, `lprofile_name` in *Reference Manual: Building Blocks*
- `sp_passwordpolicy`, `sp_displaylogin`, `sp_displayroles`, `sp_locklogin` in *Reference Manual: Procedures*

## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

## Permissions

The permission checks for `drop login profile` differ based on your granular permissions settings.

Setting	Description
---------	-------------

<b>Enabled</b>	With granular permissions enabled, you must be a user with <code>manage any login profile</code> privilege.
----------------	---

<b>Disabled</b>	With granular permissions disabled, you must be a user with <code>sso_role</code> to drop the login profile.
-----------------	--

## Auditing

You can enable the following auditing options to audit this command. Values in `event` and `extrainfo` columns from the `sysaudits` table are:

Information	Value
Audit option	<code>security, security_profile</code>
Event	141
Command or access audited	<code>drop login profile</code>
Information in <code>extrainfo</code>	<ul style="list-style-type: none"><li>• <b>Roles</b> – current active roles</li><li>• <b>Full command text</b> – full text of <code>drop login profile</code> command</li><li>• <b>Previous value</b> – NULL</li><li>• <b>Current value</b> – NULL</li><li>• <b>Other information</b> – NULL</li><li>• <b>Proxy information</b> – original login name, if <code>set proxy</code> is in effect</li></ul>

Full command text is included in `extrainfo` column. For example:

```
sa_role sso_role oper_role sybase_ts_role mon_role;  
drop login profile group1_login_profile; ; ; ; sa/ase;
```

For more information about auditing, see *Security Administration Guide > Auditing*.

## Related Information

[alter login \[page 47\]](#)

[alter login profile \[page 54\]](#)  
[create login \[page 216\]](#)  
[create login profile \[page 220\]](#)  
[drop login \[page 442\]](#)

## 1.69 drop precomputed result set

Drops a precomputed result set.

### Syntax

```
drop {precomputed result set | materialized view}
    [<owner_name>.<prs_name>
```

### Parameters

**precomputed result set | materialized view**

drops a precomputed result set or materialized view.

**<prs\_name>**

is the name of the precomputed result set. A fully qualified **<prs\_name>** cannot include the server or database name.

### Examples

#### Example 1

Drops the `authors_prs` precomputed result set:

```
drop precomputed result set authors_prs
```

### Standards

The `drop precomputed result set` command is a Transact-SQL extension and is not covered by the SQL standard.

## Permissions

You must be the precomputed result set owner.

## 1.70 drop procedure

Removes a procedure.

### Syntax

```
drop proc[edure] [<owner><procedure_name>
[, [.]<owner>.<procedure_name>] ...
```

### Parameters

#### <procedure\_name>

.is the name of the Transact-SQL or SQLJ procedure to drop. Specify the owner's name to drop a procedure of the same name owned by a different user in the current database. The default value for <owner> is the current user.

### Examples

#### Example 1

Deletes the stored procedure showind:

```
drop procedure showind
```

#### Example 2

Unregisters the extended stored procedure xp\_echo:

```
drop procedure xp_echo
```



## Usage

- `drop procedure` drops user-defined stored procedures, system procedures, and extended stored procedures (ESPs).
- The SAP ASE server checks the existence of a procedure each time a user or a program executes that procedure.
- A procedure group (more than one procedure with the same name but with different `number` suffixes) can be dropped with a single `drop procedure` statement. For example, if the procedures used with the application named `orders` were named `orderproc;1`, `orderproc;2`, and so on, the following statement drops the entire group:

```
drop proc orderproc
```

Once procedures have been grouped, individual procedures within the group cannot be dropped. For example, the following statement is not allowed:

```
drop procedure orderproc;2
```

You cannot drop extended stored procedures as a procedure group.

- `sp_helptext` displays the procedure's text, which is stored in `syscomments`.
- `sp_helpextendedproc` displays ESPs and their corresponding DLLs.
- Dropping an ESP unregisters the procedure by removing it from the system tables. It has no effect on the underlying DLL.
- `drop procedure` drops only user-created stored procedures from your current database.

See also `sp_depends`, `sp_dropextendedproc`, `sp_helptext`, `sp_rename` in *Reference Manual: Procedures*.

## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

## Permissions

The permission checks for `drop procedure` differ based on your granular permissions settings.

Setting	Description
---------	-------------

<b>Enabled</b>	With granular permissions enabled, you must be the procedure owner or a user with <code>drop any procedure</code> privilege.
----------------	--

<b>Disabled</b>	With granular permissions disabled, you must be the procedure owner or a user with <code>sa_role</code> .
-----------------	---

## Auditing

You can enable `drop` auditing option to audit this command. Values in `event` and `extrainfo` columns from the `sysaudits` table are:

Information	Value
Audit option	<code>drop</code>
Event	28
Command or access audited	<code>drop procedure</code>
Information in <code>extrainfo</code>	<ul style="list-style-type: none"><li>• <b>Roles</b> – current active roles</li><li>• <b>Full command text</b> – full text of <code>drop procedure</code> command</li><li>• <b>Previous value</b> – NULL</li><li>• <b>Current value</b> – NULL</li><li>• <b>Other information</b> – NULL</li><li>• <b>Proxy information</b> – original login name, if <code>set proxy</code> is in effect</li></ul>

Full command text is included in `extrainfo`. For example:

```
sa_role sso_role oper_role sybase_ts_role mon_role;  
drop procedure testproc1; ; ; ; sa/ase;
```

Since the command is executed on two different objects `testproc1` and `testproc2`, two separate audits records are generated, one for each object.

For more information about auditing, see *Security Administration Guide > Auditing*.

## 1.71 drop role

Drops a user-defined role.

### Syntax

```
drop role <role_name> [with override]
```

### Parameters

`<role_name>`

is the name of the role you want to drop.

### **with override**

overrides any restrictions on dropping a role. When you use the `with override` option, you can drop any role without having to check whether the role permissions have been dropped in each database.

## **Examples**

### **Example 1**

Drops the named role only if all permissions in all databases have been revoked. The system administrator or object owner must revoke permissions granted in each database before dropping a role, or the command fails:

```
drop role doctor_role
```

### **Example 2**

Drops the named role and removes permission information and any other reference to the role from all databases:

```
drop role doctor_role with override
```

## **Usage**

- You need not drop memberships before dropping a role. Dropping a role automatically removes any user's membership in that role, regardless of whether you use the `with override` option.
- Use `drop role` from the `master` database.
- All rows corresponding to a dropped role are removed from the `syspasswordhistory` table.

You cannot use `drop role` to drop system roles.

See also `sp_activeroles`, `sp_displaylogin`, `sp_displayroles`, `sp_helprotect` in *Reference Manual: Procedures*.

## **Standards**

ANSI SQL – Compliance level: Transact-SQL extension.

## **Permissions**

The permission checks for `drop role` differ based on your granular permissions settings.

Setting	Description
Enabled	With granular permissions enabled, you must be a user with <code>manage roles</code> privilege.
Disabled	With granular permissions disabled, you must be a user with <code>sso_role</code> .

## Auditing

You can enable the following auditing options to audit this command. Values in `event` and `extrainfo` columns from the `sysaudits` table are:

Information	Value
Audit option	<code>drop, role, security</code>
Event	85
Command or access audited	<code>drop role</code>
Information in <code>extrainfo</code>	<ul style="list-style-type: none"> <li>• <b>Roles</b> – current active roles</li> <li>• <b>Full command text</b> – full text of <code>drop role</code> command</li> <li>• <b>Previous value</b> – NULL</li> <li>• <b>Current value</b> – NULL</li> <li>• <b>Other information</b> – NULL</li> <li>• <b>Proxy information</b> – original login name, if <code>set proxy</code> is in effect</li> </ul>

Full command text is included in `extrainfo`. For example:

```
sa_role sso_role oper_role sybase_ts_role mon_role;
drop role doctor_role; ; ; ; sa/ase;
```

For more information about auditing, see *Security Administration Guide > Auditing*.

## Related Information

[alter role \[page 65\]](#)  
[create role \[page 257\]](#)  
[grant \[page 520\]](#)  
[revoke \[page 672\]](#)  
[set \[page 732\]](#)

## 1.72 drop rule

Removes a user-defined rule.

### Syntax

```
drop rule [<owner>.<rule_name>[, [<owner>.<rule_name>] ...
```

### Parameters

**<rule\_name>**

is the name of the rule to drop. Specify the owner's name to drop a rule of the same name owned by a different user in the current database. The default value for **<owner>** is the current user.

### Examples

#### Example 1

Removes the rule `pubid_rule` from the current database:

```
drop rule pubid_rule
```

### Usage

- Before dropping a rule, unbind it using `sp_unbindrule`. If the rule has not been unbound, an error message appears, and the `drop rule` command fails.
- You can bind a new rule to a column or user-defined datatype without unbinding its current rule. The new rule overrides the old one.
- After you drop a rule, the SAP ASE server enters new data into the columns that were previously governed by the rule without constraints. Existing data is not affected in any way.

See also `sp_bindrule`, `sp_help`, `sp_helptext`, `sp_unbindrule` in *Reference Manual: Procedures*.

## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

## Permissions

The permission checks for `drop rule` differ based on your granular permissions settings.

Setting	Description
---------	-------------

<b>Enabled</b>	With granular permissions enabled, you must be the rule owner or a user with <code>drop any rule</code> privilege.
----------------	--

<b>Disabled</b>	With granular permissions disabled, you must be the rule owner or a user with <code>sa_role</code> .
-----------------	--

## Auditing

You can enable `drop` auditing option to audit this command. Values in `event` and `extrainfo` columns from the `sysaudits` table are:

Information	Value
Audit option	<code>drop</code>
Event	30
Command or access audited	<code>drop rule</code>
Information in <code>extrainfo</code>	<ul style="list-style-type: none"><li>• <b>Roles</b> – current active roles</li><li>• <b>Full command text</b> – full text of <code>drop rule</code> command</li><li>• <b>Previous value</b> – NULL</li><li>• <b>Current value</b> – NULL</li><li>• <b>Other information</b> – NULL</li><li>• <b>Proxy information</b> – original login name, if <code>set proxy</code> is in effect</li></ul>

Full command text is included in `extrainfo`. For example:

```
sa_role sso_role oper_role sybase_ts_role mon_role; drop rule
pubid_rule; ; ; ; ; sa/ase;
```

For more information about auditing, see *Security Administration Guide > Auditing*.

## 1.73 drop service

The `drop service` command removes a user-defined Web service from the current database. Both the metadata and the corresponding stored procedure are removed.

### Syntax

```
drop service <service-name>
```

### Parameters

**<service-name>**

is the name for the user-defined Web service. This name can be any name that is valid for a stored procedure. If you specify the name of a service that does not exist, an exception results. Also, you cannot drop a service that is currently in use by another session.

### Examples

#### Example 1

Drops the user-defined Web service named `sp_who_service`:

```
drop service sp_who_service
```

### Usage

You must undeploy a user-defined Web service before you can drop it.

See also:

- *Web Services Users Guide*
- `sp_webservices` in *Reference Manual: Procedures*

### Permissions

The permission checks for `drop service` differ based on your granular permissions settings.

**Setting**    **Description**

**Enabled**    With granular permissions enabled, you must be the service owner or a user with `drop any procedure` privilege.

**Disabled**    With granular permissions disabled, you must be a user with `sa_role`.

## Auditing

You can enable `drop` auditing option to audit this command. Values in `event` and `extrainfo` columns from the `sysaudits` table are:

Information	Value
Audit option	<code>drop</code>
Event	28
Command or access audited	<code>drop service</code>
Information in <code>extrainfo</code>	<ul style="list-style-type: none"><li>• <b>Roles</b> – current active roles</li><li>• <b>Full command text</b> – full text of <code>drop service</code> command</li><li>• <b>Previous value</b> – NULL</li><li>• <b>Current value</b> – NULL</li><li>• <b>Other information</b> – NULL</li><li>• <b>Proxy information</b> – original login name, if <code>set proxy</code> is in effect</li></ul>

Full command text is included in `extrainfo`. For example:

```
sa_role sso_role oper_role sybase_ts_role mon_role;  
drop service rawservice; ; ; ; ; sa/ase;
```

For more information about auditing, see *Security Administration Guide > Auditing*.

## Related Information

[create service \[page 268\]](#)



## 1.74 drop table

Removes a table definition and all of its data, indexes, partition properties, triggers, encryption properties, and permissions from the database.

### Syntax

```
drop table [[<database>.]<owner>.]<table_name>  
[, [[<database>.]<owner>.]<table_name>] ...
```

### Parameters

**<table\_name>**

is the name of the table to drop. Specify the database name if the table is in another database, and specify the owner's name if more than one table by the same name exists in the database. The default value for **<owner>** is the current user, and the default value for **<database>** is the current database.

### Examples

#### Example 1

Removes the table `roysched` and its data and indexes from the current database:

```
drop table roysched
```

### Usage

- When you use `drop table`, any rules or defaults on the table lose their binding, and any triggers associated with it are automatically dropped. If you re-create a table, you must rebind the appropriate rules and defaults and re-create any triggers.
- When you drop a table, any partition condition associated with the table is also dropped.
- Dropping a table drops any decrypt default associated with the table's columns, and drops the columns' encryption properties.
- The system tables affected when a table is dropped are `sysobjects`, `syscolumns`, `sysindexes`, `sysprotects`, `syscomments`, `syspartitions`, `syspartitionkeys`, and `sysprocedures`.

- If CIS is enabled, and if the table being dropped was created with `create existing table`, the table is not dropped from the remote server. Instead, the SAP ASE server removes references to the table from the system tables.

See also `sp_depends`, `sp_help`, `sp_spaceused` in *Reference Manual: Procedures*.

## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

## Permissions

The permission checks for `drop table` differ based on your granular permissions settings.

### Setting Description

**Enabled** With granular permissions enabled, you must be the table owner or a user with `drop any table` privilege.

**Disabled** With granular permissions disabled, you must be the table owner or a user with `sa_role`.

## Auditing

You can enable `drop` auditing option to audit this command. Values in `event` and `extrainfo` columns from the `sysaudits` table are:

Information	Value
Audit option	<code>drop</code> ,
Event	27
Command or access audited	<code>drop table</code>
Information in <code>extrainfo</code>	<ul style="list-style-type: none"> <li>• <b>Roles</b> – current active roles</li> <li>• <b>Full command text</b> – full text of <code>drop table</code> command</li> <li>• <b>Previous value</b> – NULL</li> <li>• <b>Current value</b> – NULL</li> <li>• <b>Other information</b> – NULL</li> <li>• <b>Proxy information</b> – original login name, if <code>set proxy</code> is in effect</li> </ul>

Full command text is included in `extrainfo`. For example:

```
sa_role sso_role oper_role sybase_ts_role mon_role;
drop table t1; ; ; ; sa/ase;
```

If you drop two tables with the same `drop table` command, two auditing records are generated, one for each table.

For more information about auditing, see *Security Administration Guide > Auditing*.

## Related Information

[alter table \[page 70\]](#)

[create table \[page 273\]](#)

[delete \[page 391\]](#)

[truncate table \[page 809\]](#)

### 1.74.1 Restrictions for drop table

Restrictions for `drop table`.

- You cannot use the `drop table` command on system tables.
- You can drop a table in any database, as long as you are the table owner. For example, use either of the following to drop a table called `newtable` in the database `otherdb`:

```
drop table otherdb..newtable
```

```
drop table otherdb.yourname.newtable
```

- If you delete all the rows in a table or use the `truncate table` command, the table still exists until you drop it.

### 1.74.2 Dropping Tables with Cross-Database Referential Integrity Constraints

When you create a cross-database constraint, the SAP ASE server stores information in the `sysreferences` system table of each database.

Table 4: Information Stored About Referential Integrity Constraints

Information Stored in <code>sysreferences</code>	Columns with Information About Referenced Table	Columns with Information About Referencing Table
Key column IDs	<code>refkey1</code> through <code>refkey16</code>	<code>fokey1</code> through <code>fokey16</code>
Table ID	<code>reftabid</code>	<code>tableid</code>
Database name	<code>pmrydbname</code>	<code>frgndbname</code>

Because the referencing table depends on information from the referenced table, the SAP ASE server does not allow you to:

- Drop the referenced table,
- Drop the external database that contains it, or
- Use `sp_renamedb` to rename either database.

Use `sp_helpconstraint` to determine which tables reference the table you want to drop. Use `alter table` to drop the constraints before reissuing `drop table`.

You can drop a referencing table or its database. The SAP ASE server automatically removes the foreign-key information from the referenced database.

Each time you add or remove a cross-database constraint or drop a table that contains a cross-database constraint, dump both of the affected databases.

### ⚠ Caution

Loading earlier dumps of these databases can cause database corruption. For more information about loading databases with cross-database referential integrity constraints, see the *System Administration Guide*.

## 1.75 drop thread pool

Drops a user-defined pool.

### Considerations for Process Mode

`drop thread pool` is not supported in process mode.

### Syntax

```
drop thread pool <pool_name>
    [for instance <inst_name> | global]
```

### Parameters

<>

is the name of the pool you are dropping.

**for instance** [**<inst\_name>** | **global**]

allows you to specify either a specific instance by name, or all instances (by using `global`).

## Examples

### Example 1

Drops a pool named `sales_pool`:

```
drop thread pool sales_pool
```

## Usage

- The SAP ASE server reassigns tasks associated with the dropped thread pool to `syb_default_pool`.
- You cannot drop thread pools that are currently using an execution class definition. Use `sp_dropexeclass` to remove the execution class.
- You cannot drop system-created thread pools (those beginning with `syb_`).
- Thread pools must wait for currently running tasks to yield before they can be dropped, which may cause a slight delay in the SAP ASE server dropping the pool.
- Tasks running in a thread pool that you drop migrate to `syb_default_pool`.
- You cannot use Transact-SQL variables as parameters to `drop thread pool`.
- You can issue `drop thread pool` with `execute immediate`.

## Standards

ANSI SQL-Compliance level: Transact-SQL extension

## Permissions

The permission checks for `drop thread pool` differ based on your granular permissions settings.

Setting	Description
---------	-------------

<b>Enabled</b>	With granular permissions enabled, you must be a user with <code>manage any thread pool</code> privilege.
----------------	---

<b>Disabled</b>	With granular permissions disabled, you must be a user with <code>sa_role</code> .
-----------------	--

## Auditing

You can enable `thread_pool` auditing option to audit this command. Values in `event` and `extrainfo` columns from the `sysaudits` table are:

Information	Value
Audit option	<code>thread_pool</code>
Event	144
Command or access audited	<code>drop thread pool</code>
Information in <code>extrainfo</code>	<ul style="list-style-type: none"><li>• <b>Roles</b> – current active roles</li><li>• <b>Full command text</b> – full text of <code>drop thread pool</code> command</li><li>• <b>Previous value</b> – NULL</li><li>• <b>Current value</b> – NULL</li><li>• <b>Other information</b> – NULL</li><li>• <b>Proxy information</b> – original login name, if <code>set proxy</code> is in effect</li></ul>

Full command text is included in `extrainfo`. For example:

```
sa_role sybase_ts_role mon_role;  
drop thread pool sales_pool; ; ; ; user0/ase;
```

For more information about auditing, see *Security Administration Guide > Auditing*.

## Related Information

[alter thread pool \[page 111\]](#)

[create thread pool \[page 320\]](#)

## 1.76 drop trigger

Removes a trigger.

### Syntax

```
drop trigger [<owner>.<trigger_name>  
[, [<owner>.<trigger_name>] ...
```

## Parameters

`<trigger_name>`

is the name of the trigger to drop. Specify the owner's name to drop a trigger of the same name owned by a different user in the current database. The default value for `<owner>` is the current user.

## Examples

### Example 1

Removes `trigger1` from the current database:

```
drop trigger trigger1
```

## Usage

- `drop trigger` drops a trigger in the current database.
- You need not explicitly drop a trigger from a table to create a new trigger for the same operation (`insert`, `update`, or `delete`). In a table or column, each new trigger for the same operation overwrites the previous one.
- When a table is dropped, the SAP ASE server automatically drops any triggers associated with it.
- You can use `drop trigger` to remove or replace an existing trigger, or multiple triggers. The `drop trigger` command drops a single trigger. If you have multiple triggers on a table, you can drop them individually.

See also `sp_depends`, `sp_help`, `sp_helptext` in *Reference Manual: Procedures*.

## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

## Permissions

The permission checks for `drop trigger` differ based on your granular permissions settings.

## Setting Description

**Enabled** With granular permissions enabled, you must be the trigger owner or a user with `drop any trigger` privilege.

**Disabled** With granular permissions disabled, you must be the trigger owner or a user with `sa_role`.

## Auditing

You can enable `drop` auditing option to audit this command. Values in `event` and `extrainfo` columns from the `sysaudits` table are:

Information	Value
Audit option	<code>drop</code>
Event	29
Command or access audited	<code>drop trigger</code>
Information in <code>extrainfo</code>	<ul style="list-style-type: none"><li>• <b>Roles</b> – current active roles</li><li>• <b>Full command text</b> – full text of <code>drop trigger</code> command</li><li>• <b>Previous value</b> – NULL</li><li>• <b>Current value</b> – NULL</li><li>• <b>Other information</b> – NULL</li><li>• <b>Proxy information</b> – original login name, if <code>set proxy</code> is in effect</li></ul>

Full command text is included in `extrainfo`. For example:

```
sa_role sso_role oper_role sybase_ts_role mon_role;  
drop trigger trigger1; ; ; ; sa/ase;
```

For more information about auditing, see *Security Administration Guide > Auditing*.

## 1.77 drop type

Removes a user-defined table type.

### Syntax

```
drop type <type_name>
```



## Parameters

`<type_name>`

is the name of the table type to be dropped. You cannot drop a table type if it is referenced by tables or other database objects.

## Examples

### Example 1

Drops the `test_type` table type:

```
DROP TYPE test_type
```

## Usage

You cannot drop a table type if it is referenced by tables or other database objects.

## Permissions

`drop type` command is available to all users. Permission checks do not differ based on the granular permissions settings.

## Auditing

This command is not audited.

## Related Information

[create type \[page 337\]](#)

[create type \[page 337\]](#)

## 1.78 drop view

Removes one or more views from the current database.

### Syntax

```
drop view [<owner>.<view_name> [, [<owner>.<view_name>] ...
```

### Parameters

**<view\_name>**

is the name of the view to drop. Specify the owner's name to drop a view of the same name owned by a different user in the current database. The default value for **<owner>** is the current user.

### Examples

#### Example 1

Removes the view `new_price` from the current database:

```
drop view new_price
```

### Usage

- When you use `drop view`, the definition of the view and other information about it, including privileges, is deleted from the system tables `sysobjects`, `syscolumns`, `syscomments`, `sysdepends`, `sysprocedures`, and `sysprotects`.
- Existence of a view is checked each time the view is referenced, for example, by another view or by a stored procedure.

See also `sp_depends`, `sp_help`, `sp_helptext` in *Reference Manual: Procedures*.

### Standards

ANSI SQL – Compliance level: Transact-SQL extension.

## Permissions

The permission checks for `drop view` differ based on your granular permissions settings.

Setting	Description
---------	-------------

<b>Enabled</b>	With granular permissions enabled, you must be the view owner or a user with <code>drop any view</code> privilege.
----------------	--

<b>Disabled</b>	With granular permissions disabled, you must be the view owner or a user with <code>sa_role</code> .
-----------------	--

## Auditing

You can enable `drop` auditing option to audit this command. Values in `event` and `extrainfo` columns from the `sysaudits` table are:

Information	Value
Audit option	<code>drop</code>
Event	33
Command or access audited	<code>drop table</code>
Information in <code>extrainfo</code>	<ul style="list-style-type: none"><li>• <b>Roles</b> – current active roles</li><li>• <b>Full command text</b> – full text of <code>drop table</code> command</li><li>• <b>Previous value</b> – NULL</li><li>• <b>Current value</b> – NULL</li><li>• <b>Other information</b> – NULL</li><li>• <b>Proxy information</b> – original login name, if <code>set proxy</code> is in effect</li></ul>

Full command text is included in `extrainfo`. For example:

```
sa_role sso_role oper_role sybase_ts_role mon_role;  
drop view new_price; ; ; ; ; sa/ase;
```

For more information about auditing, see *Security Administration Guide > Auditing*.

## 1.79 dump configuration

Creates a backup of the SAP ASE configuration files into a specified dump directory. The copy is created by the SAP ASE server, not the Backup Server.

### Syntax

```
dump config[uration] to <dump_dir>
    [with {file = (<file_option>, <file_option>...)}]
```

### Parameters

to <dump\_dir>

specifies path to the directory in which to save the configuration file

with file = (<file\_option>, <file\_option>...)

allows you to make the backup of one or more files based on the options you specify.

Valid <file\_option> values include:

- server\_config[uration] – server configuration file.
- dump\_history – dump history file.
- – cluster configuration file. In cluster configurations in SAP ASE Cluster Edition, each instance can have its own server configuration file. The dump configuration command dumps the server configuration files of the instance on which it was executed. The cluster configuration file is generated from the quorum device, and is named cluster.cfg with the current timestamp appended.
- 'all' – (default) all listed (known) configuration files.

If you omit <file\_option>, all existing configuration files are backed up.

### Examples

#### Example 1

cluster\_config[uration] Creates a backup of the server configuration file and the dump history file:

```
dump configuration to "/myserver/test/backupserver"
    with file = "server_config"
```

## Example 2

Creates a backup of all listed (known) configuration files:

```
dump configuration
```

## Usage

- The `<list_option>` value 'all' must be in either single or double quotes.

See also:

- `dump database`, `load database`, `load transaction`, `online database`
- *Backing Up and Restoring User Databases* in the *System Administration Guide*.
- `sp_addumpdevice`, `sp_dboption`, `sp_dropdevice`, `sp_helpdevice`, `sp_hidetext`, `sp_logdevice`, `sp_volchanges` in *Reference Manual: Procedures*

## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

## Permissions

The permission checks for `dump configuration` differ based on your granular permissions settings.

**Setting**    **Description**

**Enabled**    With granular permissions enabled, you must be a user with `manage dump configuration` privilege.

**Disabled**    With granular permissions disabled, you must be a user with `oper_role` or `sa_role`.

## Auditing

You can enable `dump_config` auditing option to audit this command. Values in `event` and `extrainfo` columns from the `sysaudits` table are:

Information	Value
Audit option	<code>dump_config</code>
Event	149

Information	Value
Command or access audited	dump configuration
Information in <code>extrainfo</code>	<ul style="list-style-type: none"> <li>• <b>Roles</b> – current active roles</li> <li>• <b>Full command text</b> – full text of <code>dump configuration</code> command</li> <li>• <b>Previous value</b> – NULL</li> <li>• <b>Current value</b> – NULL</li> <li>• <b>Other information</b> – NULL</li> <li>• <b>Proxy information</b> – original login name, if <code>set proxy</code> is in effect</li> </ul>

Full command text is included in `extrainfo`. For example:

```
sa_role sso_role oper_role sybase_ts_role mon_role;
  dump configuration to "/tmp" with file =
"server_config"; ; ; ; sa/ase;
```

For more information about auditing, see *Security Administration Guide > Auditing*.

## 1.80 dump database

Makes a backup copy of the entire database, including the transaction log, in a form that can be read in with `load database`. Dumps and loads are performed through Backup Server.

The target platform need not be the same as the source platform where the dump database operation occurred. However, there are restrictions when using combinations of cross-platform dump and load when compression and remote backupserver are involved. See [Restrictions for dump database \[page 483\]](#).

### Syntax

```
dump database <database_name> cumulative
  [using config = <config_name>]
  [with]
  to [compress::[<compression_level>::]]<stripe_device>
    [at <backup_server_name>]
    [density = <density_value>,
    blocksize = <number_bytes>,
    capacity = <number_kilobytes>,
    dumpvolume = <volume_name>,
    file = <file_name>]
    [with shrink_log]
    with verify[= header | full]
  [stripe on [compress::[<compression_level>::]]<stripe_device>
    [at <backup_server_name>]
    [density = <density_value>,
    blocksize = <number_bytes>,
    capacity = <number_kilobytes>,
    dumpvolume = <volume_name>,
    file = <file_name>]]
```

```

[[stripe on [compress::<<compression_level>::]]<stripe_device>
 [at <backup_server_name>]
 [density = <density_value>,
  blocksize = <number_bytes>,
  capacity = <number_kilobytes>,
  dumpvolume = <volume_name>,
  file = <file_name>]]...]
[with {
  density = <density_value>,
  blocksize = <number_bytes>,
  capacity = <number_kilobytes>,
  compression = <compress_level>, verify={crc | read_after_write}
  dumpvolume = <volume_name>,
  file = <file_name>,
  [dismount | nodismount],
  [nounload | unload],
  passwd = <password>,
  retaindays = <number_days>,
  verify [= header | full]
  [noinit | init],
  notify = {client | operator_console},
  label = '<label_name>'
}]

```

(Tivoli Storage Manager) Use this syntax for copying the database when the Tivoli Storage Manager provides backup services.

```

dump database <database_name>
to "syb_tsm::<<object_name>"
 [blocksize = <number_bytes>]
[stripe on "[syb_tsm::<<object_name>"
 [blocksize = <number_bytes>]]...]
[with {
  blocksize = <number_bytes>,
  compression = <compress_level>,
  passwd = <password>,
  [noinit | init],
  notify = {client | operator_console},
  verify[ = header | full]
} ]

```

## Parameters

**config = <config\_name>**

You cannot specify a stripe directory as a parameter for the command if you use a dump configuration. The SAP ASE server creates the dump files in the stripe directory specified by the dump configuration. The dump files are named using this convention: reads the specified dump configuration and performs a dump operation using the specified values.<database\_name>.<dump\_type>.<date-timestamp>.<stripeID>.

Explicitly specified command parameters override the parameter values specified by the dump configuration.

**cumulative**

specify that the backup you create is a cumulative incremental dump.

**<database\_name>**

is the name of the database from which you are copying data. The database name can be specified as a literal, a local variable, or a stored procedure parameter.

**compress::<compression\_level>**

has been deprecated, and is included only for compatibility with older applications. Use "compression = <compress\_level>" for compression instead. See *Backing Up and Restoring User Databases* in the *reads the specified dump configuration and performs a dump operation using the System Administration Guide, Volume 2* for more information about the `compress` option.

### Note

You should use the native "compression = <compress\_level>" option over the older "compress::<compression\_level>" option. The native option allows compression of both local and remote dumps, and the dumps that it creates describe their own compression level during a load. The older option is retained for compatibility with older applications.

**to <stripe\_device>**

is the device to which to copy the data.

**at <backup\_server\_name>**

is the name of the Backup Server. Do not specify this parameter when dumping to the default Backup Server. Specify this parameter only when dumping over the network to a remote Backup Server. You can specify as many as 32 remote Backup Servers with this option. When dumping across the network, specify the *network name* of a remote Backup Server running on the machine to which the dump device is attached. For platforms that use interfaces files, the <backup\_server\_name> must appear in the interfaces file.

**density = <density\_value>**

overrides the default density for a tape device. Valid densities are 800, 1600, 6250, 6666, 10000, and 38000. Not all values are valid for every tape drive; use the correct density for your tape drive.

**blocksize = <number\_bytes>**

overrides the default block size for a dump device. The block size must be at least one database page (2048 bytes for most systems) and must be an exact multiple of the database page size. For optimal performance, specify the `blocksize` as a power of 2, for example, 65536, 131072, or 262144.

**capacity = <number\_kilobytes>**

is the maximum amount of data that the device can write to a single tape volume. The capacity must be at least five database pages and should be less than the recommended capacity for your device.

A general rule for calculating capacity is to use 70 percent of the manufacturer's maximum capacity for the device, allowing 30 percent for overhead such as record gaps and tape marks. The maximum capacity is the capacity of the device on the drive, not the drive itself. This rule works in most cases, but may not work in all cases, due to differences in overhead across vendors and across devices.



On UNIX platforms that cannot reliably detect the end-of-tape marker, indicate how many kilobytes can be dumped to the tape. You must supply a `capacity` for dump devices specified as a physical path name. If a dump device is specified as a logical device name, the Backup Server uses the `<size>` parameter stored in the `sysdevices` system table unless you specify a capacity.

**compression = <compress\_level>**

is a number between 0 and 9, 100, or 101. For single-digit compression levels, 0 indicates no compression, and 9 provides the highest level of compression. Compression levels of 100 and 101 provide a faster, more less efficient compression mode, with 100 providing faster compression and 101 providing better compression. If you do not specify `<compress_level>`, the SAP ASE server does not compress the dump.

#### **i** Note

You should use the native "compression = <compress\_level>" option over the older "compress::<compression\_level>" option, which is retained only for compatibility with older applications.

**verify={crc | read\_after\_write}**

adds a cyclic redundancy check for accidental changes to raw data for database dumps created with compression to check and for verification that the compression blocks can be correctly read and decompressed. Options are:

- `verify=crc` – indicates that you are performing a cyclic redundancy check.
- `verify=read_after_write` – Backup Server rereads every compressed block after writing and decompressing it. If Backup Server finds an error, it prints the offset in the file it finds the error. You cannot use `verify=read_after_write` with `load database` commands.

Use `load database ... verify[only]=crc` to verify the crc matches.

**dumpvolume = <volume\_name>**

establishes the name that is assigned to the volume. The maximum length of `<volume_name>` is 6 characters. Backup Server writes the `<volume_name>` in the ANSI tape label when overwriting an existing dump, dumping to a new tape, or dumping to a tape whose contents are not recognizable. The `load database` command checks the label and generates an error message if the wrong volume is loaded.

#### **⚠** Caution

Label each tape volume as you create it so that the operator can load the correct tape.

**with shrink\_log**

is used when a hole in the database might be created when the `alter database log off` command is used to shrink space from the log. This command automatically removes holes at the end of the database if the database is not in a dump sequence. Likewise, `dump database` automatically removes any hole at the end of the database if the database is not in a dump sequence (that is, when you are forced to run `dump database` because `dump transaction` is not allowed, when, for example, any minimally logged command is performed). The `with shrink_log` option of `dump`

database removes holes at the end of the database, regardless of whether the database is in a dump sequence or not..

**with verify[= header | full]**

allows the Backup Server to perform a minimal header or structural row check on the data pages as they are being copied to the archives. There are no structural checks done at this time to `gam`, `oam`, `allocation pages`, `indexes`, `text`, or `log` pages. The only other check is done on pages where the page number matches to the page header. Any faults found are reported in the `backupserver` error log.

**stripe on <stripe\_device>**

is an additional dump device. The Backup Server splits the database into approximately equal portions, and sends each portion to a different device. Dumps are made concurrently on all devices, reducing the time required to make a dump, and requiring fewer volume changes during the dump. The maximum number of supported stripes in the command syntax is 1024, however, this depends on the Backup Server configuration. In theory a Backup Server with unlimited resources can support a maximum of 639 stripes. The maximum number of stripes depends on:

- Maximum number of network connections that Backup Server can originate (specified by the `-N` option). The default is 25.
- Maximum number of server connections into the remote Backup Server (specified by the `-c` option). The default is 30.
- Maximum number of threads. The default is 48 and the maximum is 12288.
- Each stripe starts 2 `symboltblufs` when doing local dumps.
- The OS maximum number of descriptors.
- Open Server has a limitation of 1280 file descriptors that an application can keep track of.

As a general rule, the maximum number of stripes having unlimited resources is:

$$\frac{\text{MIN(OS file descriptors, Open Server descriptors)} - 2}{2} = \frac{1278}{2} = 639$$

**dismount | nodismount**

on platforms that support logical dismount, determines whether tapes remain mounted. By default, all tapes used for a dump are dismounted when the dump completes. Use `nodismount` to keep tapes available for additional dumps or loads.

**nounload | unload**

determines whether tapes rewind after the dump completes. By default, tapes do not rewind, allowing you to make additional dumps to the same tape volume. Specify `unload` for the last dump file to be added to a multidump volume. This rewinds and unloads the tape when the dump completes.

**passwd = <password>**

is the password you provide to protect the dump file from unauthorized users. The password must be between 6 and 30 characters long. You cannot use variables for passwords. See *Managing Adaptive Server Logins, Database Users, and Client Connections* in the *System Administration Guide, Volume 1*.

**retaindays = <number\_days>**

(UNIX systems) when dumping to disk, specifies the number of days that Backup Server protects you from overwriting the dump. If you try to overwrite the dump before it expires, Backup Server requests confirmation before overwriting the unexpired volume.

#### **i Note**

This option applies only when dumping to a disk; it does not apply to tape dumps.

The `<number_days>` must be a positive integer or 0, for dumps that you can overwrite immediately. If you do not specify a `retaindays` value, Backup Server uses the `tape retention in days` value set by `sp_configure`.

**noinit | init**

determines whether to append the dump to existing dump files or reinitialize (overwrite) the tape volume. By default, the SAP ASE server appends dumps following the last end-of-tape mark, allowing you to dump additional databases to the same volume. New dumps can be appended only to the last volume of a multivolume dump. Use `init` for the first database you dump to a tape to overwrite its contents.

Use `init` when you want Backup Server to store or update tape device characteristics in the tape configuration file. See the *System Administration Guide*.

**file = <file\_name>**

is the name of the dump file. The name cannot exceed 17 characters and must conform to operating system conventions for file names.

**notify = {client | operator\_console}**

overrides the default message destination.

On operating systems that offer an operator terminal feature, volume change messages are always sent to the operator terminal on the machine on which Backup Server is running. Use `client` to route other Backup Server messages to the terminal session that initiated the `dump database`.

On operating systems that do not offer an operator terminal feature, such as UNIX, messages are sent to the client that initiated the `dump database`. Use `operator_console` to route messages to the terminal on which Backup Server is running.

**label = '<label\_name>'**

is the label to identify a specific dump. The maximum length of `<label_name>` is 30 bytes.

The RegAgent thread sends the specified label to Replication Server in both Log Transfer Language (LTL) replication and stream replication. The dump label coordinates `dump` and `load` commands between the primary and replicate databases while rematerializing the replicate database. The dump labels are recorded in the database dump history file.

**syb\_tsm::<obj\_name>**

is the keyword that invokes the `libsyb_tsm.so` module that enables communication between Backup Server and Tivoli Storage Manager.

<object\_name>

is the name of the backup object on TSM server.

## Examples

### Example 1

Dumps the database using the `dmp_cfg2` dump configuration:

```
dump database testdb using config = dmp_cfg2
```

### Example 2

Dumps the database using the `dmp_cfg2` dump configuration. The archive files created as part of the dump operation are password-protected:

```
dump database testdb using config = dmp_cfg2
with passwd='mypass01'
```

#### i Note

The password must be in single or double quotes.

### Example 3

Performs a database dump using the `dmp_cfg2` dump configuration, explicitly specifying compression level 6, thereby overriding the compression level that was configured in `dmp_cfg2`:

```
dump database testdb using config = dmp_cfg2
with compression=6
```

### Example 4

Dumps the database `pubs2` to a tape device. If the tape has an ANSI tape label, this command appends this dump to the files already on the tape, since the `init` option is not specified:

```
dump database pubs2
to "/dev/nrmt0"
```

### Example 5

(UNIX only) Dumps the `pubs2` database, using the `REMOTE_BKP_SERVER` Backup Server. The command names three dump devices, so the Backup Server dumps approximately one-third of the database to each device. This command appends the dump to existing files on the tapes. The `retaindays` option specifies that the tapes cannot be overwritten for 14 days:

```
dump database pubs2
to "/dev/rmt4" at REMOTE_BKP_SERVER
stripe on "/dev/nrmt5" at REMOTE_BKP_SERVER
stripe on "/dev/nrmt0" at REMOTE_BKP_SERVER
with retaindays = 14
```

### Example 6

Initializes the tape volume, overwriting any existing files:

```
dump database pubs2
```

```
to "/dev/nrmt0"  
with init
```

### Example 7

Rewinds the dump volumes upon completion of the dump:

```
dump database pubs2  
to "/dev/nrmt0"  
with unload
```

### Example 8

(UNIX only) Sends Backup Server messages requesting volume changes to the client which initiated the dump request, rather than sending them to the default location, the console of the Backup Server machine:

```
dump database pubs2  
to "/dev/nrmt0"  
with notify = client
```

### Example 9

Creates a compressed dump of the pubs2 database into a local file called `dmp090100.dmp` using a compression level of 4:

```
dump database pubs2 to  
"compress::4::/opt/bin/Sybase/dumps/dmp090100.dmp"
```

Alternatively, you can create a compressed dump of the pubs2 database into a local file called `dmp090100.dmp` using a compression level of 100 using `compression = <compression_level>` syntax:

```
dump database pubs2 to "/opt/bin/Sybase/dumps/dmp090100.dmp"  
with compression = 100
```

### Example 10

Dumps the pubs2 database to the remote machine called "remotemachine" and uses a compression level of 4:

```
dump database pubs2 to "/Syb_backup/mydb.db" at remotemachine  
with compression = "4"
```

### Example 11

Dumps the pubs2 database to the TSM backup object "obj1.1":

```
dump database pubs2 to "syb_tsm::obj1.1"
```

### Example 12

Dumps the pubs2 database to the TSM backup object "obj1.2" using multiple stripes:

```
dump database pubs2 to "syb_tsm::obj1.2"  
stripe on "syb_tsm::obj1.2"  
stripe on "syb_tsm::obj1.2"  
stripe on "syb_tsm::obj1.2"  
stripe on "syb_tsm::obj1.2"
```

### Example 13

Removes the last fragment in `sales_db1`, which is a database hole at the end of the database.

`select *` indicates there is a hole at the end of the database:

```
select * from sysusages where dbid=db_id("sales_db1")
go
```

dbid	segmap	lstart	size	vstart	location	unreservedpgs	crdate	vde
5	3	0	1536	1536	0	598	May 5 2011	
2:59PM	3							
5	4	1536	1536	1536	0	1530	May 5 2011	
2:59PM	4							
5	0	3072	1536	3072	4	1526	May 5 2011	
2:59PM	-5							

```
dump database sales_db1 to "/tmp/sales_db1.dmp" with shrink_log
go
```

```
Backup Server session id is: 42. Use this value when executing the
'sp_volchanged' system
stored procedure after fulfilling any volume change request from the Backup
Server.
Backup Server: 4.41.1.1: Creating new disk file /tmp/sales_db1.dmp.
Backup Server: 6.28.1.1: Dumpfile name 'sales_db1111250D8E6 ' section number
1 mounted
on disk file '/tmp/sales_db1.dmp'
Backup Server: 4.188.1.1: Database sales_db1: 892 kilobytes (55%) DUMPED.
Backup Server: 4.188.1.1: Database sales_db1: 934 kilobytes (100%) DUMPED.
Backup Server: 3.43.1.1: Dump phase number 1 completed.
Backup Server: 3.43.1.1: Dump phase number 2 completed.
Backup Server: 3.43.1.1: Dump phase number 3 completed.
Backup Server: 4.188.1.1: Database sales_db1: 942 kilobytes (100%) DUMPED.
Backup Server: 3.42.1.1: DUMP is complete (database sales_db1).
```

Run `select *` to confirm that the fragment is successfully removed:

```
select * from sysusages where dbid=db_id("sales_db1")
go
```

dbid	segmap	lstart	size	vstart	location	unreservedpgs	crdate	vde
5	3	0	1536	1536	0	598	May 5 2011	
2:59PM	3							
5	4	1536	1536	1536	0	1530	May 5 2011	
2:59PM	4							

### Example 14

Verifies database `new_dump` before dumping it to the `mydumpdev` device:

```
dump database new_dump to mydumpdev with compression=x,verify=read_after_write
```

### Example 15

Performs a cyclic redundancy check and rereads every compressed block before dumping database `new_dump` to the `mydumpdev` device:

```
dump database new_dump to mydumpdev with
compression=x,verify=read_after_write,verify=crc
```

### Example 16

Dumps the `pubs2` database with the `pubs2_dmp` label :

```
dump database pubs2
with label = 'pubs2_dmp'
```

## Usage

If you use `sp_hidetext` followed by a cross-platform dump and load, you must manually drop and re-create all hidden objects.

`dump database` executes in three phases. A progress message informs you when each phase completes. When the dump is finished, it reflects all changes that were made during its execution, except for those initiated during phase 3.

Cyclic redundancy checks:

- Dumps created without the `verify=crc` parameter use the same format as versions of Backup Server earlier than 16.0.
- SAP ASE ignores the `verify=crc` option if the database was not originally dumped using `verify=crc`.
- You cannot load dumps that include cyclic redundancy checks with versions of Backup Server that do not include this functionality.
- `verify={crc | read_after_write}` checks are applicable only for files created using the `with compression` parameter.
- `verify=crc` works with any file type, including raw devices, disk files, tapes, pipes, or APIs. However, `verify=read_after_write` requires a 'seek back' for rereading the block, and is applicable only with raw devices and disk files.
- SAP ASE ignores, and does not raise an error message, if you include `verify={crc | read_after_write}` parameters that are not applicable.

Dumping compressed data:

- You cannot create a dump of a database that contains a compressed table on one platform and load this dump on a different platform. Doing so displays an error message.
- Compressed data is dumped directly to an archived location.
- `create index` commands on compressed tables that contain any form of compressed or uncompressed rows are fully recovered during a load transaction.

If you issue a `dump` command without the `init` qualifier and Backup Server cannot determine the device type, the `dump` command fails. See the *System Administration Guide, Volume 2*.

Backup servers:

- You must have a Backup Server running on the same machine as the SAP ASE server. The Backup Server must be listed in the `master..sys.servers` table. This entry is created during installation or upgrade; do not delete it.
- If your backup devices are located on another machine so that you dump across a network, you must also have a Backup Server installed on the remote machine.

The `dump database` command takes into account when a device is mirrored and will store the path to mirror devices along with regular devices in the dump header. The `sybdumptran` utility first attempts to open the primary device, and in the event the primary device cannot be opened, the mirrored device is opened, if one exists.

### i Note

If you are planning to develop new applications with SAP ASE, avoid using Backup Server 32-bit. Backup Server 64-bit is available as a migration path. End of life for 32-bit Backup server is scheduled for January of 2018.

See also:

- *Backing Up and Restoring User Databases in the System Administration Guide, Volume 2: Using Backup Server with IBM Tivoli Storage Manager* for `dump database` syntax when the Tivoli Storage Manager is licensed at your site..
- `sp_addthreshold`, `sp_dumpdevice`, `sp_dropdevice`, `sp_droptreshold`, `sp_helpdb`, `sp_helpdevice`, `sp_helpthreshold`, `sp_hidetext`, `sp_logdevice`, `sp_spaceused`, `sp_volchanged` in *Reference Manual: Procedures*

## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

## Permissions

The permission checks for `dump database` differ based on your granular permissions settings.

Setting	Description
Enabled	With granular permissions enabled, you must be the database owner, or a user with <code>dump database privilege</code> or <code>own database privilege</code> on the database.
Disabled	With granular permissions disabled, you must be the database owner or a user with <code>sa_role</code> , <code>replication_role</code> , or <code>oper_role</code> .



## Auditing

You can enable `dump` auditing option to audit this command. Values in `event` and `extrainfo` columns from the `sysaudits` table are:

Audit option	Event	Command or access audited	Information in <code>extrainfo</code> :
<code>dump</code>	34	<code>dump database</code>	<ul style="list-style-type: none"><li>• <b>Roles</b> – current active roles</li><li>• <b>Full command text</b> – full text of <code>dump database</code> command (password is obfuscated)</li></ul>
<code>dump</code>	150	<code>dump database...cumulative</code>	<ul style="list-style-type: none"><li>• <b>Previous value</b> – NULL</li><li>• <b>Current value</b> – NULL</li><li>• <b>Other information</b> – NULL</li><li>• <b>Proxy information</b> – original login name, if set <code>proxy</code> is in effect</li></ul>

Full command text (with obfuscated password) is included in `extrainfo`. For example:

```
sa_role sso_role oper_role sybase_ts_role mon_role;
dump database tdb2 to "/tmp/tdb2.dmp" with passwd = *****; ; ; ; ; sa/ase;
```

For more information about auditing, see *Security Administration Guide > Auditing*.

## Related Information

[dump transaction \[page 490\]](#)

[load database \[page 585\]](#)

[load transaction \[page 603\]](#)

## 1.80.1 Commands and System Procedures Used to Back Up Databases

Commands and system procedures used to back up databases.

To	Use
Make routine dumps of the entire database, including the transaction log.	<code>dump database</code>
Make routine dumps of the transaction log, then truncate the inactive portion. The inactive portion of a transaction log is not truncated if <code>dump transaction</code> is running concurrently with <code>dump database</code> .	<code>dump transaction</code>

To	Use
Dump the transaction log after failure of a database device.	<code>dump transaction with no_truncate</code>
Truncate the log without making a backup, then copy the entire database.	<code>dump transaction with truncate_only</code> <code>dump database</code>
Truncate the log after your usual method fails due to insufficient log space, then copy the entire database.	<code>dump transaction with no_log</code> <code>dump database</code>
Respond to the Backup Server volume change messages.	<code>sp_volchanged</code>

## 1.80.2 Scheduling Dumps

Considerations for scheduling dumps.

- SAP ASE database dumps are dynamic—they can take place while the database is active. However, they may slow the system down slightly, so you may want to run `dump database` when the database is not being heavily updated.
- Back up the `master` database regularly and frequently. In addition to your regular backups, `dump master` after each `create database`, `alter database`, and `disk init` command is issued.
- Back up the `model` database each time you make a change to the database.
- Use `dump database` immediately after creating a database, to make a copy of the entire database. You cannot run `dump transaction` on a new database until you have run `dump database`.
- Each time you add or remove a cross-database constraint or drop a table that contains a cross-database constraint, `dump` both of the affected databases.

### ⚠ Caution

Loading earlier dumps of these databases can cause database corruption.

- Develop a regular schedule for backing up user databases and their transaction logs.
- Use thresholds to automate backup procedures. To take advantage of SAP ASE last-chance threshold, create user databases with log segments on a device that is separate from data segments. For more information about thresholds, see the *System Administration Guide*.

## 1.80.3 Specifying Dump Devices

Usage information for specifying dump devices.

- You can specify the dump device as a literal, a local variable, or a parameter to a stored procedure.

- You cannot dump to the null device (on UNIX, `/dev/null`).
- Dumping to multiple stripes is supported for tape and disk devices. Placing multiple dumps on a device is supported only for tape devices.
- You can specify a local dump device as:
  - A logical device name from the `sysdevices` system table
  - An absolute path name
  - A relative path name

Backup Server resolves relative path names using the current working directory in the SAP ASE server.

- When dumping across the network, you must specify the absolute path name of the dump device. The path name must be valid on the machine on which Backup Server is running. If the name includes any characters except letters, numbers, or the underscore (`_`), you must enclose it in quotes.
- Ownership and permissions problems on the dump device may interfere with the use of `dump` commands. `sp_addumpdevice` adds the device to the system tables, but does not guarantee that you can dump to that device or create a file as a dump device.
- You can run more than one dump (or load) at the same time, as long as each uses different dump devices.

## 1.80.4 Restrictions for dump database

Restrictions for using `dump database`.

- The maximum file path/name size for a physical device is 127 characters.
- If a database has proxy tables, the proxy tables are a part of the database save set. The content data of proxy tables is not included in the save; only the pointer is saved and restored.
- Named pipes are supported as a backup device. However, Backup Server does not attempt to create a named pipe. Instead, you must create the named pipe externally before executing the `dump database` command (you need not do this for regular file).
- You cannot remove holes that are not at the end of the database using the `with shrink_log` option.
- You cannot mix SAP dumps and non-SAP data (for example, UNIX archives) on the same tape.
- If a database has cross-database referential integrity constraints, the `sysreferences` system table stores the name—not the ID number—of the external database. The SAP ASE server cannot guarantee referential integrity if you use `load database` to change the database name or to load it onto a different server.

### Caution

Before dumping a database to load it with a different name or move it to another SAP ASE server, use `alter table` to drop all external referential integrity constraints.

- You cannot use `dump database` in a user-defined transaction.
- If you issue `dump database` on a database where a `dump transaction` is already in progress, `dump database` sleeps until the transaction dump completes.
- When using 1/4-inch cartridge tape, you can dump only one database or transaction log per tape.
- You cannot dump a database if it has offline pages. To force offline pages online, use `sp_forceonline_db` or `sp_forceonline_page`.
- Before you run `dump database`, for a cross-platform dump and load, move the database to a transactional quiescent status:
  1. Verify the database runs cleanly by executing `dbcc checkdb` and `dbcc checkalloc`.

2. To prevent concurrent updates from open transactions by other processes during `dump database`, use `sp_dboption` to place the database in a single-user mode.
  3. Flush statistics to `systabstats` using `sp_flushstats`.
  4. Wait for 10 to 30 seconds, depending on the database size and activity.
  5. Run `checkpoint` against the database to flush updated pages.
  6. Run `dump database`.
- `dump transaction` and `load transaction` are not allowed across platforms.
  - `dump database` and `load database` to or from a remote `backupserver` are not supported across platforms if the dumps are compressed.
  - You cannot load a password-protected dump file across platforms.
  - If you perform `dump database` and `load database` for a parsed XML object, you must parse the text again after the `load database` is completed.
  - The SAP ASE server cannot translate embedded data structures stored as `binary`, `varbinary`, or `image` columns.
  - `load database` is not allowed on the `master database` across platforms.
  - Stored procedures and other compiled objects are recompiled from the SQL text in `syscomments` at the first execution after the `load database`.  
If you do not have permission to recompile from text, then the person who does must recompile from text using `dbcc upgrade_object` to upgrade objects.

#### **i Note**

If you migrate login records in the `syslogins` system table in the `master` database from Solaris to Linux, you can perform a `bcpl -c` character format bulk copy, and the login password from Solaris is compatible on Linux. For all other combinations and platforms, login records must be re-created because the passwords are not compatible.

## **1.80.5 Dumping Databases with Devices That Are Mirrored**

At the beginning of a `dump database`, the SAP ASE server passes Backup Server the primary device name of all database and log devices. If the primary device has been unmirrored, the SAP ASE server instead passes the name of the secondary device. If any named device fails before the Backup Server completes its data transfer, the SAP ASE server aborts the dump.

If a user attempts to unmirror any of the named database devices while a `dump database` is in progress, the SAP ASE server displays a message. The user executing the `disk unmirror` command can abort the dump or defer the `disk unmirror` until after the dump is complete.

## 1.80.6 Dumping the System Databases

The `master`, `model`, and `sybssystemprocs` databases do not have separate segments for their transaction logs. Use `dump transaction with truncate_only` to purge the log, then use `dump database` to back up the database.

Backups of the `master` database are needed for recovery procedures in case of a failure that affects the `master` database. See the *System Administration Guide* for step-by-step instructions for backing up and restoring the `master` database.

If you are using removable media for backups, the entire `master` database must fit on a single volume, unless you have another SAP ASE server that can respond to volume change messages.

## 1.80.7 Dump Files

Dumping a database with the `init` option overwrites any existing files on the tape or disk.

If you perform two or more dumps to a tape device and use the same file name for both dumps (specified with the `FILENAME` parameter), the SAP ASE server appends the second dump to the archive device. You cannot restore the second dump, because the SAP ASE server locates the first instance of the dump image with the specified file name and restores this image instead. The SAP ASE server does not search for subsequent dump images with the same file name.

Backup Server sends the dump file name to the location specified by the `with notify` clause. Before storing a backup tape, the operator should label it with the database name, file name, date, and other pertinent information. When loading a tape without an identifying label, use the `with headeronly` and `with listonly` options to determine the contents.

## 1.80.8 Volume Names

Dump volumes are labeled according to the ANSI tape-labeling standard. The label includes the logical volume number and the position of the device within the stripe set.

During loads, Backup Server uses the tape label to verify that volumes are mounted in the correct order. This allows you to load from a smaller number of devices than you used at dump time.

### **i** Note

When dumping and loading across the network, you must specify the same number of stripe devices for each operation.

## 1.80.9 Changing Dump Volumes

(UNIX systems) Backup Server requests a volume change when the tape capacity has been reached. After mounting another volume, the operator notifies Backup Server by executing `sp_volchanged` on any SAP ASE server that can communicate with Backup Server.

If Backup Server detects a problem with the currently mounted volume, it requests a volume change by sending messages to either the client or its operator console. The operator can use the `sp_volchanged` system procedure to respond to these messages.

## 1.80.10 Appending to or Overwriting a Volume


By default (`noinit`), Backup Server writes successive dumps to the same tape volume, making efficient use of high-capacity tape media. Data is added following the last end-of-tape mark. New dumps can be appended only to the last volume of a multivolume dump.

Before writing to the tape, Backup Server verifies that the first file has not yet expired. If the tape contains non-SAP data, Backup Server rejects it to avoid destroying potentially valuable information.

Use the `init` option to reinitialize a volume. If you specify `init`, Backup Server overwrites any existing contents, even if the tape contains non-SAP data, the first file has not yet expired, or the tape has ANSI access restrictions.

This figure illustrates how to dump three databases to a single volume using :

- `init` to initialize the tape for the first dump
- `noinit` (the default) to append subsequent dumps
- `unload` to rewind and unload the tape after the last dump



## 1.80.11 File Names and Archive Names

The name of a dump file identifies the database that was dumped and when the dump was made. However, in the syntax, `<file_name>` has different meanings depending on whether you are dumping to disk or to a UNIX tape.

```
file = <file_name>
```

In a dump to disk, the path name of a disk file is also its file name.

In a dump to a UNIX tape, the path name is not the file name. The ANSI Standard Format for File Interchange contains a file name field in the HDR1 label. For tapes conforming to the ANSI specification, this field in the label identifies the file name. The ANSI specification applies these labels only to tape; it does not apply to disk files.

This creates two problems:

- UNIX does not follow the ANSI convention for tape file names. UNIX considers the tape's data to be unlabeled. Although the data can be divided into files, those files have no name.
- In Backup Server, the ANSI tape labels are used to store information about the archive, negating the ANSI meanings. Therefore, disk files also have ANSI labels, because the archive name is stored there.

The meaning of `<filename>` changes, depending on the kind of dump you are performing. For example, in this syntax:

```
dump database <database_name> to '<filename>' with file='<filename>'
```

- The first `<filename>` refers to the path name you enter to display the file.
- The second `<filename>` is actually the archive name, the name stored in the HDR1 label in the archive, which the user can specify with the `file=<filename>` parameter of the `dump` or `load` command.

When the archive name is specified, the server uses that name during a database load to locate the selected archive.

If the archive name is not specified, the server loads the first archive it encounters.

In both cases, `file='<archivename>'` establishes the name that is stored in the HDR1 label, and which the subsequent `load` uses to validate that it is looking at the correct data.

If the archive name is not specified, a `dump` creates one; a `load` uses the first name it encounters.

The meaning of `<filename>` in the `to '<filename>'` clause changes, according to whether you are performing a disk or tape dump:


- If the dump is to tape, `'<filename>'` is the name of the tape device.
- If the dump is to disk, it is the name of a disk file.

If this is a disk dump and `'<filename>'` is not a complete path, the server's current working directory is prepended to the file name.

If you are dumping to tape and you do not specify a file name, Backup Server creates a default file name by concatenating:

- Last seven characters of the database name
- Two-digit year number
- Three-digit day of the year (1 – 366)
- Hexadecimal-encoded time at which the dump file was created

For example, the file `catations980590E100` contains a copy of the `publications` database made on the 59th day of 1998:



## 1.80.12 `dump database` Performance

Due to the design of indexes within a `dataserver` that provides an optimum search path, index rows are ordered for fast access to the table's data row. Index rows that contain row identifiers (RIDs), are treated as binary to achieve fast access to the user table.

Within the same architecture platform, the order of index rows remains valid, and search order for a selection criteria takes its normal path. However, when index rows are translated across different architectures, the order by which optimization was performed is invalidated, leading to an invalid index on user tables in a cross-platform dump and load.

When a database dump from a different architecture, such as big endian to little endian, is loaded, certain indexes are marked as suspect:

- Nonclustered index on APL tables.
- Clustered index on DOL tables.
- Nonclustered index on DOL tables.

To fix indexes on the target system, after loading from a different architecture dump, either:

- Drop and re-create all of the indexes, or,
- Use `sp_post_xpload`. See *System Procedures* in *Reference Manual: Procedures*.

Re-creating indexes on large tables can be a lengthy process. `sp_post_xpload` validates indexes, drops invalid indexes, and re-creates dropped indexes, in a single command.

Using `sp_post_xpload` may take longer than dropping and re-creating indexes individually. You should use the drop and re-create indexes on those databases larger than 10GB.

## 1.80.13 Compressed Dumps for an Archive Database

To use a compressed dump for an archive database:

- Create the compressed dump using the `with compression = <<compression level>>` option of the `dump database` or `dump tran` command.
- Create a memory pool for accessing the archive database.



### i Note

Dumps generated with “`compress: :`” cannot be loaded into an archive database. Therefore, any references to compression in this chapter refer to dumps generated using the `with compression = <compression level>` option.

There are no compatibility issues with dumps using this compression option on traditional databases.

## 1.80.14 Compatibility Issues for a Compressed Dump

Backup Server versions 15.0 ESD #2 and later generate a different format of compressed dump than earlier versions.

Therefore:

- You can load compressed dump made using a Backup Server version 15.0 ESD #2 and later only into a pre-15.0 ESD #2 installation using a Backup Server version 15.0 ESD #2 or later.
- If you are using a pre-15.0 ESD #2 installation and want to use your dumps for an archive database, use Backup Server version 15.0 ESD #2 or later to create compressed database dumps.

### i Note

You can use a 15.0 ESD #2 Backup Server for both dump and loads.

## 1.80.15 Encrypted Columns and dump database

The `dump` and `load` work on the ciphertext of encrypted columns, ensuring that the data for encrypted columns remains encrypted while on disk.

These commands also pertain to the entire database; default keys and keys that are created in the same database are dumped and loaded along with the data to which they pertain.

### i Note

The file size of a dump of an encrypted database is larger than that of a regular, unencrypted database.

If your keys are in a separate database than the columns they encrypt:

- When you dump the database containing encrypted columns, also dump the database where the key was created. This is necessary if new keys have been added since the last dump.
- When you dump the database containing an encryption key, dump all databases containing columns encrypted with that key. This keeps the encrypted data in sync with the available keys.
- After loading the database containing the encryption keys and the database containing the encrypted columns, bring both databases online at the same time.

Because of metadata dependencies of encrypted columns on the key's database, follow the steps below if you intend to load the key database into a database with a different name (if your data is stored in the same database as your keys, you need not follow these steps):

1. Before dumping the database containing the encrypted columns, use `alter table` to decrypt the data.
2. Dump the databases containing keys and encrypted columns.
3. After loading the databases, use `alter table` to reencrypt the data with the keys in the newly named database.

The consistency issues between encryption keys and encrypted columns are similar to those for cross-database referential integrity. See *System Administration Guide > Cross-Database Constraints and Loading Databases*.

## 1.81 dump transaction

Makes a copy of a transaction log, and removes the inactive portion of the log, if the `dump transaction` command is not running concurrently with another `dump database`.

See the Tivoli Storage Manager (TSM) syntax for `dump transaction` syntax when Tivoli is licensed at your site.

### Syntax

To make a routine log dump:

```
dump tran[saction] <database_name>
  to [compress::[<compression_level>::]]<stripe_device>
    [at <backup_server_name>]
    [density = <density_value>,
    blocksize = <number_bytes>,
    capacity = <number_kilobytes>,
    dumpvolume = <volume_name>,
    file = <file_name>]
  [[stripe on [compress::[<compression_level>::]]<stripe_device>
    [at <backup_server_name>]
    [density = <density_value>,
    blocksize = <number_bytes>,
    capacity = <number_kilobytes>,
    dumpvolume = <volume_name>,
    file = <file_name>]]
  [[stripe on [compress::[<compression_level>::]]<stripe_device>
    [at <backup_server_name>]
    [density = <density_value>,
    blocksize = <number_bytes>,
    capacity = <number_kilobytes>,
    dumpvolume = <volume_name>,
    file = <file_name>]]...]
  [with {
    density = <density_value>,
    blocksize = <number_bytes>,
    capacity = <number_kilobytes>,
    compression = <compress_level>,
    dumpvolume = <volume_name>,
    file = <file_name>,
    [dismount | nodismount],
    [nounload | unload],
    retaindays = <number_days>,
    [noinit | init],
```

```

notify = {client | operator_console},
standby_access,
label = '<label_name>'
verify[ = header | full]]

```

To truncate the log without making a backup copy:

```

dump tran[saction] <database_name>
with truncate_only

```

To truncate a log that is filled to capacity. *Use only as a last resort, as you will lose the contents of your log:*

```

dump tran[saction] <database_name>
with no_log

```

To back up the log after a database device fails:

```

dump tran[saction] <database_name>
to [compress::[<compression_level>::]]<stripe_device>
[at <backup_server_name>]
[density = <density_value>,
blocksize = <number_bytes>,
capacity = <number_kilobytes>,
dumpvolume = <volume_name>,
file = <file_name>]
[stripe on [compress::[<compression_level>::]]<stripe_device>
[at <backup_server_name>]
[density = <density_value>,
blocksize = <number_bytes>,
capacity = <number_kilobytes>,
dumpvolume = <volume_name>,
file = <file_name>]]
[[stripe on [compress::[<compression_level>::]]<stripe_device>
[at <backup_server_name>]
[density = <density_value>,
blocksize = <number_bytes>,
capacity = <number_kilobytes>,
dumpvolume = <volume_name>,
file = <file_name>]]...]
[with {
density = <density_value>,
blocksize = <number_bytes>,
capacity = <number_kilobytes>,
compression = <compress_level>
dumpvolume = <volume_name>,
file = <file_name>,
[dismount | nodismount],
[nounload | unload],
retaindays = <number_days>,
[noinit | init],
no_truncate,
notify = {client | operator_console}}]

```

To copy the transaction log when the Tivoli Storage Manager provides backup services:

```

dump transaction <database_name>
to "syb_tsm::<object_name>"
[blocksize = <number_bytes>]
[stripe on "[syb_tsm::]<object_name>"
[blocksize = <number_bytes>]]...]
[with {
blocksize = <number_bytes>,
compression = <compress_level>,
passwd = <password>,
[noinit | init],

```

```
notify = {client | operator_console},
verify[ = header | full]
}}
```

To dump a transaction based on the settings specified in a configuration file:

```
dump transaction <database_name>
using config = <configuration_name>
[with {verify [= header | full]}]
```

## Parameters

### <database\_name>

is the name of the database from which you are copying data. The name can be given as a literal, a local variable, or a parameter to a stored procedure.

### <configuration\_name>

is a unique dump configuration name. The parameter values specified in the dump configuration are used to perform the dump operation.

Any other parameters are explicitly specified in the command override the values specified by the dump configuration.

You cannot specify a stripe directory as a parameter for the command if you use a dump configuration. The SAP ASE server creates the dump files in the stripe directory specified by the dump configuration. Dump file names use this convention:

Database\_Name.Dump\_Type.Date-Timestamp.StripeID

### compress::<compression\_level>

is a number between 0 and 9, 100, or 101. For single-digit compression levels, 0 indicates no compression, and 9 provides the highest level of compression. Compression levels of 100 and 101 provide a faster, more efficient compression mode, with 100 providing faster compression and 101 providing better compression. If you do not specify <compression\_level>, the SAP ASE server does not compress the dump.

For more information about the `compress` option, see *Backing Up and Restoring User Databases* in the *System Administration Guide*.

### i Note

The `compression = <compress_level>` option allows you to compress a dump file on both local and remote machines, and differs from the `compress::<compression_level>` option, which you can use only to compress a dump file on local machine. Beginning with SAP ASE version 15.0, SAP supports—and recommends—the native `compression = <compression_level>` syntax.

### truncate\_only

removes the inactive part of the log without making a backup copy. Use on databases without log segments on a separate device from data segments. Do not specify a dump device or Backup Server name.

**no\_log**

removes the inactive part of the log without making a backup copy and without recording the procedure in the transaction log. Use `no_log` only when you are completely out of log space and cannot run the usual `dump transaction` command. Use `no_log` as a last resort and use it only once after `dump transaction with truncate_only` fails.

**to <stripe\_device>**

is the device to which data is being dumped.

**at <backup\_server\_name>**

is the name of the Backup Server. Do not specify this parameter if you are dumping to the default Backup Server. Specify this parameter only if you are dumping over the network to a remote Backup Server. You can specify as many as 32 different remote Backup Servers using this option. When dumping across the network, specify the `<network_name>` of a remote Backup Server running on the machine to which the dump device is attached. For platforms that use interfaces files, `<backup_server_name>` must appear in the interfaces file.

**density = <density\_value>**

overrides the default density for a tape device. Valid densities are 800, 1600, 6250, 6666, 10000, and 38000. Not all values are valid for every tape drive; use the correct density for your tape drive.

**blocksize = <number\_bytes>**

overrides the default block size for a dump device. The block size must be at least one database page (2048 bytes for most systems) and must be an exact multiple of the database page size.

**i Note**

Whenever possible, use the default block size; it is the best block size for your system.

**capacity = <number\_kilobytes>**

is the maximum amount of data that the device can write to a single tape volume. The capacity must be at least five database pages, and should be slightly less than the recommended capacity for your device.

A general rule for calculating capacity is to use 70 percent of the manufacturer's maximum capacity for the device, leaving 30 percent for overhead, such as record gaps and tape marks. This rule works in most cases, but may not work in all cases because of differences in overhead across vendors and devices.

On UNIX platforms that cannot reliably detect the end-of-tape marker, you must indicate how many kilobytes can be dumped to the tape. You must supply a `capacity` for dump devices specified as a physical path name. If a dump device is specified as a logical device name, the Backup Server uses the `<size>` parameter stored in the `sysdevices` system table, unless you specify a capacity.

**compression = <compress\_level>**

is a number between 0 and 9, 100, or 101. For single-digit compression levels, 0 indicates no compression, and 9 provides the highest level of compression. Compression levels of 100 and 101 provide a faster, more efficient compression mode, with 100 providing faster compression and 101 providing better compression. If you do not specify <compression\_level>, the SAP ASE server does not compress the dump.

#### **i Note**

You should use the native "compression = <compress\_level>" option over the older "compress::<compression\_level>" option. The native option allows compression of both local and remote dumps, and the dumps that it creates then describe their own compression level during a load. The older option is retained for compatibility with older applications.

**verify={crc | read\_after\_write}**

adds a cyclic redundancy check for accidental changes to raw data for database dumps created with compression to check and for verification that the compression blocks can be correctly read and decompressed. Options are:

- **verify=crc** – indicates that you are performing a cyclic redundancy check.
- **verify=read\_after\_write** – Backup Server rereads every compressed block after writing and decompressing it. If Backup Server finds an error, it prints the offset in the file it finds the error. You cannot use **verify=read\_after\_write** with **load database** commands.

**dumpvolume = <volume\_name>**

establishes the name that is assigned to the volume. The maximum length of <volume\_name> is 6 characters. The Backup Server writes the <volume\_name> in the ANSI tape label when overwriting an existing dump, dumping to a brand new tape, or dumping to a tape for which the contents are not recognizable. The **load transaction** command checks the label and generates an error message if the wrong volume is loaded.

**stripe on <stripe\_device>**

is an additional dump device. You can use up to 32 devices, including the device named in the **to <stripe\_device>** clause. The Backup Server splits the log into approximately equal portions and sends each portion to a different device. Dumps are made concurrently on all devices, reducing the time and the number of volume changes required.

**dismount | nodismount**

(on platforms that support logical dismount) determines whether tapes remain mounted. By default, all tapes used for a dump are dismounted when the dump completes. Use **nodismount** to keep tapes available for additional dumps or loads.

**nounload | unload**

determines whether tapes rewind after the dump completes. By default, tapes do not rewind, allowing you to make additional dumps to the same tape volume. Specify **unload** for the last dump file to be added to a multidump volume. This rewinds and unloads the tape when the dump completes.

**retaindays = <number\_days>**

(on UNIX platforms) specifies the number of days that Backup Server protects you from overwriting a dump. If you try to overwrite a dump before it expires, Backup Server requests confirmation before overwriting the unexpired volume.

#### **i Note**

This option is meaningful for disk, 1/4-inch cartridge, and single-file media. On multifile media, this option is meaningful for all volumes except the first.

The <number\_days> must be a positive integer or 0, for dumps you can overwrite immediately. If you do not specify a `retaindays` value, Backup Server uses the server-wide `tape retention in days` value, set by `sp_configure`.

**noinit | init**

determines whether to append the dump to existing dump files or reinitialize (overwrite) the tape volume. By default, the SAP ASE server appends dumps following the last end-of-tape mark, allowing you to dump additional databases to the same volume. You can append new dumps only to the last volume of a multivolume dump. Use `init` for the first database you dump to a tape, to overwrite its contents.

Use `init` when you want Backup Server to store or update tape device characteristics in the tape configuration file. See the *System Administration Guide*.

**file = <file\_name>**

is the name of the dump file. The name cannot exceed 17 characters and must conform to operating system conventions for file names. If you do not specify a file name, Backup Server creates a default file name.

**no\_truncate**

dumps a transaction log, even if the disk containing the data segments for a database is inaccessible, using a pointer to the transaction log in the `master` database. The `with no_truncate` option provides up-to-the-minute log recovery when the transaction log resides on an undamaged device, and the `master` database and user databases reside on different physical devices.

If you use `dump tran` with `no_truncate`, you must follow it with `dump database`, not with another `dump tran`. If you load a dump generated using the `no_truncate` option, the SAP ASE server prevents you from loading any subsequent dump.

**notify = {client | operator\_console}**

overrides the default message destination.

- On operating systems that offer an operator terminal feature, volume change messages are always sent to the operator terminal on the machine on which the Backup Server is running. Use `client` to route other Backup Server messages to the terminal session that initiated the `dump database`.
- On operating systems (such as UNIX) that do not offer an operator terminal feature, messages are sent to the client that initiated the `dump database`. Use `operator_console` to route messages to the terminal on which the Backup Server is running.

**with standby\_access**

specifies that only completed transactions are to be dumped. The dump continues to the furthest point it can find at which a transaction has just completed and there are no other active transactions.

`label = '<label_name>'`

is the label to identify a specific dump. The maximum length of `<label_name>` is 30 bytes.

The RegAgent thread sends the specified label to Replication Server in both Log Transfer Language (LTL) replication and stream replication. The dump label coordinates `dump` and `load` commands between the primary and replicate databases while rematerializing the replicate database. The dump labels are recorded in the database dump history file.

`verify [= header | full]`

allows the Backup Server to perform a minimal header or structural row check on the data pages as they are being copied to the archives. There are no structural checks done at this time to gam, oam, allocation pages, indexes, text, or log pages. The only other check is done on pages where the page number matches to the page header. Any faults found are reported in the backupserver error log.

`syb_tsm`

is the keyword that invokes the `libsyb_tsm.so` module that enables communication between Backup Server and TSM.

`<object_name>`

is the name of the backup object on TSM server.

`<configuration_name>`

is a unique dump configuration name. The parameter values specified in the dump configuration are used to perform the dump operation.

If other parameters are explicitly specified in the command, they override the parameter values specified by the dump configuration.

You cannot specify a stripe directory as a parameter for the command if you use a dump configuration. The SAP ASE server creates the dump files in the stripe directory specified by the dump configuration. The dump files are named using this convention:

Database Name.Dump Type.Date-Timestamp.StripeID

## Examples

### Example 1

Dumps the transaction log to a tape, appending it to the files on the tape, since the `init` option is not specified:

```
dump transaction pubs2
to "/dev/nrmt0"
```

### Example 2

Dumps the transaction log for the `mydb` database, using the Backup Server `REMOTE_BKP_SERVER`. The Backup Server dumps approximately half the log to each of the two devices. The `init` option overwrites



any existing files on the tape. The `retaindays` option specifies that the tapes cannot be overwritten for 14 days:

```
dump transaction mydb
  to "/dev/nrmt4" at REMOTE_BKP_SERVER
  stripe on "/dev/nrmt5" at REMOTE_BKP_SERVER
  with init, retaindays = 14
```

### Example 3

Dumps completed transactions from the `inventory_db` transaction log file to device `dev1` and labels the dump as `RESYNC001`:

```
dump tran inventory_db to dev1 with standby_access
with label = 'RESYNC001'
```

### Example 4

Dumps the transaction log for the `pubs2` database to the TSM backup object "demo2.2" with 100-level compression.

```
dump transaction pubs2 to "syb_tsm::demo2.2"
  with compression = 100
```

### Example 5

Dumps the database using the "dmp\_cfg2" configuration. The archive files created during the dump are password-protected:

```
dump transaction testdb using config = 'dmp_cfg2'
  with passwd = 'my_pass01'
go
```

### Example 6

Dumps the database using the "dmp\_cfg2" configuration using compression level 6 and (that is, overriding the compression level specified in "dmp\_cfg2"):

```
dump transaction testdb using config = 'dmp_cfg2'
  with compression = 6
go
```

## Usage

If you use `sp_hidetext` followed by a cross-platform `dump` and `load`, you must manually drop and re-create all hidden objects.

The `dump transaction` command takes into account when a device is mirrored and will store the path to mirror devices along with regular devices in the dump header. The `sybdumpttran` utility first attempts to open the primary device, and in the event the primary device cannot be opened, the mirrored device is opened, if one exists.

The commands and system procedures used to back up databases and logs are:

<b>dump database</b>	Make routine dumps of the entire database, including the transaction log.
----------------------	---

<code>dump transaction</code>	Make routine dumps of the transaction log, then truncate the inactive portion. The inactive portion of the log is not truncated if <code>dump transaction</code> is running concurrently with <code>dump database</code> .
<code>dump transaction with no_truncate</code>	Dump the transaction log after failure of a database device.
<code>dump transaction with truncate_only, dump database</code>	Truncate the log without making a backup. Then copy the entire database.
<code>dump transaction with no_log, dump database</code>	Truncate the log after your usual method fails due to insufficient log space. Then copy the entire database.
<code>sp_volchanged</code>	Respond to the Backup Server volume change messages.

See also:

- *Backing Up and Restoring User Databases* in the *System Administration Guide*.
- `sp_addumpdevice`, `sp_dboption`, `sp_dropdevice`, `sp_helpdevice`, `sp_hidetext`, `sp_logdevice`, `sp_volchanged` in *Reference Manual: Procedures*
- User documentation for Tivoli Storage Manager for more information about creating back-ups when TSM is supported at your site.

## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

## Permissions

The permission checks for `dump transaction` differ based on your granular permissions settings.

Setting	Description
<b>Enabled</b>	With granular permissions enabled, you must be the database owner, or a user with <code>dump database</code> privilege or <code>own database</code> privilege on the database.
<b>Disabled</b>	With granular permissions disabled, you must be the database owner or a user with <code>sa_role</code> , <code>replication_role</code> , or <code>oper_role</code> .

## Auditing

You can enable `drop` auditing option to audit this command. Values in `event` and `extrainfo` columns from the `sysaudits` table are:

Information	Value
Audit option	dump
Event	35
Command or access audited	dump transaction
Information in <code>extrainfo</code>	<ul style="list-style-type: none"> <li>• <b>Roles</b> – current active roles</li> <li>• <b>Full command text</b> – full text of <code>dump transaction</code> command</li> <li>• <b>Previous value</b> – NULL</li> <li>• <b>Current value</b> – NULL</li> <li>• <b>Other information</b> – NULL</li> <li>• <b>Proxy information</b> – original login name, if <code>set proxy</code> is in effect</li> </ul>

Full command text is included in `extrainfo`. For example:

```
sa_role sso_role oper_role sybase_ts_role mon_role;
dump tran tdb2 to "/tmp/tdb2.log"; ; ; ; ; ; sa/ase;
```

For more information about auditing, see *Security Administration Guide > Auditing*.

## Related Information

[dump database \[page 470\]](#)

[load database \[page 585\]](#)

[load transaction \[page 603\]](#)

[online database \[page 625\]](#)

### 1.81.1 dump transaction Restrictions

Restrictions for using `dump transaction`.

- The maximum file path/name size for a physical device is 127 characters.
- You cannot dump to the null device (on UNIX, `/dev/null`).
- Named pipes are supported as a backup device. However, Backup Server does not attempt to create a named pipe. Instead, you must create the named pipe externally before executing the `dump transaction` command (you need not do this for regular file).
- You cannot use the `dump transaction` command in a transaction.
- When using 1/4-inch cartridge tape, you can dump only one database or transaction log per tape.
- You cannot run `dump transaction <database_name>` to before fully dumping a newly created database.
- You cannot use `dump transaction <database_name>` to once an unlogged operation has been performed in the database.

- You cannot issue `dump transaction log` while the `trunc log on chkpt` database option is enabled or after enabling `select into/bulk copy/pll sort` and making minimally logged changes to the database with `select into`, fast bulk copy operations, default unlogged `writetext` operations, or a parallel sort. Use `dump database` instead.

### ⚠ Caution

Do not modify the log table `syslogs` with a `delete`, `update`, or `insert` command.

- If a database does not have a log segment on a separate device from data segments, you cannot use `dump transaction` to copy the log and truncate it.
- If a user or threshold procedure issues a `dump transaction` command on a database where a `dump database` or another `dump transaction` is in progress, the second command sleeps until the first completes.
- To restore a database, use `load database` to load the most recent database dump; then use `load transaction` to load each subsequent transaction log dump in the order in which it was made.
- Each time you add or remove a cross-database constraint, or drop a table that contains a cross-database constraint, dump both of the affected databases.

### ⚠ Caution

Loading earlier dumps of these databases can cause database corruption.

- You cannot mix SAP dumps and non-SAP data (for example, UNIX archives) on the same tape.
- You cannot dump a transaction with `no_log` or with `truncate_only` if the database has offline pages.

Restrictions differ when using the `with no_truncate` option. Under normal circumstances, the SAP ASE server returns an error message when:

- Running `dump transaction <database_name> to` before fully dumping a newly created databases:

```
This database has not been dumped since it was
created or upgraded or a transaction dump may have
been loaded using the UNTIL_TIME clause. You must
perform a DUMP DATABASE before you can dump its
transaction log.
```

- Using `dump transaction <database_name> to` once you have performed a minimally logged operation in the database:

```
Dump transaction is not allowed because a
non-logged operation was performed on the database.
Dump your database or use dump transaction with
truncate_only until you can dump your database.
```

See *Fully Recoverable DDL and dump transaction* for more information.

- Using `dump transaction <database_name> to` after you have performed `dump transaction with truncate_only`:

```
DUMP TRANsaction to a dump device is not allowed
where a truncate-only transaction dump has been
performed after the last DUMP DATABASE. Use DUMP
DATABASE instead.
```

When you use the `with no_truncate` option in your `dump transaction <database_name> to <dump_file>` command, however, the SAP ASE server does not perform a check of the database and thus

does not return any of these error messages. The SAP ASE server assumes that your database has some lost data (for example, from a failed disk) and is therefore inaccessible.

You do, however, get an error message when you then try to load your transaction. Your `load transaction` process may fail, with this error message:

```
Specified file 'dump device' is out of sequence. Current
timestamp is <X> while dump was from <Y>.
```

## 1.81.2 Copying the Log After Device Failure

After device failure, use `dump transaction` with `no_truncate` to copy the log without truncating it. You can use this option only if your log is on a separate segment and your `master` database is accessible.

The backup created by `dump transaction` with `no_truncate` is the most recent dump for your log. When restoring the database, load this dump last.

## 1.81.3 Dumping Databases Without Separate Log Segments

When a database does not have a log segment on a separate device from data segments, use `dump transaction` with `truncate_only` to remove committed transactions from the log without making a backup copy.

### ⚠ Caution

`dump transaction` with `truncate_only` provides no means to recover your databases. Run `dump database` at the earliest opportunity to ensure recoverability.

Use `with truncate_only` on the `master`, `model`, and `sybsystemprocs` databases, which do not have log segments on a separate device from data segments.

You can also use `with truncate_only` on very small databases that store the transaction log and data on the same device.

Mission-critical user databases should have log segments on a separate device from data segments. Use the `log on` clause of `create database` to create a database with a separate log segment, or `alter database` and `sp_logdevice` to transfer the log to a separate device.

## 1.81.4 Dumping Only Complete Transactions

When you use `with standby_access` to dump the transaction log, the dump proceeds to the furthest point in the log at which all earlier transactions have completed and there are no records belonging to open transactions.

Use the `with standby_access` option to dump transaction logs for loading into a server that acts as a warm standby server for the database.

You must use `dump tran[saction]...with standby_access` in all situations where you load two or more transaction logs in sequence and you want the database to be online between loads.

After loading a dump made with the `with standby_access` option, use the `online database` command with the `for standby_access` option to make the database accessible.

#### ⚠ Caution

If a transaction log contains open transactions and you dump it without the `with standby_access` option, the SAP ASE server does not allow you to load the log, bring the database online, then load a subsequent transaction dump. If you are going to load a series of transaction dumps, you can bring the database online only after a load that was originally dumped with `standby_access` or after loading the entire series.

## 1.81.5 Dumping Without the Log

`dump transaction...with no_log` truncates the log without logging the dump transaction event. Because it copies no data, it requires only the name of the database.

#### ⚠ Caution

Use `dump transaction with no_log` only as a last resort, after your usual method of dumping the transaction log (`dump transaction` or `dump transaction with truncate_only`) fails because of insufficient log space. `dump transaction with no_log` provides no means to recover your databases. Run `dump database` at the earliest opportunity to ensure recoverability.

Every use of `dump transaction...with no_log` is considered an error and is recorded in the SAP ASE error log.

If you have created your databases with log segments on a separate device from data segments, written a last-chance threshold procedure that dumps your transaction log often enough, and allocated enough space to your log and database, you should not have to use `with no_log`. If you must use `with no_log`, increase the frequency of your dumps and the amount of log space.

## 1.81.6 Scheduling Dumps

Transaction log dumps are dynamic—they can take place while the database is active. They may slow the system slightly, so run dumps when the database is not being heavily updated.

Develop a regular schedule for backing up user databases and their transaction logs.

`dump transaction` uses less storage space and takes less time than `dump database`. Typically, transaction log dumps are made more frequently than database dumps.

## 1.81.7 Using Thresholds to Automate `dump transaction`

Use thresholds to automate backup procedures. To take advantage of the SAP ASE last-chance threshold, create user databases with log segments on a separate device from data segments.

When space on the log segment falls below the last-chance threshold, the SAP ASE server executes the last-chance threshold procedure. Including a `dump transaction` command in your last-chance threshold procedure helps protect you from running out of log space. See `sp_thresholdaction`.

You can use `sp_addthreshold` to add a second threshold to monitor log space. For more information about thresholds, see the *System Administration Guide*.

## 1.81.8 Specifying Dump Devices

You can specify the dump device as a literal, a local variable, or a parameter to a stored procedure.

You can specify a local dump device as:

- A logical device name from the `sysdevices` system table
- An absolute path name
- A relative path name

The Backup Server resolves relative path names using the current working directory in the SAP ASE server.

Dumping to multiple stripes is supported for tape and disk devices. Placing multiple dumps on a device is supported only for tape devices.

When dumping across the network, specify the absolute path name of the dump device. The path name must be valid on the machine on which the Backup Server is running. If the name includes any characters except letters, numbers, or underscores (`_`), enclose it in quotes.

Ownership and permissions problems on the dump device may interfere with use of `dump` commands. `sp_adddumpdevice` adds the device to the system tables, but does not guarantee that you can dump to that device or create a file as a dump device.

You can run more than one dump (or load) at the same time, as long as they use different dump devices.

## 1.81.9 Determining Tape Device Characteristics

If you issue a `dump transaction` command without the `init` qualifier, and Backup Server cannot determine the device type, the `dump transaction` command fails.

See the *System Administration Guide*.

## 1.81.10 Backup Servers

You must have a Backup Server running on the same machine as your SAP ASE server. The Backup Server must be listed in the `master..sys.servers` table. This entry is automatically created during installation or upgrade and should not be deleted.

If your backup devices are located on another machine so that you dump across a network, you must also have a Backup Server installed on the remote machine.


## 1.81.11 Dump Files

Dumping a log with the `init` option overwrites any existing files on the tape or disk.

Dump file names identify which database was dumped and when the dump was made. If you do not specify a file name, Backup Server creates a default file name by concatenating the following:

- Last seven characters of the database name
- Two-digit year number
- Three-digit day of the year (1- 366)
- Hexadecimal-encoded time at which the dump file was created

For example, the file `cations930590E100` contains a copy of the `publications` database made on the 59th day of 1993:



The Backup Server sends the dump file name to the location specified by the `with notify` clause. Before storing a backup tape, the operator should label it with the database name, file name, date, and other pertinent information. When loading a tape without an identifying label, use the `with headeronly` and `with listonly` options to determine the contents.

## 1.81.12 Volume Names

Dump volumes are labeled according to the ANSI tape-labeling standard. The label includes the logical volume number and the position of the device within the stripe set.

During loads, Backup Server uses the tape label to verify that volumes are mounted in the correct order. This allows you to load from a smaller number of devices than you used at dump time.

### **i** Note

When dumping and loading across the network, you must specify the same number of stripe devices for each operation.



## 1.81.13 Changing Dump Volumes

(On UNIX systems) The Backup Server requests a volume change when the tape capacity has been reached. After mounting another volume, the operator notifies the Backup Server by executing the `sp_volchanged` system procedure on any SAP ASE server that can communicate with the Backup Server.

If the Backup Server detects a problem with the currently mounted volume (for example, if the wrong volume is mounted), it requests a volume change by sending messages to either the client or its operator console. The operator responds to these messages with the `sp_volchanged` system procedure.

## 1.81.14 Appending To or Overwriting a Volume


By default (`noinit`), Backup Server writes successive dumps to the same tape volume, making efficient use of high-capacity tape media. Data is added following the last end-of-tape mark. New dumps can be appended only to the last volume of a multivolume dump.

Before writing to the tape, Backup Server verifies that the first file has not yet expired. If the tape contains non-SAP data, Backup Server rejects it to avoid destroying potentially valuable information.

Use the `init` option to reinitialize a volume. If you specify `init`, Backup Server overwrites any existing contents, even if the tape contains non-SAP data, the first file has not yet expired, or the tape has ANSI access restrictions.

This figure illustrates how to dump three transaction logs to a single volume. Use:

- `init` to initialize the tape for the first dump
- `noinit` (the default) to append subsequent dumps
- `unload` to rewind and unload the tape after the last dump



## 1.81.15 Dumping Logs Stored on Mirrored Devices

At the beginning of a `dump transaction`, the SAP ASE server passes the primary device name of each logical log device to the Backup Server. If the primary device has been unmirrored, the SAP ASE server passes the name of the secondary device instead. If the named device fails before Backup Server completes its data transfer, the SAP ASE server aborts the dump.

If you attempt to unmirror a named log device while a `dump transaction` is in progress, the SAP ASE server displays a message. The user executing the `disk unmirror` command can abort the dump or defer the `disk unmirror` until after the dump completes.

`dump transaction with truncate_only` and `dump transaction with no_log` do not use the Backup Server. These commands are not affected when a log device is unmirrored, either by a device failure or by a `disk unmirror` command.

`dump transaction` copies only the log segment. It is not affected when a data-only device is unmirrored, either by a device failure or by a `disk unmirror` command.

## 1.81.16 Fully Recoverable DDL and `dump transaction`

In versions of SAP ASE earlier than 15.7, some operations are minimally logged. Since `dump transaction` is not allowed after a minimally logged operation, this restriction has an effect on recoverability and scalability.

- Recoverability and operational scalability for very large database (VLDB) installations, where `dump database` may be very time consuming.
- Up-to-the-minute recoverability of the database. Even though minimally logged operations are fully recoverable from a server failure, changes after the last successful transaction dump may be lost when data devices are broken, or if the database is corrupted. You cannot, after a minimally logged operation, use `dump tran with no_truncate` to dump the log, then recover the database using the dumped transaction log.
- You cannot restore the database to a particular time using `dump transaction`, and then `load tran with until_time`.

Beginning with SAP ASE 15.7, you can use `dump transaction` to fully recover the following operations that in earlier versions of SAP ASE were minimally logged:

- `select into` including `select into` a proxy table
- `alter table` commands that require data movement
- `reorg rebuild`

Use `sp_dboption` in the `master` database to fully log commands that are, by default, minimally logged.

## 1.82 execute

Runs a procedure or dynamically executes Transact-SQL commands.

### Syntax

```
[exec[ute]] [@<return_status> =]
  [[[<server><database>.] .]<owner>.]<procedure_name>[;<number>]
  [[@<parameter_name> =] <value> |
```

```
    [@<parameter_name> =] @<variable> [output]
  [, [@<parameter_name> =] <value> |
    [@<parameter_name> =] @<variable> [output]...]]
[with recompile]
```

or

```
exec[ute] ("<string>" | <char_variable>
  [+ "<string>" | <char_variable>
```

## Parameters

### execute | exec

is used to execute a stored procedure or an extended stored procedure (ESP). This keyword is necessary if there are multiple statements in the batch.]...)

`execute` is also used to execute a string containing Transact-SQL.

#### <@return\_status>

is an optional integer variable that stores the return status of a stored procedure.

<@return\_status> must be declared in the batch or stored procedure before it is used in an `execute` statement.

#### <server>

is the name of a remote server. You can execute a procedure on another SAP ASE server as long as you have permission to use that server and to execute the procedure in that database. If you specify a server name, but do not specify a database name, the SAP ASE server looks for the procedure in your default database.

#### <database>

is the database name. Specify the database name if the procedure is in another database. The default value for <database> is the current database. You can execute a procedure in another database as long as you are its owner or have permission to execute it in that database.

#### <owner>

.is the procedure owner's name. Specify the owner's name if more than one procedure of that name exists in the database. The default value for <owner> is the current user. The owner name is optional only if the database owner owns the procedure or if you own it.

#### <procedure\_name>

is the name of a procedure defined with `create procedure`.

#### <number>

]is an optional integer used to group procedures of the same name so that they can be dropped together with a single `drop procedure` statement. Procedures used in the same application are often grouped this way. For example, if the procedures used with an application named `orders` are named <orderproc;1>, <orderproc;2>, and so on, the following statement drops the entire group:

```
drop proc orderproc
```

After procedures have been grouped, individual procedures within the group cannot be dropped. For example, you cannot execute the statement:

```
drop procedure orderproc;2
```

#### <parameter\_name>

is the name of an argument to the procedure, as defined in `create procedure`. Parameter names must be preceded by the `@` sign.

If the "`@<parameter_name> = <value>`" form is used, parameter names and constants need not be supplied in the order defined in `create procedure`. However, if this form is used for any parameter, it must be used for all subsequent parameters.

#### <value>

is the value of the parameter or argument to the procedure. If you do not use the "`@<parameter_name> = <value>`" form, you must supply parameter values in the order defined in `create procedure`.

#### @<variable>

is the name of a variable used to store a return parameter.

#### output

indicates that the stored procedure is to return a return parameter. The matching parameter in the stored procedure must also have been created with the keyword `output`.

The `output` keyword can be abbreviated to `out`.

#### with recompile

forces compilation of a new plan. Use this option if the parameter you are supplying is atypical or if the data has significantly changed. The changed plan is used on subsequent executions. The SAP ASE server ignores this option when executing an extended system procedure.

#### **i** Note

Using `execute procedure with recompile` many times can adversely affect procedure cache performance. Since a new plan is generated every time you use `with recompile`, a useful performance plan may be pushed out of the cache if there is insufficient space for new plans.

#### <string>

is a literal string containing part of a Transact-SQL command to execute. There are no restrictions to the number of characters supplied with the literal string.

#### <char\_variable>

is the name of a variable that supplies the text of a Transact-SQL command.

## Examples

### Example 1

All three statements execute `showind` with a parameter value `titles`:

```
execute showind titles
```

```
exec showind @tablename = titles
```

If this is the only statement in a batch or file:

```
showind titles
```

### Example 2

Executes `checkcontract` on the remote server `GATEWAY`. Stores the return status indicating success or failure in `@<retstat>`:

```
declare @retstat int
execute @retstat = GATEWAY.pubs.dbo.checkcontract "409-56-4008"
```

### Example 3

Executes `roy_check`, passing three parameters. The third parameter, `@<pc>`, is an output parameter. After execution of the procedure, the return value is available in the variable `@<percent>`:

```
declare @percent int
select @percent = 10
execute roy_check "BU1032", 1050, @pc = @percent output
select Percent = @percent
```

### Example 4

Displays information about the system tables if you do not supply a parameter:

```
create procedure
showsysind @table varchar (30) = "sys%"
as
select sysobjects.name, sysindexes.name, indid
from sysindexes, sysobjects
where sysobjects.name like @table
and sysobjects.id = sysindexes.id
```

### Example 5

Executes `xp_echo`, passing in a value of "Hello World!" The returned value of the extended stored procedure is stored in a variable named `<result>`:

```
declare @input varchar (12), @in varchar (12),
        @out varchar (255), @result varchar (255)
select @input="Hello World!"
execute xp_echo @in = @input, @out= @result output
```

### Example 6

The final `execute` command concatenates string values and character variables to issue the Transact-SQL command:

```
select name from sysobjects where id=3
```

```

declare @tablename char (20)
declare @columnname char (20)
select @tablename="sysobjects"
select @columnname="name"
execute ('select ' + @columnname + ' from ' + @tablename + ' where id=3')

```

### Example 7

Executes `sp_who`:

```

declare @sproc varchar (255)
select @sproc = "sp_who"
execute @sproc

```

## Usage

- You can use `execute` with an archive database as long as any statements that reference the archive database are allowed within the archive database. A transaction inside or outside a stored procedure is not permitted with an `execute` command.
- Procedure results may vary, depending on the database in which they are executed. For example, the user-defined system procedure `sp_foo`, which executes the `db_name()` system function, returns the name of the database from which it is executed. When executed from the `pubs2` database, it returns the value "pubs2":

```

exec pubs2..sp_foo
-----
pubs2
(1 row affected, return status = 0)

```

When executed from `sybssystemprocs`, it returns the value "sybssystemprocs":

```

exec sybssystemprocs..sp_foo
-----
sybssystemprocs
(1 row affected, return status = 0)

```

- There are two ways to supply parameters—by position, or by using:

```
<@parameter_name>< = ><value>
```

If you use the second form, you need not supply the parameters in the order defined in `create procedure`.

If you are using the `output` keyword and intend to use the return parameters in additional statements in your batch or procedure, the value of the parameter must be passed as a variable. For example:

```
<parameter_name = @variable_name>
```

When executing an extended stored procedure, pass all parameters by either name or value. You cannot mix parameters by value and parameters by name in a single invocation of the `execute` command for an ESP.

If you execute a stored procedure and specify more parameters than the number of parameters expected by the procedure, the server ignores the extra parameters.

## i Note

If you spell any parameter name incorrectly, the server ignores it by treating it as an extra. You see no warnings about the spelling error, and if the parameter is defined with a default value, the server executes the procedure using that default value instead of the value you provided with the misspelled parameter.

- The dynamic SQL syntax of `exec (@<parameter_name>)` is also valid; however, it may take more keystrokes. For example, the dynamic SQL command `exec (@sproc ="7")` passes the integer value 7 to the procedure, but this can also be accomplished using `exec @sproc 7`.
- You cannot use `text`, `unitext`, and `image` columns as parameters to stored procedures or as values passed to parameters.
- Executing a procedure specifying `output` for a parameter that is not defined as a return parameter in `create procedure` causes an error.
- You cannot pass constants to stored procedures using `output`; the return parameter requires a variable name. You must declare the variable's datatype and assign it a value before executing the procedure. Return parameters cannot have a datatype of `text`, `unitext`, or `image`.
- You need not use the keyword `execute` if the statement is the first one in a batch. A batch is a segment of an input file terminated by the word "go" on a line by itself.
- Since the execution plan for a procedure is stored the first time it is run, subsequent run time is much shorter than for the equivalent set of standalone statements.
- Nesting occurs when one stored procedure calls another. The nesting level is incremented when the called procedure begins execution and is decremented when the called procedure completes execution. The nesting level is also incremented by one when a cached statement is created. Exceeding the maximum of 16 levels of nesting causes the transaction to fail. The current nesting level is stored in the `<@@nestlevel>` global variable.
- Return values 0 and -1 through -14 are currently used by the SAP ASE server to indicate the execution status of stored procedures. Values from -15 through -99 are reserved for future use. See `return` for a list of values.
- Parameters are not part of transactions, so if a parameter is changed in a transaction that is later rolled back, its value does not revert to its previous value. The value that is returned to the caller is always the value at the time the procedure returns.
- If you use `select *` in a stored procedure, the procedure does not pick up any new columns you might have added to the table using `alter table`, even if you use the `with recompile` option. To do so, you must drop and re-create the stored procedure, or else an `insert` based on a `select *` can cause erroneous results. Even if the newly added column has a default bound to it, the result of the `insert` is NULL for the newly added column.  
When you drop and re-create the stored procedure or reload the database, you see an error message if the column definitions of the target table do not match the `select *` result.
- Commands executed via remote procedure calls cannot be rolled back.
- The `with recompile` option is ignored when the SAP ASE server executes an extended stored procedure.

See also `sp_addextendedproc`, `sp_depends`, `sp_dropextendedproc`, `sp_helptext`, `sp_procxmode` in *Reference Manual: Procedures*.

## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

## Permissions

The permission to execute Transact-SQL commands defined with the `<string>` or `<char_variable>` options is checked against the user executing the command, unless the procedure was set up using the execution mode "dynamic ownership chain." See `sp_procxmode`.

The permission checks for `execute` differ based on your granular permissions settings.

Setting	Description
---------	-------------

<b>Enabled</b>	With granular permissions enabled, you must be the procedure owner or a user with <code>execute</code> permission on the procedure.
----------------	---

<b>Disabled</b>	With granular permissions disabled, you must have <code>execute</code> permission on the procedure.
-----------------	---

## Auditing

You can enable the following auditing options to audit this command. Values in `event` and `extrainfo` columns from the `sysaudits` table are:

Audit option	Event	Command or access audited	Information in <code>extrainfo</code> :
<code>exec_procedure</code>	38	Execution of a procedure	<ul style="list-style-type: none"><li>• <b>Roles</b> – current active roles</li><li>• <b>Keywords or options</b> – NULL</li><li>• <b>Previous value</b> – NULL</li><li>• <b>Current value</b> – NULL</li><li>• <b>Other information</b> – all input parameters</li><li>• <b>Proxy information</b> – original login name, if set <code>proxy</code> is in effect</li></ul>
<code>exec_trigger</code>	39	Execution of a trigger	<ul style="list-style-type: none"><li>• <b>Roles</b> – current active roles</li><li>• <b>Keywords or options</b> – NULL</li><li>• <b>Previous value</b> – NULL</li><li>• <b>Current value</b> – NULL</li><li>• <b>Other information</b> – NULL</li><li>• <b>Proxy information</b> – original login name, if set <code>proxy</code> is in effect</li></ul>

Example of `extrainfo` after executing `sp_bindrule`:

```
select event, extrainfo from sybsecurity..sysaudits_01 where event = 38
```



```

go
event  extrainfo
-----
38     sa_role sso_role oper_role sybase_ts_role mon_role; ; ; ; test_rule,
      testtable1.t1; ; ;

```

For more information about auditing, see *Security Administration Guide > Auditing*.

## Related Information

[drop procedure \[page 448\]](#)

[return \[page 669\]](#)

## 1.83 fetch

Returns a row or a set of rows from a cursor result set.

### Syntax

```

fetch [next | prior | first | last | absolute
      <fetch_offset> | relative <fetch_offset>]
[from] <cursor_name>
[into <fetch_target_list>]

```

### Parameters

**next | prior | first | last | absolute | relative**

are keywords that specify the fetch direction. You do not need to specify the fetch direction for nonscrollable cursors. If you specify the fetch direction, you can use any of the other options to access the rows from a scrollable cursor. You must specify the `<fetch_offset>` when you use `absolute` or `relative`.

**[from] <cursor\_name>**

is the name of the cursor. `from` is optional.

**<fetch\_offset>**

specifies the offset value from a specific position. `<fetch_offset>` is required when you specify `absolute` or `relative`. `<fetch_offset>` can be either signed numeral literal with scale of zero, or Transact-SQL variable with a type of integer or numeric with a zero-scale numeral.

**<fetch\_target\_list>**

is a comma-separated list of parameters or local variables into which cursor results are placed. The parameters and variables must be declared prior to the `fetch`.

## Examples

### Example 1

Returns a row of information from the cursor result set defined by the `authors_crsr` cursor:

```
fetch authors_crsr
```

### Example 2

Returns a row of information from the cursor result set defined by the `pubs_crsr` cursor into the variables `<@name>`, `<@city>`, and `<@state>`:

```
fetch pubs_crsr into @name, @city, @state
```

### Example 3

With scrollable cursors, you can use numeric literal offset with orientation keyword `absolute`. In this example, the 25th row is specified. Enter:

```
fetch absolute 25 from pubs_crsr
into @name, @city, @state
```

### Example 4

To use a Transact-SQL variable representing the 25th row, enter:

```
declare @offset int
select @offset = 25
fetch absolute @offset from c1
```

## Usage

You can fetch one or more rows at a time. To determine the number of rows fetched, use the `cursor rows` option of the `set` command, specifying the number of rows to fetch.

The value of `<@@rowcount>` is affected by whether the specified cursor is forward-only or scrollable. If the cursor is the default, nonscrollable cursor, the value of `<@@rowcount>` increments one by one, in the forward direction only, until the total number of rows in the result set are fetched.

Once all the rows have been read from the cursor result set, `<@@rowcount>` represents the total number of rows in the cursor results set. `<@@rowcount>` after a fetch to get the number of rows read for the cursor specified in that fetch.

If the cursor is scrollable, there is no maximum value for `<@@rowcount>`. For more information on `<@@rowcount>`, see *Reference Manual: Building Blocks*.

Cursor position:

- For nonscrollable cursors, after you fetch all the rows, the cursor points to the last row of the result set. If you fetch again, the SAP ASE server returns a warning through the `<@@sqlstatus>` and `<@@fetch_status>` global variables, with value indicating there is no more data, and the cursor position moves beyond the end of the result set. You can no longer update or delete from that current cursor position.
- With `fetch into`, the SAP ASE server does not advance the cursor position when an error occurs, because the number of variables in the `<fetch_target_list>` does not equal the number of target list expressions specified by the query that defines the cursor. However, it does advance the cursor position, even if a compatibility error occurs between the datatypes of the variables and the datatypes of the columns in the cursor result set.

## Standards

ANSI SQL – Compliance level: Entry-level compliant.

The fetch of multiple rows is a Transact-SQL extension.

## Permissions

`fetch` permission defaults to all users.

## Auditing

This command is not audited.

## Related Information

[declare cursor \[page 384\]](#)

[open \[page 628\]](#)

[set \[page 732\]](#)

### 1.83.1 Status Information

Status information from `<@@sqlstatus>` and `<@@fetch_status>` global variables.

Only a `fetch` statement can set `<@@sqlstatus>` and `<@@fetch_status>`. Other statements have no effect on `<@@sqlstatus>` or `<@@fetch_status>`.

The `<@@sqlstatus>` global variable holds status information (warning exceptions) resulting from the execution of a `fetch` statement. Its value reflects the last cursor fetched:

Value	Description
0	Indicates successful completion of the fetch statement.
1	Indicates that the fetch statement resulted in an error.
2	Indicates that there is no more data in the result set. This warning can occur if the current cursor position is on the last row in the result set and the client submits a fetch statement for that cursor.

The `<@@fetch_status>` global variable provides information about whether `fetch` is executed successfully in a scrollable cursor:

Value	Description
0	Indicates successful completion of the fetch statement.
-1	Indicates that the fetch operation failed, or the row fetched was beyond the result set.
-2	Reserved for future use.

## 1.83.2 fetch Restrictions

Restrictions for using `fetch`.

- Before you can use `fetch`, you must declare the cursor and `open` it.
- You can use `fetch` with an archive database.
- The `<cursor_name>` cannot be a Transact-SQL parameter or local variable.
- For nonscrollable cursors, you cannot `fetch` a row that has already been fetched. There is no way to backtrack through the result set, but you can close and reopen the cursor to create the cursor result set again and start from the beginning.
- The SAP ASE server expects a one-to-one correspondence between the variables in the `<fetch_target_list>` and the target list expressions specified by the `select` statement that defines the cursor. The datatypes of the variables or parameters must be compatible with the datatypes of the columns in the cursor result set.
- When you set chained transaction mode, the SAP ASE server implicitly begins a transaction with the `fetch` statement if no transaction is currently active. However, this situation occurs only when you set the `close on endtran` option and the cursor remains open after the end of the transaction that initially opened it, since the `open` statement also automatically begins a transaction.

## 1.83.3 Using Scrollable Cursors with `fetch_direction`

Additional information for using scrollable cursors with `<fetch_direction>`.

- If not specified, the default value is `next`.
- If not `next`, the cursor must be declared scrollable.
- `<fetch_offset>` must be an exact, signed numeric, with a scale of zero.
- Positions the cursor beyond the last row or before the first row, no data is returned and no error is raised.
- Is `absolute`, when `<fetch_offset>`  $>0$ , the offset is calculated from the position before the first row of the result set. If `<fetch_offset>`  $<0$ , the offset is calculated from the position after the last row of the result set.
- Is `relative`, when `<fetch_offset>`  $>0$ , the cursor is placed `<n>` rows after the current position; if `<fetch_offset>`  $<0$ , the cursor is placed `abs (<n>)` rows before the current position.

The row number specified in the result set is counted from 1; the first row is number 1.

## 1.83.4 Multiple Rows per Fetch

Each `fetch` returns one row to the client in default behavior. The returned rows per `fetch` can be changed to another number by entering:

```
set cursor rows number for <cursor_name>
```

`number` specifies the number of rows per `fetch` the cursor can execute. This number can be a numeric literal with no decimal point, or a local variable of type `integer`. If `<cursor rows>` is greater than one, multiple rows return to the client after `fetch`. In some cases, the rows returned by `fetch` may be less than the number of rows specified, depending on the cursor's position. The current cursor position is always one row.

## 1.83.5 Rules for Positioning the Scrollable Cursor

There are rules that govern the position of the cursor in `fetch_orientation` options when you are fetching the cursor rows, where `<cursPos>` is the cursor position.

See the `fetch_orientation`

These terms used in rules for positioning the scrollable cursor are:

- `<curRowsetStart>` – the cursor's current position.
- `<new_CurRowsetStart>` – the new current position of the cursor.
- `<total_rows>` – the total number of rows in the cursor result set.
- `<before_first>` – the row position before the first row of the cursor result set. This variable has a value of 0.
- `<after_last>` – the row position after the last row of the cursor result set. This variable has a value of `<total_rows>` + 1.
- `<first_row>` – the position at the first row of the cursor result set. This variable has value of 1.

- `<last_row>` – the position at the last row of the cursor result set. This variable has the same value as `<total_rows>`.
- `<fetchSize>` – the number of rows requested for each `fetch` operation.

Rule	Description
Fetch first	The <code>&lt;new_CurRowsetStart&gt;</code> always moves to <code>&lt;first_row&gt;</code> , regardless of the position of <code>&lt;CurRowsetStart&gt;</code> and the value of <code>&lt;fetchSize&gt;</code> .
Fetch last	<ul style="list-style-type: none"> <li>• If <code>&lt;total_rows&gt; &gt;= &lt;fetchSize&gt;</code>, then <code>&lt;new_CurRowsetStart&gt; = &lt;total_rows&gt; - &lt;fetchSize&gt; + 1</code>.</li> <li>• If <code>&lt;total_rows&gt; &lt; &lt;fetchSize&gt;</code>, then <code>&lt;new_CurRowsetStart&gt;</code> is on <code>&lt;first_row&gt;</code>.</li> </ul>
Fetch next	<ul style="list-style-type: none"> <li>• If <code>&lt;CurRowsetStart&gt;</code> is <code>&lt;before_first&gt;</code>, then <code>&lt;new_CurRowsetStart&gt;</code> is on <code>&lt;first_row&gt;</code>.</li> <li>• Let <code>&lt;curPos&gt; = (&lt;CurRowsetStart&gt; + &lt;fetchSize&gt;)</code>, <ul style="list-style-type: none"> <li>◦ <code>&lt;curPos&gt; &lt;= &lt;total_rows&gt;</code>, then <code>&lt;new_CurRowsetStart&gt; = &lt;curPos&gt;</code></li> <li>◦ <code>&lt;curPos&gt; &gt; &lt;total_rows&gt;</code>, <code>&lt;new_CurRowsetStart&gt;</code> is <code>&lt;after_last&gt;</code></li> </ul> </li> <li>• If <code>&lt;CurRowsetStart&gt;</code> is <code>&lt;after_last&gt;</code> row, then <code>&lt;new_CurRowsetStart&gt;</code> remains on <code>&lt;after_last&gt;</code>.</li> </ul>
Fetch prior	<ul style="list-style-type: none"> <li>• <code>&lt;new_CurRowsetStart&gt;</code> is <code>&lt;before_first&gt;</code> when one of these conditions is true: <ul style="list-style-type: none"> <li>◦ <code>(&lt;CurRowsetStart&gt; &gt;= 1) &amp;&amp; (&lt;CurRowsetStart&gt; - &lt;fetchSize&gt; &lt;= 0)</code></li> <li>◦ <code>&lt;CurRowsetStart&gt;</code> is <code>&lt;before_first&gt;</code></li> </ul> </li> <li>• Let <code>&lt;curPos&gt; = &lt;CurRowsetStart&gt; - &lt;fetchSize&gt;</code>; iff <code>1 &lt;= &lt;curPos&gt; &lt;= &lt;total_rows&gt;</code>, then <code>&lt;new_CurRowsetStart&gt; = &lt;curPos&gt;</code>.</li> <li>• If <code>(&lt;CurRowsetStart&gt;</code> is <code>&lt;after_last&gt;</code>), let <code>&lt;curPos&gt; = &lt;total_rows&gt; - &lt;fetchSize&gt; + 1</code> <code>&lt;new_CurRowsetStart&gt; = &lt;curPos&gt;</code> if <code>&lt;curPos&gt; &gt; 0</code> <code>&lt;new_CurRowsetStart&gt;</code> is <code>&lt;before_first&gt;</code> if <code>&lt;curPos&gt; &lt;= 0</code></li> </ul>
Fetch relative	<ul style="list-style-type: none"> <li>• If <code>(&lt;CurRowsetStart&gt;</code> is <code>&lt;before_first&gt;</code>) &amp;&amp; <code>(&lt;fetch_offset&gt; &gt; 0)</code>, then <code>&lt;new_CurRowsetStart&gt; = &lt;fetch_offset&gt;</code>.</li> <li>• <code>&lt;new_CurRowsetStart&gt;</code> is <code>&lt;before_first&gt;</code> if one of these conditions is true: <ul style="list-style-type: none"> <li>◦ <code>(&lt;CurRowsetStart&gt;</code> is <code>&lt;before_first&gt;</code>) and <code>(&lt;fetch_offset&gt; &lt; 0)</code></li> <li>◦ <code>(&lt;CurRowsetStart&gt;</code> is on <code>&lt;first_row&gt;</code>) and <code>(&lt;fetch_offset&gt; &lt; 0)</code></li> <li>◦ <code>(&lt;CurRowsetStart&gt;</code> is <code>&lt;after_last&gt;</code>) and <code>((&lt;CurRowsetStart&gt; + &lt;fetch_offset&gt; + 1) &lt;= 0)</code></li> </ul> </li> <li>• If <code>(1 &lt; &lt;CurRowsetStart&gt; &lt;= &lt;total_rows&gt;)</code>, let <code>&lt;curPos&gt; = &lt;CurRowsetStart&gt; + &lt;fetch_offset&gt;</code>, then: <ul style="list-style-type: none"> <li>◦ <code>&lt;new_CurRowsetStart&gt;</code> is on <code>&lt;first_row&gt;</code> iff <code>(&lt;curPos&gt; &lt; 1) and &lt;abs&gt;(&lt;fetch_offset&gt;) &lt;= &lt;fetchSize&gt;</code></li> <li>◦ <code>&lt;new_CurRowsetStart&gt;</code> is before <code>&lt;first_row&gt;</code> iff <code>(&lt;curPos&gt; &lt; 1) &amp;&amp; (&lt;abs&gt;(&lt;fetch_offset&gt;) &lt; &lt;fetchSize&gt;)</code></li> <li>◦ <code>&lt;new_CurRowsetStart&gt; = &lt;curPos&gt;</code> iff <code>(0 &lt; &lt;curPos&gt; &lt;= &lt;total_rows&gt;)</code></li> <li>◦ <code>&lt;new_CurRowsetStart&gt;</code> is <code>&lt;after_last&gt;</code> iff <code>&lt;curPos&gt; &gt; &lt;total_rows&gt;</code></li> </ul> </li> </ul>

Rule	Description
	<ul style="list-style-type: none"> <li>If (&lt;CurRowsetStart&gt; is &lt;after_last&gt;), let &lt;curPos&gt; = &lt;CurRowsetStart&gt; + &lt;fetch_offset&gt; + 1, then: <ul style="list-style-type: none"> <li>&lt;new_CurRowsetStart&gt; = &lt;curPos&gt; iff 1 &lt;= &lt;curPos&gt; &lt;= &lt;total_rows&gt;</li> <li>&lt;new_CurRowsetStart&gt; is &lt;before_first&gt; iff &lt;curPos&gt; &lt;= 0</li> <li>&lt;new_CurRowsetStart&gt; is &lt;after_last&gt; iff &lt;curPos&gt; &gt; &lt;total_rows&gt;</li> </ul> </li> </ul>
Fetch absolute	<ul style="list-style-type: none"> <li>If &lt;fetch_offset&gt; = 0, &lt;new_CurRowsetStart&gt; is &lt;before_first&gt;</li> <li>If &lt;fetch_offset&gt; &gt; &lt;total_rows&gt;, &lt;new_CurRowsetStart&gt; is &lt;after_last&gt;</li> <li>If 0 &lt; &lt;fetch_offset&gt; &lt;= &lt;total_rows&gt;, &lt;new_CurRowsetStart&gt; = &lt;fetch_offset&gt;</li> <li>If (&lt;fetch_offset&gt; &lt; 0) &amp;&amp; (&lt;abs&gt; (&lt;fetch_offset&gt;) &gt; &lt;total_rows&gt;), <ul style="list-style-type: none"> <li>let &lt;abs_offset&gt; = &lt;abs&gt; (&lt;fetch_offset&gt;)</li> <li>&lt;new_CurRowsetStart&gt; is &lt;before_first&gt; iff &lt;abs_offset&gt; &gt; &lt;fetchSize&gt;</li> <li>&lt;new_CurRowsetStart&gt; is on &lt;first_row&gt; iff &lt;abs_offset&gt; &lt;= &lt;fetchSize&gt;</li> </ul> </li> <li>If (&lt;fetch_offset&gt; &lt; 0) &amp;&amp; (&lt;abs&gt; (&lt;fetch_offset&gt;) &lt;= &lt;total_rows&gt;) <ul style="list-style-type: none"> <li>&lt;new_CurRowsetStart&gt; = &lt;total_rows&gt; + &lt;fetch_offset&gt; + 1</li> </ul> </li> </ul>

## 1.84 goto label

Branches to a user-defined label.

### Syntax

```
<label>:
  goto <label>
```

### Examples

#### Example 1

Shows the use of a label called `restart`:

```
declare @count smallint
select @count = 1
restart:
  print "yes"
select @count = @count + 1
while @count <= 4
  goto restart
```

## Usage

- The label name must conform to the rules for identifiers and must be followed by a colon (:) when it is declared. It is not followed by a colon when it is used with `goto`.
- Make the `goto` dependent on an `if` or `while` test, or some other condition, to avoid an endless loop between `goto` and the label.

## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

## Permissions

No permission is required to use `goto`.

## Auditing

This command is not audited.

## Related Information

[if...else \[page 569\]](#)

[while \[page 863\]](#)

## 1.85 grant

Assigns permissions to individual users, groups of users, and roles.

## Syntax

Grants permission to access database objects:

```
grant {all [privileges] | <permission_list>}
    on {<table_name> as [<correlation_name>] [<column_list>]}
```



```

| <view_name>[( <column_list>)]
| <stored_procedure_name> | <SQL_function_name>}
| <keyname>}
[where <search_conditions> [as <pred_name>]]
[ON SCHEMA <schema_name>]
to {public | <name_list> | <role_list>}
[with grant option]
[granted by <grantor>]

```

Grants permission to use built-in functions:

```

grant select
on [builtin] <builtin>
to {<name_list> | <role_list>}
[granted by <grantor>]

```

Grants system privileges to execute certain commands:

```

grant {all [privileges] | <privilege_list>}
to {public | <name_list> | <role_list>}
[granted by <grantor>]

```

Grants dbcc privileges:

```

grant {<dbcc_privilege> [on <database> ]
[, <dbcc_privilege> [on <database> ], ...]}
to {<user_list> | <role_list >}
[granted by <grantor>]

```

Grants the default permissions for specific system tables:

```

grant default permissions on system tables

```

Grants permission that allows grantee to switch server user identity to any other server login and limit its use based on the target login's roles:

```

grant set proxy to <name_list>
[restrict role<role_list> <grantor>]

```

## Parameters

### all

when used to assign permission to access database objects, `all` specifies that all permissions, except `decryptgrant all`

When granular permissions is not enabled, a system administrator or the database owner can use `grant all` to assign privileges to create database objects (see syntax for "Grants system privileges to execute certain commands"). When used by a system administrator, `grant all` assigns all `create` privileges (`create database`, `create default`, `create procedure`, `create rule`, `create table`, `create function`, and `create view`). When the database owner uses `grant all`, or executes `grant all` outside the master database, the SAP ASE server grants all `create` privileges except `create database` and prints an informational message.

Granting all create privileges using `grant all` is not supported when granular permissions is enabled. For more information, see *Using Granular Permissions* in the *Security Administration Guide*.

`all` cannot be used for a `grant` statement that includes a `where` clause.

#### <permission\_list>

is a list of object access permissions granted. If more than one permission is listed, separate them with commas. The access permissions that can be granted on each type of object include: , that are applicable to the specified object are granted. All object owners can use

<b>Column</b>	<code>select, update, that are applicable, references, decrypt</code> Specify column names in <column_list>.
<b>Encryption key</b>	<code>select</code>
<b>Stored procedure</b>	<code>execute</code>
<b>SQL function</b>	<code>execute</code>
<b>Table</b>	<code>select, insert, delete, update, update statistics, delete statistics, references, truncate table, decrypt, transfer table.</code>  <code>identity_insert</code> and <code>identity_update</code> must grant <code>decrypt</code> permissions separately. , when granular permissions are enabled.
<b>View</b>	<code>select, insert, delete, update</code> with an object name to grant permissions on their own objects.  <code>identity_insert</code> and <code>identity_update</code> , when granular permissions are enabled.

#### <correlation\_name>

is used only for `grant ... where` commands as an alias for referencing columns in <table\_name> in the `where` clause.

#### <table\_name>

is the name of the table on which you are granting permissions. The table must be in your current database. Only one object can be listed for each `grant` statement.

#### <column\_list>

is one or more named columns, separated by commas, to which the permissions apply. If columns are specified, only `select, references, decrypt, and update` permissions can be granted.

When the `grant` is made on one or more named columns using a `where` clause, then the SAP ASE server enforces row-level access on the user's `select, update` or `delete` command as follows:

- one or more of the named columns on a `grant select` statement is referenced in the target list or `where` clause of the user's `select` statement

- one or more of the named columns on a `grant update` statement is referenced in the target list of the user's `update` statement
- one or more columns on a `grant select` is referenced in the `where` clause of the user's `update` or `delete` statement where the session has set `ansi_permissions on`.

**<view\_name>**

is the name of the view on which you are granting permissions. The view must be in your current database.

**<stored\_procedure\_name>**

is the name of the stored procedure on which you are granting permission. The stored procedure must be in your current database.

**<key\_name>**

is the name of an encryption key on which you are granting access. The `<key_name>` must be in your current database.

**<SQL\_function\_name>**

is the name of the SQL function to which you are granting permission. The stored function must be in your current database. You can list only one function for each `grant` statement.

**where <search\_conditions>**

acts as a row filter, and combines with any `where` clause specified in `select`, `update`, or `delete` statements. You can use the `where` syntax only when granting `select`, `update`, and `delete` privileges on a table. `<search_conditions>` can make use of all syntax allowed in a generic `where` clause. If the `where` clause accesses a different table from the one being granted, you must use a subquery. For information on using a `where` clause on the `grant` statement see *Granting Predicated Privileges* in the *Security Administration Guide*.

**as <pred\_name>**

is the name of the predicate, and must be unique among the names of other objects owned by the grantor in the current database and must conform to the rules for identifiers. If you omit `<pred_name>`, the SAP ASE server assigns a unique name to the `grant` predicate, which you can view by using `sp_helprotect`. `<pred_name>` may not be used on `grant` statements with no `where` clause. Predicates can be referenced by name by the `revoke` command.

**to {public | <name\_list> | <role\_list>}**

- `public` – is all users. For object access permissions, `public` excludes the object owner. For object creation permissions or `set proxy` authorizations, `public` excludes the database owner.
- `<name_list>` – is a list of users' and group names, separated by commas.
- `<role_list>` – is a list of roles — either system-defined or user-defined — to which you are granting the permission.

**with grant option**

allows the users specified in `<name_list>` to grant object access permissions to other users. You can grant permissions with `grant option` only to individual users, not to

"public" or to a group or role. Predicated privileges cannot be granted with the `with grant option`.

**granted by <grantor>**

indicates the grantor as a user in the database different from the user executing the command.

**<grantor>**

a valid user name in current database, grantor's user identity instead of the executor's user identity would be recorded in the system catalog `sysprotects` as the grantor.

**<builtin>**

is a built-in function. Specifying the keyword `<builtin>` before the built-in function name allows you to differentiate between a table and a grantable built-in function with the same name. The grantable `<builtin>` functions are `set_appcontext`, `get_appcontext`, `list_appcontext`, `authmech`, `rm_appcontext`, and `next_identity` (requires select permission on the IDENTITY column).

**<privilege\_list>**

is a list of system privileges that can be granted. System privileges include server-wide and database-wide privileges. See the "Usage" section for details on how to grant system privileges. Use commas to separate multiple commands.

**<dbcc\_privilege>**

is the name of the `dbcc` privilege you are granting. It cannot be a variable. See the *Usage* section on grantable server-wide `dbcc` and database-wide `dbcc` privileges.

**i Note**

You cannot grant or revoke `dbcc` privileges to public or groups.

**<database>**

is the name of the database on which you are granting permissions. It is used with granting database-wide `dbcc` privileges. The `on database` clause is optional, and the database must be the current database. The grantee must be a valid user in the target database. `<database>` conforms to the rules for identifiers and cannot be a variable.

If there are multiple granted actions in the same command, `<database>` must be unique.

**set proxy**

grants permission for a user to impersonate another user. If grantees do not have the roles in the `<role_list>` already granted to them, `set proxy` to the target login fails if the target login has any roles in the `<role_list>` granted.

**system**

the grantee cannot switch their identity with anyone who possesses a system role they do not possess. Use `<system>` only with the `set proxy` parameter.

**restrict role <role\_list>**

allows the grantee to switch identities only if the grantee and the target login have any roles included in the `<role_list>`.

**all**

The grantee can grant their identity to anyone who has the same set of roles they possess. That is, the grantee cannot inherit any new roles by executing the `set proxy` command.

### default permissions on system tables

specifies that you grant the default permissions for the system tables listed in *Granting Default Permissions on System Tables* in the *Usage* section.

## Examples

### Example 1

Grants Mary and the "sales" group permission to use the `insert` and `delete` commands on the `titles` table:

```
grant insert, delete
on titles
to mary, sales
```

### Example 2

Grants `select` permission on the `get_appcontext` function to "public" (which includes all users):

```
grant select on builtin get_appcontext to public
```

Compare this to the following, which grants `select` permission on a table called `get_appcontext`, if a table with that name exists:

```
grant select on get_appcontext to public
```

Specifically including the `builtin` argument in your `grant` statement ensures that you do not mistakenly select a table that has the same name as a function—in this example, the `get_appcontext` function versus a table called `get_appcontext`.

### Example 3

Two ways to grant `update` permission on the `price` and `advance` columns of the `titles` table to "public" (which includes all users):

```
grant update
on titles (price, advance)
to public
```

or:

```
grant update (price, advance)
on titles
to public
```

### Example 4

Grants `transfer table` permission to user Mary for the `titles` table:

```
grant transfer table on titles to mary
```

### Example 5

Grants Mary and John permission to use the `create database` and `create table` commands. Mary and John's `create table` permission applies only to the `master` database:

```
grant create database, create table
to mary, john
```

### Example 6

Grants complete access permissions, except `decrypt` permission, on the `titles` table to all users:

```
grant all on titles
to public
```

### Example 7

Gives Mary permission to use the `update` command on the `authors` table and to grant that permission to others:

```
grant update on authors
to mary
with grant option
```

### Example 8

Gives Bob permission to use the `select` and `update` commands on the `price` column of the `titles` table and to grant that permission to others:

```
grant select, update on titles (price)
to bob
with grant option
```

### Example 9

Grants permission to execute the `new_sproc` stored procedure to all system security officers:

```
grant execute on new_sproc
to sso_role
```

### Example 10

Grants James permission to create a referential integrity constraint on another table that refers to the `price` column of the `titles` table:

```
grant references on titles (price)
to james
```

#### i Note

Before you create a table that includes a referential integrity constraint to reference another user's table, you must be granted `references` permission on that referenced table. The table must also include a unique constraint or unique index on the referenced columns. See `create table` for more information about referential integrity constraints.

### Example 11

Grants the database owner permission to specify column encryption using the `ssn_key`, when executed by the key owner. The database owner requires `select` permission on `ssn_key` to reference it on `create table`, `alter table`, or `select into`:

```
grant select on ssn_key to dbo
```

### Example 12

Grants Bob permission to create encryption keys:

```
grant create encryption key to Bob
```

### Example 13

Grants `decrypt` permission on all encrypted columns in the `customer` table:

```
grant decrypt on customer to accounts_role
```

### Example 14

Grants `dump any database` privilege to Joe in `master` to allow him to dump any database:

```
1> use master
2> go
1> grant dump any database to joe
2> go
```

### Example 15

Grants `create any object` privilege to Joe in database `pubs2` to allow Joe create any object privilege on behalf of himself or on behalf of other users in `pubs2`:

```
1> use pubs2
2> go
1> grant create any object to joe
2> go
```

### Example 16

Grants `manage roles` to Alex. This returns an error because server-wide privileges require that `master` be the current database:

```
1> use pubs2
2> go
1> grant manage roles to alex
2> go
```

```
Msg 4627, Level 16, State 1:
Line 1:
The user must be in the master database to GRANT/REVOKE this command.
```

### Example 17

Through the use of a role, the system administrator allows Carlos to run `dbcc checkalloc` on any database where he is a valid user, or where a database allows a "guest" user.

## i Note

You do not need to add Carlos as an actual user in the `master` database if the user "guest" already exists in `master`.

```
1> use master
2> go
1> create role checkalloc_role
2> go
1> grant dbcc checkalloc any database to checkalloc_role
2> go
1> create login carlos with password carlospassword
2> go
1> grant role checkalloc_role to carlos
2> go
```

## Example 18

Gives Frank, a valid user in the `master` database, the ability to execute `dbcc checkdb` for all databases in the server:

```
1> use master
2> go
1> create login frank with password frankpassword
2> go
```

```
Password correctly set.
Account unlocked.
New login created.
(return status = 0)
```

```
1> sp_adduser frank
2> go
```

```
New user added.
(return status = 0)
```

```
1> grant dbcc checkdb any database to frank
2> go
```

Now Frank can execute the `dbcc checkdb` command on each database in the server where he is a valid user:

```
% isql -Ufrank -Pfrankpassword -SSERVER
1> dbcc checkdb (tempdb)
2> go
```

```
Checking tempdb: Logical pagesize is 2048 bytes
Checking sysobjects: Logical pagesize is 2048 bytes
...
The total number of data pages in this table is 1. DBCC
execution completed. If DBCC printed error messages,
contact a user with system administrator (SA) role.
```

## i Note

You cannot grant or revoke `dbcc` privileges to public or groups.



### Example 19

If Walter needs to be a maintenance user for `pubs2` but the system administrator does not want to grant him administrator-level privileges elsewhere, the system administrator can execute:

```
1> use pubs2
2> go
1> grant dbcc checkdb on pubs2 to walter
2> go
```

#### i Note

The system administrator must be in the target database—in this case `pubs2`—and Walter must be a valid user in this target database. The `on pubs2` clause is optional.

Walter can now execute the `dbcc checkdb` command on the `customers` database without encountering an error.

### Example 20

Erroneously applies `grant dbcc` and `revoke dbcc` to groups or public:

```
1> grant dbcc tablealloc on pubs2 to public
```

```
Msg 4629, Level 16, State 1:
Line 1:
GRANT/REVOKE DBCC does not apply to groups or PUBLIC.
```

```
1> sp_addgroup gr
```

```
New group added.
(return status = 0)
```

```
1> grant dbcc tablealloc on pubs2 to gr
```

```
Msg 4629, Level 16, State 1:
Line 1:
GRANT/REVOKE DBCC does not apply to groups or PUBLIC.
```

### Example 21

You cannot grant system privileges using the `grant` option:

```
grant change password to alex with grant option
```

```
Msg 156, Level 15, State 1:
Line 1:
Incorrect syntax near the keyword 'with'.
```

### Example 22

Allows Harry to use `truncate table` and `updates statistics` on the `authors` table:

```
grant truncate table on authors to harry
grant update statistics on authors to harry
```

### Example 23

Allows Billy to use the `delete statistics` command on the `authors` table:

```
grant delete statistics on authors to billy
```

### Example 24

Grants `truncate table`, `update`, and `delete statistics` privileges to all users with the `oper_role` (if Billy and Harry possess the `oper_role`, they can now execute these commands on `authors`):

```
grant truncate table on authors to oper_role
grant update statistics on authors to oper_role
grant delete statistics on authors to oper_role
```

### Example 25

Implicitly grants permissions for `truncate table`, `delete statistics`, and `update statistics` through a stored procedure. For example, assuming Billy owns the `authors` table, he can execute the following to grant Harry privileges to run `truncate table` and `update statistics` on `authors`:

```
create procedure sprocl
as
truncate table authors
update statistics authors
go
grant execute on sprocl to harry
go
```

You can also implicitly grant permissions at the column level for `update statistics` and `delete statistics` through stored procedures.

### Example 26

Grants Harry and Billy permission to execute either `set proxy` or `set session authorization to impersonate` another user in the server:

```
grant set proxy to harry, billy
```

### Example 27

Grants users with `sso_role` permission to execute either `set proxy` or `set session authorization to impersonate` another user in the server:

```
grant set session authorization to sso_role
```

### Example 28

Grants `set proxy` to Joe but restricts him from switching identities to any user with the `sa`, `sso`, or `admin` roles (however, if he already has these roles, he can `set proxy` for any user with these roles):

```
grant set proxy to joe
restrict role sa_role, sso_role, admin_role
```

When Joe tries to switch his identity to a user with `admin_role` (in this example, `Our_admin_role`), the command fails unless he already has `admin_role`:

```
set proxy Our_admin_role
```

```
Msg 10368, Level 14, State 1:
```

```
Server 's', Line 2:Set session authorization permission
denied because the target login has a role that you do
not have and you have been restricted from using.
```

After Joe is granted the `admin_role` and retries the command, it succeeds:

```
grant role admin_role to joe
set proxy Our_admin_role
```

### Example 29

Restricts Joe from being granted any new roles when switching identities:

```
grant set proxy to joe
restrict role all
```

Joe can `set proxy` only to those users who have the same roles (or roles with fewer privileges) than he has.

### Example 30

Restricts Joe from acquiring any new system roles when using `set proxy`:

```
grant set proxy to joe
restrict role system
```

`set proxy` fails if the target login has system roles that Joe lacks.

### Example 31

Students are allowed to view information only about their own grades:

```
grant select on grades
  where user_name(uid) = USER as predicate_grades
to public
```

### Example 32

Allows registered students to see information about all courses. The first `grant` allows anyone to peruse the courses and sections offered. The second `grant` allows a user to see only his own enrollments in those courses.

```
grant select on enrollment
  (course_id, quarter, section_id)
to public
grant select on enrollment as e
  (uid, with_honors)
  where e.uid in
  (select r.uid from
  registered_students r
  where USER = user_name(r.uid))
to public
```

When a registered student enters the following query, he becomes restricted to seeing his own courses (because the `with_honors` column has been selected):

```
select course_id, quarter, with_honors
  from enrollment
```

Similarly, when a registered student tries to see how many courses people are taking with the following query:

```
select course_id, count(uid) from enrollment
group by course_id
```

The SAP ASE server returns one row giving the count of courses enrolled in by the user.

### Example 33

User Smith grants `select` permission to user John on `mary.books`, with table owner Mary as the grantor:

```
grant select on mary.books to john
granted by mary
```

### Example 34

User Smith grants `create table` permission to user John, with the `dbo` as the grantor:

```
grant create table to john
granted by dbo
```

### Example 35

With granular permissions disabled, granting system privilege `manage any login` results in an error:

```
1>sp_configure "enable granular permissions"
2>goParameter Name      Default  Memory Used  Config Value  Run Value  Unit
Type                -----
-----  ----  -----
enable granular
permissions          0         0         0         0  switch  dynamic (1
row affected)
(return status = 0)
>grant manage any login to smith
>go
Msg 16325, Level 15, State 87:
Line 1:
Cannot GRANT/REVOKE permission 'MANAGE ANY LOGIN'. Verify that the granular
permissions option is enabled.
```

### Example 36

You must specify an `<database>` clause when granting system privilege `own database`:

```
1>grant own database to smith
2>goMsg 156, Level 15, State 2:
Line 1:
Incorrect syntax near the keyword 'to'.
1>grant own database on tdb1 to smith
2>go
```

## Usage

- You can substitute the word `from` for `to` in the `grant` syntax.
- `grant dbcc` issues the following warning when you execute it while `set fipsflagger` option is enabled:

```
SQL statement on line number 1 contains Non-ANSI
text. The error is caused due to the use of DBCC.
```

- Revoking a specific permission from "public" or from a group also revokes it from users who were individually granted the permission. An exception are grants and revokes of predicated privileges.
- `grant` fails if you attempt to grant permissions to user-defined roles in a local temporary database in shared-disk cluster.

See also:

- `proc_role`, `show_role` in *Reference Manual: Building Blocks*
- `sp_column_privileges`, `sp_table_privileges`, `sp_addgroup`, `sp_adduser`, `sp_changedbowner`, `sp_changegroup`, `sp_dropgroup`, `sp_dropuser`, `sp_helpgroup`, `sp_helprotect`, `sp_helpuser` in *Reference Manual: Procedures*
- For more information on revoking a privilege from public or a group, see *How SAP ASE Saves Predicated Privileges in sysprotects* in the *Security Administration Guide*

## Standards

ANSI SQL – Compliance level: Entry-level compliant. `grant dbcc` is also a Transact-SQL extension.

`grant dbcc`, and granting permissions to groups and granting `set proxy` are Transact-SQL extensions. Granting `set session authorization` (identical in function to `set proxy`) follows the ANSI standard.

## Permissions

The permission checks for `grant` differ based on your granular permissions settings.

### Setting Description

**Enabled** With granular permissions enabled, in general, `grant` can be executed by a user with one of the following privilege management privileges, depending the privilege or permission being granted. For:

- Server-wide privileges – you must be a user with `manage server permissions` privilege or `manage security permissions` privilege.
- Database-wide privileges – you must be a user with `manage database permissions` privilege.
- Object privileges – you must be the object owner or a user with `manage any object permission` privilege

To execute `grant default`, you must be the database owner or a user with `own database` privilege on the database.

**Disabled** With granular permissions disabled, grantable system privileges are limited to `create database`, `create default`, `create function`, `create procedure`, `create rule`, `create table`, `create view`, `connect`, `set proxy`, and `set tracing`

## Setting Description

Command execution – only system administrators can grant `create database`, `connect`, and `set tracing` permissions, and only from the `master` database. Only system security officers can grant `create trigger` permission.

To execute `grant default`, you must be the database owner or a user with `sa_role`.

For:

- Database consistency checking – only system administrators can run `grant dbcc` commands.
- Database object grant access – permission for database objects defaults to object owners. Object owners can grant permission to other users on their own database objects.
- Functions – only system administrators can grant permissions on built-in functions.
- Encrypted columns – only the systems security officer and the key custodian have implicit permission to create encryption keys.
- Proxy and session authorization – only system security officers can grant `set proxy` or `set session authorization`, and only from the `master` database. Granting permission to execute `set proxy` or `set session authorization` allows the grantee to impersonate another login in the server. `set proxy` and `set session authorization` are identical, except that `set session authorization` follows the ANSI92 standard, and `set proxy` is a Transact-SQL extension.
- System tables – Database owners can grant default permissions on system tables.

## Auditing

You can enable `grant` auditing option to audit this command. Values in `event` and `extrainfo` columns from the `sysaudits` table are:

Audit option	Event	Command or access audited	Information in <code>extrainfo</code> :
<code>grant</code>	40	<code>grant</code>	<ul style="list-style-type: none"><li>• <i>Roles</i> – current active roles</li><li>• <i>Full command text</i> – full text of <code>grant</code> command</li><li>• <i>Previous value</i> – NULL</li><li>• <i>Current value</i> – NULL</li><li>• <i>Other information</i> – NULL</li><li>• <i>Proxy information</i> – original login name, if <code>set proxy</code> is in effect</li></ul>

Full command text is included in `extrainfo`. For example:

```
sa_role sso_role oper_role sybase_ts_role mon_role; grant insert, delete on
titles to mary, sales; ; ; ; ; sa/ase;
```

For more information about auditing, see *Security Administration Guide > Auditing*.

## Related Information

[create role \[page 257\]](#)

[create table \[page 273\]](#)

[revoke \[page 672\]](#)

[set \[page 732\]](#)

[setuser \[page 790\]](#)

### 1.85.1 grant all Object Creation Privileges

Understand how `grant all` works.

- `grant all` without an object name in a database does not grant `create encryption key`. `grant all` without an object name is only supported when granular permissions is disabled.
- When used without object names, `grant all` assigns these permissions: `create database`, `create default`, `create procedure`, `create rule`, `create table`, `create function`, and `create view`. `create database` permission can be granted only by a system administrator and only from within the master database.
- Only the database owner and a system administrator can use the `grant all` syntax without an object name to grant `create` command permissions to users or groups. When the `grant all` command is used by the database owner, an informational message is printed, stating that only a system administrator can grant `create database` permission. All other permissions noted above are granted.
- All object owners can use `grant all` with an object name to grant permissions on their own objects. When used with a table or view name plus user or group names, `grant all` enables `delete`, `delete statistics`, `insert`, `select`, `truncate table`, `update`, and `update statistics` permissions on the table.

### 1.85.2 Using the with grant option Parameter

Rules for using the `with grant option` parameter.

- You cannot grant permissions with `grant option` to "public" or to a group or role.
- In granting permissions, when granular permissions is disabled, a system administrator is treated as the object owner. If a system administrator grants permission on another user's object, the owner's name appears as the grantor in `sysprotects` and in `sp_helpprotect` output. When granular permissions enabled, the grantor's name appears as the grantor in `sysobjects` and in `sp_helpprotect` output.
- You cannot grant system privileges with the `grant option` parameter.
- Information for each `grant` command is kept in the `sysprotects` system table, with the following exceptions:
  - The SAP ASE server displays an informational message if a specific permission is granted to a user more than once by the same grantor. Only the first `grant` record is kept.
  - If two `grants` are exactly same except that one of them is granted with `grant option`, the `grant with grant option` is kept.

- If two `grant` statements from the same grantor grant the same permissions on a particular table to a specific user, but to different columns, the SAP ASE server treats the grants as if they were one statement. For example, the following `grant` statements are equivalent:

```
grant select on titles (price, contract)
to keiko
grant select on titles (advance) to keiko
```

```
grant select on titles (price, contract,
advance)
to keiko
```

### 1.85.3 Users and User Groups

Usage consideration for users and user groups.

- User groups allow you to `grant` or `revoke` permissions to more than one user with a single statement. Each user can be a member of one other group and is always a member of “public.”
- You can add new users with `sp_adduser` and create groups with `sp_addgroup`. To allow users with logins on the SAP ASE server to use the database with limited privileges, you can add a “guest” user with `sp_adduser` and assign limited permissions to “guest.” All users with logins can access the database as “guest.”
- To remove a user, use `sp_dropuser`. To remove a group, use `sp_dropgroup`. To add a new user to a group other than “public,” use `sp_adduser`. To change an established user’s group, use `sp_changegroup`. To display the members of a group, use `sp_helpgroup`.
- When `sp_changegroup` is executed to change group membership, it clears the in-memory protection cache by executing the following, so that the cache can be refreshed with updated information from the `sysprotects` table:

```
grant all to null
```

To modify `sysprotects` directly, contact SAP Technical Support.

### 1.85.4 Using the `grant` Command's `granted by` Option

Usage information for using the `grant` command's `granted by` option.

- `granted by` is not allowed on granting predicated privileges.
- It is not required that the grantor has permission to execute the `grant` command.
- The grantor, and not the command executor, is listed under `sysprotects.grantor`.
- You need not enable `enable granular permissions` to use the `granted by` parameter.
- Users who received their `grant` permission on an object with the `with grant` option cannot issue the `granted by` parameter. All other users may issue the `granted by` parameter.



For example, if Mary grants `select` on her table `books` to John with the `with grant option`, then John gets an error when he tries to issue the second `grant` command. Mary:

```
grant select on mary.books
to john with grant option
```

John:

```
grant select on mary.books
to joe granted by smith
```

## 1.85.5 Privileges for grant

Privileges for `grant` differ based on the level at which you are working.

Server-wide privileges must be granted in the master database. For operations each privilege is authorized to perform, see *Using Granular Permissions* of the *Security Administration Guide*.

### i Note

In the following list, when granular permissions is disabled, only privileges marked with an asterisk ( `*` ) can be granted.

`dbcc` privilege syntax `dbcc dbcc_subcmd on all` is an alias to `dbcc dbcc_subcmd any database`. Both syntaxes are supported.

The grantable server-wide system privileges are:

Category	Privileges
Privilege Management	<ul style="list-style-type: none"><li>• <code>manage security permissions</code></li><li>• <code>manage server permissions</code></li></ul>
Audit Management	<ul style="list-style-type: none"><li>• <code>manage auditing</code></li></ul>
Login and Role Management	<ul style="list-style-type: none"><li>• <code>allow exceptional login</code></li><li>• <code>change password</code></li><li>• <code>manage any login</code></li><li>• <code>manage any login profile</code></li><li>• <code>manage remote login</code></li><li>• <code>manage roles</code></li></ul>
Database Management	<ul style="list-style-type: none"><li>• <code>checkpoint (on &lt;database&gt;)</code></li><li>• <code>checkpoint any database</code></li><li>• <code>create database*</code></li><li>• <code>dump any database</code></li><li>• <code>dump database (on &lt;database&gt;)</code></li><li>• <code>load any database</code></li></ul>

## Category

## Privileges

- load database (ON <database>)
- manage any database
- mount any database
- online any database
- online database (ON <database>)
- own any database
- own database (ON <database>)
- quiesce any database
- unmount any database

## Server Management

- manage any thread pool
- manage cluster
- manage disk
- manage security configuration
- manage server
- manage server configuration
- shutdown

## DBCC Privilege

- dbcc checkalloc any database\*
- dbcc checkcatalog any database\*
- dbcc checkdb any database\*
- dbcc checkindex any database\*
- dbcc checkstorage any database\*
- dbcc checktable any database\*
- dbcc checkverify any database\*
- dbcc fix\_text any database\*
- dbcc indexalloc any database\*
- dbcc reindex any database\*
- dbcc tablealloc any database\*
- dbcc textalloc any database\*
- dbcc tune\*

## Application Management

- manage any execution class
- manage any ESP
- manage data cache
- manage dump configuration
- manage lock promotion threshold
- monitor qp performance
- manage resource limit

## Others

- connect\*

## Category

## Privileges

- kill
- kill any process
- map external file
- monitor server replication
- set proxy
- set tracing\*
- set tracing any process
- set switch
- show switch
- use any database
- use database

Database-wide privilege must be granted in the database for which the privilege is intended to be exercised. For operations each privilege is authorized to perform, see *Using Granular Permissions* in the *Security Administration Guide*.

### i Note

In the following, when granular permissions is disabled, only privileges marked with an asterisk ( \* ) can be granted.

The grantable database-wide system privileges are:

## Category

## Privileges

### Privilege Management

- manage any object permission
- manage database permissions

### User Management

- manage any user

### Set User

- setuser \*

### Replication Management

- manage replication

### Database Management

- manage database

### Query Plan Management

- manage abstract plans

### DBCC Privilege

- dbcc checkalloc \*
- dbcc checkcatalog \*
- dbcc checkdb \*
- dbcc checkindex \*
- dbcc checkstorage \*
- dbcc checktable \*
- dbcc checkverify \*

## Category

## Privileges

- dbcc fix\_text \*
- dbcc indexalloc \*
- dbcc reindex \*
- dbcc textalloc \*
- manage checkstorage
- dbcc tablealloc \*
- report checkstorage

## System Catalog

- select any audit table
- select any system catalog
- truncate any audit table

## General Object

- alter any object owner
- create any object
- drop any object

## Built-in Functions

- select \*

## Encryption Key

- create encryption key \*
- manage any encryption key
- manage column encryption key
- manage master key
- manage service key

## Default

- create default \*
- create any default
- drop any default

## Function

- create function \*
- create any function
- drop any function
- execute any function

## Index

- create any index

## Procedure

- create procedure \*
- create any procedure
- execute any procedure
- drop any procedure

## Rule

- create rule \*
- create any rule
- drop any rule

Category	Privileges
Table	<ul style="list-style-type: none"> <li>• alter any table</li> <li>• create any table</li> <li>• create table*</li> <li>• decrypt any table</li> <li>• delete any table</li> <li>• drop any table</li> <li>• identity_insert any table</li> <li>• identity_update any table</li> <li>• insert any table</li> <li>• manage any statistics</li> <li>• references any table</li> <li>• reorg any table</li> <li>• select any table</li> <li>• transfer any table</li> <li>• truncate any table</li> <li>• update any table</li> </ul>
Trigger	<ul style="list-style-type: none"> <li>• create trigger *</li> <li>• create any trigger</li> <li>• drop any trigger</li> </ul>
View	<ul style="list-style-type: none"> <li>• create view*</li> <li>• create any view</li> <li>• drop any view</li> </ul>

This table lists all grantable privileges and permissions in alphabetic order. Privileges indicated with a "\*" do not require that you enable granular permissions.

Table 5: Alphabetical Listing of Privileges

Privilege Name	Privilege Type	Managed by (when Granular Permissions is Enabled)	Implied by
allow exceptional login	server	manage server permissions	
alter any object owner	database	manage database permissions	
alter any table	database	manage database permissions	
change password	server	manage security permissions	
checkpoint any database	server	manage server permissions	

Privilege Name	Privilege Type	Managed by (when Granular Permissions is Enabled)	Implied by
checkpoint (on database)	server	manage server permissions	checkpoint any database
checkpoint (on sybsecurity)	server	manage security permissions	
connect*	server	manage server permissions	
create any default	database	manage database permissions	create any object
create any function	database	manage database permissions	create any object
create any index	database	manage database permissions	create any object
create any object	database	manage database permissions	
create any procedure	database	manage database permissions	create any object
create any rule	database	manage database permissions	create any object
create any table	database	manage database permissions	create any object
create any trigger	database	manage database permissions	create any object
create any view	database	manage database permissions	create any view
create database*	server	manage database permissions	
create default*	database	manage database permissions	create any default
create encryption key*	database	manage security permissions	manage column encryption key
create function*	database	manage database permissions	create any function
create index*	database	manage database permissions	create any index
create procedure*	database	manage database permissions	create procedure
create rule*	database	manage database permissions	create any rule

Privilege Name	Privilege Type	Managed by (when Granular Permissions is Enabled)	Implied by
create table*	database	manage database permissions	create any table
create trigger*	database	manage database permissions	create any trigger
create view*	database	manage database permissions	create any view
dbcc checkalloc*	database	manage database permissions	dbcc checkalloc any database
dbcc checkalloc any database*	server	manage server permissions	
dbcc checkcatalog*	database	manage database permissions	dbcc checkcatalog any database
dbcc checkcatalog any database*	server	manage server permissions	
dbcc checkdb*	database	manage database permissions	dbcc checkdb any database
dbcc checkdb any database*	server	manage server permissions	
dbcc checkindex*	database	manage database permissions	dbcc checkindex any database
dbcc checkindex any database *	server	manage server permissions	
dbcc checkstorage*	database	manage database permissions	dbcc checkstorage any database
dbcc checkstorage any database *	server	manage server permissions	
dbcc checktable*	database	manage database permissions	dbcc checktable any database
dbcc checktable any database*	server	manage server permissions	
dbcc checkverify*	database	manage database permissions	dbcc checkverify any database
dbcc checkverify any database*	server	manage server permissions	
dbcc fix_text*	database	manage database permissions	dbcc fix_text any database
dbcc fix_text any database*	server	manage server permissions	

Privilege Name	Privilege Type	Managed by (when Granular Permissions is Enabled)	Implied by
dbcc indexalloc*	database	manage database permissions	dbcc indexalloc any database
dbcc indexalloc any database*	server	manage server permissions	
dbcc reindex*	database	manage database permissions	dbcc reindex any database
dbcc reindex any database*	server	manage server permissions	
dbcc tablealloc*	database	manage database permissions	dbcc tablealloc any database
dbcc tablealloc any database*	server	manage server permissions	
dbcc textalloc*	database	manage database permissions	dbcc textalloc any database
dbcc textalloc any database*	server	manage server permissions	
dbcc tune*	server	manage server permissions	
decrypt*	object (column)	manage any object permission/object owner	decrypt any table
decrypt any table	database	manage database permissions	
delete*	object	manage any object permission/object owner	delete any table
delete any table	database	manage database permissions	
delete statistics*	object	manage any object permission/object owner	manage any statistics
drop any default	database	manage database permissions	drop any object
drop any function	database	manage database permissions	drop any object
drop any object	database	manage database permissions	
drop any procedure	database	manage database permissions	drop any object



Privilege Name	Privilege Type	Managed by (when Granular Permissions is Enabled)	Implied by
drop any rule	database	manage database permissions	drop any object
drop any table	database	manage database permissions	drop any object
drop any trigger	database	manage database permissions	drop any object
drop any view	database	manage database permissions	drop any object
dump any database	server	manage server permissions	
dump database (on database)	server	manage server permissions	dump any database
dump database (on sybsecurity)	server	manage security permissions	
execute*	object	manage any object permission/object owner	execute any function (for udf) execute any procedure (for system procedures)
execute any function	database	manage database permissions	
execute any procedure	database	manage database procedures	
identity_insert	object	manage any object permission/object owner	
identity_insert any table	database	manage database permissions	
identity_update	object	manage any object permission/object owner	
identity_update any table	database	manage database permissions	
insert*	object	manage any object permission/object owner	insert any table
insert any table	database	manage database permissions	
kill	server	manage server permissions	kill any process

Privilege Name	Privilege Type	Managed by (when Granular Permissions is Enabled)	Implied by
kill any process	server	manage server permissions	
load any database	server	manage server permissions	
load database (on database)	server	manage server permissions	load any database
load database (on sybsecurity)	server	manage security permissions	
manage abstract plans	database	manage database permissions	
manage any database	server	manage server permissions	
manage any encryption key	database	manage security permissions	
manage any ESP	server	manage server permissions	
manage any execution class	server	manage server permissions	
manage any login	server	manage security permissions	
manage any login profile	server	manage security permissions	
manage any remote login	server	manage security permissions	
manage any statistics	database	manage database permissions	
manage any thread pool	server	manage server permissions	
manage any user	database	manage database permissions	
manage auditing	server	manage security permissions	
manage checkstorage	database	manage database permissions	
manage cluster	server	manage server permissions	
manage column encryption key	database	manage security permissions	manage any encryption key

Privilege Name	Privilege Type	Managed by (when Granular Permissions is Enabled)	Implied by
manage data cache	server	manage server permissions	
manage database	database	manage database permissions	manage any database
manage database permissions	database	manage security permissions	
manage disk	server	manage server permissions	
manage dump configuration	server	manage server permissions	
manage lock promotion threshold	server	manage server permissions	
manage master key	database	manage security permissions	manage any encryption key
manage replication	server	manage server permissions	
manage resource limit	server	manage server permissions	
manage roles	server	manage security permissions	
manage security configuration	server	manage security permissions	
manage security permissions	server	manage security permissions	
manage server	server	manage server permissions	
manage server configuration	server	manage server permissions	
manage server permissions	server	manage server permissions	
manage service key	database	manage security permissions	manage any encryption key
map external file	server	manage server permissions	
monitor qp performance	server	manage server permissions	
monitor server replication	server	manage server permissions	

Privilege Name	Privilege Type	Managed by (when Granular Permissions is Enabled)	Implied by
mount any database	server	manage server permissions	
own any database	server	manage server permissions	
online any database	server	manage server permissions	
online database (on database)	server	manage server permissions	online any database
online database (on sybsecurity)	server	manage security permissions	
own database (on database)	server	manage server permissions	
own database (on sybsecurity)	server	manage security permissions	
quiesce any database	server	manage server permissions	
references*	object (column)	manage any object permission/object owner	references any table
references any table	database	manage database permissions	
report checkstorage	database	manage database permission	
reorg any table	database	manage database permissions	
select*	object (column)	manage any object permission/object owner	<ul style="list-style-type: none"> <li>• select any table for user tables or views</li> <li>• select any audit table for audit tables</li> <li>• select any system catalog for system tables</li> </ul>
select any audit table	database	manage database permissions	
select any system catalog	database	manage database permissions	
select any table	database	manage database permissions	
set proxy*	server	manage security permissions	

Privilege Name	Privilege Type	Managed by (when Granular Permissions is Enabled)	Implied by
set switch	server	manage server permissions	
set tracing*	server	manage server permissions	set tracing for any process
set tracing any process	server	manage server permissions	
setuser*	database	manage database permissions	
show switch	server	manage server permissions	
shutdown	server	manage server permissions	
transfer any table	database	manage database permissions	
transfer table	object	manage any object permission/object owner	transfer any table
truncate any audit table	database	manage database permissions	
truncate any table	database	manage database permissions	
truncate table*	object	manage any object permission/object owner	truncate any table
unmount any database	server	manage server permissions	
update*	object(column)	manage any object permission/object owner	update any table
update any security catalog	server	manage security permissions	
update any table	database	manage database permissions	
update statistics	object	manage any object permission/object owner	manage any statistics
use any database	server	manage server permissions	
use database (on database)	server	manage server permissions	use any database

Privilege Name	Privilege Type	Managed by (when Granular Permissions is Enabled)	Implied by
use database (on sybsecurity)	server	manage security permissions	

- Possessing one privilege may imply possessing another, more granular privilege. For example, a user with `select any table` privilege implies that the user has `select` permission on all user tables.
- When granting the following database management privileges, the `on <database>` clause must be specified for each privilege: `checkpoint`, `dump database`, `load database`, `online database`, `own database`. For example, to grant `dump database` privilege on `db1` to `smith`, you can use:

```
grant dump database on db1 to smith
```

You can grant different database management privileges on different databases in the same grant command. For example, to grant `own database` on `db1` and `load database` on `db2` to `smith`, you can use:

```
grant own database on db1, load database on db2 to smith
```

- You can grant permissions only on objects in your current database.
- `grant` and `revoke` commands are order-sensitive. The command that takes effect when there is a conflict is the one issued most recently.
- A user can be granted permission on a view or stored procedure even if he or she has no permissions on objects referenced by the procedure or view. See *Managing User Permissions* in the *Security Administration Guide*.
- The SAP ASE server grants all users permission to declare cursors, regardless of the permissions defined for the base tables or views referenced in the `declare cursor` statement. Cursors are not defined as SAP ASE objects (such as tables), so no permissions can be applied against a cursor. When a user opens a cursor, the SAP ASE server determines whether the user has `select` permissions on the objects that define that cursor's result set. It checks permissions each time a cursor is opened. If the user has permission to access the objects defined by the cursor, the SAP ASE server opens the cursor and allows the user to `fetch` row data through the cursor. The SAP ASE server does not apply permission checking for each `fetch`. However, if the user performs a `delete` or an `update` through that cursor, the regular permission checking applies for deleting and updating the data of objects referenced in the cursor result set.
- A `grant` statement adds one row to the `sysprotects` system table for each user, group, or role that receives the permission. If you subsequently `revoke` the permission from the user or group, the SAP ASE server removes the row from `sysprotects`. If you revoke the permission from selected group members only, but not from the entire group to which it was granted, the SAP ASE server retains the original row and adds a new row for the revoked permission.
- A user, group, or role can be granted the same privilege or permission by different grantors. In this situation, there are multiple rows in `sysprotects` that represents multiple grants on the same privilege or permissions. If one or more than one grants are later revoked, the user, group, or role may still have the privilege or permission if there is one grant remain unrevoked.
- If a user inherits a particular permission by virtue of being a member of a group, and the same permission is explicitly granted to the user, no row is added to `sysprotects`. For example, if "public" has been granted `select` permission on the `phone` column in the `authors` table, then John, a member of "public," is granted `select` permission on all columns of `authors`. The row added to `sysprotects` as a result of

the `grant` to John contains references to all columns in the `authors` table except for the `phone` column, on which he already had permission.

- By default, permission to issue the `create trigger` command is granted to users. When you revoke permission for a user to create triggers, a revoke row is added in the `sysprotects` table for that user. To grant permission to that user to issue `create trigger`, you must issue two `grant` commands. The first command removes the revoke row from `sysprotects`; the second inserts a grant row. If you revoke permission to create triggers, the user cannot create triggers even on tables that the user owns. Revoking permission to create triggers from a user affects only the database where the revoke command was issued.
- Use these system procedures to display information about permissions:
  - `sp_helprotect` reports permissions information for database objects, users, groups, and roles.
  - `sp_column_privileges` reports permissions information for one or more columns in a table or view.
  - `sp_table_privileges` reports permissions information for all columns in a table or view.
  - `sp_activeroles` displays all active roles—and all roles contained by those roles—for the current login session of the SAP ASE server.
  - `sp_displayroles` displays all roles granted to another role or user, or displays the entire hierarchy tree of roles in table format.
- You can view permissions using `sp_helprotect`:

```
1> use pubs2
2> go
1> sp_helprotect
2> go
```

grantor	grantee	type	action	object	column	grantable
dbo	public	Grant	Select	sysalternates	All	FALSE
...						
dbo	Walter	Grant	DBCC	DBCC	dbcc checkdb	FALSE

(1 row affected)  
(return status = 0)

- You cannot use the `grant` with `grant option` with `grant dbcc`.

## 1.85.6 Grant Access to Roles

Permissions that are granted to roles override permissions that are granted to users or groups.

For example, say John has been granted the system security officer role, and `sso_role` has been granted permission on the `sales` table. If John's individual permission on `sales` is revoked, he can still access `sales` because his role permissions override his individual permissions.

However, `grant execute` permission does not prevent users who do not have a specified role from being individually granted permission to execute a stored procedure. To ensure, for example, that only system security officers can ever be granted permission to execute a stored procedure, use the `proc_role` system function within the stored procedure itself. It checks to see whether the invoking user has the correct role to execute the procedure. See `proc_role`.

## 1.85.7 Granting Default Permissions on System Tables

System tables that you can grant and revoke the default permissions for when you issue the command from any database.

- `sysalternates`
- `sysattributes`
- `syscolumns`
- `syscomments`
- `sysconstraints`
- `sysdepends`
- `sysindexes`
- `sysjars`
- `syskeys`
- `syslogs`
- `sysobjects`
- `syspartitions`
- `sysprocedures`
- `sysprotects`
- `sysqueryplans`
- `sysreferences`
- `sysroles`
- `syssegments`
- `sysstatistics`
- `systabstats`
- `systhresholds`
- `systypes`
- `sysusermessages`
- `sysusers`
- `sysxtypes`

The command also makes the following changes:

- Revokes `syscolumns (enckryid)` and `syscolumns (enckrydb)` permissions from public.
- Revokes `syscolumns (enckrydb)` and `syscolumns (enckryid)` permissions from public.
- Revokes `sysobjects (audflags)` permissions from public
- Grants permissions for `sysobjects` to `sso_role`
- Revokes `select` on all columns of `sysencryptkeys` from public
- Grants `select` on all `sysencryptkeys` columns to `sso_role`
- Grants permissions for `syscolumns` to `sso_role`

The system tables for which you can grant and revoke the default permissions when you issue the command from the `master` database are:

- `syscharsets`
- `sysconfigures`



- syscurconfigs
- sysdatabases
- sysdevices
- syslanguages
- syslogins
- syslocks
- sysmessages
- sysprocesses
- sysremotelogins
- sysresourcelimits
- syssservers
- syssessions
- systimeranges
- systransactions
- sysusages

The command also:

- Revokes select on sysdatabases (audflags) from public
- Revokes select on sysdatabases (deftabaud) from public
- Revokes select on sysdatabases (defvwaud) from public
- Revokes select on sysdatabases (defpraud) from public
- Revokes select on sysdatabases (audflags2) from public
- Grants select on sysdatabases to sso\_role
- Revokes select on syslogins (password) from public
- Revokes select on syslogins (audflags) from public
- Revokes select on syslogins (lpid) from public
- Grants select on syslogins to sso\_role
- Revokes select on syslisteners (net\_type) from public
- Revokes select on syslisteners (address\_info) from public
- Grants select on syslisteners to sso\_role
- Revokes select on sysrvroles (srid) from public
- Revokes select on sysrvroles (name) from public
- Revokes select on sysrvroles (password) from public
- Revokes select on sysrvroles (pwwdate) from public
- Revokes select on sysrvroles (status) from public
- Revokes select on sysrvroles (logincount) from public
- Grants select on sysrvroles to public
- Revokes select on sysloginroles (suid) from public
- Revokes select on sysloginroles (srid) from public
- Revokes select on sysloginroles (status) from public
- Grants select on sysloginroles to sso\_role
- Revokes select on sysinstances (hostname) from public
- Grants select on sysinstances to sso\_role

## 1.85.8 Granting Permissions for `update statistics`, `delete statistics`, and `truncate table`

The SAP ASE server allows you to grant permissions to users, roles, and groups for the `update statistics`, `delete statistics`, and `truncate table` commands. Table owners can also provide permissions through an implicit grant by adding `update statistics`, `delete statistics`, and `truncate table` to a stored procedure and then granting execute permissions on that procedure to a user or role.

You cannot grant permissions for `update statistics` at the column level. You must have the `sso_role` to run `update statistics` or `delete statistics` on `sysroles`, `sysserverroles`, and `sysloginroles` security tables.

By default, users with the `sa_role` have permission to run `update statistics` and `delete statistics` on system tables other than `sysroles`, `sysserverroles`, and `sysloginroles`, and can transfer this privilege to other users.

You can also issue `grant all` to grant permissions on `update statistics`, `delete statistics`, and `truncate table`.

### Note

Once you grant permission to execute `update statistics` to a user, he or she also has permission to execute variations of this command, such as `update all statistics`, `update partition statistics`, `update index statistics`, `update table statistics`, and so on. For example, the following grants Billy permission to run all variations of `update statistics` on the `authors` table:

```
grant update statistics on authors to billy
```

If you revoke a user's permission to execute `update statistics`, you also revoke his or her ability to execute the variations of this command.

You cannot grant variants of `update statistics` (for example, `update index statistics`) separately. That is, you *cannot* issue:

```
grant update all statistics to harry
```

You can, however, write stored procedures that control who executes these commands. For example, the following grants Billy execute permission for `update index statistics` on the `authors` table:

```
create proc sp_ups as
update index statistics on authors
go
revoke update statistics on authors from billy
go
grant execute on sp_ups to billy
```

You cannot grant and revoke `delete statistics` permissions at the column level.

Although the SAP ASE server audits `truncate table` as a global, miscellaneous audit, it does not audit `update statistics`. To retain clear audit trails for both `truncate table` and `update statistics`, you should include both commands in a stored procedure to which you grant users execute permission, as described above.

## 1.85.9 Granting Proxies and Session Authorizations

Granting permission to execute `set proxy` or `set session authorization` allows the grantee to impersonate another login in the SAP ASE server. `set proxy` and `set session authorization` are identical, except `set session authorization` follows the SQL standard, and `set proxy` is a Transact-SQL extension.

- To grant `set proxy` or `set session authorization` permission, you must be in the `master` database.
- The name you specify in the `grant set proxy` command must be a valid user in the database; that is, the name must be in the `sysusers` table in the database.
- `grant all` does not include the `set proxy` or `set session authorization` permissions.
- You can restrict roles incrementally using `grant set proxy`. For example, you can first restrict the `sa_role`, then the `sso_role`:

```
grant set proxy to joe
restrict role sa_role
grant set proxy to joe
restrict role sso_role
```

- You cannot unrestrict individual roles. You must revoke `set proxy` to revoke permissions from all roles.

## 1.85.10 Granting a Privilege to a Role

Permissions that are granted to roles override permissions that are granted to users or groups.

For example, say John has been granted the system security officer role, and `sso_role` has been granted permission on the `sales` table. If John's individual permission on `sales` is revoked, he can still access `sales` because his role permissions override his individual permissions.

However, `grant execute` permission does not prevent users who do not have a specified role from being individually granted permission to execute a stored procedure. To ensure, for example, that only system security officers can ever be granted permission to execute a stored procedure, use the `proc_role` system function within the stored procedure itself. It checks to see whether the invoking user has the correct role to execute the procedure. See `proc_role`.

## 1.86 grant role

Grants a role to the specified logins, users, or system- or user-defined roles.

### Syntax

```
grant role <role_name>
    [where <pred_expression>]
```

```
to {<username> | <rolename | ><login_profile_name >}
```

## Parameters

**<role\_name >**

is the name of a system- or user-defined role that the system security officer is granting to a user or a role.

**where <pred\_expression>**

also referred to as a role-activation predicate, this is a SQL condition that must be satisfied when the named role is activated. <pred\_expression> may be used only when granting a role to <username> or <login\_profile\_name>. If <pred\_expression> evaluates to FALSE when the role is activated, the `set role` command fails and the SAP ASE server returns an error message. If the role is specified for automatic activation or is a default role, the SAP ASE server silently fails the activation but does not fail the login process.

**to <username> | <rolename | ><login\_profile\_name>**

identifies the name of the login, role or login profile to which you are granting the role. When the grantee is a login profile, all users with this login profile are granted the role.

## Examples

### Example 1

Grants the role "doctor" to Mary:

```
grant role doctor_role to mary
```

### Example 2

By granting `intern_role` to `doctor_role`, a doctor inherits all the privileges of an intern.

```
grant role intern_role to doctor_role
```

### Example 3

User Smith, with `manage roles` privileges, grants the `nurse_role` to user John, with user `roleAdmin` as the grantor.

```
grant role nurse_role to john
granted by roleAdmin
```

### Example 4

Grants role `ldap_user_role` to login profile `lp_10`:

```
grant role ldap_user_role where
  @@authmech = 'ldap'
to login_profile lp_10
```

Using the above example, when the session of a user assigned login profile `lp_10` enables `ldap_user_role`, the SAP ASE server checks that the session connected using LDAP. If there was an LDAP connection, the user assumes `ldap_user_role`; if not, `ldap_user_role` is not enabled. Configure the predicate evaluation to occur automatically during login by altering login profile `lp_10` and specifying `ldap_user_role` on the `auto_activated_roles` attribute. Otherwise, the evaluation of the role activation predicate occurs when the user assigned `lp_10` executes the `set role` statement.

## Usage

The SAP ASE server automatically activates roles granted to logins or login profiles (after evaluating any predicate) when the user logs in if `create login`, `alter login`, `create login profile`, or `alter login profile` specify the role for automatic activation. Otherwise, the SAP ASE server activates the role when `set role` is executed. Adaptive automatically activates a role granted to another role when the dependent role is activated.

You can use the `grant` command to grant permissions to all users who have been granted a specified role. The role can be either a system role, like `sso_role` or `sa_role`, or a user-defined role. The system security officers must create the user-defined roles using a `create role` command.

## Permissions

The permission checks for `grant role` differ based on your granular permissions settings.

Setting	Description
---------	-------------

<b>Enabled</b>	With granular permissions enabled, you must be a user with <code>manage roles</code> privilege.
----------------	---

<b>Disabled</b>	With granular permissions disabled, you must be a user with <code>sso_role</code> . To grant <code>sa_role</code> , you must be a user with <code>sa_role</code> .
-----------------	--

## Auditing

You can enable the following auditing options to audit this command. Values in `event` and `extrainfo` columns from the `sysaudits` table are:

Audit option	Event	Command or access audited	Information in <code>extrainfo</code> :
<code>grant,role,security</code>	85	<code>grant role</code>	<ul style="list-style-type: none"><li>• <i>Roles</i> – current active roles</li><li>• <i>Full command text</i> – full text of <code>grant role</code> command</li><li>• <i>Previous value</i> – NULL</li><li>• <i>Current value</i> – NULL</li><li>• <i>Other information</i> – parameter names and values</li><li>• <i>Proxy information</i> – original login name, if set <code>proxy</code> is in effect</li></ul>

Full command text and parameters are included in `extrainfo`. For example:

```
sso_role; grant role @para1_role to @para2_grantee1; ; ; @para1_role = role1,
@para2_grantee1 = user4; ; user1/ase;
```

For more information about auditing, see *Security Administration Guide > Auditing*.

## 1.87 group by and having Clauses

Used in `select` statements to divide a table into groups and to return only groups that match conditions in the `having` clause. `group by` is typically used with aggregates to specify how to group the unaggregated columns of a `select` query. `having` clauses are applied to these groups.

### Syntax

```
<Start of> select <statement>
```

```
[group by [all] <aggregate_free_expression>
[, <aggregate_free_expression>]...]
```

```
[having <search_conditions>]
```

```
<End of> select <statement>
```

## Parameters

### group by

specifies the groups into which the table is divided, and if aggregate functions are included in the select list, finds a summary value for each group. These summary values appear as columns in the results, one for each group. You can refer to these summary columns in the `having` clause.

You can use the `avg`, `count`, `count_big`, `max`, `min`, and `sum` aggregate functions in the select list before `group by` (the expression is usually a column name). See *Reference Manual: Building Blocks*.

A table can be grouped by any combination of columns—that is, groups can be nested within each other, as in Example 2.

### all

is a Transact-SQL extension that includes all groups in the results, even those excluded by a `where` clause. For example:

```
select type, avg (price)
from titles
where advance > 7000
group by all type
```

```
type
-----
UNDECIDED          NULL
business           2.99
mod_cook           2.99
popular_comp       20.00
psychology         NULL
trad_cook          14.99
(6 rows affected)
```

“NULL” in the aggregate column indicates groups that would be excluded by the `where` clause. A `having` clause negates the meaning of `all`.

### <aggregate\_free\_expression>

is an expression that includes no aggregates. A Transact-SQL extension allows grouping by an aggregate-free expression as well as by a column name.

You cannot group by column heading or alias. This example is correct:

```
select Price=avg (price), Pay=avg (advance),
Total=price * $1.15
from titles
group by price * $1.15
```

### having

sets conditions for the `group by` clause, similar to the way in which `where` sets conditions for the `select` clause.

having search conditions can include aggregate expressions; otherwise, having search conditions are identical to where search conditions. This is an example of a having clause with aggregates:

```
select pub_id, total = sum (total_sales)
from titles
where total_sales is not null
group by pub_id
having count (*)>5
```

When the SAP ASE server optimizes queries, it evaluates the search conditions in where and having clauses, and determines which conditions are search arguments (SARGs) that can be used to choose the best indexes and query plan. All of the search conditions are used to qualify the rows. For more information on search arguments, see the *Performance and Tuning Guide: Optimizer and Abstract Plans*.

## Examples

### Example 1

Calculates the average advance and the sum of the sales for each type of book:

```
select type, avg (advance), sum (total_sales)
from titles
group by type
```

### Example 2

Groups the results by type, then by pub\_id within each type:

```
select type, pub_id, avg (advance), sum (total_sales)
from titles
group by type, pub_id
```

### Example 3

Calculates results for all groups, but displays only groups whose type begins with "p":

```
select type, avg (price)
from titles
group by type
having type like 'p%'
```

### Example 4

Calculates results for all groups, but displays results for groups matching the multiple conditions in the having clause:

```
select pub_id, sum (advance), avg (price)
from titles
group by pub_id
having sum (advance) > $15000
and avg (price) < $10
and pub_id > "0700"
```



### Example 5

Calculates the total sales for each group (publisher) after joining the `titles` and `publishers` tables:

```
select p.pub_id, sum (t.total_sales)
from publishers p, titles t
where p.pub_id = t.pub_id
group by p.pub_id
```

### Example 6

Displays the titles that have an advance of more than \$1000 and a price that is more than the average price of all titles:

```
select title_id, advance, price
from titles
where advance > 1000
having price > avg (price)
```

## Usage

- You can use a column name or any expression (except a column heading or alias) after `group by`. You can use `group by` to calculate results or display a column or an expression that does not appear in the `select` list).
- The maximum number of `group by` columns (or expressions) is not explicitly limited. The only limit of `group by` results is that the width of the `group by` columns plus the aggregate results be no greater than 64K.
- Null values in the `group by` column are put into a single group.
- You cannot name `text`, `unitext`, or `image` columns in `group by` and `having` clauses.
- You cannot use a `group by` clause in the `select` statement of an updatable cursor.
- Aggregate functions can be used only in the `select` list or in a `having` clause. They cannot be used in a `where` or `group by` clause.

Aggregate functions are of two types. Aggregates applied to *all the qualifying rows in a table* (producing a single value for the whole table per function) are called *scalar aggregates*. An aggregate function in the `select` list with no `group by` clause applies to the whole table; it is one example of a scalar aggregate.

Aggregates applied to *a group of rows in a specified column or expression* (producing a value for each group per function) are called *vector aggregates*. For either aggregate type, the results of the aggregate operations are shown as new columns that the `having` clause can refer to.

You can nest a vector aggregate inside a scalar aggregate. See *Reference Manual: Building Blocks* for more information.

See also *Transact-SQL Functions* in *Reference Manual: Building Blocks*.

## Standards

ANSI SQL – Compliance level: Entry-level compliant.

The use of columns within the `select` list that are not in the `group by` list and have no aggregate functions is a Transact-SQL extension.

The use of the `all` keyword is a Transact-SQL extension.

## Auditing

This command is not audited.

## Related Information

[Transact-SQL Extensions to group by and having \[page 563\]](#)

[compute Clause \[page 125\]](#)

[declare \[page 382\]](#)

[select \[page 696\]](#)

[where Clause \[page 855\]](#)

### 1.87.1 How group by and having Queries with Aggregates Work

The `where` clause excludes rows that do not meet its search conditions; its function remains the same for grouped or nongrouped queries.

The `group by` clause collects the remaining rows into one group for each unique value in the `group by` expression. Omitting `group by` creates a single group for the whole table.

Aggregate functions specified in the `select` list calculate summary values for each group. For scalar aggregates, there is only one value for the table. Vector aggregates calculate values for the distinct groups.

The `having` clause excludes groups from the results that do not meet its search conditions. Even though the `having` clause tests only rows, the presence or absence of a `group by` clause may make it appear to be operating on groups:

- When the query includes `group by`, `having` excludes result group rows. This is why `having` seems to operate on groups.
- When the query has no `group by`, `having` excludes result rows from the (single-group) table. This is why `having` seems to operate on rows (the results are similar to `where` clause results).

### 1.87.2 Standard group by and having Queries

All `group by` and `having` queries in the Examples section adhere to the SQL standard, which dictates that queries using `group by`, `having`, and vector aggregate functions produce one row and one summary value per group.

These guidelines apply:

- Columns in a select list must also be in the `group by` expression, or they must be arguments of aggregate functions.
- A `group by` expression can contain only column names that are in the select list. However, columns used only as arguments of aggregate functions in the select list do not qualify.
- Columns in a `having` expression must be single-valued—arguments of aggregates, for instance—and they must be in the select list or `group by` clause. Queries with a select list aggregate and a `having` clause *must* have a `group by` clause. If you omit the `group by` for a query without a select list aggregate, all the rows not excluded by the `where` clause are considered to be a single group.

In nongrouped queries, the principle that “`where` excludes rows” seems straightforward. In grouped queries, the principle expands to “`where` excludes rows before `group by`, and `having` excludes rows from the display of results.”

The SQL standard allows queries that join two or more tables to use `group by` and `having`, if they also adhere to the above guidelines. When specifying joins or other complex queries, use the standard syntax of `group by` and `having` until you fully comprehend the effect of the Transact-SQL extensions to both clauses.

To help you avoid problems with extensions, the SAP ASE server provides the `fipsflagger` option to the `set` command that issues a nonfatal warning for each occurrence of a Transact-SQL extension in a query. See `set` for more information.

### 1.87.3 Transact-SQL Extensions to `group by` and `having`

Transact-SQL extensions to standard SQL let you display data more flexibly, by allowing references to columns and expressions that are not used for creating groups or summary calculations:

- A select list that includes aggregates can include *extended* columns that are not arguments of aggregate functions and are not included in the `group by` clause. An extended column affects the display of final results, since additional rows are displayed.
- The `group by` clause can include columns or expressions that are not in the select list.
- The `group by all` clause displays all groups, even those excluded from calculations by a `where` clause. See the example for the keyword `all` in the “Parameters” section.
- The `having` clause can include columns or expressions that are not in the select list and not in the `group by` clause.

When the Transact-SQL extensions add rows and columns to a display, or if `group by` is omitted, query results may be hard to interpret. The examples that follow can help you understand how Transact-SQL extensions can affect query results.

The following examples illustrate the differences between queries that use standard `group by` and `having` clauses and queries that use the Transact-SQL extensions:

1. An example of a standard grouping query:

```
select type, avg (price)
from titles
group by type
```

```
type
-----
UNDECIDED          NULL
```

```

business          13.73
mod_cook          11.49
popular_comp     21.48
psychology       13.50
trad_cook        15.96
(6 rows affected)

```

- The Transact-SQL extended column, `price` (in the select list, but not an aggregate and not in the `group by` clause), causes all qualified rows to display in each qualified group, even though a standard `group by` clause produces a single row per group. The `group by` still affects the vector aggregate, which computes the average price per group displayed on each row of each group (they are the same values that were computed for example a):

```

select type, price, avg (price)
from titles
group by type

```

```

type          price          -----
business      19.99          13.73
business      11.95          13.73
business      2.99           13.73
business      19.99          13.73
mod_cook       19.99          11.49
mod_cook       2.99           11.49
UNDECIDED     NULL           NULL
popular_comp  22.95          21.48
popular_comp  20.00          21.48
popular_comp  NULL           21.48
psychology    21.59          13.50
psychology    10.95          13.50
psychology    7.00           13.50
psychology    19.99          13.50
psychology    7.99           13.50
trad_cook     20.95          15.96
trad_cook     11.95          15.96
trad_cook     14.99          15.96
(18 rows affected)

```

- The way Transact-SQL extended columns are handled can make it look as if a query is ignoring a `where` clause. This query computes the average prices using only those rows that satisfy the `where` clause, but it also displays rows that do not match the `where` clause. The SAP ASE server first builds a worktable containing only the type and aggregate values using the `where` clause. This worktable is joined back to the `titles` table in the grouping column `type` to include the `price` column in the results, but the `where` clause is *not* used in the join. The only row in `titles` that is not in the results is the lone row with `type = "UNDECIDED"` and a NULL price, that is, a row for which there were no results in the worktable. If you also want to eliminate the rows from the displayed results that have prices of less than \$10.00, you must add a `having` clause that repeats the `where` clause, as shown in Example 4:

```

select type, price, avg (price)
from titles
where price > 10.00
group by type

```

```

type          price          -----
business      19.99          17.31
business      11.95          17.31
business      2.99           17.31

```

```

business      19.99      17.31
mod_cook      19.99      19.99
mod_cook      2.99       19.99
popular_comp  22.95      21.48
popular_comp  20.00      21.48
popular_comp  NULL       21.48
psychology    21.59      17.51
psychology    10.95      17.51
psychology    7.00       17.51
psychology    19.99      17.51
psychology    7.99       17.51
trad_cook     20.95      15.96
trad_cook     11.95      15.96
trad_cook     14.99      15.96
(17 rows affected)

```

4. If you are specifying additional conditions, such as aggregates, in the `having` clause, also include all conditions specified in the `where` clause. The SAP ASE server appears to ignore any `where` clause conditions that are missing from the `having` clause:

```

select type, price, avg (price)
from titles
where price > 10.00
group by type
having price > 10.00

```

```

type      price
-----
business  19.99      17.31
business  11.95      17.31
business  19.99      17.31
mod_cook   19.99      19.99
popular_comp  22.95      21.48
popular_comp  20.00      21.48
psychology  21.59      17.51
psychology  10.95      17.51
psychology  19.99      17.51
trad_cook  20.95      15.96
trad_cook  11.95      15.96
trad_cook  14.99      15.96
(12 rows affected)

```

5. This is an example of a standard grouping query using a join between two tables. It groups by `pub_id`, then by `type` within each publisher ID, to calculate the vector aggregate for each row:

```

select p.pub_id, t.type, sum (t.total_sales)
from publishers p, titles t
where p.pub_id = t.pub_id
group by p.pub_id, t.type

```

```

pub_id  type
-----
0736    business  18722
0736    psychology 9564
0877    UNDECIDED  NULL
0877    mod_cook   24278
0877    psychology 375
0877    trad_cook  19566
1389    business  12066
1389    popular_comp 12875
(8 rows affected)

```

It may seem that it is only necessary to specify `group by` for the `pub_id` and `type` columns to produce the results, and add extended columns as follows:

```
select p.pub_id, p.pub_name, t.type,
       sum (t.total_sales)
from publishers p, titles t
where p.pub_id = t.pub_id
group by p.pub_id, t.type
```

However, the results for the above query are much different from the results for the first query in this example. After joining the two tables to determine the vector aggregate in a worktable, the SAP ASE server joins the worktable to the table (`publishers`) of the extended column for the final results. Each extended column from a different table invokes an additional join.

As you can see, using the extended column extension in queries that join tables can easily produce results that are difficult to comprehend. In most cases, use the standard `group by` to join tables in your queries.

6. This example uses the Transact-SQL extension to `group by` to include columns that are not in the select list. Both the `pub_id` and `type` columns are used to group the results for the vector aggregate. However, the final results do not include the `type` within each publisher. In this case, you may only want to know how many distinct title types are sold for each publisher:

```
select p.pub_id, sum (t.total_sales)
from publishers p, titles t
where p.pub_id = t.pub_id
group by p.pub_id, t.type
```

```
pub_id
-----
0736      18722
0736      9564
0877      NULL
0877      24278
0877       375
0877      19566
1389      12066
1389      12875
(8 rows affected)
```

7. This example combines two Transact-SQL extension effects. First, it omits the `group by` clause while including an aggregate in the select list. Second, it includes an extended column. By omitting the `group by` clause:
  - The table becomes a single group. The scalar aggregate counts three qualified rows.
  - `pub_id` becomes a Transact-SQL extended column because it does not appear in a `group by` clause. No `having` clause is present, so all rows in the group are qualified to be displayed.

```
select pub_id, count (pub_id)
from publishers
```

```
pub_id
-----
0736          3
0877          3
1389          3
(3 rows affected)
```

8. The `where` clause excludes publishers with a `pub_id` of 1000 or more from the single group, so the scalar aggregate counts two qualified rows. The extended column `pub_id` displays all qualified rows from the `publishers` table:

```
select pub_id, count (pub_id)
from publishers
where pub_id < "1000"
```

```
pub_id
-----
0736          2
0877          2
1389          2
(3 rows affected)
```

9. This example illustrates an effect of a `having` clause used without a `group by` clause.
- The table is considered a single group. No `where` clause excludes rows, so all the rows in the group (table) are qualified to be counted.
  - The rows in this single-group table are tested by the `having` clause.
  - These combined effects display the two qualified rows.

```
select pub_id, count (pub_id)
from publishers
having pub_id < "1000"
```

```
pub_id
-----
0736          3
0877          3
(2 rows affected)
```

10. This example uses the extension to `having` that allows columns or expressions not in the `select` list and not in the `group by` clause. It determines the average price for each title type, but it excludes those types that do not have more than \$10,000 in total sales, even though the `sum` aggregate does not appear in the results:

```
select type, avg (price)
from titles
group by type
having sum (total_sales) > 10000
```

```
type
-----
business      13.73
mod_cook      11.49
popular_comp  21.48
trad_cook     15.96
(4 rows affected)
```

## 1.87.4 group by and having Clauses and Sort Orders

If your server has a case-insensitive sort order, `group by` ignores the case of the grouping columns.

For example, given this data on a case-insensitive server:

```
select lname, amount
from groupdemo
```

lname	amount
Smith	10.00
smith	5.00
SMITH	7.00
Levi	9.00
Lévi	20.00

grouping by `lname` produces these results:

```
select lname, sum (amount)
from groupdemo
```

lname	
Levi	9.00
Lévi	20.00
Smith	22.00

The same query on a case- and accent-insensitive server produces these results:

lname	
Levi	29.00
Smith	22.00

## 1.87.5 How group by Works With the Optimizer

There are two possible algorithms (implemented as operators) for doing `group by`: `GroupHashing` and `GroupSorted`. The optimizer chooses which operator to use based on factors such as the requirements these operators place on the input data streams.

The `GroupSorted` operator requires that the input rows to be aggregated are already sorted on the `group by` columns. Since the input rows must be sorted, the optimizer uses either of the following:

- An index on the `order by` columns to read the rows from the source table, and the maximum width of the `group by` columns is limited by the maximum width of an index key, which depends upon the database page size.
- A `sort` operator to order the rows on the `group by` columns before they are processed by the `GroupSorted` operator. The `group by` columns and the columns to be aggregated must fit into a worktable, so the maximum width of the `group by` columns is limited to the maximum row size on a database page, minus the width of the columns to be aggregated. The maximum `group by` column width is limited by the database page size.



The optimizer uses the GroupHashing operator if ordering on the `group by` columns is not available or the row size limitations of the GroupSorted operator are exceeded. The GroupHashing operator applies a hashing function to the values of the group by columns to be able to put rows with the same group by column values into the same hash bucket. Once the input rows have all been hashed into buckets, the rows in the buckets are aggregated to generate the group by results. The only limitation of the GroupHashing operator is that the total row size of group by columns and aggregate results cannot be larger than 64K. There is no limitation on the number of group by columns or the number of aggregation operations, just the total row width.

## 1.88 if...else

Imposes conditions on the execution of a SQL statement.

### Syntax

```
if <logical_expression >[plan< >"<abstract plan>"]
    <statements>

[else
    [if <logical_expression>] [plan< >"<abstract plan>"]
    <statement>]
```

### Parameters

#### <logical\_expression>

is an expression (a column name, a constant, any combination of column names and constants connected by arithmetic or bitwise operators, or a subquery) that returns TRUE, FALSE, or NULL. If the expression contains a `select` statement, you must enclose the `select` statement in parentheses.

#### plan "<abstract plan>"

specifies the abstract plan to use to optimize the query. It can be a full or partial plan, specified in the abstract plan language. Plans can be specified only for optimizable SQL statements, that is, `select` queries that access tables. See *Creating and Using Abstract Plans* in the *Performance and Tuning Guide: Optimizer and Abstract Plans*.

#### <statements>

is either a single SQL statement or a block of statements delimited by `begin` and `end`.

## Examples

### Example 1

Prints "yes" if 3 is larger than 2:

```
if 3 > 2
    print "yes"
```

### Example 2

Tests for the presence of authors whose postal codes are 94705, then prints "Berkeley author" for the resulting set:

```
if exists (select postalcode from authors
          where postalcode = "94705")
    print "Berkeley author"
```

### Example 3

Tests for the presence of user-created objects (all of which have ID numbers greater than 100) in a database. Where user tables exist, the `else` clause prints a message and selects their names, types, and ID numbers:

```
if (select max (id) from sysobjects) < 100
    print "No user-created objects in this database" else
begin
    print "These are the user-created objects"
    select name, type, id
    from sysobjects
    where id > 100
end
```

### Example 4

Since the value for total sales for PC9999 in the `titles` table is NULL, this query returns FALSE. The `else` portion of the query is performed when the `if` portion returns FALSE or NULL. For more information on truth values and logical expressions, see *Expressions in Reference Manual: Building Blocks*.

```
if (select total_sales
    from titles
    where title_id = "PC9999") > 100
select "true"
else
select "false"
```

## Usage

- The statement following an `if` keyword and its condition is executed if the condition is satisfied (when the logical expression returns TRUE). The optional `else` keyword introduces an alternate SQL statement that executes when the `if` condition is not satisfied (when the logical expression returns FALSE).
- The `if` or `else` condition affects the performance of only a single SQL statement, unless statements are grouped into a block between the keywords `begin` and `end` (see Example 3). The statement clause can be an `execute` command or any other legal SQL statement or statement block.

- If a `select` statement is used as part of the Boolean expression, it must return a single value.
- `if...else` constructs can be used either in a stored procedure (where they are often used to test for the existence of some parameter) or in *ad hoc* queries (see Examples 1 and 2).
- `if` tests can be nested either within another `if` or following an `else`. The maximum number of `if` tests you can nest varies with the complexity of any `select` statements (or other language constructs) that you include with each `if...else` construct.

### i Note

When an `alter table`, `create table`, or `create view` command occurs within an `if...else` block, the SAP ASE server creates the schema for the table or view before determining whether the condition is true. This may lead to errors if the table or view already exists. See *Transact-SQL Users Guide > Errors Generated by if exists()*.

- If you create tables with `varchar`, `nvarchar`, `univarchar`, or `varbinary` columns whose total defined width is greater than the maximum allowed row size, a warning message appears, but the table is created. If you try to insert more than the maximum number bytes into such a row, or to `update` a row so that its total row size is greater than the maximum length, the SAP ASE server produces an error message, and the command fails.

### i Note

When a `create table` command occurs within an `if...else` block or a `while` loop, the SAP ASE server creates the schema for the table before determining whether the condition is true. This may lead to errors if the table already exists. To avoid this situation, either make sure a view with the same name does not already exist in the database or use an `execute` statement, as follows:

```
if not exists
    (select * from sysobjects where name="my table")
begin
    execute ("create table mytable (x int)")
end
```

For dynamically executing Transact-SQL:

- When used with the `<string>` or `<char_variable>` options, `execute` concatenates the supplied strings and variables to execute the resulting Transact-SQL command. This form of the `execute` command may be used in SQL batches, procedures, and triggers.
- You cannot supply `<string>` and `<char_variable>` options to execute the following commands: `use`, `exec (<string>)` (not the `execute` stored procedure), `connect`, `begin transaction`, `rollback`, `commit`, and `dbcc`.
- `<string>` and `<char_variable>` options can be concatenated to create new tables. Within the same SQL batch or procedure, however, the table created with `execute` is visible only to other `execute` commands. After the SQL batch or procedure has completed, the dynamically created table is persistent and visible to other commands.

## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

## Permissions

No permission is required to use `if...else`.

## Auditing

This command is not audited.

## Related Information

[begin...end \[page 114\]](#)

[if...else \[page 569\]](#)

[while \[page 863\]](#)

## 1.89 insert

Adds new rows to a table or view.

### Syntax

```
insert [into] [<database>.<owner>.]<table_name>|<view_name>
  [<column_list>]
  {values (<expression> [,< expression>]...)}
  |<select_statement> [plan"<abstract plan>"]}
```

### Parameters

`into`

is optional.

`<table_name> | <view_name>`

is the name of the table or view from which you want to remove rows. Specify the database name if the table or view is in another database, and specify the owner's name if more than one table or view of that name exists in the database. The default value for `<owner>` is the current user, and the default value for `<database>` is the current database.

### <column\_list>

is a list of one or more columns to which data is to be added. Enclose the list in parentheses. The columns can be listed in any order, but the incoming data (whether in a `values` clause or a `select` clause) must be in the same order. If a column has the IDENTITY property, you can substitute the `syb_identity` keyword for the actual column name.

The column list is necessary when some, but not all, of the columns in the table are to receive data. If no column list is given, the SAP ASE server assumes that the `insert` affects all columns in the receiving table (in `create table` order).

### values

introduces a list of expressions.

### <expression>

specifies constant expressions, variables, parameters, or null values for the indicated columns. Enclose character and datetime constants in single or double quotes.

You cannot use a subquery as an <expression>.

The values list:

- Must be enclosed in parentheses
- Must match the explicit or implicit column list
- Can use "default" as a value

See *System and User-Defined Datatypes in Reference Manual: Building Blocks* for more information about data entry rules.

### <select\_statement>

is a standard `select` statement used to retrieve the values to be inserted.

### plan "<abstract plan>"

specifies the abstract plan to use to optimize the query. It can be a full or partial plan, specified in the abstract plan language. Plans can only be specified for `insert...select` statements. See *Creating and Using Abstract Plans* in the *Performance and Tuning Guide: Optimizer and Abstract Plans* for more information.

## Examples

### Example 1

```
insert titles
values ("BU2222", "Faster!", "business", "1389",
       null, null, null, "ok", "06/17/87", 0)
```

### Example 2

```
insert titles
(title_id, title, type, pub_id, notes, pubdate,
 contract)
values ('BU1237', 'Get Going!', 'business',
       '1389', 'great', '06/18/86', 1)
```

### Example 3

```
insert newauthors
  select *
  from authors
  where city = "San Francisco"
```

### Example 4

```
insert test
  select *
  from test
  where city = "San Francisco"
```

### Example 5

```
insert table1 (col1, col2, col3, col4)
  values (10, 4, default, 34)
```

### Example 6

```
create table t1 (c1 int, c2 int)
create index idx on t1(c1)
create procedure test_p_insert @var1 INT as
begin
  insert t2 (c1, c2 ) select c1, c2 from t1 where t1.c1 = @var1 with
recompile
end
exec test_p_insert 44
```

## Usage

- Use `insert` only to add new rows. Use `update` to modify column values in a row you have already inserted.
- When inserting into `text`, `unitext`, and `image` columns, an `insert` of a `NULL` into a `text`, `ortext`, or an `image` column simply allocates space for a text pointer. Use `update` to get a valid text pointer for that column.
- You can define a trigger that takes a specified action when an `insert` command is issued on a specified table.
- You can send an `insert` as a language event or as a parameterized dynamic statement to remote servers.

See also:

- *System and User-Defined Datatypes* in *Reference Manual: Building Blocks*
- `sp_bindefault`, `sp_bindrule`, `sp_help`, `sp_helppartition`, `sp_unbindefault`, `sp_unbindrule` in *Reference Manual: Procedures*
- `bcp` in the *Utility Guide*

## Standards

ANSI SQL – Compliance level: Entry-level compliant.

The following are Transact-SQL extensions:

- A `union` operator in the select portion of an `insert` statement.
- Qualification of a table or column name by a database name.
- Insertion through a view that contains a join.

### i Note

The FIPS flagger does not detect insertions through a view that contains a join.

## Permissions

The permission checks for `insert` differ based on your granular permissions settings.

Setting	Description
---------	-------------

<b>Enabled</b>	With granular permissions enabled, you must be the table owner or a user with <code>insert</code> permission on the table. Only the table owner or user with <code>insert</code> and <code>identity_insert</code> permissions can insert for the table's <code>IDENTITY</code> column.
----------------	--

<b>Disabled</b>	With granular permissions disabled, you must be the table owner or a user with <code>sa_role</code> .
-----------------	---

`insert` permission defaults to the table owner.

`insert` permission for a table's `IDENTITY` column is limited to the table owner, database owner, and system administrator.

## Auditing

Enable object-specific `insert` auditing option to audit inserts to a specific table or view. Enable user-specific `table_access` or `view_access` auditing options to audit table or view access by a specific user.

Values in `event` and `extrainfo` columns from the `sysaudits` table are:

Audit option	Event	Command or access audited	Information in <code>extrainfo</code> :
<code>insert</code>	41	<code>insert into a table</code>	<ul style="list-style-type: none"><li>• <i>Roles</i> – current active roles</li><li>• <i>Full command text</i> – full text of <code>insert</code> command</li><li>• <i>Previous value</i> – NULL</li><li>• <i>Current value</i> – NULL</li><li>• <i>Other information</i> – a list of parameter names and values (Parameters used to insert into encrypted columns are obfuscated)</li></ul>
<code>table_access</code>			

Audit option	Event	Command or access audited	Information in <code>extrainfo</code> :
<code>insert</code> <code>view_access</code>	42	<code>insert into a view</code>	<ul style="list-style-type: none"> <li><i>Proxy information</i> – original login name, if a set <code>proxy</code> is in effect</li> </ul>

Full command text and parameter names/values are included in `extrainfo`. For example:

```
sa_role sso_role oper_role sybase_ts_role mon_role; insert t1
values(@nr, @nr1, @nr2); ; ; @nr = aaa, @nr1 = *****,
@nr2 = bbb; ; sa/ase;
```

The value of parameter `@nr1` is obfuscated because it contains encrypted content.

For more information about auditing, see *Security Administration Guide > Auditing*.

## Related Information

[alter table \[page 70\]](#)

[create index \[page 192\]](#)

[create default \[page 158\]](#)

[create table \[page 273\]](#)

[dbcc \[page 349\]](#)

[delete \[page 391\]](#)

[select \[page 696\]](#)

[update \[page 819\]](#)

### 1.89.1 The Column List

The column list determines the order in which values are entered.

For example, suppose that you have a table called `newpublishers` that is identical in structure and content to the `publishers` table in `pubs2`. In the example below, the columns in the column list of the `newpublishers` table match the columns of the select list in the `publishers` table.

```
insert newpublishers (pub_id, pub_name)
select pub_id, pub_name
from publishers
where pub_name="New Age Data"
```

The `pub_id` and `pub_name` for "New Age Data" are stored in the `pub_id` and `pub_name` columns of `newpublishers`.

In the next example, the order of the columns in the column list of the `newpublishers` table does not match the order of the columns of the select list of the `publishers` table.

```
insert newpublishers (pub_id, pub_name)
```



```
select pub_name, pub_id
from publishers
where pub_name="New Age Data"
```

The result is that the `pub_id` for "New Age Data" is stored in the `pub_name` column of the `newpublishers` table, and the `pub_name` for "New Age Data" is stored in the `pub_id` column of the `newpublishers` table.

You can omit items from the column and values lists as long as the omitted columns allow null values (see Example 2).

## 1.89.2 Validating Column Values

There are a variety of ways you can validate column values.

`insert` interacts with the `ignore_dup_key`, `ignore_dup_row`, and `allow_dup_row` options, which are set with the `create index` command.

A rule or `check` constraint can restrict the domain of legal values that can be entered into a column. Rules are created with the `create rule` command and bound with `sp_binerule`. `check` constraints are declared with `create table`.

A default can supply a value if you do not explicitly enter one. Defaults are created with the `create default` command and bound with `sp_bindexdefault`, or they are declared with `create table`.

If an `insert` statement violates domain or integrity rules (see `create rule` and `create trigger`), or if it is the wrong datatype (see `create table` and *System and User-Defined Datatypes in Reference Manual: Building Blocks*), the statement fails, and the SAP ASE server displays an error message.

See `create index` for more information.

## 1.89.3 Treatment of Blanks

Empty strings, or blanks, are handled differently, depending on the datatype.

Inserting an empty string ("") into a variable character type or `text` column inserts a single space. `char` columns are padded to the defined length.

All trailing spaces are removed from data that is inserted into `varchar` and `univarchar` columns, except in the case of a string that contains only spaces. Strings that contain only spaces are truncated to a single space. Strings that are longer than the specified length of a `char`, `nchar`, `unichar`, `univarchar`, `varchar`, or `nvarchar` column are silently truncated unless the `string_rtruncation` option is set to `on`.

## 1.89.4 Inserting Rows Selected from Another Table

You can select rows from a table and insert them into the same table in a single statement.

To insert data with `select` from a table that has null values in some fields into a table that does not allow null values, provide a substitute value for any NULL entries in the original table. For example, to insert data into an `advances` table that does not allow null values, substitute 0 for the NULL fields:

```
insert advances
select pub_id, isnull (advance, 0) from titles
```

Without the `isnull` function, this command inserts all the rows with non-null values into the `advances` table, which produces error messages for all the rows where the `advance` column in the `titles` table contained NULL.

If you cannot make this kind of substitution for your data, you cannot insert data containing null values into the columns that have a `not null` specification.

Two tables can be identically structured, and yet be different as to whether null values are permitted in some fields. Use `sp_help` to see the null types of the columns in your table.

## 1.89.5 Inserting Rows in Bulk

The `ins_by_bulk` parameter improves performance by directly inserting data rows into newly allocated data pages by bulk for tables. You can set `ins_by_bulk` at the query level using the abstract plan for a specific insert statement.

The `ins_by_bulk` parameter improves performance by directly inserting data rows into newly allocated data pages by bulk for tables. You can set `ins_by_bulk` at the query level using the abstract plan for a specific insert statement.

The syntax is:

```
insert into. . .
select . . .
plan "(use ins_by_bulk on)"
```

For example:

```
insert into my_salesdetail (stor_id, ord_num, title_id, qty, discount)
select stor_id, ord_num, title_id, qty, discount from salesdetail
where qty > 100
plan '(use ins_by_bulk on)'
```

## 1.89.6 Transactions and `insert`

When you set chained transaction mode, the SAP ASE server implicitly begins a transaction with the `insert` statement if no transaction is currently active. To complete any inserts, you must commit the transaction, or roll back the changes.

For example:

```
insert stores (stor_id, stor_name, city, state)
  values ('999', 'Books-R-Us', 'Fremont', 'AZ')
if exists (select t1.city
  from stores t1, stores t2
  where t1.city = t2.city
  and t1.state = t2.state
  and t1.stor_id < t2.stor_id)
  rollback transaction
else
  commit transaction
```

In chained transaction mode, this batch begins a transaction and inserts a new row into the `stores` table. If it inserts a row containing the same city and state information as another store in the table, it rolls back the changes to `stores` and ends the transaction. Otherwise, it commits the insertions and ends the transaction. For more information about chained transaction mode, see the *Transact-SQL User's Guide*.

## 1.89.7 Inserting Values into IDENTITY Columns

When inserting a row into a table, do not include the name of the IDENTITY column in the column list or its value in the values list. If the table consists of only one column, an IDENTITY column, omit the column list and leave the values list empty.

```
insert id_table values ()
```

- The first time you insert a row into a table, the SAP ASE server assigns the IDENTITY column a value of 1. Each new row gets a column value that is one higher than the last. This value takes precedence over any defaults declared for the column in the `create table` or `alter table` statement or defaults bound to the column with `sp_bindexdefault`.  
Server failures can create gaps in IDENTITY column values. The maximum size of the gap depends on the setting of the `identity_burning set factor` configuration parameter. Gaps can also result from manual insertion of data into the IDENTITY column, deletion of rows, and transaction rollbacks.
- The table owner or user with insert permission on the table can explicitly insert a value into an IDENTITY column after setting `identity_insert <table_name>` on for the column's base table. Only table owner or user with `identity_insert` on the table can set `identity_insert table_name` on for the table. A user can set `identity_insert <table_name>` on for one table at a time in a database. When `identity_insert` is on, each `insert` statement must include a column list and must specify an explicit value for the IDENTITY column.  
Inserting a value into the IDENTITY column allows you to specify a seed value for the column or to restore a row that was deleted in error. Unless you have created a unique index on the IDENTITY column, the SAP ASE server does not verify the uniqueness of the value; you can insert any positive integer.

To insert an explicit value into an IDENTITY column, the table owner, database owner, or system administrator must set `identity_insert <table_name>` on for the column's base table, not for the view through which it is being inserted.

- The maximum value that can be inserted into an IDENTITY column is  $10^{\text{precision}} - 1$  for a numeric. For integer identities, it is the maximum permissible value of its type (such as 255 for `tinyint`, 32767 for `smallint`). Once an IDENTITY column reaches this value, any additional `insert` statements return an error that aborts the current transaction.

When this happens, use the `create table` statement to create a new table that is identical to the old one, but that has a larger precision for the IDENTITY column. Once you have created the new table, use either the `insert` statement or the `bcp` utility to copy the data from the old table to the new one.

- Use the `<@@identity>` global variable to retrieve the last value that you inserted into an IDENTITY column. If the last `insert` or `select into` statement affected a table with no IDENTITY column, `<@@identity>` returns the value 0.
- An IDENTITY column selected into a result table observes the following rules with regard to inheritance of the IDENTITY property:
  - If an IDENTITY column is selected more than once, it is defined as `not null` in the new table. It does not inherit the IDENTITY property.
  - If an IDENTITY column is selected as part of an expression, the resulting column does not inherit the IDENTITY property. It is created as `null` if any column in the expression allows nulls; otherwise, it is created as `not null`.
  - If the `select` statement contains a `group by` clause or aggregate function, the resulting column does not inherit the IDENTITY property. Columns that include an aggregate of the IDENTITY column are created `null`; others are created `not null`.
  - An IDENTITY column that is selected into a table with a union or join does not retain the IDENTITY property. If the table contains the union of the IDENTITY column and a `null` column, the new column is defined as `null`; otherwise, it is defined as `not null`.

## 1.89.8 Inserting Data Through Views

If you create a view using `with check option`, each row that is inserted through the view must meet the selection criteria of the view.

For example, the `stores_cal` view includes all rows of the `stores` table for which `state` has a value of "CA":

```
create view stores_cal
as select * from stores
where state = "CA"
with check option
```

The `with check option` clause checks each `insert` statement against the view's selection criteria. Rows for which `state` has a value other than "CA" are rejected.

If a view is created `with check option`, all views derived from the base view must satisfy the view's selection criteria. Each new row inserted through a derived view must be visible through the base view.

Consider the view `stores_cal30`, which is derived from `stores_cal`. The new view includes information about stores in California with payment terms of "Net 30:"

```
create view stores_cal30
```

```
as select * from stores_cal
where payterms = "Net 30"
```

Because `stores_cal` was created with `check option`, all rows inserted or updated through `stores_cal30` must be visible through `stores_cal`. Any row with a `state` value other than "CA" is rejected.

`stores_cal30` does not have a `with check option` clause of its own. This means you can insert or update a row with a `payterms` value other than "Net 30" through `stores_cal30`. The following `update` statement would be successful, even though the row would no longer be visible through `stores_cal30`:

```
update stores_cal30
set payterms = "Net 60"
where stor_id = "7067"
```

`insert` statements are not allowed on join views created with `check option`.

If you insert or update a row through a join view, all affected columns must belong to the same base table.

## 1.89.9 Partitioning Tables for Improved Insert Performance

An unpartitioned table with no clustered index consists of a single doubly linked chain of database pages, so each insertion into the table uses the last page of the chain. The SAP ASE server holds an exclusive lock on the last page while it inserts the rows, blocking other concurrent transactions from inserting data into the table.

Partitioning a table with the `partition` clause of the `alter table` command creates additional page chains. Each chain has its own last page, which can be used for concurrent insert operations. This improves insert performance by reducing page contention. If the table is spread over multiple physical devices, partitioning also improves insert performance by reducing I/O contention while the server flushes data from cache to disk. For more information about partitioning tables for insert performance, see *Controlling Physical Data Placement in Performance and Tuning Guide: Basics*.

## 1.90 kill

Kills a process.

### Syntax

```
kill <spid> [with (statusonly | force)]
```

### Parameters

<spid>

is the identification number of the process you want to kill. `<spid>` must be a constant; it cannot be passed as a parameter to a stored procedure or used as a local variable. Use `sp_who` to see a list of processes and other information.

#### with (statusonly | force)

- `statusonly` – reports on the progress of a server process ID (`<spid>`) in rollback status. It does not terminate the `<spid>`. The `statusonly` report displays the percent of rollback completed and the estimated length of time in seconds before the rollback completes.
- `force` – attempts to forcibly terminate a runaway task when a non forcible kill fails. If the runaway task has shared resources needed by other tasks, the `kill with force` command does not take effect and a message is added to the SAP ASE error log indicating the resource that is preventing the forcible kill. The `force` parameter should only be used when a runaway task cannot be terminated by a non-forced `kill` command. Do not use the `force` parameter on the terminating task.

## Examples

### Example 1

Kills process number 1378:

```
kill 1378
```

### Example 2

Reports on the process of the rollback of `<spid>` number 13:

```
kill 13 with statusonly
```

```
spid: 13 Transaction rollback in progress. Estimated rollback completion:17%  
Estimated time left: 13 seconds
```

To track the progress of a rollback, you must run `kill...with statusonly` multiple times. If the rollback of the `spid` has completed when you issue `kill...statusonly` or if the SAP ASE server is not rolling back the specified `spid`, `kill...statusonly` returns the following message:

```
Status report cannot be obtained. KILL spid:<nn> is not  
in progress.
```

### Example 3

Terminates `spid` 16:

```
kill 16 with force
```

## Usage

- Execute `sp_who` to get a report on the current processes, such as:

fid	spid	status	loginame	origname	hostname	blk	dbname	cmd
0	1	recv sleep	bird	bird	jazzy	0	master	AWAITING COMMAND
0	2	sleeping	NULL	NULL		0	master	NETWORK HANDLER
0	3	sleeping	NULL	NULL		0	master	MIRROR HANDLER
0	4	sleeping	NULL	NULL		0	master	AUDIT PROCESS
0	5	sleeping	NULL	NULL		0	master	CHECKPOINT SLEEP
0	6	recv sleep	rose	rose	petal	0	master	AWAITING COMMAND
0	7	running	robert	sa	helos	0	master	SELECT
0	8	send sleep	daisy	daisy	chain	0	pubs2	SELECT
0	9	alarm sleep	lily	lily	pond	0	master	WAITFOR
0	10	lock sleep	viola	viola	cello	7	pubs2	SELECT

The `spid` column contains the process identification numbers used in the Transact-SQL `kill` command. The `blk` column contains the process ID of a blocking process, if there is one. A blocking process (which may have an exclusive lock) is one that is holding resources that are needed by another process. In this example, process 10 (a `select` on a table) is blocked by process 7 (a `begin transaction` followed by an `insert` on the same table).

The `status` column reports the state of the command. The status values and the effects of `sp_who` are:

Status	Description	Effect of kill command
recv sleep	Waiting on a network read.	Immediate.
send sleep	Waiting on a network send.	Immediate.
alarm sleep	Waiting on an alarm, such as <code>waitfor delay "10:00"</code> .	Immediate.
lock sleep	Waiting on a lock acquisition.	Immediate.
sleeping	Waiting on disk I/O or some other resource. Probably indicates a process that is running, but doing extensive disk I/O.	Process is killed when it "wakes up;" usually immediately. A few sleeping processes do not wake up, and require an SAP ASE restart to clear.
runnable	In the queue of runnable processes.	Immediate.
running	Actively running on one of the server engines.	Immediate.
infected	The SAP ASE server has detected a serious error condition; extremely rare.	<code>kill</code> command not recommended. A SAP ASE server restart is probably required to clear the process.
background	A process, such as a threshold procedure, run by an SAP ASE server rather than by a user process.	Immediate; use <code>kill</code> with extreme care. Recommend a careful check of <code>sysprocesses</code> before killing a background process.

Status	Description	Effect of <code>kill</code> command
<code>log suspend</code>	Processes suspended by reaching the last-chance threshold on the log.	Immediate.

- To get a report on the current locks and the `<spid>`s of the processes holding them, use `sp_lock`.
- In a clustered environment, a privileged Kerberos user can use the `kill` command to stop the `spid` for a DBMS task on a remote instance.
- SAP ASE issues this message if you use `with force` to terminate a `spid` that holds spinlocks:

```
You cannot kill spid '<spid_number>' with force option as it is holding
spinlock(s).
```

- `<spid>` must be a constant; it cannot be passed as a parameter to a stored procedure or used as a local variable.

See also `sp_lock`, `sp_who` in *Reference Manual: Procedures*.

## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

## Permissions

The permission checks for `kill` differ based on your granular permissions settings.

### Setting Description

**Enabled** With granular permissions enabled, you must have the `kill` privilege to kill you own process, and have the `kill any process` privilege to kill another user's processes.

**Disabled** With granular permissions disabled, you must be a user with `sa_role`. `kill` privilege is not transferable.



## Auditing

You can enable `security` auditing option to audit this command. Values in `event` and `extrainfo` columns from the `sysaudits` table are:

Audit option	Event	Command or access audited	Information in <code>extrainfo</code> :
<code>security</code>	89	<code>kill</code>	<ul style="list-style-type: none"><li>• <i>Roles</i> – current active roles</li><li>• <i>Full command text</i> – full text of <code>kill</code> command</li><li>• <i>Previous value</i> – NULL</li><li>• <i>Current value</i> – NULL</li><li>• <i>Other information</i> – NULL</li><li>• <i>Proxy information</i> – original login name, if set <code>proxy</code> is in effect</li></ul>

Full command text is included in `extrainfo`. For example:

```
sa_role sso_role oper_role sybase_ts_role mon_role; kill 14; ; ; ; sa/ase;
```

For more information about auditing, see *Security Administration Guide > Auditing*.

## Related Information

[shutdown \[page 792\]](#)

## 1.91 load database

Loads a backup copy of a user database, including its transaction log, that was created with `dump database`, as well as materializes archive databases that have been loaded with a database dump.

The target platform of a `load database` operation need not be the same platform as the source platform where the `dump database` operation occurred. `dump database` and `load database` are performed from either a big endian platform to a little endian platform, or from a little endian platform to a big endian platform.

See *Using Backup Server with IBM Tivoli Storage Manager* for the `load database` syntax when the Tivoli Storage Manager is licensed at your site.

## Syntax

Makes a routine database load:

```
load database <database_name> cumulative
```

```

from [compress::

```

Returns header or file information without loading the backup:

```

load database <database_name>
from [compress::]<stripe_device>
  [at <backup_server_name>]
  [density = <density_value>,
  blocksize = <number_bytes>,
  dumpvolume = <volume_name>,
  file =< file_name>]
[stripe on [compress::]<stripe_device>
  [at <backup_server_name>]
  [density = <density_value>,
  blocksize = <number_bytes>,
  dumpvolume = <volume_name>,
  file = <file_name>]
[[stripe on [compress::]<stripe_device>
  [at <backup_server_name>]
  [density = <density_value>,
  blocksize = <number_bytes>,
  dumpvolume = <volume_name>,
  file = <file_name>]]...]
[with {
  density = <density_value>,
  blocksize = <number_bytes>,
  dumpvolume = <volume_name>,
  file = <file_name>,
  [dismount | nodismount],
  [nounload | unload],
  passwd = <password>,
  listonly [= full],
  headeronly,
  notify = {client | operator_console},
  verify[only]=crc
  }]}

```

Materializes an archive database:

```
load database <database_name>
  from <dump_device>
  [ [stripe on <stripe_device>] ... ]
  [with [norecovery,][passwd=<password>]
```

Generates a sequence of load database SQL statements to restore a database to a specified point in time:

```
load database <database_name>
  [from <stripe_device>]
  with listonly=[load_sql | create_sql | volume]
```

Loads a copy of the database when the Tivoli Storage Manager is licensed at your site:

```
load database <database_name>
  from syb_tsm:[[-S <source_sever_name>][[-D <source_database_name>]
  ::]<object_name> [blocksize = <number_bytes>]
  [stripe on syb_tsm:[[-S <source_sever_name>]
  [-D <source_database_name>]::]<object_name>
  [blocksize = <number_bytes>]]
  [[stripe on syb_tsm:[[-S <source_sever_name>]
  [-D <source_database_name>]::]<object_name>
  [blocksize = <number_bytes>]]...]
  [with {
    blocksize = <number_bytes>,
    passwd = <password>,
    listonly [= full],
    headeronly,
    notify = {client | operator_console},
    [[verifyonly | verify] [= header | full]]
  } ]
```

## Parameters

### <database\_name>

is the name of the database to receive the backup copy. It can be either a database created with the `for load` option, or an existing database. Loading dumped data to an existing database overwrites all existing data. The receiving database must be at least as large as the dumped database. The database name can be specified as a literal, a local variable, or a stored procedure parameter.

For archive databases, <database\_name> is the name of the archive database into which you want to load.

### **cumulative**

load a backup created with the dump database cumulative keyword.

### **compress::**

invokes the decompression of the archived database. For more information about the `compress` option, see *Backing Up and Restoring User Databases in the System Administration Guide*.

### **i Note**

You should use the native "`compression = <compress_level>`" option over the older "`compress::<compression_level>`" option. If you use the native

option for `dump database`, you do not need to use `"compress::<compression_level>"` when loading your database.

**from <dump\_device>**

specifies the name of the disk database dump from which you want to load the dump.

**from <stripe\_device>**

is the device from which data is being loaded. For a list of supported dump devices, see the SAP ASE installation and configuration guides.

**at <backup\_server\_name>**

is the name of a remote Backup Server running on the machine to which the dump device is attached. For platforms that use interfaces files, the `<backup_server_name>` must appear in the interfaces file.

**listonly = [load\_sql | create\_sql | volume]**

generates the following:

- `load_sql` – sequence of `load database` or `load transaction SQL` commands to perform restore to a specified point in time.

#### i Note

Do not use the `from` clause (including `from <stripe_device>`) when using with `listonly=load_sql`; the server displays an error and the `load database` command does not execute.

- `create_sql` – displays the sequence of `disk init/sp_cacheconfig`, `disk init`, `create/alter database`, and the `create/alter database` sequence from the latest dump image obtained from the backup history. When you use with `listonly=create_sql` when loading a database from a stripe device, this option displays `disk init/sp_cacheconfig`, `disk init`, `create`, or `alter database` sequence from the dump image.
- `volume` – displays volume information from the dump image.

#### i Note

To use the `listonly = create_sql` and `listonly = load_sql` parameters, you must first turn on the `sp_configure enable dump history` parameter:

```
sp_config "enable dump history" 1
```

**density = < density\_value>**

is ignored. See `dump database`.

**blocksize = <number\_bytes>**

overrides the default block size for a dump device. If you specify a block size on UNIX systems, it should be identical to that used to make the dump. See `dump database`.

**dumpvolume = <volume\_name>**

is the volume name field of the ANSI tape label. `load database` checks this label when the tape is opened and generates an error message if the wrong volume is loaded.

### i Note

When using `load database`, the `dumpvolume` option does not provide an error message if an incorrect file name is given for the `file=<filename>` option. The backup server searches the entire tape looking for that file, regardless of an incorrect tape mounted.

`file = <file_name>`

is the name of a particular database dump on the tape volume. If you did not record the dump file names when you made the dump, use `listonly` to display information about all dump files.

`stripe on <stripe_device>`

is an additional dump device. You can use up to 32 devices, including the device named in the `to <stripe_device>` clause. The Backup Server loads data from all devices concurrently, reducing the time and the number of volume changes required.

`dismount | nodismount`

(on platforms that support logical dismount) determines whether tapes remain mounted. By default, all tapes used for a load are dismounted when the load completes. Use `nodismount` to keep tapes available for additional loads or dumps.

`nounload | unload`

determines whether tapes rewind after the load completes. By default, tapes do not rewind, allowing you to make additional loads from the same tape volume. Specify `unload` for the last dump file to be loaded from a multidump volume. This rewinds and unloads the tape when the load completes.

`with [norecovery]`

indicates when materializing an archive database that the `load database` command does not run recovery, and that the database is brought online automatically after the `load database` command has completed.

`passwd = <password>`

is the password you provided to protect the dump file from unauthorized users. The password must be between 6 and 30 characters long. You cannot use variables for passwords. For rules on passwords, see *Managing Adaptive Server Logins, Database Users, and Client Connections* in the *System Administration Guide, Volume 1*.

`until_time = <datetime>`

generates a load sequence to load (to a specified point in time).

`listonly [= full]`

displays information about all dump files on a tape volume, but **does not load the database**. `listonly` identifies the database and device, the date and time the dump was made, and the date and time it can be overwritten. `listonly = full` provides additional details about the dump. Both reports are sorted by ANSI tape label.

After listing the files on a volume, the Backup Server sends a volume change request. The operator can either mount another tape volume or terminate the list operation for all dump devices.

Due to current implementation, the `listonly` option overrides the `headeronly` option.

### ⚠ Caution

Do not use `load database` with `listonly` on 1/4-inch cartridge tape.

**with verify[only][=header | full | crc]**

performs a minimal header or structural row check on the data pages as they are being copied to the archives, but **does not load the database**. There are no structural checks done at this time to `gam`, `oam`, `allocation` pages, `indexes`, `text`, or `log` pages. The only other check is done on pages where the page number matches to the page header. Any faults found are reported in the `backupserver` error log

Use `crc` to indicate that you are performing a cyclic redundancy check for accidental changes to raw data for compressed database or transaction dumps.

**headeronly**

displays header information for a single dump file, but **does not load the database**. `headeronly` displays information about the first file on the tape unless you use the `file = <file_name>` option to specify another file name. The dump header indicates:

- Type of dump (database or transaction log)
- Database ID
- File name
- Date the dump was made
- Character set
- Sort order
- Page count
- Next object ID

**notify = {client | operator\_console}**

overrides the default message destination.

- On operating systems that offer an operator terminal feature, volume change messages are always sent to the operator terminal on the machine on which the Backup Server is running. Use `client` to route other Backup Server messages to the terminal session that initiated the `dump database`.
- On operating systems (such as UNIX) that do not offer an operator terminal feature, messages are sent to the client that initiated the `dump database`. Use `operator_console` to route messages to the terminal on which the Backup Server is running.

**copyonly=<path>**

extracts a database dump file from a dump that is stored on a storage device, such as Tivoli Storage Manager or Legato (one file per device or stripe). Using `load database <database_name> from <device> with copyonly=<path>` does not load pages from the dump in `<database_name>`, but rather, copies pages to device stripes using the path specified in the `copyonly` option. There are no layout or size restrictions for `<database_name>`, which need not match the dump that you are copying/loading. You may also use this to extract a dump from a compressed dump of the form `compress::<level>::<stripe>`.

Specify `<device>` in the form `name::name`.

#### **override**

you must use `with override` to successfully load the database containing encryption keys that encrypt columns in other databases.

#### **syb\_tsm::<object\_name>**

is the keyword that invokes the `libsyb_tsm.so` module that enables communication between Backup Server and TSM.

#### **-S <source\_server\_name>**

specifies the name of the source SAP ASE server when it is not the same as the target SAP ASE server. This parameter is required when the target server for the load operation is different from the source server used for the dump operation.

#### **-D <source\_database\_name>**

specifies the name of the source database when it is not the same as the target database. This parameter is required when the target database for the load operation is different from the source database used for the dump operation.

#### **verify[only]=crc**

performs a cyclic redundancy check as it loads the database.

## Examples

### Example 1

Reloads the database `pubs2` from a tape device:

```
load database pubs2
  from "/dev/nrmt0"
```

### Example 2

Loads the `pubs2` database, using the Backup Server `REMOTE_BKP_SERVER`. This command names three devices:

```
load database pubs2
  from "/dev/nrmt4" at REMOTE_BKP_SERVER
  stripe on "/dev/nrmt5" at REMOTE_BKP_SERVER
  stripe on "/dev/nrmt0" at REMOTE_BKP_SERVER
```

### Example 3

Loads the `pubs2` database from a compressed dump file called `dmp090100.dmp` located at `/opt/bin/Sybase/dumps`:

```
load database pubs2 from
  "compress::/opt/bin/Sybase/dumps/dmp090100.dmp"
```

### Example 4

Loads the `key_db` database, which contains encryption keys. You must use `with override` if the encryption keys in `key_db` were used to encrypt columns in other databases:

```
load database key_db from "/tmp/key_db.dat" with override
```

### Example 5

Loads the `testdb` database from "syb\_tsm::obj1.2". See `dump database` for the associated dump command.

```
load database testdb from "syb_tsm::obj1.2"
stripe on "syb_tsm::obj1.2"
stripe on "syb_tsm::obj1.2"
stripe on "syb_tsm::obj1.2"
stripe on "syb_tsm::obj1.2"
```

### Example 6

Loads the `pubs2` database from the TSM backup object "obj1.1" when the source database (`testdb`) of the associated dump command is different than the target database (`pubs2`) of the load command.

```
load database pubs2 from "syb_tsm::-D testdb::obj1.1"
```

### Example 7

Creates database `testdb` on five database devices named `testdata1`, `testdata2`, `testdata3`, `testlog4`, and `testlog5`:

```
disk init name = 'testdata1', physname='/tmp/t_dat1',size='10M'
go
disk init name='testdata2',physname='/tmp/t_dat2',size='10M'
go
disk init name='testdata3',physname='/tmp/t_dat3',size='10M'
go
disk init name='testlog4',physname='/tmp/t_log4',size='10M'
go
disk init name='testlog5',physname='/tmp/t_log5',size='10M'
go
create database testdb on testdata1='10M', testdata2='8M', testdata3='5M'
    log on testlog4='6M',testlog5 with override
go
alter database testdb on testdata3 = '5M'
go
alter database testdb log on testlog4 = '2M'
go
```

The dump of the database `testdb` is taken using `dump database`, which writes additional database device information in dump header.

```
dump database testdb to "test.dmp"
go
```

The load of the database `testdb` using the dump image `test.dmp` with the `with headeronly` option results in displaying dump header contents. This results in displaying additional information about the database devices:

```
1> load database testdb from "test.dmp" with headeronly
2> go
Backup Server: 6.28.1.1: Dumpfile name 'test1025109FD6 ' section number 1
mounted on disk file '/punedbaccess3_dev3/kelkara/backupserver/test.dmp'
....
dbdevinfo: vdevno=1 devname=testdata1 path=/tmp/test1.dat db_size=10485760
device_size=20967424
dbdevinfo: vdevno=2 devname=testdata2 path=/tmp/test2.dat db_size=8388608
device_size=20967424
dbdevinfo: vdevno=3 devname=testdata3 path=/tmp/test3.dat db_size=10485760
device_size=20967424
```



```

dbdevinfo: vdevno=4 devname=testlog4 path=/tmp/test4.dat db_size=8388608
device_size=20967424
dbdevinfo: vdevno=5 devname=testlog5 path=/tmp/test5.dat db_size=6291456
device_size=20967424
...

```

The database device information consists of `vdevno`, `devname`, `path`, `db_size` and `device_size`. The `device_size` is the total size of device allocated at the time of `disk init` command. The `db_size` is the size of the device used by database `testdb`. The load of the database `testdb` using the dump image `test.dmp` with the `create_sqlgenddonly` option displays sequence of `create/alter` database commands which can be used to create target database with same data/log segment layout as for the source database at the time of `dump` command. This output can be routed to a file so as to generate `isql` command script to create target the database:

```

1> load database test from "test.dmp" with listonly=create_sql
2> go
DISK INIT
      name = 'testdata1'
      , physname = '/tmp/t_dat1'
      , size = '10M'
go
DISK INIT
      name = 'testdata2'
      , physname = '/tmp/t_dat2'
      , size = '10M'
go
DISK INIT
      name = 'testdata3'
      , physname = '/tmp/t_dat3'
      , size = '10M'
go
DISK INIT
      name = 'testlog4'
      , physname = '/tmp/t_log4'
      , size = '10M'
go
DISK INIT
      name = 'testlog5'
      , physname = '/tmp/t_log5'
      , size = '10M'
go
CREATE DATABASE testdb
ON testdata1 = '10M'
, testdata2 = '8M'
, testdata3 = '5M'
LOG ON testlog4 = '6M'
, testlog5 = '6M'
go
ALTER DATABASE testdb
ON testdata3 = '5M'
LOG ON testlog4 = '2M'
go

```

### Example 8

Displays the load command sequence required to restore a specific database using the latest available dumps. The dump records from the dump history file are read to prepare the load sequence:

```

1> load database testdb with listonly=load_sql
2> go
LOAD DATABASE testdb FROM '/dumpdir/testdb_DB_1.1.dmp'
STRIPE ON '/dumpdir/testdb_DB_1.2.dmp'
STRIPE ON '/dumpdir/testdb_DB_1.3.dmp'
go

```

```
LOAD TRANSACTION testdb FROM '/dumpdir/testdb_XACT_2.dmp'
go
LOAD TRANSACTION testdb FROM '/dumpdir/testdb_XACT_3.dmp'
go
LOAD TRANSACTION testdb FROM '/dumpdir/testdb_XACT_4.1.dmp'
STRIPE ON '/dumpdir/testdb_XACT_4.2.dmp'
go
```

### Example 9

Performs a cyclic redundancy check as it loads the `new_dump` database dump:

```
load database new_dump from mydumpdev with verify[only]=crc
```

### Example 10

Extracts a database dump file from a dump stored on a storage device using the `copyonly` option. The example first creates a dump:

```
1> dump database repro to "compress::1::/tmp/repro.str1.compr"
2> stripe on "compress::1::/tmp/repro.str2.compr"
```

The example then loads using `copyonly` using a different database:

```
1> load database model from "compress::1::/tmp/repro.str1.compr"
2> stripe on "compress::1::/tmp/repro.str2.compr"
3> with copyonly="/tmp/repro.cp.stripes"
Backup Server session id is: 37. Use this value when executing the
'sp_volchanged' system stored procedure after fulfilling any
volume change request from the Backup Server.
Backup Server: 4.132.1.1: Attempting to open byte stream device:
'compress::1::/tmp/repro.str1.compr::000'
Backup Server: 4.132.1.1: Attempting to open byte stream device:
'compress::1::/tmp/repro.str2.compr::001'
Backup Server: 6.28.1.1: Dumpfile name 'repro1519104C88 ' section
number 1 mounted on byte stream 'compres
```

This then generates one dump file per stripe, with the `<path>` from the `copyonly` option following a four-digit number:

```
> ls /tmp/repro.cp.str.*
/tmp/repro.cp.stripes.0000
/tmp/repro.cp.stripes.0001
```

## Usage

- If you use `sp_hidetext` followed by a cross-platform dump and load, you must manually drop and re-create all hidden objects.
- `load database` preserves segment mapping, including user segments.
- The `listonly` and `headeronly` options display information about the dump files without loading them.
- If you run `load database ... listonly=create_sql` from a database dump that includes a shrunken log device, the SAP ASE server may list an unknown device in the `create database` command. You can eliminate this unknown device from the `create database` command if you include the shrunken log device is on the last mapped segment and issue `dump database ... with shrink_log`.
- Dumps and loads are performed through Backup Server.

- To make sure databases are synchronized correctly so that all proxy tables have the correct schema to the content of the primary database you just reloaded, you may need to run the `alter database <dbname> for proxy_update` command on the server hosting the proxy database.

See also:

- *Backing Up and Restoring User Databases* in the *System Administration Guide*.
- `sp_helpdb`, `sp_helpdevice`, `sp_hidetext`, `sp_volchanged` in *Reference Manual: Procedures*

## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

## Permissions

The permission checks for `load database` differ based on your granular permissions settings.

### Setting Description

**Enabled** With granular permissions enabled, you must be the database owner, or a user with `load database` privilege or `own database` privilege on the database.

**Disabled** With granular permissions disabled, you must be the database owner, or a user with any of these roles:

- `sa_role`, or,
- `replication_role`, or,
- `oper_role`

## Auditing

You can enable `load` auditing option to audit this command. Values in `event` and `extrainfo` columns from the `sysaudits` table are:

Audit option	Event	Command or access audited	Information in <code>extrainfo</code> :
<code>load</code>	43	<code>load database</code>	<ul style="list-style-type: none"> <li>• <b>Roles</b> – current active roles</li> <li>• <b>Full command text</b> – full text of executed command (for <code>load database . . . cumulative</code>, password is obfuscated)</li> </ul>

Audit option	Event	Command or access audited	Information in <code>extrainfo</code> :
	151	load database...cumulative	<div style="border: 1px solid #ccc; padding: 5px;"> <p><b>i Note</b></p> <p>Full command text is not printed for load database with <code>[headeronly listonly verifyonly]</code>.</p> <ul style="list-style-type: none"> <li>• <b>Previous value</b> – NULL</li> <li>• <b>Current value</b> – NULL</li> <li>• <b>Other information</b> – NULL</li> <li>• <b>Proxy information</b> – original login name, if set <code>proxy</code> is in effect</li> </ul> </div>

Full command text (with obfuscated password) is included in `extrainfo`. For example:

```
sa_role sso_role oper_role sybase_ts_role mon_role; load database tdb2
  from "/tmp/tdb2.dmp" with passwd="*****"; ; ; ; ; sa/ase;
```

For more information about auditing, see *Security Administration Guide > Auditing*.

## Related Information

[Encrypted Columns and dump database \[page 489\]](#)

[alter database \[page 14\]](#)

[dbcc \[page 349\]](#)

[dump database \[page 470\]](#)

[dump transaction \[page 490\]](#)

[load transaction \[page 603\]](#)

[online database \[page 625\]](#)

## 1.91.1 Commands and System Procedures to Restore Databases

Commands and system procedures for restoring databases from backups.

Command or System Procedure	Action
<code>create database for load</code>	Create a database for the purpose of loading a dump.
<code>load database</code>	Restore a database from a dump.

Command or System Procedure	Action
<code>load transaction</code>	Apply recent transactions to a restored database.
<code>online database</code>	Make a database available for public use after a normal load sequence or after upgrading the database to the current version of SAP ASE.
<code>load {database   transaction} with {headeronly   listonly}</code>	Identify the dump files on a tape.
<code>sp_volchanged</code>	Respond to the Backup Server volume change messages.

## 1.91.2 Restrictions for load database

Restrictions for using `load database`.

- CIS only – Any proxy tables in the database are part of the database save set. The content data of proxy tables is not included in the save; only the pointer is saved and restored.
- You can only load a database dump into a server with the same sort order as the source server.
- Named pipes are supported as a backup device. However, Backup Server does not attempt to create a named pipe. Instead, you must create the named pipe externally before executing the `dump database` command (you need not do this for regular file).
- You cannot load a dump that was generated on a server earlier than version 12.5.4.
- If a database has cross-database referential integrity constraints, the `sysreferences` system table stores the name—not the ID number—of the external database. The SAP ASE server cannot guarantee referential integrity if you use `load database` to change the database name or to load it onto a different server.
- Each time you add or remove a cross-database constraint or drop a table that contains a cross-database constraint, dump both of the affected databases.

### ⚠ Caution

Loading earlier dumps of these databases can cause database corruption. Before dumping a database to load it with a different name or move it to another SAP ASE server, use `alter table` to drop all external referential integrity constraints.

- `load database` clears the suspect page entries pertaining to the loaded database from `master..sysattributes`.
- `load database` overwrites any existing data in the database.
- After a database dump is loaded, two processes may require additional time before the database can be brought online:
  - Backup Server zeroes the non-allocated pages that are in the source database's space map. This zeroing is embedded as part of the physical load, and happens during the `load database`. If the target database is larger than the source, then the space above the ceiling of the source database's space map is zeroed by the SAP ASE server after Backup Server has completed the load.
  - Recovery ignores transactions that completed before the checkpoint that was written by `dump database` at the start of its operation. Completed transactions in the active portion of the transaction

log are rolled forward by recovery. In a load sequence, rollback of incomplete transactions happens at the end of that sequence, under `online database`.

- The receiving database must be as large as or larger than the database to be loaded. If the receiving database is too small, the SAP ASE server displays an error message that gives the required size.
- You cannot load from the null device (on UNIX, `/dev/null`).
- You cannot use `load database` in a user-defined transaction.
- Once you load a database, the SAP ASE server automatically identifies the endian type on the dump file and performs all necessary conversions while the `load database` and `online database` commands execute.

After the SAP ASE server converts the index rows, the order of index rows may be incorrect. The SAP ASE server marks the following indexes on user tables as suspect indexes during execution of `online database`:

- Nonclustered index on APL (all pages locked) table
- Clustered index on DOL (data-only locked) table
- Nonclustered index on DOL table

During cross-platform dump and load operations, suspect partitions are handled as follows:

- During the first `online database` command, after you execute `load database` across two platforms with different endian types, the hash partition is marked suspect.
- Any global clustered index on a round-robin partition, which has an internally generated partition condition with a `unichar` or `univarchar` partition key, is marked suspect.
- After the database is online, use `sp_post_xpload` to fix the suspect partitions and indexes.

### **i** Note

See *Reference Manual: Procedures* for information about checking and rebuilding indexes on user tables using the `sp_post_xpload` stored procedure.

- `dump transaction` and `load transaction` are not allowed across platforms.
- `dump database` and `load database` to or from a remote `backupserver` are not supported across platforms if the dumps are compressed.
- You cannot load a password-protected dump file across platforms.
- If you perform `dump database` and `load database` for a parsed XML object, you must parse the text again after the `load database` command has completed.
- You cannot perform `dump database` and `load database` across platforms on SAP ASE versions earlier than 11.9.
- SAP ASE servers cannot translate embedded data structures stored as `binary`, `varbinary`, or `image` columns.
- `load database` is not allowed on the `master database` across platforms.
- Stored procedures and other compiled objects are recompiled from the SQL text in `syscomments` at the first execution after the `load database`.

If you do not have permission to recompile from text, then the person who does has to recompile from text using `dbcc upgrade_object` to upgrade objects.

## 1.91.3 Locking Out Users During Loads

A database cannot be in use while it is being loaded. `load database` sets the status of the database to "offline." No one can use the database while its status is "offline." The "offline" status prevents users from accessing and changing the database during a load sequence.

A database loaded by `load database` remains inaccessible until `online database` is issued.

## 1.91.4 Upgrading Database and Transaction Log Dumps

Restore and upgrade a user database dump from an earlier version to the most current version of the SAP ASE.

1. Load the most recent database dump.
2. Load, *in order*, all transaction log dumps made since the last database dump.  
The SAP ASE server checks the timestamp on each dump to make sure that it is being loaded to the correct database and in the correct sequence.
3. Issue `online database` to do the upgrade and make the database available for public use.
4. Dump the newly upgraded database immediately after upgrade, to create a dump consistent with the current version of SAP ASE.

## 1.91.5 Specifying Dump Devices

You can specify the dump device as a literal, a local variable, or a parameter to a stored procedure.

- You can specify a local device as:
  - A logical device name from the `sysdevices` system table
  - An absolute path name
  - A relative path name

The Backup Server resolves relative path names using the current working directory in SAP ASE.

- When loading across the network, specify the absolute path name of the dump device. The path name must be valid on the machine on which the Backup Server is running. If the name includes characters other than letters, numbers, or the underscore (`_`), enclose the entire name in quotes.
- Ownership and permissions problems on the dump device may interfere with use of `load` commands.
- You can run more than one load (or dump) at the same time, as long as each load uses a different physical device.

## 1.91.6 Backup Servers

You must have a Backup Server running on the same machine as the SAP ASE server. The Backup Server must be listed in the `master..sys.servers` table. This entry is created during installation or upgrade; do not delete it.

If your backup devices are located on another machine, so that you load across a network, you must also have a Backup Server installed on the remote machine.

## 1.91.7 Volume Names

Dump volumes are labeled according to the ANSI tape labeling standard. The label includes the logical volume number and the position of the device within the stripe set.

During loads, Backup Server uses the tape label to verify that volumes are mounted in the correct order. This allows you to load from a smaller number of devices than you used at dump time.

### i Note

When dumping and loading across the network, you must specify the same number of stripe devices for each operation.

## 1.91.8 Changing Dump Volumes

If the Backup Server detects a problem with the currently mounted volume, it requests a volume change by sending messages to either the client or its operator console. After mounting another volume, the operator notifies the Backup Server by executing `sp_volchanged` on any SAP ASE server that can communicate with the Backup Server.

## 1.91.9 Restoring the System Databases

You can only load dumps of the `master` database into the `master` database or an archive database.

See the *System Administration Guide* for step-by-step instructions for restoring the system databases from dumps.

## 1.91.10 Disk Mirroring

At the beginning of a load, the SAP ASE server passes Backup Server the primary device name of each logical database and log device. If the primary device has been unmirrored, the SAP ASE server passes the name of



the secondary device instead. If any named device fails before Backup Server completes its data transfer, the SAP ASE server aborts the load.

If you attempt to unmirror any named device while a `load database` is in progress, the SAP ASE server displays a message. The user executing `disk unmirror` can abort the load or defer the `disk unmirror` until after the load completes.

Backup Server loads the data onto the primary device, then `load database` copies it to the secondary device. `load database` takes longer to complete if any database device is mirrored.

## 1.91.11 Materializing an Archive Database

An archive database is a placeholder that is useful only once it has been loaded with a database dump. The load process does not actually copy pages, however, it materializes the database using page mapping.

### i Note

You do not need to have Backup Server running when loading a database dump into an archive database.

## 1.91.12 Using load database with norecovery

The `with norecovery` option of the `load database` command allows a database dump to be loaded into an archive database without recovering anything, reducing the time required to load. Many database pages can be modified or allocated during recovery, causing them to be stored in the modified pages section. Therefore, skipping recovery consumes minimum space in the modified pages section. The `with norecovery` option allows a quick view into an archive database.

If you use `with norecovery`, the database is brought online automatically.

However, using `load database with norecovery` for a database that requires recovery may leave it transactionally and physically inconsistent. Running `dbcc` checks on a physically inconsistent database may produce many errors.

Once you have loaded an archive database `with norecovery`, you must have `sa_role` or database owner privileges to use it.

## 1.91.13 Using Logical Devices with an Archive Database

You can use `sp_addumpdevice` to create a logical device from which an archive database can be loaded.

```
sp_addumpdevice 'archive database', '<logical_name>',  
                '<physical_name>'
```

After you have executed this command, use the `<logical_name>` instead of the `<physical_name>` as the `<dump_device>` or `<stripe_device>` in a `load database` command.

## i Note

You cannot use an archive database logical device as a device specification for a load into a traditional database or when dumping a traditional database.

### 1.91.14 load database Limitations with an Archive Database

`load database` has limitations when used with an archive database.

- The database dump for an archive database is required to be a disk dump on a file system mounted on the local machine. This can be local storage or NFS storage. `load database ... at <remote server>` syntax is not supported, nor are database dumps on tape.
- Cross-architecture loads are not supported. The database dump and the `load database` command must be performed on the same architecture with respect to byte ordering.
- The dumped database must have the same page size as that used by the server that is hosting the archive database.
- The major version of the server on which the dump was taken must be earlier than or equal to the major version of the server hosting the archive database.
- The character set and sort order on the server on which the database dump was taken must be the same as the character set and sort order of the server hosting the archive database.

### 1.91.15 load database and Encrypted Columns

If you store keys in a database that is separate from the columns encrypted by those keys, you must load both databases from dumps that were made simultaneously, avoiding a problem where the encrypted column's key is missing after the load.

After loading the databases for keys and data, bring both databases on line simultaneously.

You should not load your key database into a database with a different name because metadata dependencies exist between encrypted columns and their keys. If you must change the name of the key database:

1. Before dumping the database containing the encrypted columns, use `alter table` to decrypt the data.
2. Dump the databases containing keys and encrypted columns.
3. After loading the databases, use `alter table` to re-encrypt the data with the keys in the newly named database.

### 1.91.16 Loading Compressed Data

You cannot create a dump of a compressed table on one platform and load the dump onto a different platform.

`create index` commands on compressed tables that contain any form of compressed or uncompressed rows are fully recovered during a `load transaction`.

## 1.92 load transaction

Loads a backup copy of the transaction log that was created with `dump transaction`.

### Syntax

Makes a routine log load:

```
load tran[saction] <database_name>
  from [compress::]<stripe_device>
    [at <backup_server_name>]
    [density = <density_value>,
     blocksize = <number_bytes>,
     dumpvolume = <volume_name>,
     file = <file_name>]
  [[stripe on [compress::]<stripe_device>
    [at <backup_server_name>]
    [density = <density_value>,
     blocksize = <number_bytes>,
     dumpvolume = <volume_name>,
     file = <file_name>]
  [[stripe on [compress::]<stripe_device>
    [at <backup_server_name>]
    [density = <density_value>,
     blocksize = <number_bytes>,
     dumpvolume = <volume_name>,
     file = <file_name>]]...]]
  [with {
    density = <density_value>,
    blocksize = <number_bytes>,
    compression,
    dumpvolume = <volume_name>,
    file = <file_name>,
    [dismount | nodismount],
    [nounload | unload],
    notify = {client | operator_console}
    copyonly = <path_prefix>,
  }]]
```

Returns header or file information without loading the backup log:

```
load tran[saction] <database_name>
  from [compress::]<stripe_device>
    [at <backup_server_name>]
    [density = <density_value>,
     blocksize = <number_bytes>,
     dumpvolume = <volume_name>,
     file = <file_name>]
  [[stripe on [compress::]<stripe_device>
    [at <backup_server_name>]
    [density = <density_value>,
     blocksize = <number_bytes>,
     dumpvolume = <volume_name>,
     file = <file_name>]
  [[stripe on [compress::]<stripe_device>
    [at <backup_server_name>]
    [density = <density_value>,
     blocksize = <number_bytes>,
     dumpvolume = <volume_name>,
     file = <file_name>]]...]]
```

```

    file = <file_name>]]...]
[with {
  density = <density_value>,
  blocksize = <number_bytes>,
  compression,
  dumpvolume = <volume_name>,
  file = <file_name>,
  [dismount | nodismount],
  [nounload | unload],
  listonly [= full],
  headeronly,
  notify = {client | operator_console}
  until_time = <datetime>}}]

```

Loads a transaction log into an archive database:

```

load tran[saction] <database_name>
from <dump_device>
[[stripe on <stripe_device>] ... ]

```

(Tivoli Storage Manager only) Loads a copy of the transaction log when the Tivoli Storage Manager is licensed at your site.

```

load transaction <database_name>
from syb_tsm:[[-S <source_sever_name>][[-D <source_database_name>]
::]<object_name> [blocksize = <number_bytes>]
[stripe on syb_tsm:[[-S <source_sever_name>]
[-D <source_database_name>]::]<object_name>
[blocksize = <number_bytes>]]
[[stripe on syb_tsm:[[-S <source_sever_name>]
[-D <source_database_name>]::]<object_name>
[blocksize = <number_bytes>]]...]
[with {
  blocksize = <number_bytes>,
  passwd = <password>,
  listonly [= full],
  headeronly,
  notify = {client | operator_console},
  until_time = datetime
} ]

```

## Parameters

### <database\_name>

is the name of the database to receive data from a dumped backup copy of the transaction log. The log segment of the receiving database must be at least as large as the log segment of the dumped database. The database name can be specified as a literal, a local variable, or a parameter of a stored procedure. For archive databases, <database\_name> is the archive database into which you are loading the transaction log.

### compress::

invokes the decompression of the archived transaction log. See *Backing Up and Restoring User Databases* in the *System Administration Guide* for more information about the `compress` option.

### i Note

You should use the native "compression = <compress\_level>" option over the older "compress::<compression\_level>" option. If you use the native option for dump database, you do not need to use "compress::<compression\_level>" when loading your database.

#### from <stripe\_device>

is the name of the dump device from which you are loading the transaction log. For a list of supported dump devices, see the SAP ASE installation and configuration guides.

#### at <backup\_server\_name>

is the name of a remote Backup Server running on the machine to which the dump device is attached. For platforms that use interfaces files, the <backup\_server\_name> must appear in the interfaces file.

#### from <dump\_device>

is the local disk transaction log dump.

#### density = <density\_value>

overrides the default density for a tape device. **This option is ignored.**

#### blocksize = <number\_bytes>

overrides the default block size for a dump device. If you specify a block size on UNIX systems, it should be identical to that used to make the dump.

#### dumpvolume = <volume\_name>

is the volume name field of the ANSI tape label. load transaction checks this label when the tape is opened and generates an error message if the wrong volume is loaded.

#### file = <file\_name>

is the name of a particular database dump on the tape volume. If you did not record the dump file names when you made the dump, use listonly to display information about all the dump files.

#### stripe on <stripe\_device>

is an additional dump device. You can use up to 32 devices, including the device named in the to <stripe\_device> clause. The Backup Server loads data from all devices concurrently, reducing the time and the number of volume changes required.

#### compression

indicates that the log you are loading was compressed to a file on a remote server. You do not need to specify the compression level for load transaction.

The with compression option differs from the compress option, which you use to load a compressed log from a local file.

### i Note

You should use the native "compression = <compress\_level>" option over the older "compress::<compression\_level>" option. If you use the native option for dump database, you do not need to use "compress::<compression\_level>" when loading your database.

### **dismount | nodismount**

(on platforms that support logical dismount) determines whether tapes remain mounted. By default, all tapes used for a load are dismounted when the load completes. Use `nodismount` to keep tapes available for additional loads or dumps.

### **nounload | unload**

determines whether tapes rewind after the load completes. By default, tapes do not rewind, allowing you to make additional loads from the same tape volume. Specify `unload` for the last dump file to be loaded from a multidump volume. This rewinds and unloads the tape when the load completes.

### **listonly [= full]**

displays information about all the dump files on a tape volume, but **does not load the transaction log**. `listonly` identifies the database and device, the date and time the dump was made, and the date and time it can be overwritten. `listonly = full` provides additional details about the dump. Both reports are sorted by ANSI tape label.

After listing the files on a volume, the Backup Server sends a volume change request. The operator can either mount another tape volume or terminate the list operation for all dump devices.

In the current implementation, `listonly` overrides `headeronly`.

#### **⚠ Caution**

Do not use `load transaction` with `listonly` on 1/4-inch cartridge tape.

### **headeronly**

displays header information for a single dump file, but **does not load the database**. `headeronly` displays information about the first file on the tape unless you use the `file =<file_name>` option to specify another file name. The dump header indicates:

- Type of dump (database or transaction log)
- Database ID
- File name
- Date the dump was made
- Character set
- Sort order
- Page count
- Next object ID
- Checkpoint location in the log
- Location of the oldest `begin transaction` record
- Old and new sequence dates

### **notify = {client | operator\_console}**

overrides the default message destination.

- On operating systems that offer an operator terminal feature, volume change messages are always sent to the operator terminal on the machine on which the Backup Server is running. Use `client` to route other Backup Server messages to the terminal session that initiated the `dump database`.

- On operating systems (such as UNIX) that do not offer an operator terminal feature, messages are sent to the client that initiated the `dump database`. Use `operator_console` to route messages to the terminal on which the Backup Server is running.

**copyonly=<path\_prefix>**

extracts a transaction log file from a dump that is stored on a storage device, such as Tivoli Storage Manager or Legato (one file per device or stripe). Using `load tran <database_name> from <device>` with `copyonly=<path_prefix>` does not load pages from the dump in `<database_name>`, but rather, copies pages to device stripes using the path specified in the `copyonly` option. There are no layout or size restrictions for `<database_name>`, which need not match the dump that you are copying/loading. You may also use this to extract a dump from a compressed dump of the form `compress::<level>::<stripe>`.

Specify `<device>` in the form `name::name`.

**until\_time**

loads the transaction log up to a specified time in the transaction log. Only transactions committed before the specified time are saved to the database.

**syb\_tsm**

is the keyword that invokes the `libsyb_tsm.so` module that enables communication between Backup Server and TSM.

**<object\_name>**

is the name of the backup object on TSM server.

**-S <source\_server\_name>**

specifies the name of the source SAP ASE server when it is not the same as the target SAP ASE server. This parameter is required when the target server for the load operation is different from the source server used for the dump operation.

**-D <source\_database\_name>**

specifies the name of the source database when it is not the same as the target database. This parameter is required when the target database for the load operation is different from the source database used for the dump operation.

## Examples

### Example 1

Loads the transaction log for the database `pubs2` tape:

```
load transaction pubs2
  from "/dev/nrmt0"
```

### Example 2

Loads the transaction log for the `pubs2` database, using the Backup Server `REMOTE_BKP_SERVER`:

```
load transaction pubs2
  from "/dev/nrmt4" at REMOTE_BKP_SERVER
```

```
stripe on "/dev/nrmt5" at REMOTE_BKP_SERVER
stripe on "/dev/nrmt0" at REMOTE_BKP_SERVER
```

### Example 3

Loads the transaction log for `pubs2`, up to March 20, 2008, at 10:51:43:866 a.m.:

```
load transaction pubs2
  from "/dev/ntmt0"
  with until_time = "mar 20, 2008 10:51:43:866am"
```

### Example 4

Loads transactions from the TSM backup object "demo2.1" to the `testdb` database. The source and target databases are the same. See `dump transaction` for information:

```
load transaction testdb from "syb_tsm::demo2.1"
```

### Example 5

Loads transactions from the TSM backup object "obj1.1" when the target database (`pubs2`) is different from the source database (`testdb`):

```
load transaction pubs2 from "syb_tsm::
-D testdb::obj1.1"
```

## Usage

- If you use `sp_hidetext` followed by a cross-platform `dump` and `load`, you must manually drop and re-create all hidden objects.
- The `listonly` and `headeronly` options display information about the dump files without loading them.
- Dumps and loads are performed through Backup Server.

See also:

- For step-by-step instructions for restoring the system databases from dumps, see the *System Administration Guide*.
- *Backing Up and Restoring User Databases* in the *System Administration Guide*.
- `sp_dboption`, `sp_helpdb`, `sp_helpdevice`, `sp_hidetext`, `sp_volchange` in *Reference Manual: Procedures*

## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

## Permissions

The permission checks for `load transaction` differ based on your granular permissions settings.



## Setting Description

- Enabled** With granular permissions enabled, you must be the database owner, or a user with `load database privilege` or `own database privilege` on the database.
- Disabled** With granular permissions disabled, you must be the database owner, or a user with any of these roles:
- `sa_role`, or,
  - `replication_role`, or,
  - `oper_role`

## Auditing

You can enable `load` auditing option to audit this command. Values in `event` and `extrainfo` columns from the `sysaudits` table are:

Audit option	Event	Command or access audited	Information in <code>extrainfo</code> :
<code>load</code>	44	<code>load transaction</code>	<ul style="list-style-type: none"><li>• <b>Roles</b> – current active roles</li><li>• <b>Full command text</b> – full text of <code>load transaction</code> command</li></ul> <div data-bbox="922 1137 1394 1330" style="background-color: #f0f0f0; padding: 10px;"><p><b>i Note</b></p><p>Full command text is not printed for <code>load transaction</code> with <code>[headeronly listonly verifyonly]</code>.</p></div> <ul style="list-style-type: none"><li>• <b>Previous value</b> – NULL</li><li>• <b>Current value</b> – NULL</li><li>• <b>Other information</b> – NULL</li><li>• <b>Proxy information</b> – original login name, if set <code>proxy</code> is in effect</li></ul>

Full command text is included in `extrainfo`. For example:

```
sa_role sso_role oper_role sybase_ts_role mon_role; load tran tdb2 from
"/tmp/tdb2.log"; ; ; ; sa/ase;
```

For more information about auditing, see *Security Administration Guide > Auditing*.

## Related Information

[disk unmirror \[page 425\]](#)

[dump database \[page 470\]](#)

[dump transaction \[page 490\]](#)

[load database \[page 585\]](#)

[online database \[page 625\]](#)

## 1.92.1 load transaction Restrictions

Restrictions for using `load transaction`.

- You cannot load a dump that was generated on a version earlier than 11.9 server.
- Named pipes are supported as a backup device. However, Backup Server does not attempt to create a named pipe. Instead, you must create the named pipe externally before executing the `dump transaction` command (you need not do this for regular file).
- The database and transaction logs must be at the same release level.
- Load transaction logs in chronological order.
- You cannot load from the null device (on UNIX, `/dev/null`).
- You cannot use `load transaction` after an `online database` command that performs an upgrade. The correct sequence for upgrading a database is `load database`, `load transaction`, `online database`.
- Do not issue `online database` until all transaction logs are loaded. The command sequence is:
  1. Load database
  2. Load transaction (repeat as needed)
  3. Online databaseHowever, to load additional transaction logs while retaining read-only access to the database (a typical “warm backup” situation), use the `dump tran for standby_access` option to generate the transaction dumps. You can then issue `online database for standby_access` for read-only access.
- You cannot use the `load transaction` command in a user-defined transaction.

## 1.92.2 Restoring a Database

Restore a database.

- Load the most recent database dump
- Load, *in order*, all transaction log dumps made since the last database dump
- Issue `online database` to make the database available for public use

Each time you add or remove a cross-database constraint, or drop a table that contains a cross-database constraint, dump *both* of the affected databases.

### Caution

Loading earlier dumps of these databases can cause database corruption.

For more information on backup and recovery of SAP ASE databases, see the *System Administration Guide*. Alternatively, you can use the `sybrestore` utility to restore databases. See `sybrestore` in the *Utility Guide*.

## 1.92.3 Recovering a Database to a Specified Time

You can use the `until_time` option for most databases that can be loaded or dumped. `until_time` does not apply to databases such as `master`, in which the data and logs are on the same device. Also, you cannot use it on any database that has had a truncated log since the last `dump database`, such as `tempdb`.

The `until_time` option is useful for the following reasons:

- It enables you to have a database consistent to a particular time. For example, in an environment with a decision-support system (DSS) database and an online transaction processing (OLTP) database, the system administrator can roll the DSS database to an earlier specified time to compare data between the earlier version and the current version.
- If a user inadvertently destroys data, such as dropping an important table, you can use the `until_time` option to back out the errant command by rolling forward the database to a point just before the data was destroyed.

To effectively use the `until_time` option after data has been destroyed, you must know the exact time the error took place. You can find out by executing a `select getdate ()` command immediately after the error. For a more precise time using milliseconds, use the `convert` function, for example:

```
select convert (char (26), getdate (), 109)
```

```
-----  
Feb 26 1997 12:45:59:650PM
```

After you load a transaction log using `until_time`, the SAP ASE server restarts the database's log sequence. This means that until you dump the database again, you cannot load subsequent transaction logs after the `load transaction` using `until_time`. Dump the database before you dump another transaction log.

Only transactions that committed before the specified time are saved to the database. However, in some cases, transactions committed shortly after the `until_time` specification are applied to the database data. This may occur when several transactions are committing at the same time. The ordering of transactions may not be written to the transaction log in time-ordered sequence. In this case, the transactions that are out of time sequence are reflected in the data that has been recovered. The time should be less than a second.

For more information on recovering a database to a specified time, see the *System Administration Guide*.

Alternatively, you can use the `sybrestore` utility to restore a database to a point in time, within the range of time during which the database is backed up in the dump history files. See `sybrestore` in the *Utility Guide*.

## 1.92.4 Locking Users Out During Loads

When you are load a database, it cannot be in use.

`load transaction`, unlike `load database`, does not change the offline or online status of the database. `load transaction` leaves the status of the database the way it found it. `load database` sets the status of the database to "offline." No one can use the database while it is "offline." The "offline" status prevents users from accessing and changing the database during a load sequence.

## 1.92.5 Upgrading Database and Transaction Log Dumps

Restore and upgrade a user database dump from an earlier version to the most current version of SAP ASE.

1. Load the most recent database dump.
2. Load, *in order*, all transaction logs generated after the last database dump.
3. Use `online database` to do the upgrade.
4. Dump the newly upgraded database immediately after the upgrade, to create a dump that is consistent with the current version of SAP ASE.

## 1.92.6 Specifying Dump Devices

You can specify the dump device as a literal, a local variable, or a parameter to a stored procedure.

When loading from a local device, you can specify the dump device as:

- An absolute path name
- A relative path name
- A logical device name from the `sysdevices` system table

Backup Server resolves relative path names, using the current working directory in the SAP ASE server.

When loading across the network, specify the absolute path name of the dump device. (You cannot use a relative path name or a logical device name from the `sysdevices` system table.) The path name must be valid on the machine on which the Backup Server is running. If the name includes any characters other than letters, numbers or the underscore (`_`), you must enclose it in quotes.

Ownership and permissions problems on the dump device may interfere with use of load commands. `sp_addumpdevice` adds the device to the system tables, but does not guarantee that you can load from that device or create a file as a dump device.

You can run more than one load (or dump) at the same time, as long as each one uses a different physical device.

## 1.92.7 Backup Servers

You must have a Backup Server running on the same machine as your SAP ASE server. The Backup Server must be listed in the `master..sys.servers` table. This entry is created during installation or upgrade and should not be deleted.

If your backup devices are located on another machine so that you load across a network, you must also have a Backup Server installed on the remote machine.

## 1.92.8 Volume Names

Dump volumes are labeled according to the ANSI tape-labeling standard. The label includes the logical volume number and the position of the device within the stripe set.

During loads, Backup Server uses the tape label to verify that volumes are mounted in the correct order. This allows you to load from a smaller number of devices than you used at dump time.

### i Note

When dumping and loading across a network, you must specify the same number of stripe devices for each operation.

## 1.92.9 Changing Dump Volumes

If Backup Server detects a problem with the currently mounted volume, it requests a volume change by sending messages to either the client or its operator console. After mounting another volume, the operator notifies Backup Server by executing `sp_volchanged` on any SAP ASE server that can communicate with Backup Server.

## 1.92.10 Disk Mirroring

Disk mirroring creates a software mirror that immediately takes over when the primary device fails.

At the beginning of a load, the SAP ASE server passes the primary device name of each logical database device and each logical log device to the Backup Server. If the primary device has been unmirrored, the SAP ASE server passes the name of the secondary device instead. If any named device fails before the Backup Server completes its data transfer, the SAP ASE server aborts the load.

- If you attempt to unmirror any of the named devices while a `load transaction` is in progress, the SAP ASE server displays a message. The user executing `disk unmirror` can abort the load, or defer `disk unmirror` until after the load completes.
- Backup Server loads the data onto the primary device, then `load transaction` copies it to the secondary device. `load transaction` takes longer to complete if any database device is mirrored.

## 1.92.11 Loading a Transaction Log into an Archive Database

When you load a transaction log into an archive database, `load tran` runs the recovery redo pass. Modified and new database pages are written to the permanent changes segment. You must have enough space in the modified pages section to accommodate these changes.

If necessary, increase space for the modified pages section by using `alter database` to increase the normal database storage allocated to the archive database.

Unlike a traditional database, an archive database can be brought online in the middle of a load sequence without breaking the load sequence. When a traditional database is loaded and then brought online without using the `for standby_access` clause, it is no longer possible to load the next transaction log in the load sequence. An archive database however, can be brought online without the `for standby_access` clause and later, loaded with the next transaction log in the load sequence. This allows read-only operations like running consistency checks, at any time during the load sequence. This is possible because when loading a transaction log into the archive database, the SAP ASE server automatically removes the disposable changes segment from the modified pages section. This effectively reverts the archive database to its state after the previous load was done, thereby allowing the next transaction log in the sequence to be loaded.

## 1.93 lock table

Explicitly locks a table within a transaction.

### Syntax

```
lock table <table_name> in
    {share | exclusive} mode
    [wait [<numsecs>] | nowait]
```

### Parameters

**<table\_name>**

specifies the name of the table to be locked.

**share | exclusive**

specifies the type of lock, shared or exclusive, to be applied to the table or partition.

**wait <numsecs>**

specifies the number of seconds to wait, if a lock cannot be acquired immediately. If `<numsecs>` is omitted, specifies that the `lock table` command should wait until lock is granted.

**nowait**

causes the command to fail if the lock cannot be acquired immediately.

## Examples

### Example 1

Tries to acquire a shared table lock on the `titles` table. If a session-level wait has been set with `set lock wait`, the `lock table` command waits for that period of time; otherwise, the server-level wait period is used:

```
begin transaction
lock table titles in share mode
```

### Example 2

Tries to acquire an exclusive table lock on the `authors` table. If the lock cannot be acquired within 5 seconds, the command returns an informational message. Subsequent commands within the transaction continue as they would have without `lock table`:

```
begin transaction
lock table authors in exclusive mode wait 5
```

### Example 3

If a table lock is not acquired within 5 seconds, the procedure checks the user's role. If the procedure is executed by a user with `sa_role`, the procedure prints an advisory message and proceeds without a table lock. If the user does not have `sa_role`, the transaction is rolled back:

```
create procedure bigbatch
as
begin transaction
lock table titles in share mode wait 5
if @@error = 12207
begin
/*
** Allow SA to run without the table lock
** Other users get an error message
*/
if (proc_role ("sa_role") = 0)
begin
print "You cannot run this procedure at
this time, please try again later"
rollback transaction
return 100
end
else
begin
print "Couldn't obtain table lock,
proceeding with default locking."
end
end
/* more SQL here */
commit transaction
```

## Usage

- You can use `lock table` with an archive database.
- If you use `lock table` as the first statement after the `set chained on` command, this creates a new transaction.

- You cannot lock a table on which you previously executed the `dbcc tune(des_bind...)` command because the SAP ASE server does not allow shared or exclusive table locks on hot objects. For example, the SAP ASE server issues warning number 8242 if you:

- Create a table
- Run `dbcc tune (des_bin. . . )`. For example:

```
dbcc tune(des_bin, 4, new_table)
```

- Attempt to lock the table:

```
begin tran
lock table new_table in exclusive mode
go
```

```
Msg 8242, Level 16, State 1:
Server 'server01', Line 2:
The table 'new_table' in database 'big_db' is bound to metadata cache
memory. Unbind the table and retry the query later.
```

- You can use `lock table` only within a transaction. The table lock is held for the duration of the transaction.
- The behavior of `lock table` depends on the wait-time options that are specified in the command or that are active at the session level or server level.
- If the `wait` and `nowait` option are not specified, `lock table` uses either the session-level wait period or the server-level wait period. If a session-level wait has been set using `set lock wait`, it is used, otherwise, the server-level wait period is used.
- If the table lock cannot be obtained with the time limit (if any), the `lock table` command returns message 12207. The transaction is not rolled back. Subsequent commands in the transaction proceed as they would have without the `lock table` command.
- You cannot use `lock table` on system tables or temporary tables.
- You can issue multiple `lock table` commands in the same transaction.

## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

## Permissions

You must be the table owner. You must have `select` access permission on the table to use `lock table in share mode`. You must have `delete`, `insert`, or `update` access permission on the table to use `lock table in exclusive mode`.

## Auditing

This command is not audited.



## Related Information

[set](#) [page 732]

## 1.94 merge

Transfers rows from a source table into a target table.

- Inserts rows that are in the source and have no matching key columns in the target.
- Updates rows with key columns that already exist in the target with the values from the source row.

## Syntax

```
merge
into [[<database>.<owner>.<identifier> [as <table_alias>]
using [[<database>.<owner>.<identifier> [as <table_alias>]
    | (<select_query>) as <alias_name> [<column_list>]
on <merge_search_condition>
[ when matched [and <search_conditions> ]
  then {update set {<col_name> = <expression>} | delete} ]
[ when not matched [and <search_conditions> ]
  then insert [(<column_list>)] values (<value_list>)
```

## Parameters

**into** [[<database>.<owner>.<identifier> [as <table\_alias>]

specifies the target object as a table or updatable view as a table alias. The target can be a fully qualified name identifier or a short name identifier—does not include the database name and the owner name—and in which case the SAP ASE server uses the current database and the user or database owner.

You may also specify the table alias as an alternative to reference the target table.

**using** [[<database>.<owner>.<identifier> [as <table\_alias>] | (<select\_query>)]  
**as** <alias\_name> [<column\_list>]

specifies the source object as a table, view, or derived table. When the source object is:

- A table or view – use [[<database>.<owner>.<identifier>.
- A derived table – reference it by the `select` query, in the form of an alias name and an optional column list that defines the derived table.

**<merge\_search\_conditions>**

checks whether the row in the source table matches the row in the target table, and consists of a list of predicates such as "`<col_name> = <col_name>`".

### <search\_conditions>

are well-formed Boolean expressions used in the `matched/not matched` clauses.

### `update set {<col_name> = <expression>} | delete`

both options are always in the `matched` clause. `update` assigns new values to the matching row, while `delete` removes the current matching row.

### `insert [(<column_list>)] values (<value_list>)`

always appears in the `not matched` clause, and inserts the nonmatching row in the target table.

## Examples

### Example 1

Merges the `DailySales` table into `GlobalSales`:

```
merge into GlobalSales
  (Item_number, Description, Quantity) as G
using DailySales as D
ON D.Item_number = G.Item_number
when not matched
  then
    insert (Item_number, Description, Quantity )
    values (D.Item_number, D.Description, D.Quantity)
when matched
  then update set
    G.Quantity = G.Quantity + D.Quantity
```

### Example 2

Uses a derived table as the source table with dynamic parameter markers:

```
merge into GlobalSales as G
using (select ?, ?, ?) as
D (Item_number, Description, Quantity)
ON D.Item_number = G.Item_number
when not matched
  then
    insert (Item_number, Description, Quantity )
    values (D.Item_number, D.Description, D.Quantity)
when matched
  then update set
    G.Quantity = G.Quantity + D.Quantity
```

## Usage

- The target table can have a referential integrity constraint, as long as the data it merges does not violate the constraint.
- There are no specific optimization for `merge` queries with `on` clauses that reference constant Boolean expressions, such as `(1=0)` or `(1=1)`.
- The target columns referenced in the `on` clause cannot be in the `set` clause of the `update` action.

- Although you can invoke a `merge` statement from within a stored procedure, `update` and `insert` statements are not allowed within a scalar SQL function.
- The target table cannot be an updatable view with `instead of` triggers.
- The `merge` statements can be cached, and the literals in the `set` clause of the `update` action and in the `insert` value list in the `insert` action are the target of the literal parameterization process.
- The target table cannot be a proxy table.
- For each row in the source table, if the row:
  - Has a matching row in the target table and the search condition is evaluated to `true` – execute the `update` in the target table, or the corresponding row in the target table.
  - Has no matching row in the target table and the search condition is evaluated to `true` – insert the row in the target table.

The `merge` statement can have multiple `when matched` and `when not matched` clauses with different search conditions. The first `when` in the `when` clauses that has its condition satisfied runs the corresponding action; the rest are ignored.

- For each row in the target table, `merge` generates an error if it finds more than one matching row in the source table.
- SAP ASE includes bulk insert and parallel index updates for the insert portion of `merge into` statements, along with a run-time optimization for bulk insert.

Massive data loading and merging data from a transactional database into the data warehouse for increased analytics are common operations in the SAP® Business Information Warehouse (BW) environment. During the BW data-loading process query statement, `merge into` is frequently used to load data into an existing table or to update and delete existing rows.

This improves bulk-data performance for the `insert` portion of `merge into` statements when a large volume of data is loaded with all rows logged, with and without an index. Noticeable performance improvement occurs when the source and target tables use a join predicate resulting in more `insert` operations, as opposed to `update` and `delete` operations. Improvements may not be significant for small source tables.

Additionally, SAP ASE automatically chooses the bulk insert, and therefore parallel index updates, for `insert select`, `batch insert` and `merge into` based on the run-time statistics. In versions of SAP ASE earlier than 15.7 SP100, this choice was hinted by the `set` command and optimizer hints.

## Permissions

Any user who has `select` permission on the source object, and `insert`, `update`, or `delete` permission on the target object can use `merge`.

## Auditing

This command is not audited.

## 1.95 mount

Attaches a database to a destination or secondary SAP ASE server.

`mount` decodes the information in the manifest file and makes the set of databases available. `mount` differs from other copying procedures such as the `bcp` bulk copy utility in that all required supporting activities are executed, including adding database devices, if necessary, and activating them, creating the catalog entries for the new databases, and recovering them.

If you are using different device names at the destination SAP ASE server when mounting the databases, use `mount` with `listonly` and modify the device path names at the destination server, then use `mount` to actually mount the databases.

### Note

For every login that is allowed access to a database on the original SAP ASE server, it is more convenient to have a corresponding login for the same `suid` at the destination SAP ASE server, to avoid user ID reconciliation issues.

For permissions to remain unchanged, the login maps at the destination SAP ASE server must be identical to that on the source SAP ASE server. For more information on login maps, see *Managing Remote Servers* in *System Administration Guide, Volume 1*.

## Syntax

```
mount database all | <database_mapping>[, <database_mapping>, ...]
  from "<manifest_file>"
  [using <device_mapping> [, <device_mapping>...]]
  [with listonly |<dbid_option> [, <dbid_option> ...]]
<database_mapping>:
  <origdbname> as <newdbname>
  | <newdbname> = <origdbname>
  | <origdbname>
  | <newdbname>
<device_mapping>
  <logical_device_name> as <new_physical_name>
  | <new_physical_name> = <logical_device_name>
  | <original_physical_name>
  | <new_physical_name>
```

## Parameters

### <manifest\_file>

the manifest file is the binary file that describes the databases that are present on a set of database devices.

Operations that can perform character translations of the file contents (such as `ftp`) corrupt the manifest file unless performed in binary mode.

## <dbid\_option>

- `fixdbid` – fixes the database ID stored in the allocation pages to match the target database ID.
- `allow_dbid_mismatch` – avoids raising a device validation error due to multiple database IDs found in the allocation pages.

## Examples

### Example 1

Finds the path names listed on the manifest file from the source SAP ASE server:

```
mount database all from "/data/sybase2/mfile1" with listonly
go
```

```
[database]
  mydb
[device]
  "/data/sybase1/d0.dbs" = "1dev1"
  "/data/sybase2/d14.dbs" = "1dev13"
```

When you use the path names different from the source ones, verify or modify them to meet your criteria at the destination SAP ASE server.

### Example 2

After the database devices are copied to the secondary SAP ASE server, you then mount it:

```
mount database all from "/data/sybase2/mfile1" using      "/data/sybase2/
d0.dbs" = "1dev1",
  "/data/sybase2/d14.dbs" = "1dev13"
```

When the `mount` process has completed, the databases are still offline. Use the `online database` command to bring them online. You need not restart the server.

### Example 3

The destination server can be the same as the source server. In this case, the database names must be mapped to a different name, and the logical device names are internally renamed.

1. Create an exact copy of database `mydb` in the same server:

```
1> quiesce database mydb_tag hold mydb for external dump to
  "/data/mydb.manifest"
2> go
```

2. Copy the OS file:

```
$ cp /data/sybase2/mydb.dbs /data/sybase2/mydb_copy.dbs
```

3. You can now mount it as a copy:

```
1> quiesce database mydb_tag release
2> go
1> mount database mydb as mydb_copy
2> from "/data/mydb.manifest"
3> using mydb_dev as "/data/sybase2/mydb_copy.dbs"
```

```
3> go
```

The physical device `//data/sybase2/mydb_copy.dbs/` is automatically assigned a machine-generated logical name with the format `<Cccc$<mydb_dev>` where:

- `<C>` – is [A–Z]
- `<c>` – is [A–Z, 0–9], and refers to the encoded logical device number
- `<mydb_dev>` – contains up to 26 characters from the old logical device name.

Database IDs for the transported databases should not exist on the destination SAP ASE server. Because the database has been mounted on the same server, the database ID had to be changed. The allocation pages in the mounted device keep the original database ID, and that information is used by the `disk refit` command. Use the `dbcc checkalloc` command to reconcile the `dbid` after running `mount database` so that `disk refit` can work on the mounted devices. Run `checkalloc` if the database is not being mounted for temporary use.

## Usage

- The `using` clause allows you to define a mapping via the “=” sign or the “as” clause.
- If there are more than one device, a mapping can be one using “=” and another using “as.”
- You can map devices by name in both databases and devices, specifying both logical and physical, and by order. If a database is mapped by name, all databases must be mapped by name and vice versa. The same happens for devices.
- You cannot `mount` a subset of a transported set of databases at the destination SAP ASE server; all databases and their devices in the manifest file must be mounted together.
- When executing the `mount` command at the destination SAP ASE server:
  - The page size in the destination SAP ASE server must be equal to the page size in the source SAP ASE server.
  - There must be enough devices configured at the destination SAP ASE server to successfully add all the devices belonging to the mounted databases.
  - If the logical device you are mounting from the source SAP ASE server has the same name as the logical device on the destination SAP ASE server, these devices are automatically renamed unless you include an alias with the `mount` command.  
If the physical device name already exists on the destination SAP ASE server, you must rename the physical device name on the source SAP ASE server at the operating system level and provide the new physical device name with the `mount` command.
  - The log version must be the same in the source and destination SAP ASE servers.
  - You cannot mount a database from an SAP ASE server with a higher major version number. For example, you cannot mount a 15.0 version database on a 12.5.x version of SAP ASE.
  - The platforms of the source and destination SAP ASE servers must be the same.
  - Differences in the sort order or character set are resolved by rules followed by `load database`. A database with a different character set can be mounted only if the sort order is binary.
- You can issue a `mount` with external dump on servers that have mirroring enabled. However:
  - Devices that are mirrored in the source server are not mirrored in the target.
  - The physical file from the active disk is stored in the manifest file.

`mount database` and `unmount database` are supported in the Cluster Edition. If an instance fails while one of these commands is in progress, the command may abort. In this case, the user must reissue `mount database` or `unmount database` when the instance failover recovery is complete.

Once databases are mounted on the destination SAP ASE server, certain settings are cleared on the mounted database:

- Replication is turned off.
- Audit settings are cleared and turned off.
- CIS options, default remote location, and type are cleared.
- Cache bindings are dropped for both the mounted databases and their objects.
- Recovery order is dropped for the mounted databases and becomes the default `dbid` order.

System considerations:

- You cannot use the `mount` command in a transaction.
- You cannot `mount` a database on server configured for high availability.

When you `mount` databases onto an SAP ASE server, if you change the `dbid` of the database you are mounting, all procedures are marked for recompilation in the database. This increases the time it takes to recover the database at the destination, and delays the first execution of the procedure.

The database ID is also stored in the allocation pages of the database and remains unchanged. In this case, SAP ASE will report this message:

```
MOUNT DATABASE: A new database id was required for database 'db' in order to
mount it.
DBCC CHECKALLOC must be run on this database to make corrections.
```

To avoid having to run the full version of `dbcc checkalloc` to fix the database ID, you can use the option `with fixdbid`. When this option is provided, `dbcc checkalloc` will only read the allocation pages and fix those with an incorrect database ID.

In case the database ID is not fixed, after the database is mounted and it is extended using `alter database`, the allocation pages will then have two different IDs. If this database is unmounted and mounted again, the following error could be raised:

```
MOUNT DATABASE: Failed to validate the devices.
The device allocations are not consistent with the descriptions in the manifest
file.
```

To avoid this issue, you can use the option `with allow_dbid_mismatch`.

For renaming devices, the manifest file contains the device paths known to the source SAP ASE server that created the manifest file. If the destination SAP ASE server accesses the devices with a different path, you can specify the new path to the `mount` command.

1. Use the `mount` command with `listonly` to display the old path:

```
mount database all from "/work2/Mpubs_file" with listonly
go
```

```
[database]
  mydb
[device]
  "/work2/Devices/pubdat.dat" = "pubs2dat"
```

- If the new path for the device `pubs2dat` is `/work2/Devices/pubsdevice.dat` (the devices path in Windows), specify the new device in the `mount` command:

```
mount database all from "/work2/Mpubs_file" using
"/work2/datadevices/pubsdevice.dat" = "pubs2dat"
```

If the logical device names exist in the destination server, they are renamed using an automatically generated unique name.

See also *Database Mount and Unmount* in *System Administration Guide: Volume 2*.

## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

## Permissions

The permission checks for `mount` differ based on your granular permissions settings.

**Setting**    **Description**

**Enabled**    With granular permissions enabled, you must be a user with `mount any database` privilege.

**Disabled**    With granular permissions disabled, you must be a user with `sa_role` or `oper_role`.

## Auditing

You can enable `mount` auditing option to audit this command. Values in `event` and `extrainfo` columns from the `sysaudits` table are:

Audit option	Event	Command or access audited	Information in <code>extrainfo</code> :
<code>mount</code>	101	<code>mount database</code>	<ul style="list-style-type: none"> <li><i>Roles</i> – current active roles</li> <li><i>Full command text</i> – full text of <code>mount database</code> command</li> <li><i>Previous value</i> – NULL</li> <li><i>Current value</i> – NULL</li> <li><i>Other information</i> – NULL</li> <li><i>Proxy information</i> – original login name, if set <code>proxy</code> is in effect</li> </ul>

Full command text is included in `extrainfo`. For example:

```
sa_role sso_role oper_role sybase_ts_role mon_role; mount database all from
```



```
"/data/sybase2/mfile1" with listonly; ; ; ; sa/ase;
```

For more information about auditing, see *Security Administration Guide > Auditing*.

## Related Information

[quiesce database \[page 643\]](#)

[unmount \[page 816\]](#)

## 1.96 online database

Marks a database available for public use after a normal load sequence; if needed, upgrades a loaded database to the current version of SAP ASE; brings a database online after loading a transaction log dumped with the `for standby_access` option. You can also use `online database` to bring an archive database online.

### Syntax

```
online database <database_name> [for standby_access]
```

### Parameters

**<database\_name>**

specifies the name of the database to be brought online.

**for standby\_access**

brings the database online on the assumption that the database contains no open transactions.

### Examples

#### Example 1

Makes the `pubs2` database available for public use after a load sequence completes:

```
online database pubs2
```

## Example 2

Brings the database `inventory_db` online. Used after loading `inventory_db` with a transaction-log dump obtained through `dump tran...with standby_access`:

```
online database inventory_db for standby_access
```

## Usage

- `online database` brings a database online for general use after a normal database or transaction log load sequence.
- When `load database` is issued, the database's status is set to "offline." The offline status is set in the `sysdatabases` system table and remains set until `online database` completes.
- Do *not* issue `online database` until all transaction logs are loaded. The command sequence is:
  - `load database`
  - `load transaction` (there may be more than one `load transaction`)
  - `online database`
- If you execute `online database` against a currently online database, no processing occurs and no error messages are generated.
- You can only use `online database...for standby_access` with a transaction log that was dumped using `dump transaction...with standby_access`. If you use `online database...for standby_access` after loading a transaction log that was dumped without using `dump transaction...with standby_access`, `online database` generates an error message and fails.
- You can use `sp_helpdb` to find out whether a database is currently online, online for standby access, or offline.

When upgrading databases:

- `online database` initiates, if needed, the upgrade of a loaded database and transaction log dumps to make the database compatible with the current version of SAP ASE. After the upgrade completes, the database is made available for public use. If errors occur during processing, the database remains offline.
- `online database` is required only after a database or transaction log load sequence. It is not required for new installations or upgrades. When you upgrade SAP ASE to a new version, all databases associated with that server are automatically upgraded.
- `online database` upgrades only version 12.5.4 or later user databases.
- After you upgrade a database with `online database`, dump the newly upgraded database to create a dump that is consistent with the current version of SAP ASE. You must dump the upgraded database before you can issue a `dump transaction` command.

For archive databases:

- The `online database <database_name>` command performs undo recovery during which modified and allocated pages may be remapped to the modified pages section.
- You do not need to bring a database online if it has been loaded with `norecovery`, since the load automatically brings the database online without running the recovery undo pass.

See also `sp_helpdb` in *Reference Manual: Procedures*.

## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

## Permissions

The permission checks for `online database` differ based on your granular permissions settings.

Setting	Description
---------	-------------

<b>Enabled</b>	With granular permissions enabled, you must be the database owner, or a user with <code>online database privilege</code> or <code>own database privilege</code> on the database.
----------------	--

<b>Disabled</b>	With granular permissions disabled, you must be the database owner, or a user with any of these roles:
-----------------	--

- `sa_role`, or,
- `replication_role`, or,
- `oper_role`

## Auditing

You can enable `security` auditing option to audit this command. Values in `event` and `extrainfo` columns from the `sysaudits` table are:

Audit option	Event	Command or access audited	Information in <code>extrainfo</code> :
<code>security</code>	83	<code>online database</code>	<ul style="list-style-type: none"><li>• <i>Roles</i> – current active roles</li><li>• <i>Full command text</i> – full text of <code>online database</code> command</li><li>• <i>Previous value</i> – NULL</li><li>• <i>Current value</i> – NULL</li><li>• <i>Other information</i> – NULL</li><li>• <i>Proxy information</i> – original login name, if set <code>proxy</code> is in effect</li></ul>

Full command text is included in `extrainfo`. For example:

```
sa_role sso_role oper_role sybase_ts_role mon_role; online database
pubs2; ; ; ; ;
sa/ase;
```

For more information about auditing, see *Security Administration Guide > Auditing*.

## Related Information

[dump database \[page 470\]](#)

[dump transaction \[page 490\]](#)

[load database \[page 585\]](#)

[load transaction \[page 603\]](#)

## 1.97 open

Opens a cursor for processing.

### Syntax

```
open <cursor_name>
```

### Parameters

**<cursor\_name>**

is the name of the cursor to open.

### Examples

#### Example 1

Opens the cursor named `authors_crshr`:

```
open authors_crshr
```

### Usage

- `open` opens a cursor. Cursors allow you to modify or delete rows on an individual basis. You must first open a cursor to use the `fetch`, `update`, and `delete` statements. For more information about cursors, see the *Transact-SQL User's Guide*.
- `open` includes the following considerations in an in-memory row storage environment:

- Opening a `read` cursor on multiversion concurrency controlled or on-disk multiversion concurrency controlled-enabled tables using any snapshot isolation level materializes all affected rows.
- Opening an `update` cursor on multiversion concurrency controlled or on-disk multiversion concurrency controlled-enabled tables that use `statement snapshot` or `transaction snapshot` isolation levels materializes all affected rows and keeps an `UP_ROW` lock. The `UP_ROW` lock is upgraded to an `EX_ROW` lock if the row is updated using the cursor.
- Materializing rows requires disk space.
- The SAP ASE server returns an error message if the cursor is already open or if the cursor has not been created with the `declare cursor` statement.
- Opening the cursor causes the SAP ASE server to evaluate the `select` statement that defines the cursor (specified in the `declare cursor` statement) and makes the cursor result set available for processing.
- When the cursor is first opened, it is positioned before the first row of the cursor result set.
- You can use `open` with an archive database.
- When you set the chained transaction mode, the SAP ASE server implicitly begins a transaction with the `open` statement if no transaction is currently active.

## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

## Permissions

`open` permission defaults to all users.

## Auditing

This command is not audited.

## Related Information

[close \[page 122\]](#)

[declare cursor \[page 384\]](#)

[fetch \[page 513\]](#)

## 1.98 order by Clause

Returns query results in the specified columns in sorted order.

### Syntax

```
[<Start of> select <statement>]
```

```
[order by  
  { [<table_name>.| <view_name>.]  
    <column_name> | <select_list_number> | <expression>  
    [asc | desc]  
  [, { [<table_name>.| <view_name>.]  
    <column_name> | <select_list_number> | <expression>  
    [asc | desc]]...]
```

```
[<End of> select <statement>]
```

### Parameters

#### order by

sorts the results by columns.

#### asc

sorts the results in ascending order. If you do not specify `asc` or `desc`, `asc` is assumed.

#### desc

sorts the results in descending order.

### Examples

#### Example 1

Selects the titles with a price that is greater than \$19.99, and lists them with the titles in alphabetical order:

```
select title, type, price  
from titles  
where price > $19.99  
order by title  
title  
      type          price  
-----  
But Is It User Friendly?  
    popular_comp          22.95  
Computer Phobic and Non-Phobic Individuals: Behavior Variations
```

psychology	21.59
Onions, Leeks, and Garlic: Cooking Secrets of the Mediterranean	
trad_cook	20.95
Secrets of Silicon Valley	
popular_comp	20.00

### Example 2

Lists the books from the `titles` table, in descending alphabetical order of the type, and calculates the average price and advance for each type:

```
select type, price, advance
from titles
order by type desc
compute avg (price), avg (advance) by type
```

### Example 3

Lists the title IDs from the `titles` table, with the advances divided by the total sales, ordered from the lowest calculated amount to the highest:

```
select title_id, advance/total_sales
from titles
order by advance/total_sales
title_id
-----
MC3026          NULL
PC9999          NULL
MC2222          0.00
TC4203          0.26
PS3333          0.49
BU2075          0.54
MC3021          0.67
PC1035          0.80
PS2091          1.11
PS7777          1.20
BU1032          1.22
BU7832          1.22
BU1111          1.29
PC8888          1.95
TC7777          1.95
PS1372          18.67
TC3218          18.67
PS2106          54.05
```

### Example 4

Lists book titles and types in order by the type, renaming the columns in the output:

```
select title as BookName, type as Type
from titles
order by Type
```

## Usage

- `order by` returns query results in the specified columns in sorted order. `order by` is part of the `select` command.
- In Transact-SQL, you can use `order by` to sort items that do not appear in the `select` list. You can sort by a column heading, a column name, an expression, an alias name (if specified in the `select` list), or a number representing the position of the item in the `select` list (`<select_list_number>`).

- If you sort by `<select_list_number>`, the columns to which the `order by` clause refers must be included in the `select` list, and the `select` list cannot be `*` (asterisk).
- Use `order by` to display your query results in a meaningful order. Without an `order by` clause, you cannot control the order in which the SAP ASE server returns results.

See also `sp_configure`, `sp_helpsort`, `sp_lock`, `sp_sysmon` in *Reference Manual: Procedures*.

## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

Specifying new column headings in the `order by` clause of a `select` statement when the `union` operator is used is a Transact-SQL extension.

The behavior of `order by` when identical table column name and column alias name exist is a vendor-specific extension of the ANSI SQL standard.

## Auditing

This command is not audited.

## Related Information

[compute Clause \[page 125\]](#)

[declare \[page 382\]](#)

[group by and having Clauses \[page 558\]](#)

[select \[page 696\]](#)

[set \[page 732\]](#)

[where Clause \[page 855\]](#)

### 1.98.1 order by Clause Restrictions

Restrictions for using the `order by` clause.

- The maximum number of columns allowed in an `order by` clause is 400.
- You cannot use `order by` on `text`, `unitext`, or `image` datatype columns.
- Subqueries and view definitions cannot include an `order by` clause (or a `compute` clause or the keyword `into`). Conversely, you cannot use a subquery in an `order by` list.
- You cannot update the result set of a server- or language- type cursor if it contains an `order by` clause in its `select` statement. For more information about the restrictions applied to updatable cursors, see the *Transact-SQL User's Guide*.



- If you use `compute by`, you must also use an `order by` clause. The expressions listed after `compute by` must be identical to or a subset of those listed after `order by`, must be in the same left-to-right order, must start with the same expression, and must not skip any expressions. For example, if the `order by` clause is:

```
order by a, b, c
```

the `compute by` clause can be any (or all) of these:

```
compute by a, b, c
compute by a, b
compute by a
```

You can also use the keyword `compute` can be used without `by` to generate grand totals, grand counts, and so on. In this case, `order by` is optional.

## 1.98.2 Behavior of `order by` When Identical Table Column Name and Column Alias Name Exist

The SAP ASE server interprets a column name in the `order by` clause as the alias name under several specific conditions.

- The `order by` clause contains a reference to a qualified column name (that is, `order by <table>.<column>`).
- Both the table column name and alias name exist.
- The names for both the table column and alias are identical to the column name in the `order by` clause.

In this example, the result set from the two queries differ, even though the `order by` clause is identical; yet, the `order by` clause refers to a different column in both cases:

```
create table t (A int, B char(3))
insert into t (A, B) values(1, 'az')
insert into t (A, B) values(2, 'bb')
go
/* t.B refers to the table column B */
select A, reverse(B) as C from t order by t.B
go
/* t.B refers to the alias column B */
select A, reverse(B) as B from t order by t.B
go
```

```
A C
-----
1 za
2 bb
(2 rows affected)
A B
-----
2 bb
1 za
(2 rows affected)
```

This behavior occurs because the SAP ASE server allows the `order by` clause to reference an alias column name that is qualified by the table name. When a base table column also exists with the same column name as the alias column, the SAP ASE server gives precedence to the alias column.

## 1.98.3 Collating Sequences

The sort order (collating sequence) on your SAP ASE server determines how your data is sorted.

With `order by`, null values precede all others.

The sort order choices are binary, dictionary, case-insensitive, case-insensitive with preference, and case- and accent-insensitive. Sort orders that are specific to national languages may also be provided.

`sp_helpsort` reports the sort order installed on the SAP ASE server.

The effect of sort order choices are:

SAP ASE Sort Order	Effects on <code>order by</code> Results
Binary order	Sorts all data according to the numeric byte-value of each character in the character set. Binary order sorts all uppercase letters before lowercase letters. Binary sort order is the only option for multibyte character sets.
Dictionary order	Sorts uppercase letters before their lowercase counterparts (case-sensitive). Dictionary order recognizes the various accented forms of a letter and sorts them after the unaccented form.
Dictionary order, case-insensitive	Sorts data in dictionary order but does not recognize case differences.
Dictionary order, case-insensitive with preference	Sorts an uppercase letter in the preferred position, before its lowercase version. It does not recognize case difference when performing comparisons (for example, in <code>where</code> clauses).
Dictionary order, case- and accent-insensitive	Sorts data in dictionary order, but does not recognize case differences; treats accented forms of a letter as equivalent to the associated unaccented letter. This sort order intermingles accented and unaccented letters in sorting results.

## 1.98.4 Sort Rules

When two rows have equivalent values in the SAP ASE sort order, rules are used to order the rows.

- The values in the columns named in the `order by` clause are compared.
- If two rows have equivalent column values, the binary value of the entire rows is compared byte by byte. This comparison is performed on the row in the order in which the columns are stored internally, not the order of the columns as they are named in the query or in the original `create table` clause. In brief, data is stored with all the fixed-length columns, in order, followed by all the variable-length columns, in order.
- If rows are equal, row IDs are compared.

Given this table:

```
create table sortdemo (lname varchar (20),
                      init char (1) not null)
```

And this data:

```
lname      init
```

```

-----
Smith      B
SMITH     C
smith     A

```

You get these results when you order by `<lname>`:

```

lname      init
-----
smith     A
Smith     B
SMITH     C

```

Since the fixed-length `char` data (the `init` column) is stored first internally, the `order by` sorts these rows based on the binary values "Asmith", "BSmith," and "CSMITH".

However, if the `init` is of type `varchar`, the `<lname>` column is sorted first, and then the `init` column. The comparison takes place on the binary values "SMITHC", "SmithB", and "smithA", and the rows are returned in that order.

## 1.98.5 Descending Scans

Use of the keyword `desc` in an `order by` clause allows the query optimizer to choose a strategy that eliminates the need for a worktable and a sort step to return results in descending order.

This optimization scans the page chain of the index in reverse order, following the previous page pointers on each index page.

- To use this optimization, the columns in the `order by` clause must match the index order. They can be a subset of the keys, but must be a prefix subset, that is, they must include the first keys. You cannot use the descending scan optimization if the columns named in the `order by` clause are a superset of the index keys.
 

If the query involves a join, all tables can be scanned in descending key order, as long as the requirements for a prefix subset of keys are met. You can also use descending scan optimization for one or more tables in a join, while other tables are scanned in ascending order.
- If other user processes are scanning forward to perform updates or deletes, performing descending scans can cause deadlocks. Deadlocks may also be encountered during page splits and shrinks. You can use `sp_sysmon` to track deadlocks on your server, or you can use the configuration parameter `print deadlock information` to send deadlock information to the error log.
- If your applications must return results in descending order, but the descending scans optimization creates deadlock problems, some possible workarounds are:
  - Use `set transaction isolation level 0` scans for descending scans. For more information on the effect of isolation level 0 reads, see the `set` command, and *Using Locking Commands in Performance and Tuning Guide: Locking*.
  - Disable descending scan optimization with the configuration parameter `allow backward scans so` that all queries that use `desc` scan the table in ascending order and sort the result set into descending order. See the *System Administration Guide*.
  - Break problematic descending scans into two steps, selecting the required rows into a temporary table in ascending order in the first step, and selecting from the temporary table in descending order in the second step.
- If a backward scan uses a clustered index that contains overflow pages because duplicate key values are present, the result set returned by the descending scan may not be in exact reverse order of the result set

that is returned with an ascending scan. The specified key values are returned in order, but the order of the rows for the identical keys on the overflow pages may be different. For an explanation of how overflow pages in clustered indexes are stored, see *Indexes* in *Performance and Tuning Guide: Basics*.

## 1.99 prepare database

Provides a period of time during which you can perform a mirror split or snapshot without suspending transactional activity.

### Syntax

```
prepare database <tag_name> hold <database_list>
    [for external dump [to <manifest_file>]]
    [with override, quiesce]
prepare database <tag_name> release
```

### Parameters

#### <tag\_name>

is a user-defined name that designates the list of databases to `hold` or `release`. The tag name must be unique across the server for all active `prepare database` commands. Active `quiesce database` and `prepare database` commands can share the same tag name, but both are considered to be independent operations.

#### hold

when used with to `<manifest_file>` clause, holds the database and creates a manifest file.

#### ⚠ Caution

Since the manifest file is binary, operations that perform character translations of the file contents (such as `ftp`) corrupt the file unless performed in binary mode.

#### <database\_list>

is the list of the databases included in the `prepare database hold` command.

#### for external dump

specifies that, when the `hold` completes, you physically copy all affected database devices, using some facility external to the SAP ASE server. The copy operation serves as a replacement for the combination of `dump database` and `load database`.

#### <manifest\_file>

a binary file that describes the databases that are present on a set of database devices. The manifest file is used if the copy of the database is to be mounted on another server

using `mount database`. The manifest file can be created only if the set of databases that occupy those devices are isolated, self-contained on those devices.

#### with `override`

overrides any restrictions that prevent you from successfully executing `prepare database` on a database. Specifically, makes sure that semantic issues with the manifest file do not abort the command

#### with `quiesce`

drains prepared transactions in the database as part of the `hold` phase, then prevents writes to the database once the hold is complete. By default, `prepare database` does not quiesce the database. `prepare database ... with quiesce` is equivalent to using the `quiesce database` command.

## Examples

### Quiescing the `ordersdb` database

Provides a period of time during which you can perform a mirror split or snapshot on the `ordersdb` database without suspending transactional activity:

```
prepare database tag hold ordersdb with quiesce
prepare database tag release
```

This command performs the same task as issuing:

```
quiesce database tag hold ordersdb
quiesce database tag release
```

## Usage

- `prepare database` does not suspend transactional activity unless the you specify `with quiesce`.
- You can make database copies available with the `mount database` command on a secondary installation or by starting a copy of an entire installation with the `dataserver -q` option .
- If you execute a `dump database` or `dump transaction` command on a database that was held by a `prepare database hold` command, the SAP ASE server blocks those commands until the database is released with `prepare database release`.
- `prepare database` does not perform any backup operations. Instead, it puts the database in a state that allows for an external backup of the database device files. This external backup is consistent and can be used to recover the databases to a consistent state. You can load transaction log dumps to a database recovered from an external dump.

## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

## Permissions

The permission checks for `prepare database` differ based on your granular permissions settings.

Setting	Description
---------	-------------

<b>Enabled</b>	With granular permissions enabled, you must be a user with <code>quiesce any database</code> privilege.
----------------	---

<b>Disabled</b>	With granular permissions disabled, you must be a user with <code>sa_role</code> .
-----------------	--

## Auditing

You can enable `quiesce` auditing option to audit this command. Values in `event` and `extrainfo` columns from the `sysaudits` table are:

Audit option	Event	Command or access audited	Information in <code>extrainfo</code> :
<code>quiesce</code>	96	<code>prepare database</code>	<ul style="list-style-type: none"><li>• <i>Roles</i> – current active roles</li><li>• <i>Full command text</i> – full text of <code>prepare database</code> command</li><li>• <i>Previous value</i> – NULL</li><li>• <i>Current value</i> – NULL</li><li>• <i>Other information</i> – NULL</li><li>• <i>Proxy information</i> – original login name, if a set <code>proxy</code> is in effect</li></ul>

Full command text is included in `extrainfo`. For example:

```
sa_role sso_role oper_role sybase_ts_role mon_role; prepare database tag1
hold testldb with quiesce; ; ; ; sa/ase;
```

For more information about auditing, see *Security Administration Guide > Auditing*.

## 1.100 prepare transaction

Used by DB-Library in a two-phase commit application to see if a server is prepared to commit a transaction.

### Syntax

```
prepare tran[saction]
```

### Usage

See the *Open Client DB-Library Reference Manual*.

### Standards

ANSI SQL – Compliance level: Transact-SQL extension.

### Permissions

Any user can execute `prepare transaction`. Permission checks do not differ based on the granular permissions settings.

### Auditing

This command is not audited.

### Related Information

[begin transaction \[page 116\]](#)

[rollback \[page 690\]](#)

[save transaction \[page 694\]](#)

## 1.101 print

Prints a user-defined message on the user's screen.

### Syntax

```
print
  {<format_string> | @<local_variable> |
  @@<global_variable>}
  [, <arg_list>]
```

### Parameters

#### <format\_string>

can be either a variable or a string of characters. The maximum length of <format\_string> is 1023 bytes.

Format strings can contain up to 20 unique placeholders in any order. These placeholders are replaced with the formatted contents of any arguments that follow <format\_string> when the text of the message is sent to the client.

To allow reordering of the arguments when format strings are translated to a language with a different grammatical structure, placeholders are numbered. A placeholder for an argument appears in this format: “ %<nn> !”—a percent sign (%), followed by an integer from 1 to 20, followed by an exclamation point (!). The integer represents the argument number in the string in the argument list. “%1!” is the first argument in the original version, “%2!” is the second argument, and so on.

Indicating the position of the argument in this way makes it possible to translate correctly, even when the order in which the arguments appear in the target language is different.

For example, assume the following is an English message:

```
%1! is not allowed in %2!.
```

The German version of this message is:

```
%1! ist in %2! nicht zulässig.
```

The Japanese version of this message is:

**%2! の中で %1! は許されません。**



In this example, "%1!" represents the same argument in all three languages, as does "%2!". This example shows the reordering of the arguments that is sometimes necessary in the translated form.

#### @<local\_variable>

must be of type `char`, `nchar`, `varchar`, or `nvarchar`, and must be declared within the batch or procedure in which it is used.

#### @@<global\_variable>

must be of type `char` or `varchar`, or be automatically convertible to these types, such as @@<version>. Currently, @@<version> is the only character-type global variable.

#### <arg\_list>

may be a series of either variables or constants separated by commas. <arg\_list> is optional unless a format string containing placeholders of the form "<%nn>!" is provided. In that case, the <arg\_list> must have at least as many arguments as the highest numbered placeholder. An argument can be any datatype except `text` or `image`; it is converted to a character datatype before being included in the final message.

## Examples

### Example 1

Prints "Berkeley author" if any authors in the `authors` table live in the 94705 postal code:

```
if exists (select postalcode from authors
where postalcode = '94705')
print "Berkeley author"
```

### Example 2

Declares a variable, assigns a value to the variable, and prints the value:

```
declare @msg char (50)
select @msg = "What's up, doc?"
print @msg
```

```
What's up, doc?
```

### Example 3

Demonstrates the use of variables and placeholders in messages:

```
declare @tablename varchar (30)
select @tablename = "titles"
declare @username varchar (30)
select @username = "ezekiel"
print "The table '%1!' is not owned by the user '%2!'.", @tablename, @username
```

```
The table 'titles' is not owned
by the user 'ezekiel.'
```

## Usage

- The maximum output string length of `<format_string>` plus all arguments after substitution is 1023 bytes.
- If you use placeholders in a format string, keep this in mind: for each placeholder `<n>` in the string, the placeholders 1 through `<n-1>` must also exist in the same string, although they do not have to be in numerical order. For example, you cannot have placeholders 1 and 3 in a format string without having placeholder 2 in the same string. If you omit a number in a format string, an error message is generated when `print` is executed.
- The `<arg_list>` must include an argument for each placeholder in the `<format_string>`, or the transaction is aborted. You can use more arguments than placeholders.
- To include a literal percent sign as part of the error message, use two percent signs ("`%%`") in the `<format_string>`. If you include a single percent sign ("`%`") in the `<format_string>` that is not used as a placeholder, the SAP ASE server returns an error message.
- If an argument evaluates to NULL, it is converted into a zero-length character string. If you do not want zero-length strings in the output, use the `isnull` function. For example, if `@<arg>` is null, the following statement prints `I think we have nothing here.:`

```
declare @arg varchar (30)
select @arg = isnull (coll, "nothing") from
table_a where ...
```

```
print "I think we have %1! here", @arg
```

- You can add user-defined messages to the system table `sysusermessages` for use by any application. Use `sp_addmessage` to add messages to `sysusermessages`; use `sp_getmessage` to retrieve messages for use by `print` and `raiserror`.
- Use `raiserror` instead of `print` to print a user-defined error message and have the error number stored in `@@<error>`.

See also `sp_addmessage`, `sp_getmessage` in *Reference Manual: Procedures*.

## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

## Permissions

No permission is required to use `print`.

## Auditing

This command is not audited.

## Related Information

[declare](#) [page 382]

[raiserror](#) [page 648]

## 1.102 quiesce database

Suspends and resumes updates to a specified list of databases.

### Syntax

```
quiesce database <tag_name> hold <database_list> [for external dump]
      [to <manifest_file> [with override]]
```

or:

```
quiesce database <tag_name> release
```

### Parameters

#### <tag\_name>

is a user-defined name that designates the list of databases to `hold` or `release`. The `<tag_name>` must conform to the rules for identifiers.

#### hold

when used with `to manifest_file` clause, holds the database and creates a manifest file.

#### ⚠ Caution

Since the manifest file is binary, operations that perform character translations of the file contents (such as `ftp`) corrupt the file unless performed in binary mode.

#### <database\_list>

is the list of the databases included in the `quiesce database hold` command.

#### for external dump

specifies that while updates to the databases in the list are suspended, you physically copy all affected database devices, using some facility external to the SAP ASE server. The copy operation serves as a replacement for the combination of `dump database` and `load database`.

#### <manifest\_file>

the binary file that describes the databases that are present on a set of database devices. It can be created only if the set of databases that occupy those devices are isolated, self-contained on those devices.

Since the manifest file is a binary file, operations that can perform character translations of the file contents (such as `ftp`) corrupt the file unless performed in binary mode.

#### with override

overrides any restrictions that prevent you from successfully executing `quiesce database` on a database.

## Examples

### Example 1

Suspends update activity on `salesdb` and `ordersdb`:

```
quiesce database report_dbs hold salesdb, ordersdb
```

### Example 2

Resumes update activity on the databases labeled `report_dbs`:

```
quiesce database report_dbs release
```

### Example 3

Suspends update activity to the `pubs2`

```
quiesce database pubs_tag hold pubs2 for external dump
```

### Example 4

Places the database in a hold status and builds the manifest file for a database to be copied to another SAP ASE server: database and signifies your intent to make an external copy of this database:

```
quiesce database pubs_tag hold pubs2 for external dump to  
"/work2/sybase1/mpubs_file with override
```

Once the command completes, control returns to the user.

### Example 5

Copies the database devices, using the `mount database with listonly` to list all of the devices to be copied to view:

```
1> mount database all from "/data/sybase2/mfile1" with listonly  
2> go
```

```
"/data/sybase1/d0.dbs" = "1dev1"
```

You cannot create a manifest file if the set of databases that are quiesced contain references to databases outside of the set. Use `with override` database and signifies your intent to make option to bypass this restriction:

```
quiesce database pubs2_tag release for external dump to Mpubs_file
```

### Example 6

<key\_db> contains the encryption key used to encrypt columns in <col\_db>:

```
quiesce database key_tag hold key_db for external
      dump to "/tmp/keydb.dat"
quiesce database encr_tag hold col_db for external dump      to "/tmp/
col.dat" with override
quiesce database col_tag hold key_db, col_db for
      external dump to "/tmp/col.dat"
```

## Usage

- `quiesce database` used with the `hold` keyword suspends all updates to the specified database. Transactions cannot update data in suspended databases, and background tasks such as the checkpoint process and housekeeper process skip all databases that are in the suspended state.
- You can issue a `quiesce database` with `external dump` on servers that have mirroring enabled. However:
  - Devices that are mirrored in the source server are not mirrored in the target.
  - The physical file from the active disk is stored in the manifest file.
- SAP ASE aborts all running `quiesce database` commands if you issue `shutdown` or `shutdown with nowait`.
- `quiesce database` used with the `release` keyword allows updates to resume on databases that were previously suspended.
- `quiesce database` used with the `for external dump` clause signifies that you intend to make an external copy of the database.
- Recovery for this database may fail or the database may not be consistent if you:
  - Quiesce a reduced-durability database (including `tempdb`)
  - Copy the device
  - Mount this database on another SAP ASE serverChange a database's durability with `alter database` before you issue a `quiesce database` command.
- `quiesce database` is not supported for in-memory row storage-enabled databases.
- The `quiesce database hold` and `release` commands need not be executed from the same user session.
- If the databases specified in the `quiesce database hold` command contain distributed or multidatabase transactions that are in the prepared state, the SAP ASE server waits during a timeout period for those transactions to complete. If the transactions do not complete during the timeout period, `quiesce database hold` fails.
- If the SAP ASE server is executing a `dump database` or `dump transaction` command on a database specified in `quiesce database hold`, the database is suspended only after the `dump` command completes.

- If you execute a `dump database` or `dump transaction` command on a database while updates to the database are suspended, the SAP ASE server blocks those commands until the database is released with `quiesce database release`.
- If you attempt to run a query against a database that is quiesced, the SAP ASE server issues error message 880:

```
Your query is blocked because it tried to write and
database '%.*s' is in quiesce state. Your query will
proceed after the DBA performs QUIESCE DATABASE
RELEASE
```

The query is run once the database is no longer in a quiescent state.

- To duplicate or copy databases, use `quiesce database` with the extension for creating the manifest file. The `quiesce database` effects the `quiesce hold` by blocking writes in the database, and then creates the manifest file. The command then returns control of the database to the user. You can now use a utility to copy the database to another SAP ASE server. These rules for `quiesce database hold` must be followed for the copy operation:
  - The copy operation cannot begin until the `quiesce database hold` process has completed.
  - Every device for every database in the `quiesce database` command must be copied.
  - The copy process must complete before you invoke `quiesce database release`.
- `quiesce database` does not perform any backup operations. Instead, it puts the database in a state that allows for an external backup of the database device files. This external backup is consistent and can be used to recover the databases to a consistent state. You can load transaction log dumps to a database recovered from an external dump.

See also `sp_helpdb`, `sp_who` in *Reference Manual: Procedures*.

## Permissions

The permission checks for `quiesce database` differ based on your granular permissions settings.

### Setting Description

**Enabled** With granular permissions enabled, you must be a user with `quiesce any database` privilege.

**Disabled** With granular permissions disabled, you must be a user with `sa_role`.

## Auditing

You can enable `quiesce` auditing option to audit this command. Values in `event` and `extrainfo` columns from the `sysaudits` table are:

Audit option	Event	Command or access audited	Information in <code>extrainfo</code> :
<code>quiesce</code>	96	<code>quiesce database</code>	<ul style="list-style-type: none"><li>• <i>Roles</i> – current active roles</li><li>• <i>Full command text</i> – full text of <code>quiesce database</code> command</li><li>• <i>Previous value</i> – NULL</li><li>• <i>Current value</i> – NULL</li><li>• <i>Other information</i> – NULL</li><li>• <i>Proxy information</i> – original login name, if set <code>proxy</code> is in effect</li></ul>

Full command text is included in `extrainfo`. For example:

```
sa_role sso_role oper_role sybase_ts_role mon_role; quiesce database tag1
hold testldb; ; ; ; sa/ase;
```

For more information about auditing, see *Security Administration Guide > Auditing*.

## Related Information

[dump database \[page 470\]](#)

[dump transaction \[page 490\]](#)

### 1.102.1 Encrypted Columns and quiesce database

You can use `quiesce database` when the database contains an encryption key.

- You must use `with override` to `quiesce` a database whose columns are encrypted with keys stored in other databases.
- `quiesce database <key_db> <col_db>` is allowed where `<key_db>` is the database with the encryption key and `<col_db>` is the database with a table that has a column encrypted with the key in `<key_db>`.

## 1.102.2 quiesce database in a Clustered Environment

If you issue `shutdown instance` or `shutdown cluster`, the cluster aborts all `quiesce database` commands.

- The cluster rejects all `quiescedb` commands issued by a user if `shutdown instance` or `shutdown cluster` commands are in progress.
- The cluster aborts all `quiesce database` commands if instance failover recovery is in progress.
- The cluster rejects all `quiesce database` commands issued by a user if instance failover recovery is in progress.
- You cannot add a new instance to the cluster while the master database is part of an ongoing `quiesce database hold` command.

## 1.103 raiserror

Prints a user-defined error message on the user's screen and sets a system flag to record that an error condition has occurred.

### Syntax

```
raiserror <error_number>
    [{<format_string> | @<local_variable>}] [, <arg_list>]
    [with errordata <restricted_select_list>]
```

### Parameters

#### <error\_number>

is a local variable or an integer with a value greater than 17,000. If the `<error_number>` is between 17,000 and 19,999, and `<format_string>` is missing or empty (""), the SAP ASE server retrieves error message text from the `sysmessages` table in the `master` database. These error messages are used chiefly by system procedures.

If `<error_number>` is 20,000 or greater and `<format_string>` is missing or empty, `raiserror` retrieves the message text from the `sysusermessages` table in the database from which the query or stored procedure originates. The SAP ASE server attempts to retrieve messages from either `sysmessages` or `sysusermessages` in the language defined by the current setting of `<@@langid>`.

#### <format\_string>



is a string of characters with a maximum length of 1024 bytes. Optionally, you can declare `<format_string>` in a local variable and use that variable with `raiserror` (see `<@local_variable>`).

`raiserror` recognizes placeholders in the character string that is to be printed out. Format strings can contain up to 20 unique placeholders in any order. These placeholders are replaced with the formatted contents of any arguments that follow `<format_string>`, when the text of the message is sent to the client.

To allow reordering of the arguments, when format strings are translated to a language with a different grammatical structure, the placeholders are numbered. A placeholder for an argument appears in this format: “%nn!”—a percent sign (%), followed by an integer from 1 to 20, followed by an exclamation point (!). The integer represents the argument number in the string in the argument list. “%1!” is the first argument in the original version, “%2!” is the second argument, and so on.

Indicating the position of the argument in this way makes it possible to translate correctly, even when the order in which the arguments appear in the target language is different from their order in the source language.

For example, assume the following is an English message:

```
%1! is not allowed in %2!.
```

The German version of this message is:

```
%1! ist in %2! nicht zulässig.
```

The Japanese version of this message is:

％2! の中で ％1! は許されません。

In this example, “%1!” represents the same argument in all three languages, as does “%2!”. This example shows the reordering of the arguments that is sometimes necessary in the translated form.

#### **@<local\_variable>**

is a local variable containing the `<format_string>` value. It must be of type `char` or `varchar` and must be declared within the batch or procedure in which it is used.

#### **<arg\_list>**

is a series of variables or constants separated by commas. `<arg_list>` is optional unless a format string containing placeholders of the form “%<nn>!” is provided. An argument can be any datatype except `text` or `image`; it is converted to the `char` datatype before being included in the final string.

If an argument evaluates to NULL, the SAP ASE server converts it to a zero-length `char` string.

#### **with errordata**

supplies extended error data for Client-Library™ programs.

#### **<restricted\_select\_list>**

consists of one or more of the following items:

- “\*”, representing all columns in `create table` order.
- A list of column names in the order you want to see them. When selecting an existing IDENTITY column, you can substitute the `syb_identity` keyword, qualified by the table name, where necessary, for the actual column name.
- A specification to add a new IDENTITY column to the result table:

```
<column_name> = identity (<precision>)
```

- A replacement for the default column heading (the column name), in the following forms:

```
<column_heading> = <column_name>
```

```
<column_name column_heading>
```

```
<column_name> as <column_heading>
```

The column heading may be enclosed in quotation marks for any of these forms. The heading must be enclosed in quotation marks if it is not a valid identifier (that is, if it is a reserved word, if it begins with a special character, or if it contains spaces or punctuation marks).

- An expression (a column name, constant, function, or any combination of column names, constants, and functions connected by arithmetic or bitwise operators, or a subquery).
- A built-in function or an aggregate.
- Any combination of the items listed above.

The `<restricted_select_list>` can also perform variable assignment, in the form:

```
@<variable> = <expression>  
[, <@variable> = <expression> ...]
```

Restrictions to `<restricted_select_list>` are:

- You cannot combine variable assignment with any of the other `<restricted_select_list>` options.
- You cannot use `from`, `where`, or other `select` clauses in `<restricted_select_list>`.
- You cannot use “\*” to represent all columns in `<restricted_select_list>`.

See the *Transact-SQL User's Guide*.

## Examples

### Example 1

Returns an error if it does not find the table supplied with the `@<tablename>` parameter:

```
create procedure showtable_sp @tablename varchar (18)
```

```

as
if not exists (select name from sysobjects
              where name = @tablename)
  begin
    raiserror 99999 "Table %1! not found.",
    @tablename
  end
else
  begin
    select sysobjects.name, type, crdate, indid
    from sysindexes, sysobjects
    where sysobjects.name = @tablename
    and sysobjects.id = sysindexes.id
  end
end

```

### Example 2

Adds a message to `sysusermessages`, then tests the message with `raiserror`, providing the substitution arguments:

```

sp_addmessage 25001,
"There is already a remote user named '%1!'
for remote server '%2!'."
raiserror 25001, jane, myserver

```

### Example 3

Uses the `with errordata` option to return the extended error data `<column>` and `<server>` to a client application, to indicate which column was involved and which server was used:

```

raiserror 20100 "Login must be at least 5
characters long" with errordata "column" =
"login", "server" = @@servername

```

## Usage

- User-defined messages can be generated ad hoc, as in Example 1 and Example 3, or they can be added to the system table `sysusermessages` for use by any application, as shown in Example 2. Use `sp_addmessage` to add messages to `sysusermessages`; use `sp_getmessage` to retrieve messages for use by `print` and `raiserror`.
- Error numbers for user-defined error messages must be greater than 20,000. The maximum value is 2,147,483,647 ( $2^{31}-1$ ).
- The severity level of all user-defined error messages is 16. This level indicates that the user has made a nonfatal error.
- The maximum output string length of `<format_string>` plus all arguments after substitution is 1024 bytes.
- If you use placeholders in a format string, keep this in mind: for each placeholder `<n>` in the string, the placeholders `<1>` through `<n-1>` must exist in the same string, although they do not have to be in numerical order. For example, you cannot have placeholders 1 and 3 in a format string without having placeholder 2 in the same string. If you omit a number in a format string, an error message is generated when `raiserror` is executed.
- If there are too few arguments relative to the number of placeholders in `<format_string>`, the SAP ASE server displays an error message and aborts the currently executing statement, but does not abort any open transactions. However, if this error occurs within a stored procedure, the SAP ASE server continues

with the next statement at the line that called `raiserror`, and any open transactions remain open. If the error occurs in a batch of SQL code, the SAP ASE server aborts the batch, and any open transactions remain open.

- To include a literal percent sign as part of the error message, use two percent signs ("%") in the `<format_string>`. If you include a single percent sign ("%") in the `<format_string>` that is not used as a placeholder, the SAP ASE server returns an error message.
- If an argument evaluates to NULL, it is converted into a zero-length `char` string. If you do not want zero-length strings in the output, use the `isnull` function.
- When `raiserror` is executed, the error number is placed in the global variable `<@@error>`, which stores the error number that was most recently generated by the system.
- Use `raiserror` instead of `print` if you want an error number stored in `<@@error>`.
- To include an `<arg_list>` with `raiserror`, put a comma after `<error_number>` or `<format_string>` before the first argument. To include extended error data, separate the first `<extended_value>` from `<error_number>`, `<format_string>`, or `<arg_list>` using a space (not a comma).

See also `sp_addmessage`, `sp_getmessage` in *Reference Manual: Procedures*.

## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

## Permissions

No permission is required to use `raiserror`.

## Auditing

This command is not audited.

## Related Information

[declare \[page 382\]](#)

[print \[page 640\]](#)

## 1.104 readtext

Reads `text`, `unitext`, and `image` values, starting from a specified offset and reading a specified number of bytes or characters.

### Syntax

```
readtext [[<database>.]<owner>.]<table_name>.<column_name>
<text_pointer> offset size
[holdlock | noholdlock] [readpast]
[using {bytes | chars | characters}]
[at isolation {
  [read uncommitted | 0] |
  [read committed | 1] |
  [repeatable read | 2] |
  [serializable | 3]}}
```

### Parameters

#### <table\_name.column\_name>

is the name of the `text`, `unitext`, or `image` column. You must include the table name. Specify the database name if the table is in another database, and specify the owner's name if more than one table of that name exists in the database. The default value for `<owner>` is the current user, and the default value for `<database>` is the current database.

#### <text\_pointer>

is a `varbinary (16)` value that stores the pointer to the `text`, `unitext`, or `image` data. Use the `textptr` function to determine this value. `text`, `unitext`, and `image` data is not stored in the same set of linked pages as other table columns. It is stored in a separate set of linked pages. A pointer to the actual location is stored with the data; `textptr` returns this pointer.

#### <offset>

specifies the number of bytes or characters to skip before starting to read `text`, `unitext`, or `image` data.

#### <size>

specifies the number of bytes or characters of data to read.

#### holdlock

causes the text value to be locked for reads until the end of the transaction. Other users can read the value, but they cannot modify it.

#### noholdlock

prevents the server from holding any locks acquired during the execution of this statement, regardless of the transaction isolation level currently in effect. You cannot specify both a `holdlock` and a `noholdlock` option in a query.

#### **readpast**

specifies that `readtext` should silently skip rows with exclusive locks, without waiting and without generating a message.

#### **using**

specifies whether `readtext` interprets the `<offset>` and `<size>` parameters as a number of bytes (`bytes`) or as a number of `textptr` characters (`chars` or `characters` are synonymous). This option has no effect when used with a single-byte character set or with `image` values (`readtext` reads `image` values byte by byte). If the `using` option is not given, `readtext` interprets the `<size>` and `<offset>` arguments as bytes.

#### **at isolation**

specifies the isolation level (0, 1, or 3) of the query. If you omit this clause, the query uses the isolation level of the session in which it executes (isolation level 1 by default). If you specify `holdlock` in a query that also specifies `at isolation read uncommitted`, the SAP ASE server issues a warning and ignores the `at isolation` clause. For the other isolation levels, `holdlock` takes precedence over the `at isolation` clause.

#### **read uncommitted**

specifies isolation level 0 for the query. You can specify 0 instead of `read uncommitted` with the `at isolation` clause.

#### **read committed**

specifies isolation level 1 for the query. You can specify 1 instead of `read committed` with the `at isolation` clause.

#### **repeatable read**

specifies isolation level 2 for the query. You can specify 2 instead of `serializable` with the `at isolation` clause.

#### **serializable**

specifies isolation level 3 for the query. You can specify 3 instead of `serializable` with the `at isolation` clause.

## **Examples**

### **Example 1**

Selects the second through the sixth character of the `copy` column:

```
declare @val varbinary (16)
select @val = textptr (copy) from blurbs
where au_id = "648-92-1872"
readtext blurbs.copy @val 1 5 readpast using chars
```

## Usage

- The `textptr` function returns a 16-byte binary string (text pointer) to the `text`, `unitext`, or `image` column in the specified row or to the `text`, `unitext`, or `image` column in the last row returned by the query, if more than one row is returned. Declare a local variable to hold the text pointer, then use the variable with `readtext`.
- The value in the global variable `@@<textsize>`, which is the limit on the number of bytes of data to be returned, supersedes the size specified for `readtext` if it is less than that size. Use `set textsize` to change the value of `@@<textsize>`.
- When using bytes as the offset and size, the SAP ASE server may find partial characters at the beginning or end of the `text` data to be returned. If it does, and character set conversion is on, the server replaces each partial character with a question mark (?) before returning the text to the client.
- The SAP ASE server must determine the number of bytes to send to the client in response to a `readtext` command. When the `<offset>` and `<size>` are in bytes, determining the number of bytes in the returned text is simple. When the offset and size are in characters, the server must calculate the number of bytes being returned to the client. As a result, performance may be slower when using characters as the `<offset>` and `<size>`. The `using characters` option is useful only when the SAP ASE server is using a multibyte character set: it ensures that `readtext` does not return partial characters.
- You cannot use `readtext` on `text`, `unitext`, or `image` columns in views.
- If you attempt to use `readtext` on `text` values after changing to a multibyte character set, and you have not run `dbcc fix_text`, the command fails, and an error message instructs you to run `dbcc fix_text` on the table.

See also *text*, *image*, and *unitext Datatypes* in *Reference Manual: Building Blocks*.

## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

## Permissions

`readtext` requires `select` permission on the table.

## Auditing

This command is not audited.

## Related Information

[set](#) [page 732]

[writetext](#) [page 865]

### 1.104.1 Using the readpast Option

Usage information for `readpast`.

- `readpast` applies only to data-only-locked tables, and is ignored if it is specified for an allpages-locked table.
- `readpast` is incompatible with the `holdlock` option. If both are specified in a command, an error is generated and the command terminates.
- If `readtext` specifies `at isolation read uncommitted`, `readpast` generates a warning, but does not terminate the command.
- If the statement isolation level is set to 3, `readpast` generates an error and terminates the command.
- If the session-wide isolation level is 3, `readpast` is silently ignored.
- If the session-wide isolation level is 0, `readpast` generates a warning, but does not terminate the command.

### 1.104.2 Using readtext with unitext Columns

When you issue `readtext` on a column defined for the `unitext` datatype, the `readtext <offset>` parameter specifies the number of bytes, or Unicode values, to skip before starting to read the `unitext` data.

The `readtext <size>` parameter specifies the number of bytes, or 16-bit Unicode values, to read. If you specify using `bytes` (the default), the `<offset>` and `<size>` values are adjusted to always start and end on the Unicode character boundaries, if necessary.

If `enable surrogate processing` is on, `readtext` truncates only on the surrogate boundary, and starting/ending positions are also adjusted accordingly and returns whole Unicode characters. For this reason, issuing `readtext` against a column defined for `unitext` may return fewer bytes than specified.

In the following example, the `unitext` column `ut` includes the string `U+0101U+0041U+0042U+0043`:

```
declare @val varbinary (16)
select @val = textptr (ut) from unitable
where i = 1
readtext foo.ut @val 1 5
```

This query returns the value `U+0041U+0042`.

The `<offset>` position is adjusted to 2 since `readtext` cannot start from the second byte of a Unicode character. Unicode characters are always composed of an even number of bytes. Starting at the second byte (or ending in an odd number of bytes) shifts the result by one byte, and renders the result set inaccurate.

In the example above, the `<size>` value is adjusted to 4 since `readtext` cannot read the partial byte of the fourth character, `U+0043`.



In the following query, `enable surrogate processing` is enabled, and the `ut` column contains the string `U+d800dc00U+00c2U+dbffdeffU+d800dc00`:

```
declare @val varbinary (16)
select @val = textptr (ut) from unitable
where i = 2
readtext foo.ut @val 1 8
```

This query returns the value `U+00c2U+dbffdeff`. The starting position is reset to 2, and the actual result size is 6 bytes rather than 8 since `readtext` does not break in the middle of a surrogate pair. Surrogate pairs (in this example, the first value in the range `d800..dbff` and the second in the range `dc00..dfff`) require 4-byte boundaries, and the rules of Unicode conformance for UTF-16 do not allow the division of these 4-byte characters.

## 1.105 reconfigure

Allows existing scripts to run without modification (currently has no effect).

### Syntax

```
reconfigure
```

### Usage

If you have scripts that include `reconfigure`, change them at your earliest convenience. Although `reconfigure` is included in this version, it may not continue to be supported in subsequent versions.

See also `sp_configure` in *Reference Manual: Procedures*.

### Standards

ANSI SQL – Compliance level: Transact-SQL extension.

### Permissions

`reconfigure` permission defaults to system administrators and is not transferable.

## Auditing

This command is not audited.

## 1.106 refresh precomputed result set

Refreshes the specified precomputed result set.

### Syntax

```
refresh precomputed result set <prs_name>
```

### Parameters

<prs\_name>

name of the precomputed result set. A fully qualified <prs\_name> cannot include the server or database name.

### Examples

#### Example 1

Refreshes the `au_prs` precomputed result set:

```
refresh precomputed result set au_prs
```

### Usage

`refresh precomputed result set` permission defaults to the precomputed result set owner and can be transferred to other users.

## Standards

The `refresh precomputed result set` command is a Transact-SQL extension and is not covered by the SQL standard.

## Permissions

You must have `create table` privilege to refresh precomputed result sets.

## Auditing

Refreshing precomputed result sets is not audited.

## 1.107 remove java

Removes one or more Java-SQL classes, packages, or JARs from a database, when Java classes are installed in the database.

## Syntax

```
remove java
  class <class_name>[, <class_name>]...
  | package <package_name>[, <package_name>]...
  | jar <jar_name>[, <jar_name>]...[retain classes]
```

## Parameters

**class** <class\_name>

the name of one or more Java classes to be removed from the database. The classes must be installed in the current database.

**package** <package\_name>

the name of one or more Java packages to be removed. The packages must be stored in the current database.

**jar** <jar\_name>

either a SQL identifier or character string value of up to 30 bytes that contains a valid SQL identifier. Each `<jar_name>` must be equal to the name of a retained JAR in the current database.

#### retain classes

specifies that the named JARs are no longer retained in the database, and the retained classes have no associated JAR.

## Usage

- If a `remove java` statement is contained in a stored procedure, the current database is the database that is current when the procedure is created, not the database that is current when the procedure is called. If a `remove java` statement is not contained in a stored procedure, the current database is the database that is current when the `remove` statement is executed.
- If `class` or `package` is specified and any removed class has an associated JAR, then an exception is raised.
- If any stored procedure, table, or view contains a reference to a removed class as the datatype of a column, variable, or parameter, then an exception is raised.
- All removed classes are:
  - Deleted from the current database.
  - Unloaded from the Java Virtual Machine (Java VM) of the current connection. The removed classes are not unloaded from the Java VMs of other connections.
- If any exception is raised during the execution of `remove java`, then all actions of `remove java` are cancelled.
- You cannot remove a Java-SQL class if that class is directly referenced by a SQLJ stored procedure or function.
- To remove a Java-SQL class from the database, you must:
  1. Delete all SQLJ stored procedures or functions that directly reference the class using `drop procedure` and `drop function`.
  2. Delete the Java-SQL class from the database using `remove java`.
- When you use `remove java`, an exclusive table lock is placed on `sysxtypes`.
- If `jar` is specified, then an exclusive table lock is placed on `sysjars`.

See also:

- *Java in Adaptive Server Enterprise*
- `sp_helpjava` in *Reference Manual: Procedures*
- `sysjars`, `sysxtypes` in *Reference Manual: Tables*
- `extractjava`, `installjava` in the *Utility Guide*

## Permissions

You must be a system administrator or database owner to use `remove java`.

The permission checks for `remove jar class` differ based on your granular permissions settings.

Setting	Description
Enabled	With granular permissions enabled, you must be a user with <code>manage</code> database privilege.
Disabled	With granular permissions disabled, you must be the database owner.

## Auditing

You can enable `remove` auditing option to audit this command. Values in `event` and `extrainfo` columns from the `sysaudits` table are:

Audit option	Event	Command or access audited	Information in <code>extrainfo</code> :
<code>remove</code>	94	<code>remove java</code>	<ul style="list-style-type: none"> <li>• <i>Roles</i> – current active roles</li> <li>• <i>Keywords or options</i> – NULL</li> <li>• <i>Previous value</i> – NULL</li> <li>• <i>Current value</i> – NULL</li> <li>• <i>Other information</i> – NULL</li> <li>• <i>Proxy information</i> – original login name, if a set <code>proxy</code> is in effect</li> </ul>

Example of the `extrainfo` column:

```
sa_role sso_role oper_role sybase_ts_role mon_role; ; ; ; ; test1/ase;
```

For more information about auditing, see *Security Administration Guide > Auditing*.

## 1.108 reorg

Reclaims unused space on pages, removes row forwarding, or rewrites all rows in the table to new pages, depending on the option used.

### Syntax

```
reorg compact <table_name> [partition <partition_name>]
    [with {resume, time = <no_of_minutes>, compress}]
```

```
reorg forwarded_rows <table_name> [partition <partition_name>]
    [with {resume, time = <no_of_minutes>, compress}]
```

```
reorg rebuild <table_name> [<index_name> [partition <index_partition_name>]]
```

```
[with online]]
```

```
reorg reclaim_space <table_name> [<index_name>] [partition <partition_name>]  
[with {resume, time = <no_of_minutes>, compress}]
```

```
reorg defrag <table_name> [partition {<partition_list>}]  
[with {time = <hh:mm>| resume | skip_compact_extents [= <pct_value>}}]
```

## Parameters

### compact

combines the functions of `reorg reclaim_space` and `reorg forwarded_rows` to both reclaim space and undo row forwarding in the same pass.

### forwarded\_rows

removes row forwarding. While unforwarding or reinserting a data row on a table configured for compression, the row is compressed according to the table's compression level.

### <index\_partition\_name>

is the name of the index partition on which you are running `reorg. update statistics` performs a check to validate that `<index_partition_name>` is an index partition. If you specify an index partition, only that index partition is rebuilt

### <indexname>

specifies the name of the index to be reorganized.

### <partition\_name>

is the name of the partition on which you are running `reorg`.

### <tablename>

specifies the name of the table to be reorganized. If `<indexname>` is specified, only the index is reorganized.

### rebuild

if a table name is specified, rewrites all rows in a table to new pages, so that the table is arranged according to its clustered index (if one exists), with all pages conforming to current space management settings and with no forwarded rows and no gaps between rows on a page. If the table has an index, all indexes are dropped and re-created. If an index name is specified, `reorg` rebuilds that index while leaving the table accessible for read and update activities.

New rows follow the compression level of the partition or table, regardless of the compression level of the data in the original table or partition.

#### i Note

`reorg rebuild` is not supported for system catalogs.

### with online

allows concurrent access to the table while `reorg rebuild` runs. See *System Administration Guide: Volume 2 > Using the reorg Command*.

## reclaim\_space

reclaims unused space left by deletes and updates. For each data page in a table, if there is unused space resulting from committed deletes or row-shortening updates, `reorg reclaim_space` rewrites the current rows contiguously, leaving all unused space at the end of the page. If there are no rows on the page, the page is deallocated.

If a table is marked for compression, `reclaim_space` compresses the data.

### Note

`reorg reclaim_space` only affects tables with variable-length rows, and only frees up space within a page. To reduce the number of pages used, use the `reorg rebuild` command.

## with resume

initiates reorganization from the point at which a previous `reorg` command terminated. Used when the previous `reorg` command specified a time limit (`with time = <no_of_minutes>`).

## with time = <no\_of\_minutes>

specifies the number of minutes that the `reorg` command is to run.

## with compress

allows you to compress the rows affected by the `reorg` operation.

## defrag

reorganizes each partition list or partition in the table while allowing concurrent reads or writes on the data being reorganized. See *System Administration Guide: Volume 2 > Using the reorg Command > Running reorg defrag*.

## partition

is the subset of the table that shares the same column definitions, constraints, and defaults as the table.

## <partition\_list>

is the list of partition names.

## time

reorganizes the table or the list of partitions for the specified interval of time. `<hh>` is the number of hours and has no limit, and `<mm>` is the number of minutes 0–59.

## resume

resumes table reorganization from the end of the last reorganized data page invoked from the previous `reorg defrag.resume` continues until the entire table or list of partitions is reorganized, processing only those partitions that are currently either unvisited or partially reorganized. Running `time = <hh:mm>` with `resume` indicates that you are running reorganization from the previous position of reorganization and running it only for the specified interval of time.

## skip\_compact\_extents

skips compact extents. The compactness of an extent is measured as the percentage occupancy in that extent.

## <pct\_value>

is the compactness of an extent measured as the percentage occupancy in that extent with a value of 1–100. Compactness = (Total space occupied in an extent / Total space in an extent) x 100

If `skip_compact_extents` is used, all the extents with compactness greater than or equal to the threshold occupancy percent value specified would be skipped for reorganization. If no threshold percent value is specified, the default percent value is 80%.

## Examples

### Example 1

Reclaims unused page space in the `titles` table:

```
reorg reclaim_space titles
```

### Example 2

Reclaims unused page space in the index `titleind`:

```
reorg reclaim_space titles titleind
```

### Example 3

Initiates `reorg compact` on the `titles` table. `reorg` starts at the beginning of the table and continues for 120 minutes. If the `reorg` completes within the time limit, it returns to the beginning of the table and continues until the full time period has elapsed:

```
reorg compact titles with time = 120
```

### Example 4

Initiates `reorg compact` at the point where the previous `reorg compact` stopped and continues for 30 minutes:

```
reorg compact titles with resume, time = 30
```

### Example 5

Runs `reorg forwarded_rows` on the `smallsales` partition of the `titles` table:

```
reorg forwarded_rows titles partition smallsales
```

### Example 6

Runs `reorg forwarded_rows` on the `authors` table:

```
reorg forwarded_rows authors
```

### Example 7

Runs `reorg reclaim_space` on the `bigsales` partition of `titles`:

```
reorg reclaim_space titles partition bigsales
```



### Example 8

Runs `reorg compact` on the `bigsales` partition of `titles`:

```
reorg compact titles partition bigsales
```

### Example 9

Runs `reorg compact` on the `titles` table and compresses the affected rows:

```
reorg compact titles with compress
```

### Example 10

Runs `reorg rebuild` on the index partition `idx_p2` of index `local_idx` on table `sales`:

```
reorg rebuild sales local_idx partition idx_p2
```

### Example 11

Reorganizes the partition list, starting from the beginning of each partition and continuing until its end:

```
reorg defrag salesdetail [partition {seg1 [,seg2[,seg3]]}]
```

### Example 12

Reorganizes the partition list, starting from the beginning of each partition and continuing until the specified time interval is reached.

```
reorg defrag salesdetail [partition  
  {seg1 [,seg2[,seg3]]}] with time = 01:20
```

### Example 13

Restarts reorganization for each partition in the partition list that is either unvisited or partially reorganized, from where the previous invocation of reorganization has stopped, and if no point for resuming is available, reorganization starts from the beginning of the partition. Reorganization continues until the end of each partition.

```
reorg defrag salesdetail [partition {seg1 [,seg2[,seg3]]}]  
  with resume
```

### Example 14

Reorganizes the partition list, starting from the beginning of the partition and continuing until its end, skipping the extents with more than the specified occupancy threshold. If a percentage is not specified, extents exceeding 80% occupied are considered compact, and skipped.

```
reorg defrag salesdetail [partition {seg1 [,seg2[,seg3]]}]  
  with skip_compact_extents [ = <1-100>]
```

### Example 15

Reorganizes each partition in the partition list that is either unvisited or partially reorganized, starting from the point where the previous invocation of reorganization stopped. If no point is available for resuming, reorganization starts from the beginning of the partition. Reorganization continues until the specified time interval is reached.

```
reorg defrag salesdetail [partition {seg1 [,seg2[,seg3]]}]  
  with time = 01:20, resume
```

### Example 16

Reorganizes the partition list, starting from the beginning of the partition and continuing until the specified interval of time completes, skipping each extent that qualifies to be compact as per the `<pct_value>` specified for `skip_compact_extents`. If a percentage is not specified, extents exceeding 80% occupied are considered compact, and skipped.

```
reorg defrag salesdetail [partition {seg1 [,seg2[,seg3]}}]
  with time = 01:20, skip_compact_extents [ = <1-100>]
```

### Example 17

Reorganizes each partition in the partition list that is either unvisited or partially reorganized, starting from the point where the previous invocation of reorganization stopped. If no point is available for resuming, reorganization starts from the beginning of the partition. Reorganization continues until the end of each partition. It skips extents that qualify to be compact as per the `<pct_value>` provided for `skip_compact_extents`. If the `<pct_value>` is not provided, extents exceeding 80% occupied are considered compact and hence skipped.

```
reorg defrag salesdetail [partition {seg1 [,seg2[,seg3]}}]
  with resume, skip_compact_extents[ = <1-100>]
```

### Example 18

Reorganizes each partition in the partition list that is either unvisited or partially reorganized, starting from the point where the previous invocation of reorganization has stopped. If no point is available for resuming, reorganization starts from the beginning of the partition. Reorganization continues until the specified time interval completes. It skips extents that qualify to be compact as per the `<pct_value>` specified for `skip_compact_extents`. If a percentage is not specified, extents exceeding 80% occupied are considered compact and hence skipped.

```
reorg defrag salesdetail [partition {seg1 [,seg2[,seg3]}}]
  with time = 01:20, resume, skip_compact_extents [ = <1-100>]
```

For every 10% of a partition processed, this information appears:

```
Examined n allocation unit(s). Processed x pages out of y
data pages. z% completed, resulting in p% space compaction.
```

At the end of processing each partition, the time elapsed in the current invocation is printed as:

```
Elapsed time 1m : 56s : 623ms.
```

## Usage

- The table specified in `reorg`—excluding `reorg rebuild`—must have a `datarows-` or `datapages-` locking scheme.
- You cannot include the `reorg rebuild ... with online` parameter on IMRS-enabled databases.
- Index scans traverse faster after you run `reorg`.
- Running `reorg` against a table can have a negative effect on performance of concurrent queries.
- If you do not include the index or partition name, the entire table is rebuilt.

- You can perform a `dump tran` on a table after rebuilding its index. However, you cannot perform a `dump tran` if the entire table has been rebuilt.
- Although online index rebuilding is allowed on a placement index, it rebuilds only the index pages. The data pages remain untouched, which means datarows are neither sorted nor rewritten to fresh pages. You can rebuild data pages by dropping a placement index, and then re-creating it.
- You can run `writetext` concurrently with the `online` parameter.
- `reorg` has no effect on space allocated to `text` or `image` columns.
- You cannot issue `reorg` within a transaction.
- `reorg rebuild` requires additional disk space equal to the size of the table and its indexes. You can find out how much space a table currently occupies by using `sp_spaceused`. You can use `sp_helpsegment` to check the amount of space available.
- You cannot run `reorg rebuild` on system tables.
- You can rebuild the index for `systabstats`, but you cannot run `reorg rebuild` on the table itself.
- Versions of SAP ASE earlier than 15.0 restricted you from using `reorg rebuild` on all-pages locked tables. SAP ASE versions 15.0 and later allow you to run `reorg rebuild` on entire tables that uses allpages locking. `reorg rebuild` rebuilds the entire table, copying the data to new sets of pages, and rebuilds all indexes.
- You cannot use the `reorg` sub commands (for example, `compact`, `reclaim_space`, and `forwarded_rows`) on all-pages-locked tables.
- You cannot use `reorg rebuild <table_name> <index_name>` or `<partition_name>` on allpages-locked tables.
- `reorg rebuild` requires that you set the database option `select into/bulkcopy/pllsort` to `true` and run `checkpoint` in the database.
- Running `reorg rebuild <table_name>` updates the statistics for all leading index columns. However, running `reorg rebuild <table_name> <index_name>` does not automatically update the statistics. Instead, the SAP ASE server automatically updates index statistics when you run `reorg rebuild <index_name>` if the update includes a sufficient change in data to affect its plan choice and performance.
- After running `reorg rebuild`, you must dump the database before you can dump the transaction log.
- Requirements for using `reorg rebuild` on an index are less stringent than for tables. The following rules apply:
  - You do not need to set `select into` to rebuild an index.
  - Rebuilding a table requires space for a complete copy of the table. Rebuilding an index works in small transactions, and deallocates pages once they are copied; therefore, the process needs space only for the pages copied on each transaction.
  - You can rebuild the index on a table while transaction level scans (dirty reads) are active.

When using `reclaim_space`, `forwarded_rows`, and `compact` parameters:

- Minimize interference with other activities by using multiple small transactions of brief duration. Each transaction is limited to eight pages of `reorg` processing.
- Rewrite space for a single partition.
- Provide `resume` and `time` options that allow you to set a time limit on how long a `reorg` runs and to resume a `reorg` from the point at which the previous `reorg` stopped. This allows you to, for example, use a series of partial reorganizations at off-peak times to run the `reorg` command on a large table.

Garbage collection and locks:

- For datarow tables – the SAP ASE server performs garbage collection using a latch, and releases the latch on a page before moving to the next page. No locks are obtained until the garbage collection encounters a forwarded row, when it acquires an exclusive table lock, which it holds until the end of that transaction. Subsequent transaction use latches until they encounter forwarded rows.
- For data page tables – the SAP ASE server performs garbage collection using a page lock, but releases the page lock before moving to the next page. When the garbage collector encounters a forwarded row, it acquires an exclusive table lock, which it holds until the end of the transaction. Subsequent transactions use page locks until it encounters another forwarded row.
- Use `reorg compact` if garbage collection encounters OAM pages that are allocated to the object, but do not refer to the allocation (running `reorg compact` requires a shared table lock).

The following considerations apply when using the `resume` and `time` parameters:

- If you specify only the `resume` option, the `reorg` begins at the point where the previous `reorg` stopped and continues to the end of the table.
- If you specify only the `time` option, the `reorg` starts at the beginning of the table and continues for the specified number of minutes.
- If you specify both options, the `reorg` starts at the point where the previous `reorg` stopped and continues for the specified number of minutes.

When running `reorg` on compressed tables:

- `reorg rebuild` – sorts the rows according to the placement index (if one exists), writing the rows to new data pages according to the space management settings currently in effect. New rows are compressed or decompressed according to individual partition's compression level, regardless of the data compression state in the original table or partition.
- `reorg reclaim_space` – compresses data rows to save more space if the table is marked for compression.

The following considerations apply when using the `reorg defrag`:

- Tables must be data-only-locking (DOL) and have at least one index to use `reorg defrag`. Sybase recommends that the table has a unique index to efficiently accommodate the movement of the forwarded locations during reorganization.
- You can run only one instance of `reorg defrag` at a time on a table.
- Using `reorg defrag...with resume` on versions of SAP ASE earlier than 15.7 SP131 require you to restart the defragmentation process from the start of the table or partition when the object is marked fully defragmented (message 11943). On versions 15.7 SP131 and later, the defragmentation process is started from the beginning of the object and restarting the defragmentation process is not required.
- When `reorg defrag` is in progress, DDLs cannot run on the table, for example `add/drop partition`, `create/drop index`, `add/modify/drop columns`. Also, other existing `reorg` subcommands like `rebuild/reclaim/compact/forwarded rows` cannot run when `reorg defrag` is in progress.

See also:

- See the *System Administration Guide*.
- `sp_chgattribute` in *Reference Manual: Procedures*

## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

## Permissions

The permission checks for `reorg` differ based on your granular permissions settings.

Setting	Description
Enabled	With granular permissions enabled, you must be the table owner, or a user with <code>reorg any table</code> privilege.
Disabled	With granular permissions disabled, you must be the table owner or a user with <code>sa_role</code> .

## Auditing

This command is not audited.

## 1.109 return

Exits from a batch or procedure unconditionally and provides an optional return status. Statements following `return` are not executed.

## Syntax

```
return [<integer_expression>] [plan "<abstract_plan>"]
```

## Parameters

### <integer\_expression>

is the integer value returned by the procedure. Stored procedures can return an integer value to a calling procedure or an application program.

### plan "<abstract\_plan>"

specifies the abstract plan to use to optimize the query. The abstract plan can be a full or partial plan specified in the abstract plan language. Plans can be specified only for optimizable SQL statements, that is, queries that access tables. See *Creating and Using Abstract Plans* in the *Performance and Tuning Guide: Optimizer and Abstract Plans* for more information.

## Examples

### Example 1

If no user name is given as a parameter, the `return` command causes the procedure to exit after a message has been sent to the user's screen. If a user name is given, the names of the rules created by that user in the current database are retrieved from the appropriate system tables:

```
create procedure findrules @nm varchar (30) = null as
if @nm is null
begin
    print "You must give a user name"
    return
end
else
begin
    select sysobjects.name, sysobjects.id,
        sysobjects.uid
    from sysobjects, master..syslogins
        where master..syslogins.name = @nm
        and sysobjects.uid = master..syslogins.suid
        and sysobjects.type = "R"
end
```

### Example 2

If the updates cause the average price of business titles to exceed \$15, the `return` command terminates the batch before any more updates are performed on titles:

```
print "Begin update batch"
update titles
    set price = price + $3
    where title_id = 'BU2075'
update titles
    set price = price + $3
    where title_id = 'BU1111'
if (select avg (price) from titles
    where title_id like 'BU%') > $15
begin
    print "Batch stopped; average price over $15"
    return
end
update titles
    set price = price + $2
    where title_id = 'BU1032'
```

### Example 3

Creates two user-defined status codes: a value of 1 is returned if the `contract` column contains a 1; a value of 2 is returned for any other condition (for example, a value of 0 on `contract` or a `title_id` that did not match a row):

```
create proc checkcontract @param varchar (11)
as
declare @status int
if (select contract from titles where title_id = @param) = 1
    return 1
else
    return 2
```

## Usage

- The return status value can be used in subsequent statements in the batch or procedure that executed the current procedure, but must be given in the form:

```
execute @<retval> = <procedure_name>
```

- The SAP ASE server reserves 0 to indicate a successful return, and negative values in the range -1 to -99 to indicate different reasons for failure. If no user-defined return value is provided, the SAP ASE value is used. User-defined return status values cannot conflict with those reserved by the SAP ASE server. Numbers 0 and -1 through -14 are currently in use:

Value	Meaning
0	Procedure executed without error
-1	Missing object
-2	Datatype error
-3	Process was chosen as deadlock victim
-4	Permission error
-5	Syntax error
-6	Miscellaneous user error
-7	Resource error, such as out of space
-8	Nonfatal internal problem
-9	System limit was reached
-10	Fatal internal inconsistency
-11	Fatal internal inconsistency
-12	Table or index is corrupt
-13	Database is corrupt
-14	Hardware error

Values -15 to -99 are reserved for future SAP ASE use.

- If more than one error occurs during execution, the status with the highest absolute value is returned. User-defined return values always take precedence over SAP ASE-supplied return values.
- The `return` command can be used at any point where you want to exit from a batch or procedure. Return is immediate and complete: statements after `return` are not executed.
- A stored procedure cannot return a NULL return status. If a procedure attempts to return a null value, for example, using `return @<status>` where `@<status>` is NULL, a warning message is generated, and a value in the range of 0 to -14 is returned.

## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

## Permissions

No permission is required to use `return`.

## Auditing

This command is not audited.

## Related Information

[begin...end \[page 114\]](#)

[execute \[page 506\]](#)

[if...else \[page 569\]](#)

[while \[page 863\]](#)

## 1.110 revoke

Revokes permissions from users, roles, or groups.

## Syntax

Revokes permission to access database objects:

```
revoke [grant option for]
  {all [privileges] | <permission_list>}
on {<table_name> [(<column_list>)]
  | <view_name> [(<column_list>)]
  | <stored_procedure_name> | <function_name>
  | <keyname>}
[with {<pred_name> | {all |no} predicates}]
from {public | <name_list> | <role_list>}
[cascade]
[granted by <grantor>]
```



Revokes permission to select built-in functions:

```
revoke select
  on [builtin] <builtin>
  from {<name_list> | <role_list>}
  [granted by <grantor>]
```

Revokes system privileges:

```
revoke {all [privileges] | <privilege_list>}
  from {public | <name_list> | <role_list>}
  [granted by <grantor>]
```

Revokes permission to run `set proxy`

```
revoke set proxy
  from {public | <name_list> | <role_list>}
  [granted by <grantor>]
```

Revokes dbcc privileges:

```
revoke {<dbcc_privilege> [on <database>]
  [, <dbcc_privilege> [on <database>], ...]}
  from {<user_list> | <role_list>}
  [granted by <grantor>]
```

Revokes the default permissions from public:

```
revoke default permissions on system tables
```

## Parameters

### **all**

when used to assign permission to access database objects (see syntax for "Revokes permission to access database objects"), `all` specifies that all permissions, except `decrypt`, that are applicable to the specified object are revoked. All object owners can use `revoke all` with an object name to revoke permissions on their own objects. You must revoke `decrypt` permissions separately.

When granular permissions is not enabled, a system administrator or the database owner can use `revoke all` to revoke privileges to create database objects (see syntax for "Revokes system privileges"). When used by a system administrator, `revoke all` revokes all `create` privileges (`create database`, `create default`, `create procedure`, `create rule`, `create table`, `create function`, and `create view`). When the database owner uses `revoke all`, or executes `revoke all` outside the master database, the SAP ASE server revokes all `create` privileges except `create database` and prints an informational message.

Revoking all `create` privileges using `revoke all` is not supported when granular permissions is enabled. For more information, see *Using Granular Permissions* in the *Security Administration Guide*.

`all` cannot be used for a `revoke` statement that includes a `where` clause.

### <permission\_list>

is a list of permissions to revoke. If more than one permission is listed, separate them with commas. The following table illustrates the access permissions that can be granted and revoked on each type of object:

<b>Table</b>	<code>select, insert, delete, update references, update statistics, delete statistics, truncate table, decrypt, identity_insert *, identity_update *</code>
<b>View</b>	<code>select, insert, delete, update, decrypt, identity_insert *, identity_update *</code>
<b>Column</b>	<code>select, update, references, decrypt</code>  Column names can be specified in either <permission_list> or <column_list>.
<b>Stored procedure</b>	<code>execute</code>
<b>Encryption key</b>	<code>select</code>
<b>Function</b>	<code>execute *</code>

#### **i** Note

Permissions with an asterisk (\*) can only be granted when granular permissions is enabled.

### <builtin>

is a built-in function. Specifying built-in functions allows you to differentiate between a table and a revocable built-in function with the same name. The functions are `set_appcontext`, `get_appcontext`, `list_appcontext`, `authmech`, and `rm_appcontext`.

### <privilege\_list>

is a list of system privileges that can be revoke. System privileges include server-wide and database-wide privileges. See the "Usage" section for details on how to revoke system privileges. Use commas to separate multiple commands.

### <table\_name>

is the name of the table on which you are revoking permissions. The table must be in your current database.

### <column\_list>

is a list of columns, separated by commas, to which the privileges apply. If columns are specified, only `select`, `reference`, `decrypt`, and `update` permissions can be revoked.

### <view\_name>

is the name of the view on which you are revoking permissions. The view must be in your current database.

### <stored\_procedure\_name>

is the name of the stored procedure on which you are revoking permissions. The stored procedure must be in your current database.

**<function\_name>**

is the name of the function for which you are revoking permissions. The function must be in your current database.

**<keyname>**

is the name of the key from which you are revoking permission. The encryption key must be in your current database. Only one object can be listed for each revoke statement. You can revoke only `select` permission from a key.

**with {<pred\_name> | {all | no} predicates}**

may be followed by a named predicate, the double keyword `all predicates`, or the double keyword `no predicates`:

**<pred\_name>** is the name of the predicated grant you are revoking. `sp_helpprotect` displays the predicate names that identify row-filtering grants.

**no predicates** instructs the SAP ASE server to remove only non-predicated grants for the given access from the named grantee.

**all predicates** instructs the SAP ASE server to remove all the predicated grants for the given access from the named grantor. Any non-predicated grants remain.

If you omit the `with` clause, both predicated and non-predicated grants are revoked (the default behavior).

**public**

is all users. For object access permissions, `public` excludes the object owner. For object creation permissions or `set proxy` authorizations, `public` excludes the database owner. You cannot grant permissions with `grant option` to "public" or to other groups or roles.

**<name\_list>**

is a list of user and group names, separated by commas.

**set proxy**

Revokes privilege from a user to impersonate another user.

**grant option for**

revokes with `grant option` permissions, so that the users specified in `<name_list>` can no longer grant the specified permissions to other users. If those users have granted permissions to other users, you must use the `cascade` option to revoke permissions from those users. The user specified in `<name_list>` retains permission to access the object, but can no longer grant access to other users. `grant option for` applies only to object access permissions, not to object creation permissions.

**cascade**

revokes the specified object access permissions from all users to whom the revokee granted permissions. Applies only to object access permissions, not to object creation permissions. When you use `revoke` without `grant option for`, permissions granted to other users by the revokee are also revoked: the cascade occurs automatically.

**granted by <grantor>**

indicates to revoke the permission or privilege granted by <grantor> instead of the user executing the `revoke` command.

**<grantor>**

a valid user name in current database.

**<dbcc\_privilege>**

is the name of the `dbcc` privileges you are revoking. It cannot be a variable.

**<database>**

is the name of the database on which you are revoking permissions. It is used with database-specific `dbcc` privileges to revoke permission only on the target database. The revokee must be a valid user in the target database. <database> conforms to the rules for identifiers and cannot be a variable.

If there are multiple revoked actions in the same command, <database> must be unique.

**<user\_list>**

is a list of users from whom you are revoking the permission, and cannot be a variable.

**<role\_list>**

is a list of the name of system or user-defined roles from whom you are revoking the permission, and cannot be a variable.

**i Note**

You cannot grant or revoke `dbcc` privileges to public or groups.

**all [privileges]**

uses `all` or `all privileges` to revoke all granted and denied privileges.

**<column\_list>**

if used with `with <pred_name>`, the predicated row access is removed for the named columns. If there still exist other columns referenced for this row-level privilege, the privilege and its related named predicate remain in `sysprotects` for the reduced column list.

**default permissions on system tables**

specifies that you revoke the default permissions for the system tables listed in "Revoking Default Permissions on System Tables."

## Examples

### Example 1

Revokes `insert` and `delete` permissions on the `titles` table from Mary and the "sales" group:

```
revoke insert, delete
on titles
from mary, sales
```

### Example 2

Revokes `select` permission on the `get_appcontext` function from "public" (which includes all users):

```
revoke select on builtin get_appcontext from public
```

Compare this to the following, which revokes `select` permission on a table called `get_appcontext`, if a table with that name exists:

```
revoke select on get_appcontext from public
```

### Example 3

Two ways to revoke `update` permission on the `price` and `advance` columns of the `titles` table from "public":

```
revoke update
on titles (price, advance)
from public
```

or:

```
revoke update (price, advance)
on titles
from public
```

### Example 4

Revokes permission from Mary and John to use the `create database` and `create table` commands. Because `create database` permission is being revoked, this command must be executed within the `master` database. Mary's and John's `create table` permission is revoked only within the `master` database:

```
revoke create database, create table from mary, john
```

### Example 5

Revokes permission from Harry and Billy to execute either `set proxy` or `set session authorization` to impersonate another user in the server:

```
revoke set proxy from harry, billy
```

### Example 6

Revokes permission from users with `sso_role` to execute either `set proxy` or `set session authorization`:

```
revoke set session authorization from sso_role
```

### Example 7

Revokes all object creation permissions from Mary in the current database (except `create encryption key` and `create trigger`):

```
revoke all from mary
```

### Example 8

Revokes all object access permissions on the `titles` table from Mary (except `decrypt` permission):

```
revoke all on titles from mary
```

### Example 9

Two ways to revoke Tom's permission to create a referential integrity constraint on another table that refers to the `price` and `advance` columns in the `titles` table:

```
revoke references  
on titles (price, advance)  
from tom
```

or:

```
revoke references (price, advance)  
on titles  
from tom
```

### Example 10

Revokes permission to execute `new_sproc` from all users who have been granted the "operator" role:

```
revoke execute on new_sproc from oper_role
```

### Example 11

Revokes John's permission to grant `insert`, `update`, and `delete` permissions on the `authors` table to other users. Also revokes from other users any such permissions that John has granted:

```
revoke grant option for  
insert, update, delete  
on authors  
from john  
cascade
```

### Example 12

Revokes `dbcc` privileges from Frank:

```
revoke dbcc checkdb on all from frank
```

### Example 13

Revokes `truncate table` and `update statistics` privileges from Harry on the `authors` table:

```
revoke truncate table on authors from harry  
revoke update statistics on authors from harry
```

Users Billy and Harry can no longer run these commands on `authors`.

#### Example 14

Revokes `truncate table` and `update` and `delete statistics` privileges from all users with the `oper_role`:

```
revoke truncate table on authors from oper_role
revoke update statistics on authors from oper_role
revoke delete statistics on authors from oper_role
```

#### Example 15

Revokes `decrypt` permissions from `public`:

```
revoke decrypt on customer from public
```

#### Example 16

Revokes `create encryption key` permissions from user `joe`:

```
revoke create encryption key from joe
```

#### Example 17

Revokes `select` permission for the `ssn_key` from the database owner.

```
revoke select on ssn_key from dbo
```

#### Example 18

The following examples assume the following grants have been made for selecting from table `t1` by `user1`:

- An unconditional grant to see all rows for `t1.col1` and `t1.col4`:

```
grant select on t1 (col1, col4) to user1
```

- A row-filtering grant to be applied when selecting `t1.col2` or `t1.col3`:

```
grant select on t1 (col2, col3)
  where col1 = 1 as pred1
  to user1
```

Removes `select` permission on `t1.col2` with `pred1`:

```
revoke select on t1 (col2) with pred1
  from user1
```

#### Note

After this revoke, `pred1` is still applied when `user1` selects `t1.col3`.

If the grantor issued either of the following, then all permissions on `t1` using `pred1` would be revoked from `user1`:

```
revoke select on t1 (col2, col3) with pred1
  from user1
```

or

```
revoke select on t1 with pred1
```

### Example 19

After the grants described in the previous example, the following removes the grant on `t1.col2` and `t1.col3` with predicate `pred1` (all predicates revokes all row-filtering predicated grants for a given access and grantee):

```
revoke select on t1 with all predicates
from user1
```

### Example 20

Removes all `select` access on `t1` from `user1`; that is, all predicated and nonpredicated grants on `t1` are granted to `user1` for `select` on `t1`:

```
revoke select on t1 from user1
```

### Example 21

Applies to only the non-predicated grant:

```
revoke select on t1 with no predicates
```

### Example 22

Revokes `select` permission on table `mary.books` from `john` granted by `mary`:

```
revoke select on mary.books from john granted by mary
```

### Example 23

Revokes system privilege `manage any login` from user `smith`:

```
use master
```

```
revoke manage any login from smith
```

## Usage

- See the `grant` command for more information about permissions.
- You can revoke permissions only on objects in your current database.
- You can revoke only permissions or privileges that were granted by you without using the `granted by <grantor>` option. With the `granted by <grantor>` option, you can revoke permissions or privileges granted by other users.
- `grant` and `revoke` commands are order-sensitive. When there is a conflict, the command issued most recently takes effect. Exceptions are grants and revokes of predicated privileges. See *How SAP ASE Saves Predicated Privileges in sysprotects* in the *Security Administration Guide*.
- You can substitute the word `to` for the word `from` in the `revoke` syntax.
- If you do not specify `grant option for` in a `revoke` statement, with `grant option` permissions are revoked from the user along with the specified object access permissions. In addition, if the user has granted the specified permissions to any other users, all of those permissions are revoked. In other words, the `revoke` cascades.
- A user, group, or role can be granted the same privilege or permission by different grantors. In this situation, there are multiple rows in `sysprotects` which represents multiple grants on the same privilege



or permission. If one or more than one grants are revoked later, the user, group, or role may still have the privilege or permission if there is at least one grant remain unrevoked.

- A `grant` statement adds one row to the `sysprotects` system table for each user, group, or role that receives the permission. If you subsequently `revoke` the permission from the user or group, the SAP ASE server removes the row from `sysprotects`. If you revoke the permission from only selected group members, but not from the entire group to which it was granted, the SAP ASE server retains the original row and adds a new row for the revoke.
- Permission to issue `create trigger` is granted to users by default. When you revoke permission for a user to create triggers, a revoke row is added in the `sysprotects` table for that user. To grant permission to issue `create trigger`, you must issue two grant commands. The first command removes the revoke row from `sysprotects`; the second inserts a grant row. If you revoke permission to create triggers, the user cannot create triggers even on tables that the user owns. Revoking permission to create triggers from a user affects only the database where the revoke command was issued.
- In a clustered environment, `revoke` fails if you attempt to revoke permissions from user-defined roles in a local temporary database.
- Database user groups allow you to `grant` or `revoke` permissions to more than one user at a time. A user is always a member of the default group, "public" and can be a member of only one other group. The SAP ASE installation script assigns a set of permissions to "public."  
Create groups with `sp_addgroup` and remove groups with `sp_dropgroup`. Add new users to a group with `sp_adduser`. Change a user's group membership with `sp_changegroup`. To display the members of a group, use `sp_helpgroup`.

See also:

- `proc_role` in *Reference Manual: Building Blocks*
- `sp_activeroles`, `sp_adduser`, `sp_changedbowner`, `sp_changegroup`, `sp_displaylogin`, `sp_displayroles`, `sp_dropgroup`, `sp_dropuser`, `sp_helpgroup`, `sp_helprotect`, `sp_helpuser` in *Reference Manual: Procedures*

## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

## Permissions

The permission checks for `revoke` differ based on your granular permissions settings.

Setting	Description
---------	-------------

<b>Enabled</b>	With granular permissions enabled, in general, <code>revoke</code> can be executed by a user with one of the following privilege management privileges, depending the privilege or permission being revoked.
----------------	--

For server-wide privileges, you must be a user with `manage server permissions` privilege or `manage security permissions` privilege.

For database-wide privileges, you must be a user with `manage database permissions` privilege.

## Setting Description

For object privileges, you must be the object owner or be a user with `manage any object permission` privilege.

To execute `revoke default`, you must be the database owner or a user with `own database privilege` on the database.

**Disabled** With granular permissions enabled:

- Command execution – only a system administrator can revoke `create database` permission, and only from the `master` database. Only a system security officer can revoke `create trigger` and `create encryption key` permission.
- Database consistency checking – only system administrators can run `revoke dbcc` commands. Database owners cannot run `revoke dbcc`.
- Database object access – revoke permission for database objects defaults to object owners. An object owner can revoke permission from other users on his or her own database objects.
- Functions – only system administrators can revoke permissions on built-in functions.
- Proxy and session authorization – only a system security officer can revoke set proxy or set session authorization, and only from the master database.
- Roles – you can revoke roles only from the `master` database. Only a system security officer can revoke `sso_role`, or a user-defined role from a user or a role. Only system administrators can revoke `oper_role` and `sa_role` from a user or a role. Only a user who has both `sa_role` and `sso_role` can revoke a role that includes `sa_role`.
- Tables – database owners can revoke default permissions on system tables. Table owners and the system security officer can revoke `decrypt` permission on a table or a list of columns in a table.
- Defaults – database owners and logins with `sa_role` can revoke defaults.

## Auditing

You can enable `revoke` auditing option to audit this command. Values in `event` and `extrainfo` columns from the `sysaudits` table are:

Information	Value
Audit option	<code>revoke</code>
Event	47
Command or access audited	<code>revoke</code>
Information in <code>extrainfo</code>	<ul style="list-style-type: none"><li>• <b>Roles</b> – current active roles</li><li>• <b>Full command text</b> – full text of <code>revoke</code> command</li><li>• <b>Previous value</b> – NULL</li><li>• <b>Current value</b> – NULL</li><li>• <b>Other information</b> – NULL</li></ul>

## Information

## Value

- **Proxy information** – original login name, if `set proxy` is in effect

Full command text is included in `extrainfo`. For example:

```
sa_role sso_role oper_role sybase_ts_role mon_role;  
    revoke insert, delete on titles from mary, sales; ; ; ;  
sa/ase;
```

For more information about auditing, see *Security Administration Guide > Auditing*.

## Related Information

[grant \[page 520\]](#)

[set \[page 732\]](#)

[setuser \[page 790\]](#)

### 1.110.1 Using the revoke Command's granted by Option

Usage information for using the `revoke` command's `granted by` option.

- `granted by` is not allowed on revoking predicated privileges.
- It is not required that the `grantor` has permission to execute the `grant` command.
- The permission granted by the grantor (indicated by `sysprotects.grantor`), not the command executor, would be revoked.
- You need not enable `enable granular permissions` to use the `granted by` parameter.
- Users who received their `grant` permission on an object with the `with grant` option cannot issue the `granted by` parameter. All other users may issue the `granted by` parameter.

For example, John gets permission on `mary`'s table through `with grant` option. An error returns when he tries to issue the `revoke` statement using `granted by` option. Mary:

```
grant select on mary.books to john  
with grant option
```

Mary:

```
grant select on mary.books to smith
```

John:

```
revoke select on mary.books from smith  
granted by mary
```

## 1.110.2 Revoking `set proxy` and `set session authorization`

To revoke `set proxy` or `set session authorization` you must be in the `master` database.

`set proxy` and `set session authorization` are identical, with one exception: `set session authorization` follows the SQL standard. If you are concerned about using only SQL standard commands and syntax, use `set session authorization`.

`revoke all` does *not* include `set proxy` or `set session authorization` permissions.

## 1.110.3 Revoking Default Permissions on System Tables

Revokes default permissions on all system tables from “public.”

The system tables you can revoke the default permissions for when you issue the command from any database are:

- `sysalternates`
- `sysattributes`
- `syscolumns`
- `syscomments`
- `sysconstraints`
- `sysdepends`
- `sysindexes`
- `sysjars`
- `syskeys`
- `syslogs`
- `sysobjects`
- `syspartitions`
- `sysprocedures`
- `sysprotects`
- `sysqueryplans`
- `sysreferences`
- `sysroles`
- `syssegments`
- `sysstatistics`
- `systabstats`
- `systhresholds`
- `systypes`
- `sysusermessages`
- `sysusers`
- `sysxtypes`

The system tables you revoke the default permissions for when you issue this command from the `master` database are:

- `sysdatabases`
- `sysdevices`
- `syslocks`
- `sysmessages`
- `sysprocesses`
- `systransactions`
- `sysusages`
- `sysconfigures`
- `syscurconfigs`
- `syslanguages`
- `syscharsets`
- `syssservers`
- `sys timeranges`
- `sysresource limits`
- `syslogins`
- `sysremotelogins`

## 1.110.4 Revoking Permissions for `update statistics`, `delete statistics`, and `truncate table`

The SAP ASE server allows you to revoke permissions for users, roles, and groups for the `update statistics`, `delete statistics`, and `truncate table` commands.

Table owners can also provide permissions through an implicit `grant` by adding `update statistics`, `delete statistics`, and `truncate table` to a stored procedure and then granting `execute` permissions on that procedure to a user or role.

You cannot revoke permissions for `update statistics` at the column level. You must have the `sso_role` to run `update statistics` or `delete statistics` on `sysroles`, `sysssrvroles`, and `sysloginroles` security tables.

By default, the database owner has permission to run `update statistics` and `delete statistics` on system tables other than `sysroles`, `sysssrvroles`, and `sysloginroles`, and can transfer this privilege to other users.

You can also issue `grant all` to grant permissions on `update statistics`, `delete statistics`, and `truncate table`.

### **i** Note

Once you revoke permission to execute `update statistics` from a user, they also lose permission to execute variations of this command, such as `update all statistics`, `update partition statistics`, `update index statistics`, `update statistics <table>`, and so on. For example, the

following revokes Billy permission from running all variations of `update statistics` on the `authors` table:

```
revoke update statistics on authors to billy
```

If you revoke a user's permission to execute `update statistics`, you also revoke their ability to execute the variations of this command.

You cannot revoke variants of `update statistics` (for example, `update index statistics`) separately. That is, you *cannot* issue:

```
revoke update all statistics from harry
```

You cannot grant and revoke `delete statistics` permissions at the column level. See the “Usage” section of `grant`.

## 1.110.5 Using the `cascade` Option

`revoke grant option for` revokes the user's ability to grant the specified permission to other users, but does not revoke the permission itself from that user. If the user has granted that permission to others, you must use the `cascade` option; otherwise, you receive an error message and the `revoke` fails.

For example, say you revoke the `with grant option` permissions from the user `Bob` on `titles`, with this statement:

```
revoke grant option for select
on titles
from bob
cascade
```

- If `Bob` has not granted this permission to other users, this command revokes his ability to do so, but he retains `select` permission on the `titles` table.
- If `Bob` has granted this permission to other users, you must use the `cascade` option. If you do not, you receive an error message and the `revoke` fails. `cascade` revokes this `select` permission from all users to whom `Bob` has granted it, as well as their ability to grant it to others.

You cannot use `revoke` with the `cascade` option to revoke privileges granted by the table owner. For example, the owner of a table (`UserA`) can grant privileges to another user (`UserB`) as in this scenario:

```
create table T1 (...)
grant select on T1 to UserB
```

However, the system administrator cannot revoke `UserB`'s privileges using the `revoke privileges` command with the `cascade` option as in this statement:

```
revoke select on T1 from UserA cascade
```

This statement revokes the `select` privileges of the table owner, but does not revoke those privileges from `UserB`.

By default, all data manipulation language (DML) operations are revoked implicitly for users other than the table owner (except for `decrypt` permission when `restricted decrypt` permission is enabled. See the

*Encrypted Columns Users Guide*). Because the `sysprotects` table contains no records indicating that the table owner has granted and then revoked privileges, the `cascade` option is not invoked. You must revoke explicitly the `select` privilege from UserB.

## 1.111 revoke role

Revokes a role from a group, login, login profile, or role:

### Syntax

```
revoke role {<role_name>[, <role_list> ...]} from  
           {<grantee>[, <grantee> ...]}
```

### Parameters

#### **role**

is the name of a system or user-defined role. Use `revoke role` to revoke granted roles from roles, logins, or login profiles.

#### **<role\_name>**

is the name of a system or user-defined role. When revoking a role from a grantee you are revoking all permissions which that grantee has through role membership.

#### **<grantee>**

is the name of a system role, user-defined role, a login profile, or the login name of a user, from whom you are revoking a role.

#### **<role\_list>**

is a list of the name of the system or user-defined roles you are revoking and cannot be a variable.

### Examples

#### Example 1

Revokes "doctor\_role" from "specialist\_role":

```
revoke role doctor_role from specialist_role
```

### Example 2

Revokes "doctor\_role" and "surgeon\_role" from "specialist\_role" and "intern\_role", and from users Mary and Tom:

```
revoke role doctor_role, surgeon_role from specialist_role, intern_role,
mary, tom
```

### Example 3

User Smith, with `manage roles` privileges, revokes the `nurse_role` from the `doctor_role`, which was originally granted by `roleAdmin`:

```
revoke role nurse_role from doctor_role
granted by roleAdmin
```

#### i Note

`manage roles` privileges is only available when granular permissions is enabled.

### Example 4

Revokes the system role `oper_role` from the login profile assumed by system operators.

```
revoke role oper_role from lp_operator
```

## Usage

- You can revoke a role from a user while the user is logged in. The SAP ASE server verifies a user's activated roles before performing access checks.
- If you revoke a role from a login profile, the SAP ASE server revokes the role from all users assigned to that profile, including users currently logged in to the SAP ASE server.

See also:

- `proc_role` in *Reference Manual: Building Blocks*
- `sp_activeroles`, `sp_adduser`, `sp_changedbowner`, `sp_changegroup`, `sp_displaylogin`, `sp_displayroles`, `sp_dropgroup`, `sp_dropuser`, `sp_helpgroup`, `sp_helprotect`, `sp_helpuser` in *Reference Manual: Procedures*

## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

## Permissions

The permission checks for `revoke role` differ based on your granular permissions settings.



## Setting Description

**Enabled** When granular permissions is enabled, you must be a user with `manage roles` privilege.

**Disabled** With granular permissions enabled, you can revoke roles only from the `master` database. Only a system security officer can revoke `sso_role`, `oper_role`, or a user-defined role from a user or a role. Only system administrators can revoke `sa_role` from a user or a role. Only a user who has both `sa_role` and `sso_role` can revoke a role that includes `sa_role`.

### i Note

With granular permissions enabled or disabled, the `sso_role` and `sa_role` cannot be revoked from the "sa" login.

## Auditing

You can enable the following auditing options to audit this command. Values in `event` and `extrainfo` columns from the `sysaudits` table are:

Information	Value
Audit option	<code>revoke, role, security</code>
Event	85
Command or access audited	<code>revoke role</code>
Information in <code>extrainfo</code>	<ul style="list-style-type: none"><li>• <b>Roles</b> – current active roles</li><li>• <b>Full command text</b> – full text of <code>revoke role</code> command</li><li>• <b>Previous value</b> – NULL</li><li>• <b>Current value</b> – NULL</li><li>• <b>Other information</b> – NULL</li><li>• <b>Proxy information</b> – original login name, if <code>set proxy</code> is in effect</li></ul>

Full command text and parameters are included in `extrainfo`. For example:

```
sso_role; revoke role @para1_role from @para2_grantee1; ; ;
@para1_role = role1, @para2_grantee1 = user4; ; user1/ase;
```

For more information about auditing, see *Security Administration Guide > Auditing*.

## Related Information

[grant \[page 520\]](#)

[set \[page 732\]](#)

[setuser \[page 790\]](#)

## 1.112 rollback

Rolls back a user-defined transaction to the named savepoint in the transaction or to the beginning of the transaction.

### Syntax

```
rollback [tran | transaction | work]
        [<transaction_name> | <savepoint_name>]
```

### Parameters

**tran | transaction | work**

specifies that you want to roll back the transaction or the work. If you specify `tran`, `transaction`, or `work`, you can also specify the `<transaction_name>` or the `<savepoint_name>`.

**<transaction\_name>**

is the name assigned to the outermost transaction. It must conform to the rules for identifiers.

**<savepoint\_name>**

is the name assigned to the savepoint in the `save transaction` statement. The name must conform to the rules for identifiers.

### Examples

#### Example 1

Rolls back the transaction:

```
begin transaction
delete from publishers where pub_id = "9906"
rollback transaction
```

### Usage

- `rollback transaction` without a `<transaction_name>` or `<savepoint_name>` rolls back a user-defined transaction to the beginning of the outermost transaction.

- `rollback transaction <transaction_name>` rolls back a user-defined transaction to the beginning of the named transaction. Though you can nest transactions, you can roll back only the outermost transaction.
- `rollback transaction <savepoint_name>` rolls a user-defined transaction back to the matching save transaction `<savepoint_name>`.

Restrictions for rollback are:

- If no transaction is currently active, the `commit` or `rollback` statement has no effect.
- The `rollback` command must appear within a transaction. You cannot roll back a transaction after `commit` has been entered.

To roll back an entire transaction:

- `rollback` without a savepoint name cancels an entire transaction. All the transaction's statements or procedures are undone.
- If no `<savepoint_name>` or `<transaction_name>` is given with the `rollback` command, the transaction is rolled back to the first `begin transaction` in the batch. This also includes transactions that were started with an implicit `begin transaction` using the chained transaction mode.

For rolling back to a savepoint:

- To cancel part of a transaction, use `rollback` with a `<savepoint_name>`. A savepoint is a marker set within a transaction by the user with the command `save transaction`. All statements or procedures between the savepoint and the `rollback` are undone.
- After a transaction is rolled back to a savepoint, it can proceed to completion (executing any SQL statements after that `rollback`) using `commit`, or it can be canceled altogether using `rollback` without a savepoint. There is no limit on the number of savepoints within a transaction.

For rollbacks within triggers and stored procedures:

- In triggers or stored procedures, `rollback` statements without transaction or savepoint names roll back all statements to the first explicit or implicit `begin transaction` in the batch that called the procedure or fired the trigger.
- When a trigger contains a `rollback` command without a savepoint name, the rollback aborts the entire batch. Any statements in the batch following the rollback are not executed.
- A remote procedure call (RPC) is executed independently from any transaction in which it is included. In a standard transaction (that is, not using Open Client DB-Library two-phase commit), commands executed via an RPC by a remote server are not rolled back with `rollback` and do not depend on `commit` to be executed.
- For complete information on using transaction management statements and on the effects of `rollback` on stored procedures, triggers, and batches, see the *Transact-SQL User's Guide*.

## Standards

ANSI SQL – Compliance level: Entry-level compliant.

Transact-SQL extensions – The `rollback transaction` and `rollback tran` forms of the statement and the use of a transaction name.

## Permissions

No permission is required to use `rollback`.

## Auditing

This command is not audited.

## Related Information

[begin transaction \[page 116\]](#)

[commit \[page 123\]](#)

[rollback trigger \[page 692\]](#)

[save transaction \[page 694\]](#)

## 1.113 rollback trigger

Rolls back the work done in a trigger, including the data modification that caused the trigger to fire, and issues an optional `raiserror` statement.

## Syntax

```
rollback trigger
    [with <raiserror_statement>]
```

## Parameters

**with** `<raiserror_statement>`

specifies a `raiserror` statement, which prints a user-defined error message and sets a system flag to record that an error condition has occurred. This provides the ability to raise an error to the client when `rollback trigger` is executed so that the transaction state in the error reflects the rollback. For information about the syntax and rules defining `raiserror_statement`, see the `raiserror` command.

## Examples

### Example 1

Rolls back a trigger and issues the user-defined error message 25002:

```
rollback trigger with raiserror 25002
    "title_id does not exist in titles table."
```

## Usage

- When `rollback trigger` is executed, the SAP ASE server aborts the currently executing command and halts execution of the rest of the trigger.
- If the trigger that issues `rollback trigger` is nested within other triggers, the SAP ASE server rolls back all work done in these triggers up to and including the update that caused the first trigger to fire.
- The SAP ASE server ignores a `rollback trigger` statement that is executed outside a trigger and does not issue a `raiserror` associated with the statement. However, a `rollback trigger` statement executed outside a trigger but inside a transaction generates an error that causes the SAP ASE server to roll back the transaction and abort the current statement batch.

## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

## Permissions

No permission is required to use `rollback trigger`.

## Auditing

This command is not audited.

## Related Information

[raiserror \[page 648\]](#)

[rollback \[page 690\]](#)

## 1.114 save transaction

Sets a savepoint within a transaction.

### Syntax

```
save transaction <savepoint_name>
```

### Parameters

<savepoint\_name>

is the name assigned to the savepoint. It must conform to the rules for identifiers.

### Examples

#### Example 1

After updating the `royaltypercentchanged`, then determine how a 10 percent increase in the book's price affects the authors' royalty earnings. The transaction is rolled back to the savepoint with `rollback transaction`:

```
begin transaction royalty_change

update titleauthor
set royaltyper = 65
from titleauthor, titles
where royaltyper = 75
and titleauthor.title_id = titles.title_id
and title = "The Gourmet Microwave"

update titleauthor
set royaltyper = 35
from titleauthor, titles
where royaltyper = 25
and titleauthor.title_id = titles.title_id
and title = "The Gourmet Microwave"

save transaction percentchanged
update titles
set price = price * 1.1
where title = "The Gourmet Microwave"

select (price * total_sales) * royaltyper
from titles, titleauthor
where title = "The Gourmet Microwave"
and titles.title_id = titleauthor.title_id

rollback transaction percentchanged
```

```
commit transaction
```

## Usage

- A savepoint is a user-defined marker within a transaction that allows portions of a transaction to be rolled back. entries for the two authors, insert the savepoint `rollback <savepoint_name>` rolls back to the indicated savepoint; all statements or procedures between the savepoint and the `rollback` are undone. Statements preceding the savepoint are not undone — but neither are they committed. After rolling back to the savepoint, the transaction continues to execute statements. A `rollback` without a savepoint cancels the entire transaction. A `commit` allows it to proceed to completion.
- If you nest transactions, `save transaction` entries for the two authors, insert creates a savepoint only in the outermost transaction.
- There is no limit on the number of savepoints within a transaction.
- If no `<savepoint_name>` or `<transaction_name>` is given with the `rollback` command, all statements back to the first `begin transaction` in a batch are rolled back, and the entire transaction is canceled.

See also *Transact-SQL User's Guide* for using transaction statements.

## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

## Permissions

No permission is required to use `save transaction`.

## Auditing

This command is not audited.

## Related Information

[begin transaction \[page 116\]](#)

[commit \[page 123\]](#)

[rollback \[page 690\]](#)

## 1.115 select

Retrieves rows from database objects.

### Syntax

```
select ::=
  select [all | distinct]
  [top <n>]
  <select_list>
  [<into_clause>]
  [<partition_clause>]
  [<from_clause>]
  [<compression_clause>]
  [<index_compression_clause>]
  [<where_clause>]
  [<group_by_clause>]
  [<having_clause>]
  [<order_by_clause>]
  [<limit_clause>]
  [<sort_clause>]
  [<compute_clause>]
  [<read_only_clause>]
  [<isolation_clause>]
  [<browse_clause>]
  [ <recompile_clause>]
  [<for_xml_clause>]
  [<plan_clause>]
```

```
<select_list> ::=
```

For details on <select\_list>, see the [Parameters \[page 698\]](#) section.

```
<into_clause> ::=
  into [[<database>.] <owner>.] <table_name>
  [( (<colname> encrypt [with [<database>.]<owner>.]<keyname>][,
    <colname> encrypt_clause ...])]
  | [compressed = <compression_level> | not compressed]
  [in row [( <length>)] | off row ]
  [[external table at
    '<server_name>.<database>.<owner>.<object_name>'
    | external directory at '<pathname>'
    | external file at '<pathname>' [column delimiter '<string>']]
  [on <segment_name>]
  dml_logging = (full | minimal)
  [<partition_clause>]
  [lock {datarows | datapages | allpages}]
  [with [, <into_option>[, <into_option>] [recompile] ...]]
  | into existing table <table_name>
```

```
<partition_clause> ::=
  partition by range (<column_name>[, <column_name>]...)
  ([<partition_name>] values <= ( {constant | MAX}
    [, {constant | MAX}] ... ) [on <segment_name>]
    [<compression_clause>] [on <segment_name>]
    [, [<partition_name>] values <= ( {constant | MAX}
    [, {constant | MAX}] ... ) [on <segment_name>]]...)
    [<compression_clause>] [on <segment_name>]
```



```

| partition by hash (<column_name>[, <column_name>]...)
  { (<partition_name> [on <segment_name>]
    [<compression_clause>] [on <segment_name>]
    [, <partition_name> [on <segment_name>]]...)
    [<compression_clause>] [on <segment_name>]
  | <number_of_partitions>
    [on (<segment_name>[, <segment_name>] ...)]}
| partition by list (<column_name>)
  ([<partition_name>] values (constant[, constant] ...)
   [<compression_clause>] [on <segment_name>]
   [, [<partition_name>] values (constant[, constant] ...)
     [<compression_clause>] [on <segment_name>]
  | partition by roundrobin
    { (<partition_name> [on <segment_name>]
      [, <partition_name> [on <segment_name>]]...)
      [<compression_clause>] [on <segment_name>]
    | <number_of_partitions>
      [on (<segment_name>[, <segment_name>]...)]}

```

```

<into_option> ::=
  | max_rows_per_page = <num_rows>
  | exp_row_size = <num_bytes>
  | reservepagegap = <num_pages>
  | identity_gap = <gap>
  | compression = {none | page | row}
  | lob_compression = off | <compression_level>

```

```

<from_clause> ::=
  from <table_reference>[,<table_reference>]...
  <table_reference> ::=
    <table_view_name> | <ANSI_join>
  <table_view_name> ::=
    [[<database>.]<owner>.] {{<table_name> | <view_name>}}
    [as] [<correlation_name>]
    [(index {<index_name> | <table_name>})]
    [parallel [<degree_of_parallelism>]]
    [prefetch size][lru | mru]
    [holdlock | noholdlock]
    [readpast]
    [shared]
  <ANSI_join> ::=
    <table_reference> <join_type> join <table_reference>
    <join_conditions>
  <join_type> ::= inner | left [outer] | right [outer]
  <join_conditions> ::= on <search_conditions>

```

```

<compression_clause> ::=
  with compression = {none | page | row}

```

```

<index_compression_clause> ::=
  with index_compression = {none | page}

```

```

<where_clause> ::=
  where <search_conditions>
  for update [of <column_list>]

```

```

<group_by_clause> ::=
  group by [all] <aggregate_free_expression>
  [, <aggregate_free_expression>]...

```

```

<having_clause> ::=
  having <search_conditions>

```

```
<order_by_clause> ::=
    order by <sort_clause>[, <sort_clause>]...
```

```
<limit_clause> ::=
    rows <limit_sub_clause>
```

```
<limit_sub_clause> ::=
    limit <limit_value> [offset <offset_value>]
    | offset <offset_value> [limit <limit_value>]
```

```
<sort_clause> ::=
    {[[[<database>.]<owner>.]<table_name>.|<view_name>.]<column_name>
    | <select_list_number>
    | <>]
    [asc | desc]
```

```
<compute_clause> ::=
    compute <row_aggregate> (<column_name>)
    [, <row_aggregate> (<column_name>)]...
    [by <column_name> [, <column_name>]...]
```

```
<read_only_clause> ::=
    for {read only | update [of <column_name_list>]}
```

```
<isolation_clause> ::=
    at isolation
    {read uncommitted | 0}
    | {read committed | 1}
    | {repeatable read | 2}
    | {serializable | 3}
    | {statement snapshot}
    | {transaction snapshot}
    | {readonly statement snapshot}
```

```
<browse_clause> ::=
    for browse
```

```
<recompile_clause> ::=
    with recompile
```

```
<plan_clause> ::=
    plan "abstract plan"
```

See the *XML Services* book for syntax, examples, and usage information for the `select...for_xml_clause`.

## Parameters

### **all**

includes all rows in the results. `all` is the default.

### **distinct**

includes only unique rows in the results. `distinct` must be the first word in the select list. `distinct` is ignored in browse mode.

Null values are considered equal for the purposes of the keyword `distinct`: only one NULL is selected, no matter how many are encountered.

You can include up to 1023 partitions in queries that include unions of multiple tables or partitions.

### `top <n>`

is used with `select...into` statements to limit the number of rows inserted in the target table. This is different from `set rowcount`, which is ignored during a `select...into`.

- When used with `delete`, `update`, or in a view, you cannot specify ordering. If there is an implied order on the table from a clustered index, that order applies; otherwise, the results are unpredictable, as they can be in any order.
- `<n>` is an unsigned 32-bit value between 0 through  $2^{32}-1$  (4GB-1 or 4,294,967,295). Zero indicates "no" rows.
- When used with cursors, `top <n>` limits the overall size of the result set. Specifying `set cursor rowcount` limits the results of a single fetch.
- When a view definition contains `select top <n>` and a query with a `where` clause uses it, the results may be inconsistent.
- When used with `<limit_clause>`, `top <n>` is evaluated after `<limit_clause>`. See [The Limit Clause and "Top N" Option \[page 727\]](#).

### `<select_list>`

consists of one or more of the following items:

- "\*", representing all columns in `create table` order.
- A list of column names in the order in which you want to see them. When selecting an existing IDENTITY column, you can substitute the `syb_identity` keyword, qualified by the table name, where necessary, for the actual column name.
- A specification to add a new IDENTITY column to the result table:

```
<column_name> = identity (int | smallint | tinyint |  
precision)
```

If you specify `int`, `smallint`, or `tinyint`, the resulting column is an integer. If you specify `precision`, the result is numeric datatype.

- A replacement for the default column heading (the column name), in one of these forms:
  - `<column_heading> = <column_name>`
  - `<column_name column_heading>`
  - `<column_name> as <column_heading>`

The column heading can be enclosed in quotation marks for any of these forms.

The heading must be enclosed in quotation marks if it is not a valid identifier (that is, if it is a reserved word, if it begins with a special character, or if it contains spaces or punctuation marks).

- An expression (a column name, constant, function, or any combination of column names, constants, and functions connected by arithmetic or bitwise operators, or a subquery).
- A built-in function or an aggregate.
- Any combination of the items listed above.

The `<select_list>` can also assign values to variables, in the form:

```
<@variable> = <expression>[, <@variable> = <expression> ...]
```

You cannot combine variable assignment with any other `<select_list>` option.

#### `<into_clause>` ::=

- `into` – except when used with `existing table`, creates a new table based on the columns specified in the select list and the rows chosen in the `where` clause.
- `<colname>` – specifies encryption on `<colname>` in the target table. By default, the SAP ASE server decrypts data selected from the source table. You must use the `encrypt` keyword to preserve the data encryption or to encrypt a column in the target database that was not encrypted in the source database.
- `encrypt` – specifies the key used on the source data, or a different key.
- `with database...key` – indicates if the large object (LOB) data in the row is compressed and to what level.
  - 0 – the row is not compressed.
  - 1 through 9 – the SAP ASE server uses ZLib compression. Generally, the higher the compression number, the more the SAP ASE server compresses the LOB data, and the greater the ratio between compressed and uncompressed data (that is the greater the amount of space savings, in bytes, for the compressed data versus the size of the uncompressed data).  
However, the amount of compression depends on the LOB content, and the higher the compression level, the more CPU-intensive the process. That is, level 9 provides the highest compression ratio but also the heaviest CPU usage.
  - 100 – the SAP ASE server uses FastLZ compression. The compression ratio that uses the least CPU usage; generally used for shorter data.
  - 101 – the SAP ASE server uses FastLZ compression. A value of 101 uses slightly more CPU than a value of 100, but uses a better compression ratio than a value of 100.
- `compressed = <compression_level> | not compressed` – the compression algorithm ignores rows that do not use LOB data.
- `in row [( <length> )]` – sets or changes the in-row characteristics for the LOB columns in the target table. If you do not specify `<length>`, the SAP ASE server uses the configured default in-row length.  
By default, a LOB column in the target table inherits the storage property of the corresponding LOB column in the `selectconvert(text, <column>)` built-in function, the column then automatically uses off-row storage unless you change the setting by specifying `in row [( <length> )]`.
- `off row` – changes the storage format of the column from in-row to off-row.
- `external [[ <table> ] | <directory> | <file>]` – indicates that the type of the external object is a table, directory, or file. If you do not indicate a file, directory, or table, `select into` assumes that you are using a table.

#### **i** Note

You cannot specify an external location when using any part of the `<partition_clause>`. Partitions can be created only on tables on the current server and database.

- '`<server_name>.[<database>].[<owner>].<object_name>`' – indicates that you are selecting into a table or view found on the remote `<server_name>`.
- at '`<pathname>`' – indicates the full, operating system-specific path name of the external file or directory you are selecting into. All directories in `<pathname>` must be accessible to the SAP ASE server.
- column delimiter '`<string>`' – indicates the delimiter that you are using to separate columns after converting the column's data to string format. `<string>` can have as many as 16 characters. If you do not specify a delimiter, `select into` uses the tab character.
- on `<segment_name>` – specifies that the table is to be created on the named segment. Before the on `<segment_name>` option can be used, the device must be initialized with `disk init`, and the segment must be added to the database with `sp_addsegment`. See your system administrator or use `sp_helpsegment` for a list of the segment names available in your database.
- `dml_logging = (full | minimal)` – determines the amount of logging for insert, update and delete operations, and for some forms of bulk inserts:
  - `full` – the SAP ASE server logs all transactions
  - `minimal` – the SAP ASE server does not log row or page changes
- `lock datarows | datapages | allpages` – specifies the locking scheme to be used for a table created with a `select into` command. The default is the server-wide setting for the `lock scheme` configuration parameter.
- existing table `<table_name>` – indicates that you are selecting data into a proxy table. You cannot use this `select into` with any other table type except proxy. The column list in the `select` list must match the type, length, and number in the proxy table.

#### `<partition_clause> ::=`

- `partition by range` – specifies records are to be partitioned according values in the partitioning column or columns. Each partitioning column value is compared with sets of user-supplied upper and lower bounds to determine partition assignment.
- `<column_name>` – when used in the `<partition_clause>`, specifies a partition key column.
- `<partition_name>` – specifies the name of a new partition on which table records are to stored. Partition names must be unique within the set of partitions on a table or index. Partition names can be delimited identifiers if `set quoted_identifier` is on. Otherwise, they must be valid identifiers. If `<partition_name>` is omitted, the SAP ASE server creates a name in the form `<table_name>_<partition_id>`. The SAP ASE server truncates partition names that exceed the allowed maximum length.
- `values <= <constant> | MAX` – specifies the inclusive upper bound of values for a named partition. Specifying a constant value for the highest partition bound imposes an implicit integrity constraint on the table. The keyword `MAX` specifies the maximum value in a given datatype.
- on `<segment_name>` – when used in the `<partition_clause>`, specifies the name of the segment on which to place the partition. When using on `<segment_name>`, the logical device must already have been assigned to the

database with `create database` or `alter database`, and the segment must have been created in the database with `sp_addsegment`. See your system administrator or use `sp_helpsegment` for a list of the segment names available in your database.

- `partition by hash` – specifies records are to be partitioned by a system-supplied hash function. The function target table's LOB column is produced as a result of an expression, such as the computes the hash value of the partition keys that specify the partition to list. If the specifies records are to be partitioned by a system-supplied hash function. The function target table's LOB column is produced as a result of an expression, such as the computes the hash value of the partition keys that specify the partition to which records are assigned. which records are assigned.
- `partition by list` – specifies records are to be partitioned according to literal values specified in the named column. The partition key contains only one column. You can list up to 250 constants as the partition values for each list partition.
- `partition by roundrobin` – specifies records are to be partitioned in a sequential manner. A round-robin-partitioned table has no partitioning key. Neither the user nor the optimizer knows in which partition a particular record resides.

#### `<into_option> ::=`

- `max_rows_per_page` – limits the number of rows on data pages for a table created with `select into`. Unlike `fillfactor`, the `max_rows_per_page` value is maintained when data is inserted or deleted. `max_rows_per_page` is not supported on data-only-locked tables.
- `exp_row_size = <num_bytes>` – specifies the expected row size for a table created with the `select into` command. Valid only for datarows and datapages locking schemes and only for tables that have variable-length rows. Valid values are 0, 1, and any value greater than the minimum row length and less than the maximum row
- `reservepagegap = <num_pages>` – specifies a ratio of filled pages to empty pages that is to be left as `select into` allocates extents to store data. This option is valid only for the `select into` command. For each specified `<num_pages>`, one empty page is left for future expansion of the table. Valid values are 0 – 255. The default value is 0.
- `identity_gap = <gap>` – specifies the identity gap for the table. This value overrides the system identity gap setting for this table only.  
If you are creating a table in a `select into` statement from a table that has a specific identity gap setting, the new table does not inherit the identity gap setting from the parent table. Instead, the new table uses the identity burning set factor setting. To give the new table a specific `identity_gap` `select into` statement. You can give the new table an identity gap that is the same as or different from the parent table.
- `with compression = {none | page | row}` – indicates the level of compression to be applied to the table or partition. The new compression level applies to the newly inserted or updated data:
  - `none` – the data in this table or partition is not compressed. For partitions, `none` indicates that data in this partition remains uncompressed even if the table compression is altered to `row` or `page` compression.

- `row` – compresses one or more data items in an individual row. The SAP ASE server stores data in a `row`-compressed form only if the compressed form saves space compared to an uncompressed form. Set `row` compression at the partition or table level.
- `page` – when the page fills, existing data rows that are `row`-compressed are then compressed using page-level compression to create page-level dictionary, index, and character-encoding entries. Set `page` compression at the partition or table level.  
The SAP ASE server compresses data at the page level only after it has compressed data at the row level, so setting the compression to `page` implies both `page` and `row` compression.
- `lob_compression = <compression_level>` – determines the compression level for the table.

**<from\_clause> ::=**

- `from` – indicates which tables and views to use in the `select` statement. `from` required except when the `select` list contains no column names (that is, it contains constants and arithmetic expressions only):

```
select 5 x, 2 y, "the product is", 5*2 Result
```

x	y		Result
5	2	the product is	10

At most, a query can reference 250 tables and 128 worktables (such as those created by aggregate functions). The 250-table limit includes:

- Tables (or views on tables) listed in the `from` clause
- Each instance of multiple references to the same table (self-joins)
- Tables referenced in subqueries
- Tables being created with `into`
- Base tables referenced by the views listed in the `from` clause
- `<view_name>`, `<table_name>` – lists tables and views used in the `select` statement. Specify the database name if the table or view is in another database, and specify the owner's name if more than one table or view of that name exists in the database. The default value for `<owner>` is the current user, and the default value for `<database>` is the current database.

If there is more than one table or view in the list, separate their names by commas. The order of the tables and views following the keyword `from` does not affect the results.

You can query tables in different databases in the same statement.

Table names and view names can be given correlation names (aliases), either for clarity or to distinguish the different roles that tables or views play in self-joins or subqueries. To assign a correlation name, give the table or view name, then a space, then the correlation name, like this:

```
select pub_name, title_id
       from publishers pu, titles t
       where t.pub_id = pu.pub_id
```

All other references to that table or view (for example, in a `where` clause) must use the correlation name. Correlation names cannot begin with a numeral.

- `index <index_name>` – specifies the index to use to access `<table_name>`. You cannot use this option when you select from a view, but you can use it as part of a `select` clause in a `create view` statement.
- `parallel [<degree_of_parallelism>]` – specifies a parallel partition or index scan, if the SAP ASE server is configured to allow parallel processing. `<degree_of_parallelism>` specifies the number of worker processes that scan the table or index in parallel. If set to 1, the query executes serially.
- `prefetch <size>` – specifies the I/O size, in kilobytes, for tables bound to caches with large I/Os configured. You cannot use this option when you select from a view, but you can use it as part of a `select` clause in a `create view` statement. `sp_helpcache` shows the valid sizes for the cache an object is bound to or for the default cache. To configure the data cache size, use `sp_cacheconfigure`. When using `prefetch` and designating the prefetch size (`<size>`), the minimum is 2K and any power of two on the logical page size up to 16K.

prefetch size options, in kilobytes:

- 2K page size – 2, 4, 8 16
- 4K page size – 4, 8, 16, 32
- 8K page size – 8, 16, 32, 64
- 16K page size – 16, 32, 64, 128

The `prefetch` size specified in the query is only a suggestion. To allow the size specification, configure the data cache at that size. If you do not configure the data cache to a specific size, the default `prefetch` size is used.

If CIS is enabled, you cannot use `prefetch` for remote servers.

- `lru | mru` – LRU (least recently used) and MRU (most recently used) specify the buffer replacement strategy to use for the table. You cannot use this option when you select from a view, but you can use it as part of a `select` clause in a `create view` statement.
  - Use `lru` to force the optimizer to read the table into the cache on the LRU/MRU chain.
  - Use `mru` to discard the buffer from cache and replace it with the next buffer for the table.
- `holdlock` – makes a shared lock on a specified table or view more restrictive by holding it until the transaction completes (instead of releasing the shared lock as soon as the required data page is no longer needed, whether or not the transaction has completed).

The `holdlock` option applies only to the table or view for which it is specified, and only for the duration of the transaction defined by the statement in which it is used. Setting the `transaction isolation level 3` option of the `set` command implicitly applies a `holdlock` for each `select` statement within a transaction. The keyword `holdlock` is not permitted in a `select` statement that includes the `for browse` option. You cannot specify both a `holdlock` and a `noholdlock` option in a query.

If CIS is enabled, you cannot use `holdlock` for remote servers.
- `noholdlock` – prevents the server from holding any locks acquired during the execution of this `select` statement, regardless of the transaction isolation level



currently in effect. You cannot specify both a `holdlock` and a `noholdlock` option in a query.

- `readpast` – specifies that the query should silently skip rows with exclusive locks, without waiting and without generating a message.
- `shared` – instructs the SAP ASE server to use a shared lock (instead of an update lock) on a specified table or view. This allows other clients to obtain an update lock on that table or view. You can use the `shared` keyword only with a `select` clause included as part of a `declare cursor` statement. For example:

```
declare shared_crsr cursor
for select title, title_id
from titles shared
where title_id like "BU%"
```

You can use the `holdlock` keyword in conjunction with `shared` after each table or view name, but `holdlock` must precede `shared`.

- `<ANSI join>` – an inner or outer join that uses the ANSI syntax. The `from` clause specifies the tables to be joined.
- `inner` – includes only the rows of the inner and outer tables that meet the conditions of the `on` clause. The result set of a query that includes an inner join does not include any null-supplied rows for the rows of the outer table that do not meet the conditions of the `on` clause.
- `outer` – includes all the rows from the outer table whether or not they meet the conditions of the `on` clause. If a row does not meet the conditions of the `on` clause, values from the inner table are stored in the joined table as null values. The `where` clause of an ANSI outer join restricts the rows that are included in the query result.
- `left` – left joins retain all the rows of the table reference listed on the left of the join clause. The left table reference is referred to as the outer table or row-preserving table.

In the queries below, T1 is the outer table and T2 is the inner table:

```
T1 left join T2
T2 right join T1
```

- `right` – right joins retain all the rows of the table reference on the right of the join clause (see example above).
- `<search_conditions>` – used to set the conditions for the rows that are retrieved. A search condition can include column names, expressions, arithmetic operators, comparison operators, the keywords `not`, `like`, `is null`, `and`, `or`, `between`, `in`, `exists`, `any`, and `all`, subqueries, case expressions, or any combination of these items.

**`index_compression = {none | page}`**

creates an index compressed table by selecting from an existing table:

- `none` – indexes on the specified table are not compressed. Indexes that are specifically created with `index_compression = PAGE` are compressed.
- `page` – all indexes on the specified table are compressed. Indexes that are specifically created with `index_compression = NONE` are not compressed.

`<column_list>`

is a list of columns separated by commas.

#### **<group\_by\_clause> ::=**

- `group by` – finds a value for each group. These values appear as new columns in the results, rather than as new rows.  
When `group by` is used with standard SQL, each item in the select list must either have a fixed value in every row in the group or be used with aggregate functions, which produce a single value for each group. Transact-SQL has no such restrictions on the items in the select list. Also, Transact-SQL allows you to group by any expression (except by a column alias); with standard SQL, you can group by a column only.  
You can use the following aggregates with `group by` (<expression> is almost always a column name):
  - `sum` ([all | distinct] <expression>) – Total of the values in the numeric column.
  - `avg` ([all | distinct] <expression>) – Average of the values in the numeric column.
  - `count` ([all | distinct] <expression>) – Number of (distinct) non-null values in the column returned as an integer.
  - `count_big` ([all | distinct] <expression>) – Number of distinct non-null values in the column returned as a bigint.
  - `count` (\*) – Number of selected rows returned as an integer.
  - `count_big` (\*) – Number of selected rows returned as a bigint.
  - `max` (<expression>) – Highest value in the column.
  - `min` (<expression>) – Lowest value in the column.A table can be grouped by any combination of columns — that is, groups can be nested within each other. You cannot group by a column heading; you must use a column name, an expression, or a number representing the position of the item in the select list.
- `group by all` – includes all groups in the results, even those that do not have any rows that meet the search conditions.
- <aggregate\_free\_expression> – is an expression that includes no aggregates.

#### **having**

sets conditions for the `group by` clause, similar to the way that `where` sets conditions for the `select` clause. There is no limit on the number of conditions that can be included.

You can use a `having` clause without a `group by` clause.

If any columns in the select list do not have aggregate functions applied to them and are not included in the query's `group by` clause (illegal in standard SQL), the meanings of `having` and `where` are somewhat different.

In this situation, a `where` clause restricts the rows that are included in the calculation of the aggregate, but does not restrict the rows returned by the query. Conversely, a `having` clause restricts the rows returned by the query, but does not affect the calculation of the aggregate.

#### **<limit\_clause> ::=**

supports returning a specific continuous set of rows from a query result. For example, 100 rows from the 10th or 100th row can be returned. `<limit_clause>` can also return a special number of rows from the beginning of the query result, which is equivalent to the `top <n>` option:

- `rows` – indicates the the beginning of the `limit` clause
- `limit <limit_value>` – specifies the maximum number of rows in the result. `<limit_value>` is an unsigned `bigint` value.
- `offset <offset_value>` – specifies the number of rows to skip before the `select` statement result.

#### `<order_by_clause> ::=`

- `order by` – sorts the results by columns. In Transact-SQL, you can use `order by` for items that do not appear in the `select` list. You can sort by a column name, a column heading (or alias), an expression, or a number representing the position of the item in the `select` list (the `<select_list_number>`). If you sort by `select` list number, the columns to which the `order by` clause refers must be included in the `select` list, and the `select` list cannot be `*` (asterisk).  
Using `select max` with `order by` can return more than one row in the result set.
- `asc` – sorts results in ascending order (the default).
- `desc` – sorts results in descending order.

#### **compute**

used with row aggregates (`sum`, `avg`, `min`, `max`, `count`, and `count_big`) to generate control break summary values. The summary values appear as additional rows in the query results, allowing you to see detail and summary rows with one statement.

You cannot use a `select into` clause with `compute`.

If you use `compute by`, you must also use an `order by` clause. The columns listed after `compute by` must be identical to or a subset of those listed after `order by`, and must be in the same left-to-right order, start with the same expression, and not skip any expressions.

For example, if the `order by` clause is `order by a, b, c`, the `compute by` clause can be any (or all) of these:

```
compute by a, b, c
compute by a, b
compute by a
```

The keyword `compute` can be used without `by` to generate grand totals, grand counts, and so on. `order by` is optional if you use `compute` without `by`.

If CIS is enabled, `compute` is not forwarded to remote servers.

#### `<read_only_clause> ::=`

- `for {read only | update}` – specifies that a cursor result set is read-only or updatable.  
With SAP ASE versions earlier than 15.7, you can use this option only within a stored procedure, and only when the procedure defines a query for a cursor. In this case, the `select` is the only statement allowed in the procedure. It defines the `for`

`read only` or `for update` option (instead of the `declare cursor` statement). This method of declaring cursors provides the advantage of page-level locking while fetching rows.

Also, with SAP ASE versions earlier than 15.7, if the `select` statement in the stored procedure is not used to define a cursor, the SAP ASE server ignores the `for read only | update` option. See the Embedded SQL documentation for more information about using stored procedures to declare cursors.

If `select for update` is set, you can use the `for update` option at the language level outside of a stored procedure, but within a transaction. Such a `select` need not refer to a cursor. When you use `select for update` in datarows-locked tables, the selected rows are exclusively locked for the duration of the transaction.

For information about read-only or updatable cursors, see the *Transact-SQL User's Guide*.

- of `<column_name_list>` – is the list of columns from a cursor result set defined as updatable with the `for update` option.

#### `<isolation_clause> ::=`

- `at isolation` – specifies the isolation level of the query. If you omit this clause, the query uses the isolation level of the session in which it executes (isolation level 1 by default). The `at isolation` clause is valid only for single queries or within the `declare cursor` statement. The SAP ASE server returns a syntax error if you use `at isolation`:
  - With a query using the `into` clause
  - Within a subquery
  - With a query in the `create view` statement
  - With a query in the `insert` statement
  - With a query using the `for browse` clause

If there is a `union` operator in the query, you must specify the `at isolation` clause after the last `select`. If you specify `holdlock`, `noholdlock`, or `shared` in a query that also specifies `at isolation read uncommitted`, the SAP ASE server issues a warning and ignores the `at isolation` clause. For the other isolation levels, `holdlock` takes precedence over the `at isolation` clause. For more information about isolation levels, see the *Transact-SQL User's Guide*.

If CIS is enabled, you cannot use `at isolation` for remote servers.

If the table is multiversion concurrency-control (MVCC)-enabled (at the schema level) then even if the session's isolation level is `read committed`, the data in the table is scanned using `statement snapshot` isolation level semantics

- `read uncommitted | 0` – specifies isolation level 0 for the query.
- `read committed | 1` – specifies isolation level 1 for the query.
- `repeatable read | 2` – specifies transaction isolation level 2 for the query.
- `serializable | 3` – specifies isolation level 3 for the query.
- `statement snapshot` – specifies isolation level statement snapshot for the query. If a command is executed using the statement snapshot isolation level, the DML or scanner reads the data snapshot that existed before the start of the statement. All statements qualify the rows according to the timestamp of the statement.

- `transaction snapshot` – specifies isolation level statement snapshot for the query. If a command is executed using the statement snapshot isolation level, the DML or scanner reads the data snapshot that existed before the start of the transaction. All statements within the transaction qualify the rows according to the timestamp of the transaction.
- `readonly statement snapshot` – specifies isolation level readonly statement snapshot for the query. If a command is executed using the readonly statement snapshot, scanners read the snapshot of data that existed before the start of statement, but update always updates the latest version of the row, regardless of the qualified version.

**for browse**

must be attached to the end of a SQL statement sent to the SAP ASE server in a DB-Library browse application. See the *Open Client DB-Library Reference Manual* for details.

**with recompile**

specifies that only the statements in stored procedures that are marked for recompile are recompiled. `with recompile` is supported for certain `select` statements. For examples and information about restrictions, see the *Transact-SQL Users Guide > Compiling Individual Statements in a Stored Procedure*.

**intersect**

creates the intersect of data specified by two `select` statements. For more information, see [Using intersect and except \[page 727\]](#).

**except**

returns rows from the first `select` statement which are not returned by a second `select` statement, see [Using intersect and except \[page 727\]](#).

**plan "<abstract plan>"**

specifies the abstract plan to use to optimize the query. It can be a full or partial plan, specified in the abstract plan language. See *Creating and Using Abstract Plans* in the *Performance and Tuning Guide* for more information.

## Examples

### Example 1

Selects all rows and columns from the `publishers` table:

```
select * from publishers
```

pub_id	pub_name	city	state
0736	New Age Books	Boston	MA
0877	Binnet & Hardley	Washington	DC
1389	Algodata Infosystems	Berkeley	CA

### Example 2

Selects all rows from specific columns of the `publishers` table:

```
select pub_id, pub_name, city, state from publishers
```

### Example 3

Selects all rows from specific columns of the `publishers` table, substituting one column name and adding a string to the output:

```
select "The publisher's name is",
       Publisher = pub_name, pub_id
from publishers
```

	Publisher	pub_id
-----	-----	-----
The publisher's name is	New Age Books	0736
The publisher's name is	Binnet & Hardley	0877
The publisher's name is	Algodata Infosystems	1389

### Example 4

Selects all rows from specific columns of the `titles` table, substituting column names:

```
select type as Type, price as Price
from titles
```

### Example 5

Specifies the locking scheme and the reserve page gap for `select into`:

```
select title_id, title, price
into bus_titles
lock datarows with reservepagegap = 10
from titles
where type = "business"
```

### Example 6

Encrypts the `creditcard` column when selecting into the `bigspenders` table:

```
select creditcard, custid, sum(amount)
into #bigspenders (creditcard
encrypt with cust.database.new_cc_key) from daily_xacts
group by creditcard having sum(amount) > $5000
```

### Example 7

Selects only the rows that are not exclusively locked. If any other user has an exclusive lock on a qualifying row, that row is not returned:

```
select title, price
from titles readpast
where type = "news"
and price between $20 and $30
```

### Example 8

Selects specific columns and rows, placing the results into the temporary table `#advance_rpt`:

```
select pub_id, total = sum (total_sales)
into #advance_rpt
```

```
from titles
where advance < $10000
      and total_sales is not null
group by pub_id
having count (*) > 1
```

#### Example 9

Selects the top 3 rows from `au_lname` from the `authors` table:

```
select top 3 au_lname from authors
```

#### Example 10

Concatenates two columns and places the results into the `#tempnames` temporary table:

```
select "Author_name" = au_fname + " " + au_lname
into #tempnames
from authors
```

#### Example 11

Selects specific columns and rows, returns the results ordered by type from highest to lowest, and calculates summary information:

```
select type, price, advance from titles
order by type desc
compute avg (price), sum (advance) by type
compute sum (price), sum (advance)
```

#### Example 12

Selects specific columns and rows, and calculates totals for the `price` and `advance` columns:

```
select type, price, advance
from titles compute sum (price), sum (advance)
```

#### Example 13

Creates the `coffeetabletitles` table, a copy of the `titles` table which includes only books priced over \$20:

```
select * into coffeetabletitles from titles
where price > $20
```

#### Example 14

Creates the `newtitles` table, an empty copy of the `titles` table:

```
select * into newtitles from titles
where 1 = 0
```

#### Example 15

Gives an optimizer hint:

```
select title_id, title
from titles (index title_id_ind prefetch 16)
where title_id like "BU%"
```

### Example 16

Selects the `IDENTITY` column from the `sales_east` and `sales_west` tables by using the `syb_identity` keyword:

```
select sales_east.syb_identity, sales_west.syb_identity
from sales_east, sales_west
```

### Example 17

Creates the `newtitles` table, a copy of the `titles` table with an `IDENTITY` column:

```
select *, row_id = identity (10)
into newtitles from titles
```

### Example 18

Specifies a transaction isolation level for the query:

```
select pub_id, pub_name
from publishers
at isolation read uncommitted
```

### Example 19

Selects from `titles` using the `repeatable read` isolation level. No other user can change values in or delete the affected rows until the transaction completes:

```
begin tran
select type, avg (price)
  from titles
  group by type
at isolation repeatable read
```

### Example 20

Gives an optimizer hint for the parallel degree for the query:

```
select ord_num from salesdetail
(index salesdetail parallel 3)
```

### Example 21

Joins the `titleauthor` and the `titles` tables on their `title_id` columns. The result set only includes those rows that contain a `price` greater than 15:

```
select au_id, titles.title_id, title, price
from titleauthor inner join titles
on titleauthor.title_id = titles.title_id
and price > 15
```

### Example 22

The result set contains all the authors from the `authors` table. The authors who do not live in the same city as their publishers produce null values in the `pub_name` column. Only the authors who live in the same city as their publishers, Cheryl Carson and Abraham Bennet, produce a non-null value in the `pub_name` column:

```
select au_fname, au_lname, pub_name
from authors left join publishers
on authors.city = publishers.city
```



### Example 23

Create a new table with an identity gap (`newtable`) from an existing table (`oldtable`). The table is specify using the `select into` statement:

```
select identity into newtable
with identity_gap = 20
from oldtable
```

For more information about identity gaps, see *Managing Identity Gaps in Tables* in the *Transact-SQL Users Guide*.

### Example 24

Creates a new table, `bay_area_authors` with row-level compression, and populates it with information about authors that live in the San Francisco Bay Area:

```
select * into bay_area_authors
with compression = row
from authors
where postalcode like '94%'
```

### Example 25

Creates a new table named `titles_2` that compresses all columns except `title` and `advance`:

```
select * into titles_2
(title not compressed,
advance not compressed)
with compression = page
from titles
```

### Example 26

Set the `select for update` configuration parameter, perform a `select for update`, then an update within the same transaction:

```
sp_configure 'select for update', 1
```

Parameter Name	Unit	Type	Default	Memory Used	Config Value	Run Value
select for update		0	0	1	1	1
not applicable		dynamic				

(1 row affected)  
Resulting configuration value and memory use have not changed from previous values: new configuration value 1, previous value 1.  
(return status = 0)

```
begin tran
```

```
select c_int, c_bigdatetime from basetb11
where c_int > 90 for update of c_bigint
```

c_int	c_bigdatetime
91	Sep 14 2009 9:00:00.000000PM
92	Sep 15 2009 9:00:00.000000PM
93	Sep 16 2009 9:00:00.000000PM
94	Sep 17 2009 9:00:00.000000PM

```

95          Sep 18 2009  9:00:00.000000PM
96          Sep 19 2009  9:00:00.000000PM
97          Sep 20 2009  9:00:00.000000PM
98          Sep 21 2009  9:00:00.000000PM
99          Sep 22 2009  9:00:00.000000PM
100         Sep 23 2009  9:00:00.000000PM
(10 rows affected)

```

```
update basetbl1 set c_bigint = 5000 where c_int > 90
```

```

(10 rows affected)
commit tran
go

```

### Example 27

Creates a new table `sales_report` from an existing table `sales_detail`. The new table is partitioned by range on the `qty` column.

```

select * into sales_report partition by range (qty)
  (smallorder values <= (500) on seg1,
  bigorder values <= (5000) on seg2)
from sales_detail

```

### Example 28

Finds the statements that incur too many I/Os as candidates for tuning:

```
select lio_avg, qtext from sysquerymetrics order by
lio_avg
```

### Example 29

Selects the `titles` table into the `pubs3` database:

```

select title_id, title, price
into bus_titles
with dml_logging = minimal
from titles

```

### Example 30

Performs a `select distinct` from table `tbl1`, which includes 1023 partitions:

```

select distinct int_1 from tbl1
select int_1 from tbl1 order by int_1
select * from tbl1 order by int_1

```

### Example 31

Selects a limited number of rows using the `limit` clause:

```

1> select * from limit_tab order by a rows limit 2 offset 3
2> go

```

```

a          b          c
-----
          4          4 row4
          5          5 row5
(2 rows affected)

```

### Example 32

Selects a limited number of rows using the `offset` clause:

```
1> select * from limit_tab order by a rows offset 8
2> go
```

```
 a          b          c
-----
          9          9   row9
          10         10 row10
(2 rows affected)
```

Using the `offset` clause without the `order_by` clause displays an error message:

```
1> select * from limit_tab rows offset 2
2> go
```

```
Msg 102, Level 15, State 181:
Line 1:
Incorrect syntax near '2'.
```

### Example 33

Recompile an entire statement having subqueries/derived tables using the `:with recompile` clause:

```
select pub_name from
publishers where
"business" in
    (select type from
      (select type from titles, publishers
       where titles.pub_id = publishers.pub_id) dt_titles )
with recompile
```

## Usage

- The keywords in the `select` statement, as in all other statements, must be used in the order shown in the syntax statement.
- The maximum number of expressions in a `select` statement is 4096.
- The keyword `all` can be used after `select` for compatibility with other implementations of SQL. `all` is the default. Used in this context, `all` is the opposite of `distinct`. All retrieved rows are included in the results, whether or not some are duplicates.
- Except in `create table`, `create view`, and `select into` statements, column headings may include any characters, including blanks and SAP ASE keywords, if the column heading is enclosed in quotes. If the heading is not enclosed in quotes, it must conform to the rules for identifiers.
- The character string indicated by `like` cannot be longer than 255 bytes.
- You cannot use the `select...for browse` option on tables containing more than 255 columns.
- Column headings in `create table`, `create view`, and `select into` statements, as well as table aliases, must conform to the rules for identifiers.
- To insert data with `select` from a table that has null values in some fields into a table that does not allow null values, you must provide a substitute value for any NULL entries in the original table. For example, to

insert data into an `advances` table that does not allow null values, this example substitutes "0" for the NULL fields:

```
insert advances
select pub_id, isnull (advance, 0) from titles
```

Without the `isnull` function, this command would insert all the rows with non-null values into the `advances` table, and produce error messages for all rows where the `advance` column in the `titles` table contained NULL.

If you cannot make this kind of substitution for your data, you cannot insert data containing null values into the columns with the NOT NULL specification.

Two tables can be identically structured, and yet be different as to whether null values are permitted in some fields. Use `sp_help` to see the null types of the columns in your table.

- The default length of the `text`, `unitext`, or `image` data returned with a `select` statement is 32K. Use `set textsize` to change the value. The size for the current session is stored in the global variable `<@@textsize>`. Certain client software may issue a `set textsize` command on logging in to the SAP ASE server.
- Data from remote SAP ASE servers can be retrieved through the use of remote procedure calls. See `create procedure` and `execute` for more information.
- A `select` statement used in a cursor definition (through `declare cursor`) must contain a `from` clause, but it cannot contain a `compute`, `for browse`, or `into` clause. If the `select` statement contains any of the following constructs, the cursor is considered read-only and not updatable:
  - `distinct` option
  - `group by` clause
  - Aggregate functions
  - `union` operator

If you declare a cursor inside a stored procedure with a `select` statement that contains an `order by` clause, that cursor is also considered read-only. Even if it is considered updatable, you cannot delete a row using a cursor that is defined by a `select` statement containing a join of two or more tables. See `declare cursor` for more information.

- If a `select` statement that assigns a value to a variable returns more than one row, the last returned value is assigned to the variable. For example:

```
declare @x varchar (40)
select @x = pub_name from publishers
print @x
```

```
(3 rows affected)
Algodata Infosystems
```

Before you write queries using the ANSI inner and outer join syntax, read *Outer Joins* in the *Transact-SQL Users Guide*.

See also:

- `avg`, `count`, `isnull`, `max`, `min`, `sum` in *Reference Manual: Building Blocks*
- `sp_cachestrategy`, `sp_chgattribute`, `sp_dboption` in *Reference Manual: Procedures*

## Standards

ANSI SQL – Compliance level: Entry-level compliant.

Transact-SQL extensions include:

- `select into` to create a new table
- `lock` clauses
- `compute` clauses
- Global and local variables
- `index` clause, `prefetch`, `parallel` and `lru | mru`
- `holdlock`, `noholdlock`, and `shared` keywords
- "`<column_heading> = <column_name>`"
- Qualified table and column names
- `select` in a `for browse` clause
- The use, within the `select` list, of columns that are not in the `group by` list and have no aggregate functions
- `at isolation repeatable read | 2` option

## Permissions

The permission checks for `select` differ based on your granular permissions settings.

Setting	Description
---------	-------------

<b>Enabled</b>	With granular permissions enabled, you must be the table or view owner. You must be a user with <code>select</code> permission on the table or view.
----------------	---

<b>Disabled</b>	With granular permissions disabled, you must be the table or view owner or a user with <code>sa_role</code> . You must be a user with <code>select</code> permission on the table or view. <code>select</code> permission defaults to the owner of the table or view, who can transfer it to other users.
-----------------	---

## Auditing

Enable object-specific `select` auditing option to audit `select` statements on a specific table or view. Enable user-specific `table_access` or `view_access` auditing options to audit table or view access by a specific user.

Values in `event` and `extrainfo` columns from the `sysaudits` table are:

Audit option	Event	Command or access audited	Information in <code>extrainfo</code> :
<code>select</code> <code>table_access</code>	62	<code>select from a table</code>	<ul style="list-style-type: none"><li>• <i>Roles</i> – current active roles</li><li>• <i>Full command text</i> – full text of <code>select</code> command</li></ul>
<code>select</code> <code>view_access</code>	63	<code>select from a view</code>	<ul style="list-style-type: none"><li>• <i>Previous value</i> – NULL</li><li>• <i>Current value</i> – NULL</li><li>• <i>Other information</i> – a list of parameter name value pairs</li><li>• <i>Proxy information</i> – original login name, if set <code>proxy</code> is in effect</li></ul>

Full command text and parameter names/values are included in `extrainfo`. For example:

```
sa_role sso_role oper_role sybase_ts_role mon_role; select *
  from t1 where c1 = @val1 and c2 = @val2; ; ; @val1=10, @val2 = 20;
; sa/ase;
```

For more information about auditing, see *Security Administration Guide > Auditing*.

## Related Information

[alter database \[page 14\]](#)

[compute Clause \[page 125\]](#)

[create database \[page 140\]](#)

[create index \[page 192\]](#)

[create table \[page 273\]](#)

[delete \[page 391\]](#)

[disk init \[page 401\]](#)

[group by and having Clauses \[page 558\]](#)

[insert \[page 572\]](#)

[order by Clause \[page 630\]](#)

[set \[page 732\]](#)

[union operator \[page 812\]](#)

[update \[page 819\]](#)

[where Clause \[page 855\]](#)

## 1.115.1 Using select into

`select into` is a two-step operation. The first step creates the new table, and the second step inserts the specified rows into the new table.

### i Note

You can `select into` a CIS existing table.

- Page allocations during `select into` operations are logged, so large `select into` operations may fill the transaction log.  
If a `select into` statement fails after creating a new table, the SAP ASE server does *not* automatically drop the table or deallocate its first data page. This means that any rows inserted on the first page before the error occurred remain on the page. Check the value of the @@<error> global variable after a `select into` statement to be sure that no error occurred. Use the `drop table` statement to remove the new table, then reissue the `select into` statement.
- The name of the new table must be unique in the database and must conform to the rules for identifiers. You can also `select into` temporary tables (see Examples 7, 8, and 11).
- Any rules, constraints, or defaults associated with the base table are not carried over to the new table. Bind rules or defaults to the new table using `sp_bindrule` and `sp_bindefault`.
- `select into` does not carry over the base table's `max_rows_per_page` value, and it creates the new table with a `max_rows_per_page` value of 0. Use `sp_chgattribute` to set the `max_rows_per_page` value.
- The `select into/bulkcopy/pllsort` option must be set to `true` (by executing `sp_dboption`) in order to `select into` a permanent table. You do not have to set the `select into/bulkcopy/pllsort` option to `true` in order to `select into` a temporary table, since the temporary database is never recovered.  
After you have used `select into` in a database, you must perform a full database dump before you can use the `dump transaction` command. `select into` operations log only page allocations and not changes to data rows. Therefore, changes are not recoverable from transaction logs. In this situation, issuing the `dump transaction` statement produces an error message instructing you to use `dump database` instead.  
By default, the `select into/bulkcopy/pllsort` option is set to `false` in newly created databases. To change the default situation, set this option to `true` in the `model` database.
- `select into` can be used with an archive database.
- `select into` runs more slowly while a `dump database` is taking place.
- You can use `select into` to create a duplicate table with no data by having a false condition in the `where` clause (see Example 12).
- You must provide a column heading for any column in the `select` list that contains an aggregate function or any expression. The use of any constant, arithmetic or character expression, built-in functions, or concatenation in the `select` list requires a column heading for the affected item. The column heading must be a valid identifier or must be enclosed in quotation marks (see Examples 7 and 8).
- Datatypes and nullability are implicitly assigned to literal values when `select into` is used, such as:

```
select x = getdate () into mytable
```

This results in a non-nullable column, regardless of whether `allow nulls by default` is on or not. It depends upon how the `select` commands are used and with what other commands within the syntax.

The `convert` syntax allows you to explicitly specify the datatype and nullability of the resulting column, not the default.

Wrap `getdate` with a function that does result in a null, such as:

```
select x = nullif (getdate (), "1/1/1900") into mytable
```

Or, use the `convert` syntax:

```
select x = convert (datetime null, getdate ()) into mytable
```

- You cannot use `select into` inside a user-defined transaction or in the same statement as a `compute` clause.
- To select an IDENTITY column into a result table, include the column name (or the `syb_identity` keyword) in the `select` statement's `<column_list>`. The new column observes the following rules:
  - If an IDENTITY column is selected more than once, it is defined as NOT NULL in the new table. It does not inherit the IDENTITY property.
  - If an IDENTITY column is selected as part of an expression, the resulting column does not inherit the IDENTITY property. It is created as NULL if any column in the expression allows nulls; otherwise, it is created as NOT NULL.
  - If the `select` statement contains a `group by` clause or aggregate function, the resulting column does not inherit the IDENTITY property. Columns that include an aggregate of the IDENTITY column are created NULL; others are NOT NULL.
  - An IDENTITY column that is selected into a table with a union or join does not retain the IDENTITY property. If the table contains the union of the IDENTITY column and a NULL column, the new column is defined as NULL. Otherwise, it is defined as NOT NULL.
- You cannot use `select into` to create a new table with multiple IDENTITY columns. If the `select` statement includes both an existing IDENTITY column and a new IDENTITY specification of the form `<column_name = >identity< (precision)>`, the statement fails.
- If CIS is enabled, and if the `into` table resides on the SAP ASE server, the SAP ASE server uses bulk copy routines to copy the data into the new table. Before doing a `select into` with remote tables, set the `select into/bulkcopy` database option to `true`.
- For information about the Embedded SQL command `select into <host_var_list>`, see the *Open Client Embedded SQL Reference Manual*.
- Considerations for using `select into` in an in-memory row storage (IMRS) cache system:
  - You cannot use `select into` with the IMRS parameters.
  - New rows are inserted directly into the page store if the table being selected into is IMRS-enabled.

## 1.115.2 Converting the NULL Properties of a Target Column with `select...into`

Use the `convert` command to change the nullability of a target column into which you are selecting data.

For example, the following selects data from the `titles` table into a target table named `temp_titles`, but converts the `total_sales` column from `null` to `not null`:

```
select title, convert (char (100) not null, total_sales)
total_sales
into #temp-sales
```



```
from titles
```

### 1.115.3 Specifying a Compression Level

Destination tables you create with `select into` do not inherit any configuration from the source table. That is, if the table from which you pull data is configured for row-level compression, the table that results from the `select into` is not configured for compression unless you explicitly state the compression level.

- You can indicate column-, partition-, and table-level compression for the destination table (the compression level of the partition overrides the compression level of the table).
- When you compress the target table, the SAP ASE server selects the compression level for columns (if they qualify), regardless of the compression level of the corresponding columns in the source table.
- The `select into` command can include a list of columns that are not compressed on the target table.
- You cannot encrypt compressed columns on a target table.

### 1.115.4 Parameter Interactions with Data Compression

The various `select` parameters behave differently when working with compression.

- `max_rows_per_page` applies only to allpages-locked compressed tables; you cannot use it on data-only-locked tables.
- You can use `exp_row_size` on allpages- and data-only-locked tables with variable-length columns. However, the table must be able to expand updates on the same page without causing page splits on allpages-locked tables or row forwarding on data-only-locked tables. `exp_row_size` computes space limits identically for compressed and uncompressed tables. However, because compression results in a page with a lot of free space, the space set aside for `exp_row_size` may cause far fewer rows to fit on the page than would fit on this page if you did not set `exp_row_size`. You cannot use `exp_row_size` on tables with fixed-length columns, even though the SAP ASE server may convert some fixed-length columns to variable-length columns during the compression process.
- `fillfactor` applies determines the space used on the data pages after compression. This is relevant only when you are creating clustered indexes, an operation which requires a sort of the data pages.

### 1.115.5 Using `select` for update

If the configuration parameter `select for update` is set to 1, the rows selected by `select for update` are exclusively locked provided that the command is executed on a datarows-locked table within a transaction context, or in chained mode. If `select for update` is run within a cursor context, the `cursor open` and `fetch` statements must be within the context of a transaction.

Rows selected with `select for update`, within or outside of a cursor context, retain an exclusive lock until the transaction is complete.

Limitations of `select for update`:

- `select for update` is not valid in a subquery block.
- `select for update` is applicable only when the `select` returns rows directly from a base table and not from a work table. You cannot use `select for update` with queries that have aggregates or `group by`, `computed`, `union`, `having`, or `distinct` clauses.
- More rows may qualify for the actual transaction update than with `select for update`. These rows may appear in the updated set. Prevent such “phantom” rows by using isolation level 3.
- During `select` processing, concurrent `select for update` tasks may attempt to lock the same set of rows in different order, causing application deadlocks. However, once `select for update` completes, subsequent updates to the set of rows are not blocked, and encounter no deadlocks.
- All existing restrictions on updateable cursors apply to `select for update` both within and outside of the cursor context. The only difference is that with `select for update`, the `order by` clause is supported with an updateable cursor. The limitations and restrictions on updateable cursors apply to both language and execute cursors.
- All tables referenced by `select for update` must be from the same database.
- `select for update` is supported only on tables with datarows locked.

## 1.115.6 Specifying in-row LOB Columns

By default, LOB columns in the target table inherit the storage property of the corresponding LOB columns in the `select` list. If the target table’s LOB column is produced as a result of an expression, such as the `convert(text, <column>)` built-in function, then the column automatically uses off-row storage.

## 1.115.7 Specifying a Lock Scheme Using `select...into`

The `lock` option, used with `select...into`, allows you to specify the locking scheme for the table created by the command. If you do not specify a locking scheme, the default locking scheme, as set by the configuration parameter `lock scheme`, is applied.

When you use the `lock` option, you can also specify the space management properties `max_rows_per_page`, `exp_row_size`, and `reservepagegap`.

You can change the space management properties for a table created with `select into`, using `sp_chgattribute`.

## 1.115.8 Specifying a Partition Strategy Using `select...into`

The `partitions_clause`, when used with `select...into`, allows you to specify the partition properties of the table created by the command. If you do not specify a partition type, the SAP ASE server creates an unpartitioned table. If any row to be inserted does not satisfy the criteria for any partition in the target table, `select...into` fails.

## 1.115.9 Using index, prefetch, and lru | mru

The `index`, `prefetch` and `lru | mru` options specify the index, cache and I/O strategies for query execution. These options override the choices made by the SAP ASE optimizer. Use them with caution, and always check the performance impact with `set statistics io on`.

For more information about using these options, see the *Performance and Tuning Guide*.

## 1.115.10 Using Encrypted Columns

Considerations for using encrypted columns.

If you use the `encrypt` clause without specifying a key name, the SAP ASE server uses the database default key to encrypt the data in the target column.

If a column in the source table is encrypted and you do not specify the `encrypt` clause for the target column, the SAP ASE server decrypts the data in the source table and inserts plain text data in the target column.

If you specify encryption for the target column with the same key used for the source column data, and if the key does not use an initialization vector or random padding, then the SAP ASE server copies the data from the source column to the target column as cipher text, without intermediate decryption and reencryption operations.

If, however, you specify encryption for the target column using a different key from that used for the source column, or if the key uses an initialization vector or padding during encryption, the SAP ASE server performs a decryption and encryption operation for each selected row of the encrypted column.

## 1.115.11 Using parallel

The `parallel` option reduces the number of worker threads that the SAP ASE optimizer can use for parallel processing. The `<degree_of_parallelism>` cannot be greater than the configured `max_parallel_degree`. If you specify a value that is greater than the configured `max_parallel_degree`, the optimizer ignores the `parallel` option.

When multiple worker processes merge their results, the order of rows that the SAP ASE server returns may vary from one execution to the next. To get rows from partitioned tables in a consistent order, use an `order by` clause, or override parallel query execution by using `parallel 1` in the `from` clause of the query.

A `from` clause specifying `parallel` is ignored if any of the following conditions is true:

- The `select` statement is used for an update or insert.
- The `from` clause is used in the definition of a cursor.
- `parallel` is used in the `from` clause within any inner query blocks of a subquery.
- The `select` statement creates a view.
- The table is the inner table of an outer join.
- The query specifies `min` or `max` on the table and specifies an index.
- An unpartitioned clustered index is specified or is the only `parallel` option.

- The query specifies `exists` on the table.
- The value for the configuration parameter `max_scan_parallel_degree` is 1 and the query specifies an index.
- A nonclustered index is covered. For information on index covering, see *Indexes* in the *Performance and Tuning Guide*.
- The table is a system table or a virtual table.
- The query is processed using the OR strategy. For an explanation of the OR strategy, see the *Performance and Tuning Guide*.
- The query returns a large number of rows to the user.

## 1.115.12 Using `readpast`

The `readpast` option allows a `select` command to access the specified table without being blocked by incompatible locks held by other tasks. You can perform `readpast` queries only on data-only-locked tables.

If the `readpast` option is specified for an allpages-locked table, the `readpast` option is ignored. The command operates at the isolation level specified for the command or session. If the isolation level is 0, dirty reads are performed, and the command returns values from locked rows and does not block. If the isolation level is 1 or 3, the command blocks when pages with incompatible locks must be read.

This table shows the interactions of session-level isolation levels and `readpast` on a table in a `select` command:

Table 6: Effects of Session-Level Isolation Levels and `readpast`

Session Isolation Level	Effects
0, <code>read uncommitted</code> (dirty reads)	<code>readpast</code> is ignored, and rows containing uncommitted transactions are returned to the user. A warning message is printed.
1, <code>read committed</code>	Rows or pages with incompatible locks are skipped; no locks are held on the rows or pages read  Using <code>readpast</code> may produce duplicates and adding the <code>distinct</code> clause does not clear this problem.  To resolve this, when using <code>readpast</code> , use a <code>group by</code> clause <i>in addition to</i> a <code>distinct</code> clause to avoid duplicates.
2, <code>repeatable read</code>	Rows or pages with incompatible locks are skipped; shared locks are held on all rows or pages that are read until the end of the statement or transaction; holds locks on all pages read by the statement until the transaction completes.
3, <code>serializable</code>	<code>readpast</code> is ignored, and the command executes at level 3. The command blocks on any rows or pages with incompatible locks.

`select` commands that specify `readpast` fail with an error message if they also include any of the following:

- An `at isolation` clause, specifying 0 or `read uncommitted`
- An `at isolation` clause, specifying 3 or `serializable`
- The `holdlock` keyword on the same table

If `at isolation 2` or `at isolation repeatable read` is specified in a `select` query that specifies `readpast`, shared locks are held on the `readpast` tables until the statement or transaction completes.

If a `select` command with the `readpast` option encounters a text column that has an incompatible lock on it, `readpast` locking retrieves the row, but returns the text column with a value of `null`. No distinction is made, in this case, between a text column containing a null value and a null value returned because the column is locked.

### 1.115.13 Expanded select \* Syntax

When the source text of a stored procedure or trigger is stored in the system table `syscomments`, a query using `select *` is stored in `syscomments` expanding the column list referenced in the `select *`.

For example, a `select *` from a table containing the columns `col1` and `col2` is stored as:

```
select <table>.col1, <table>.col2 from <table>
```

The expanding of the column-list checks whether identifiers (table-names, column-names and so on) comply with the rules for identifiers.

For example, if a table includes the columns `col1` and `2col`, the second column-name starts with a number, which can only be included by using brackets in the `create table` statement.

When performing a `select *` in a stored procedure or trigger from this table, the text in `syscomments` looks similar to:

```
select <table>.col1, <table>[2col] from <table>
```

For all identifiers used in the text that expands a `select *`, brackets are added when the identifier does not comply with the rules for identifiers.

You must add brackets around identifiers to make sure the SAP ASE server can use the SQL text while performing an upgrade to a more recent release.

### 1.115.14 Using select with Variables, Global Variables, and Constants

Issuing `select` statements that reference only `@variables`, `@@global variables`, and constants in chained mode do not start new transactions.

This enables you to create SQL constructs similar to:

```
set chained ON
<... Perform some DML or other commands ...>
select @@error, @@trancount, @@transtate
```

In some circumstances, SAP ASE may rollback the active transaction if an error occurs while executing DML or other statements. Use the `select` statement to check the state of the transaction while the server is in chained mode, and—without automatically starting a new transaction—collect the date and time the error occurred that triggered the rollback.

Although most functions start new transactions when used in `select` statements, these diagnostic functions do not:

- `getdate`
- `getutcdate`
- `current_date`
- `current_time`
- `current_bigdatetime`
- `current_bigtime`
- `abs`
- `asehostname`
- `hostname`
- `switchprop`

## 1.115.15 Pagination Queries Using `limit` and `offset`

You can limit your query results if you only want to see the first few rows or implement table pagination.

The `limit` option allows you to limit the number of rows returned from a query, while `offset` allows you to omit a specified number of rows before the beginning of the result set. Using both `limit` and `offset` skips both rows as well as limit the rows returned.

You can use `limit` and `offset` on these statement types:

- `select` statements
- Device tables
- Union
- Non-correlated subqueries

### Using `limit` and `offset` Together

- Typically, the values for `limit` and `offset` are natural numbers, and lower than the result size of the `order by` clause.
- Specifying a negative number for either `limit` or `offset` returns an error message.
- The result of `limit_clause` is empty when the value of `offset` is larger than or equal to the result size of the `order by` clause.
- When the values of `limit` and `offset` are larger than the result size of `order by`, only the rows from `offset` to the end of the result of `order by` are returned.  
This example specifies a limit of five rows starting from the seventh row (that is, the row immediately following the value specified by `offset`):

```
select * from table1 order by column1 rows limit 5 offset 6
```

If there are only 10 rows in `table1`, the result will contain only the remaining four rows, even though you specified a limit of five rows.

### i Note

When using both `limit` and `offset` clauses together, using the `order by` clause returns results in your desired order, and prevents a result set with an unexpected sort order.

## The Limit Clause and "Top N" Option

When used with `<limit_clause>`, `top <n>` is evaluated after `<limit_clause>`.

This example returns the employees from 10th to 17th at first, and then it filters out the first three employees (10th to 12th):

```
select top 3 * from employee
       where age < 30 order by age ASC rows limit 8 offset 10
```

## The Limit Clause, Union Statement, and Derived Tables

Using `<limit_clause>` with a union statement affects the entire union result. However when you use `<limit_clause>` in a derived table, this only affects the derived table.

In this example, `<limit_clause>` affects only those rows selected from both `t1` and `t2`:

```
select c1,c2 from t1 union (select d1,d2 from t2)
       order by c1,c2 rows limit 3 offset 2
```

In this second example, however, `<limit_clause>` only takes effect when executing the subquery:


```
select c1, c2 from t1 union
       (select d2, d2 from t2 order by d1,d2 rows limit 3)
```

## 1.115.16 Using intersect and except

Use the `intersect` parameter to return the common data of two or more queries, and the `except` parameters to subtract one query result set from another.

### intersect Parameter

The `intersect` parameter is used to return a single result set of a `select` statement for common data of two or more queries. Duplicate rows are eliminated from the result set and only the rows selected by all queries or data sets are returned. If a record exists in one query and not in the other, it will be omitted from the `intersect` results.



The syntax is:

```
select [ top <n>] <select_list>
    [<into_clause>] <from_clause> [<where_clause>]
    [<group_by_clause>] [<having_clause>]
    [intersect
    select [ top<n>] <select_list>
    [<from_clause>] [<where_clause>]
    [<group_by_clause>] [<having_clause>]]...
    [<order_by_clause>]
    [<compute_clause>]
```

where:

- `top <n>` – the top unsigned integer. The top limit applies to the individual selects that form an intersect, not to the intersect as a whole.
- `<into_clause>` – creates a new table based on the columns specified in the `select` list and the rows chosen in the `<where_clause>`. The first query in the intersect operation is the only one that can contain an `<into_clause>`.
- `intersect` – creates the intersect of data specified by two select statements.

This example shows the intersect results of tables t1 and t2:

```
1> select * from t1
2> go
a
-----
    2
    6
    1
    1
1> select * from t2
2> go
a
-----
    1
    6
    6
    6
    7
    7
    7
    7
1> select * from t1
2> intersect
3> select * from t2
4> go
a
-----
    1
    6
```



Usage:

- The maximum number of subqueries within a single side of an intersect is 50.
- The total number of tables that can appear on all sides of a intersect query is 256.
- You can use intersect in select-view statements. For example:

```
create view v1 as
select * from Jan1998Sales
intersect
select * from Feb1998Sales
```

- The clauses, `<order_by>` and `<compute_clause>` are allowed only at the end of the `intersect` statement to define the order of the final results, or to compute summary values.
- The clauses, `<group_by>` and `<having_clause>` can be used only within individual queries and cannot be used to affect the final result set.
- The default evaluation order of a SQL statement containing the `intersect` parameter is left-to-right.
- `intersect` is an n-ary operator. When inside a query with only `intersect` operators, brackets are not necessary to specify order. For example:

```
select * from t1 intersect (select * from t2 intersect select * from t3 )
```

is same as

```
(select * from t1 intersect select * from t2) intersect select * from t3
```

- The first query in an `intersect` statement may contain an `<into_clause>` that creates a table to hold the final result set. The `<into_clause>` must be in the first query, or you receive an error message.
- `intersect` can appear within an `insert...select` statement. For example:

```
insert into sales.fromeast
select * from sales
intersect
select * from sales_east
```

- All select lists in a statement must have the same number of expressions (column names, arithmetic expressions, aggregate functions, and so on) and same type (datatype). For example, the following statement is invalid because the first select list contains more expressions than the second:

```
/* Example of invalid command--shows imbalance */
/* in select list items */
select au_id, title_id, au_ord from titleauthor
intersect
select stor_id, date from sales
```

- Corresponding columns in the select lists of the `intersect` statements must occur in the same order. This is because `intersect` compares the columns one-to-one in the order given in the individual queries.
- The column names in the table resulting from an `intersect` are taken from the first individual query in the `intersect` statement. Define a new column heading for the result by setting it in the first query. To refer to a column in the result set by a new name (for example, in an `<order_by>` clause), refer to it by that name in the first select statement. For example, the following query is correct:

```
select Cities = city from stores
intersect
select city from stores_east
order by Cities
```

- Queries with the same set operators with explicit ordering is supported. For example:


```
select 1 intersect (select 2 intersect select 3)
```

Queries with different set operators and explicit ordering mentioned using parenthesis is not supported. For example:

```
select * from t1 intersect (select * from t2 union select * from t3)
```

## except Parameter

The `except` parameter is used to return a result set based on two select statements, in which the rows from the first select statement that are not available in second select statement, are returned. All rows from the second query are subtracted from the first query.



### i Note

`except` and `minus` can be used interchangeably. The parameter name `except` is used throughout the documentation for the sake of simplicity.

The syntax is:

```
select [top <n>] <select_list>
    [<into_clause>] <from_clause>] [<where_clause>]
    [<group_by_clause>] [<having_clause>]
except
select [top <n>] <select_list>
    [<into_clause>] <from_clause>] [<where_clause>]
    [<group_by_clause>] [<having_clause>]
```

where:

- `top <n>` – the top unsigned integer. The top limit applies to individual selects which are present on either side of the `except` parameter, not to the `except` as a whole.
- `<into_clause>` – creates a new table based on the columns specified in the select list and the rows chosen in the `<where_clause>`.
- `except` – returns rows from the first `select` statement that are not returned by second `select` statement.

This example shows the results of the `except` statement for tables `t1` and `t2`:

```
1> select * from t1
```

```

2> go
a
-----
      2
      6
      1
      1
1> select * from t2
2> go
a
-----
      1
      6
      6
      6
      7
      7
      7
      7
1> select * from t1
2> except
3> select * from t2
4> go
a
-----
      2

```

Usage:

- Multiple select queries are allowed. For example:

```
select 1 except select 2 except select 3
```

The execution order is:

```
(select 1 except select 2) except select 3
```

- The maximum number of subqueries within a single side of an `except` parameter is 50.
- The total number of tables that can appear on both sides of `except` parameter is 256.
- You can create views on `select` statements involving `except` parameter. For example:

```
create view v1 as
select * from t1
except
select * from t2
```

- The clauses `<order_by>` and `<compute_clause>` are allowed only at the end of the `except` statement, to define the order of the final results or to compute summary values.
- The group by and having clauses can be used only within individual queries and cannot be used to affect final result set.
- The first query in an `except` statement may contain an `into` clause that creates a table to hold the final result set. The `into` statement must be in the first query, or you receive an error message.
- The `except` operator is a binary operator. Parentheses are required to specify order. If order is not defined, `except` is evaluated in the order of left to right.
- The `except` parameter can appear within an `insert select` statement. For example:

```
insert into t3
select * from t1
except
```

```
select * from t2
```

- Both select lists in an SQL statement must have same number of expressions (column names, arithmetic expressions, aggregate functions, and so on). For example, the following statement is invalid because the first select list contains more expressions than the second:

```
select au_id, title_id, au_ord from titleauthor
except
select stor_id, date from sales
```

- Corresponding columns in the `select` lists of the `except` parameter must occur in the same order, because `except` compares the columns one-to-one in the order given in the individual queries.
- The column names in the table resulting from an `except` statement are taken from the first individual query in the statement. Define the new column heading for the result by setting it in the first query. To refer to a column in the result set by a new name, refer to it by the name in the first select statement. For example, following query is correct:

```
select Cities = city from stores
except
select city from stores_east
order by Cities
```

## 1.116 set

Sets SAP ASE query-processing options for the duration of the user's work session; sets some options inside a trigger or stored procedure.

### Syntax

```
set advanced_aggregation on/off
```

```
set @<variable> = <expression>[, @<variable> = <expression>...]
```

```
set ansinull {on | off}
```

```
set ansi_permissions {on | off}
```

```
set arithabort [arith_overflow | numeric_truncation] {on | off}
```

```
set arithignore [arith_overflow] {on | off}
```

```
set bulk array size <number>
```

```
set bulk batch size <number>
```

```
set builtin_date_strings <number>
```

```
set {chained, close on endtran, nocount, noexec, parseonly,  
self_recursion, showplan, sort_resources} {on | off}
```

```
set char_convert {off | on [with {error | no_error}] |  
<charset> [with {error | no_error}]}
```

```
set cis_rpc_handling {on | off}
```

```
set [clientname <client_name> | clienthostname <host_name>  
| clientapplname <application_name>]
```

```
set compression {on | off | default}
```

```
set cursor rows <number> for <cursor_name>
```

```
set {datefirst <number>, dateformat <format>, language <language>}
```

```
set delayed_commit {on | off | default}
```

```
set deferred_name_resolution { on | off }
```

```
set dml_logging {minimal | default}
```

```
set encryption passwd '<password_phrase>'  
for {key | column} {<keyname> | <column_name>}
```

```
set erase_residual_data {on | off}
```

```
set export_options {on | off}
```

```
set fipsflagger {on | off}
```

```
set flushmessage {on | off}
```

```
set fmtonly {on | off}
```

```
set forceplan {on | off}
```

```
set identity_insert [<database>.[<owner>.]<table_name> {on | off}
```

```
set identity_update <table_name> {on | off}
```

```
set index_union {on | off}
```

```
set ins_by_bulk {on | off}
```

```
set join_bloom_filter {on | off}
```

```
set literal_autoparam {on | off}
```

```
set lock {wait [<numsecs>] | nowait | default}
```

```
set logbulkcopy {on | off }
```

```
set materialized_view_optimization {disable | fresh | stale}
```

```
set metrics_capture {on | off}
```

```
set mon_stateful_history {on | off}
```

```
set no_chained_tran_for_10_select {on | off}
```

```
set nodata
```

```
set offsets {select, from, order, compute, table,  
            procedure, statement, param, execute} {on | off}
```

```
set option <show>
```

```
set opttimeoutlimit
```

```
set parallel_degree <number>
```

```
set plan {dump | load} [<group_name>] {on | off}
```

```
set plan exists check {on | off}
```

```
set plan for <show>
```

```
set plan optgoal {allrows_oltp | allrows_mix | allrows_dss |  
                user_defined_goal_identifier}
```

```
set plan optlevel <value>
```

```
set plan opttimeoutlimit <number>
```

```
set plan replace {on | off}
```

```
set prefetch [on|off]
```

```
set proc_output_params {on | off}
```

```
set proc_return_status {on | off}
```

```
set process_limit_action {abort | quiet | warning}
```

```
set proxy <login_name>
```

```
set quoted_identifier {on | off}
```

```
set remote_command_encryption {on | off}
```

```
set repartition_degree <number>
```

```
set repthreshold < number>
```

```
set resource_granularity <number>
```

```
set role {"sa_role" | "sso_role" | "oper_role" |  
         <role_name >[with passwd "<password>"]} {on | off}
```

```
set {rowcount <number>, textsize <number>}
```

```
set scan_parallel_degree <number>
```

```
set send_locator {on | off }
```

```
set session_authorization <login_name>
```

```
set switch [serverwide] {on | off} print_minlogged_mode_override
```

```
set switch [serverwide] {on | off} <trace_flag> , [<trace_flag> ,] [with <option>  
[, <option>]
```

```
set show_exec_info ["on" | "off"]
```

```
set show_object_list {on | off}
```

```
set show_permission_source ["on" | "off" ]
```

```
set show_permission_source, {on|off}
```

```
set show_sqltext {on | off}
```

```
set show_transformed_sql, {on|off}
```

```
set spinlock_aggregation {on | off}
```

```
set statement_cache on | off
```

```
set statistics {io, ioplan, subquerycache, time, plancost} {on | off}
```

```
set statistics plan_detail_html {on | off}
```

```
set statistics plan_directory_html {<dir_name> | on | off}
```

```

set statistics plan_html {on | off}

set statistics parallel_plan_detail_html {on | off}

set statistics query_name_html {<queryname> | on | off}

set statistics resource {on | off}

set statistics simulate {on | off}

set strict_dtm_enforcement {on | off}

set string_rtruncation {on | off}

set system_view {instance | cluster | clear}

set textsize {<number>}

set statistics timing_html {on | off}

set tracefile [<filename>] [off] [for <spid>]

set transaction isolation level {
    [read uncommitted | 0] |
    [read committed | 1] |
    [repeatable read | 2] |
    [serializable | 3]}
    [statement snapshot]
    [transaction snapshot]
    [readonly statement snapshot]

set transactional_rpc {on | off}

```

## Parameters

### **set advanced\_aggregation**

enables and disables advanced aggregation at the session level.

### **set @<variable> = <expression>**

allows multiple variable assignments in one statement. The `set @<variable> = <expression>` command is an identical — and an alternative — command to `select @<variable> = <expression>` in Transact-SQL.

<expression> includes constant, function, any combination of constants, and functions connected by arithmetic or bitwise operators, or a subquery.

### **set ansinull {on | off}**

impacts on both aggregate and comparison behaviors.

### **set ansi\_permissions {on | off}**



determines whether ANSI SQL permission requirements for `delete` and `update` statements are checked. The default is `off`.

Permissions required with `set ansi_permissions` for `update`:

**Off** `update` permission on columns where values are being set.

- On**
- `update` permission on columns where values are being set
  - `select` permission on all columns appearing in `where` clause
  - `select` permission on all columns on right side of `set` clause

Permissions required with `set ansi_permissions` for `delete`:

**Off** `delete` permission on table.

- On**
- `delete` permission on table
  - `select` permission on all columns appearing in `where` clause

**set arithabort [arith\_overflow | numeric\_truncation] {on | off}**

determines how the SAP ASE server behaves when an arithmetic error occurs. The two `arithabort` options, `arithabort arith_overflow` and `arithabort numeric_truncation`, handle different types of arithmetic errors. You can set each option independently or set both options with a single `set arithabort on` or `set arithabort off` statement.

- `arithabort arith_overflow` – specifies the SAP ASE server behavior following a divide-by-zero error, range overflow during an explicit or implicit datatype conversion, or a domain error. This type of error is serious. The default setting, `arithabort arith_overflow on`, rolls back the entire transaction in which the error occurs. If the error occurs in a batch that does not contain a transaction, `arithabort arith_overflow on` does not roll back earlier commands in the batch; however, the SAP ASE server does not execute any statements in the batch that follow the error-generating statement. Setting `arith_overflow` to `on` refers to the execution time, not to the level of normalization to which the SAP ASE server is set. If you set `arithabort arith_overflow off`, the SAP ASE server aborts the statement that causes the error, but continues to process other statements in the transaction or batch.
- `arithabort numeric_truncation` – specifies the SAP ASE behavior following a loss of scale by an exact numeric type during an implicit datatype conversion. (When an explicit conversion results in a loss of scale, the results are truncated without warning.) The default setting, `arithabort numeric_truncation on`, aborts the statement that causes the error, but the SAP ASE server continues to process other statements in the transaction or batch. If you set `arithabort numeric_truncation off`, the SAP ASE server truncates the query results and continues processing.

**set arithignore [arith\_overflow] {on | off}**

determines whether the SAP ASE server displays a message after a divide-by-zero error or a loss of precision. By default, the `arithignore` option is set to `off`. This causes the SAP ASE server to display a warning message after any query that results in

numeric overflow. To have the SAP ASE server ignore overflow errors, use `setarithignore on`. You can omit the optional `arith_overflow` keyword without any effect.

#### **set bulk array size <number>**

establishes the number of rows that are buffered in local server memory before being transferred using the bulk copy interface.

Use this option only with CIS for transferring rows to a remote server using `select into`.

View your current setting using the `<@@bulkarraysize>` global variable.

`<number>` – indicates the number of rows to buffer. If the rows being transferred contain `text`, `unitext`, `image` or `java` ADTs, then the bulk copy interface ignores the current setting for array size and uses a value of 1. Also, the array size actually used never exceeds the value of `<@@bulkbatchsize>`. If `<@@bulkbatchsize>` is smaller than array size, then the smaller value is used.

The initial value of the array size is inherited by new connections from the current setting of the configuration property `cis bulk insert array size`, which defaults to 50. Setting this value to 0 resets the value to the default.

#### **set bulk batch size <number>**

establishes the number of rows transferred to a remote server via `select into <proxy_table>` when the bulk interface is used. The bulk interface is available to all SAP ASE servers, as well as DirectConnect for Oracle version 12.5.1.

Use this option only with CIS for transferring rows to a remote server using `select into`.

View your current setting using the `<@@bulkbatchsize>` global variable.

The bulk interface allows a `commit` after a specified number of rows. This allows the remote server to free any log space being consumed by the bulk transfer operation, and enables the transfer of large data sets from one server to another without filling the transaction log.

The initial value of the batch size is inherited by new connections from the current setting of the configuration property `cis bulk insert batch size`, which by default is 0. A value of 0 indicates that no rows should be committed until after the last row is transferred.

#### **set builtin\_date\_strings <number>**

if a string is given as an argument in place of the chronological value the server interprets it as a `datetime` value regardless of its apparent precision. This is the default behavior and indicated by a `builtin_date_strings` value of 0.

Changing the `builtin_date_strings` value to 1 makes the server interpret the argument strings as `bigdatetimes`. This affects the result of chronological builtins.

**set {chained, close on endtran, nocount, noexec, parseonly, self\_recursion, showplan, sort\_resources} {on | off}**

<b>chained</b>	Begins a transaction just before the first data retrieval or data modification statement at the beginning of a session and after a transaction ends. In chained mode, the SAP ASE server implicitly executes a <code>begin transaction</code> command before the following statements: <code>delete</code> , <code>fetch</code> , <code>insert</code> , <code>lock table</code> , <code>open</code> , <code>select</code> , and <code>update</code> . You cannot execute <code>set chained</code> within a transaction.
<b>close on endtran</b>	Causes the SAP ASE server to close all cursors opened within a transaction at the end of that transaction. A transaction ends by the use of either the <code>commit</code> or <code>rollback</code> statement. However, only cursors declared within the scope that sets this option (stored procedure, trigger, and so on) are affected. For more information about cursor scopes, see the <i>Transact-SQL User's Guide</i> .  For more information about the evaluated configuration, see the <i>System Administration Guide</i> .
<b>nocount</b>	Controls the display of rows affected by a statement. <code>set nocount on</code> disables the display of rows; <code>set nocount off</code> reenables the count of rows.
<b>noexec</b>	Compiles each query but does not execute it. <code>noexec</code> is often used with <code>showplan</code> . After you set <code>noexec on</code> , no subsequent commands are executed (including other <code>set</code> commands) until you set <code>noexec off</code> .
<b>parseonly</b>	Checks the syntax of each query and returns any error messages without compiling or executing the query. Do not use <code>parseonly</code> inside a stored procedure or trigger.
<b>self_recursion</b>	Determines whether the SAP ASE server allows triggers to cause themselves to fire again (this is called self recursion). By default, the SAP ASE server does not allow self recursion in triggers. You can turn this option on only for the duration of a current client session; its effect is limited by the scope of the trigger that sets it. For example, if the trigger that sets <code>self_recursion on</code> returns or causes another trigger to fire, this option reverts to <code>off</code> . This option works only within a trigger and has no effect on user sessions.
<b>showplan</b>	Generates a description of the processing plan for the query. The results of <code>showplan</code> are of use in performance diagnostics. <code>showplan</code> does not print results when it is used inside a stored procedure or trigger. For parallel queries, <code>showplan</code> output also includes the adjusted query plan at runtime, if applicable. See the <i>Performance and Tuning Guide</i> .

**sort\_resources** Generates a description of the sorting plan for a `create index` statement. The results of `sort_resources` are of use in determining whether a sort operation is done serially or in parallel. When `sort_resources` is on, the SAP ASE server prints the sorting plan but does not execute the `create index` statement. See *Parallel Sorting* in the *Performance and Tuning Guide*.

```
set char_convert {off | on [with {error | no_error}] | <charset> [with {error | no_error}]}
```

enables or disables character set conversion between the SAP ASE server and a client. If the client is using Open Client DB-Library release 4.6 or later, and the client and server use different character sets, conversion is turned on during the login process and is set to a default based on the character set the client is using. You can also use `set char_convert <charset>` to start conversion between the server character set and a different client character set.

`<charset>` can be either the character set's ID or a name from `syscharsets` with a `type` value of less than 2000.

`set char_convert off` turns conversion off so that characters are sent and received unchanged. `set char_convert on` turns conversion on if it is turned off. If character set conversion was not turned on during the login process or by the `set char_convert` command, `set char_convert on` generates an error message.

If you request character set conversion with `set char_convert <charset>`, and the SAP ASE server cannot perform the requested conversion, the conversion state remains the same as it was before the request. For example, if conversion is set to `off` prior to the `set char_convert <charset>` command, conversion remains turned off if the request fails.

When the `with no_error` option is included, the SAP ASE server does not notify an application when characters from the SAP ASE server cannot be converted to the client's character set. Error reporting is initially turned on when a client connects with the SAP ASE server: if you do not want error reporting, you must turn it off for each session with `set char_convert {on | charset} with no_error`. To turn error reporting back on within a session, use `set char_convert {on | charset} with error`.

Whether or not error reporting is turned on, the bytes that cannot be converted are replaced with ASCII question marks (?).

See the *System Administration Guide* for more about error handling in character set conversion.

```
set cis_rpc_handling {on | off}
```

makes CIS the default mechanism for handling RPCs in a clustered environment.

```
set [clientname <client_name> | clienthostname <host_name> | clientapplname <application_name>]
```

assigns names to the client.

**clientname**  
**<client\_name>**

Assigns a client an individual name. This is useful for differentiating among clients in a system where many clients connect to the SAP ASE server using the same client name. After you assign a new name to a user, they appear in the `sysprocesses` table under the new name.

`<client_name>` is the new name you assign to the user.

**clienthostname**  
**<host\_name>**

Assigns a host an individual name. This is useful for differentiating among clients in a system where many clients connect to the SAP ASE server using the same host name. After you assign a new name to a host, it appears in the `sysprocesses` table under the new name.

`<host_name>` is the new name you assign to the host.

**clientapplname**  
**<application\_name>**

Assigns an application an individual name. This is useful for differentiating among clients in a system where many clients connect to the SAP ASE server using the same application name. After you assign a new name to an application, it appears in the `sysprocesses` table under the new name.

`<application_name>` is the new name you assign to the application.

**set compression {on | off | default}**

enables or disables compression for the session:

**on** Enables data compression on new data for tables and partitions on which compression is configured. The SAP ASE server compresses all rows that qualify.

**off** Inserts and updates all new data as uncompressed. Inserts that trigger a page compression ignore the uncompressed rows. Updated rows remain uncompressed. Uncompressed rows that are compressed during an update (rows inserted as `uncompressed` remain uncompressed until explicitly compressed).

**default** Resets the compression level to the default setting (inserts and updates are compressed according to the table or partition setting).

Unlike most `set` parameters, if you execute `set export_options` before issuing `set compression` in a nested procedure, the SAP ASE server does not export the compression level to the parent procedure context.

**set cursor rows <number> for <cursor\_name>**

causes the SAP ASE server to return the `<number>` of rows for each cursor `fetch` request from a client application. The `<number>` can be a numeric literal with no decimal point or a local variable of type `integer`. If the `<number>` is less than or equal to zero, the value is set to 1. You can set the `cursor rows` option for a cursor, whether it is open or closed. However, this option does not affect a `fetch` request containing an

into clause. `<cursor_name>` specifies the cursor for which to set the number of rows returned.

**set {datefirst <number>, dateformat <format>, language <language>}**

specifies the following settings:

- `datefirst <number>` – uses numeric settings to specify the first day of the week. The `us_english` language default is Sunday.

To Set the First Day of the Week as	Use
Monday	1
Tuesday	2
Wednesday	3
Thursday	4
Friday	5
Saturday	6
Sunday (us_english language default)	7

### Note

Regardless of which day you set as the first day of the week, the value of that first day becomes 1. This value is not the same as the numeric setting you use in `set datefirst <n>`. For example, if you set Sunday as your first day of the week, its value is 1. If you set Monday as your first day of the week, Monday's value becomes 1. If you set Wednesday as your first day of the week, Wednesday's value becomes 1, and so on.

- `dateformat <format>` – sets the order of the date parts `<month>/<day>/<year>` for entering `datetime`, `smalldatetime`, `date` or `time` data. Valid arguments are `<mdy>`, `<dmy>`, `<ymd>`, `<ydm>`, `<myd>`, and `<dym>`. The `us_english` language default is `<mdy>`.
- `language <language>` – is the official name of the language that displays system messages. The language must be installed on the SAP ASE server. The default is `us_english`.

**set deferred\_name\_resolution**

sets deferred name resolution on for the current session only.

This option works only at the session level if you set the server level `deferred_name_resolution` option off. If server level `deferred_name_resolution` is OFF, `set deferred_name_resolution on` takes effect at the session level and can be switched off again at session level. If, however, `deferred_name_resolution` is set on at server level, `set deferred_name_resolution off` does not take effect on the session, because it cannot override the server setting.

**set delayed\_commit {on | off | default}**

determines when log records are written to disk. With the `delayed_commit` parameter set to true, the log records are asynchronously written to the disk and control is returned to the client without waiting for the IO to complete.

The session-level setting overrides any existing the database-level setting. Change `delayed_commit` to its default to revert back to the database-level setting.

### **i Note**

Use `delayed_commit` only after careful consideration of your application.

**set dml\_logging {minimal | default}**

determines the amount of logging for `insert`, `update`, and `delete` (DML) operations. Valid values are:

- `minimal` – the SAP ASE server attempts to log no changes for the DML statements. In most cases, the SAP ASE server generates little or no logging to `syslogs`.
- `default` – the SAP ASE server disables session-specific minimal logging and uses the logging mode you enabled for individual tables based on table-specific and database-wide logging levels.

Changes to logging apply only to objects owned by the user in this session, when applicable. In addition, only the tables owned by the session owner are affected by `set dml_logging`:

- Any user can execute `set dml_logging` for `minimal` logging and for returning to the `default` mode of logging. Once this `set` succeeds, DML on all tables owned by the user executing the statement in any database is minimally logged for the current session, until `set dml_logging default` is executed.
- DML logging defaults to the database- and table-level settings when `minimal` logging is enabled for the session but the DML operates on tables not owned by the session's user.
- The DML logging setting in a session or procedure is inherited by procedures, however, only the tables owned by the user running the session are affected.

**set encryption passwd '<password\_phrase>' for {key | column} {<keyname> | <column\_name>}**

creates the encryption key's password to encrypt or decrypt data on an `insert`, `update`, `delete`, `select`, `alter table`, or `select into` statement.

- `<password_phrase>` – is the explicit password specified with the `create encryption key` or `alter encryption key` command to protect the key.
- `key` – indicates that the SAP ASE server uses this password to decrypt the key when accessing any column encrypted by the named key
- `column` – specifies that the SAP ASE server use this password only in the context of encrypting or decrypting the named column. End users do not necessarily know the name of the key that encrypts a given column.
- `<keyname>` – may be supplied as a fully qualified name. For example:

```
[ [<database> . ] [ <owner> ] . ] <keyname>
```

- `<column_name>` – is the name of the column on which you are setting an encryption password. Supply `<column_name>` as:

```
[[ <database>.] [ <owner> ]. ]<table_name>.<column_name>
```

### Note

SAP ASE returns an error if you execute `set encryption passwd` for a master key that is already encrypted with the Hardware Security Module (HSM) key.

#### **set erase\_residual\_data {on | off}**

allows you to enable or disable the removal of residual data based on your needs.

When you enable the option at a session level, residual data is removed from all the page deallocations that occur during that session. This includes page deallocations of tables that have the "erase residual data" option turned OFF explicitly.

This option can be set by any user for the particular session; no special permissions are required.

#### **set export\_options [on | off]**

the SAP ASE server's default behavior is to reset any set parameter changes that are set by a trigger or system procedure after they finish running. Enabling `set export_options` allows you to retain the session settings that are set by a system procedure or trigger for the duration of the session.

For example, this enables `set export_options`:

```
set export_options on
```

This disables `set export_options` and returns the SAP ASE server to the default behavior:

```
set export_options off
```

#### **set fipsflagger {on | off}**

determines whether the SAP ASE server displays a warning message when Transact-SQL extensions to entry-level ANSI SQL are used. By default, the SAP ASE server does not tell you when you use nonstandard SQL. This option does not disable SQL extensions. Processing completes when you issue the non-ANSI SQL command.

#### **set flushmessage {on | off}**

determines when the SAP ASE server returns messages to the user. By default, messages are stored in a buffer until the query that generated them is completed or the buffer is filled to capacity. Use `set flushmessage on` to return messages to the user immediately, as they are generated.

#### **set fmtonly {on | off}**

captures plans in stored procedures without actually executing them.

#### **set forceplan {on | off}**

causes the query optimizer to use the order of the tables in the `from` clause of a query as the join order for the query plan. `forceplan` is generally used when the optimizer



fails to choose a good plan. Forcing an incorrect plan can have severely bad effects on I/O and performance. See the *Performance and Tuning Guide*.

### **i** Note

The query optimizer ignores attempts to force illegal join orders with outer joins, such as in the following:

```
1> set forceplan on
2> select * from table1, table2
   where table2.id *= table1.id
```

**set identity\_insert** [**<database>**.**<owner>**.]**<table\_name>** {**on** | **off**}

determines whether explicit inserts into a table's IDENTITY column are allowed. This option can be used only with base tables. It cannot be used with views or set within a trigger.

After setting `identity_insert on` for the table, the table owner or users with `insert` permission on the column can manually insert any legal value greater than 5. For example, inserting a value of 55 would create a large gap in IDENTITY column values:

```
insert stores_cal
(syb_identity, stor_id, stor_name)
values (55, "5025", "Good Reads")
select syb_identity from stores_cal
```

```
id_col
-----
      1
       5
      55

(3 rows affected)
```

If `identity_insert` is then set to `off`, the SAP ASE server assigns an IDENTITY column value of  $55 + 1$ , or 56, for the next insertion. If the transaction that contains the `insert` statement is rolled back, the SAP ASE server discards the value 56 and uses a value of 57 for the next insertion.

Unless you have created a unique index on the IDENTITY column, the SAP ASE server does not verify the uniqueness of the inserted value; you can insert any positive integer.

Setting `identity_insert <table_name> off` restores the default behavior by prohibiting explicit inserts to IDENTITY columns. At any time, you can use `set identity_insert <table_name> on` for a single database table within a session.

The permission checks for `set identity_insert table_name on|off` differ based on your granular permissions settings.

Setting	Description
---------	-------------

<b>Enabled</b>	With granular permissions enabled, you must be the table owner or a user with <code>identity_insert</code> permission on the table. Table owner or user with
----------------	--

Setting	Description
---------	-------------

`manage any object permission` privilege can grant the permission to others.

**Disabled** With granular permissions disabled, you must be the table owner, database owner, or a user with `sa_role`. `identity_insert` permission is not transferable.

### `set identity_update <table_name> {on | off}`

With `set identity_update` on, you can explicitly update the value of the IDENTITY column on a table. `identity_update` changes the identity column value for the qualified rows. When `identity_update` is enabled, you can update the identity value to any value greater than 0. However, if the input value is greater than the `identity burn max` value, a new set of ID values is allocated, and the `identity burn max` value on the OAM page is updated accordingly. If `update` is included in a transaction, the new `identity burn max` value cannot be rolled back. You can use `syb_identity` to point to the identity column for update. For example:

```
update <table_name> set syb_identity = <value>
where clause
```

The SAP ASE server does not check for duplicate entries or verify that entries are unique. You can update an existing value to any positive integer within the range allowed by the column's declared precision. You can check for duplicate entries by creating a unique index on the identity column.

The permission checks for `set identity_update table_name on|off` differ based on your granular permissions settings.

Setting	Description
---------	-------------

**Enabled** With granular permissions enabled, you must be the table owner or a user with `identity_update` permission on the table. Table owner or user with `manage any object permission` privilege can grant the permission to others.

**Disabled** With granular permissions disabled, you must be the table owner, database owner, or a user with `sa_role`. `identity_update` permission is not transferable.

### `set index_union on | off`

when enabled, sets limits the scan of a table with an `or` clause.

Index unions (also known as an `or` strategy) are used for queries that contain `or` clauses. For example:

```
select * from titleauthor where au_id = "409-56-7008" or title_
id = "PC8888"
```

If `index_union` is:

- Enabled – this example uses an index on `au_id` to find the row IDs (RIDs) of all `titleauthor` tuples with `au_id = "409-56-7008"`, and uses an index on `title_id` to find the RIDs of all `titleauthor` tuples with `title_id = "PC8888"`. The SAP ASE server then performs a union on all RIDs to eliminate duplicates. The resulting RIDs are joined with a `RidJoin` to access the data tuples.
- Disabled – the SAP ASE server does not use an index union strategy in a query to limit the table scan. Instead, it uses other access paths on the table (in the example above, it would use a table scan for table `titleauthor`), and applies the `or` clause as a filter in the scan operator.

### **ins\_by\_bulk**

provides faster data loading by using parallel index updates for insert statements into a data rows-locked table with non-clustered indexes.

### **set literal\_autoparam on | off**

is on by default. If the server-level setting for `literal_autoparam` is on, this option enables and disables use of that feature. If the server level setting is `off`, this setting has no effect.

### **set join\_bloom\_filter**

enables or disables the use of bloom filters for query plan optimization.

### **set lock {wait [<numsecs>] | nowait | default}**

specifies the settings for a lock.

- |                        |  |
|------------------------|--|
| <b>wait</b>            | Specifies the length of time that a command waits to acquire locks before aborting and returning an error.   |
| <b>&lt;numsecs&gt;</b> | Specifies the number of seconds a command is to wait to acquire a lock. Valid values are from 0 to 2147483647, the maximum value for an integer.                           |
| <b>lock nowait</b>     | Specifies that if a command cannot acquire a lock immediately, it returns an error and fails. <code>set lock nowait</code> is equivalent to <code>set lock wait 0</code> . |
| <b>default</b>         | Disables the current session-level lock wait settings, and instead uses the current server-wide <code>lock wait period</code> configuration parameter setting.             |

### **set logbulkcopy {on | off}**

configures fast-logged `bcp` for the session.

### **set materialized\_view\_optimization {disable | fresh | stale}**

determines which precomputed result sets are considered during query optimization. One of:

- disable** (Default) the SAP ASE server does not use any precomputed result sets in query optimization.

**fresh** The SAP ASE server considers only the precomputed result sets with an `immediate refresh` policy.

**stale** The SAP ASE server considers all enabled precomputed result sets for query optimization, even if they are stale.

**set metrics\_capture {on | off}**

enables the capture of query processing (QP) metrics at the session level, and sets the capture to on. QP metrics identify and compare empirical metric values in query execution. When a query is executed, it is associated with a set of defined metrics that are the basis for comparison in QP metrics.

**set mon\_stateful\_history on | off**

When disabled, queries to the historical monitoring tables (`monSysStatement`, `monErrorLog`, `monSysSQLText`, `monSysPlanText`, and `monDeadLock`) return all rows in the table buffer.

When enabled, queries to the historical monitoring tables return only rows that were added to the tables since `mon_stateful_history` was disabled.

**set no\_chained\_tran\_for\_10\_select**

when `set chained` is enabled, skips the beginning of chained transaction for select queries being executed at isolation level 0.

**set nodata**

specifies that no data be routed to the client when a query is executed to completion. When you specify `set nodata on`, only the TDS format stream is sent to the client, and the query behaves as if no rows qualified.

**set offsets {select, from, order, compute, table, procedure, statement, param, execute} {on | off}**

returns the position of specified keywords (with relation to the beginning of the query) in Transact-SQL statements. The keyword list is a comma-separated list that can include any of the following Transact-SQL constructs: `select`, `from`, `order`, `compute`, `table`, `procedure`, `statement`, `param`, and `execute`. The SAP ASE server returns offsets if there are no errors.

This option is used in Open Client DB-Library only.

**set option <show\_option> {normal | brief | long | on | off}**

generates diagnostics output in text format.

The valid values for `<show_option>` are:

- `show` – shows the basic syntax common to all modules
- `show_lop` – shows the logical operators (scans, joins, etc.) used
- `show_managers` – shows data structure managers used during optimization.
- `show_log_props` – shows the logical properties (row count, selectivity, etc.) evaluated.
- `show_parallel` – shows details of parallel query optimization
- `show_histograms` – shows the processing of histograms associated with SARG/Join columns

- `show_abstract_plan` – shows the details of an abstract plan
- `show_search_engine` – shows the details of the join ordering algorithm
- `show_counters` – shows the optimization counters
- `show_best_plan` – shows the details of the best query plan selected by the optimizer
- `show_pio_costing` – shows estimates of physical input/output (reads/writes from/to the disk)
- `show_lio_costing` – shows estimates of logical input/output (reads/writes from/to memory)
- `show_elimination` – shows partition elimination
- `show_missing_stats {brief | long | on | off}` – shows details of useful statistics missing from SARG/Join columns. Set to:
  - `brief` – the SAP ASE server creates minimal statistics for each query, and `show_missing_stats` does not report warnings on user created temporary tables.
  - `long` – the SAP ASE server creates full statistics for each query, including user-created temporary tables.
  - `on` – enables SAP ASE to display statistics for columns that contribute to a query, but for which there are no statistics.
  - `off` – disables SAP ASE from displaying missing statistics.

See *Displaying Query Optimization Strategies and Estimates in Query Optimizer* for more information.

The permission checks for `set option <show_option>` differ based on your granular permissions settings.

Setting	Description
---------	-------------

<b>Enabled</b>	With granular permissions enabled, you must be a user with either <code>set tracing</code> privilege or <code>monitor qp performance</code> privilege.
----------------	--

<b>Disabled</b>	With granular permissions disabled, you must be a user with <code>set tracing</code> privilege or a user with <code>sa_role</code> .
-----------------	--

#### **set opttimeoutlimit**

sets the timeout limit for the optimizer. The valid range of values for `opttimeoutlimit` 0 to 4000 ms, with 0 indicating no optimization limit.

#### **set parallel\_degree <number>**

specifies an upper limit for the number of worker processes used in the parallel execution of a query. This number must be less than or equal to the number of worker processes per query, as set by the `max parallel degree` configuration parameter. The `<@@parallel_degree>` global variable stores the current setting.

#### **set plan {dump | load} [<group\_name>] {on | off}**

introduces an abstract plan command.

<b>dump</b>	Enables or disables capturing abstract plans for the current connection. If a <code>&lt;group_name&gt;</code> is not specified, the plans are stored in the default group, <code>ap_stdout</code> .
<b>load</b>	Enables or disables loading abstract plans for the current connection. If a <code>&lt;group_name&gt;</code> is not specified, the plans are loaded from the default group, <code>ap_stdin</code> .
<b>&lt;group_name&gt;</b>	Is the name of the abstract plan group to use for loading or storing plans.

See *Creating and Using Abstract Plans* in the *Performance and Tuning Guide*.

**set plan exists check {on | off}**

when used with `set plan load`, stores hash keys for up to 20 queries from an abstract plan group in a per-user cache.

**set plan for <show>**

generates an XML document for the diagnostic output. The valid values for `<show>` are:

<b>show_exec_xml</b>	Gets the compiled plan output in XML, showing each of the query plan operators.
<b>show_execio_xml</b>	Gets the plan output along with estimated and actual IOs. This also includes the query text.
<b>show_opt_xml</b>	Gets optimizer diagnostic output, which shows all of the different components like logical operators, output from the managers, some of the search engine diagnostics, and the best query plan.
<b>show_lop_xml</b>	Gets the output logical operator tree in XML.
<b>show_managers_xml</b>	Shows the output of the different component managers during the preparation phase of the query optimizer.
<b>show_log_props_xml</b>	Shows the logical properties for a given equivalence class (one or more group of relations in the query).
<b>show_parallel_xml</b>	Shows the diagnostics related to the optimizer while generating parallel query plans.
<b>show_histograms_xml</b>	Shows diagnostics related to histograms and the merging of histograms.
<b>show_abstract_plan_xml</b>	Shows the AP generation/application.
<b>show_search_engine_xml</b>	Shows the search engine related diagnostics.
<b>show_counters_xml</b>	Shows plan object construction/destruction counters.

<code>show_best_plan_xml</code>	Shows the best plan in XML.
<code>show_pio_costing_xml</code>	Shows actual PIO costing in XML.
<code>show_lio_costing_xml</code>	Shows actual LIO costing in XML.
<code>show_elimination_xml</code>	Shows partition elimination in XML.
<code>client</code>	When specified, output goes to the client.
<code>message</code>	When specified, output goes to an internal message buffer.

See *Displaying Query Optimization Strategies and Estimates in Performance and Tuning Series: Query Processing and Abstract Plans* for more information.

The permission checks for `set plan for <show>` differ based on your granular permissions settings.

#### Setting Description

**Enabled** With granular permissions enabled, you must be a user with either `set tracing` privilege or `monitor qp performance` privilege.

**Disabled** With granular permissions disabled, you must be a user with `set tracing` privilege or a user with `sa_role`.

`set plan optgoal {allrows_oltp | allrows_mix | allrows_dss | user_defined_goal_identifier}`

sets the optimization goal.

- `allrows_mix` – is the default optimization goal, and the most useful goal in a mixed-query environment. It balances the needs of OLTP and DSS query environments.
- `allrows_dss` – is the most useful goal for operational DSS queries of medium to high complexity. Currently, this goal is provided on an experimental basis.

See *Understanding Query Processing in SAP ASE in Performance and Tuning Series: Query Processing and Abstract Plans* for more information about optimization plans.

`set plan optlevel <value>`

sets the optimization level for the session. Each SAP ASE release or ESD may include a new optimization level. For example:

- `ase_current` – enables all optimizer changes through the current release.
- `ase_default` – disables all optimizer changes since version 15.0.3 ESD #1.
- `ase1503esd2` – enables all optimizer changes through version 15.0.3 ESD #2.
- `ase1503esd3` – enables all optimizer changes through version 15.0.3 ESD #3.

See *Controlling Optimization in Performance and Tuning Series: Query Processing and Abstract Plans*.

`set plan opttimeoutlimit <number>`

sets the timeout at the session level, where `<n>` is any integer between 0 and 1000. See *Understanding Query Processing in Adaptive Server in Performance and Tuning Series: Query Processing and Abstract Plans* for more information about optimization plans.

**set plan replace {on | off}**

enables or disables replacing existing abstract plans during plan capture mode. By default, plan replacement is off.

**set prefetch {on | off}**

enables or disables large I/Os to the data cache.

**set proc\_output\_params {on | off}**

controls sending of output parameters that a stored procedure generates back to the client. `set proc_output_params off` suppresses sending the output parameters back to the client. The default for this parameter is `on`.

**set proc\_return\_status {on | off}**

controls sending of a return status TDS token back to the client. `set proc_return_status off` suppresses sending the return status token to the client, and `isql` client does not display the `(return status = 0)` message. The default for this parameter is `on`.

**⚠ Caution**

If the client application that executes a procedure relies on the success or failure of the procedure based on the return status, then do not use the `set proc_return_status off` option.

**set process\_limit\_action {abort | quiet | warning}**

specifies whether the SAP ASE server executes parallel queries when an insufficient number of worker processes is available. Under these circumstances, setting these `process_limit_action` parameter options results in different behaviors:

- quiet** The SAP ASE server silently adjusts the plan to use a degree of parallelism that does not exceed the number of available processes.
- warning** When an insufficient number of worker processes are available, the SAP ASE server issues a warning message when adjusting the plan
- abort** The SAP ASE server aborts the query and issues an explanatory message an insufficient number of worker processes are available.

**set proxy <login\_name>**

allows you to assume the permissions, login name, and `suid` (server user ID) of `<login_name>`. For `<login_name>`, specify a valid login from `master..syslogins`, enclosed in quotation marks. To revert to your original login name and `suid`, use `set proxy` with your original `<login_name>`.

**i Note**

To use `set proxy <login_name>`, the user, including the system security officer, must have explicitly granted permission. Without explicit permission, neither the "sa\_role" nor the "sso\_role" can issue the `set proxy login_name` command.



**set quoted\_identifier {on | off}**

determines whether the SAP ASE server recognizes delimited identifiers within double quotation marks. By default, `quoted_identifier` is `off` and all identifiers must either:

- Conform to the rules for valid identifiers.
- Be enclosed in brackets.

If you use `set quoted_identifier on`, double quotation marks behave the way brackets do, and you can use table, view, and column names that begin with a nonalphanumeric character, including characters that would not otherwise be allowed, or are reserved words, by enclosing the identifiers within double quotation marks. Delimited identifiers cannot exceed 28 bytes, may not be recognized by all front-end products, and may produce unexpected results when used as parameters to system procedures.

When `quoted_identifier` is `on`, all character strings enclosed within double quotes are treated as identifiers. Use single quotes around character or binary strings.

**set remote\_command\_encryption {on | off}**

Enables or disables encryption during the session for commands sent between the local server and the remote server when using CIS. Both local and remote servers require version 16.0 SP03.

Enabling this configuration encrypts the following commands and system procedures: `connect to <server_name>`, `execute <server_name> ... <proc_name>`, `sp_autoconnect`, `sp_passthru`, and `sp_remotesql`.

If either the local or remote server uses a version of ASE that does not support the `set remote_command_encryption` command, the `set` command is ignored and the commands are sent unencrypted.

If the client sends an encrypted command to the local server, that command is not re-encrypted when the local server sends the command to the remote server, since the command is already encrypted.

**set repartition\_degree <number>**

is the maximum degree to which any intermediate data stream is re-partitioned for semantic purposes. See *Parallel Query Processing in Performance and Tuning Series: Query Processing and Abstract Plans* for more information about setting the value of `max repartition degree` for a session.

**set repthreshold <number>**

sets the SQL replication threshold at the session level. If `repthreshold` is invoked in a stored procedure, its scope is that of the procedure. If it is invoked in a user session, its scope is that of the session.

A user can alter the scope of the threshold and set the session threshold using a login trigger, in which case you need not explicitly set the session threshold at login. For example:

```
create proc myproc
as
    set repthreshold 777
-----
```

```
alter login sa modify login script 'myproc'
-----
option changed.
```

```
(Return status = 0
```

The procedure 'myproc' is invoked each time the user `sa` logs in, and ensures that the replication threshold is set at 777 for the whole session.

Another way to alter the scope of the threshold is to use `set export_options`:

```
create proc p2
as
    set repthreshold222
    set export_options on
-----
```

After `p2` is executed the threshold remains set at 222. The hierarchy of thresholds is Session > Table > Database

When you set the session threshold to 0, the only replication thresholds that still matter are table and database thresholds, if they have been specified, in that order. If you set no threshold, the threshold defaults to 50 rows.

To set the table level threshold, see `sp_setrepdbmode`; to set the database level threshold, see `sp_setrepdefmode`, both in the *Reference Manual: Procedures*.

The session threshold is exportable; a stored procedure can set the threshold and turn the `export_options` setting ON. The SAP ASE server enforces the new threshold in the invoking procedure or session.

The permission checks for `set repthreshold` differ based on your granular permissions settings.

Setting	Description
---------	-------------

<b>Enabled</b>	With granular permissions enabled, you must be a user with <code>manage replication</code> privilege.
----------------	---

<b>Disabled</b>	With granular permissions disabled, you must be a user with <code>replication_role</code> .
-----------------	---

### `set resource_granularity <number>`

overrides the global value `max resource granularity` and sets it to a session-specific value, which influences whether the SAP ASE server uses memory-intensive operation or not. See *Parallel Query Processing* in *Query Processor* for more information.

### `set role {<role_name >[with passwd "<password>"]} {on | off}`

Use `set role <role_name> off` to turn a role off, and `set role <role_name> on` to turn it back on again, as needed.

- `<role_name>` can be the name of a system role or a user-defined role. When you log in, all system roles that have been granted to you are automatically activated. If you have been granted `sa_role` or `sso_role`, you cannot set these roles off

unless you are a named or aliased user in the database or there exists a "guest" user.

- `<role_name>` – is the name of any user-defined role created by the system security officer. User-defined roles are not turned on by default. To set user-defined roles to activate at login, system security officer must specify the role as a default or auto activated role when creating or altering a login or a login profile.
- `with <passwd>` – specifies the password to activate the role. If a user-defined role has an attached password, you must specify the password to activate the role.

To use `set role`, the role must have been granted to you. If you gain entry to a database only because you have a certain role, you cannot turn that role off while you are using the database.

If you were granted a role using an activation predicate, the SAP ASE server evaluates the predicate when you execute `set role on`. If the predicate evaluates to `false`, the SAP ASE server returns an error and does not activate the role.

**set {rowcount `<number>`, textsize `<number>`}**

causes the SAP ASE server to stop processing the query (`select`, `insert`, `update`, or `delete`) after the specified number of rows are affected. The `<number>` can be a numeric literal with no decimal point or a local variable of type `integer`. To turn this option off, use:

```
set rowcount 0
```

You can determine the current value for `set rowcount` with the `<@@setrowcount>` global variable. For example:

```
select @@setrowcount
-----
                 37
```

**set scan\_parallel\_degree `<number>`**

specifies the maximum session-specific degree of parallelism for hash-based scans (parallel index scans and parallel table scans on nonpartitioned tables). This number must be less than or equal to the current value of the `max scan parallel degree` configuration parameter. The `<@@scan_parallel_degree>` global variable stores the current setting.

**set send\_locator {on | off }**

specifies whether the SAP ASE server sends the LOB or the locator that references the LOB in a result set sent to the client. When the option is `off` (the default), the SAP ASE server sends the LOB.

**set session authorization `<login_name>`**

is identical to `set proxy`, with this exception: `set session authorization` follows the SQL standard, while `set proxy` is a Transact-SQL extension.

**set show\_exec\_info**

generates additional information when a command executes.

- `on` – generates extra diagnostics about the logging mode for a DML statement. Displays the selected logging mode for the current statement and session, and the user executing the DML.
- `off` – disables `show_exec_info`.

**set show\_object\_list {on | off}**

allows you to print datachange counters for a query plan in the `sp_showplan` output. A datachange counter indicates whether the statistic of a table is stale.

When using `set show_object_list`, consider the following:

- `sp_showplan` prints datachange counters regardless of the status of `show_object_list` as long as `<display_level>` is not set to default. See `sp_showplan` in *Reference Manual: Procedures*.
- `set show_object_list on` only prints datachange counters on stored procedures for the session.
- Ad-hoc queries do not print anything even if you set `show_object_list` to `on`.
- datachange counters are not printed when a stored procedure is executed even if you set `show_object_list` to `on`.

**set show\_permission\_source, {on|off}**

display the grantee, type of grantee, grantor, action, object, and predicate in tabular form. The grantee can be `<user_name>`, `<role_name>`, or `<group_name>`. The `Type of grantee` column displays whether the grantee is user, role, or group. If there are no predicates, the SAP ASE server returns a NULL.

When using `set show_permission_source, {on|off}`, consider:

- If you grant permission to a role that is part of a hierarchy the permission is not granted directly to the user. For example, if you granted permissions for `role1` to `role2`, which in turn is granted to `role3`, and that permission is granted to a user. `set show_permission_source` displays "role1" in the `grantee` column and not `role3` because `role1` was granted the permission and not `role3`. Use `sp_displayroles ... expand_up` to see information about `role3`.
- If more than one grantor grants permission for a particular action, `set show_permission_source` displays the permission associated with the grantor with the highest user ID.
- `set show_permission_source` displays information at the object level and not the column level because there may be more than one row for the same object from different grantors on different columns.
- If more than one permission exists with different predicates on an object for a combination of actions and grantors, `set show_permission_source` displays all the predicate names, with a separate row for each predicate.

**set show\_sqltxt {on | off}**

allows you to print the SQL text for ad-hoc queries, stored procedures, cursors, and dynamic prepared statements.

You do not need to enable the `set show_sqltext` before you execute the query (as you do with commands like `set showplan on`) to collect diagnostic information for a SQL session. Instead you can enable it while the commands are running to help determine which query is performing poorly and diagnose their problems.

Before you enable `show_sqltext`, you must first enable `dbcc traceon` to display the output to standard out:

```
dbcc traceon(3604)
```

The syntax for `set show_sqltext` is:

```
set show_sqltext {on | off}
```

For example, this enables `show_sqltext`:

```
set show_sqltext on
```

Once `set show_sqltext` is enabled, the SAP ASE server prints all SQL text to standard out for each command or system procedure you enter. Depending on the command or system procedure you run, this output can be extensive.

To disable `show_sqltext`, enter:

```
set show_sqltext off
```

#### **set show\_transformed\_sql, {on|off}**

displays the an intermediate form of the query as SQL text during SAP ASE query processing—that is, after query transformations for views, predicated privileges, encryption, and so on, have been made, but before query transformations for subqueries have occurred.

#### **set spinlock\_aggregation {on | off}**

determines whether SAP ASE aggregates the spinlock metrics reported in `monSpinlockActivity` when the result set includes multiple rows with the same value for `SpinlockName`.

By default, SAP ASE aggregates the values for `Grabs`, `Waits`, and `Spins` for all spinlocks with the same value. Set `set spinlock_aggregation` to `off` to configure SAP ASE to return a separate row for each spinlock instance in the `monSpinlockActivity` table.

#### **set statement\_cache on | off**

is `on` by default. If the server-level setting for `statement_cache` is `on`, this option enables and disables use of that feature. If the server level setting is `off`, this setting has no effect.

#### **set statistics query\_name\_html [queryname | on | off]**

helps differentiate or identify files related to the execution of same query.

#### **set statistics {io, ioplan, subquerycache, time, plancost, simulate} {on | off}**

displays various types of statistics information:

##### **io**

Displays statistics for each table referenced in the statement:

- The number of times the table is accessed (scan count)
- The number of logical reads (pages accessed in memory)
- The number of physical reads (database device accesses)

For each command, `statistics io` displays the number of buffers written.

If the SAP ASE server has been configured to enforce resource limits, `statistics io` also displays the total I/O cost.

<b>ioplan</b>	Displays the IO statistics per plan for each view.
<b>subquerycache</b>	Displays the number of cache hits, misses, and the number of rows in the subquery cache for each subquery.
<b>time</b>	Displays the amount of time the SAP ASE server used to parse and compile for each command. For each step of the command, <code>statistics time</code> displays the amount of time the SAP ASE server used to execute the command. Times are given in milliseconds and timeticks, the exact value of which is machine-dependent.
<b>plancost</b>	Displays the query statistics in a tree format.

#### **i Note**

When you enable `set statistics plancost`, the SAP ASE server abbreviates the names for `lio`, `pio`, and `row` to `l`, `p`, and `r`, respectively.

<b>simulate</b>	Specifies that the optimizer should use simulated statistics to optimize the query.
<b>resource</b>	tracks procedure cache consumption for the executed query, and prints the compile and execution time resource consumption, in bytes. For execution time it prints the: <ul style="list-style-type: none"><li>• Number of threads used for execution</li><li>• Auxiliary scan descriptors used</li><li>• Average/stable procedure cache consumption</li><li>• High water mark for procedure cache usage.</li></ul> If there are sorts or hash operations in the query, the high water mark can be significantly higher than the average procedure cache consumption. For compiler time, it prints the estimated threads for the query execution and the procedure cache consumption to optimize the query.

See *Using the set statistics Command in Performance and Tuning Series: Improving Performance with Statistical Analysis*.

```
set statistics {plan_detail_html, parallel_plan_detail_html,  
plan_directory_html, plan_html, timing_html} {on | off}
```

displays various types of statistics information in HTML format.

<b>plan_detail_html</b>	Generates a graphical query plan in HTML format containing information about details per thread and plan fragments for query plans that are executed in parallel using several worked threads. Use this option to diagnose the behavior of specific threads and plan fragments in comparison with the global execution of the query.
<b>parallel_plan_detail_html</b>	Generates a graphical query plan in HTML format containing information details of plan operators, such as the name, different timestamps captured during the execution, number of rows affected, number of estimated rows, elapsed time, and so on.
<b>plan_directory_html</b> "dirName"	Specifies the directory path name into which to write the HTML query plans. The file name is identified by a combination of user name, spid, and timestamp. When set to off, the dumping of the HTML data to an external file is stopped. When set to on, the dumping of HTML data to an external file in a directory previously indicated is resumed. No output is generated if a directory name was not previously provided.
<b>plan_html</b>	Generates a graphical query plan in HTML format containing information about the number of rows and number of threads per operator.
<b>timing_html</b>	Generates a graphical query plan in HTML format containing execution statistics related to the timing spent in each operator per execution phase. CPU usage and Wait distribution is generated for queries executed in parallel.

See *Using the set statistics Command in Performance and Tuning Series: Improving Performance with Statistical Analysis*.

**set strict\_dtm\_enforcement {on | off}**

determines whether the server propagates transactions to servers that do not support SAP ASE transaction coordination services. The default value is inherited from the value of the `strict dtm enforcement` configuration parameter.

**set string\_rtruncation {on | off}**

determines whether the SAP ASE server raises a SQLSTATE exception when an `insert` or `update` command truncates a `char`, `unichar`, `varchar` or `univarchar` string. If the truncated characters consist only of spaces, no exception is raised. The default setting, `off`, does not raise the SQLSTATE exception, and the character string is silently truncated.

**set system\_view {instance | cluster | clear}**

(clusters only) specifies the system view for a session, and controls the materialization of fake tables, which impact the output of stored procedures such as `sp_who`.

- `instance` – sets the system view for the current instance.
- `cluster` – sets the system view for the cluster.
- `clear` – clears any session-level setting, reverting to the `system_view` setting for the logical cluster hosting that spid. Enter `select @@system_view` to check the current value.

```
set switch [serverwide] {on | off} <trace_flag>[,<trace_flag>] [,with <option>]  
[, <option>]
```

allows you to set trace flags and switch names locally and server-wide.

- `serverwide` – (optional) sets a switch serverwide ON or OFF. The default is session-specific.
- `on` – trace flags are switched on.
- `off` – trace flags are switched off.
- `<trace_flag>` – a sequence of numbers (the old traceflag numbers) and/or switch names.
- `<option>` – (optional) a sequence of switch options. Valid values are:
  - `override` – this option is necessary to enable a non-documented switch names or trace flags
  - `no_info` – this option is used to suppress any informational warnings
- `print_minlogged_mode_override` – generates trace information to session output, reporting on the statement for which the minimally logged mode of a table was overridden by some other rules, such as presence of referential integrity constraints, deferred mode choice, name of the table affected and a description of the affecting rules, and so on.

The permission checks for `set switch` differ based on your granular permissions settings.

Setting	Description
---------	-------------

<b>Enabled</b>	With granular permissions enabled:
----------------	------------------------------------

- To set traceflag 3604/3605, you must have either `monitor qp performance` privilege or `set switch` privilege.

For all other traceflags, you must have `set switch` privilege.

<b>Disabled</b>	With granular permissions disabled, you must have <code>sa_role</code> .
-----------------	--

```
set textsize [<number>]
```

specifies the maximum size in bytes of `text`, `unitext`, or `image` type data that is returned with a `select` statement. The `<@@textsize>` global variable stores the current setting.

The default setting is 32K in `isql`. Some client software sets other default values. To reset `textsize` to the default size (32K), use:

```
set textsize 0
```



**set tracefile** [**<filename>**] [**off**] [**for <spid>**]

once enabled, saves all SQL text for the current session to the specified file, each SQL text batch appending to the previous batch.

The syntax to enable tracing is:

```
set tracefile <file_name> [off] [for <spid>
```

The syntax to disable tracing is:

```
set tracefile off [for <spid>]
```

where:

- **<file\_name>** – is the full path to the file in which you are saving the SQL text. If you do not specify a directory path, the SAP ASE server creates the file in \$SYBASE.

### **i Note**

If **<file\_name>** contains special characters (":", "/", and so on) other than numbers and letters, you must include **<file\_name>** in quotes. For example, this **<file\_name>** must be in quotes because of the "/" for the directory structure:

```
set tracefile '/tmp/mytracefile.txt' for 25
```

If **<file\_name>** does not contain special characters and you want to save it to \$SYBASE, it does not require quotes. For example, this **<file\_name>** does not need to be in quotes:

```
set tracefile mytracefile.txt
```

- **off** – disables the tracing for this session or spid.
- **<spid>** – server process ID whose SQL text you want saved to a trace file. Only the users with the SA or systems security officer role can enable tracing for other spids. You cannot save the SQL text for system tasks (such as the housekeeper or the port manager).

### **i Note**

After you use `set tracefile` for a particular session, the diagnostic output of all successive set commands or DBCC traces are then redirected to a tracefile.

Make sure to switch off all the diagnostic commands you turned on before issuing `set tracefile off`, or else the output that should go to the tracefile instead goes to the client.

The permission checks for `set tracefile` differ based on your granular permissions settings.

Setting	Description
---------	-------------

<b>Enabled</b>	With granular permissions enabled, setting tracefile for your own session requires either <code>set tracing</code> privilege or <code>monitor qp performance</code> privilege. To set tracefile for other user's session you must have either <code>set tracing any process</code> privilege or <code>monitor qp performance</code> privilege.
----------------	--

<b>Disabled</b>	With granular permissions disabled, setting tracefile for your own session requires <code>set tracing</code> privilege; to set tracefile for other user's session you must have either <code>sa_role</code> or <code>sso_role</code> .
-----------------	--

```
set transaction isolation level {[read uncommitted | 0] | [read committed | 1] | [repeatable read | 2] | [serializable | 3] [statement snapshot] [transaction snapshot] [readonly statement snapshot]}
```

sets the transaction isolation level for your session. After you set this option, any current or future transactions operate at that isolation level.

- `read uncommitted | 0` – scans at isolation level 0 do not acquire any locks. Therefore, the result set of a level 0 scan may change while the scan is in progress. If the scan position is lost due to changes in the underlying table, a unique index is required to restart the scan. In the absence of a unique index, the scan may be aborted. By default, a unique index is required for a level 0 scan on a table that does not reside in a read-only database. You can override this requirement by forcing the SAP ASE server to choose a nonunique index or a table scan, as follows:

```
select * from <table_name> (index <table_name>)
```

Activity on the underlying table may cause the scan to be aborted before completion.

- `read committed | 1` – by default, the SAP ASE transaction isolation level is `read committed` or 1, which allows shared read locks on data.
- `repeatable read | 2` – prevents nonrepeatable reads.
- `serializable | 3` – specifies isolation level 3, the SAP ASE server applies a `holdlock` to all `select` and `readtext` operations in a transaction, which holds the queries' read locks until the end of that transaction. If you also set `chained mode`, that isolation level remains in effect for any data retrieval or modification statement that implicitly begins a transaction.
- `statement snapshot -`.
- `transaction snapshot -`.
- `readonly statement snapshot -`.

```
set transactional_rpc {on | off}
```

controls the handling of remote procedure calls. If this option is set to `on`, when a transaction is pending, the RPC is coordinated by the SAP ASE server. If this option is set to `off`, the remote procedure call is handled by the SAP ASE site handler. The default value is inherited from the value of the `enable xact coordination` configuration parameter.

## Examples

### Example of ansinull

Tells the SAP ASE server to evaluate NULL-valued operands of equality (=) and inequality (!=) comparisons and aggregate functions in compliance with the entry level ANSI SQL standard:

```
set ansinull on
```

When you use `set ansinull on`, aggregate functions and row aggregates raise the following SQLSTATE warning when the SAP ASE server finds null values in one or more columns or rows:

```
Warning - null value eliminated in set function
```

If the value of either the equality or the inequality operands is NULL, the comparison's result is UNKNOWN. For example, the following query returns no rows in `ansinull` mode:

```
select * from titles where price = null
```

If you use `set ansinull off`, the same query returns rows in which `price` is NULL.

### Example of char\_convert

Activates character set conversion, setting it to a default based on the character set the client is using. The SAP ASE server also notifies the client or application when characters cannot be converted to the client's character set:

```
set char_convert on with error
```

### Example of cis\_rpc\_handling

Specifies that CIS handles outbound RPC requests by default:

```
set cis_rpc_handling on
```

### Example of clientname

Assigns this user the client name `alison`, the host name `money1`, and the application name `webserver2`:

```
set clientname 'alison'  
set clienthostname 'money1'  
set clientapplname 'webserver2'
```

### Example of cursor rows

Returns five rows for each succeeding `fetch` statement requested by a client using `test_cursor`:

```
set cursor rows 5 for test_cursor
```

### Example of dml\_logging

This example shows how the DML logging mode for multiple statements on the same table remains unchanged if the table was initially operated with minimal logging in a transaction.

1. Begin the transaction and set the DML logging to minimal:

```
begin tran  
set dml_logging minimal
```

2. Run an `insert` command:

```
insert into tabl values(1)
```

3. Set DML logging back to the default:

```
set dml_logging default
```

Even though you reset DML logging to the default, because `t1` was previously run with minimal logging in this transaction, this `insert` is executed with minimal logging:

```
insert into tabl values(1)
```

The error log includes reasons the logging mode choice was overridden.

### Example of `export_options`

Tells the SAP ASE server to retain the session settings that are set by a system procedure or trigger for the duration of the session:

```
set export_options on
```

To disable `set export_options` and return the SAP ASE server to the default behavior, use:

```
set export_options off
```

You can export these optimization settings using `set export_options on`.

### **i** Note

By default, `set export_options` are enabled for login triggers.

### Example of `fipsflagger`

Tells the SAP ASE server to display a warning message if you use a Transact-SQL extension:

```
set fipsflagger on
```

Then, if you use nonstandard SQL, like this:

```
use pubs2
go
```

The SAP ASE server displays:

```
SQL statement on line number 1 contains Non-ANSI text.
The error is caused due to the use of use database.
```

### Example of `identity_insert`

Inserts a value of 100 into the `IDENTITY` column of the `stores_south` table, then prohibits further explicit inserts into this column. Note the use of the `syb_identity` keyword; the SAP ASE server replaces the keyword with the name of the `IDENTITY` column:

```
set identity_insert stores_south on
go
insert stores_south (syb_identity)
values (100)
go
set identity_insert stores_south off
```

```
go
```

### Example of identity\_update

Enables `identity_update` and updates tables with values 1 and 10, respectively, then disables `identity_update`:

```
set identity_update t1 on
update t1 set c2 = 10 where c1 =1
select * from t1
c1          c2
-----
1           10
```

```
set identity_update t1 off
```

### Example of lock nowait

Subsequent commands in the session or stored procedure return an error and fail if they cannot get requested locks immediately:

```
set lock nowait
```

### Example of lock wait

Subsequent commands in the current session or stored procedure wait indefinitely long to acquire locks:

```
set lock wait
```

Alternatively, in this example, subsequent commands in the session or stored procedure wait 5 seconds to acquire locks before generating an error message and failing:

```
set lock wait 5
```

### Example of plan dump

Enables capturing abstract plans to the `dev_plans` group:

```
set plan dump dev_plans on
```

### Example of plan load

Enables loading of abstract plans from the `dev_plans` group for queries in the current session:

```
set plan load dev_plans on
```

### Example of proc\_output\_params

Suppresses the output of parameter information:

```
1> create procedure sp_pout (@x int output) as select
    @x = @x + 1
2> go
1> set proc_output_params off
2> go
1> declare @x int
2> select @x = 1
3> exec sp_pout @x output
4> print "Value of @x returned from sproc is: %!", @x
5> go
(1 row affected)
(return status = 0)
```

```
Value of @x returned from sproc is: 1
```

If you do not perform `set proc_output_params off`, the output after (return status = 0) includes the following:

```
Return parameters:
-----
                2
```

### Example of `proc_return_status`

Suppresses the output of both parameters and the return status TDS token:

```
set proc_output_params off
go
set proc_return_status OFF
go
declare @x int
select @x = 2
exec sp_pout @x output
print "Value of @x returned from sproc is: %!", @x
go (1 row affected)
Value of @x returned from sproc is: 2
(1 row affected)
```

In addition, you can also suppress the lines reporting the number of rows affected to generate output with no extra messages using the `set nocount on` option before running this batch.

### Example of proxy

The user executing this command now operates within the server as the login "mary" and Mary's server user ID:

```
set proxy "mary"
```

### Example of rowcount

For each `insert`, `update`, `delete`, and `select` statement, the SAP ASE server stops processing the query after it affects the first four rows. For example:

```
select title_id, price from titles
title_id price
-----
BU1032      19.99
BU1111      11.95
BU2075       2.99
BU7832      19.99
(4 rows affected)
```

```
set rowcount 4
```

### Example of `quoted_identifier` on

Tells the SAP ASE server to treat any character string enclosed in double quotes as an identifier. The table name "`!*&strange_table`" and the column name "`emp's_name`" are legal identifier names while `quoted_identifier` is on:

```
set quoted_identifier on
go
create table "!*&strange_table"
("emp's_name" char(10), age int)
go
```

```
set quoted_identifier off
go
```

#### Example of quoted\_identifier off

Treats a character string enclosed in brackets as an identifier. The table name [!\*&strange\_table] and the column name [emp's\_name] are legal identifier names because they are enclosed in brackets, even though quoted\_identifier is off:

```
set quoted_identifier off
go
create table [!*&strange_table]
    ([emp's_name] char(10), age int)
go
```

#### Example of role

Activates the "doctor" role. This command is used by users to specify the roles they want activated:

```
set role doctor_role < >on
```

#### Example of role off

Deactivates the user's system administrator role for the current session:

```
set role "sa_role" off
```

#### Example of role with password on

Activates the "doctor" role when the user enters the password:

```
set role doctor_role with passwd "physician" on
```

#### Example of scan\_parallel\_degree

Specifies a maximum degree of parallelism of 4 for parallel index scans and parallel table scans on nonpartitioned tables:

```
set scan_parallel_degree 4
```

#### Example of session authorization

Sets session authorization for a user:

```
set session authorization "mary"
```

#### Example of showplan

Returns a description of the processing plan for each query, but does not execute it:

```
set showplan, noexec on
go
select * from publishers
go
```

#### Example of spinnlock\_aggregation

Shows a result set from monSpinlockActivity with set spinnlock\_aggregation disabled:

```
1> set spinnlock_aggregation off
2> go
1> select * from monSpinlockActivity
2> where SpinnlockName like "default data cache%"
```

```

3> order by Contention
4> go
Grabs          Spins          Waits          OwnerPID
              LastOwnerPID Contention      InstanceID SpinlockSlotID
              SpinlockName
-----
-----
              37697          978          1          0
              1638413          0.000027          0          2338
              default data cache          16396          15
              2          0
              1638413          0.000122          0          2340
              default data cache
              17317          24          3          0
              1638413          0.000173          0          2339
              default data cache
              27533          629          5          0
              1638413          0.000182          0          2341
              default data cache

```

When you select the number of rows from this instance of `monSpinlockActivity`:

```

select count(*) from monSpinlockActivity
-----
                2384

```

However, if you enable `set spinlock_aggregation` and perform the same query:

```

1> set spinlock_aggregation on
2> go
1> select * from monSpinlockActivity
2> where SpinlockName like "default data cache%"
3> order by Contention
4> go
Grabs          Spins          Waits          OwnerPID
              LastOwnerPID Contention      InstanceID SpinlockSlotID
              SpinlockName
-----
-----
              99235          1646          11          0
              1769486          0.000111          0          2338
              default data cache

```

This instance of `monSpinlockActivity` now shows much fewer rows:

```

select count(*) from monSpinlockActivity
-----
                324

```

### Example of statistics

Displays the statistics for the query in a tree format:

```
set statistics plancost on
```

```

select * from authors
au_id   au_fname   au_lname   phone      address
city    state     country    postalcode
-----

```



```

-----
-----172-32-1176 White Johnson
408 496-7223 10932 Bigge Rd.
Menlo Park CA USA 94025
213-46-8915 Green Marjorie 415 986-7020 309 63rd St. #411
Oakland CA USA 94618
. . .
998-72-3567 Ringer Albert 801 826-0752 67 Seventh Av.
Salt Lake City UT USA 84152
===== Lava Operator Tree =====
Emit
(VA = 1)
23 rows est: 23
cpu: 0
/
TableScan
authors
(VA = 0)
23 rows est: 23
lio: 1 est: 2
pio: 0 est: 2
=====
(23 rows affected)

```

### Example of statistics ioplan

Displays the IO statistics per plan for each view:

```

set statement_cache off
set quoted_identifier on
set showplan on
set statistics ioplan on
go
Execution Time (ms.):          0          Clock Time (ms.):          0
select count(*) from AI_ICLRWGHT v
go
QUERY PLAN FOR STATEMENT 1 (at line 1).
Optimized using Serial Mode
STEP 1
The type of query is SELECT.
4 operator(s) under root
|ROOT:EMIT Operator (VA = 4)
|
| |SCALAR AGGREGATE Operator (VA = 3)
| | Evaluate Ungrouped COUNT AGGREGATE.
| |
| | |NESTED LOOP JOIN Operator (VA = 2) (Join Type: Inner Join)
| | |
| | | |SCAN Operator (VA = 0)
| | | | FROM TABLE
| | | | "SMT_D_AGGR_RULE"
| | | | from view: v
| | | | "AGG_RULE"
| | | | Table Scan.
| | | | Forward Scan.
| | | | Positioning at start of table.
| | | | Using I/O Size 16 Kbytes for data pages.
| | | | With LRU Buffer Replacement Strategy for data pages.
| | |
| | | |SCAN Operator (VA = 1)
| | | | FROM TABLE
| | | | "AGS_SMT_CLR_RATE"
| | | | from view: v
| | | | "COL"
| | | | Index : "AGS_SMT_CLR_RATE~0"
| | | | Forward Scan.
| | | | Positioning by key.

```

```

| | | | Index contains all needed columns. Base table will not
be read.
| | | | Keys are:
| | | | AGGREGATION_RULE ASC
| | | | Using I/O Size 16 Kbytes for index leaf pages.
| | | | With LRU Buffer Replacement Strategy for index leaf
pages.
Statement number: 1
4 operator(s) under root
|ROOT:EMIT Operator (VA = 4)
| |SCALAR AGGREGATE Operator (VA = 3)
| | Evaluate Ungrouped COUNT AGGREGATE.
| | NESTED LOOP JOIN Operator (VA = 2)
| | |SCAN Operator (VA = 0)
| | |View: v
| | |Table: "SMT_D_AGGR_RULE" ("AGG_RULE")
| | | sc 4, lr: (l=0 a=4), pr: (r=0 a=2)
| | |SCAN Operator (VA = 1)
| | |View: v
| | |Table: "AGS_SMT_CLR_RATE" ("COL")
| | | sc 4, lr: (l=0 a=4), pr: (r=2 a=0)
(1 row affected)

```

### Example of statistics plan\_directory\_html

Writes HTML generated query plan and execution statistics to a file in a specified directory in an external file:

```

set statistics plan_directory_html "/usr/myDir/HTML"
go
set statistics plan_directory_html on
go

```

### Example of string\_rtruncation

Causes the SAP ASE server to generate an exception when truncating a char, unichar, or nchar string:

```

set string_rtruncation on

```

If an insert or update statement would truncate a string, the SAP ASE server displays:

```

string data, right truncation

```

### Example of textsize

Sets the limit on text, unitext, or image data returned with a select statement to 100 bytes:

```

set textsize 100

```

### Example of switch on

Sets the server wide switch on to generate trace information to session output:

```

set switch on print_minlogged_mode_override
go

```

```

Switch 'print_minlogged_mode_override' is turned on.
All supplied switches are successfully turned on.

```

You can also set the server wide switch on to set traceflags for 110, an undocumented traceflag, with no additional informational warnings:

```
set switch serverwide on 110 with override, no_info
```

### Example of tracefile

Opens a trace file named `sql_text_file` for the current session:

```
set tracefile '/var/sybase/text_dir/sql_text_file'
```

Subsequent outputs from `set showplan`, `set statistics io`, and `dbcc traceon(100)` are saved in `sql_text_file`.

You can also choose not to specify a directory path, so the trace file is saved in `$$SYBASE/sql_text_file`:

```
set tracefile 'sql_text_file' for 11
```

Any SQL run on spid 11 is saved to this tracefile.

The following saves the SQL text for spid 86:

```
set tracefile '/var/sybase/text_dir/sql_text_file' for 86
```

### Example of transaction\_rpc

Specifies that when a transaction is pending, the RPC is handled by the CIS access methods rather than by the SAP ASE site handler:

```
set transaction_rpc on
```

### Examples of transaction isolation levels

All subsequent queries in the session run at the repeatable reads transaction isolation level:

```
set transaction isolation level 2
```

This example implements read-locks with each `select` statement in a transaction for the duration of that transaction:

```
set transaction isolation level 3
```

### Example of show\_exec\_info

Changes the `show_exec_info` from `minimal` to `full` within the same session:

1. Log in to the SAP ASE server:

```
isql -Ubob -Pbob123
use myimdb
```

2. Create table `tab1`:

```
create table tab1(col1 int)
```

3. Enable `show_exec_info` and set DML logging to `minimal`:

```
set show_exec_info on
set dml_login minimal
```

4. Insert values into `tab1`:

```
insert into tab1 values(1)
```

5. The SAP ASE server displays the name of the table and database, the user ID running the command, and the logging mode used:

```
Operating on the table 'tab1', database 'myimdb'  
(owner ID 3) in 'minimal' logging mode by user ID 3.
```

6. Set the DML logging back to default:

```
set dml_logging default
```

7. Insert more values into `tab1`:

```
insert into tab1 values(1)
```

8. The SAP ASE server displays the name of the table and database, the user ID running the command, and the logging mode used:

```
Operating on the table 'tab1', database 'myimdb'  
(owner ID 3) in 'full' logging mode by user ID 3.
```

### Example of set statistics resource

Once enabled, all subsequent queries for the session track the procedure cache consumption:

```
set statistics resource on  
go  
use pubs2  
go  
Statement: 1 Compile time resource usage: (est worker processes=0  
proccache=0),  
Execution time resource usage: (worker processes=0 auxsdsc=0 plansize=2  
proccache=2 proccache hwm=2 tempdb hwm=0)
```

### Example of setting a session

Once enabled, all subsequent queries for the session track the procedure cache consumption:

```
set statistics resource on  
go  
use pubs2  
go  
Statement: 1 Compile time resource usage: (est worker processes=0  
proccache=0),  
Execution time resource usage: (worker processes=0 auxsdsc=0 plansize=2  
proccache=2 proccache hwm=2 tempdb hwm=0)
```

## Usage

- `fipsflagger`, `string_rtruncation`, `ansinull`, `ansi_permissions`, `arithabort`, and `arithignore` affect aspects of SAP ASE error handling and compliance to SQL standards.
- You can use the `cis_rpc_handling` and `transactional_rpc` options only when CIS is enabled.
- The `async_log_service` option and `delayed_commit` are mutually exclusive. `delayed_commit` does not work if `async_log_service` is set to "true."

- `parallel_degree` and `scan_parallel_degree` limit the degree of parallelism for queries, if the SAP ASE server is configured for parallelism. When you use these options, you give the optimizer a hint to limit parallel queries to use fewer worker processes than allowed by the configuration parameters. Setting these parameters to 0 restores the server-wide configuration values.  
If you specify a number that is greater than the numbers allowed by the configuration parameters, the SAP ASE server issues a warning message and uses the value set by the configuration parameter.
- If you use the `set` command inside a trigger or stored procedure, most `set` options revert to their former settings after the trigger or procedure executes.  
The following options do not revert to their former settings after the procedure or trigger executes, but remain for the entire SAP ASE session or until you explicitly reset them:
  - `datefirst`
  - `dateformat`
  - `identity_insert`
  - `language`
  - `quoted_identifier`
- If you specify more than one `set` option, the first syntax error causes all following options to be ignored. However, the options specified before the error are executed, and the new option values are set.
- If you assign a user a client name, host name, or application name, these assignments are only active for the current session. You must reassign these the next time the user logs in. Although the new names appear in `sysprocesses`, they are not used for permission checks, and `sp_who` still shows the client connection as belonging to the original login. For more information about setting user processes, see the *System Administration Guide*.
- All `set` options except `showplan` and `char_convert` take effect immediately. `showplan` takes effect in the following batch. Here are two examples that use `set showplan on`:

```
set showplan on
select * from publishers
go
pub_id  pub_name                city      state
-----
0736    New Age Books              Boston    MA
0877    Binnet & Hardley           Washington DC
1389    Algodata Infosystems      Berkeley  CA
(3 rows affected)
```

But:

```
set showplan on
go
select * from publishers
go
```

```
QUERY PLAN FOR STATEMENT 1 (at line 1).
STEP 1
  The type of query is SELECT
  FROM TABLE
    publishers
  Nested iteration
  Table Scan
  Ascending Scan.
  Positioning at start of table.
pub_id  pub_name                city      state
-----
0736    New Age Books              Boston    MA
0877    Binnet & Hardley           Washington DC
```

```
1389   Algodata Infosystems Berkeley CA
(3 rows affected)
```

- The SAP ASE server automatically stores one or more spaces in `clientname`, `clienthostname`, and `clientapplname` columns. For this reason, a query using any of these three columns that includes "is null" does not return an expected result set.
- `set proxy` issue the following warning when they are issued while `set fipsflagger` option is enabled:

```
SQL statement on line number 1 contains Non-ANSI
text. The error is caused due to the use of DBCC.
```

- If you use a login trigger to set current execution properties, any exportable `set` option that you enable or disable inside a login trigger takes affect in the current process.

See also:

- `convert` in *Reference Manual: Building Blocks*
- `isql`, `optdiag` in the *Utility Guide*
- `sp_setrepdbmode`, `sp_setrepdefmode` in *Reference Manual: Procedures*

## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

The ANSI SQL standard specifies behavior that differs from Transact-SQL behavior in versions of SAP ASE earlier than 15.7. Compliant behavior is enabled, by default, for all Embedded-SQL precompiler applications. Other applications needing to match this standard of behavior can use these `set` options with the following settings:

Option	Value
<code>ansi_permissions</code>	on
<code>ansinull</code>	on
<code>arithabort</code>	off
<code>arithabort numeric_truncation</code>	on
<code>arithignore</code>	off
<code>chained</code>	on
<code>close on endtran</code>	on
<code>fipsflagger</code>	on
<code>quoted_identifier</code>	on
<code>string_rtruncation</code>	on

Option	Value
transaction isolation level	3

## Permissions

Permission checks may differ based on your granular permission settings. In general, `set` permission defaults to all users and no special permissions are required to use it. Exceptions include `set identity_insert`, `set identity_update`, `set option show_option`, `set plan for show`, `set proxy`, `set repthreshold`, `set role`, `set session authorization`, `set tracefile`, and `set switch`. See command description above for permission requirements for each exception.

## Auditing

You can enable the following auditing options to audit this command. Values in `event` and `extrainfo` columns from the `sysaudits` table are:

Audit option	Event	Command or access audited	Information in <code>extrainfo</code> :
role	55	set role	<ul style="list-style-type: none"> <li>• <b>Roles</b> – current active roles</li> </ul>
security	55	set role	<ul style="list-style-type: none"> <li>• <b>Full command text</b> – full text of the audited command (password is obfuscated)</li> </ul>
security	88	set session authorization/set proxy	<ul style="list-style-type: none"> <li>• <b>Previous value</b> – NULL</li> <li>• <b>Current value</b> – NULL</li> <li>• <b>Other information</b> – NULL</li> <li>• <b>Proxy information</b> – original login name, if <code>set proxy</code> is in effect.</li> </ul>

For `set role`, full command text (with obfuscated password) is included in `extrainfo`. For example:

```
sa_role sso_role oper_role sybase_ts_role mon_role; set role
roleA with passwd ***** on; ; ; ; ; sa/ase;
```

For more information about auditing, see *Security Administration Guide > Auditing*.

## Related Information

[Aggregate Behavior \[page 778\]](#)

[Delimited Identifiers \[page 789\]](#)

[Using Proxies \[page 782\]](#)

[fetch \[page 513\]](#)

[grant \[page 520\]](#)

[insert \[page 572\]](#)

[lock table \[page 614\]](#)

[revoke \[page 672\]](#)

## 1.116.1 set Options That Can Be Grouped Together

Some `set` options can be grouped together.

- `parseonly`, `noexec`, `prefetch`, `showplan`, `rowcount`, and `nocount` control the way a query is executed. It does not make sense to set both `parseonly` and `noexec` on. The default setting for `rowcount` is 0 (return all rows); the default for the others is `off`.
- The `statistics` options display performance statistics after each query. The default setting for the `statistics` options is `off`. For more information about `noexec`, `prefetch`, `showplan` and `statistics`, see the *Performance and Tuning Guide*.
- You can update up to 1024 columns in the `set` clause using literals, variables, or expressions returned from a subquery.
- `offsets` is used in DB-Library to interpret results from the SAP ASE server. The default setting for this option is `on`.
- `datefirst`, `dateformat`, and `language` affect date functions, date order, and message display. If used within a trigger or stored procedure, these options do not revert to their previous settings. In the default language, `us_english`, `datefirst` is 1 (Sunday), `dateformat` is `<mdy>`, and messages are displayed in `us_english`. Some language defaults (including `us_english`) produce Sunday=1, Monday=2, and so on; others produce Monday=1, Tuesday=2, and so on. `set language` implies that the SAP ASE server should use the first weekday and date format of the language it specifies, but does not override an explicit `set datefirst` or `set dateformat` command issued earlier in the current session.
- `cursor rows` and `close on endtran` affect the way the SAP ASE server handles cursors. The default setting for `cursor rows` with all cursors is 1. The default setting for `close on endtran` is `off`.
- `chained` and `transaction isolation level` allow the SAP ASE server to handle transactions in a way that is compliant with the SQL standards.

## 1.116.2 Compile-Time Changes for Some `set` Parameters

In version 15.0.2 and later, the SAP ASE server changes the compile-time behavior for some abstract plan `set` parameters when you use them to create stored procedures or run them in Transact-SQL batches.

In earlier versions of SAP ASE, the `set` parameters took effect after the stored procedure was executed or recompiled. SAP ASE 15.0.2 allows you to use optimizer `set` parameters at compile time to affect the optimizer in stored procedures or batches.

### **i** Note

This changed behavior may effect the composition of the result set. You should review the result set created by the 15.0.2 versions of the `set` parameters before using them in your production systems.



You must reset the `set` parameter before returning from the stored procedure or the execution of subsequent stored procedures may be affected. If you intend to propagate this change to subsequent stored procedures, use `export_options` parameter.

The optimizer options that you can export when you use `set export_options` on are:

- `addend_union_all`
- `auto_query_tuning`
- `basic_optimization`
- `bushy_space_search`
- `distinct_hashing`
- `distinct_sorted`
- `distinct_sorting`
- `group_hashing`
- `group_inserting`
- `group_sorted`
- `hash_join`
- `hash_union_distinct`
- `index_intersection`
- `index_union`
- `merge_join`
- `merge_union_all`
- `merge_union_distinct`
- `multi_gt_store_index`
- `nary_nl_join`
- `nl_join`
- `opportunistic_distinct`
- `opportunistic_grouping`
- `optgoal`
- `opttimeout`
- `order_sorting`
- `parallel_query`
- `query_tuning_mem_limit`
- `query_tuning_time_limit`
- `replicated_partitioning`
- `showabstractplan`
- `showbestplan`
- `showcodegen`
- `showcounters`
- `showelimination`
- `showexecio`
- `showfinalplan`
- `showhistograms`
- `showliocosting`

- `showlogprops`
- `showlop`
- `showmanagers`
- `shownostats`
- `showparallel`
- `showpiocosting`
- `showpllcosting`
- `showsearchengine`
- `store_index`
- `streaming_sort`

### 1.116.3 Aggregate Behavior

`ansinull` determines whether NULL-valued operands in aggregate functions are evaluated in compliance with the ANSI SQL standard. If you use `set ansinull on`, the SAP ASE server generates a warning when an aggregate function eliminates a null-valued operand from the calculation.

For example, if you perform the following query on the `titles` table with `set ansinull off` (the default value):

```
select avg (total_sales) from titles
```

The SAP ASE server returns:

```
-----
      6090
```

However, if you perform the same query with `set ansinull on`, the SAP ASE server returns the following:

```
1> use pubs2
2> go
1> select avg (total_sales) from titles
2> go
```

```
-----
      6090
(1 row affected)
```

```
1> set ansinull on
2> go
1> select avg (total_sales) from titles
2> go
```

```
-----
      6090
Warning - null value eliminated in set function
(1 row affected)
```

This message indicates that some entries in `total_sales` contain NULL instead of a real amount, so you do not have complete data on total sales for all books in this table. However, of the available data, the value returned is the highest.

## 1.116.4 Comparison Behavior

The SQL standard requires that if either one of the two operands of an equality comparison is NULL, the result is UNKNOWN. Transact-SQL treats NULL values differently.

If one of the operands is a column, parameter, or variable, and the other operand is the NULL constant or a parameter or variable whose value is NULL, the result is either TRUE or FALSE:

- Sybase NULL mode – “`val = NULL`” is true when “`val`” is NULL
- ANSI NULL mode – “`val = NULL`” is unknown when “`val`” is NULL

The ANSI rule for the `where` and `on` clauses return rows that are true, and rejects rows that are both false and unknown.

The ANSI rule for a `check` constraint rejects values that are false. For this reason, unknown or true results are not rejected.

If you:

- Enable `ansinull` mode – do not use the Sybase NULL comparisons (`val = NULL` or `val != NULL`).
- Expect to use ANSI-null mode during `insert` and `update` – do not use the Sybase NULL comparisons in `check` constraints.

Instead, use the `ANSI IS NULL` or `IS NOT NULL` syntax to prevent from having unexpected results.

## 1.116.5 Roles and `set` Options

When a user logs in to SAP ASE, the user's roles are not necessarily active, depending upon how the role is set up as a default role.

A system security officer can change role automatic activation using `alter login` or `alter login profile`

Use `set role <role_name> on` or `set role <role_name> off` to turn roles on and off.

For example, if you have been granted the system administrator role, you assume the identity (and user ID) of database owner in the current database. To assume your real user ID, execute this command:

```
set role "sa_role" off
```

If you are not a user in the current database, and if there is no “guest” user, you cannot set `sa_role off`.

If the user-defined role you intend to activate has an attached password, you must specify the password to turn the role on. Thus, you would enter:

```
set role "<role_name>" with passwd "<password>" on
```

During `set role`, the SAP ASE server locks the role if your failed role activation attempts reach the number you set in `max_failed_logins`. When this happens, `locksuid`, `lockdate`, and `lockreason` in `sysserverroles`.

## 1.116.6 In-Memory and Relaxed-Durability Databases

Data copied into a table created with `select into` is minimally logged. `with dml_logging = minimal` specifies the logging mode for future DML operations on this table.

- Setting the logging level to `minimal` affects the logging mode only on objects owned by the current user. However, if the user has system administrator privileges, setting the logging to `minimal` affects the logging mode for all objects in the user's session.
- `show_exec_info` does not display the reason the SAP ASE server overrides a minimally logged mode selected by a user. Use `set switch on print_minlogged_mode_override` to view the reasons for this override.
- Session-specific settings for the logging mode override the logging options set at the table and database level, and include these restrictions:
  - Database-wide settings
  - Disabling DML logging for the current session based on the logging mode:
    - Database-wide logging mode settings
    - Table-specific logging mode settings
    - The ownership of the tables being updated
- If you set the session-specific DML logging to `minimal`, running `set dml_logging default` returns the logging mode for the affected tables to their default logging mode, based on the table and database-wide settings.
- You cannot use `set dml_logging` to perform fully logged DML if the database or table owner has already configured the table to run with minimal logging.

## 1.116.7 In-Memory Row Storage

- You can specify a single table with the `set row_caching` parameter to disable row caching. Issuing this command to specify a second table automatically reverts row caching for first table to its prior (`default`) setting (usually enabled). However, row caching is temporarily disabled for the second table.
- Ongoing updates or deletes occurring in the IMRS continue to be performed when you disable row caching, and selects of cached rows return the data directly from the IMRS. Disabling row caching only affects new usage of the IMRS.
- There is no impact on the table's row caching property for users from another session while `set row_caching` is in effect in the altered session.
- `set row_caching` alters only new row caching usage for this session. The server continues to perform updates, deletes, and selects of rows already in the in-memory row storage, and cached rows return the data directly from the in-memory row storage.
- Use the `bcp in ... - initstring` parameter to temporarily disable row caching for the `bcp` session, and redirect all inserts to the page store. For example:

```
bcp production..large_table in vldb_data_file.dat \  
--initstring "set row_caching production..large_table off
```

## 1.116.8 Setting Compression for a Session

Enabling or disabling compression for a session does not change the compression level for existing data.

- Updated rows remain uncompressed. The SAP ASE server uncompresses any compressed rows during the update.
- If `set compression` is set to `off`, commands that require a data copy (for example, `reorg rebuild` and `alter table`) uncompress data rows.
- After you configure `set compression on`, subsequent updates use the partition or tables' compression level.

## 1.116.9 Using Predicated Privileges

Use `set show_transformed_sql` to display the SQL text.

- Use `set show_transformed_sql` with `set noexec` to display the text of an SQL query, but not execute the query.
- When you enable `show_transformed_sql` for a session, DML or `select` commands displays the SQL text of:
  - Predicate text, if predicates exist on tables in the SQL command. If no predicates exist, `show_transformed_sql` displays NULL.
  - User query text
  - SQL text of the query after aggregate processing, view processing, encryption, and predicate merging. For queries that do not access any predicates, the SQL text denotes the text after view processing, encryption, and so on.
  - SQL text of the query after subquery processing.

## 1.116.10 Distributed Transactions, CIS, and `set` Options

When the SAP ASE server distributed transaction management services are enabled, you can place RPCs within transactions. These RPCs are called transactional RPCs.

A transactional RPC contains work that can be included in the context of a current transaction. This remote unit of work can be committed or rolled back along with the work performed by the local transaction.

- The behavior of the `cis_rpc_handling` configuration property and the `set transactional_rpc` commands changed with the introduction of ASTC. In versions earlier than 12.0, enabling `cis_rpc_handling` caused *all* RPCs to be routed through CIS's Client-Library connection. As a result, whenever `cis_rpc_handling` was enabled, `transactional_rpc` behavior occurred whether or not it had been specifically set. As of SAP ASE 12.0, this behavior has changed. If `cis_rpc_handling` is enabled and `transactional_rpc` is `off`, RPCs within a transaction are routed through the site handler. RPCs executed outside a transaction are sent via CIS's Client-Library connection.
- To use transactional RPCs, enable CIS and distributed transaction management with `sp_configure`, then issue the `set transactional_rpc` command. When `set transactional_rpc` is `on` and a transaction is pending, the SAP ASE server (as opposed to the SAP ASE site handler) coordinates the RPC.

The `set transactional_rpc` command default is `off`. The `set cis_rpc_handling` command overrides the `set transactional_rpc` command. If you set `cis_rpc_handling` on, all outbound RPCs are handled by CIS.

- See the *Component Integration Services User's Guide* for a discussion of using `set transactional_rpc`, `set cis_rpc_handling`, and `sp_configure`.

## 1.116.11 Using Proxies

Considerations for using proxies.

### i Note

Without explicit permission, neither the `sa_role` nor the `sso_role` can issue the `set proxy login_name` command. To use `set proxy login_name`, any user, including the system security officer, must have permission explicitly granted by the system security officer.

- Before you can use the `set proxy` or `set session authorization` command, you must be granted `set proxy privilege` or `set session authorization privilege` in master.
- You can switch your server user identity to any other server login and limit its use based on the target login roles by using:

```
grant set proxy to <user_or_role_list>
[restrict role <role_list> | all | system]
```

- Executing `set proxy` or `set session authorization` with the original `<login_name>` reestablishes your previous identity.
- You cannot execute `set proxy` or `set session authorization` from within a transaction.
- The SAP ASE server permits only one level of login identity change. Therefore, after you use `set proxy` or `set session authorization` to change identity, you must return to your original identity before changing it again. For example, assume that your login name is "ralph". To create a table as "mary", create a view as "joe", then return to your own login identity. Use the following statements:

```
set proxy "mary"
create table mary_sales
(stor_id char (4),
ord_num varchar (20),
date datetime)
grant select on mary_sales to public
set proxy "ralph"
set proxy "joe"
create view joes_view (publisher, city,
state)
as select stor_id, ord_num, date
from mary_sales
set proxy "ralph"
```

- If a user issues `set proxy` to assume the permissions, login name, and `suid` of another user, the SAP ASE server checks the proxy user's access to database objects, rather than the original user's access. The SAP ASE server uses the name and password information of the user who logged in to check for automatic access to encryption keys using login credentials. The SAP ASE server does not have access to the proxy user's password. Access to keys through the login password is on behalf of the user who logs in, not on behalf of the user assumed through an alias, `set proxy`, or `setuser`. Access to copies of

encryption keys that were set up for login association, but which are still encrypted by the system encryption password or the master key, is treated similarly.

## 1.116.12 Using lock wait

Considerations for using `lock wait`.

- By default, an SAP ASE task that cannot immediately acquire a lock waits until incompatible locks are released, then continues processing. This is equivalent to `set lock wait` with no value specified in the `<numsecs>` parameter.
- You can set a server-wide lock wait period by using `sp_configure` with the `lock wait period` option.
- `lock wait period`, with the session-level setting `set lock wait nnn`, is only applicable for user-defined tables. These settings have no influence on system tables.
- A lock wait period defined at the session level or in a stored procedure with the `set lock` command overrides a server-level lock-wait period.
- If `set lock wait` is used by itself, with no value for `<numsecs>`, all subsequent commands in the current session wait indefinitely to acquire requested locks.
- `sp_sysmon` reports the number of times that tasks waiting for a lock could not acquire the lock within the waiting period.

## 1.116.13 Repeatable-Reads Transaction Isolation Level

The repeatable-reads isolation level, also known as transaction isolation level 2, holds locks on all pages read by a statement until the transaction completes.

A nonrepeatable read occurs when one transaction reads rows from a table and a second transaction can modify the same rows and commit the changes before the first transaction completes. If the first transaction rereads the rows, they now have different values, so the initial read is not repeatable. Repeatable reads hold shared locks for the duration of a transaction, blocking transactions that update the locked rows or rows on the locked pages.

## 1.116.14 Using Simulated Statistics

You can load simulated statistics into a database using the `simulate` mode of the `optdiag` utility program. If `set statistics simulate on` has been issued in a session, queries are optimized using simulated statistics, rather than the actual statistics for a table.

## 1.116.15 Global Variables Affected by set Options

Global variables that contain information about the session options controlled by the `set` command.

Table 7: Global Variables Containing Session Options

Global Variable	Description
<code>&lt;@@char_convert&gt;</code>	Contains 0 if character set conversion not in effect. Contains 1 if character set conversion is in effect.
<code>&lt;@@client_csexpansion&gt;</code>	Returns the expansion factor used when converting from the server character set to the client character set. For example, if <code>&lt;@@client_csexpansion&gt;</code> contains a value of 2, a character in the server character set could take up to twice the number of bytes after translation to the client character set.
<code>&lt;@@cursor_rows&gt;</code>	A global variable designed specifically for scrollable cursors. Displays the total number of rows in the cursor result set. Returns the value -1:
<code>&lt;@@datefirst&gt;</code>	<p>Set using <code>set datefirst n</code> where <code>n</code> is a value between 1 and 7. Returns the current value of <code>&lt;@@datefirst&gt;</code>, indicating the specified first day of each week, expressed as <code>tinyint</code>.</p> <p>The default value in SAP ASE is Sunday (based on the <code>us_language</code> default), which you set by specifying <code>set datefirst 7</code>. See the <code>datefirst</code> option of the <code>set</code> command for more information on settings and values.</p>
<code>&lt;@@isolation&gt;</code>	Contains the current isolation level of the Transact-SQL program. <code>&lt;@@isolation&gt;</code> takes the value of the active level (0, 1, or 3).
<code>&lt;@@lock_timeout&gt;</code>	Set using <code>set lock wait n</code> . Returns the current <code>&lt;lock_timeout&gt;</code> setting, in milliseconds. <code>&lt;@@lock_timeout&gt;</code> returns the value of <code>n</code> . The default value is no timeout. If no <code>set lock wait n</code> is executed at the beginning of the session, <code>&lt;@@lock_timeout&gt;</code> returns -1.
<code>&lt;@@options&gt;</code>	Contains a hexadecimal representation of the session's <code>set</code> options.
<code>&lt;@@parallel_degree&gt;</code>	Contains the current maximum parallel degree setting.



Global Variable	Description
<code>&lt;@@rowcount&gt;</code>	<p>Contains the number of rows affected by the last query. <code>&lt;@@rowcount&gt;</code> is set to 0 by any command that does not return rows, such as an <code>if</code>, <code>update</code>, or <code>delete</code> statement. With cursors, <code>&lt;@@rowcount&gt;</code> represents the cumulative number of rows returned from the cursor result set to the client, up to the last <code>fetch</code> request.</p> <p><code>&lt;@@rowcount&gt;</code> is updated even when <code>nocount</code> is on.</p>
<code>&lt;@@scan_parallel_degree&gt;</code>	Contains the current maximum parallel degree setting for nonclustered index scans.
<code>&lt;@@textsize&gt;</code>	<p>Contains the limit on the number of bytes of <code>text</code>, <code>unitext</code> or image data a <code>select</code> returns. Default limit is 32K bytes for <code>isql</code>; the default depends on the client software. Can be changed for a session with <code>set textsize</code>.</p> <p>If you use <code>enable surrogate processing</code>, Unicode surrogates (two 16-bit values) are returned as single characters, even though the actual return size may be less than the <code>&lt;@@text&gt;</code> size value.</p>
<code>&lt;@@tranchained&gt;</code>	Contains the current transaction mode of the Transact-SQL program. <code>&lt;@@tranchained&gt;</code> returns 0 for unchained or 1 for chained.

Table 8: set Options and Values for @@options

Numeric value	Hexadecimal value	set option
4	0x04	<code>showplan</code>
5	0x05	<code>noexec</code>
6	0x06	<code>arithignore</code>
8	0x08	<code>arithabort</code>
13	0x0D	<code>control</code>
14	0x0E	<code>offsets</code>
15	0x0F	<code>statistics io and statistics time</code>
16	0x10	<code>parseonly</code>
18	0x12	<code>procid</code>
20	0x14	<code>rowcount</code>
23	0x17	<code>nocount</code>
77	0x4D	<code>opt_sho_fi</code>

Numeric value	Hexadecimal value	set option
78	0x4E	select
79	0x4F	set tracefile

## 1.116.16 Using fipsflagger with Java in the Database

When `fipsflagger` is on, the SAP ASE server displays a warning message when some extensions are used.

- The `installjava` utility
- The `remove java` command
- Column and variable declarations that reference Java classes as datatypes
- Statements that use Java-SQL expressions for member references

The status of `fipsflagger` does not affect arithmetic expressions performed by Java methods.

For more information about Java in the database, see *Java in Adaptive Server Enterprise*.

## 1.116.17 Restrictions for set tracefile

Restrictions for using `set tracefile`.

- You cannot save the SQL text for system tasks (such as the housekeeper or the port manager).
- You must have the `sa` or `sso` roles, or be granted `set tracing` permission, to run `enable` or `disable tracing`.
- `set tracefile` is not allowed to open an existing file as a tracefile.
- During an SA or systems security officer session, if you `enable set tracefile` for a specific `spid`, all subsequent tracing commands executed take effect on that `spid`, not the system administrator or systems security officer `spid`.
- If the SAP ASE server runs out of file space while writing the tracefile, it closes the file and disables the tracing.
- If an `isql` session starts tracing for a `spid`, but the `isql` session quits without disabling the tracing, another `isql` session can begin tracing this `spid`.
- Tracing occurs for the session for which it is enabled only, not for the session that enabled it.
- You cannot trace more than one session at a time from a single `sa` or `sso` session. If you attempt to open a tracefile for a session for which there is already a trace file open, the SAP ASE server issues this error message: `tracefile is already open for this session`.
- You cannot trace the same session from multiple `sa` or `sso` sessions.
- The file storing the trace output is closed when the session being traced quits or when you `disable tracing`.
- Before you allocate resources for tracing, keep in mind that each tracing requires one file descriptor per engine.

## 1.116.18 `set` Options That Save Diagnostic Information to a Trace File

You can use `set tracefile` in combination with other `set` commands and options that provide diagnostic information for a better understanding of slow-running queries.

These are the `set` commands and options that save diagnostic information to a file:

- `set show_sqltext [on | off]`
- `set showplan [on | off]`
- `set statistics io [on | off]`
- `set statistics time [on | off]`
- `set statistics plancost [on | off]`

These are the `set` options:

- `set option show [normal | brief | long | on | off]`
- `set option show_lop [normal | brief | long | on | off]`
- `set option show_parallel [normal | brief | long | on | off]`
- `set option show_search_engine [normal | brief | long | on | off]`
- `set option show_counters [normal | brief | long | on | off]`
- `set option show_managers [normal | brief | long | on | off]`
- `set option show_histograms [normal | brief | long | on | off]`
- `set option show_abstract_plan [normal | brief | long | on | off]`
- `set option show_best_plan [normal | brief | long | on | off]`
- `set option show_code_gen [normal | brief | long | on | off]`
- `set option show_pio_costing [normal | brief | long | on | off]`
- `set option show_ljo_costing [normal | brief | long | on | off]`
- `set option show_log_props [normal | brief | long | on | off]`
- `set option show_elimination [normal | brief | long | on | off]`

## 1.116.19 Restrictions for `show_sqltext`

Restrictions for using `show_sqltext`.

- You must have the `sa` or `sso` roles to run `show_sqltext`.
- You cannot use `show_sqltext` to print the SQL text for triggers.
- You cannot use `show_sqltext` to show a binding variable or a view name.

## 1.116.20 Exporting set Options from a Login Trigger

The SAP ASE server enables `set` options inside login triggers to remain valid for the entire user session.

The following `set` options are automatically exported:

- `altnames`
- `ansi_permissions`
- `ansinull`
- `arithabort [overflow | numeric_truncation]`
- `arithignore [overflow]`
- `cis_rpc_handling`
- `close on endtran`
- `colnames`
- `command_status_reporting`
- `dup_in_subquery`
- `explicit_transaction_required`
- `fipsflagger`
- `flushmessage`
- `fmtonly`
- `forceplan`
- `format`
- `nocount`
- `or_strategy`
- `prefetch`
- `proc_output_params`
- `proc_return_status`
- `procid`
- `quoted_identifier`
- `raw_object_serialization`
- `remote_indexes`
- `replication`
- `rowcount`
- `self_recursion`
- `showplan`
- `sort_resources`
- `statistics io`
- `statement_cache`
- `strict_dtm_enforcement`
- `string_rtruncation`
- `textptr_parameters`
- `transactional_rpc`
- `triggers`

## 1.116.21 Delimited Identifiers

When the `quoted_identifier` option is set to `on`, you do not need to use double quotes around an identifier if the syntax of the statement requires that a quoted string contain an identifier.

For example:

```
set quoted_identifier on
create table "lone" (c1 int)
```

However, `object_id` requires a string, so you must include the table name in quotes to select the information:

```
select object_id ('lone')
```

```
-----
896003192
```

You can include an embedded double quote in a quoted identifier by doubling the quote:

```
create table "embedded""quote" (c1 int)
```

However, there is no need to double the quote when the statement syntax requires the object name to be expressed as a string:

```
select object_id ('embedded"quote')
```

### 1.116.21.1 Bracketed Identifiers

The SAP ASE server supports an alternative to quoted identifiers that uses brackets to surround an identifier. The behavior of bracketed identifiers is identical to that of quoted identifiers, with the exception that you do not have to use `set quoted_identifier on` to use them.

When you use bracketed identifiers instead of quoted identifiers to create objects, your objectname should have at least one valid character, such as:

- `create table [<table name>]`
- `create database [<database name>]`

All trailing spaces are removed from the objectname, so the following are all treated identically:

```
[tab1<space><space>]
[tab1<space><space>]
[tab1]
[tab1<space><space><space>]
tab1
```

This applies to all objects that can be created using bracketed identifiers.

The following are restrictions when using delimited identifiers in SAP ASE servers:

- A dot (.) cannot appear in an identifier name, however delimited
- Object names as stored procedure parameters – SAP ASE stored procedure object names can be treated as strings, and do not need delimiters. For example, the following gives correct results if a table named `table` actually exists:

```
exec sp_help 'dbo.table'
```

However, the brackets are not stripped from the object name in the following:

```
exec sp_help 'dbo.[table]'
```

## 1.117 setuser

Allows a database owner to impersonate another user.

### Syntax

```
setuser ["<user_name>"]
```

### Parameters

<user\_name>

Is the username.

### Examples

#### Example 1

The database owner temporarily adopts Mary's identity in the database in order to grant Joe permissions on `authors`, a table owned by Mary:

```
setuser "mary"  
go  
grant select on authors to joe  
setuser  
go
```

## Usage

- The database owner uses `setuser` to adopt the identity of another user in order to use another user's database object, to grant permissions, to create an object, or for some other reason.
- Except for sessions run by login account "sa," when the database owner uses the `setuser` command, the SAP ASE server checks the permissions of the user being impersonated instead of the permissions of the database owner. The user being impersonated must be listed in the `sysusers` table of the database.
- `setuser` affects permissions only in the local database. It does not affect remote procedure calls or accessing objects in other databases.
- `setuser` remains in effect until another `setuser` command is given or until the current database is changed with the `use` command.
- `setuser` has no effect when creating a database.
- Executing `setuser` with no user name reestablishes the database owner's original identity.
- System administrators can use `setuser` to create objects that are owned by another user. However, since system administrators operates outside the permissions system, they cannot use `setuser` to acquire another user's permissions.
- You cannot use the `setuser` command:
  - When you create a new procedure using the `with execute as owner` option.
  - With an existing stored procedure, or a stored procedure that was upgraded from an earlier version of SAP ASE, that includes `with execute as owner`.

## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

## Permissions

The permission checks for `setuser` differ based on your granular permissions settings.

Setting	Description
Enabled	With granular permissions enabled, you must have <code>setuser</code> privilege to run <code>setuser</code> . <code>setuser</code> privilege is granted to the database owner by default.
Disabled	With granular permissions disabled, <code>setuser</code> privilege defaults to the database owner and is not transferable.

## Auditing

You can enable `setuser` auditing option to audit this command. Values in `event` and `extrainfo` columns from the `sysaudits` table are:

Information	Value
Audit option	setuser
Event	84
Command or access audited	setuser
Information in <code>extrainfo</code>	<ul style="list-style-type: none"> <li>• <b>Roles</b> – current active roles</li> <li>• <b>Keywords or options</b> – NULL</li> <li>• <b>Previous value</b> – NULL</li> <li>• <b>Current value</b> – NULL</li> <li>• <b>Other information</b> – Name of the user being set</li> <li>• <b>Proxy information</b> – original login name, if <code>set proxy</code> is in effect</li> </ul>

Example of `extrainfo` after executing `setuser`:

```
sa_role sso_role oper_role sybase_ts_role
mon_role; ; ; ; user1; ; sa/ase;
```

For more information about auditing, see *Security Administration Guide > Auditing*.

## Related Information

[grant \[page 520\]](#)

[revoke \[page 672\]](#)

[use \[page 850\]](#)

## 1.118 shutdown

Shuts down the SAP ASE server from which the command is issued, its local Backup Server, or a remote Backup Server.

### Syntax

```
shutdown [<srvname>] [with {wait[="<hh:mm:ss>"] | nowait}]
```

(Cluster Edition) Syntax for clusters:

```
shutdown {cluster | [<instance_name>]} [with {wait | nowait}]
```



## Parameters

**<srvname>**

is the logical name by which the Backup Server is known in the SAP ASE `sys.servers` system table. This parameter is not required when shutting down the local SAP ASE server.

**with wait**

is the default. This shuts down the SAP ASE server or Backup Server gracefully.

**<hh:mm:ss>**

is an optional setting that specifies the maximum time the server waits for all running or sleeping processes to finish their job.

**with nowait**

shuts down the SAP ASE server or Backup Server immediately, without waiting for currently executing statements to finish.

### ⚠ Caution

Use `shutdown with nowait` only in extreme circumstances. In the SAP ASE server, issue a `checkpoint` command before executing a `shutdown with nowait`. Use of `shutdown with nowait` can lead to gaps in IDENTITY column values.

**cluster**

(shared disk clusters only) specifies that all instances in the cluster are to shut down.

**<instance\_name>**

(Cluster Edition shared disk clusters only) is the name of a specific instance to shut down.

## Examples

### Example 1

Shuts down the SAP ASE server from which the `shutdown` command is issued:

```
shutdown
```

### Example 2

Shuts down the SAP ASE server immediately:

```
shutdown with nowait
```

### Example 3

Shuts down the local Backup Server:

```
shutdown SYB_BACKUP
```

#### Example 4

Shuts down the remote Backup Server REM\_BACKUP:

```
shutdown REM_BACKUP
```

#### Example 5

Shuts down the current cluster:

```
shutdown cluster
```

#### Example 6

Shuts down the instance "ase1", but leaves the cluster running:

```
shutdown ase1
```

## Usage

- Unless you use the `nowait` option, `shutdown` attempts to bring the SAP ASE server down gracefully by:
  - Disabling logins (except for the system administrator)
  - Performing a checkpoint in every database
  - Waiting for currently executing SQL statements or stored procedures to finish

### i Note

Attempting a normal shutdown on a dataserver does not terminate batches of SQL that include infinite looping and Transact-SQL that include `waitfor delay` commands.

Shutting down the server without the `nowait` option minimizes the amount of work that must be done by the automatic recovery process.

A graceful shutdown waits for the currently executing statement to complete, under the assumption that many statements are atomic transactions that commit on completion. However, a graceful shutdown does not wait for a longer transaction to commit if the session would go into "awaiting command" state within a transaction. Instead, shutdown commences and the transaction rolls back on recovery.

You should check the `master..syslogshold` table for any long-running open transaction and deal with it before you issue a shutdown. You may deal with such transactions by contacting the users running them to see they can commit the transactions, or kill them and wait for a rollback. Rolling back an active transaction is faster before a shutdown rather than after recovery, as many pages may still be in cache, and there is less scanning of the log involved. If there are multiple long-running transaction, check `syslogshold` repeatedly until you see no very old transactions.

### i Note

Shutting down with a long-running open transaction on the server can result in a lengthy recovery time.

- After a polite or impolite shutdown, SAP ASE guarantees full recoverability of in-memory row storage-enabled databases and their contents. The contents of in-memory row storage-enabled databases is restored to the last committed transaction prior to an impolite shutdown.

- Unless you use the `nowait` option, `shutdown <backup_server>` waits for active dumps and loads to complete. Once you issue a `shutdown` command to a Backup Server, no new dumps or loads that use this Backup Server can start.
- You can halt only the local SAP ASE server with `shutdown`; you cannot halt a remote SAP ASE server.
- You can halt a Backup Server only if:
  - It is listed in your `sys.servers` table. Use `sp_addserver` to add entries to `sys.servers`.
  - It is listed in the interfaces file for the SAP ASE server where you execute the command.
- Use `sp_helpserver` to determine the name by which a Backup Server is known to the SAP ASE server. Specify the Backup Server's name — not its `<network_name>` — as the `<srvname>` parameter. For example:

```
sp_helpserver
```

name	network_name	status	id
REM_BACKUP	WHALE_BACKUP	timeouts, no net password encryption	3
SYB_BACKUP	SLUG_BACKUP	timeouts, net password encryption	1
eel	eel		0
whale	whale	timeouts, no net password encryption	2

To shut down the remote Backup Server named WHALE\_BACKUP, use:

```
shutdown REM_BACKUP
```

In a clustered environment, the `shutdown` command with no options is invalid in a clustered environment, as for example:

```
shutdown
go
```

See also `sp_addserver`, `sp_helpserver` in *Reference Manual: Procedures*.

## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

## Permissions

The permission checks for `shutdown` differ based on your granular permissions settings.

### Setting Description

**Enabled** With granular permissions enabled:

- To shutdown a SMP server, a cluster instance, or a backup server, you must be a user with `shutdown` privilege.

**Setting**    **Description**

- To shutdown a cluster, you must be a user with `shutdown privilege` and `manage cluster privilege`.

**Disabled** With granular permissions disabled, you must be a user with `sa_role`.

## Auditing

You can enable `security` auditing option to audit this command. Values in `event` and `extrainfo` columns from the `sysaudits` table are:

Information	Value
Audit option	<code>security</code>
Event	64
Command or access audited	Server shutdown
Information in <code>extrainfo</code>	<ul style="list-style-type: none"><li>• <b>Roles</b> – current active roles</li><li>• <b>Full command text</b> – full text of <code>shutdown</code> command</li><li>• <b>Previous value</b> – NULL</li><li>• <b>Current value</b> – NULL</li><li>• <b>Other information</b> – NULL</li><li>• <b>Proxy information</b> – original login name, if <code>set proxy</code> is in effect</li></ul>

Example of `extrainfo` after shutting down a server:

```
sa_role sso_role oper_role sybase_ts_role mon_role; shutdown; ; ; ; ;
sa/ase;
```

For more information about auditing, see *Security Administration Guide > Auditing*.

## Related Information

[alter database \[page 14\]](#)

[checkpoint \[page 120\]](#)

## 1.118.1 Specifying a Wait Time

When you use `with wait` with the `<hh:mm:ss>` option, the time you specify is not the maximum total time the server takes to shut itself down. Instead, the server takes into account the time it takes to perform the first `checkpoint`, and automatically subtracts this from the time you specified.

For example, if you specify a maximum wait time of 20 minutes and the first `checkpoint` takes 3 minutes, the server allows up to 17 minutes for the processes to finish. If for some reason the second `checkpoint` takes longer, however, this is not calculated into the `with wait <hh:mm:ss>` parameter you specify.

The server also accommodates a `checkpoint` that takes longer than the time you specify in `with wait <hh:mm:ss>`. For example, if you specify a wait time of 10 minutes but the first `checkpoint` takes 20 minutes to complete, the server does not interrupt `checkpoint` midway, but instead waits for `checkpoint` to complete. When this occurs, the server immediately begins to shut down after `checkpoint` is complete, since the time you specified has passed, and runs the last `checkpoint` with the flag informing you of the flushes you must perform.

The server performs a number of tasks as it prepares to shut down:

1. Performs `checkpoint` on all the databases
2. Prevents any new user from logging in
3. Waits for all running or sleeping processes to finish their job
4. Performs another `checkpoint` on the databases, this time with a flag that informs you that you need to flush:
  - All the dynamic thresholds in mixed log-data databases
  - All the object statistics
  - The values of the identity fields to avoid holes after recovery

## 1.119 transfer encryption key

You can encrypt master and dual master encryption keys with user passwords and export them into a file, then import them at the target SAP ASE from the file by specifying the same user passwords. Importing the master key creates master key that is encrypted with the same user password. You should alter the master key to re-encrypt with the HSM key configured on the target system or with a new user password.

### Syntax

```
transfer encryption key [dual] master
  with password 'password'
  {to | from} destination_file
  [with override]
```

## Parameters

### [dual] master

specifies the database-level keys used to encrypt other keys within the database in which they are defined. These keys are not used to encrypt data.

### with passwd '<password>'

specifies the password used to encrypt and decrypt the key when importing and exporting.

### to | from

specifies whether you are exporting the key to the destination file or importing it from the destination file.

### <destination\_file>

specifies the file or path name to export or import the master key. The file or path name should be accessible to the SAP ASE server.

### with override

is only applicable when importing; specify it if a key already exists. SAP ASE reports an error if a key exists, and you don't specify this clause.

If there are keys that are encrypted with a key being imported, SAP ASE performs a validation to ensure the imported key can decrypt the existing keys encrypted with it.

Any key copies of the master or dual master key being imported are dropped.

## Example

This example migrates a database containing a master key encrypted with external key from source to target SAP ASE and encrypts the master key with the HSM key in the target SAP ASE.

At the source SAP ASE:

```
use master
dump database src_db
  to '/path/to/dumpfile'
use src_db
transfer encryption key master
  with password 'mysecret8'
  to '/path/to/file'
```

At the target SAP ASE:

```
use master
create encryption key hsm_key
  on external keystore
load database target_db
  from '/path/to/dumpfile'
online database target_db
use target_db
transfer encryption key master
  with password 'mysecret8'
```

```

    from '/path/to/file'
    with override
alter encryption key master
    with password 'mysecret8'
    modify encryption with external key

```

## 1.120 transfer table

Initiates an incremental table transfer.

### Syntax

```

transfer table [[<db>.<owner>.<table>] [to | from] <destination_file>
  [for { ase | bcp | iq | csv }]
  [with {column_separator=<string>}, {column_order=<option>},
  {encryption=<option>}, {row_separator=<string>},
  {resend=<id>}, {progress=<sss>}, {tracking_id=<nnn>}
  {sync = true | false}], {fixed_length = true | false},
  null_byte = true | false}]

```

### Parameters

#### <table>

is any valid table within the SAP ASE server. `transfer table` requires `sa_role`, or ownership of the table. Table owners can grant `transfer table` privileges for tables they own.

#### to | from

indicates the direction of the transfer. You cannot use all the parameters for the `transfer table...from` that you use with `transfer table...to`. The parameters for the `from` parameter are:

- `column_order=<option>` (does not apply to a load using `for ase`; reserved for future use)
- `column_separator=<string>` (does not apply to a load using `for ase`; reserved for future use)
- `encryption={true | false}` (does not apply to a load using `for ase`; reserved for future use)
- `progress=<nnn>`
- `row_separator=<string>` (does not apply to a load using `for ase`; reserved for future use)

#### <destination\_file>

- 16.0 SP02 PL03 and earlier – write to any file or path name that is valid for the operating system, and that the SAP ASE server can access. If the file is a relative file path, the SAP ASE server provides its absolute path. If the SAP ASE server cannot open `<destination_file>`, it issues an error message. The SAP ASE server removes a destination file if all these conditions apply:
  - The file is a regular file, not a named pipe, symbolic link, or other special file.
  - The SAP ASE server opens the file as part of this transfer.
  - The transfer fails, or sends no rows.
- 16.0 SP02 PL04 and later – write output files only to a defined output directory tree rather than to any directory writable by the running server. See *Reference Manual: Procedures > sp\_file\_path*.

**for {ase | bcp | iq | csv}**

names one of the destination data formats. If you omit the `for` clause, the default value of the first transfer of a specified table is `for ase`. Subsequent transfers default to the format used by the previous successful transfer, unless the command specifies format with `resend = id`, in which case the default is the specified prior transfer format.

- `ase` – a format for importing data into the SAP ASE server. This output format is a licensed feature, available to RAP customers and to customers with licenses for in-memory databases. No data transformations are applied. This file format includes a header that describes the table, including the source computer's byte order, character set, and default sort order. This is the default value for tables that have had no successful prior transfers.
- `bcp` – a format for importing data as `bcp` binary-formatted data. Rows are output as binary data that can be loaded using `bcp`. No data transformations are applied. As part of the transfer, the SAP ASE server creates a format file that `bcp` uses to describe the data and appears in the same directory as the output file. You cannot use `for bcp` to transfer to a named pipe. If the output file is any file type other than a named pipe, the SAP ASE server uses this naming convention for the format file:

```
{<table_name>},{<database_id>},{<object_id>}.fmt
```

- `iq` – writes data in a form suitable for loading into SAP IQ using IQ's `load table` command. The SAP ASE server writes data to the file in a binary format, and applies any necessary data transformations to convert its datatypes to versions that are compatible with IQ. Unless you include the `with fixed_length='true'` or `with null_byte='true'` modifiers, `for iq` writes data in a default format, which is nullable data that includes a following "null byte," a one-byte indicator containing a:
  - 0 if the column is not null
  - 1 if the column is null
 Non-nullable data does not include this null byte (see IQ's documentation for `load table`). Variable-length strings are preceded by one or two bytes indicating the length of the string, where the number of prefix bytes is determined by the column's maximum length: one byte for strings up to 255 bytes, or two bytes for strings 256 bytes or longer (SAP ASE supports strings up to about 16000 bytes). Except for strings, every column is transmitted as a fixed width, padded if necessary to expand it to this fixed-width size.



Use these modifiers to determine the data's format:

- `with fixed_length='true'` – all columns, including strings, are padded to their full width. Strings are padded with blanks; other columns are padded with `<NUL>` or `0x00`. No column has a length indicator
- `with null_byte='true'` – all columns must have a null byte, whether or not the column is nullable. This qualifier forces `for iq` to use the `fixed_length='true'` modifier, regardless of what the command specifies

### **i** Note

The SAP ASE `datetime` format in binary differs from the IQ `timestamp` format in binary. For this reason, do not use the `transfer table` command's `for iq` clause if you have any date- or time-related fields in either the ASE or IQ table. Doing so causes the transfer to fail, and you see an error message.

- `csv` – a format of character-coded values. Rows are output as character-coded data. Columns are separated by a designated column separator, and rows are terminated by a designated row terminator. Separators and terminators are user-defined.

#### **with clause**

provides options that modify the command's operation.

#### **column\_separator = <string>**

declares a string written between output columns in `csv` format, replacing the default. The string written for subsequent transfers defaults to the previously specified `column_separator`.

#### **column\_order= <option>**

declares the order in which column data is written to the output. These options are:

- `id` – order by column ID, as given in `syscolumns`. This is the only acceptable column order when the transfer is `for bcp`, and is the default value for those transfers.
- `name` – order by column name as given in `syscolumns`, using the SAP ASE server's current character set and sort order.
- `name_utf8` – order by column name as given in `syscolumns`, translating the column name to UTF8 characters before sorting.
- `offset` – order by column offset within the data row. This is the only acceptable column order when the transfer is `for ase`, and is the default value for those transfers.

The SAP ASE server issues an error message if you use a `column_order` that does not match the `for` clause format. The column orders are:

- `for ase` – use the `offset` column order
- `for bcp` – use the `id` column order

#### **encryption = <option>**

specifies how the command handles encrypted columns. Options are:

- `true` – decrypt columns before transmission. This is the default value. The user must have permission to decrypt any encrypted columns.

- `false` – transmit columns encrypted exactly as they appear in the data row.

### i Note

To recover the data, the receiver must know the encryption key and algorithm used to encrypt it. If the SAP ASE server writes encrypted data to a file, it writes the data as it was encrypted when it was first stored in the table. Transferring the data does not alter it. To recover that data, the receiver must know the key that encrypted the data, and any special features of the encryption algorithm (for example, whether it used an initialization vector).

**progress = <sss>**

indicates that the transfer should generate progress messages every <sss> seconds during its operation. The default is to omit progress messages.

**row\_separator = <string>**

declares a string to be written at the end of each output row in `csv` format, replacing the default. This option has no effect unless the transfer is `for csv`. As with `column_separator`, the default for all transfers in `csv` mode after the first is the default value of the most recent successful transfer. The default row separator is platform-dependent: a line feed (`Ctrl` + `J`) on Linux and UNIX, or a carriage return and line feed (`Ctrl` + `M` `Ctrl` + `J`) on Windows.

**resend = <id>**

identifies a history entry from a table whose sequence ID column obtains the starting timestamp for this data transfer. This option resends previously sent data. `resend = <id>` is ignored unless the table named in the command is marked for incremental transfer. If the specified `sequence ID` does not exist for this table, the SAP ASE server resends the entire table.

The SAP ASE server selects the indicated entry's starting timestamp as the starting timestamp for this transfer, and the indicated entry's destination type (`ase`, `bcp`, and so on) as the transfer's default destination type.

Negative values for `id` retrieve history entries for previously completed successful transfers of the specified table. -1 names the most recently complete successful transfer, -2 the next most recent, and so forth. The transfer history table stores entries for both successful and failed transfers.

**tracking\_id = <nnn>**

specifies an optional integer identifier that helps track a given transfer. Use the `spt_TableTransfer.tracking_id` column to determine the value for <nnn> and use the value in queries. This example returns the ending status and sequence ID of tracking ID number 123, along with the complete path to the output data file (returns NULL if these values do not exist):

```
select end_code, sequence_id, pathname from spt_TableTransfer
where id = object_id('mytable') and tracking_id = 123
```

The SAP ASE server does not control the `tracking_id` or require that it be unique.

### i Note

This tracking ID is not the sequence ID used for `resend =<id>`.

#### `sync = true | false`

determines how the transfer reacts with transactions. Options are:

- `true` – the transfer is synchronized so that rows from the table included in the transfer are captured as a group. `transfer` waits until all transactions affecting this table end before it starts. New transactions that affect this table cannot modify the table while `transfer` waits to start. Instead, they wait until `transfer` begins. While `transfer` is in progress, transactions cannot modify rows in this table until they are inspected by `transfer`.
- `false` – the transfer is not synchronized. `transfer` sends rows that are within the selected timestamp range, regardless of whether it can send other rows from the table. This is the default behavior.

### i Note

`sync` affects only the tables you are transferring. `transfer` does not consider cross-table constraints.

#### `fixed_length = true | false`

determines whether `transfer...for iq` transfers all columns as fixed-length fields in the output file. Typically, the SAP ASE server transfers varying-length strings with a 1- or 2-byte prefix length. Setting `fixed_length` to `true` causes the SAP ASE server to pad strings with blanks until they reach column's maximum width. You must use the `padding` parameter with the `for iq` parameter. Setting `fixed_length` to:

- `true` – the SAP ASE server pads strings to their full width instead of using a prefix length.
- `false` – the SAP ASE server sends the string using the default behavior—sending the string with the prefix length.

#### `null_byte = true | false`

determines whether `transfer...for iq` appends a byte to the end of each transmitted column, indicating whether the column is null. Typically, the SAP ASE server provides this byte only for nullable columns. Options are:

- `true` – the SAP ASE server includes a null byte at the end of all columns—0 if the column is null, 1 if it is not—whether or not the column is nullable. `true` forces `for iq` to use the `fixed_length='true'` modifier, regardless of what you specified with the `transfer` command.
- `false` – the SAP ASE server provides a null byte only for nullable columns.

### i Note

Regardless of whether it is set to `true` or `false`, `null_byte` only applies to transfers that include `for iq` clause.

## Examples

### Example 1

Grants permission for user "john" to transfer table `mytable`:

```
grant transfer table on mytable to john
```

### Example 2

Transfers `mytable` to an output file, formatted for loading into SAP IQ. If this example did not include `name_utf8`, the default order would default to the column ID order:

```
transfer table mytable to '/path/to/file' for iq  
with column_order = 'name_utf8'
```

### Example 3

Transfers `mytable`, formatted for the SAP ASE file format, which uses a column output order of `offset`. This example requests `resend` from a history entry that does not exist; therefore, the entire table is transferred:

```
transfer table mytable to '/path/to/file3/' for ase  
with resend=10
```

The example changes the default column order for a `for ase` transfer. After the transfer, the default receiver is `ase`, the column order is `offset`, and column and row separators are null.

## Usage

- `transfer table` sends only committed data that has changed since the previous transfer.
- The `<string>` argument to `column_separator` and `row_separator` in the `with` clause may be up to 64 bytes long, and may contain formatting instructions:
  - `"\b"` indicates a backspace, `<BS>` (`[Ctrl]` + `[H]`).
  - `"\n"` indicates a newline, `<LF>` (`[Ctrl]` + `[J]`).
  - `"\r"` indicates a carriage return, `<CR>` (`[Ctrl]` + `[M]`).
  - `"\t"` indicates a `<TAB>` (`Ctrl+I`).
  - `"\"` indicates a backslash.
  - Any `"\"` in the string that is not part of one of these sequences is an actual backslash, and appears as such in the string.
- `transfer table .. from` does not fire triggers during updates or inserts.
- `transfer table` is not supported on in-memory row storage-enabled databases.
- When `transfer table` runs into an error (such as a duplicate key), the SAP ASE server displays just an error number, making it difficult to understand the cause of the error. For example:

```
Msg 2633, Level 20, State 1  
Server 'SYB155', Line 1  
TRANSFER TABLE failed to insert a row to table 'my_tab'.  
The indicated error was 2601.  
Msg 16025, Level 16, State 1  
Server 'SYB155', Line 1
```

```
TRANSFER TABLE my_tab: command failed with status 2633.
```

To retrieve the error message, manually query `master..sysmessages`. For example, if 2601 is your error number, enter:

```
select * from master..sysmessages where error = 2601
```

You can use `transfer table` for tables that are not marked for incremental transfer, with these restrictions:

- Not all rows are always transferred. If a user updates the table while the transfer is in progress, the updated rows may not be transferred.
- The transfer is not incremental; you can transfer only the entire table, and later transfers are not notified of this transfer.
- No history entry is written to `spt_TableTransfer`. The transfer appears in `monTableTransfer` for the duration of the transfer, but once the transfer is complete the record vanishes.

## Permissions

Permission to transfer a table does not automatically grant permission to decrypt data within that table. To decrypt any encrypted columns, you must gain specific permission from the table owner.

The following describes permission checks for `transfer table` that differ based on your granular permissions settings.

Setting	Description
---------	-------------

<b>Enabled</b>	With granular permissions enabled, you must be the table owner or a user with <code>transfer table</code> permission on the table.
----------------	--

<b>Disabled</b>	With granular permissions disabled, you must be the table owner, be a user with <code>transfer table</code> permission, or a user with <code>sa_role</code> .
-----------------	---

## Auditing

You can enable `transfer_table` auditing option to audit this command. Values in `event` and `extrainfo` columns from the `sysaudits` table are:

Information	Value
Audit option	<code>transfer_table</code>
Event	136
Command or access audited	<code>transfer table</code>
Information in <code>extrainfo</code>	<ul style="list-style-type: none"><li>• <b>Roles</b> – current active roles</li><li>• <b>Full command text</b> – full text of <code>transfer table</code> command</li></ul>

## Information

## Value

- **Previous value** – NULL
- **Current value** – NULL
- **Other information** – NULL
- **Proxy information** – original login name, if `set proxy` is in effect

Full command text is included in `extrainfo`. For example:

```
sa_role sso_role oper_role sybase_ts_role mon_role;  
transfer table t2 '/dev/quasrl' for ase; ; ; ; sa/ase;
```

For more information about auditing, see *Security Administration Guide > Auditing*.

## Related Information

[alter table \[page 70\]](#)

[create table \[page 273\]](#)

## 1.121 truncate lob

Truncates an LOB to a specified length.

## Syntax

```
truncate lob <locator_descriptor> [(<result_length>)]
```

## Parameters

**<locator\_descriptor>**

is a valid locator: a host variable, a local variable, or the literal binary value of a locator.

**<result\_length>**

is a length, in characters, for `text` and `unitext` locators, and in bytes for `image` locators.

## Examples

### Example 1

<@w> to 20 characters:Truncates the LOB referenced by text locator

```
truncate lob @w (20)
```

## Usage

If <result\_length>Truncates the LOB referenced by text locator is not specified or is 0 (zero), the SAP ASE server deallocates the LOB memory, and points the locator to a null LOB.

See also `locator_valid`, `return_lob`, `create_locator` in *Reference Manual: Building Blocks* .

## Permissions

Any user can execute `truncate lob`.

## Auditing

This command is not audited.

## Related Information

[deallocate locator \[page 381\]](#)

## 1.122 truncate precomputed result set

Truncates the data in a precomputed result set.

## Syntax

```
truncate {precomputed result set | materialized view}
```

```
[<owner_name>.]<prs_name>
```

## Parameters

**precomputed result set | materialized view**

specifies whether to truncate the data in a materialized view or precomputed result set.

**<owner\_name>**

is the name of the owner.

**<prs\_name>**

is the name of the precomputed result set. A fully qualified **<prs\_name>** cannot include the server or database name.

## Examples

### Example 1

Truncates the `authors_prs` precomputed result set:

```
truncate precomputed result set authors_prs
```

## Usage

`truncate precomputed result set` automatically alters the precomputed result set to `disable`. To reenble the precomputed result set, issue `refresh precomputed result set`.

## Permissions

You must be the precomputed result set owner to run `truncate precomputed result set`.

## Auditing

This command is not audited.



## 1.123 truncate table

Removes all rows from a table or partition.

### Syntax

```
truncate table [[<database>.]<owner>.]<table_name>  
[partition <partition_name>]
```

### Parameters

**[<database>.]<owner>.]<table\_name>**

is the name of the table to truncate. Specify the database name if the table is in another database, and specify the owner's name if more than one table of that name exists in the database. The default value for `<owner>` is the current user, and the default value for `<database>` is the current database.

**partition <partition\_name>**

specifies the name of the partition to truncate.

### Examples

#### Example 1

Removes all data from the `authors` table:

```
truncate table authors
```

#### Example 2

Removes all data from the `smallsales` partition of the `titles` table:

```
truncate table titles partition smallsales
```

### Usage

- `truncate table` deletes all rows from a table. The table structure and all the indexes continue to exist until you issue a `drop table` command. The rules, defaults, and constraints that are bound to the columns remain bound, and triggers remain in effect.

- You may issue `truncate table` on in-memory row storage-enabled tables. Once the data rows in the in-memory row storage-enabled are deleted, a background housekeeper process reclaims their memory after the `truncate table` operation commits. If the amount of available memory falls below critical thresholds, the housekeeper process attempts memory reclamation immediately following a completed `truncate table`. All indexes, if any, are also truncated.
- You cannot include the `truncate table ... with online` parameter on IMRS-enabled databases.
- The SAP ASE server no longer uses distribution pages; statistical information is now stored in the tables `sysstatistics` and `systabstats`.  
During `truncate table`, statistical information is no longer deleted (deallocated), so you need not run `update statistics` after adding data.  
`truncate table` does not delete statistical information for the table.
- `truncate table` is equivalent to—but faster than—a `delete` command without a `where` clause. `delete` removes rows one at a time and logs each deleted row as a transaction; `truncate table` deallocates whole data pages and makes fewer log entries. Both `delete` and `truncate table` reclaim the space occupied by the data and its associated indexes.
- Truncating a partition does not affect the data in other partitions.
- You can truncate only one partition at a time.
- Truncating a table locks the entire table until the truncation process is complete.
- Because the deleted rows are not logged individually, `truncate table` cannot fire a trigger.
- You cannot use `truncate table` if another table has rows that reference it. Delete the rows from the foreign table, or truncate the foreign table, then truncate the primary table.
- You can grant and revoke permissions to users and roles to use `truncate table` on tables with the `grant` and `revoke` commands.
- You cannot use `truncate table <table_name> partition <partition_name>` when the table object is marked for replication and is created using hash- or round-robin-based partitions. Doing so returns a message similar to:

```
Msg 4725, Level 20, State 1:
Server 'SYBASE_161', Line 1:
Cannot truncate partition 'tpart_1216004332' of table 'tpart' because this
command
is not allowed when replication is enabled on a hash or round-robin
partitioned table.
```

This happens because inserted data into such a table is replicated, but it is not guaranteed that the inserted data is in the same partition as stored on the primary datasever. A `truncate table` with a partition clause could therefore result in the primary database being out of sync with the replicate database.

## Standards

ANSI SQL – Compliance level: Entry-level compliant.

## Permissions

The permission checks for `truncate table` differ based on your granular permissions settings.

## Setting Description

**Enabled** With granular permissions enabled, you must be the table owner or a user with `truncate table` permission on the table. To truncate an auditing table, you must have `manage auditing privilege` or `truncate any audit table` privilege.

**Disabled** With granular permissions disabled, you must be the table owner, a user with `truncate table` permission on the table, a user with `replication_role`, or a user with `sa_role`. To truncate an auditing table, you must be a user with `sso_role`.

## Auditing

You can enable `truncate` auditing option to audit this command. Values in `event` and `extrainfo` columns from the `sysaudits` table are:

Information	Value
Audit option	<code>truncate</code>
Event	64
Command or access audited	<code>truncate table</code>
Information in <code>extrainfo</code>	<ul style="list-style-type: none"><li>• <b>Roles</b> – current active roles</li><li>• <b>Full command text</b> – full text of <code>truncate table</code> command</li><li>• <b>Previous value</b> – NULL</li><li>• <b>Current value</b> – NULL</li><li>• <b>Other information</b> – NULL</li><li>• <b>Proxy information</b> – original login name, if <code>set proxy</code> is in effect</li></ul>

Full command text is included in `extrainfo`. For example:

```
sa_role sso_role oper_role sybase_ts_role mon_role;  
truncate table t2; ; ; ; sa/ase;
```

For more information about auditing, see *Security Administration Guide > Auditing*.

## Related Information

- [alter table \[page 70\]](#)
- [create table \[page 273\]](#)
- [delete \[page 391\]](#)
- [drop table \[page 457\]](#)
- [grant \[page 520\]](#)
- [revoke \[page 672\]](#)

## 1.124 union operator

Returns a single result set that combines the results of two or more queries. Duplicate rows are eliminated from the result set unless the `all` keyword is specified.

### Syntax

```
select [top <unsigned_integer>] <select_list>
    [into <clause>] [from <clause>] [where <clause>]
    [group by <clause>] [having <clause>]
    [union [all]
select [top <unsigned_integer>] <select_list>
    [from <clause>] [where <clause>]
    [group by <clause>] [having <clause>] ]...
    [order by <clause>]
    [compute <clause>]
    [limit <clause>]
```

### Parameters

#### `top <unsigned_integer>`

The top limit applies to the individual selects that form a union, not to the union as a whole.

#### `into`

creates a new table based on the columns specified in the select list and the rows chosen in the `where` clause. The first query in the union operation is the only one that can contain an `into` clause.

#### `union`

creates the union of data specified by two `select` statements.

#### `all`

includes all rows in the results; duplicates are not removed.

### Examples

#### Example 1

The result set includes the contents of the `stor_id` and `stor_name` columns of both the `sales` and `sales_east` tables:

```
select stor_id, stor_name from sales
union
select stor_id, stor_name from sales_east
```

### Example 2

The `into` clause in the first query specifies that the `results` table holds the final result set of the union of the specified columns of the `publishers`, `stores`, and `stores_east` tables:

```
select pub_id, pub_name, city into results
from publishers
union
select stor_id, stor_name, city from stores
union
select stor_id, stor_name, city from stores_east
```

### Example 3

First, the union of the specified columns in the `sales` and `sales_east` tables is generated. Then, the union of that result with `publishers` is generated. Finally, the union of the second result and `authors` is generated:

```
select au_lname, city, state from authors
union
((select stor_name, city, state from sales
union
select stor_name, city, state from sales_east)
union
select pub_name, city, state from publishers)
```

### Example 4

Returns six rows. The top limit applies to the individual `select` statements that form a union, not to the union as a whole:

```
select top 3 au_lname from authors
union all
select top 3 title from titles
```

### Example 5

Skips two rows from the beginning of the `union all` result set, and returns, at most, 10 rows:

```
select au_lname from authors
union all
select title from titles rows limit 10 offset 2
```

### Example 6

Returns 10 rows selected from `titles` and all rows selected from `authors`:

```
(select au_lname from authors)
union all
(select title from titles rows limit 10)
```

### Example 7

Returns at most, eight rows, from `mytab1` and `mytab2`, and three rows from `mytab1`.

```
(select a, b from mytab1 rows limit 3)
union
(select c, d from mytab2) rows limit 8
```

## Usage

- You cannot use:
  - The `union` operator in a subquery
  - The `union` operator with the `for browse` clause
  - An identity function in a `select into` statement with the `union` operator.
- The maximum number of subqueries within a single side of a `union` is 250.
- The total number of tables that can appear on all sides of a `union` query is 256.
- You can use `union` in `select` statements. For example:

```
create view
select * from Jan1998Sales
union all
select * from Feb1998Sales
union all
```

- The `order by` and `compute` clauses are allowed only at the end of the `union` statement to define the order of the final results or to compute summary values.
- You can only use the `group by` and `having` clauses within individual queries; you cannot use them to affect the final result set.
- You can use the `limit` clause either in individual queries or in the final result set. If an individual query contains the `limit` clause, put all queries in parentheses. For example:

```
((select a, b from mytab1 rows limit 3 offset 5)
union
(select c, d from mytab2 rows limit 8) rows limit 5 offset 6)
union
(select e, f from mytab3 rows limit 4 offset 3) rows offset 2 limit 3
```

- The default evaluation order of a SQL statement containing `union` operators is left to right.
- Since `union` is a binary operation, you add parentheses to an expression involving more than two queries to specify evaluation order.
- The first query in a `union` statement may contain an `into` clause that creates a table to hold the final result set. The `into` statement must be in the first query, or you receive an error message (see Example 2).
- The `union` operator can appear within an `insert...select` statement. For example:

```
insert into sales.overall
select * from sales
union
select * from sales_east
```

- All `select` lists in a SQL statement must have the same number of expressions (column names, arithmetic expressions, aggregate functions, and so on). For example, the following statement is not valid because the first `select` list contains more expressions than the second:

```
/* Example of invalid command--shows imbalance */ /* in select list items */
select au_id, title_id, au_ord from titleauthor
union
select stor_id, date from sales
```

- Corresponding columns in the `select` lists of `union` statements must occur in the same order, because `union` compares the columns one-to-one in the order given in the individual queries.
- The column names in the table resulting from a `union` are taken from the *first* individual query in the `union` statement. To define a new column heading for the result set, do it in the first query. Also, to refer to

a column in the result set by a new name (for example, in an `order by` statement), refer to it by that name in the first `select` statement. For example, the following query is correct:

```
select Cities = city from stores
union
select city from stores_east
order by Cities
```

- The descriptions of the columns that are part of a `union` operation need not be identical. The rules for the datatypes and the corresponding column in the result table are:

Table 9: Resulting Datatypes in Union Operations

Datatype of Columns in <code>union</code> Operation	Datatype of Corresponding Column in Result Table
Not datatype-compatible (data conversion is not handled implicitly by the SAP ASE server)	Error returned by the SAP ASE server.
Both are fixed-length character with lengths L1 and L2	Fixed-length character with length equal to the greater of L1 and L2.
Both are fixed-length binary with lengths L1 and L2	Fixed-length binary with length equal to the greater of L1 and L2.
Either or both are variable-length character	Variable-length character with length equal to the maximum of the lengths specified for the column in the union.
Either or both are variable-length binary	Variable-length binary with length equal to the maximum of the lengths specified for the columns in the union.
Both are numeric datatypes (for example, <code>smallint</code> , <code>int</code> , <code>float</code> , <code>money</code> )	A datatype equal to the maximum precision of the two columns. For example, if a column in table A is of type <code>int</code> and the corresponding column in table B is of type <code>float</code> , then the datatype of the corresponding column of the result table is <code>float</code> , because <code>float</code> is more precise than <code>int</code> .
Both column descriptions specify NOT NULL	Specifies NOT NULL.

See also `convert` in *Reference Manual: Building Blocks*.

## Standards

ANSI SQL – Compliance level: Entry-level compliant

The following are Transact-SQL extensions:

- The use of `union` in the select clause of an `insert` statement
- Specifying new column headings in the `order by` clause of a `select` statement when the `union` operator is present in the `select` statement

## Auditing

This command is not audited.

## Related Information

[compute Clause \[page 125\]](#)

[declare \[page 382\]](#)

[group by and having Clauses \[page 558\]](#)

[order by Clause \[page 630\]](#)

[select \[page 696\]](#)

[where Clause \[page 855\]](#)

## 1.125 unmount

Shuts down the database and drops it from the SAP ASE server. The devices are also deactivated and dropped.

### ⚠ Caution

The `unmount` command removes a database and all its information from the SAP ASE server. Use the `unmount` command only when you want to remove the database from one SAP ASE server to another SAP ASE server.

## Syntax

```
unmount database <dbname_list> to <manifest_file>
```

## Parameters

### <dbname\_list>

the database being unmounted. You can `unmount` more than one database.

### <manifest\_file>

the binary file that describes the databases that are present on a set of database devices. It can be created only if the set of databases that occupy those devices are isolated and self-contained on those devices.

Since the manifest file is a binary file, operations that perform character translations of the file contents (such as `ftp`) corrupt the file unless done in binary mode.



## Examples

### Example 1

Unmounts a database from a server and creates the manifest file for the database:

```
unmount database pubs2 to "/work2/Devices/Mpubs2_file"
```

### Example 2

The encryption key created in `key_db` has been used to encrypt columns in `col_db`. These commands successfully unmount the named databases:

```
unmount database key_db, col_db
```

```
unmount database key_db with override
```

```
unmount database col_db with override
```

## Usage

- The database and its pages are not altered when they are unmounted. The database pages remain on the operating system devices. If necessary, you can disconnect and move the devices at the source SAP ASE server once the `unmount` command completes. Use the `<manifest_file>` null extension to create the manifest file for use at the secondary SAP ASE server.
- The `unmount` command limits the number of databases in a single command to eight.
- You cannot:
  - Unmount system, archived, in-memory, proxy, quiesced, `sybsystemprocs`, or temporary databases.
  - Unmount databases created with `async_init`, but for which the initialization has not yet completed.
  - Unmount databases whose encryption or decryption has not yet completed.
  - Use the `unmount` command in a transaction.
  - Unmount a database on an HA-configured server.
- `mount database` and `unmount database` are supported in the Cluster Edition. If an instance fails while one of these commands is in progress, the command may abort. In this case, the user must re-issue `mount database` or `unmount database` when the instance failover recovery is complete.
- If a database contains encrypted columns and the keys are stored in a different database, you can:
  - With encrypted columns and the database containing the keys in a single command (for example, `unmount database encr_db, keys_db to <manifest_file>`), or,
  - Using the `with override` parameter (for example, `unmount database encr_db to <manifest_file> with override`).
- If the database has referential constraints and the primary key is stored in a different database, you must:
  - Unmount the database containing the referential constraints and the one holding the keys, or,
  - Use the `with override` parameter.
- You must unmount all the database in a single command for disks that contain fragments of multiple databases.
- You can issue an `unmount` with `external dump` on servers that have mirroring enabled. However:

- Devices that are mirrored in the source server are not mirrored in the target.
- The physical file from the active disk is stored in the manifest file.
- These commands fail with an error message without the `override`:

```
unmount database key_db
```

```
unmount database col_db
```

## Standards

ANSI SQL – Compliance level: Entry-level compliant.

## Permissions

The permission checks for `unmount` differ based on your granular permissions settings.

**Setting**    **Description**

**Enabled**    With granular permissions enabled, you must be a user with `unmount any database` privilege.

**Disabled**    With granular permissions disabled, you must be a use with `sa_role`.

## Auditing

You can enable `unmount` auditing option to audit this command. Values in `event` and `extrainfo` columns from the `sysaudits` table are:

Information	Value
<b>Audit option</b>	<code>unmount</code>
<b>Event</b>	102
<b>Command or access audited</b>	<code>unmount database</code>
<b>Information in <code>extrainfo</code></b>	<ul style="list-style-type: none"> <li>● <b>Roles</b> – current active roles</li> <li>● <b>Full command text</b> – full text of <code>unmount database</code> command</li> <li>● <b>Previous value</b> – NULL</li> <li>● <b>Current value</b> – NULL</li> <li>● <b>Other information</b> – NULL</li> <li>● <b>Proxy information</b> – original login name, if <code>set proxy</code> is in effect</li> </ul>

Information Value

Full command text is included in `extrainfo`. For example:

```
sa_role sso_role oper_role sybase_ts_role mon_role;
    unmount database mount_db1 to "/qpamd6_eng4/s19484806/
m_file1"; ; ; ; sa/ase;
```

For more information about auditing, see *Security Administration Guide > Auditing*.

## Related Information

[mount \[page 620\]](#)

[quiesce database \[page 643\]](#)

## 1.126 update

Changes data in existing rows, either by adding data or by modifying existing data.

### Syntax

```
update [top <unsigned_integer>]
  [[<database>.]<owner>.]<table_name> | <view_name>
  set [[[[<database>.]<owner>.]<table_name>.|<view_name>.]
  <column_name1> =
  {<expression1> | NULL | (<select_statement>)} |
  <variable_name1> =
  {<expression1> | NULL | (<select_statement>)}
  [, <column_name2> =
  {<expression2> | NULL | (<select_statement>)}]... |
  [, <variable_name2> =
  {<expression2> | NULL | (<select_statement>)}]...
  [from [[<database>.]<owner>.]<view_name> [readpast] |
  <table_name>
  [(index {<index_name> | <table_name>}
  [prefetch size][lru|mru])]]
  [readpast]
  [, [[<database>.]<owner>.]<view_name> [readpast] | <table_name>
  [(index {<index_name> | <table_name>}
  [prefetch size][lru|mru])]]]
  [readpast] ...]
  [where search_conditions]
  [plan< >"<abstract plan>"]
```

```
update [[<database>.]<owner>.]<table_name> | <view_name>
  set [[[[<database>.]<owner>.]<table_name>.|<view_name>.]
  <column_name1> =
  {<expression1> | NULL | (<select_statement>)} |
```

```

<variable_name1> =
    {<expression1> | NULL | (<select_statement>)}
[, <column_name2> =
    {<expression2> | NULL | (<select_statement>)}]... |
[, <variable_name2> =
    {<expression2> | NULL | (<select_statement>)}]...
where current of <cursor_name>

```

## Parameters

**<table\_name> | <view\_name>**

is the name of the table or view to update. Specify the database name if the table or view is in another database, and specify the owner's name if more than one table or view of that name exists in the database. The default value for **<owner>** is the current user, and the default value for **<database>** is the current database.

**top <unsigned\_integer>**

inserts the `TOP <n>` clause immediately after the keyword, and limits the number of rows updated.

**set**

specifies the column name or variable name and assigns the new value. The value can be an expression or a NULL. When more than one column name or variable name and value are listed, they must be separated by commas.

**from**

uses data from other tables or views to modify rows in the table or view you are updating.

**readpast**

causes the `update` command to modify unlocked rows only on datarows-locked tables, or rows on unlocked pages, for datapages-locked tables. `update...readpast` silently skips locked rows or pages rather than waiting for the locks to be released.

**where**

is a standard `where` clause (see `where` clause).

**index {<index\_name> | <table\_name>}**

**<index\_name>** specifies the index to be used to access **<table\_name>**. You cannot use this option when you update a view.

**prefetch <size>**

specifies the I/O size, in kilobytes, for tables bound to caches with large I/Os configured. You cannot use this option when you update a view. `sp_helpcache` shows the valid sizes for the cache to which an object is bound or for the default cache. To configure the data cache size, use `sp_cacheconfigure`.

When using `prefetch` and designating the prefetch size (`<size>`), the minimum is 2K and any power of two on the logical page size up to 16K. `prefetch` size options in kilobytes are:

Logical Page Size	Prefetch Size Options
2	2, 4, 8 16
4	4, 8, 16, 32
8	8, 16, 32, 64
16	16, 32, 64, 128

The `prefetch` size specified in the query is only a suggestion. To allow the size specification configure the data cache at that size. If you do not configure the data cache to a specific size, the default `prefetch` size is used.

If CIS is enabled, you cannot use `prefetch` for remote servers.

#### `lru | mru`

specifies the buffer replacement strategy to use for the table. Use `lru` to force the optimizer to read the table into the cache on the MRU/LRU (most recently used/least recently used) chain. Use `mru` to discard the buffer from cache and replace it with the next buffer for the table. You cannot use this option when you update a view.

#### `where current of`

causes the SAP ASE server to update the row of the table or view indicated by the current cursor position for `<cursor_name>`.

#### `<index_name>`

is the name of the index to be updated. If an index name is not specified, the distribution statistics for all the indexes in the specified table are updated.

#### `plan "<abstract plan>"`

specifies the abstract plan to use to optimize the query. It can be a full or partial plan, specified in the abstract plan language. See *Creating and Using Abstract Plans* in the *Performance and Tuning Series: Query Processing and Abstract Plans* for more information.

## Examples

### Example 1

Changes all the McBaddens in the `authors` table to MacBaddens:

```
update authors
set au_lname = "MacBadden"
where au_lname = "McBadden"
```

### Example 2

Modifies the `total_sales` column to reflect the most recent sales recorded in the `sales` and `salesdetail` tables. This assumes that only one set of sales is recorded for a given title on a given date, and that updates are current:

```
update titles
set total_sales = total_sales + qty
from titles, salesdetail, sales
where titles.title_id = salesdetail.title_id
and salesdetail.stor_id = sales.stor_id
and salesdetail.ord_num = sales.ord_num
and sales.date in
(select max (sales.date) from sales)
```

### Example 3

Changes the price of the book in the `titles` table that is currently pointed to by `title_crshr` to \$24.95:

```
update titles
set price = 24.95
where current of title_crshr
```

### Example 4

Finds the row for which the `IDENTITY` column equals 4 and changes the price of the book to \$18.95. The SAP ASE server replaces the `syb_identity` keyword with the name of the `IDENTITY` column:

```
update titles
set price = 18.95
where syb_identity = 4
```

### Example 5

Updates the `titles` table using a declared variable:

```
declare @x money
select @x = 0
update titles
set total_sales = total_sales + 1,
  @x = price
where title_id = "BU1032"
```

### Example 6

Updates rows on which another task does not hold a lock:

```
update salesdetail set discount = 40
from salesdetail readpast
where title_id like "BU1032"
and qty > 100
```

### Example 7

```
create table t1 (c1 int, c2 int)
create index idx on t1(c1)
create procedure test_p_update @var1 INT as
begin
  update t1 set c2 = 100 where c1 = @var1 with recompile
end
exec test_p_update 10
```

## Usage

- Use `update` to change values in rows that have already been inserted. Use `insert` to add new rows.
- You can refer to as many as 15 tables in an `update` statement.
- `update` interacts with the `ignore_dup_key`, `ignore_dup_row`, and `allow_dup_row` options set with the `create index` command. See `create index` for more information.
- You can define a trigger that takes a specified action when an `update` command is issued on a specified table or on a specified column in a table.
- In pre-12.5.2 versions of SAP ASE, queries that used `update` and `delete` on views with a `union all` clause were sometimes resolved without using worktables, which occasionally lead to incorrect results. In SAP ASE 12.5.2, queries that use `update` and `delete` on views with a `union all` clause are always resolved using worktables in `tempdb`.

See also `sp_bindefault`, `sp_bindrule`, `sp_help`, `sp_helppartition`, `sp_helpindex`, `sp_unbindefault`, `sp_unbindrule` in *Reference Manual: Procedures*.

## Standards

ANSI SQL – Compliance level: Entry-level compliant.

The following are Transact-SQL extensions:

- The use of a `from` clause or a qualified table or column name are Transact-SQL extensions detected by the FIPS flagger. Updates through a join view or a view of which the target list contains an expression are Transact-SQL extensions that cannot be detected until run time and are not flagged by the FIPS flagger.
- The use of variables.
- `readpast`

## Permissions

If `set ansi_permissions` is on, you need `update` permission on the table being updated and, in addition, you must have `select` permission on all columns appearing in the `where` clause and on all columns following the `set` clause. By default, `ansi_permissions` is off.

The following describes permission checks for `update` that differ based on your granular permissions settings.

Setting	Description
<b>Enabled</b>	With granular permissions enabled, you must be the table or view owner, or a user with <code>update</code> permission..
<b>Disabled</b>	With granular permissions disabled, you must be the table or view owner, a user with <code>update</code> permission, or a user with <code>sa_role</code> .

## Auditing

Enable object-specific `update` auditing option to audit updates on a specific table or view. Enable user-specific `table_access` or `view_access` auditing options to audit table or view access by a specific user.

Values in `event` and `extrainfo` columns from the `sysaudits` table are:

Audit option	Event	Command or access audited	Information in <code>extrainfo</code> :
<code>update</code> <code>table_access</code>	70	update to a table	<ul style="list-style-type: none"><li>• <i>Roles</i> – current active roles</li><li>• <i>Full command text</i> – full text of <code>update</code> command (Values of parameters used to update encrypted columns are obfuscated)</li></ul>
<code>update</code> <code>view_access</code>	71	update to a view	<ul style="list-style-type: none"><li>• <i>Previous value</i> – NULL</li><li>• <i>Current value</i> – NULL</li><li>• <i>Other information</i> – parameters and their values</li><li>• <i>Proxy information</i> – original login name, if set <code>proxy</code> is in effect</li></ul>

Full command text and parameter names/values are included in `extrainfo`. For example:

```
sa_role sso_role oper_role sybase_ts_role mon_role; update t1
set c1 = @vall; ; ; @vall = *****; ; sa/ase;
```

Parameter value for `@vall` is obfuscated because it contains encrypted information.

For more information about auditing, see *Security Administration Guide > Auditing*.

For more information about auditing encrypted columns, see *Database Encryption Users Guide > Column Encryption*.

## Related Information

[alter table \[page 70\]](#)

[create index \[page 192\]](#)

[insert \[page 572\]](#)

[where Clause \[page 855\]](#)

[create default \[page 158\]](#)



## 1.126.1 Using update with Transactions

When you set `chained transaction mode` on, and no transaction is currently active, the SAP ASE server implicitly begins a transaction with the `update` statement. To complete the update, you must either `commit` the transaction or `rollback` the changes.

For example:

```
update stores set city = 'Concord'
  where stor_id = '7066'
if exists (select t1.city, t2.city
  from stores t1, stores t2
  where t1.city = t2.city
  and t1.state = t2.state
  and t1.stor_id < t2.stor_id)
  rollback transaction
else
  commit transaction
```

This batch begins a transaction (using chained transaction mode) and updates a row in the `stores` table. If it updates a row containing the same city and state information as another store in the table, it rolls back the changes to the `stores` table and ends the transaction. Otherwise, it commits the updates and ends the transaction.

The SAP ASE server does not prevent you from issuing an `update` statement that updates a single row more than once in a given transaction. For example, both of these updates affect the price of the book with `title_id` MC2022, since its type id "mod\_cook":

```
begin transaction
update titles
set price = price + $10
where title_id = "MC2222"
update titles
set price = price * 1.1
where type = "mod_cook"
```

## 1.126.2 Using Joins in Updates

Performing joins in the `from` clause of an `update` is an Transact-SQL extension to the ANSI standard SQL syntax for updates.

Because of the way an `update` statement is processed, updates from a single statement do not accumulate. That is, if an `update` statement contains a join, and the other table in the join has more the one matching value in the join column, the second update is not based on the new values from the first update but on the original values. The results are unpredictable, since they depend on the order of processing.

Consider this join:

```
update titles set total_sales = total_sales + qty
  from titles t, salesdetail sd
  where t.title_id = sd.title_id
```

The `total_sales` value is updated only once for each `title_id` in `titles`, for *one* of the matching rows in `salesdetail`. Depending on the join order for the query, on table partitioning, or on the indexes available, the

results can vary each time. But each time, only a single value from `salesdetail` is added to the `total_sales` value.

If the intention is to return the sum of the values that match the join column, the following query, using a subquery, returns the correct result:

```
update titles set total_sales = total_sales +
    (select isnull (sum (qty),0)
     from salesdetail sd
     where t.title_id = sd.title_id)
from titles t
```

### 1.126.3 Using update with Character Data

Updating variable-length character data, or `text` or `unitext` columns, with the empty string ("") inserts a single space. Fixed-length character columns are padded to the defined length.

All trailing spaces are removed from variable-length column data, except when a string contains only spaces. Strings that contain only spaces are truncated to a single space. Strings longer than the specified length of a `char`, `nchar`, `unichar`, `varchar`, `univarchar`, or `nvarchar` column are silently truncated unless you set `string_rtruncation` on.

An update to a `text` or `unitext` column initializes the `text` or `unitext` column, assigns it a valid text pointer, and allocates at least one text page.

### 1.126.4 Using update with Cursors

Considerations for using `update` with cursors.

- You cannot update a scrollable cursor.
- To update a row using a cursor, define the cursor with `declare cursor`, then open it. The cursor name cannot be a Transact-SQL parameter or a local variable. The cursor must be updatable, or the SAP ASE server returns an error. Any update to the cursor result set also affects the base table row from which the cursor row is derived.
- The `<table_name>` or `<view_name>` specified with an `update...where current` of must be the table or view specified in the first `from` clause of the `select` statement that defines the cursor. If that `from` clause references more than one table or view (using a join), you can specify only the table or view being updated.  
After the update, the cursor position remains unchanged. You can continue to update the row at that cursor position, provided another SQL statement does not move the position of that cursor.
- The SAP ASE server allows you to update columns that are not specified in the list of columns of the cursor's `<select_statement>`, but that are part of the tables specified in the `<select_statement>`. However, when you specify a `<column_name_list>` with `for update`, and you are declaring the cursor, you can update only those specific columns.
- You can see the behavior of a cursor closing implicitly when the cursor is defined by a join operation, and another `update` command from the same client session deletes a row (updated in deferred mode) in the current position of the cursor. If:

- A searched or positioned update in an allpages-locked table changes a value of an index key – a subsequent `fetch` command may fail.
- A searched or positioned update in a data-only-locked table or data-row-locked table changes a value of an index key – the cursor remains positioned on the row, and the next `fetch` returns the next qualifying row.  
If the data-only-locked tables are semantic-partitioned tables and the update is being done in deferred mode, however, the row moves to a different partition as a result of the update, and a subsequent `fetch` command may fail.

## 1.126.5 Updating IDENTITY Columns

You cannot update a column with the IDENTITY property, either through its base table or through a view. To determine whether a column was defined with the IDENTITY property, use `sp_help` on the column's base table.

An IDENTITY column selected into a result table observes the following rules with regard to inheritance of the IDENTITY property:

- If an IDENTITY column is selected more than once, it is defined as NOT NULL in the new table. It does not inherit the IDENTITY property.
- If an IDENTITY column is selected as part of an expression, the resulting column does not inherit the IDENTITY property. It is created as NULL if any column in the expression allows nulls; otherwise, it is NOT NULL.
- If the `select` statement contains a `group by` clause or aggregate function, the resulting column does not inherit the IDENTITY property. Columns that include an aggregate of the IDENTITY column are created NULL; others are created NOT NULL.
- An IDENTITY column that is selected into a table with a union or join does not retain the IDENTITY property. If the table contains the union of the IDENTITY column and a NULL column, the new column is defined as NULL. Otherwise, it is defined as NOT NULL.

## 1.126.6 Updating Data Through Views

Considerations for updating data through views.

- You cannot update views defined with the `distinct` clause.
- If a view is created with `check option`, each row that is updated through the view must remain visible through the view. For example, the `stores_cal` view includes all rows of the `stores` table where `state` has a value of "CA". The `with check option` clause checks each update statement against the view's selection criteria:

```
create view stores_cal
as select * from stores
where state = "CA"
with check option
```

An update statement such as this one fails if it changes `state` to a value other than "CA":

```
update stores_cal
```

```
set state = "WA"
where store_id = "7066"
```

- If a view is created with `check option`, all views derived from the base view must satisfy the view's selection criteria. Each row updated through a *derived* view must remain visible through the base view. Consider the view `stores_cal30`, which is derived from `stores_cal`. The new view includes information about stores in California with payment terms of "Net 30":

```
create view stores_cal30
as select * from stores_cal
where payterms = "Net 30"
```

Because `stores_cal` was created with `check option`, all rows updated through `stores_cal30` must remain visible through `stores_cal`. Any row that changes `state` to a value other than "CA" is rejected. Notice that `stores_cal30` does not have a `with check option` clause of its own. Therefore, you can update a row with a `<payterms>` value other than "Net 30" through `stores_cal30`. For example, the following `update` statement would be successful, even though the row would no longer be visible through `stores_cal30`:

```
update stores_cal30
set payterms = "Net 60"
where stor_id = "7067"
```

- You cannot update a row through a view that joins columns from two or more tables, unless both of the following conditions are true:
  - The view has no `with check option` clause, and
  - All columns being updated belong to the same base table.
- `update` statements are allowed on join views that contain a `with check option` clause. The update fails if any of the affected columns appear in the `where` clause in an expression that includes columns from more than one table.
- If you update a row through a join view, all affected columns must belong to the same base table.

## 1.126.7 Using index, prefetch, or lru | mru

`index`, `prefetch`, and `lru | mru` override the choices made by the SAP ASE optimizer. Use them with caution, and always check the performance impact with `set statistics io on`.

For more information about using these options, see the *Performance and Tuning Guide*.

## 1.126.8 Using readpast

The `readpast` option applies only to data-only-locked tables. `readpast` is ignored if it is specified for an allpages-locked table.

- The `readpast` option is incompatible with the `holdlock` option. If both are specified in the same `select` command, an error is generated and the command terminates.
- If the session-wide isolation level is 3, the `readpast` option is ignored.
- If the transaction isolation level for a session is 0, `update` commands using `readpast` do not issue warning messages. For datapages-locked tables, these commands modify all rows on all pages that are not

locked with incompatible locks. For datarows-locked tables, they affect all rows that are not locked with incompatible locks.

- If an `update` command with `readpast` applies to two or more text columns, and the first text column checked has an incompatible lock on it, `readpast` locking skips the row. If the column does not have an incompatible lock, the command acquires a lock and modifies the column. Then, if any subsequent text column in the row has an incompatible lock on it, the command blocks until it can obtain a lock and modify the column.
- See the *Performance and Tuning Guide* for more on `readpast`.

## 1.126.9 Using Variables in update Statements

Considerations for using variables in update statements.

- You can assign variables in the `set` clause of an `update` statement, similarly to setting them in a `select` statement.
- Before you use a variable in an `update` statement, you must declare the variable using `declare`, and initialize it with `select`, as shown in Example 5.
- Variable assignment occurs for every qualified row in the update.
- When a variable is referenced on the right side of an assignment in an `update` statement, the current value of the variable changes as each row is updated. The current value is the value of the variable just before the update of the current row. The following example shows how the current value changes as each row is updated.

Suppose you have the following statement:

```
declare @x int
select @x=0
update table1
  set C1=C1+@x, @x=@x+1
  where column2=xyz
```

The value of C1 before the update begins is 1. This table shows how the current value of the `@<x>` variable changes after each update:

Row	Initial C1 value	Initial @<x> value	Calculations: C1+@<x>= updated C1	Updated C1 value	Calculations: <@<x>+1= updated @<x>	Updates value
A	1	0	1+0	1	0+1	1
B	1	1	1+1	2	1+1	2
C	2	2	2+2	4	2+1	3
D	4	3	4+3	7	3+1	4

- When multiple variable assignments are given in the same `update` statement, the values assigned to the variables can depend on their order in the assignment list, but they might not always do so. For best results, do not rely on placement to determine the assigned values.
- If multiple rows are returned and a non-aggregating assignment of a column to a variable occurs, then the final value of the variable is the last row processed; therefore, it might not be useful.

- An `update` statement that assigns values to variables need not set the value of any qualified row.
- If no rows qualify for the update, the variable is not assigned.
- A variable that is assigned a value in the `update` statement cannot be referenced in subquery in that same `update` statement, regardless of where the subquery appears in that `update` statement.
- A variable that is assigned a value in the `update` statement cannot be referenced in a `where` or `having` clause in that same `update` statement.
- In an update driven by a join, a variable that is assigned a value in the right hand side of the `update` statement uses columns from the table that is not being updated. The result value depends on the join order chosen for the update and the number of rows that qualify from the joined table.
- Updating a variable is not affected by a rollback of the `update` statement because the value of the updated variable is not stored on disk.

## 1.127 update all statistics

Updates all statistics information for a given table, including histograms on all columns, regardless of whether they are indexed. You can run `update all statistics` on a single data partition.

### Syntax

```
update all statistics
  <table_name> [partition <data_partition_name>]
  [using<step> values]
  [with consumers = <consumers>]
  [, sampling=<N> [percent]]
  [, no_hashing | partial_hashing | hashing]
  [, max_resource_granularity = <N> [percent]]
  [, histogram_tuning_factor = int]
  [, print_progress = <int>]
```

### Parameters

**<table\_name>**

is the name of the table for which statistics are being updated.

**<data\_partition\_name>**

is the name of the partition to be updated. Statistics for each local index partition on the data partition is updated. Does not update statistics for global indexes.

**using <step> values**

specifies the number of histogram steps. The default value is 20 for columns where no statistics exist. To change the default, use `sp_configure` to modify the `<number of histogram steps>` parameter. If statistics for a column already exist in `sysstatistics`, the default value is the current number of steps.

The steps are applied to each partition of a partitioned table—for example, `update index statistics` on a single data partition, or local index scan, then by default, 20 steps are applied for each partition. scan. If hash-based statistics gathering is enabled, then statistics are gathered on uses the default value of 20 steps for each data and index partition involved in the scan for updating statistics. If global statistics are generated through an index scan of a global index, then 20 steps are applied by default. If partition statistics are generated, either through a data scan on a single data partition, or local index scan, then by default, 20 steps are applied for each partition. scan. If hash-based statistics gathering is enabled, then statistics are gathered on all the minor attributes as well during the index scans. For all other columns, including leading columns of a global index,

If the histogram steps specified through `using <step>` values is  $M$  all the minor attributes as well during the index scans. For all other columns, if the `histogram_tuning_factor` parameter is  $N$ , then `update index statistics` uses between 0 and  $M*N$  steps, depending on the number of frequency cells that `update index statistics` isolates and whether any range cells exist.

**with consumers = <consumers>**

specifies the number of consumer processes to be used for a sort when `<column_list>` is provided and parallel query processing is enabled. The `consumers` option specifies the degree of parallelism applied to a sort performed for statistics update on a single data partition. For example, if `update statistics` with a column list is applied to a table with three data partitions, data from each of the three partitions is sorted separately and the `consumers` option is applied during each of the sort. The three sorts themselves are not performed in parallel.

#### Note

The value for the `max utility parallel degree` configuration parameter must be greater than the value for `with consumers`. For example, if `with consumers` is set to 2, then `max utility parallel degree` must be at least 3.

**with sampling = <N> percent**

specifies the percentage of the column to be randomly sampled to gather statistics. The value for `<N>` is any number between 1 and 100.

**[no\_hashing | partial\_hashing | hashing]**

indicates the level of hash-based statistics `update all statistics` gathers. One of:

- no\_hashing** updates all statistics uses the algorithm from SAP ASE versions earlier than 15.7, gathering sort-based statistics.
- partial\_hashing** updates all statistics uses the algorithm for columns with fewer than 65536 unique values. If updates all statistics encounters unique column counts greater or equal to the 65536 threshold, it uses an extra scan with a sort.
- hashing** updates all statistics uses low-domain and high-domain hashing to create the histograms.

The default for these parameters is the configured value for `update statistics hashing`.

**max\_resource\_granularity = <N> percent**

limits the amount of `tempdb` buffer cache used with the `update all statistics` and hashing.

**histogram\_tuning\_factor = <integer>**

determines the distribution granularity of `update all statistics`.

**print\_progress = <int>**

Determines if `update all statistics` displays progress messages.

- 0 – (the default) command does not display any progress messages
- 1 – command displays progress messages

## Examples

### Example 1

Updates all statistics for the `salesdetail` table:

```
update all statistics salesdetail
```

### Example 2

Updates all statistics for the `smallsales` partition. Statistics for each local index partition on the data partition are updated. Does not update statistics for the global `indexes.salesdetail` table:

```
update all statistics salesdetail partition smallsales
```

### Example 3

Updates hash-based statistics for the `authors` table:

```
update all statistics authors with hashing
```

## Usage

- `update all statistics` specifies the number of histogram steps. The default value is 20, for columns where updates all the statistics information for a given table. The SAP ASE server keeps statistics about the distribution of pages within a table, and uses these statistics when considering whether or not to use a parallel scan in query processing on partitioned tables, and which index (es) to use in query processing. The optimization of your queries depends on the accuracy of the stored statistics.
- Histogram statistics are created on each column, either through an index scan of a leading column, a projection of the column into a work table followed by a sort, or by using hashing to concurrently generate histograms on several columns for respective scans.
- Density statistics are created for all the prefix subsets of the columns of index (es) whose statistics is being updated. For example, if an index is on columns `c1`, `c2` and `c3`, then the prefix subsets are `(c1,c2)` and `(c1, c2, c3)`.



- When you run `update all statistics` `update all statistics` performs either a data scan followed by a sort or performs a data scan that uses hash-based statistics gathering. The advantage of hash-based statistics is that one data scan can collect histograms on all columns, whereas sort-based statistics uses a separate scan for each column.
- `update statistics` commands create partition-specific statistics. Global statistics are implicitly created during partition statistics creation. The partition statistics serve as input to global statistics creation and enable per-partition DDL operations. Global statistics are used by the optimizer.
- `update all statistics` regenerates and update the table statistics stored in `systabstats` for each data and index partition of the table. If the `update all statistics` command is run for a specific data partition, the table statistics are generated and updated only for that data partition and any local index partitions. Global indexes are skipped.

When using hash-based statistics:

- The `partial_hashing` parameter uses hashing on columns only when it produces histograms that are as accurate and of equivalent quality as those produced by sorting (low domain cases), otherwise, the `partial_hashing` parameter uses sorting for high-domain cases.
- Hashing may produce less accurate histograms than sorting in some cases (high-domain cases).
- Although hash-based statistics do not require the `tempdb` disk space or procedure cache memory used by sorting, it may use a significant amount of `tempdb` buffer cache memory.
- Large sorts used for the `no_hashing` parameter may scavenge statements in the statement cache and stored procedures to release procedure cache memory to support the sort.
- `max_resource_granularity` limits the amount of `tempdb` buffer cache memory used for hashing or `partial_hashing`. It does not affect the amount of memory used by the `no_hashing` parameter or sorting.
- If you include the `partial_hashing` parameter, and a previous histogram on a column exists that indicates a high-domain column, then the SAP ASE server assumes that sort-based statistics are required on this column. If no previous histogram exists on a column, then the SAP ASE server assumes this column is low-domain until the high domain limit is reached.

## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

## Permissions

You must be the table owner or a user with `update statistics` permission on the table to run `update all statistics`.

## Auditing

This command is not audited.

## Related Information

[update index statistics \[page 834\]](#)

[update statistics \[page 839\]](#)

[update table statistics \[page 848\]](#)

## 1.128 update index statistics

Updates the statistics for all columns in an index.

### Syntax

```
update index statistics
  <table_name> [[partition <data_partition_name><index_name> [partition
<index_partition_name>]]]
  [using step values]
  [with consumers = ] |
  [[<consumers>][, sampling=<N> [percent]]
  [, no_hashing | partial_hashing | hashing]
  [, max_resource_granularity = <N>] percent]]
  [, histogram_tuning_factor = <int>]
  [, print_progress = <int>]
```

### Parameters

#### <table\_name>

when used with `update statistics`, `<table_name>` is the name of the table with which the index is associated. `<table_name>` is required, since Transact-SQL does not require index names to be unique in a database.

#### <data\_partition\_name>

is the name of the partition to be updated. Statistics for each local index partition on the data partition is updated. Does not update statistics for global indexes.

#### <index\_name>

is the name of the index to be updated. If an index name is not specified, the distribution statistics for all the indexes in the specified table are updated.

#### <index\_partition\_name>

is the name of the index partition to be updated.

`using <step> values`

`sp_configure` to modify the `<number of histogram steps>` parameter. If statistics for a column already exist in `sysstatistics`, the default value is the current number of steps.

The steps are applied to each partition of a partitioned table—for example, `update index statistics` uses the default value of 20 steps for each data and index partition involved in the scan for updating statistics. If global statistics are generated through an index scan of a global index, then 20 steps are applied by default. If partition statistics are generated, either through a data scan or local index scan, then 20 steps are applied by default for each partition.

If the histogram steps specified through using `<step>` values is M, and the `histogram_tuning_factor` parameter is N, then `update index statistics` uses between 0 and M\*N steps, depending on the number of frequency cells that `update index statistics` isolates and whether any range cells exist.

**with consumers = `<consumers>`**

specifies the number of histogram steps. The default value is 20, for columns that specify the number of consumer processes to be used for a sort when `<column_list>` is provided and parallel query processing is enabled. The `consumers` option specifies the degree of parallelism applied to a sort performed for statistics update on a single data partition. For example, if `update statistics` with a column list is applied to a table with three data partitions, data from each of the three partitions is sorted separately and the `consumers` option is applied during each of the sort. The three sorts themselves are not performed in parallel.

#### i Note

The value for the `max utility parallel degree` configuration parameter must be greater than the value for `with consumers`. For example, if `with consumers` is set to 2, then `max utility parallel degree` must be at least 3.

**with sampling = `<N>` percent**

specifies the percentage of the column to be randomly sampled in order to gather statistics. The value for `<N>` is any number between 1 and 100.

#### i Note

Hashing does not currently support sampling.

**no\_hashing | partial\_hashing | hashing**

indicates the level of hash-based statistics `update index statistics` gathers. One of:

**no\_hashing** (default) `update index statistics` uses the algorithm from SAP ASE versions earlier than 15.7, gathering sort-based statistics.

**partial\_hashing** `update index statistics` uses the algorithm for columns with fewer than 65536 unique values. If `update index statistics` encounters unique column counts that are greater

than or equal to the 65536 threshold, it uses an extra scan with a sort.

**hashing** `update index statistics` uses low-domain and high-domain hashing to create the histograms.

**max\_resource\_granularity = <N> percent**

limits the amount of `tempdb` buffer cache used with `update index statistics` and hashing.

**with histogram\_tuning\_factor = <integer>**

determines `update index statistics`'s distribution granularity.

**print\_progress = <int>**

Determines if `update index statistics` displays progress messages.

- 0 – (the default) command does not display any progress messages
- 1 – command displays progress messages

## Examples

### Example 1

Generates statistics for all columns in all indexes of the `authors` table:

```
update index statistics authors
```

### Example 2

Generates statistics for all columns in the `au_names_ix` index of the `authors` table:

```
update index statistics authors au_names_ix
```

### Example 3

Generates statistics on all inner columns of the `au_names_ix` index using a sampling rate of 20 percent:

```
update index statistics authors au_names_ix
with sampling = 20 percent
```

The statistics for the leading column of `au_names_ix` is gathered using a full scan of the index pages; sampling is not applied on this column.

### Example 4

Shows the progress messages when `update index statistics` is run on table `bigtable`:

```
update index statistics bigtable with partial_hashing, print_progress=1
```

```
Update Statistics STARTED.
Update Statistics index scan started on index 'bigtable_NC1'.
...It is using existing index scan to hash minor column 'a2' (column id = 2).
...Column 'a2' (column id = 2) is moved from hashing to sorting.
Update Statistics table scan started on table 'bigtable' for summary
statistics.
```

```
Update Statistics table scan started on table 'bigtable'.
...Sorting started for column 'a2' (column id = 2).
Update Statistics FINISHED.
```

### Example 5

Generates statistics for all the columns of an index partition:

```
update index statistics publishers publish1_idx
partition p1
```

## Usage

- `update index statistics`, when used with a table name and an index name, updates statistics for all columns in the specified index. If `update index statistics` is used with just a table name, it updates statistics for all columns in all indexes of the table.
- If you run `update index statistics` against large tables, the command fails with error number 1105 if `tempdb` is not large enough to process the command.
- Specifying the name of an unindexed column or the nonleading column of an index generates statistics for that column without creating an index.
- Histogram statistics are created for each column of indexes whose statistics is being updated.
- Density statistics are created for all the prefix subsets of the columns of index (es) whose statistics are being updated.
- If you use `update index statistics` on a specific partition, you update global statistics implicitly as well.
- The partition statistics serve as input to global statistics creation and enable per-partition DDL operations. Global statistics are used by the optimizer.
- `update index statistics` also regenerates and updates the table statistics stored in `systabstats` for each data and index partition of the table the command updates. If you run the `update index statistics` command for a specific data partition, the table statistics are generated and updated only for that data partition and for any local index partitions. Global indexes are skipped. If you run the `update index statistics` for a specific index partition, only the table statistics for that index partition are updated.
- The `with consumers` clause is designed for use on partitioned tables on RAID devices, which appear to the SAP ASE server as a single I/O device, but which are capable of producing the high throughput required for parallel sorting.
- The `update index statistics` command generates a series of update statistics operations that use the same locking, scanning, and sorting as the equivalent index-level and column-level command. For example, if the `salesdetail` table has a nonclustered index named `sales_det_ix` on `salesdetail` (`stor_id`, `ord_num`, `title_id`), the `update index statistics salesdetail` command performs these `update statistics` operations:

```
update statistics salesdetail sales_det_ix
update statistics salesdetail (ord_num)
update statistics salesdetail (title_id)
```

When using hash-based statistics:

- The `partial_hashing` parameter uses hashing on columns only when it produces histograms that are as accurate and of equivalent quality as those produced by sorting (low-domain cases), otherwise, the `partial_hashing` parameter uses sorting for high-domain cases.
- Hashing in high-domain cases may produce histograms with up to a 50 percent fewer steps compared to sorting.
- Although hash-based statistics do not require the `tempdb` disk space or procedure cache memory used by sorting, it may use a significant amount of `tempdb` buffer cache memory.
- Large sorts used for the `no_hashing` parameter may scavenge statements in the statement cache and stored procedures to release procedure cache memory to support the sort.
- `max_resource_granularity` limits the amount of `tempdb` buffer cache memory used for hashing or `partial_hashing`. It does not affect the amount of memory used by the `no_hashing` parameter or sorting.
- If you include the `partial_hashing` parameter, and a previous histogram on a column exists that indicates a high-domain column, then the SAP ASE server assumes that sort-based statistics are required on this column. If no previous histogram exists on a column, then the SAP ASE server assumes this column is low-domain until the high-domain limit is reached.

See also *Parallel Sorting* in the *Performance and Tuning Guide*.

## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

## Permissions

The permission checks for `update index statistics` differ based on your granular permissions settings.

Setting	Description
---------	-------------

<b>Enabled</b>	With granular permissions enabled, you must be the table owner, a user with <code>update statistics</code> permission on the table or a user with <code>manage any statistics</code> permission.
----------------	--

<b>Disabled</b>	With granular permissions disabled, you must be the table owner or a user with <code>update statistics</code> permission on the table.
-----------------	--

`update statistics` permission can be granted or transferred to anyone by the table owner or system administrator.

## Auditing

This command is not audited.

## Related Information

[delete statistics \[page 398\]](#)

[update all statistics \[page 830\]](#)

[update statistics \[page 839\]](#)

[update table statistics \[page 848\]](#)

## 1.129 update statistics

Updates information about the distribution of key values in specified indexes, for all columns in an index, table, or partition, and resets the data change counters for global nonclustered indexes.

### Syntax

```
update statistics <table_name>
  [[partition <data_partition_name>]
   [(<column1>, <column2>, ...) | (<column1>), (<column2>), ...] |
  <index_name> [partition <index_partition_name>]]
  [using_step values | [out_of_range [on | off | default]]]
  [with consumers = <consumers>][, sampling=<N> percent]
  [, no_hashing | partial_hashing | hashing]
  [, max_resource_granularity = <N> [percent]]
  [, histogram_tuning_factor = <int>]
  [, print_progress = <int>]
```

### Parameters

#### <table\_name>

when used with `update statistics`, `<table_name>` is the name of the table with which the index is associated. `<table_name>` is required, since Transact-SQL does not require index names to be unique in a database.

#### <index\_name>

is the name of the index to be updated. If an index name is not specified, the distribution statistics for all the indexes in the specified table are updated.

#### <data\_partition\_name>

is the name of the partition to be updated. Statistics for each local index partition on the data partition is updated. Does not update statistics for global indexes.

#### <index\_partition\_name>

is the name of the index partition to be updated.

(<column1>, <column2>, ...)

creates the same statistics that are created if a local index is created and included on this column tuple. That is, creates a histogram on `column1`, and create multiattribute distributions on all column prefixes (`column1, column2`), (`column1, column2, column3`).

**(`<column1>`), (`<column2>`)**

comma-separated list of columns on which you are running `update statistics`. Allows for a single `update statistics` command to create a histogram on each column in the list, but does not create any multi-attribute distributions.

**using `<step>` values**

specifies the number of histogram steps. The default value is 20, for columns where no statistics exist. If you need to change the default for this, use `sp_configure` to modify the `<number of histogram steps>` parameter. If statistics for a column already exist in `sysstatistics`, the default value is the current number of steps.

The steps are applied to each partition of a partitioned table—for example, `update statistics` uses the default value of 20 steps for each data and index partition involved in the scan for updating statistics. If global statistics are generated through an index scan of a global index, then 20 steps are applied by default. If partition statistics are generated, either through a data scan or local index scan, then 20 steps are applied by default for each partition.

If the histogram steps specified through `using <step> values` is *M*, and the `histogram_tuning_factor` parameter is *N*, then `update statistics` uses between 0 and *M\*N* steps, depending on the number of frequency cells that `update statistics` isolates and whether any range cells exist.

**out\_of\_range [on | off | default]**

Column statistics for rapidly growing tables may become out-of-date when `update statistics` completes, resulting in out-of-range SARGs (search clauses) that select a greater range of values than described by the column's histogram. Out-of-range SARGS have a selectivity of 0. The `out_of_range` histogram adjustment feature adjusts a column's histogram, and assigns an appropriate selectivity value to such SARGs.

Histogram adjustment for out of range SARGS is enabled server wide by default.

`out_of_range` specifies an out-of-range histogram adjustment at the column level. One of:

**on** Enables out-of-range histogram adjustment for `column_name`.

**off** Disables out-of-range histogram adjustment for `column_name`.

**default** Affects the out-of-range histogram adjustment depending on the value of trace flag 15355. When the trace flag is:

- On – disables out-of-range histogram adjustment
- Off – enables out-of-range histogram adjustment

**with consumers = `<consumers>`**

specifies the number of consumer processes to be used for a sort when `<column_list>` is provided and parallel query processing is enabled. The `consumers`



option specifies the degree of parallelism applied to a sort performed for statistics update on a single data partition. For example, if `update statistics` with a column list is applied to a table with three data partitions, data from each of the three partitions is sorted separately and the `consumers` option is applied during each of the sort. The three sorts themselves are not performed in parallel.

### **i** Note

The value for the `max utility parallel degree` configuration parameter must be greater than the value for `with consumers`. For example, if `with consumers` is set to 2, then `max utility parallel degree` must be at least 3.

#### **with sampling = <N> percent**

specifies the percentage of the column to be randomly sampled in order to gather statistics. The value for `<N>` is any number between 1 and 100. Sampling applies to all `update statistics` types:

- `update statistics <table_name> (<col_name>)`
- `update index statistics`
- `update all statistics`

#### **index**

specifies that statistics for all columns in an index are to be updated.

#### **no\_hashing | partial\_hashing | hashing**

indicates the level of hash-based statistics `update statistics` gathers. One of:

**no\_hashing** (the default) `update statistics` uses the algorithm from SAP ASE versions earlier than 15.7, gathering sort-based statistics.

**partial\_hashing** `update statistics` uses the algorithm for columns with fewer than 65536 unique values. If `update statistics` encounters unique column counts that are greater than or equal to the 65536 threshold, it uses an extra scan with a sort.

**hashing** `update statistics` uses low-domain and high-domain hashing to create the histograms.

#### **max\_resource\_granularity = <N> percent**

limits the amount of `tempdb` buffer cache used with `update statistics` and hashing.

#### **with histogram\_tuning\_factor = <integer>**

determines `update statistics`'s distribution granularity.

#### **print\_progress = <int>**

Determines if `update statistics` displays progress messages.

- 0 – (the default) command does not display any progress messages
- 1 – command displays progress messages

## Examples

### Example 1

Generates statistics for the `price` column of the `titles` table:

```
update statistics titles (price) using 40 values
```

### Example 2

Updates statistics on the data partition `smallsales` the SAP ASE server creates histograms for each leading column and densities for the composite columns of each local index of the data partition. Statistics are not updated for global indexes:

```
update statistics titles partition smallsales
```

### Example 3

Updates statistics on the data partition `smallsales`. The SAP ASE server creates histograms on column `col1` and creates densities for the composite columns `col1` and `col2`:

```
update statistics titles partition smallsales (col1, col2)
```

### Example 4

When an `out_of_range` SARG is detected for a column, the optimizer adjusts the column's histogram and assigns an appropriate selectivity value to the out-of-range clause:

```
update statistics TOFO_FUOP_ORD(OrdDt) using  
out_of_range on
```

### Example 5

If trace flag 15355 is turned on, the column's histogram is not adjusted for out-of-range SARGs:

```
update statistics TOFO_FUOP_ORD(OrdDt) using  
out_of_range default
```

### Example 6

Shows the progress messages when `update statistics` is run on table `bigtable`:

```
update statistics bigtable with print_progress=1  
Update Statistics STARTED.  
Update Statistics index scan started on index 'bigtable_NC1'.  
Update Statistics table scan started on table 'bigtable' for summary  
statistics.  
Update Statistics FINISHED.
```

### Example 7

Shows the progress messages when `update statistics ... with hashing` is run on table `bigtable`:

```
update statistics bigtable (a1), (a2), (a3) with hashing, print_progress=1  
Update Statistics STARTED.  
Update Statistics table scan started on table 'bigtable'.  
...Column 'a3' (column id = 3) is picked as hash victim due to limited  
resource.  
Update Statistics table scan started on table 'bigtable'.
```

## Example 8

Runs `update statistics` on the `authors` table with a `histogram_tuning_factor` of 5 percent:

```
update statistics authors with histogram_tuning_factor = 5
```

## Usage

- The SAP ASE server keeps statistics about the distribution of the key values in each index, and uses these statistics in its decisions about which index (es) to use in query processing.
- `update statistics` is supported for in-memory row storage-enabled tables. However, `update statistics` does not affect or track the row contents in the in-memory row storage, and does not generate new statistics in `systabstats` or `sysstatistics` for the in-memory row storage. For example, `systabstats.pagecnt` reports the number of pages in the table or index, and `systabstats.rowcnt` reports the total number of rows in the table, including those in the in-memory row storage. Column histograms generated using sorting or hashing include rows from the in-memory row storage. However, cluster ratio computations performed by as part of `update statistics` include rows from the page store, but ignore rows in the in-memory row storage.
- When you create a nonclustered index on a table that contains data, `update statistics` is automatically run for the new index. When you create a clustered index on a table that contains data, `update statistics` is automatically run for all indexes.
- Running `update statistics` on an empty table does not affect the system tables.
- The optimization of your queries depends on the accuracy of the statistics. If there is significant change in the key values in your index, you should rerun `update statistics` on that index or column. Use the `update statistics` command if a great deal of data in an indexed column has been added, changed, or removed (that is, if you suspect that the distribution of key values has changed).
- You should also run `update statistics` on system tables with a large number of rows. If you have permission to run the command on a user table, it is no different with respect to system table. Without statistics, there is always a chance for system stored procedures to perform poorly.
- `update statistics` skips global indexes when you run the command on a data partition.
- `update statistics`, when used with a table name and an index name, updates statistics for the leading column of an index. If `update statistics` is used with just a table name, it updates statistics for the leading columns of all indexes on the table.
- If a comma-separated list, `(col1), (col2) . . .`, is used and hashing is enabled, then one scan can be used to gather statistics, if you do not exceed the resource granularity. If sorting is enabled, then one scan for each is used. If you use partial hashing, one scan can be used for low-domain columns, if you do not exceed the resource granularity, and one scan is used for the sort for each of the high-domain columns (that is, if you have three columns, you have three sorts).
- Specifying the name of an unindexed column or the nonleading column of an index generates statistics for that column without creating an index.
- Specifying more than one column in a column list (for example `(col1, col2, . . . )`) generates or updates a histogram for the first column, and density statistics for all prefix subsets of the list of columns. Hash-based statistics cannot be used in this case.
- If you use `update statistics` to generate statistics for nonleading columns of clustered indexes and nonindexed columns, `update statistics` must scan the table and perform a sort. The SAP ASE server ignores sampling for `update statistics` unless you specify a column list (such as `(col1), (col2) . . .`, or `(col1, col2, col3)`). Use `update all statistics` or `update index`

`statistics` if you require sampling in situations other than a column list. If you specify a column list, and these columns are nonleading columns of clustered indexes and nonindexed columns, `update statistics` must scan the table and perform a sort, or use hash-based algorithms.

- If you use `update statistics` on a specific partition, you update global statistics implicitly as well.
- The SAP ASE server raises error 16015 if you attempt to use `out_of_range` options for `update statistics` alongside other options such as `consumers` or `sampling`. The SAP ASE server raises error 16016 if you specify `out_of_range` options for a column that currently has no column level statistics.
- `update statistics` regenerates and updates the table statistics stored in `sysstabstats` for each data and index partition of the table the command updates. If you run the `update statistics` command for a specific data partition, the table statistics are generated and updated only for that data partition and for any local index partitions. Global indexes are skipped. If you run the `update statistics` for a specific index partition, only the table statistics for that index partition are updated.
- The `with consumers` clause is designed for use on partitioned tables on RAID devices, which appear to the SAP ASE server as a single I/O device, but which are capable of producing the high throughput required for parallel sorting. See *Using Statistics to Improve Performance* in the *Performance and Tuning Series: Query Processing and Abstract Plans*.
- The `update index statistics` command generates a series of update statistics operations that use the same locking, scanning, and sorting as the equivalent index-level and column-level command. For example, if the `salesdetail` table has a nonclustered index named `sales_det_ix` on `salesdetail (stor_id, ord_num, title_id)`, the `update index statistics salesdetail` command performs these `update statistics` operations:

```
update statistics salesdetail sales_det_ix
update statistics salesdetail (ord_num)
update statistics salesdetail (title_id)
```

- `update statistics` is not run on system tables in the master database during upgrade from earlier versions. Indexes exist on columns queried by most system procedures, and running `update statistics` on these tables is not required for normal usage. However, running `update statistics` is allowed on all system tables in all databases, except those that are not normal tables. These tables, which are built from internal structures when queried, include `syscurconfigs`, `sysengines`, `sysgams`, `syslisteners`, `syslocks`, `syslogs`, `syslogshold`, `sysmonitors`, `sysprocesses`, `syssecmechs`, `systemstlog` and `sysstransactions`. You do not need to run `update statistics` on Replication Server RSSD tables. Running `update statistics` on these tables can result in Replication Server errors if you run it while Replication Server attempts to access the RSSD tables. RSSD tables and their format are specific to Replication Server processing.
- `update statistics` acquires memory from the default data cache instead of `tempdb` buffer cache if the session is using a `tempdb` bound to an inmemory device.
- These `update statistics` parameters retain their values on all affected columns and override any configuration settings until the statistics for the columns are deleted, or until you run `sp_modifystats ... REMOVE_STICKINESS` on the columns:
  - `using step values`
  - `out_of_range`
  - `no_hashing`
  - `partial_hashing`
  - `hashing`

- `histogram_tuning_factor`
- `sampling = <N> percent`

### Note

`consumers` and `max_resource_granularity` do not retain their values.

For example, if you issue:

```
update statistics table_name(column1) with no_hashing
```

Subsequent `update statistics` commands on this table use the default configuration value for `update statistics hashing` on all columns except `column1`, which continues to use `no_hashing` until you delete the `column1` statistics.

- `with consumers` and `with sampling` apply to sorts and not to hashing. You may include the `partial_hashing` parameter with `with consumers` and `with sampling` parameters, but `with consumers` and `with sampling` apply only to sorts on the high-domain columns. If you explicitly include the `with hashing` parameter with the `with consumers` or `with sampling` parameters, the SAP ASE server ignores those parameters.

See also:

- *Performance and Tuning Guide*  
For `optdiag` syntax and usage, see *Statistics Tables and Displaying Statistics with optdiag* in *Performance and Tuning Series: Monitoring and Analyzing*.

## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

## Permissions

The permission checks for `update statistics` differ based on your granular permissions settings.

Setting	Description
<b>Enabled</b>	With granular permissions enabled, you must be the table owner, a user with <code>update statistics</code> permission on the table or a user with <code>manage any statistics</code> permission.
<b>Disabled</b>	With granular permissions disabled, you must be the table owner or a user with <code>update statistics</code> permission on the table.  <code>update statistics</code> permission can be granted or transferred to anyone by the table owner or system administrator.

## Auditing

This command is not audited.

## Related Information

[delete statistics \[page 398\]](#)

[update all statistics \[page 830\]](#)

[update index statistics \[page 834\]](#)

[update table statistics \[page 848\]](#)

### 1.129.1 Types of Scans Performed During update statistics

The types of scans performed during `update statistics`, the types of locks acquired, and when sorts are needed.

For leaf level index scans, see *When Does SAP ASE Perform Scans and Sorts* in the *Performance and Tuning Series: Query Processing and Abstract Plans* to determine which indexes get scanned if the column for which the statistics is being sampled exists in two or more indexes.

Table 10: Table Name

<code>update statistics</code> Specifying	Scans and Sorts Performed	Locking
Allpages-locked table	Table scan, plus a leaf-level scan of each nonclustered index	Level 1; shared intent table lock, shared lock on current page
Data-only-locked table	Table scan, plus a leaf-level scan of each nonclustered index and the clustered index, if one exists	Level 0; dirty reads

Table 11: Table Name and Clustered Index Name

<code>update statistics</code> Specifying	Scans and Sorts Performed	Locking
Allpages-locked table	Table scan	Level 1; shared intent table lock, shared lock on current page
Data-only-locked table	Leaf level index scan <sup>1</sup>	Level 0; dirty reads

Table 12: Table Name and Nonclustered Index Name

<code>update statistics</code> Specifying	Scans and Sorts Performed	Locking
Allpages-locked table	Leaf level index scan	Level 1; shared intent table lock, shared lock on current page

<code>update statistics</code> Specifying	Scans and Sorts Performed	Locking
Data-only-locked table	Leaf level index scan <sup>1</sup>	Level 0; dirty reads

Table 13: Table Name and Column Name

<code>update statistics</code> Specifying	Scans and Sorts Performed	Locking
Allpages-locked table	Table scan; creates a worktable and sorts the worktable	Level 1; shared intent table lock, shared lock on current page
Data-only-locked table	Table scan; creates a worktable and sorts the worktable	Level 0; dirty reads

## 1.129.2 update statistics and Sampling

The SAP ASE server scans samples of data pages. You can use update statistics to create and update statistics on the leading column of all indexes on the specified table, or the leading column of a specified index.

```
update statistics <table_name> [<index_name>] with sampling = <N> percent
```

When you use the `sampling = <N> percent` option with the `using <steps> value`, you must specify the `sampling = <N> percent` option last:

```
update statistics titles (type)
  using 40 value
  with sampling = 10 percent
```

If you do not, you get an error message:

```
update statistics titles (type)
  with sampling = 10 percent
  using 40 value
```

```
Msg 156, Level 15, State 2:
Line 1:
Incorrect syntax near the keyword 'using'.
```

## 1.129.3 create index and Stored Procedures

The SAP ASE server automatically recompiles stored procedures after executing `update statistics` statements. Although ad hoc queries that you start before executing `update statistics` still continue to work, they do not take advantage of the new statistics.

## 1.129.4 Using Hash-Based Statistics

The `partial_hashing` parameter uses hashing on columns only when it produces histograms that are as accurate and of equivalent quality as those produced by sorting (low-domain cases), otherwise, the `partial_hashing` parameter uses sorting for high-domain cases.

Hashing may produce less accurate histograms than sorting in some cases (high-domain cases).

Although hash-based statistics do not require the `tempdb` disk space or procedure cache memory used by sorting, it may use a significant amount of `tempdb` buffer cache memory.

Large sorts used for the `no_hashing` parameter may scavenge statements in the statement cache and stored procedures to release procedure cache memory to support the sort.

`max_resource_granularity` limits the amount of `tempdb` buffer cache memory used for hashing or `partial_hashing`. It does not affect the amount of memory used by `no_hashing` parameter or sorting.

If you include the `partial_hashing` parameter, and a previous histogram on a column exists that indicates a high-domain column, the SAP ASE server assumes that sort-based statistics are required on this column. If no previous histogram exists on a column, then the SAP ASE server assumes this column is low-domain until the high-domain limit is reached.

## 1.130 update table statistics

Updates statistics that are stored in `sysabstats` table, such as rowcount, cluster ratios, and so on. Does not affect column statistics stored in `sysstatistics`.

### Syntax

```
update table statistics <table_name>
    [partition <data_partition_name>]
    [<index_name> [partition <index_partition_name>]]
```



## Parameters

`<table_name>`

is the name of the table you are updating the statistics for.

`<data_partition_name>`

is the name of the data partition for which you are updating the statistics for. If you do not include this, table statistics for all the data partitions are updated.

`<index_name>`

is the name of index associated with the partition.

`<index_partition_name>`

is the name of the index partition.

## Examples

### Example 1

Performs a table statistics update on the `smallsales` partition:

```
update table statistics titles partition smallsales
```

### Example 2

Performs a table statistics update on all of the partitions in the `titles` table:

```
update table statistics titles
```

## Usage

- `update table statistics` does not update statistics for index partitions. To generate table-level statistics for index partitions, use `update statistics`.
- Because running `update table statistics` incurs the I/O cost of running `update statistics`, use `update statistics` to generate both column and table statistics. You can create, and then drop, a global index to generate global statistics. When you run `update statistics` on a single partition, you create global statistics by merging partition statistics. However, these merged global statistics are less accurate than the global statistics created as a side-effect of global index creation. Avoid generating column statistics that overwrite more accurate, earlier versions of column statistics. When you specify:
  - `<index_name>` – `update table statistics` updates statistics for all the index partitions of the index.
  - `<index_partition>` – `update table statistics` updates statistics for the specific index partition.

See also *Performance and Tuning Guide*.

## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

## Permissions

The permission checks for `update table statistics` differ based on your granular permissions settings.

Setting	Description
---------	-------------

<b>Enabled</b>	With granular permissions enabled, you must be the table owner, a user with <code>update statistics</code> permission on the table or a user with <code>manage any statistics</code> permission.
----------------	--

<b>Disabled</b>	With granular permissions disabled, you must be the table owner or a user with <code>update statistics</code> permission on the table.
-----------------	--

`update statistics` permission can be granted or transferred to anyone by the table owner or system administrator.

## Auditing

This command is not audited.

## Related Information

[update all statistics \[page 830\]](#)

[update index statistics \[page 834\]](#)

[update statistics \[page 839\]](#)

## 1.131 use

Specifies the database with which you want to work.

## Syntax

```
use <database_name>
```

## Parameters

`<database_name>`

is the name of the database to open.

## Examples

### Example 1

Specifies to use `pubs2` as the working database:

```
use pubs2
go
```

## Usage

- Allowed with an archive database.
- `use` cannot be included in a stored procedure or a trigger.
- `sp_addalias` adds an alias, which permits a user to use a database under another name to gain access to that database.

See also `sp_addalias` and `sp_adduser` in *Reference Manual: Procedures*.

## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

## Permissions

The permission checks for `use` differ based on your granular permissions settings.

Setting	Description
---------	-------------

Enabled	With granular permissions disabled, you must be a valid, alias, or guest user, or, a user with <code>own database privilege</code> or <code>use database privilege</code> on the database.
---------	--

If the database has a guest account, all users can use the database. If the database does not have a guest account, you must be a valid user in the database, have an alias in the database, or have `own database privilege` or `use database privilege` on the database.

Setting	Description
---------	-------------

<b>Disabled</b>	With granular permissions disabled, you must be a valid, alias, or guest user, or, a user with sa_role or sso_role.
-----------------	---

If the database has a "guest" account, all users can use the database. If the database does not have a "guest" account, you must be a valid user in the database, have an alias in the database, or be a system administrator or system security officer.

## Auditing

This command is not audited.

## Related Information

[create database \[page 140\]](#)

[drop database \[page 429\]](#)

## 1.132 waitfor

Specifies a specific time, a time interval, or an event for the execution of a statement block, stored procedure, or transaction.

## Syntax

```
waitfor {delay <time> | time <time> | errexit | processexit | mirroredit}
```

## Parameters

### delay

instructs the SAP ASE server to wait until the specified amount of time has passed, up to a maximum of 24 hours.

### time

instructs the SAP ASE server to wait until the specified time.

<time>

is a time in one of the acceptable formats for `date/time` data, or a variable of character type. You cannot specify dates—the date portion of the `date/time` value is not allowed. You can use the datatype `time` for this information.

#### **errorexit**

instructs the SAP ASE server to wait until a kernel or user process terminates abnormally.

#### **processexit**

instructs the SAP ASE server to wait until a kernel or user process terminates for any reason.

#### **mirrorexit**

instructs the SAP ASE server to wait for a mirror failure.

## Examples

### Example 1

At 2:20 p.m., the `chess` table is updated with my next move, and a procedure called `sendmail` inserts a row in a table owned by Judy, notifying her that a new move now exists in the `chess` table:

```
begin
  waitfor time "14:20"
  insert chess (next_move)
    values ('Q-KR5')
  execute sendmail 'judy'
end
```

### Example 2

After 10 seconds, the SAP ASE server prints the message specified:

```
declare @var char (8)
select @var = "00:00:10"
begin
  waitfor delay @var
  print "Ten seconds have passed. Your time
    is up."
end
```

### Example 3

After any process exits abnormally, the SAP ASE server prints the message specified:

```
begin
  waitfor errorexit
  print "Process exited abnormally!"
end
```

## Usage

- After issuing the `waitfor` command, you cannot use your connection to the SAP ASE server until the time or event that you specified occurs.

- You can use `waitfor errexit` with a procedure that kills the abnormally terminated process, to free system resources that would otherwise be taken up by an infected process.
- To find out which process terminated, check the `sysprocesses` table with `sp_who`.
- The time you specify with `waitfor time` or `waitfor delay` can include hours, minutes, and seconds. Use the format "hh:mi:ss", as described in *Date and Time Datatypes* in *Reference Manual: Building Blocks*. The following example instructs the SAP ASE server to wait until 4:23 p.m:

```
waitfor time "16:23"
```

This statement instructs the SAP ASE server to wait for 1 hour and 30 minutes:

```
waitfor delay "01:30"
```

- Changes in system time (such as setting the clock back for Daylight Savings Time) can delay the `waitfor` command.
- You can use `waitfor mirrorexit` within a DB-Library program to notify users when there is a mirror failure.

See also:

- *Date and Time Datatypes* in *Reference Manual: Building Blocks*
- `sp_who` in *Reference Manual: Procedures*

## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

## Permissions

No permission is required to use `waitfor`.

## Auditing

This command is not audited.

## Related Information

[begin...end \[page 114\]](#)

## 1.133 where Clause

Sets the search conditions in a `select`, `insert`, `update`, or `statement`.

### Syntax

Search conditions immediately follow the keyword `where` in a `select`, `insert`, `update`, or `delete` statement. If you use more than one search condition in a single statement, connect the conditions with `and` or `or`:

- `where [not] <expression> <comparison_operator> <expression>`
- `<expression> <comparison_operator> <expression> | {...}`
- `<expression> [not] like "where [not] where {[not] <match_string>"`  
`[escape "<escape_character>"]`
- `where {[not]where [not]where [not] <expression> is [not] null`
- `where [not] <expression> [not] between <expression> and <expression>`
- `where [not] <expression> [not] in ({<value_list> |< subquery>})`
- `where [not] exists (<subquery>)`
- `where [not] <expression> <comparison_operator> {any | all} (<subquery>)`
- `where [not] <column_name> <join_operator> <column_name>`
- `where [not] <logical_expression>`
- `where [not] <expression> {and | or} [not] <expression>`
- `where <column_name> is [not] null`

### Parameters

#### `not`

negates any logical expression or keywords such as `like`, `null`, `between`, `in`, and `exists`.

#### `<expression>`

is a column name, a constant, a function, a subquery, or any combination of column names, constants, and functions connected by arithmetic or bitwise operators. For more information about expressions, see *Expressions in Reference Manual: Building Blocks*.

#### `<comparison_operator>`

is one of the following operators:

=	Equal to
>	Greater than
<	Less than
>=	Greater than or equal to
<=	Less than or equal to
!=	Not equal to
<>	Not equal to
!>	Not greater than
!<	Not less than

In comparing `char`, `nchar`, `unichar`, `varchar`, `univarchar`, and `nvarchar` data, `<` means closer to the beginning of the alphabet and `>` means closer to the end of the alphabet.

Case and special character evaluations depend on the collating sequence of the operating system on the machine on which the SAP ASE server is located. For example, lowercase letters may be greater than uppercase letters, and uppercase letters may be greater than numbers.

Trailing blanks are ignored for the purposes of comparison. For example, `"Dirk"` is the same as `"Dirk "`.

In comparing dates, `<` means earlier and `>` means later. Put quotes around all character and date data used with a comparison operator. For example:

```
= "Bennet"  
> "94609"
```

See *User-Defined Datatypes* in *Reference Manual: Building Blocks* for more information about data entry rules.

## **like**

is a keyword indicating that the following character string (enclosed by single or double quotes) is a matching pattern. `like` is available for `char`, `varchar`, `unichar`, `univarchar`, `nchar`, `nvarchar`, `datetime`, `date` and `time`, `text`, and `unitext` columns, but not to search for seconds or milliseconds.

You can use the keyword `like` and wildcard characters with `datetime` and `date` data as well as with `char` and `varchar`. When you use `like` with `datetime` or `date` and `time` values, the SAP ASE server converts the dates to standard `datetime` format, then to `varchar`. Since the standard storage format does not include seconds or milliseconds, you cannot search for seconds or milliseconds with `like` and a pattern.



It is a good idea to use `like` when you search for `date/time` values, since `date/time` entries may contain a variety of date parts. For example, if you insert the value "9:20" into a column named `arrival_time`, the following clause would not find it because the SAP ASE server converts the entry into "Jan 1, 1900 9:20AM.":

```
where arrival_time = '9:20'
```

However, the following clause would find it:

```
where arrival_time like '%9:20%'
```

### <match\_string>

is a string of characters and wildcard characters enclosed in quotes. The wildcard characters are:

- % Any string of 0 or more characters.
- Any single character.
- [ ] Any single character within the specified range ([a-f]) or set ([abcdef]).
- [^] Any single character that is not within the specified range ([^a-f]) or set ([^abcdef]).

### escape

specifies an escape character with which you can search for literal occurrences of wildcard characters.

### <escape\_character>

is any single character. See *Using the escape Clause in Reference Manual: Building Blocks*.

### is null

searches for null values.

### between

is the range-start keyword. Use `and` for the range-end value. The following range is inclusive:

```
where @val between x and y
```

The following range is not:

```
x and @val < y
```

Queries using `between` return no rows if the first value specified is greater than the second value.

### and

joins two conditions and returns results when both of the conditions are true.

When more than one logical operator is used in a statement, `and` operators are usually evaluated first. However, you can change the order of execution with parentheses.

### in

allows you to select values that match any one of a list of values. The comparator can be a constant or a column name, and the list can be a set of constants or, more commonly, a subquery. For information on using `in` with a subquery, see the *Transact-SQL User's Guide*. Enclose the list of values in parentheses.

#### <value\_list>

is a list of values. Put single or double quotes around character values, and separate each value from the following one with a comma (see example 7). The list can be a list of variables, for example:

```
in (@a, @b, @c)
```

However, you cannot use a variable containing a list, such as the following, for a values list:

```
@a = "'1', '2', '3'"
```

#### **exists**

is used with a subquery to test for the existence of some result from the subquery. See the *Transact-SQL User's Guide*.

#### <subquery>

is a restricted `select` statement (`order by` and `compute` clauses and the keyword `into` are not allowed) inside the `where` or `having` clause of a `select`, `insert`, `delete`, or `update` statement, or a subquery. See the *Transact-SQL User's Guide*.

#### **any**

is used with `>`, `<`, or `=` and a subquery. It returns results when any value retrieved in the subquery matches the value in the `where` or `having` clause of the outer statement. See the *Transact-SQL User's Guide*.

#### **all**

is used with `>` or `<` and a subquery. It returns results when all values retrieved in the subquery match the value in the `where` or `having` clause of the outer statement. See the *Transact-SQL User's Guide*.

#### <column\_name>

is the name of the column used in the comparison. Qualify the column name with its table or view name if there is any ambiguity. For columns with the `IDENTITY` property, you can specify the `syb_identity` keyword, qualified by a table name where necessary, rather than the actual column name.

<column\_name> allows `text`, `unitext`, or `image` datatypes.

#### <join\_operator>

is a comparison operator or one of the join operators `=*` or `*=`. See the *Transact-SQL User's Guide*.

#### <logical\_expression>

is an expression that returns `TRUE` or `FALSE`.

#### **or**

joins two conditions and returns results when either of the conditions is true.

When more than one logical operator is used in a statement, `or` operators are normally evaluated after `and` operators. However, you can change the order of execution with parentheses.

## Examples

### Example 1

```
where advance * $2 > total_sales * price
```

### Example 2

Finds all the rows in which the phone number does not begin with 415:

```
where phone not like '415%'
```

### Example 3

Finds the rows for authors named Carson, Carsen, Karsen, and Karson:

```
where au_lname like "[CK]ars[eo]n"
```

### Example 4

Finds the row of the `sales_east` table in which the `IDENTITY` column has a value of 4:

```
where sales_east.syb_identity = 4
```

### Example 5

```
where advance < $5000 or advance is null
```

### Example 6

```
where (type = "business" or type = "psychology") and advance > $5500
```

### Example 7

```
where total_sales between 4095 and 12000
```

### Example 8

Finds the rows in which the state is one of the three in the list:

```
where state in ('CA', 'IN', 'MD')
```

### Example 9

Selects data based on null values of `text`, `unitext`, and `image` columns:

```
create table temp1(c1 int, c2 text null, c3 unitext null, c4 image null)
insert into temp1 values(1, null, replicate("u",5), null)
insert into temp1 values(2, replicate("x",3), null, null)
go
select * from temp1 where c2 is null
go
```

c1	c2	c3	c4
----	----	----	----

```

-----
1      NULL      0x7500750075007500      NULL
(1 row affected)

```

```

select * from temp1 where c2 is not null and c3 is null and c4 is null
go

```

```

c1      c2      c3      c4
-----
2      xxx      NULL      NULL

```

### Example 10

Updates data based on non-null values of text column:

```

insert into temp1 values(3, replicate("y", 3), null, 0x858585847474)
insert into temp1 values(4, replicate("z",3),"aaa", 0x75)
go
update temp1 set c2 = "updated" where c2 is not null
select * from temp1 where c2 is not null
go

```

```

(3 rows affected)
c1      c2      c3      c4
-----
2      updated  NULL  NULL
3      updated  NULL  0x858585847474
4      updated  0x610061006100  0x75

```

### Example 11

Selects data into table temp2 based on null values of text column in temp1:

```

select c1, c2 into temp2 from temp1 where c2 is null
select * from temp2
go

```

```

(1 row affected)
c1      c2
-----
1      NULL

```

### Example 12

Inserts data into table temp2, selecting from temp1, based on non-null values of text column in temp1:

```

insert into temp2 select c1, c2 from temp1 where c2 is not null
select * from temp2
go

```

```

(3 rows affected)
c1      c2
-----
1      NULL
2      updated
3      updated
4      updated
(4 rows affected)

```

### Example 13

Selects data in a subquery based on null value of `text` column:

```
select count(*) from temp2
where c1 in (select c1 from temp1 where c2 is null and c3 is not null)
```

```
-----
              1
(1 row affected)
```

### Example 14

Deletes data based on null value of `unitext` column:

```
delete from temp1 where c3 is null
go
```

```
(2 rows affected)
```

## Usage

- `where` and `having` search conditions are identical, except that aggregate functions are not permitted in `where` clauses. For example, this clause is legal:

```
having avg (price) > 20
```

This clause is not legal:

```
where avg (price) > 20
```

For examples, see *Transact-SQL Functions in Reference Manual: Building Blocks* for information on the use of aggregate functions, and `group by` and `having` clauses.

- Joins and subqueries are specified in the search conditions; see the *Transact-SQL User's Guide* for full details.
- You can use the keyword `like` to search a `unitext` column for a specific pattern. However, the `like` clause is not optimized when it is used with a `unitext` column. `like` pattern matching for `unitext` depends on the default Unicode sort order, which is also used for `like` pattern matching for `unicar` and `univarchar` datatypes.
- The `where` clause accepts `text` and `unitext` LOB locators, but not `image` LOB locators, for the variables `<expression>` and `<match_string>`.

```
...
where <expression> like '<match_string>'
...
```

When `<match_string>` is a locator, the SAP ASE server uses only up to 16KB of the corresponding LOB.

- Specifying the null condition selects only those rows with a null value in the specified LOB column. The LOB value may be null either because it was explicitly assigned a null value, or because the LOB was not initialized.
- The number of `and` and `or` conditions in a `where` clause is limited only by the amount of memory available to run the query.

- The pattern string included in the `like` predicate is limited only by the size of string that can be placed in a `varchar`.
- There are two ways to specify literal quotes within a `char` or `varchar` entry. The first method is to use two quotes. For example, if you began a character entry with a single quote, and you want to include a single quote as part of the entry, use two single quotes:

```
'I don''t understand.'
```

Or use double quotes:

```
"He said, ""It's not really confusing."""
```

The second method is to enclose a quote in the opposite kind of quotation mark. In other words, surround an entry containing double quotes with single quotes (or vice versa). Here are some examples:

```
'George said, "There must be a better way."
"Isn't there a better way?"
'George asked, "Isn"t there a better way?"'
```

- To enter a character string that is longer than the width of your screen, enter a backslash (`\`) before going to the next line.
- If a column is compared to a constant or variable in a `where` clause, the SAP ASE server converts the constant or variable into the datatype of the column so that the optimizer can use the index for data retrieval. For example, `float` expressions are converted to `int` when compared to an `int` column. For example:

```
where int_column = 2
```

selects rows where `<int_column> = 2`.

- When the SAP ASE server optimizes queries, it evaluates the search conditions in `where` and `having` clauses, and determines which conditions are search arguments (SARGs) that can be used to choose the best indexes and query plan. All of the search conditions are used to qualify the rows. For more information on search arguments, see the *Performance and Tuning Guide*.

See also:

- *Date and Time Datatypes* in *Reference Manual: Building Blocks*
- `sp_helpjoins` in *Reference Manual: Procedures*

## Standards

ANSI SQL – Compliance level: Entry-level compliant.

## Auditing

This command is not audited.

## Related Information

[delete](#) [page 391]

[execute](#) [page 506]

[insert](#) [page 572]

[group by and having Clauses](#) [page 558]

[select](#) [page 696]

[update](#) [page 819]

## 1.134 while

Sets a condition for the repeated execution of a statement or statement block. The statements are executed repeatedly, as long as the specified condition is true.

### Syntax

```
while <logical_expression> [plan "<abstract plan>"] <statement>
```

### Parameters

**<logical\_expression>**

is any expression that returns TRUE, FALSE, or NULL.

**plan "<abstract plan>"**

specifies the abstract plan to use to optimize the query. It can be a full or partial plan, specified in the abstract plan language. Plans can only be specified for optimizable SQL statements, that is, queries that access tables. See *Creating and Using Abstract Plans* in the *Performance and Tuning Series: Query Processing and Abstract Plans* for more information.

**<statement>**

can be a single SQL statement, but is usually a block of SQL statements delimited by `begin` and `end`.

### Examples

#### Example 1

If the average price is less than \$30, double the prices of all books in the `titles` table. As long as it is still less than \$30, the `while` loop keeps doubling the prices. In addition to determining the titles whose price

exceeds \$20, the `select` inside the `while` loop indicates how many loops were completed (each average result returned by the SAP ASE server indicates one loop):

```
while (select avg (price) from titles) < $30
begin
    select title_id, price
        from titles
        where price > $20
    update titles
        set price = price * 2
end
```

## Usage

- The execution of statements in the `while` loop can be controlled from inside the loop with the `break` and `continue` commands.
- The `continue` command causes the `while` loop to restart, skipping any statements after the `continue`. The `break` command causes an exit from the `while` loop. Any statements that appear after the keyword `end`, which marks the end of the loop, are executed. The `break` and `continue` commands are often activated by `if` tests.

For example:

```
while (select avg (price) from titles) < $30
begin
    update titles
        set price = price * 2
    if (select max (price) from titles) > $50
        break
    else
        if (select avg (price) from titles) > $30
            continue
        print "Average price still under $30"
end
select title_id, price from titles
    where price > $30
```

This batch continues to double the prices of all books in the `titles` table as long as the average book price is less than \$30. However, if any book price exceeds \$50, the `break` command stops the `while` loop. The `continue` command prevents the `print` statement from executing if the average exceeds \$30. Regardless of how the `while` loop terminates (either normally or because of the `break` command), the last query indicates which books are priced over \$30.

- If two or more `while` loops are nested, the `break` command exits to the next outermost loop. All the statements after the end of the inner loop run, then the next outermost loop restarts.

### ⚠ Caution

If a `create table` or `create view` command occurs within a `while` loop, the SAP ASE server creates the schema for the table or view before determining whether the condition is true. This may lead to errors if the table or view already exists.



## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

## Permissions

No permission is required to use `while`.

## Auditing

This command is not audited.

## Related Information

[begin...end \[page 114\]](#)

[break \[page 118\]](#)

[continue \[page 136\]](#)

[goto label \[page 519\]](#)

## 1.135 writetext

Permits minimally logged, interactive updating of an existing `text`, `unitext` or `image` column.

### Syntax

```
writetext [[<database>.<owner>.]<table_name>.<column_name>  
          <text_pointer> [readpast] [with log] <data>
```

### Parameters

**<table\_name>.<column\_name>**

is the name of the table and `text`, `unitext` or `image` column to update. Specify the database name if the table is in another database, and specify the owner's name if

more than one table of that name exists in the database. The default value for `<owner>` is the current user, and the default value for `<database>` is the current database.

#### `<text_pointer>`

a `varbinary (16)` value that stores the pointer to the `text`, `unitext` or `image` data. Use the `textptr` function to determine this value. `text`, `unitext` or `image` data is not stored in the same set of linked pages as other table columns. It is stored in a separate set of linked pages. A pointer to the actual location is stored with the data; `textptr` returns this pointer.

#### `readpast`

specifies that the command should modify only unlocked rows. If the `writetext` command finds locked rows, it skips them, rather than waiting for the locks to be released.

The `readpast` option applies only to data-only-locked tables. `readpast` is ignored if it is specified for an allpages-locked table.

If the session-wide isolation level is 3, the `readpast` option is silently ignored.

If the transaction isolation level for a session is 0, `writetext` commands using `readpast` do not issue warning messages. These commands at session isolation level 0 modify the specified text column if the text column is not locked with incompatible locks.

#### `with log`

logs the inserted `text`, `unitext` or `image` data. The use of this option aids media recovery, but logging large blocks of data quickly increases the size of the transaction log, so make sure that the transaction log resides on a separate database device. See `create database`, `sp_logdevice`, and the *System Administration Guide* for details.

#### `<data>`

is the data to write into the `text`, `unitext` or `image` column. `text` and `unitext` data must be enclosed in quotes. `image` data must be preceded by "0x". Check the information about the client software you are using to determine the maximum length of `text`, `unitext` or `image` data that can be accommodated by the client.

## Examples

### Example 1

Puts the text pointer into the local variable `@<val>`. Then, `writetext` places the text string "hello world" into the text field pointed to by `@<val>`:

```
declare @val varbinary (16)
select @val = textptr (copy) from blurbs
    where au_id = "409-56-7008"
writetext blurbs.copy @val with log "hello world"
```

### Example 2

```
declare @val varbinary (16)
```

```
select @val = textptr (copy)
from blurbs readpast
  where au_id = "409-56-7008"
writetext blurbs.copy @val readpast with log "hello world"
```

### Example 3

writetext includes information about unitext datatypes, and places the string "Hello world" into the unitext field that <@val> points to:

```
declare @val varbinary (16)
select @val = textptr (ut) from unitable
where i = 100
writetext unitable.ut @val with log "Hello world"
```

The varchar constant is implicitly converted to unitext before the column is updated.

## Usage

- The maximum length of text that can be inserted interactively with writetext is approximately 120K bytes for text, unitext or image data.
- By default, writetext is a minimally logged operation; only page allocations and deallocations are logged, but the text, unitext or image data is not logged when it is written into the database. To use writetext in its default, minimally logged state, a system administrator must use sp\_dboption to set select into/bulkcopy/pllsort to true.
- writetext logs operations on in-row LOB columns.
- You can run the writetext command (with or without the with log parameter) simultaneously with the online parameter.
- writetext updates text data in an existing row. The update completely replaces all of the existing text.
- writetext operations are not caught by an insert or update trigger and for this reason, updating with writetext does not result in an update of the row timestamp.
- writetext requires a valid text pointer to the text, unitext or image column. For a valid text pointer to exist, a text, or unitext column must contain either actual data or a null value that has been explicitly entered with update.

Given the table textnull with columns textid and <x>, where <x> is a text column that permits nulls, this update sets all the text values to NULL and assigns a valid text pointer in the text column:

```
update textnull
set x = null
```

No text pointer results from an insert of an explicit null:

```
insert textnull values (2,null)
```

And, no text pointer results from an insert of an implicit null:

```
insert textnull (textid)
values (2)
```

- insert and update on text columns are logged operations.
- You cannot use writetext on text and image columns in views.

- If you attempt to use `writetext` on `text` values after changing to a multibyte character set, and you have not run `dbcc fix_text`, the command fails, and an error message is generated, instructing you to run `dbcc fix_text` on the table.
- `writetext` in its default, non-logged mode runs more slowly while a `dump` database is taking place.
- The Client-Library functions `dbwritetext` and `dbmoretext` are faster and use less dynamic memory than `writetext`. These functions can insert up to 2 GB of `text` data.

See also *Converting text and image Datatypes* in *Reference Manual: Building Blocks*.

## Standards

ANSI SQL – Compliance level: Transact-SQL extension.

## Permissions

You must be the table owner or a user with `update` permission to run `writetext`.

## Auditing

This command is not audited.

## Related Information

[readtext \[page 653\]](#)

## 2 Interactive SQL Commands

Enter Interactive SQL commands in the top pane of the Interactive SQL display. These commands are intended only for Interactive SQL and are not sent to the SAP ASE server for execution.

For information about Interactive SQL, see *Using Interactive SQL* in the *Utility Guide*.

### 2.1 clear

Clears the Interactive SQL panes.

#### Syntax

```
clear
```

#### Usage

Use the `clear` statement to clear the SQL Statements and Messages panes and the Results, Messages, Plan, and Plan tabs in the Results pane.

`clear` closes the cursor associated with the data being cleared.

#### Permissions

Any user can execute this command.

## 2.2 configure

Opens the Interactive SQL Options dialog.

### Syntax

```
configure
```

### Usage

The `configure` statement opens the Interactive SQL Options dialog and displays the current settings of all Interactive SQL options. It does not display or allow you to modify database options.

You can configure Interactive SQL settings in this dialog. If you select Make Permanent, the options are saved for use in subsequent Interactive SQL sessions. If you do not choose Make Permanent, and instead click OK, the options are set temporarily and remain in effect for the current database connection only.

### Permissions

Any user can run `configure`.

### Related Information

[set \[page 732\]](#)

## 2.3 connect

Establishes a connection to a database.

### Syntax

```
connect
```

```
[to <engine_name>]
[database <database_name>]
[as <connection_name>]
[user] <user_id> identified by password
<engine_name>, <database_name>, <connection_name>, <user_id>,
  <password> : {<identifier> | <string> | <hostvar>}
```

```
connect using <connect_string> : {<identifier> | <string> | <hostvar>}
```

## Parameters

### <engine\_name>

is the name of the engine to which you are connecting.

### <database\_name>

is the name of the database to which you are connecting. It must conform to the rules for identifiers and cannot be a variable.

### as

you can optionally name a connection by specifying the `as` clause. This allows multiple connections to the same database, or multiple connections to the same or different database servers, all simultaneously. Each connection has its own associated transaction. You may get locking conflicts between your transactions if, for example, you modify the same record in the same database from two different connections.

### <connection\_name>

is the login name you are using to make the connection.

### user

indicates that you are connecting to the SAP ASE server as a user.

### <user\_id>

is the ID of the user who is connecting.

### identified by password

indicates that the user needs to include a password when they connect.

### <password>

is the password of the user connecting to the SAP ASE server.

### <identifier>

is the identifier you are using for the connection information.

### <string>

is the string you are using for the connection information.

### <hostvar>

is the variable information for the host name and port.

### <connect\_string>

is a list of parameter settings of the form `<keyword> = <value>`, separated by semicolons, and must be enclosed in single quotes.

## Examples

### Example 1

Connects to a database from Interactive SQL. Interactive SQL prompts for a user ID and a password:

```
connect
```

### Example 2

Connects to the default database as DBA from Interactive SQL. Interactive SQL prompts for a password:

```
connect user "DBA"
```

### Example 3

As user `dba`, with password `sql`, connects to the `pubs2` database of an SAP ASE server running on host "tribble" at port number 5000:

```
connect to "tribble:5000"  
database pubs2  
user dba  
identified by sql
```

### Example 4

As user `dba`, with password `sql`, connects to an SAP ASE server named "tribble" (defined in `interfaces` file):

```
connect to tribble  
user dba  
identified by sql
```

## Usage

- `connect` establishes a connection to the database identified by `<database_name>` running on the server identified by `<engine_name>`.
- No statements are allowed until a successful `connect` statement has been executed.
- Interactive SQL behavior – if you do not specify a database or server in the `connect` statement, Interactive SQL remains connected to the current database, rather than to the default server and database. If you do specify a database name without a server name, Interactive SQL attempts to connect to the specified database on the current server. If you specify a server name without a database name, Interactive SQL connects to the default database on the specified server.
- In the user interface, if the password or the user ID and password are not specified, the user is prompted to type the missing information.
- When Interactive SQL is running in command-prompt mode (`-nogui` is specified when you start Interactive SQL from a command prompt) or batch mode, or if you execute `connect` without an `as` clause, an unnamed connection is opened. If there is another unnamed connection already opened, the old one is automatically closed. Otherwise, existing connections are not closed when you run `connect`.
- Multiple connections are managed through the concept of a current connection. After a successful `connect` statement, the new connection becomes the current one. To switch to a different connection, use the `set connection` statement. Use the `disconnect` statement to drop connections.



- In Interactive SQL, the connection information (including the database name, your user ID, and the database server) appears in the title bar above the SQL Statements pane. If you are not connected to a database, Not Connected appears in the title bar.

## Permissions

Any user can execute this command.

## Related Information

[disconnect](#) [page 873]

[set connection](#) [page 886]

## 2.4 disconnect

Drops the current connection to a database.

### Syntax

```
disconnect [{<identifier> | <string> | <hostvar>} | current | all]
```

### Parameters

{<identifier> | <string> | <hostvar>}

is the login name you are using to make the connection.

- <identifier> – is the identifier you are using for the connection information.
- <string> – is the string you are using for the connection information.
- <hostvar> – is the variable information for the host name and port.

**current**

indicates that you are disconnecting the current connection.

**all**

indicates that you are disconnecting all connections.

## Examples

### Example 1

Disconnects all connections:

```
disconnect all
```

## Usage

`disconnect` drops a connection to the database server and releases all resources used by it. If the connection to be dropped was named on the `connect` statement, the name can be specified. Specifying `all` drops all of the application's connections to all database environments. `current` is the default, and drops the current connection.

An implicit `rollback` is executed on connections that are dropped.

## Permissions

Any user can execute this command.

## Related Information

[connect \[page 870\]](#)

[set connection \[page 886\]](#)

## 2.5 exit

Leaves Interactive SQL.

## Syntax

```
{exit | quit | bye} [{<number> | <connection_variable>}]
```

## Parameters

`exit | quit | bye`

closes your connection with the database, then closes the Interactive SQL environment.

`{<number> | <connection_variable>}`

can be used in batch files to indicate success or failure of the commands in an Interactive SQL command file. The default return code is 0.

- `<number>` – is the number of the return code.
- `<connection_variable>` – is a variable indicating a specific connection.

## Usage

Before closing the database connection, Interactive SQL automatically executes a `commit` statement if the `commit_on_exit` option is set to on. If this option is set to off, Interactive SQL performs an implicit `rollback`. By default, the `commit_on_exit` option is set to on.

## Permissions

Any user can execute this command.

## 2.6 input

Imports data into a database table from an external file or from the keyboard.

## Syntax

```
input into [ <owner>.<table_name>
  [ from <filename> | prompt]
  [ format { ascii | dbase | dbase11 | dbase111 | excel | fixed | foxpro |
lotus } ]
  [ escape character <character>]
  [ escapes { on | off } ]
  [ by order | by name ]
  [ delimited by string ]
  [ column widths (integer , . . . ) ]
  [ nostrip ]
  [ ( <column_name>, . . . ) ]
  [ encoding {<identifier> | <string>}]
```

## Parameters

### from clause

is the file name that is passed to the server as a quoted string. The string is therefore subject to the same formatting requirements as other SQL strings. In particular:

- To indicate directory paths, you must represent the backslash character (\) by two backslashes. To load data from the file `c: emp\input.dat` into the `employee` table:

```
input into employee
from 'c: nn temp nn input.dat'
```

- The path name is relative to the machine on which Interactive SQL is running.

### prompt

allows the user to enter values for each column in a row. When running in windowed mode, a dialog appears where the user can enter the values for the new row. If the user is running Interactive SQL on the command line, Interactive SQL prompts the user to type the value for each column on the command line.

### format

each set of values must be in the format specified by the `format` clause, or the `set option input_format` statement if the `format` clause is not specified. When input is entered by the user, a dialog is provided for the user to enter one row per line in the input format.

Certain file formats contain information about column names and types.

Using this information, the `input` statement creates the database table if it does not already exist. This is a very easy way to load data into the database. The formats that have enough information to create the table are: `dbase11`, `dbase111`, `foxpro`, and `lotus`.

Input from a command file is terminated by a line containing `end`. Input from a file is terminated at the end of the file.

Allowable `input` formats are:

- `ascii` – input lines are assumed to be ASCII characters, one row per line, with values separated by commas. Alphabetic strings may be enclosed in apostrophes (single quotes) or quotation marks (double quotes). Strings containing commas must be enclosed in either single or double quotes. If the string itself contains single or double quotes, double the quote character to use it within the string. Optionally, you can use the `delimited by` clause to specify a delimiter string other than the default, which is a comma.  
Three other special sequences are also recognized. The two characters represent a new line character, “\”, represents a single (\), and the sequence `\xDD` represents the character with hexadecimal code `DD`.
- `dbase` – the file is in DBASEII or DBASEIII format. Interactive SQL attempts to determine which format, based on information in the file. If the table does not exist, it is created.
- `dbase11` – the file is in DBASEII format. If the table does not exist, it is created.

- `dbase111` – the file is in DBASEIII format. If the table does not exist, it is created.
- `excel` – input file is in the format of Microsoft Excel 2.1. If the table does not exist, it is created.
- `fixed` – input lines are in fixed format. Use the `column widths` clause to specify column widths. If they are not specified, column widths in the file must be the same as the maximum number of characters required by any value of the corresponding database column's type.  
You cannot use the `fixed` format with binary columns that contain embedded new line and End of File character sequences.
- `foxpro` – the file is in FoxPro format. If the table does not exist, it is created.
- `lotus` – the file is a Lotus WKS format worksheet. `input` assumes that the first row in the Lotus WKS format worksheet is column names. If the table does not exist, it is created. In this case, the types and sizes of the columns created may not be correct because the information in the file pertains to a cell, not to a column.

### escape character

is the default escape character for hexadecimal codes and symbols is a backslash (`\`), so `\x0A` is the linefeed character, for example.

You can change the escape character using the `escape character` clause. For example, to use the exclamation mark as the escape character, enter:

```
... escape character '!'
```

Only one single-byte character can be used as an escape character.

### escapes

with `escapes` enabled (the default), characters following the backslash character are recognized and interpreted as special characters by the database server. New line characters can be included as the combination `\n`, other characters can be included in data as hexadecimal ASCII codes, such as `\x09` for the tab character. A sequence of two backslash characters (`\\`) is interpreted as a single backslash. A backslash followed by any character other than `n`, `x`, `X` or `\` is interpreted as two separate characters. For example, `\q` inserts a backslash and the letter `q`.

### by

allows the user to specify whether the columns from the input file should be matched up with the table columns based on their ordinal position in the lists (`order`, the default) or by their names (`name`). Not all input formats have column name information in the file. `name` is allowed only for those formats that do. They are the same formats that allow automatic table creation: `dbase11`, `dbase111`, `foxpro`, and `lotus`.

### delimited

allows you to specify a string to be used as the delimiter in ASCII input format.

### column widths

can be specified for `fixed` format only; it specifies the widths of the columns in the input file. If `column widths` is not specified, the widths are determined by the database column types. Do not use this clause if you are inserting `long varchar` or `binary` data in `fixed` format.

### nostrip

normally, for ASCII input format, trailing blanks are stripped from unquoted strings before the value is inserted. `nostrip` can be used to suppress trailing blank stripping. Trailing blanks are not stripped from quoted strings, regardless of whether the option is used. Leading blanks are stripped from unquoted strings, regardless of the `nostrip` option setting.

If the ASCII file has entries such that a column appears to be null, it is treated as NULL. If the column in that position cannot be NULL, a zero is inserted in numeric columns, and an empty string in character columns.

## encoding

allows you to specify the encoding that is used to read the file. `encoding` can be used only with the ASCII format.

If `encoding` is not specified, Interactive SQL determines the code page that is used to read the file as follows, where code page values occurring earlier in the list take precedence over those occurring later in the list:

- The code page specified with the `default_isql_encoding` option (if this option is set)
- The code page specified with the `-codepage` option when Interactive SQL was started
- The default code page for the computer Interactive SQL is running on

## Examples

### Example 1

Imports data into the table `employees` from the ASCII text file `new_emp.inp`:

```
input into employee
from new_emp.inp
format ASCII
```

## Usage

- The `input` statement allows efficient mass insertion into a named database table. Lines of input are read either from the user via an input window (if `prompt` is specified) or from a file (if you specify `from <file_name>`). If neither is specified, the input is read from the command file that contains the `input` statement. In Interactive SQL, this can even be directly from the SQL Statements pane. In this case, input is ended with a line containing only the string `end`.
- If a column list is specified for any input format, the data is inserted into the specified columns of the named table. By default, the `input` statement assumes that column values in the input file appear in the same order in which they appear in the database table definition. If the input file's column order is different, you must list the input file's actual column order at the end of the `input` statement.

In this example, you create a table called `inventory`. To import ASCII data from the input file that contains the name value before the quantity value, you must list the input file's actual column order at the end of the `input` statement for the data to be inserted correctly:

```
create table inventory (  
  quantity int,  
  item varchar(60)  
)
```

The ASCII data from the input file `stock.txt` that contains the name value before the quantity value:

```
'Shirts', 100  
'Shorts', 60
```

The input file's actual column order at the end of the `input` statement for the data to be inserted correctly:

```
input into inventory  
from stock.txt  
FORMAT ASCII  
(item, quantity)
```

- By default, `input` stops when it attempts to insert a row that causes an error. Errors can be treated in different ways by setting the `on_error` and `conversion_error` options. Interactive SQL prints a warning in the Messages pane if any string values are truncated on `input`. Missing values for NOT NULL columns are set to zero for numeric types and to the empty string for non-numeric types. If `input` attempts to insert a NULL row, the input file contains an empty row.

## Permissions

You must have `insert` permission on the table or view.

## 2.7 output

Imports data into a database table from an external file or from the keyboard.

### Syntax

```
output to <filename>  
  [ append ]  
  [ verbose ]  
  [ format {ascii | dbase | dbase11| dbase111  
           | excel | fixed | foxpro | lotus | sql | xml}]  
  [ escape character <character> ]  
  [ escapes { on | off }  
  [ delimited by string ]  
  [ quote string [ all ] ]  
  [ column widths (integer , . . . ) ]
```

```
[ hexadecimal { on | off | asis } ]  
[ encoding {<string> | <identifier>}]
```

## Parameters

### append

appends the results of the query to the end of an existing output file without overwriting the previous contents of the file. If the `append` clause is not used, the `output` statement overwrites the contents of the output file by default. The `append` keyword is valid if the output format is ASCII, `fixed`, or SQL.

### verbose

Writes error messages about the query, the SQL statement used to select the data, and the data itself to the output file. Lines that do not contain data are prefixed by two hyphens. If you omit `verbose` (the default) only the data is written to the file. `verbose` is valid if the output format is ASCII, `fixed`, or SQL. Allowable output formats are:

- `ascii` – the output is an ASCII format file with one row per line in the file. All values are separated by commas, and strings are enclosed in apostrophes (single quotes). You can change the delimiter and quote strings using the `delimited by` and `quote` clauses. If `all` is specified in the `quote` clause, all values (not just strings) are quoted.  
Three other special sequences are also used. The two characters represent a new line character, “\”, represents a single \, and the sequence `\xDD` represents the character with hexadecimal code DD. This is the default output format.
- `dbase11` – the output is in DBASEII, which includes column definitions. A maximum of 32 columns can be output. Column names are truncated to 11 characters, and each row of data in each. If the table does not exist, it is created.
- `dbase111` – the output is a dBASE III format file, which includes column definitions. A maximum of 128 columns can be output. Column names are truncated to 11 characters, and each row of data in each column is truncated to 255 characters.
- `excel` – the output is an Excel 2.1 worksheet. The first row of the worksheet contains column labels (or names if there are no labels defined). Subsequent worksheet rows contain the actual table data.
- `fixed` – the output is fixed format with each column having a fixed width. You can specify the width for each column with `column widths`. No column headings are output in this format.  
If the `column widths` clause is omitted, the width for each column is computed from the datatype for the column, and is large enough to hold any value of that datatype. The exception is that `long varchar` and `long binary` data default to 32K.
- `foxpro` – the output is a FoxPro format file, which includes column definitions. A maximum of 128 columns can be output. Column names are truncated to 11 characters. Column names are truncated to 11 characters, and each row of data in each column is truncated to 255 characters.
- `html` – the output is in the HyperText Markup Language format.



- `lotus` – the output is a Lotus WKS format worksheet. Column names are placed as the first row in the worksheet. There are certain restrictions on the maximum size of Lotus WKS format worksheets that other software (such as Lotus 1-2-3) can load. There is no limit to the size of file Interactive SQL can produce.
- `SQL` – the output is an Interactive SQL input statement required to recreate the information in the table.
- `XML` – the output is an XML file encoded in UTF-8 and containing an embedded DTD. Binary values are encoded in CDATA blocks with the binary data rendered as 2-hex-digit strings. The `input` statement does not accept XML as a file format.

### escape character

is the default escape character for characters stored as hexadecimal codes and symbols is a backslash (`\`), so, for example, `\x0A` is the linefeed character.

You can change the default escape character using `escape character`. For example, to use the exclamation mark as the escape character, enter:

```
... escape character '!'
```

### escapes

if enabled (the default), characters following the backslash character are recognized and interpreted as special characters by the database server. New line characters can be included as the combination `\n`, and other characters can be included in data as hexadecimal ASCII codes, such as `\x09` for the tab character. A sequence of two backslash characters (`\`) is interpreted as a single backslash. A backslash followed by any character other than `n`, `x`, `X` or `\` is interpreted as two separate characters. For example, `\q` inserts a backslash and the letter `q`.

### delimited by

for the ASCII output format only. The delimiter string is placed between columns (default comma).

### quote

for the ASCII output format only. The quote string is placed around string values. The default is a single quote character. If `all` is specified in the `quote` clause, the quote string is placed around all values, not just around strings.

### column width

specifies the column widths for the `fixed` format output

### hexidecimal

specifies how binary data is to be unloaded for the ASCII format only. When set to `on`, binary data is unloaded in the format `0xabcd`. When set to `off`, binary data is escaped when unloaded (`\xab\xcd`). When set to `asis`, values are written as is, that is, without any escaping—even if the value contains control characters. `asis` is useful for text that contains formatting characters such as tabs or carriage returns.

### encoding

allows you to specify the encoding that is used to write the file. `encoding` can be used only with the ASCII format.

If `encoding` is not specified, Interactive SQL determines the code page that is used to write the file as follows, where code page values occurring earlier in the list take precedence over those occurring later in the list:

- The code page specified with `default_isql_encoding` (if this option is set)
- The code page specified with the `-codepage` option when Interactive SQL was started
- The default code page for the computer Interactive SQL is running

## Examples

### Example 1

Places the contents of the employee table in a file in ASCII format:

```
select *
    from employee
go
output to employee.txt
    format ASCII
```

### Example 2

Places the contents of the employee table at the end of an existing file, and includes any messages about the query in this file as well:

```
select *
    from employee
go
output to employee.txt append verbose
```

### Example 3

In this example, you need to export a value that contains an embedded line feed character. A line feed character has the numeric value 10, which you can represent as the string `'\x0a'` in a SQL statement. If you execute the following statement, with `hexadecimal` set to `on`:

```
select 'line1 n x0aline2'
go
output to file.txt hexadecimal on
```

You see a file with one line in it containing the following text:

```
line10x0aline2
```

However, if you execute the same statement with `hexadecimal` set to `off`, you see the following:

```
line1 n x0aline2
```

Finally, if you set `hexadecimal` to `asis`, you see a file with two lines:

```
line1
line2
```

You get two lines when you use `asis` because the embedded line feed character has been exported without being converted to a two-digit hexadecimal representation, and without being prefixed by anything.

## Usage

- The `output` statement copies the information retrieved by the current query to a file.
- You can specify the output format with the optional `format` clause. If you do not specify the `format` clause, the Interactive SQL `output_format` option setting is used.
- The current query is the `select` or `input` statement that generated the information appearing on the Results tab in the Results pane. The `output` statement reports an error if there is no current query.
- In Interactive SQL, the Results tab displays only the results of the current query. All previous query results are replaced with the current query results.

## Permissions

Any user can execute this command.

## 2.8 parameters

Specifies parameters to an Interactive SQL command file.

### Syntax

```
parameters parameter1, parameter2, . . .
```

### Examples

#### Example 1

Specifies two parameters to an Interactive SQL command file:

```
parameters department_id, file;
select emp_lname
  from employee
  where dept_id = {department_id}
>#{file}.dat
```

If you save this script in a file named `test.sql`, you can run it from Interactive SQL using the following command:

```
read test.SQL [100] [data]
```

## Usage

- The `parameters` statement names the parameters for a command file, so that they can be referenced later in the command file.
- Parameters are referenced by putting `{parameter1}` into the file where you want the named parameter to be substituted. There cannot be any spaces between the braces and the parameter name.
- If a command file is invoked with less than the required number of parameters, Interactive SQL prompts for values of the missing parameters.

## Permissions

Any user can execute this command.

## Related Information

[read \[page 884\]](#)

## 2.9 read

Reads Interactive SQL statements from a file.

## Syntax

```
read [ encoding {<identifier> | <string>} ] <file_name> [ <parameters> ]
```

## Parameters

`encoding {<identifier> | <string>}`

allows you to specify the encoding that is used to write the file. `encoding` can be used only with the ASCII format.

- `<identifier>` – is the identifier you are using to indicate the file you are reading.
- `<string>` – is the string you are using to indicate the file you are reading.

`<file_name>`

is the name of the file you are reading.

<parameters>

correspond to the parameters listed in the statement file.

## Examples

### Example 1

Reads a file called `status.rpt` and another file called `birthday.SQL`:

```
READ status.rpt '160'  
READ birthday.SQL [>= '1988-1-1'] [<= '1988-1-30']
```

## Usage

- The `read` statement reads a sequence of Interactive SQL statements from the named file. This file can contain any valid Interactive SQL statement, including other `read` statements. `read` statements can be nested to any depth. If the file name does not contain an absolute path, Interactive SQL searches for the file. Interactive SQL first searches the current directory, and then the directories specified in the environment variable `SQLPATH`, and then the directories specified in the environment variable `PATH`. If the named file has no file extension, Interactive SQL searches each directory for the same file name with the extension `.SQL`.
- The encoding argument allows you to specify the encoding that is used to read the file. The `read` statement does not process escape characters when it reads a file. It assumes that the entire file is in the specified encoding. If encoding is not specified, Interactive SQL determines the code page that is used to read the file as follows, where code page values occurring earlier in the list take precedence over those occurring later in the list:
  - The code page specified with the `default_isql_encoding` option (if this option is set)
  - The code page specified with the `-codepage` option when Interactive SQL was started
  - The default code page for the computer Interactive SQL is running on
- Parameters can be listed after the name of the command file. These parameters correspond to the parameters named on the `parameters` statement at the beginning of the statement file. Interactive SQL substitutes the corresponding parameter wherever the source file contains `{<parameter_name>}`, where `<parameter_name>` is the name of the appropriate parameter.
- The parameters passed to a command file can be identifiers, numbers, quoted identifiers, or strings. When quotes are used around a parameter, the quotes are placed into the text during the substitution. You must enclose in square brackets (`[ ]`) parameters that are not identifiers, numbers, or strings (contain spaces or tabs). This allows for arbitrary textual substitution in the command file.
- If not enough parameters are passed to the command file, Interactive SQL prompts for values for the missing parameters.

## Permissions

Any user can execute this command.

## 2.10 set connection

Changes the current database connection to another server.

### Syntax

```
set connection {<identifier> | <string> | <hostvar>}
```

### Parameters

**<identifier>**

is the login name identifier you are using for the connection information.

**<string>**

is the string you are using for the connection information.

**<hostvar>**

is the variable information for the host name and port.

### Usage

The `set connection` statement changes the active database connection to another server. The current connection state is saved, and resumes again when it again becomes the active connection. If you omit `<connection_name>` and there is a connection that was not named, that connection becomes the active connection.

## Permissions

Any user can execute this command.

## Related Information

[connect](#) [page 870]

[disconnect](#) [page 873]

## 2.11 start logging

Starts logging executed SQL statements to a log file.

### Syntax

```
start logging <file_name>
```

### Parameters

`file_name`

is the file to which you are logging the session.

### Examples

#### Example 1

Starts logging to a file called `filename.sql`, located in the `c:` directory:

```
start logging 'c: n filename.sql'
```

### Usage

The `start logging` statement starts copying all subsequent executed SQL statements to the log file that you specify. If the file does not exist, Interactive SQL creates it. Logging continues until you explicitly stop the logging process with the `stop logging` statement, or until you end the current Interactive SQL session. You can also start and stop logging by selecting SQL | Start Logging and SQL | Stop Logging.

## Permissions

Any user can execute this command.

## Related Information

[stop logging \[page 888\]](#)

## 2.12 stop logging

Stops logging of executed SQL statements in the current session.

### Syntax

```
stop logging
```

### Examples

#### Example 1

Stops the current logging session:

```
stop logging
```

### Usage

The `stop logging` statement stops Interactive SQL from writing each SQL statement you execute to a log file. You can start logging with the `start logging` statement. You can also start and stop logging by selecting `SQL | Start Logging` and `SQL | Stop Logging`.

## Permissions

Any user can execute this command.



## Related Information

[start logging \[page 887\]](#)

## 2.13 system

Launches an executable file from within Interactive SQL.

### Syntax

```
system '['<path>] <file_name>'
```

### Parameters

**<path>**

is the path to the Notepad program.

**<file\_name>**

is the file name of the program you are launching.

### Examples

#### Example 1

Launches the Notepad program, assuming that the Notepad executable is in your path.

```
system 'notepad.exe'
```

### Usage

- The `system` statement must be entirely contained on one line.
- Comments are not allowed at the end of a `system` statement.
- Enclose the path and file name in single quotation marks.

## Permissions

Any user can execute this command.

## Related Information



[connect \[page 870\]](#)

# Important Disclaimers and Legal Information

## Hyperlinks

Some links are classified by an icon and/or a mouseover text. These links provide additional information.

About the icons:

- Links with the icon : You are entering a Web site that is not hosted by SAP. By using such links, you agree (unless expressly stated otherwise in your agreements with SAP) to this:
  - The content of the linked-to site is not SAP documentation. You may not infer any product claims against SAP based on this information.
  - SAP does not agree or disagree with the content on the linked-to site, nor does SAP warrant the availability and correctness. SAP shall not be liable for any damages caused by the use of such content unless damages have been caused by SAP's gross negligence or willful misconduct.
- Links with the icon : You are leaving the documentation for that particular SAP product or service and are entering a SAP-hosted Web site. By using such links, you agree that (unless expressly stated otherwise in your agreements with SAP) you may not infer any product claims against SAP based on this information.

## Beta and Other Experimental Features

Experimental features are not part of the officially delivered scope that SAP guarantees for future releases. This means that experimental features may be changed by SAP at any time for any reason without notice. Experimental features are not for productive use. You may not demonstrate, test, examine, evaluate or otherwise use the experimental features in a live operating environment or with data that has not been sufficiently backed up.

The purpose of experimental features is to get feedback early on, allowing customers and partners to influence the future product accordingly. By providing your feedback (e.g. in the SAP Community), you accept that intellectual property rights of the contributions or derivative works shall remain the exclusive property of SAP.

## Example Code

Any software coding and/or code snippets are examples. They are not for productive use. The example code is only intended to better explain and visualize the syntax and phrasing rules. SAP does not warrant the correctness and completeness of the example code. SAP shall not be liable for errors or damages caused by the use of example code unless damages have been caused by SAP's gross negligence or willful misconduct.

## Gender-Related Language

We try not to use gender-specific word forms and formulations. As appropriate for context and readability, SAP may use masculine word forms to refer to all genders.

© 2019 SAP SE or an SAP affiliate company. All rights reserved.

No part of this publication may be reproduced or transmitted in any form or for any purpose without the express permission of SAP SE or an SAP affiliate company. The information contained herein may be changed without prior notice.

Some software products marketed by SAP SE and its distributors contain proprietary software components of other software vendors. National product specifications may vary.

These materials are provided by SAP SE or an SAP affiliate company for informational purposes only, without representation or warranty of any kind, and SAP or its affiliated companies shall not be liable for errors or omissions with respect to the materials. The only warranties for SAP or SAP affiliate company products and services are those that are set forth in the express warranty statements accompanying such products and services, if any. Nothing herein should be construed as constituting an additional warranty.

SAP and other SAP products and services mentioned herein as well as their respective logos are trademarks or registered trademarks of SAP SE (or an SAP affiliate company) in Germany and other countries. All other product and service names mentioned are the trademarks of their respective companies.

Please see <https://www.sap.com/about/legal/trademark.html> for additional trademark information and notices.