

SystemTest™ Release Notes

How to Contact MathWorks



www.mathworks.com
[comp.soft-sys.matlab](mailto:comp.soft-sys.matlab@mathworks.com)
www.mathworks.com/contact_TS.html

Web
Newsgroup
Technical Support



suggest@mathworks.com
bugs@mathworks.com
doc@mathworks.com
service@mathworks.com
info@mathworks.com

Product enhancement suggestions
Bug reports
Documentation error reports
Order status, license renewals, passcodes
Sales, pricing, and general information



508-647-7000 (Phone)



508-647-7001 (Fax)



The MathWorks, Inc.
3 Apple Hill Drive
Natick, MA 01760-2098

For contact information about worldwide offices, see the MathWorks Web site.

SystemTest™ Release Notes

© COPYRIGHT 2006–2012 by The MathWorks, Inc.

The software described in this document is furnished under a license agreement. The software may be used or copied only under the terms of the license agreement. No part of this manual may be photocopied or reproduced in any form without prior written consent from The MathWorks, Inc.

FEDERAL ACQUISITION: This provision applies to all acquisitions of the Program and Documentation by, for, or through the federal government of the United States. By accepting delivery of the Program or Documentation, the government hereby agrees that this software or documentation qualifies as commercial computer software or commercial computer software documentation as such terms are used or defined in FAR 12.212, DFARS Part 227.72, and DFARS 252.227-7014. Accordingly, the terms and conditions of this Agreement and only those rights specified in this Agreement, shall pertain to and govern the use, modification, reproduction, release, performance, display, and disclosure of the Program and Documentation by the federal government (or other entity acquiring for or through the federal government) and shall supersede any conflicting contractual terms or conditions. If this License fails to meet the government's needs or is inconsistent in any respect with federal procurement law, the government agrees to return the Program and Documentation, unused, to The MathWorks, Inc.

Trademarks

MATLAB and Simulink are registered trademarks of The MathWorks, Inc. See www.mathworks.com/trademarks for a list of additional trademarks. Other product or brand names may be trademarks or registered trademarks of their respective holders.

Patents

MathWorks products are protected by one or more U.S. patents. Please see www.mathworks.com/patents for more information.

Summary by Version	1
Version 2.6.3 (R2012a) SystemTest Software	4
Version 2.6.2 (R2011b) SystemTest Software	5
Version 2.6.1 (R2011a) SystemTest Software	6
Version 2.6 (R2010b) SystemTest Software	8
Version 2.5 (R2010a) SystemTest Software	14
Version 2.4 (R2009b) SystemTest Software	17
Version 2.3 (R2009a) SystemTest Software	20
Version 2.2 (R2008b) SystemTest Software	23
Version 2.1 (R2008a) SystemTest Software	26
Version 2.0 (R2007b) SystemTest Software	34
Version 1.1 (R2007a) SystemTest Software	37
Version 1.0.1 (R2006b) SystemTest Software	39
Version 1.0 (R2006a+) SystemTest Software	40
Compatibility Summary for SystemTest Software	41

Summary by Version

This table provides quick access to what's new in each version. For clarification, see "Using Release Notes" on page 2.

Version (Release)	New Features and Changes	Version Compatibility Considerations	Fixed Bugs and Known Problems
Latest Version V2.6.3 (R2012a)	No	No	Bug Reports Includes fixes
V2.6.2 (R2011b)	No	No	Bug Reports Includes fixes
V2.6.1 (R2011a)	No	Yes Summary	Bug Reports Includes fixes
V2.6 (R2010b)	Yes Details	Yes Summary	Bug Reports Includes fixes
V2.5 (R2010a)	Yes Details	Yes Summary	Bug Reports Includes fixes
V2.4 (R2009b)	Yes Details	Yes Summary	Bug Reports Includes fixes
V2.3 (R2009a)	Yes Details	Yes Summary	Bug Reports Includes fixes
V2.2 (R2008b)	Yes Details	No	Bug Reports Includes fixes
V2.1 (R2008a)	Yes Details	Yes Summary	Bug Reports Includes fixes
V2.0 (R2007b)	Yes Details	Yes Summary	Bug Reports Includes fixes
V1.1 (R2007a)	Yes Details	Yes Summary	Bug Reports Includes fixes
V1.0.1 (R2006b)	No	No	Yes Details
V1.0 (R2006a+)	Yes Details	No	No

Using Release Notes

Use release notes when upgrading to a newer version to learn about:

- New features
- Changes
- Potential impact on your existing files and practices

Review the release notes for other MathWorks® products required for this product (for example, MATLAB® or Simulink®). Determine if enhancements, bugs, or compatibility considerations in other products impact you.

If you are upgrading from a software version other than the most recent one, review the current release notes and all interim versions. For example, when you upgrade from V1.0 to V1.2, review the release notes for V1.1 and V1.2.

What Is in the Release Notes

New Features and Changes

- New functionality
- Changes to existing functionality

Version Compatibility Considerations

When a new feature or change introduces a reported incompatibility between versions, the **Compatibility Considerations** subsection explains the impact.

Compatibility issues reported after the product release appear under Bug Reports at the MathWorks Web site. Bug fixes can sometimes result in incompatibilities, so review the fixed bugs in Bug Reports for any compatibility impact.

Fixed Bugs and Known Problems

MathWorks offers a user-searchable Bug Reports database so you can view Bug Reports. The development team updates this database at release time

and as more information becomes available. Bug Reports include provisions for any known workarounds or file replacements. Information is available for bugs existing in or fixed in Release 14SP2 or later. Information is not available for all bugs in earlier releases.

Access Bug Reports using your MathWorks Account.

Documentation on the MathWorks Web Site

Related documentation is available on mathworks.com for the latest release and for previous releases:

- Latest product documentation
- Archived documentation

Version 2.6.3 (R2012a) SystemTest Software

This table summarizes what's new in Version 2.6.3 (R2012a):

New Features and Changes	Version Compatibility Considerations	Fixed Bugs and Known Problems
No	No	Bug Reports

Version 2.6.2 (R2011b) SystemTest Software

This table summarizes what's new in Version 2.6.2 (R2011b):

New Features and Changes	Version Compatibility Considerations	Fixed Bugs and Known Problems
No	No	Bug Reports Includes fixes

Version 2.6.1 (R2011a) SystemTest Software

This table summarizes what's new in Version 2.6.1 (R2011a):

New Features and Changes	Version Compatibility Considerations	Fixed Bugs and Known Problems
No	Yes Summary	Bug Reports Includes fixes

Changes introduced in this version are:

Deprecation of Test Results Viewer

In R2010b, the Test Results Viewer was no longer available from the SystemTest™ desktop. It could still be opened via the `stviewer` function.

The following were removed from the desktop user interface in R2010b:

- The **Visualize and plot saved results by launching the Test Results Viewer** option on the **General** tab of the **Test Properties** pane.
- The **Tools > Test Results Viewer** menu command.
- In the Preferences dialog box, the confirmation warning “Warn about launching the Test Results Viewer without any saved results.”

In R2011a, the Test Results Viewer is no longer available, even via the `stviewer` function. We recommend using `stresults` to view saved results instead. You can view the results you have chosen to save for your test using a workspace variable called `stresults`. It provides access to the test results object, which is useful for comparing the results of separate test runs and for postprocessing test results. For more information on viewing saved results see “Accessing Test Results from the MATLAB Command Line”.

For visualization of data within the SystemTest software, you can use the General Plot element and view the generated plots after a test run. For information on using the General Plot element, see “General Plot Element”.

For visualizing test cases and signals, you can use the Test Case Editor. For more information, see “Authoring Signals in the Test Case Editor”.

Compatibility Considerations

When you open a test that was previously configured to use the Test Results Viewer, you will get a warning dialog saying “This test was configured to open the Test Results Viewer when the test finishes running. This option is no longer available.”

The following outline describes the timing of the deprecation process:

- **R2010b** — The Test Results Viewer was no longer available from the SystemTest desktop. It could still be opened via the `stviewer` function.
- **R2011a (current release)** — The Test Results Viewer has been removed. The `stviewer` function produces an error stating that the Viewer is no longer available.
- **R2011b (or later)** — The `stviewer` function will be removed.

Version 2.6 (R2010b) SystemTest Software

This table summarizes what's new in Version 2.6 (R2010b):

New Features and Changes	Version Compatibility Considerations	Fixed Bugs and Known Problems
Yes Details below	Yes Summary	Bug Reports Includes fixes

New features and changes introduced in this version are:

- “Automatically Generate SystemTest Test from Simulink” on page 8
- “Simulink Bus Support in Test Case Editor” on page 9
- “Additional Model Coverage Support” on page 9
- “Programmatic Interface for Test Case Editor” on page 9
- “Programmatic Interface for Requirements Linking in Test Case Editor” on page 10
- “Deprecation of Test Results Viewer” on page 10
- “Plot Element Transition, Conversion Utility” on page 12
- “Future Deprecation of Hardware Elements” on page 12
- “Future Deprecation of Macintosh Support” on page 13

Automatically Generate SystemTest Test from Simulink

You can now create a SystemTest test from Simulink. It will automatically generate relevant parts of the test based on your model. The feature automatically generates the following in your test:

- Simulink element, configured properly
- Test Case Data test vector, configured properly
- Signals in the Test Case Editor, configured properly
- Mappings of the Inports in your model

You can also automatically generate the test harness via the MATLAB command line, using new functions for this feature.

For more information, see “Generating a SystemTest Test Harness from a Simulink Model”.

Simulink Bus Support in Test Case Editor

The Test Case Editor now supports the use of buses in your model and can be used to create buses and signals within buses. The full bus hierarchy is now reflected in the Test Case Editor and you can work with the signals inside buses.

For more information, see “Buses in the Test Case Editor”

Additional Model Coverage Support

Two metrics have been added to the Model Coverage support in the Simulink element – **Signal Size Coverage** and **Simulink Design Verifier**. **Signal Size Coverage** records the minimum, maximum, and allocated size for all variable-size signals in a model. The **Simulink Design Verifier** coverage option collects model coverage data for some Simulink Design Verifier™ blocks.

Support for External Embedded MATLAB® files was also added. It enables coverage for external functions that Embedded MATLAB functions call in your model. The Embedded MATLAB functions may be defined in an Embedded MATLAB block.

For more information, see “Simulink Model Coverage”.

Programmatic Interface for Test Case Editor

The functionality of the Test Case Editor is now available via the MATLAB command line. The new functions will allow you to do the following tasks programmatically:

- create test cases, signals, and segments
- add test cases, signals, and segments to a SystemTest test

- configure and edit test cases, signals, and segments in a test
- extract test cases, signals, and segments from a test

For more information, see “Test Case and Signal Authoring Programmatically”

Programmatic Interface for Requirements Linking in Test Case Editor

The functionality of requirements linking using Telelogic DOORS® and the Test Case Editor is now available via the MATLAB command line. The new functions will allow you to do the following tasks programmatically:

- create requirements links to Telelogic DOORS® objects
- add requirements to test cases in the Test Case Editor

For more information, see “Create Requirements Programmatically”

Deprecation of Test Results Viewer

In R2010b, the Test Results Viewer is no longer available from the SystemTest desktop. It can still be opened via the `stviewer` function.

The following have been removed from the desktop user interface:

- The **Visualize and plot saved results by launching the Test Results Viewer** option on the **General** tab of the **Test Properties** pane.
- The **Tools > Test Results Viewer** menu command.
- In the Preferences dialog box, the confirmation warning “Warn about launching the Test Results Viewer without any saved results.”

To open the Test Results Viewer, use the `stviewer` function in MATLAB after a test run.

The Test Results Viewer will no longer be available in a future release, even via the `stviewer` function. We recommend using `stresults` to view saved results instead. You can view the results you have chosen to save for your test using a workspace variable called `stresults`. It provides access to the test results object, which is useful for comparing the results of separate test runs

and for postprocessing test results. For more information on viewing saved results see “Accessing Test Results from the MATLAB Command Line”.

For visualization of data within the SystemTest software, you can use the General Plot element and view the generated plots after a test run. For information on using the General Plot element, see “General Plot Element”.

For visualizing test cases and signals, you can use the Test Case Editor. For more information, see “Authoring Signals in the Test Case Editor”.

Compatibility Considerations

When you open a test that was previously configured to use the Test Results Viewer, you will get a warning dialog saying “This test was configured to open the Test Results Viewer when the test finishes running. This option is no longer available.”

If you do open the Viewer using the `stviewer` function, you will get a warning on the command line saying “The viewer will be removed in a future release.”

The following outline describes the timing of the deprecation process:

- **R2010b** — The Test Results Viewer is no longer available from the SystemTest desktop. It can still be opened via the `stviewer` function. You will receive the warnings described above.
- **R2011a** — The Test Results Viewer will be removed. The `stviewer` function will produce an error stating that the Viewer is no longer available.
- **R2011b (or later)** — The `stviewer` function will be removed.

Plot Element Transition, Conversion Utility

The Vector Plot and Scalar Plot elements have been replaced by the General Plot element. The General Plot element supports all MATLAB plot types. You can plot any type of data, using any MATLAB plot types or Simulink data.

The General Plot element has special support for the many time-based data formats produced from a Simulink model. The supported data types include an array, a structure, a structure with time, or a time series. You can also plot Simulink data provided by test vectors, such as the Signal Builder Block test vector, the Simulink Design Verifier Data File test vector, or the Spreadsheet Data test vector.

Note As of R2010a, you could no longer create new Scalar Plot or Vector Plot elements. They no longer appear in the **Insert** menu or the **New Element** button.

Conversion Utility

Tests containing Scalar Plot or Vector Plot elements will not automatically load with those elements. You will be prompted to convert them to General Plot elements.

For information on performing the conversion, and conversion details about the Scalar Plot and Vector Plot elements, see “Deprecated Elements”.

Compatibility Considerations

For an outline of the timing for this deprecation, see Compatibility Considerations in the R2010a section of the release notes.

Future Deprecation of Hardware Elements

In a future release, possibly R2011a, the following elements will be removed from SystemTest software:

- **Data Acquisition > Analog Input**
- **Data Acquisition > Analog Output**

- **Data Acquisition > Digital Input**
- **Data Acquisition > Digital Output**
- **Image Acquisition > Video Input**
- **Instrument Control > From Instrument**
- **Instrument Control > Query Instrument**
- **Instrument Control > To Instrument**

These elements will be removed in a future release (R2011a or later). We therefore recommend not creating new tests using these elements.

Future Deprecation of Macintosh Support

In a future release, (R2011a or later), the SystemTest software will no longer be supported on any Mac® platform, including maci64.

Version 2.5 (R2010a) SystemTest Software

This table summarizes what's new in Version 2.5 (R2010a):

New Features and Changes	Version Compatibility Considerations	Fixed Bugs and Known Problems
Yes Details below	Yes Summary	Bug Reports Includes fixes

New features and changes introduced in this version are:

- “Test Case Editor and Signal Authoring” on page 14
- “Support for Requirements Linking” on page 15
- “Test Property Enhancements” on page 15
- “Plot Element Transition, Conversion Utility” on page 15

Test Case Editor and Signal Authoring

You can create signals in the SystemTest software and use them to test a Simulink model. The Test Case Editor provides a graphical way of creating, editing, and visualizing signal data in SystemTest.

The tool provides the ability to create signals based on commonly used patterns and to specify values for attributes of those signal segments. You can easily create the following types of signals: constant, step, ramp, pulse, square, sine, and custom.

The tool also allows you to view and manage signals, and to organize them into test cases. You can manage a large number of test cases and signals. The Test Case Editor is accessed through the Test Case Data test vector in the SystemTest software.

For information on using the Test Case Editor, see “Authoring Signals in the Test Case Editor”.

Support for Requirements Linking

You can link test cases created in the new Test Case Editor to requirements that are in Telelogic DOORS®. This is done through the **Requirements** tab in the Test Case Editor. The integration allows you to easily link any DOORS requirements to any test cases by selecting them by their object headings.

For more information on linking requirements to test cases, see “Link to Requirements in Telelogic® DOORS®”

Test Property Enhancements

Further enhancements were added to saving of results files in the **Test Properties** pane. New output folder options for the test results and the Test Report allow you to select between several relative locations, which makes moving or sharing files easier, or to assign an absolute location.

The options for results files are now on a new tab, **Output Files**, on the **Test Properties** pane.

For more information see “Saving Test Results” and “Generate a Test Report”, or the Desktop Help for the **Output Files** tab.

Plot Element Transition, Conversion Utility

The Vector Plot and Scalar Plot elements have been replaced by the General Plot element that was introduced in R2008b. The General Plot element supports all MATLAB plot types. You can plot any type of data, using any MATLAB plot types or Simulink data.

The General Plot element has special support for the many time-based data formats produced from a Simulink model. The supported data types include an array, a structure, a structure with time, or a time series. You can also plot Simulink data provided by test vectors, such as the Signal Builder Block test vector, the Simulink Design Verifier Data File test vector, or the Spreadsheet Data test vector.

Note You can no longer create new Scalar Plot or Vector Plot elements. They no longer appear in the **Insert** menu or the **New Element** button.

Conversion Utility

Tests containing Scalar Plot or Vector Plot elements will not automatically load with those elements. You will be prompted to convert them to General Plot elements.

For information on performing the conversion, and conversion details about the Scalar Plot and Vector Plot elements, see “Deprecated Elements”.

Compatibility Considerations

The following outline describes the timing of the transition process:

- **R2009a and R2009b** — You should no longer create new Vector Plot or Scalar Plot elements. Tests containing the old elements continued to work, but we recommended that you do not create any new ones, and instead use the General Plot element.
- **R2010a (current version)** — You can no longer create new Vector Plot or Scalar Plot elements. They no longer appear in the **Insert** menu or the **New Element** button. A warning will appear if you load a test containing the old elements. Tests containing the old elements will continue to work, but you cannot create any new ones.

You will not lose the use of the old elements in existing tests. Previously created Vector Plot and Scalar Plot elements will be converted to the General Plot element. See the previous section.

- **A future release** — You can no longer load tests containing Vector Plot or Scalar Plot elements. If you try to load one, you will get an error, and will have to convert the element to the General Plot element. Previously created Vector Plot and Scalar Plot elements will be converted to the General Plot element.

Version 2.4 (R2009b) SystemTest Software

This table summarizes what's new in Version 2.4 (R2009b):

New Features and Changes	Version Compatibility Considerations	Fixed Bugs and Known Problems
Yes Details below	Yes Summary	Bug Reports Includes fixes

New features and changes introduced in this version are:

- “Test Vector Data Viewer” on page 17
- “Test Property Enhancements” on page 17
- “Minor Enhancements to Simulink Element” on page 18
- “Plot Element Transition” on page 18

Test Vector Data Viewer

You can now view the test vector data while configuring a Probability Distribution test vector. The viewer will display non-time-based data for this type of test vector, allowing you to view your data before running a test.

Probability Distribution test vector data is displayed in a histogram. To access the data viewer, click the **View Data** button in the Insert Test Vector dialog box.

For more information see “Viewing Data While Configuring the Test Vector”.

Test Property Enhancements

Enhancements were added to saving of results files in the **Test Properties** pane. New output folder options for the test results and the Test Report allow you to select between several relative locations, which makes moving or sharing files easier, or to assign an absolute location.

For more information see “Saving Test Results” and “Generate a Test Report”.

Minor Enhancements to Simulink Element

Minor enhancements have been done in the Simulink element, including an easier way to extract time data and changing the model end time when importing all signals.

Plot Element Transition

The Vector Plot and Scalar Plot elements are being replaced by the General Plot element that was introduced in R2008b. The General Plot element supports all MATLAB plot types. You can plot any type of data, using any MATLAB plot types or Simulink data.

The General Plot element has special support for the many time-based data formats produced from a Simulink model. The supported data types include an array, a structure, a structure with time, or a time series. You can also plot Simulink data provided by test vectors, such as the Signal Builder Block test vector, the Simulink Design Verifier Data File test vector, or the Spreadsheet Data test vector.

Compatibility Considerations

The following outline describes the timing of the transition process:

- **R2009a and R2009b** — You should no longer create new Vector Plot or Scalar Plot elements. Tests containing the old elements will continue to work, but we recommend that you do not create any new ones. We recommend using the General Plot element.
- **A future release** — You can no longer create new Vector Plot or Scalar Plot elements. A warning will appear if you load a test containing the old elements. Tests containing the old elements will continue to work, but you cannot create any new ones.

You will not lose the use of the old elements in existing tests. Previously created Vector Plot and Scalar Plot elements will be converted to the General Plot element.

- **A future release** — You can no longer load tests containing Vector Plot or Scalar Plot elements. If you try to load one, you will get an error, and will have to convert the element to the General Plot element. Previously

created Vector Plot and Scalar Plot elements will be converted to the General Plot element.

Version 2.3 (R2009a) SystemTest Software

This table summarizes what's new in Version 2.3 (R2009a):

New Features and Changes	Version Compatibility Considerations	Fixed Bugs and Known Problems
Yes Details below	Yes Summary	Bug Reports Includes fixes

New features and changes introduced in this version are:

- “MAT-File Test Vector” on page 20
- “Automatic Naming of Test Vectors and Test Variables” on page 20
- “Enhanced Inport Support for the Simulink Element” on page 21
- “Additional Editing Capability for Test Vectors” on page 21
- “Plot Element Transition” on page 21

MAT-File Test Vector

A new MAT-file test vector has been added. It reads data from individual MAT-files into the SystemTest environment. For more information on this feature, see “Create MAT-File Test Vectors”.

Automatic Naming of Test Vectors and Test Variables

A new feature has been added to the Simulink element to make creating or mapping test vectors and test variables easier. You now have the option of automatically naming test vectors and test variables from the names used in the model inports and outports. This is particularly useful for testing Simulink models with large numbers of inports or outports.

This feature is accessed by clicking the **Mappings Assistant** button in the Simulink element. For more information about this feature, see the Desktop Help for the Simulink element (in the **Desktop Help** pane when the Simulink element is selected), the subtopics called *Using the Inport Block Mappings Assistant*, and *Using the Model Output Mappings Assistant*.

Enhanced Inport Support for the Simulink Element

Enhanced support has been added in the Simulink element for logged signals, including time series and bus signals.

You can feed data logged from a Simulink model to Inport blocks of another model using the Simulink element and a MAT-File test vector that contains the logged signal data.

A common usage scenario is to log the signals while running a model and store them in a MAT-File. Then acquire them from the Mat-File using a MAT-File test vector and map that to Inport blocks in the Simulink element. For more information on this feature, see “Map Logged Signals from a Model to Inport Blocks”.

Additional Editing Capability for Test Vectors

You can now edit test vectors from within elements. In prior versions of the SystemTest software, you could only edit test vectors from the **Test Vectors** pane. Now you can edit them there, as well as from within individual elements.

Plot Element Transition

The Vector Plot and Scalar Plot elements are being replaced by the new General Plot element that was introduced in R2008b. The General Plot element supports all MATLAB plot types. You can plot any type of data, using any MATLAB plot types or Simulink data.

The General Plot element has special support for the many time-based data formats produced from a Simulink model. The supported data types include an array, a structure, a structure with time, or a time series. You can also plot Simulink data provided by test vectors, such as the Signal Builder Block test vector, the Simulink Design Verifier Data File test vector, or the Spreadsheet Data test vector.

Compatibility Considerations

The following outline describes the timing of the transition process:

- **Version R2009a** — Customers should no longer create new Vector Plot or Scalar Plot elements. Tests containing the old elements will continue to work, but we recommend that you do not create any new ones. We recommend using the General Plot element.
- **Version R2009a + 1** — Customers can no longer create new Vector Plot or Scalar Plot elements. There will be a warning if you load a test containing the old elements. Tests containing the old elements will continue to work, but you cannot create any new ones.

You will not lose the use of the old elements in existing tests. Previously created Vector Plot and Scalar Plot elements will be converted to the General Plot element.

- **Version R2009a + 2** — Customers can no longer load tests containing Vector Plot or Scalar Plot elements. If you try to load one, you will get an error, and will have to convert the element to the General Plot element. Previously created Vector Plot and Scalar Plot elements will be converted to the General Plot element.

Version 2.2 (R2008b) SystemTest Software

This table summarizes what's new in Version 2.2 (R2008b):

New Features and Changes	Version Compatibility Considerations	Fixed Bugs and Known Problems
Yes Details below	No	Bug Reports Includes fixes

New features and changes introduced in this version are:

- “Signal Builder Block Test Vector” on page 23
- “Multiple Test Vector Groups” on page 23
- “New Plot Element” on page 24
- “Simulink Design Verifier Data File Test Vector” on page 24
- “Model Coverage Support for Reference Blocks” on page 25
- “Run Status Hyperlink Change” on page 25

Signal Builder Block Test Vector

If you have created a Simulink model test harness using a Signal Builder block, you can automate the running of all your test cases by integrating them into a SystemTest test. This also offers the ability to collect cumulative model coverage metrics for all your Signal Builder test cases.

For more information on this feature, see “Create Signal Builder Block Test Vectors”.

Multiple Test Vector Groups

The ability to create multiple test vector groups has been added to the SystemTest software. A test vector group is a collection of test vectors of the same length whose values are indexed sequentially with the other vectors in the group. Groups are commonly used for Monte Carlo and Design of Experiments (DOE) based testing, or when multiple vectors have a relationship (e.g. the mass and damping values of different throttle body types). Until R2008b, you could only create one test vector group.

For example, you could have a model of an automobile motor with two blocks – one block for the fuel system and one for the oxygen flow. Each block has a number of inports that are mapped to SystemTest vectors. In previous release you could not create a test that checks how the model behaves when performing a Monte Carlo test on both the fuel system and oxygen flow at the same time. With multiple test vector group support, you can now perform a Monte Carlo style test on both blocks, saving time in the test run.

For more information on this feature, see “Create Grouped Test Vectors”.

New Plot Element

The new General Plot element offers support of all MATLAB plot types. You can plot any type of data, using any MATLAB plot types, or Simulink data.

The General Plot element allows you to plot data produced from a Simulink model. The supported data types include an array, a structure, a structure with time, or a time series. Note that the element creates a line for each signal in the Simulink data. If time is not present, the signals are plotted against their indices.

You can also plot Simulink data provided by test vectors, such as the Signal Builder Block test vector, the Simulink Design Verifier Data File test vector, or the Spreadsheet Data test vector.

For more information on this feature, see **Working with the Basic Elements > Basic Elements > General Plot Element** in the SystemTest help.

Simulink Design Verifier Data File Test Vector

The Simulink Design Verifier Data File test vector can read test cases created by the Simulink Design Verifier software. In order to use this test vector, you need a Simulink Design Verifier data file with test cases.

To use this feature, you first run Simulink Design Verifier with the appropriate configuration. Then you can do one of two things:

- Generate a SystemTest harness for the model from Simulink. When it completes, a new test opens automatically in SystemTest and a Simulink

Design Verifier Data File test vector is automatically created. This workflow is described in “Automatically Creating a SystemTest Test Harness from Simulink Design Verifier”.

- If you already have a data file from Simulink Design Verifier, you can create a test vector in SystemTest that uses the data, and configure overrides in a Simulink element. This workflow is described in “Creating a Simulink Design Verifier Data File Test Vector”.

Model Coverage Support for Reference Blocks

The SystemTest software now supports Model Coverage for Reference blocks. The Simulink element will allow model coverage to be gathered for referenced models.

For more information on this feature, see “Simulink Model Coverage”.

Run Status Hyperlink Change

Prior to R2008b, after a test ran, the **Run Status** pane contained a link “Open Test Results in Viewer.” This is no longer available. However, you can still open the results in the Test Results Viewer by selecting the **Tools > Test Results Viewer** menu or setting the automatic launch option on the **General** tab in the **Test Properties** pane.

The hyperlink in **Run Status** has been replaced by a link that opens the test results object in MATLAB.

Version 2.1 (R2008a) SystemTest Software

This table summarizes what's new in Version 2.1 (R2008a):

New Features and Changes	Version Compatibility Considerations	Fixed Bugs and Known Problems
Yes Details below	Yes Summary	Bug Reports Includes fixes

New features and changes introduced in this version are:

- “Overriding Individual Simulink Inport Blocks” on page 27
- “Improvements in the Simulink Element” on page 27
- “M API to Access Test Results in MATLAB” on page 28
- “Test Vector Types” on page 29
- “Option to Reuse Test Vector Values” on page 29
- “Reading Microsoft Excel Data into Test Vectors” on page 29
- “Test Vectors User Interface Change” on page 31
- “Test File Format Change” on page 31
- “General UI Changes” on page 32
- “Default Setting Changes” on page 33
- “Test Results Viewer Notes” on page 33

Overriding Individual Simulink Inport Blocks

You can now override individual Simulink Inport block signals via the Simulink element.

In the element, you can map test signals to individual Simulink Inport blocks using the new **Override Inport Block Signals with SystemTest Data** section on the **Mappings** tab.

For information on using this feature, see *Overriding Inport Block Signals* in the SystemTest documentation.

Limitations and Restrictions

When you select **Inherit from model** as the mapping for an individual Inport block, it will not support models that defined their `ExternalInput` as expressions of `t`, time series, Simulink Time Series, or `TSArray`.

Individual Inport mappings restrict the dimension of the mapping variable to a vector (dimension = 1).

Improvements in the Simulink Element

The Simulink element has been updated to use collapsible panes for the different mapping options, offering better usability within the element. Any mappings from previous TEST-files are loaded into the appropriate collapsible pane. The four collapsible panes consist of:

- Inport Block Signals (new feature – Importing Simulink Inports)
- Block Parameters
- To Workspace Variables
- Outports

In previous releases, when loading TEST-files, Simulink models associated with a Simulink element were not automatically loaded into memory during load time. In Release 2008a, the Simulink element will now load its model during load time, which is indicated by the load progress bar.

In previous releases, the Simulink element would not recognize To Workspace blocks stored within locked masks or block parameter fields for sample time, data type, and scaling. These options are now accessible through the element.

M API to Access Test Results in MATLAB

After you run a test that includes results you saved using the **Saved Results** in the **Test Browser**, you can view the results in MATLAB using a test results object. This feature is useful for comparing the results of separate test runs and for postprocessing of test results.

After running a test, a MATLAB variable named `stresults` is made available, allowing you to access the test results object and work with the data in MATLAB. One of the main advantages to accessing test results in the command line is that all of the MATLAB plotting tools are available to use on the results data. You can plot the data using any of the plot types MATLAB offers.

Another major use of the test results object is to quickly access and view your results in the form of a dataset object. The dataset object offers a convenient form for managing and displaying a large amount of data.

For information on using the new test results object, see [Accessing Test Results from the MATLAB Command Line](#) in the SystemTest documentation.

In previous releases, test results were not accessible during test execution. In Release 2008a, the most current test results can be accessed at any time in the test by using the `systest.testresults.getCurrent` function.

Compatibility Considerations

In previous releases, test results were managed in an undocumented MATLAB structure accessible as a variable named `stresults` or from the test results MAT-file. For Release 2008a, the test results are now managed as a documented test results object. Any dependencies on the previous undocumented test results format will need to be updated to use the new test results object.

For information on using the new test results object, see [Accessing Test Results from the MATLAB Command Line](#) in the SystemTest documentation.

Test Vector Types

In this release, three test vector types are now available, described as MATLAB Expression, Spreadsheet Data, and Probability Distribution. Test vector data for TEST-files from prior releases will be loaded as a MATLAB Expression test vector type.

Other Test Vector Changes

The Probability Distribution support now recalls the configuration values used to generate the distribution, avoiding the need to reenter the configuration values when a distribution needs to be edited.

The Probability Distribution test vector now uses default values for its fields. Previous versions configured the fields blank. You can replace the defaults with the values you want to use.

Option to Reuse Test Vector Values

You can now choose to reuse test vector values each time a test is run. This is useful for Monte Carlo testing when used in conjunction with the new Probability Distribution test vector type. To reuse test vector values, do not select the option called **Evaluate Test Vector each time the test is run** when configuring a Test Vector.

Note About This Feature

In previous releases, test vector values were always reevaluated upon loading and running the test. To maintain this behavior, in Release 2008a, any existing TEST-files will be loaded with their test vectors configured to **Evaluate Test Vector each time the test is run**, which is the new configuration option for test vectors. Any new test vectors created though will, by default, not be configured to reevaluate each time the test is run.

Reading Microsoft Excel Data into Test Vectors

A new test vector type, Spreadsheet Data, is now available to read data from Microsoft® Excel® files into the SystemTest software. You can import data from multiple files, and can read whole sheets or a subset of a sheet.

For information about using this feature, see [Creating Spreadsheet Data Test Vectors](#) in the SystemTest documentation.

Notes About This Feature

If a file has been added to a Spreadsheet Data test vector, any changes within the file (i.e., sheets being renamed, added, or removed) will not be automatically reflected within the SystemTest software. To have the SystemTest software reflect the change, remove the file from the test vector and then add it back.

Specific rows/columns from a Spreadsheet Data test vector can be selected using a new mapping option provided in the Simulink element's **Override Inport Block Signals with SystemTest Data** option on the **Mappings** tab. This selection option is not currently supported for other Simulink mapping types or other test elements.

The Spreadsheet Data test vector is officially supported on Windows® platforms and can read all Microsoft Excel spreadsheet files. This also includes CSV files. On platforms other than Windows, the SystemTest software only supports reading XLS files and does not support CSV files.

The following undo/redo actions are not currently supported for the Spreadsheet Data test vector:

- Adding, removing, moving up, moving down, selecting, or unselecting of files/spreadsheets
- Any edits made on the **String Mappings** tab

The Spreadsheet Data test vector stores the absolute path to any files added. If the file changes location, even if the file is still on the MATLAB path, it will not be found. You should remove and add the file again if the location or name changes.

The other two test vector types (MATLAB Expression and Probability Distribution) clear their values and set their length to 0 whenever an "Evaluate" fails. For the Spreadsheet Data test vector, if an "Evaluate" fails, then the last known values, headers, and string replacements remain and will only be updated when an "Evaluate" is successful. This can lead to

discrepancies between the actual values used and the way the Spreadsheet Data test vector user interface is configured.

- For example, if the test vector successfully reads Column A, the values are stored, etc. If the test vector is configured to read Columns B to C, and that leads to an error somewhere, the text fields will still show Columns B to C, even though the values that would be used are from Column A.
- In this same example, a failed evaluation would put the test vector in error. However, if you save and then reload the test vector, the error state is removed. Therefore, you could have saved this test vector reading from bad data in Columns B to C, and then reload and the red error borders are gone. When it runs (if you do not reevaluate each time the test is run, or manually, before pressing the **Run** button) it will use old values from column A, even though the information in the **Test Vectors** pane says Columns B to C.

Test Vectors User Interface Change

The overall UI for test vectors and test variables has been redesigned into a table and embedded edit area, offering easier management and interaction. By default, the test vectors and test variables are no longer docked in the bottom left of the desktop. Instead, they are docked in the middle pane along with the **Properties** pane. A listing of test vectors and variables are also provided in the **Test Browser**.

The list of test vectors in the **Test Browser** will always reflect an alphabetized order, regardless of their order in the **Test Vectors** edit pane. The test variables tree is not currently alphabetized and will reflect the order from the edit pane.

Multiple test vectors can be selected in the edit pane to allow for multiple test vector evaluation or deletion. Multiple test vector editing, though, is not currently supported.

Test File Format Change

The following changes have been made.

Compatibility Considerations

TEST-files are being saved in a new internal binary format as of Release 2008a. Files from previous releases are compatible with Release 2008a and can be loaded without any problems. TEST-files saved in Release 2008a will not be loadable in previous SystemTest releases.

The results MAT-file generated by the SystemTest software, or those saved by the Test Results Viewer, stores data in the form of a new test results object for Release 2008a. These result MAT-files are not loadable by previous SystemTest releases.

General UI Changes

The desktop toolbar has been updated to offer a more concise set of options.

- The **Run** and **Stop** buttons have been relocated toward the right end of the toolbar.
- The buttons that launch the Test Results Viewer, Test Report, and Simulink have been removed. These options continue to be available from the menu bar.
- The Current Directory chooser at the top of the desktop has been removed. The current directory can still be changed by using the MATLAB desktop Current Directory chooser.

A progress bar has been introduced providing status when TEST-files are loaded.

The **Run Status** progress bar has been updated to an indeterminate bar, suggesting ongoing testing when working in distributed mode. The new progress bar no longer displays the percentage complete. Information on current progress is still provided via the status text above the progress bar.

The **New** button in the **Test Browser** pane, originally used to add elements, can now be used to add elements, test vectors, and test variables.

Compatibility Considerations

Three reserved names have been introduced, restricting the names that can be used for Test Vectors, Variables, Saved Results, or Derived Results (created in the Test Results Viewer). These reserved names are:

- ObsNames
- Properties
- VarNames

Any existing TEST-files that use these names will be loaded with a warning indicating what alternate name is being used in place of the restricted name.

Default Setting Changes

With the addition of a new test results object for exploring and analyzing test results, by default, the **Visualize and plot saved results by launching the Test Results Viewer** option is turned off when new TEST-files are created. The option is still available in the **Test Properties** pane.

The default desktop layout no longer displays the **Elements** pane by default. It is still available via the **Desktop** menu.

Test Results Viewer Notes

The Test Results Viewer currently supports viewing scalar, vector, time series, and image data. It is not currently compatible with any other data formats. Attempting to load other data formats will produce an error. In particular, using the new Spreadsheet Data test vector to read in multiple columns/rows of data, producing a matrix of values for each test iteration, will likely not be loadable by the Test Results Viewer. It is recommended the new test results object, which is compatible with all data formats, be used instead to view and analyze test results.

When configured to launch, the Test Results Viewer would always launch at the end of a test, even when the test was unable to run to completion or if there were no test results to view. In Release 2008a, the viewer will only launch if the test runs to completion and if test results are being saved. Otherwise the request is ignored.

Version 2.0 (R2007b) SystemTest Software

This table summarizes what's new in Version 2.0 (R2007b):

New Features and Changes	Version Compatibility Considerations	Fixed Bugs and Known Problems
Yes Details below	Yes Summary	Bug Reports Includes fixes

New features and changes introduced in this version are:

- “Distributed Testing” on page 34
- “Randomized Test Vectors” on page 34
- “Grouped Test Vector Support in the Test Results Viewer” on page 35
- “Run SystemTest Tests from the MATLAB Command Line” on page 35
- “Platforms No Longer Supported” on page 35
- “Invalid Characters in Element Names” on page 35

Distributed Testing

You can now distribute the SystemTest software tests across multiple computers or processors for faster performance. You must have a license for the Parallel Computing Toolbox™ software to use this feature.

You can set up a test and then distribute the test iterations as tasks, which are performed by different workers. No changes to the test setup are required. This can speed up the total time the test takes to execute.

Randomized Test Vectors

The SystemTest software now provides an easy way to generate randomized test vector values for your test. Probability distribution functions can be used to set up test vectors, which is useful for performing Monte Carlo analyses.

If you have the Statistics Toolbox™ software, the SystemTest software integrates with it to provide use of some of its probability distribution functions, such as `Exponential`, `Gamma`, `Lognormal`, `T`, and `Weibull`. If you

don't have the Statistics Toolbox software, you have access to MATLAB probability distribution functions such as Normal (Gaussian) and Uniform.

Grouped Test Vector Support in the Test Results Viewer

The Test Results Viewer now lets you use grouped test vectors in plot configurations.

You can also show grouped test vectors as dependent variables in scatter plots. If a dependent variable is a grouped test vector, you can now explore the relationship it has with the other vectors in the group.

Run SystemTest Tests from the MATLAB Command Line

You can now run tests that you set up in the SystemTest software from the MATLAB command line. This is useful for running multiple tests as a batch or calling a test file as part of a MATLAB file.

Platforms No Longer Supported

The following platforms are no longer supported for use with the SystemTest software:

- Solaris™ 64
- PowerPC® Mac

Note that since these platforms are not supported, you cannot have any worker machines in a distributed testing cluster that use these platforms.

Invalid Characters in Element Names

The following characters are now considered invalid to include within element names:

- '
- <

- >

You cannot use these three characters in element names. If you create a new test element with one or more of these characters in the element name, then the SystemTest software throws an error dialog and the element name is reset to the default value, which is the name of the element type.

Compatibility Considerations

If you try to load an existing test with an invalid element name (containing one or more of the three characters listed above), the SystemTest software displays an error dialog indicating that the element name is invalid. The test will load successfully, but the element with an invalid name is reset to use the default name for the element.

If this occurs, simply rename the element to a name that does not contain any of the invalid characters. You rename an element by double-clicking its name in the **Test Browser**.

Version 1.1 (R2007a) SystemTest Software

This table summarizes what's new in Version 1.1 (R2007a):

New Features and Changes	Version Compatibility Considerations	Fixed Bugs and Known Problems
Yes Details below	Yes Summary	Bug Reports Includes fixes

New features and changes introduced in this version are:

- “Enhanced Limit and Tolerance Checking” on page 37
- “Undo/Redo Support” on page 37
- “Flexible Test Iteration Definition Using Grouped Test Vectors” on page 37
- “Enhanced Reporting of Test Execution” on page 38
- “Test Results Viewer Save and Load Capabilities” on page 38
- “Remove Test Vectors from the Limit Check Element” on page 38

Enhanced Limit and Tolerance Checking

The Limit Check element has new functionality that creates many more options for defining the pass/fail criteria for a test. In addition to scalar versus scalar comparisons, other comparison types are now supported: scalar versus vector, vector versus vector, and matrix versus matrix. You can now perform tolerance checking as well. This feature allows you to check absolute tolerance or relative tolerance of variables used throughout the SystemTest software.

Undo/Redo Support

Undo/redo support is now available in the SystemTest desktop.

Flexible Test Iteration Definition Using Grouped Test Vectors

Test vectors can now be grouped, in order to affect the way iterations are run. By grouping test vectors, they will be combined sequentially with the other

grouped vectors, and then permuted with all the ungrouped test vectors. This gives you more control over the flow of your tests and is useful for Monte Carlo or Design of Experiments (DOE) based testing as well as defining signal groups, similar to those defined in the Simulink Signal Builder block.

Enhanced Reporting of Test Execution

Reports generated for the test execution now contain more information. For example, the new report includes test description text, snapshots of the plots generated by Plot elements, and snapshots of the models used in Simulink elements.

Test Results Viewer Save and Load Capabilities

Users can now save the plotting and analysis work done in the Test Results Viewer. Data, constraints, and plots created in the Test Results Viewer can be saved and then reloaded in order to continue working on or viewing the data, or to share it with others.

Remove Test Vectors from the Limit Check Element

Test vectors are no longer available in the **Test Variable** column of the Limit Check element since there is no rationale for that use case. The “Test Vector” choice has been removed from the drop down in the Limit Check table.

Compatibility Considerations

Any existing tests using Test Vectors will have their Limit Check tables now launch in an error state. Tests cannot have Test Vectors in the **Test Variable** column. To correct the problem, choose an available variable for the limit check or create a new variable.

Version 1.0.1 (R2006b) SystemTest Software

This table summarizes what's new in Version 1.0.1 (R2006b):

New Features and Changes	Version Compatibility Considerations	Fixed Bugs and Known Problems
No	No	Yes Details

The SystemTest software was introduced in R2006a+. See “Version 1.0 (R2006a+) SystemTest Software” on page 40 for details about this product.

This release includes bug fixes or enhancements, which are listed below.

Bug Fixes or Enhancements

The following enhancements were made in Version 1.0.1:

- The Stop element can now be used in Pre Test. In Version 1.0, it could be used only in Main Test. It is now available in both Main Test and Pre Test.
- The Stop element now generates a hyperlink in the **Run Status** pane that gives the name of the Stop element that terminated the test and shows the element in the SystemTest desktop.

Version 1.0 (R2006a+) SystemTest Software

This table summarizes what's new in Version 1.0 (R2006a+):

New Features and Changes	Version Compatibility Considerations	Fixed Bugs and Known Problems
Yes Details below	No	No

Version 1.0 was released in Web-downloadable form after R2006a, and includes the features listed below.

The SystemTest product provides a software framework for developing tests that exercise MATLAB algorithms and Simulink models. It includes predefined test elements that let you build and maintain standard test routines. You can save and share tests throughout a development project, ensuring standard and repeatable test verification from research and development through preproduction. You can map test variables into a result set for analysis.

SystemTest is integrated with MATLAB, enabling you to use the MATLAB scripting language and analysis tools to explore large data sets and gain further insight into the behavior of the system. Key features include:

- Develops, manages, and edits test structures
- Uses predefined test elements to test MATLAB algorithms and Simulink models
- Incorporates MATLAB scripts directly into a test
- Maps MATLAB and Simulink workspace variables to test variables
- Offers reusability, so that after you design a test, you can save it for later use by you or others
- Visualizes and analyzes multidimensional test results

Compatibility Summary for SystemTest Software

This table summarizes new features and changes that might cause incompatibilities when you upgrade from an earlier version, or when you use files on multiple versions. Details are provided in the description of the new feature or change.

Version (Release)	New Features and Changes with Version Compatibility Impact
Latest Version V2.6.3 (R2012a)	None
V2.6.2 (R2011b)	None
V2.6.1 (R2011a)	See the Compatibility Considerations subheading for this change: <ul style="list-style-type: none"> • “Deprecation of Test Results Viewer” on page 6
V2.6 (R2010b)	See the Compatibility Considerations subheading for these changes: <ul style="list-style-type: none"> • Deprecation of Test Results Viewer • Plot Element Transition
V2.5 (R2010a)	See the Compatibility Considerations subheading for this change: <ul style="list-style-type: none"> • Plot Element Transition
V2.4 (R2009b)	See the Compatibility Considerations subheading for this change: <ul style="list-style-type: none"> • Plot Element Transition

Version (Release)	New Features and Changes with Version Compatibility Impact
V2.3 (R2009a)	See the Compatibility Considerations subheading for this change: <ul style="list-style-type: none">• Plot Element Transition
V2.2 (R2008b)	None
V2.1 (R2008a)	See the Compatibility Considerations subheading for these changes: <ul style="list-style-type: none">• M API to Access Test Results in MATLAB• Test File Format Change• General UI Changes
V2.0 (R2007b)	See the Compatibility Considerations subheading for this change: <ul style="list-style-type: none">• Invalid Characters in Element Names
V1.1 (R2007a)	See the Compatibility Considerations subheading for this change: <ul style="list-style-type: none">• “Remove Test Vectors from the Limit Check Element” on page 38
V1.0.1 (R2006b)	None
V1.0 (R2006a+)	None