

Release Notes for SB2SL

How to Contact MathWorks



www.mathworks.com Web
comp.soft-sys.matlab Newsgroup
www.mathworks.com/contact_TS.html Technical Support



suggest@mathworks.com Product enhancement suggestions
bugs@mathworks.com Bug reports
doc@mathworks.com Documentation error reports
service@mathworks.com Order status, license renewals, passcodes
info@mathworks.com Sales, pricing, and general information



508-647-7000 (Phone)



508-647-7001 (Fax)



The MathWorks, Inc.
3 Apple Hill Drive
Natick, MA 01760-2098

For contact information about worldwide offices, see the MathWorks Web site.

Release Notes for SB2SL

© COPYRIGHT 2007–2012 by The MathWorks, Inc.

The software described in this document is furnished under a license agreement. The software may be used or copied only under the terms of the license agreement. No part of this manual may be photocopied or reproduced in any form without prior written consent from The MathWorks, Inc.

FEDERAL ACQUISITION: This provision applies to all acquisitions of the Program and Documentation by, for, or through the federal government of the United States. By accepting delivery of the Program or Documentation, the government hereby agrees that this software or documentation qualifies as commercial computer software or commercial computer software documentation as such terms are used or defined in FAR 12.212, DFARS Part 227.72, and DFARS 252.227-7014. Accordingly, the terms and conditions of this Agreement and only those rights specified in this Agreement, shall pertain to and govern the use, modification, reproduction, release, performance, display, and disclosure of the Program and Documentation by the federal government (or other entity acquiring for or through the federal government) and shall supersede any conflicting contractual terms or conditions. If this License fails to meet the government's needs or is inconsistent in any respect with federal procurement law, the government agrees to return the Program and Documentation, unused, to The MathWorks, Inc.

Trademarks

MATLAB and Simulink are registered trademarks of The MathWorks, Inc. See www.mathworks.com/trademarks for a list of additional trademarks. Other product or brand names may be trademarks or registered trademarks of their respective holders.

Patents

MathWorks products are protected by one or more U.S. patents. Please see www.mathworks.com/patents for more information.

R2012b+

Second-Order Integrator Conversion	2
------------------------------------------	---

R2012a+

No New Features or Changes

R2011b+

Trigonometric Blocks Now Converted to Algebraic Equivalents	6
Translator Options Tab	7

R2011a+

No New Features or Changes

R2010b+

Support for the Simulink For Each Subsystem Block	12
Saving and Restoring the Complete SimState	13

R2010a+

ConstantAlgebraicExpression and ConstantLogicalExpression Blocks Now Converted to Simulink Constant Block	16
Translator Options Dialog Box Change for Report Format Tab	17
Multiple Procedure Blocks with Same Name are Now Converted	18
Printing from Tree View Behavior Changed	19

R2009b+

Translation Improvements	22
--------------------------------	----

R2009a+

Translations Use Simulink Switch Block	24
Translations Use Simulink Integer Delay Block Where Appropriate	25
Translations Use Simulink Native Logic Blocks When Requested	26

R2008b+

No New Features or Changes

R2008a+

Unified Translator Options and Windows Preferences Dialog Boxes	30
New Save Button for User Preferences	31
New Translation Build Options Check Box	32

Fixed Bugs	33
------------------	----

R2007b+

Block Wiring Alignment Changes for Inports and Outports	36
Naming Changes	37
General Translation Changes	38
Visual Changes	40
Fixed Bugs	41

R2012b+

Version: 2.7.10
New Features: No
Bug Fixes: No

Second-Order Integrator Conversion

The SB2SL translator now converts second-order integrator blocks in the SystemBuild™ model to the native Simulink® Second-Order Integrator block. This change improves efficiency of generated code and performance, such as efficient detection of zero crossings and prevention of direct feedthrough and algebraic loops. In previous releases, the translator converted these SystemBuild blocks to the SB2SL NthOrder1 block with the **Order of Integration** parameter set to 2.

R2012a+

Version: 2.7.9
New Features: No
Bug Fixes: No

No New Features or Changes

R2011b+

Version: 2.7.8
New Features: Yes
Bug Fixes: No

Trigonometric Blocks Now Converted to Algebraic Equivalents

The SB2SL translator now converts SystemBuild model trigonometric blocks to the algebraic equivalent of their compound trigonometric functions. This change improves efficiency of generated code and performance. In previous releases, the translator converted these SystemBuild model blocks to combinations of native Simulink trigonometric functions.

Translator Options Tab

The **View report after report creation** check box on the SB2SL: Translator Options > Report Format tab is now enabled only when the **Format** parameter is set to Web (HTML). In previous releases, this check box was always enabled.

R2011a+

Version: 2.7.7
New Features: No
Bug Fixes: No

No New Features or Changes

R2010b+

Version: 2.7.6
New Features: Yes
Bug Fixes: No

Support for the Simulink For Each Subsystem Block

The SB2SL translator now supports the Simulink For Each Subsystem within the limitations of that subsystem.

Saving and Restoring the Complete SimState

Use the SimState feature to save the complete simulation state. Unlike the final states stored in earlier versions of Simulink, the SimState contains the complete simulation state of the model (including block states that are logged). You can then restore the state at a later time and continue simulation from the exact instant at which you stopped the simulation. See [Saving and Restoring the Simulation State as the SimState](#) in the Simulink User's Guide.

R2010a+

Version: 2.7.5
New Features: Yes
Bug Fixes: No

ConstantAlgebraicExpression and ConstantLogicalExpression Blocks Now Converted to Simulink Constant Block

The SB2SL translator now converts SystemBuild model ConstantAlgebraicExpression and ConstantLogicalExpression blocks to the native Simulink Constant block. In previous releases, the translator converted these SystemBuild model blocks to the Simulink S-functions.

Translator Options Dialog Box Change for Report Format Tab

The SB2SL File > Preferences > Report Format tab **View report after conversion** check box has changed:

- The new name is **View report after report creation**.
- Select this check box to display the report after it is created.

Multiple Procedure Blocks with Same Name are Now Converted

The SB2SL translator now converts multiple procedure blocks with the same name. In previous releases, the translator was unable to convert multiple procedure blocks with the same name.

Printing from Tree View Behavior Changed

The SB2SL translator now prints the requested tree view for your model as selected in the **Window > Tree** menu. In previous releases, the translator reverted the view to **Normal** before printing.

R2009b+

Version: 2.7.4
New Features: Yes
Bug Fixes: No

Translation Improvements

A number of translation improvements have been made to improve block conversion results.

R2009a+

Version: 2.7.3
New Features: Yes
Bug Fixes: No

Translations Use Simulink Switch Block

The SB2SL translator now converts SystemBuild model switch blocks to the native Simulink Switch block. In previous releases, the translator converted SystemBuild model switch blocks to the SB2SL library Switch block.

The difference between the Simulink Switch block and its SystemBuild counterpart is the order of the input ports. During translation, the SB2SL translator converts to the Simulink Switch block port order.

The SB2SL library Switch block continues to exist for SystemBuild models translated in previous releases.

Translations Use Simulink Integer Delay Block Where Appropriate

The SB2SL translator now converts SystemBuild model integer delay blocks to the native Simulink Integer Delay block where appropriate. This substitution occurs only if the SystemBuild model delays are integer values of the sample time. If the SystemBuild model delays are noninteger values of the sample time, the translator continues to use the SB2SL library DTimeDelay block.

Translations Use Simulink Native Logic Blocks When Requested

Upon request, the SB2SL translator now converts SystemBuild model logic blocks to the native Simulink logic blocks where appropriate. This substitution occurs only if you select SB2SL **Preferences** > **Build** and then select the **Logic blocks** check box. See Translation Build Options in the SB2SL User's Guide.

R2008b+

Version: 2.7.2
New Features: No
Bug Fixes: No

No New Features or Changes

R2008a+

Version: 2.7.1
New Features: Yes
Bug Fixes: No

Unified Translator Options and Windows Preferences Dialog Boxes

The SB2SL translator options and windows preferences dialog boxes are now consolidated on SB2SL **File > Preferences**. For further details, see Setting Translation Options in the SB2SL User's Guide.

In previous releases, the SB2SL translator options were located in **Build > Options** and the windows preferences were located in **Windows > Preferences**.

New Save Button for User Preferences

The SB2SL Translator Options dialog box now has a **Save** button. Clicking this button saves and applies your selections. The next time you restart SB2SL, it loads the saved settings. In previous releases, you were not able to save preferences. For further details, see [Generating a Report](#) in the SB2SL User's Guide.

New Translation Build Options Check Box

The SB2SL **File > Preferences > Translation Build Options** tab contains a new check box, **Use round sum block**. When you select this check box, SB2SL uses a round summing junction instead of a square one in the Simulink model. This is only a visual change. For further details, see Translation Build Options in the SB2SL User's Guide.

Fixed Bugs

This section lists fixes to bugs that occurred in the previous version of SB2SL.

Translation of Some Block IDs to Annotations Failed

In the previous release, there was an issue in the way that SB2SL handled the translation of some block IDs to annotations. This is no longer an issue. SB2SL can now translate all expected blocks.

R2007b+

Version: 2.7
New Features: Yes
Bug Fixes: No

Block Wiring Alignment Changes for Inports and Outports

When SB2SL converts a National Instruments® SystemBuild model to a Simulink model, it organizes the model blocks and the connections between them using a predefined algorithm. In this release, SB2SL now converts the models with the following conventions to improve block layout:

- Aligns inport blocks at the same height as the signal port that they drive
- Places inport blocks near the block port they connect to
- Staggers input blocks horizontally to prevent overlapping
- Aligns output blocks at the same height as and within a fixed distance of the signal port that drives them
- Staggers output blocks horizontally to prevent overlapping
- Uses duplicate inport blocks for multirouted inport signals instead of routing multiple wires from a single port

Naming Changes

SB2SL now converts the names in SystemBuild models in the following way:

- SB2SL now names the top-level model for its corresponding SuperBlock. This helps with component-based modeling. In previous releases, SB2SL named the top-level model untitled.
- SB2SL now names converted subsystems for their SuperBlocks without including the block ID in the block name. SB2SL now includes the block ID in the 'AttributesFormatString' property of the Subsystem block (see Default Conversion Results in the SB2SL User's Guide).
- All inport blocks now follow the standard Simulink naming pattern *InNN* instead of the previous *input-NN* pattern.
- Inport and Output block names no longer appear under the block by default. To display the block name, select **Format > Show Name** for the block. In previous releases, Inport and Output block names were displayed under the blocks.
- All outport blocks now follow the standard Simulink naming pattern *OutNN* instead of the previous *output-NN* pattern.
- SB2SL blocks now insert the block ID in the 'AttributesFormatString' property of the block by default. The ID is still visible just below the block name, but it is not part of the block name. See the **Put IDs in annotations** build option in Translation Build Options of the SB2SL User's Guide.
- For unnamed SystemBuild blocks, SB2SL provides a unique canonical name in the Simulink environment (such as *Sum*, *Product*, and so forth) and hides the name. To display the block name, select **Format > Show Name** for the block.

General Translation Changes

SB2SL has the following general translation changes:

- SB2SL now recognizes both the `.sbd` and `.xmd` file extensions. You can open these as long as they are in the textual format. In previous releases, SB2SL recognized only `.xmd` file extensions.
- SB2SL now enables the following:
 - Code reuse (to support the `Reusable` function option of the **Real-Time Workshop system code** parameter for subsystem blocks (see “Nonvirtual Subsystem Code Generation Options” in the Real-Time Workshop® User’s Guide.)
 - Variable-step solvers in referenced models
 - Improved performance with accelerated models
 - Simulink Normal mode for model reference

These changes are for the following blocks in the SB2SL library:

1VarPoly
 ConditionBlock
 DAxisRotation
 Decoder
 Encoder
 IAxisRotation
 LogExpression
 ZILogExpression
 General
 General0

- SB2SL now optionally converts the Condition block using native Simulink if-else blocks and action subsystems for the Condition block **Mode** parameter set to `With Default` and `No Default`. This change allows the Simulink software to provide additional optimization and configuration ability in simulation and code generation. See the **Use native blocks if possible** build option in Translation Build Options of the SB2SL User’s Guide.
- The following SB2SL Build menu translation options have been added:

- **Create SuperBlock libraries**
- **Use native blocks if possible**
- **Put IDs in annotations**
- The SB2SL Build menu **Avoid block crossing** translation option has been renamed to **Route wires around blocks**.
- SB2SL now converts procedure SuperBlocks to atomic subsystems.
- BlockScripts now support code generation, with the following limitations:
 - BlockScripts that contain scalar parameters cannot generate embedded real-time (ERT) target code.
 - BlockScripts cannot be used in referenced models.

Visual Changes

SB2SL has the following visual changes:

- If a SystemBuild blocks has its border option enabled, SB2SL no longer converts that block with a drop shadow.
- SB2SL dialog boxes for error, query, and options now have improved fonts, colors, layout, and interactivity.

Fixed Bugs

This section lists fixes to bugs that occurred in the previous version of SB2SL.

Selecting SuperBlocks for Conversion of Smaller SystemBuild Models Was Not Possible

In a previous release, you could not select a SuperBlock in SB2SL and convert just that block to a smaller SystemBuild model. This is no longer a problem.

SB2SL Cannot Convert SystemBuild Models that Contain Limiter Functions with Particular Limits

SB2SL cannot convert SystemBuild models that contain limiter functions with an upper limit parameter value that is less than the lower limit parameter value. (The larger value is used for the upper limit parameter and the smaller value is used for the lower limit parameter.) This is no longer a problem.