

NAG C Library Function Document

nag_opt_nlp_option_get_integer (e04wkc)

1 Purpose

`nag_opt_nlp_option_get_integer (e04wkc)` is used to get the value of an Integer optional argument. `nag_opt_nlp_option_get_integer (e04wkc)` can be used before or after calling `nag_opt_nlp_solve (e04wdc)`.

2 Specification

```
#include <nag.h>
#include <nage04.h>

void nag_opt_nlp_option_get_integer (const char *string, Integer *ivalue,
                                     Nag_E04State *state, NagError *fail)
```

3 Description

`nag_opt_nlp_option_get_integer (e04wkc)` obtains the current value of an integer option. For example

```
e04wkc ("Iterations", &itnlim, &state, &fail);
```

will result in the value of the optional argument **Iterations** being output in `itnlim`.

A complete list of optional arguments, their abbreviations, synonyms and default values is given in Section 11 of the document for `nag_opt_nlp_solve (e04wdc)`.

4 References

None.

5 Arguments

- | | | |
|----|--|--------------------------------|
| 1: | string – const char * | <i>Input</i> |
| | <i>On entry:</i> a single valid keyword of an Integer optional argument (as described in Section 11 of the document for <code>nag_opt_nlp_solve (e04wdc)</code>). | |
| 2: | ivalue – Integer * | <i>Output</i> |
| | <i>On exit:</i> the Integer value associated with the keyword in string . | |
| 3: | state – Nag_E04State * | <i>Communication Structure</i> |
| | Note: state is a NAG defined type (see Section 2.2.1.1 of the Essential Introduction). | |
| | state contains internal information required for functions in this suite. It must not be modified in any way. | |
| 4: | fail – NagError * | <i>Input/Output</i> |
| | The NAG error argument (see Section 2.6 of the Essential Introduction). | |

6 Error Indicators and Warnings

NE_BAD_PARAM

On entry, argument $\langle\text{value}\rangle$ had an illegal value.

NE_E04_OPTION_INVALID

The supplied option string is invalid. Check that the keywords are neither ambiguous nor misspelt. The option **string** is $\langle value \rangle$.

NE_E04WCC_NOT_INIT

Initialization function nag_opt_nlp_init (e04wcc) has not been called.

NE_INTERNAL_ERROR

An internal error has occurred in this function. Check the function call and any array sizes. If the call is correct then please consult NAG for assistance.

7 Accuracy

Not applicable.

8 Further Comments

None.

9 Example

See Section 9 of the document for nag_opt_nlp_option_set_file (e04wec).
