

# Creating and Downloading Waveform Files

## Agilent Technologies N5182A/E4438C/E8267D Signal Generators

This guide applies to the following signal generator models:

**N5182A MXG Signal Generator**

**E4438C ESG Signal Generator**

**E8267D PSG Signal Generator**

Due to our continuing efforts to improve our products through firmware and hardware revisions, signal generator design and operation may vary from descriptions in this guide. We recommend that you use the latest revision of this guide to ensure you have up-to-date product information. Compare the print date of this guide (see bottom of page) with the latest revision, which can be downloaded from the following websites:

*<http://www.agilent.com/find/intuilink>*

*<http://www.agilent.com/find/downloadassistant>*

*<http://www.agilent.com/find/signalstudio>*

*<http://www.agilent.com/find/mxg>*

*<http://www.agilent.com/find/psg>*

*<http://www.agilent.com/find/esg>*



**Agilent Technologies**

**Manufacturing Part Number: E4400-90627**

**Printed in USA**

**September 26, 2006**

© Copyright 2006 Agilent Technologies, Inc.

---

## Notice

The material contained in this document is provided “as is”, and is subject to being changed, without notice, in future editions.

Further, to the maximum extent permitted by applicable law, Agilent disclaims all warranties, either express or implied with regard to this manual and to any of the Agilent products to which it pertains, including but not limited to the implied warranties of merchantability and fitness for a particular purpose. Agilent shall not be liable for errors or for incidental or consequential damages in connection with the furnishing, use, or performance of this document or any of the Agilent products to which it pertains. Should Agilent have a written contract with the User and should any of the contract terms conflict with these terms, the contract terms shall control.

**Creating and Downloading Waveform Files**

|  |    |
|--|----|
| Overview of Downloading and Extracting Waveform Files . . . . .                | 2  |
| Waveform Data Requirements . . . . .   | 3  |
| Understanding Waveform Data . . . . .  | 4  |
| Bits and Bytes . . . . .   | 4  |
| LSB and MSB (Bit Order) . . . . .  | 4  |
| Little Endian and Big Endian (Byte Order) . . . . .                            | 5  |
| Byte Swapping . . . . .  | 6  |
| DAC Input Values . . . . .   | 7  |
| 2's Complement Data Format . . . . .   | 9  |
| I and Q Interleaving . . . . .   | 10 |
| Waveform Structure . . . . .   | 11 |
| File Header . . . . .  | 11 |
| Marker File . . . . .  | 11 |
| I/Q File . . . . .   | 13 |
| Waveform . . . . .   | 13 |
| Waveform Phase Continuity . . . . .  | 14 |
| Phase Discontinuity, Distortion, and Spectral Regrowth . . . . .               | 14 |
| Avoiding Phase Discontinuities . . . . .                                       | 14 |
| Waveform Memory . . . . .  | 17 |
| Memory Allocation . . . . .  | 20 |
| Memory Size . . . . .  | 22 |
| Commands for Downloading and Extracting Waveform Data . . . . .                | 24 |
| Waveform Data Encryption . . . . .   | 24 |
| File Transfer Methods . . . . .  | 26 |
| SCPI Command Line Structure . . . . .  | 26 |
| Commands and File Paths for Downloading and Extracting Waveform Data . . . . . | 27 |
| FTP Procedures . . . . .   | 31 |
| Creating Waveform Data . . . . .   | 33 |
| Code Algorithm . . . . .   | 33 |
| Downloading Waveform Data . . . . .  | 40 |
| Using Simulation Software . . . . .  | 40 |
| Using Advanced Programming Languages . . . . .                                 | 43 |
| Loading, Playing, and Verifying a Downloaded Waveform . . . . .                | 46 |
| Loading a File from Non-Volatile Memory . . . . .                              | 46 |
| Playing the Waveform . . . . .   | 46 |
| Verifying the Waveform . . . . .   | 47 |
| Building and Playing Waveform Sequences . . . . .                              | 48 |
| Using the Download Utilities . . . . .   | 49 |
| Downloading E443xB Signal Generator Files . . . . .                            | 50 |

---

# Contents

- E443xB Data Format . . . . . 50
- Storage Locations for E443xB ARB files. . . . . 50
- SCPI Commands . . . . . 51
- Programming Examples. . . . . 53
  - C++ Programming Examples. . . . . 53
  - MATLAB Programming Examples . . . . . 78
  - Visual Basic Programming Examples . . . . . 85
  - HP Basic Programming Examples . . . . . 91
- Troubleshooting Waveform Files . . . . . 100
  - Configuring the Pulse/RF Blank (Agilent MXG) . . . . . 101
  - Configuring the Pulse/RF Blank (ESG/PSG) . . . . . 101

---

# Creating and Downloading Waveform Files

---

**NOTE** The ability to play externally created waveform data in the signal generator is available only in the N5182A with Option 651/652/654, E4438C ESG Vector Signal Generators with Option 001/601 or 002/602, and E8267D PSG Vector Signal Generators with Option 601 or 602.

---

This manual explains how to create Arb-based waveform data and download it into the signal generator. This information is also available in the signal generator's *Programming Guide*.

- [“Overview of Downloading and Extracting Waveform Files” on page 2](#)
- [“Understanding Waveform Data” on page 4](#)
- [“Waveform Structure” on page 11](#)
- [“Waveform Phase Continuity” on page 14](#)
- [“Waveform Memory” on page 17](#)
- [“Commands for Downloading and Extracting Waveform Data” on page 24](#)
- [“Creating Waveform Data” on page 33](#)
- [“Downloading Waveform Data” on page 40](#)
- [“Loading, Playing, and Verifying a Downloaded Waveform” on page 46](#)
- [“Using the Download Utilities” on page 49](#)
- [“Downloading E443xB Signal Generator Files” on page 50](#)
- [“Programming Examples” on page 53](#)
- [“Troubleshooting Waveform Files” on page 100](#)

## Overview of Downloading and Extracting Waveform Files

The signal generator lets you download and extract waveform files. You can create these files either external to the signal generator or by using one of the internal modulation formats (ESG/PSG only). The signal generator also accepts waveform files created for the earlier E443xB ESG signal generator models. For file extractions, the signal generator encrypts the waveform file information. The exception to encrypted file extraction is user-created I/Q data. The signal generator lets you extract this type of file unencrypted. After extracting a waveform file, you can download it into another Agilent signal generator that has the same option or software license required to play it. Waveform files consist of three items:

1. I/Q data
2. Marker data
3. File header

---

**NOTE** This order of download is required, as the I/Q data downloads result in deletion of all of these three parts of the file.

---

The signal generator automatically creates the marker file and the file header if the two items are *not* part of the download. In this situation, the signal generator sets the file header information to unspecified (no settings saved) and sets all markers to zero (off).

There are three ways to download waveform files: FTP, programmatically or using one of three available free download utilities created by Agilent Technologies:

- Intuilink for Agilent PSG/ESG Signal Generators  
<http://www.agilent.com/find/intuilink>

---

**NOTE** Agilent Intuilink is *not* available for the Agilent MXG.

---

- Agilent MXG/PSG/ESG Download Assistant for use only with MATLAB  
<http://www.agilent.com/find/downloadassistant>
- N7622A Signal Studio Toolkit  
<http://www.agilent.com/find/signalstudio>

---

**NOTE** FTP can be used without programming commands to transfer files from the PC to the signal generator or from the signal generator to the PC.

---

## Waveform Data Requirements

To be successful in downloading files, you must first create the data in the required format.

- Signed 2's complement
- 2-byte integer values
- Input data range of  $-32768$  to  $32767$
- Minimum of 60 samples per waveform (60 I and 60 Q data points)
- Interleaved I and Q data
- Big endian byte order
- The same name for the marker, header, and I/Q file

This is only a requirement if you create and download a marker file and or file header, otherwise the signal generator automatically creates the marker file and or file header using the I/Q data file name. For more information, see [“Waveform Structure” on page 11](#).

For more information on waveform data, see [“Understanding Waveform Data” on page 4](#).

## Understanding Waveform Data

The signal generator accepts binary data formatted into a binary I/Q file. This section explains the necessary components of the binary data, which uses ones and zeros to represent a value.

### Bits and Bytes

Binary data uses the base-two number system. The location of each bit within the data represents a value that uses base two raised to a power ( $2^{n-1}$ ). The exponent is  $n - 1$  because the first position is zero. The first bit position, zero, is located at the far right. To find the decimal value of the binary data, sum the value of each location:

$$\begin{aligned} 1101 &= (1 \times 2^3) + (1 \times 2^2) + (0 \times 2^1) + (1 \times 2^0) \\ &= (1 \times 8) + (1 \times 4) + (0 \times 2) + (1 \times 1) \\ &= 13 \text{ (decimal value)} \end{aligned}$$

Notice that the exponent identifies the bit position within the data, and we read the data from right to left.

The signal generator accepts data in the form of bytes. Bytes are groups of eight bits:

$$\begin{aligned} 01101110 &= (0 \times 2^7) + (1 \times 2^6) + (1 \times 2^5) + (0 \times 2^4) + (1 \times 2^3) + (1 \times 2^2) + (1 \times 2^1) + (0 \times 2^0) \\ &= 110 \text{ (decimal value)} \end{aligned}$$

The maximum value for a single unsigned byte is 255 ( $11111111$  or  $2^8-1$ ), but you can use multiple bytes to represent larger values. The following shows two bytes and the resulting integer value:

$$01101110 \ 10110011 = 28339 \text{ (decimal value)}$$

The maximum value for two unsigned bytes is 65535. Since binary strings lengthen as the value increases, it is common to show binary values using hexadecimal (hex) values (base 16), which are shorter. The value 65535 in hex is FFFF. Hexadecimal consists of the values 0, 1, 2, 3, 4, 5, 6, 7, 8, 9, A, B, C, D, E, and F. In decimal, hex values range from 0 to 15 (F). It takes 4 bits to represent a single hex value.

|          |          |          |          |          |
|----------|----------|----------|----------|----------|
| 1 = 0001 | 2 = 0010 | 3 = 0011 | 4 = 0100 | 5 = 0101 |
| 6 = 0110 | 7 = 0111 | 8 = 1000 | 9 = 1001 | A = 1010 |
| B = 1011 | C = 1100 | D = 1101 | E = 1110 | F = 1111 |

For I and Q data, the signal generator uses two bytes to represent an integer value.


### LSB and MSB (Bit Order)

Within groups (strings) of bits, we designate the order of the bits by identifying which bit has the highest value and which has the lowest value by its location in the bit string. The following is an example of this order.

Most Significant Bit (MSB)      This bit has the highest value (greatest weight) and is located at the far left of the bit string.



Least Significant Bit (LSB) This bit has the lowest value (bit position zero) and is located at the far right of the bit string.




Because we are using 2 bytes of data, the LSB appears in the second byte.

### Little Endian and Big Endian (Byte Order)

When you use multiple bytes (as required for the waveform data), you must identify their order. This is similar to identifying the order of bits by LSB and MSB. To identify byte order, use the terms little endian and big endian. These terms are used by designers of computer processors.


#### Little Endian Order (Or “Intel Order”)

The lowest order byte that contains bits 0–7 comes first.



#### Big Endian Order

The highest order byte that contains bits 8–15 comes first.



Notice in the previous figure that the LSB and MSB positioning changes with the byte order. In little endian order, the LSB and MSB are next to each other in the bit sequence.

---

Intel is a registered trademark of Intel Corporation.

---

**NOTE** For I/Q data downloads, the signal generator requires big endian order. For each I/Q data point, the signal generator uses four bytes (two integer values), two bytes for the I point and two bytes for the Q point.

---

The byte order, little endian or big endian, depends on the type of processor used with your development platform. Intel processors and its clones use little endian. (Intel© is a U.S. registered trademark of Intel Corporation.) Sun™ and Motorola processors use big endian. The Apple PowerPC processor, while big endian oriented, also supports the little endian order. Always refer to the processor’s manufacturer to determine the order they use for bytes and if they support both, to understand how to ensure that you are using the correct byte order.


Development platforms include any product that creates and saves waveform data to a file. This includes Agilent Technologies Advanced Design System EDA software, C++, MATLAB, and so forth.

The byte order describes how the system processor stores integer values as binary data in memory. If you output data from a little endian system to a text file (ASCII text), the values are the same as viewed from a big endian system. The order only becomes important when you use the data in binary format, as is done when downloading data to the signal generator.

## Byte Swapping

While the processor for the development platform determines the byte order, the recipient of the data may require the bytes in the reverse order. In this situation, you must reverse the byte order before downloading the data. This is commonly referred to as byte swapping. You can swap bytes either programmatically or by using the Agilent Technologies IntuiLink for Agilent MXG, PSG, and ESG Signal Generators software. For the signal generator, byte swapping is the method to change the byte order of little endian to big endian. For more information on little endian and big endian order, see “Little Endian and Big Endian (Byte Order)” on page 5.

The following figure shows the concept of byte swapping for the signal generator. Remember that we can represent data in hex format (4 bits per hex value), so each byte (8 bits) in the figure shows two example hex values.



---

Sun is a trademark or registered trademark of Sun Microsystems, Inc. in the U.S. and other countries.

To correctly swap bytes, you must group the data to maintain the I and Q values. One common method is to break the two-byte integer into one-byte character values (0–255). Character values use 8 bits (1 byte) to identify a character. Remember that the maximum unsigned 8-bit value is 255 ( $2^8 - 1$ ). Changing the data into character codes groups the data into bytes. The next step is then to swap the bytes to align with big endian order.

---

**NOTE** The signal generator always assumes that downloaded data is in big endian order, so there is no data order check. Downloading data in little endian order will produce an undesired output signal.

---

## DAC Input Values

The signal generator uses a 16-bit DAC (digital-to-analog convertor) to process each of the 2-byte integer values for the I and Q data points. The DAC determines the range of input values required from the I/Q data. Remember that with 16 bits we have a range of 0–65535, but the signal generator divides this range between positive and negative values:

- 32767 = positive full scale output
- 0 = 0 volts
- -32768 = negative full scale output

Because the DAC's range uses both positive and negative values, the signal generator requires signed input values. The following list illustrates the DAC's input value range.

| <u>Voltage</u> | <u>DAC Range</u> | <u>Input Range</u> | <u>Binary Data</u> | <u>Hex Data</u> |
|----------------|------------------|--------------------|--------------------|-----------------|
| Vmax           | 65535            | 32767              | 01111111 11111111  | 7FFF            |
| ⋮              | ⋮                | ⋮                  | ⋮                  | ⋮               |
| ⋮              | 32768            | 1                  | 00000000 00000001  | 0001            |
| 0 Volts        | 32767            | 0                  | 00000000 00000000  | 0000            |
| ⋮              | 32766            | -1                 | 11111111 11111111  | FFFF            |
| ⋮              | ⋮                | ⋮                  | ⋮                  | ⋮               |
| Vmin           | 0                | -32768             | 10000000 00000000  | 8000            |

Notice that it takes only 15 bits ( $2^{15}$ ) to reach the Vmax (positive) or Vmin (negative) values. The MSB determines the sign of the value. This is covered in [“2's Complement Data Format” on page 9](#).

### Using E443xB ESG DAC Input Values

In this section, the words *signal generator* with or without a model number refer to an N5182A Agilent MXG, E4438C ESG, E8267D PSG. The signal generator input values differ from those of the earlier E443xB ESG models. For the E443xB models, the input values are all positive (unsigned) and

the data is contained within 14 bits plus 2 bits for markers. This means that the E443xB DAC has a smaller range:

- 0 = negative full scale output
- 8192 = 0 volts
- 16383 = positive full scale output

Although the signal generator uses signed input values, it accepts unsigned data created for the E443xB and converts it to the proper DAC values. To download an E443xB files to the signal generator, use the same command syntax as for the E443xB models. For more information on downloading E443xB files, see “[Downloading E443xB Signal Generator Files](#)” on page 50.


### Scaling DAC Values

The signal generator uses an interpolation algorithm (sampling between the I/Q data points) when reconstructing the waveform. For common waveforms, this interpolation can cause overshoot, which may exceed the limits of the signal process path’s internal number representation, causing arithmetic overload. This will be reported as either a data path overload error (N5182A) or a DAC over-range error condition (E4438C/E8267D). Because of the interpolation, the error condition can occur even when all the I and Q values are within the DAC input range. To avoid the DAC over-range problem, you must scale (reduce) the I and Q input values, so that any overshoot remains within the DAC range.

---

**NOTE** Whenever you interchange files between signal generator models, ensure that all scaling is adequate for that signal generator’s waveform.

---



There is no single scaling value that is optimal for all waveforms. To achieve the maximum dynamic

range, select the largest scaling value that does not result in a DAC over-range error. There are two ways to scale the I/Q data:

- Reduce the input values for the DAC.
- Use the SCPI command `:RADiO:ARB:RSCaling <val>` to set the waveform amplitude as a percentage of full scale.

**NOTE** The signal generator factory preset for scaling is 70%. If you reduce the DAC input values, ensure that you set the signal generator scaling (`:RADiO:ARB:RSCaling`) to an appropriate setting that accounts for the reduced values.

To further minimize overshoot problems, use the correct FIR filter for your signal type and adjust your sample rate to accommodate the filter response.

**NOTE** FIR filter capability is only available on the E4438C with Option 001/601 or 002/602 and on the E8267D with Option 601 or 602.

## 2's Complement Data Format

The signal generator requires signed values for the input data. For binary data, two's complement is a way to represent positive and negative values. The most significant bit (MSB) determines the sign.

- 0 equals a positive value (01011011 = 91 decimal)
- 1 equals a negative value (10100101 = -91 decimal)

Like decimal values, if you sum the binary positive and negative values, you get zero. The one difference with binary values is that you have a carry, which is ignored. The following shows how to calculate the two's complement using 16-bits. The process is the same for both positive and negative values.

Convert the decimal value to binary.

```
23710 = 01011100 10011110
```

Notice that 15 bits (0-14) determine the value and bit 16 (MSB) indicates a positive value. Invert the bits (1 becomes 0 and 0 becomes 1).

```
10100011 01100001
```

Add one to the inverted bits. Adding one makes it a two's complement of the original binary value.

```
10100011 01100001
+ 00000000 00000001
10100011 01100010
```

The MSB of the resultant is one, indicating a negative value (-23710).

Test the results by summing the binary positive and negative values; when correct, they produce zero.

```
01011100 10011110
+ 10100011 01100010
00000000 00000000
```

## I and Q Interleaving


When you create the waveform data, the I and Q data points typically reside in separate arrays or files. The signal generator requires a single I/Q file for waveform data playback. The process of interleaving creates a single array with alternating I and Q data points, with the Q data following the I data. This array is then downloaded to the signal generator as a binary file. The interleaved file comprises the waveform data points where each set of data points, one I data point and one Q data point, represents one I/Q waveform point.

---

**NOTE** The signal generator can accept separate I and Q files created for the earlier E443xB ESG models. For more information on downloading E443xB files, see [“Downloading E443xB Signal Generator Files”](#) on page 50.

---

The following figure illustrates interleaving I and Q data. Remember that it takes two bytes (16 bits) to represent one I or Q data point.



## Waveform Structure

To play back waveforms, the signal generator uses data from the following three files:

- File header
- Marker file
- I/Q file

All three files have the same name, the name of the I/Q data file, but the signal generator stores each file in its respective directory (headers, markers, and waveform). For information on file extractions, see [“Commands for Downloading and Extracting Waveform Data” on page 24](#).

### File Header

The file header contains settings for the ARB modulation format such as sample rate, marker polarity, I/Q modulation attenuator setting and so forth. When you create and download I/Q data, the signal generator automatically creates a file header with all saved parameters set to unspecified. With unspecified header settings, the waveform either uses the signal generator default settings, or if a waveform was previously played, the settings from that waveform. Ensure that you configure and save the file header settings for each waveform.

---


**NOTE** If you have no RF output when you play back a waveform, ensure that the marker RF blanking function has not been set for any of the markers. The marker RF blanking function is a header parameter that can be inadvertently set active for a marker by a previous waveform. To check for and turn RF blanking off manually, refer to [“Configuring the Pulse/RF Blank \(Agilent MXG\)” on page 101](#) and [“Configuring the Pulse/RF Blank \(ESG/PSG\)” on page 101](#).

---

### Marker File

The marker file uses one byte per I/Q waveform point to set the state of the four markers either on (1) or off (0) for each I/Q point. When a marker is active (on), it provides an output trigger signal to the rear panel EVENT 1 connector (Marker 1 only) or and the AUX IO, event 2 connector pin (Markers 1, 2, 3, or 4), that corresponds to the active marker number. (For more information on active markers and their output trigger signal location, refer to your signal generator’s *User’s Guide*.) Because markers are set at each waveform point, the marker file contains the same number of bytes as there are waveform points. For example, for 200 waveform points, the marker file contains 200 bytes.

Although a marker point is one byte, the signal generator uses only bits 0–3 to configure the markers; bits 4–7 are reserved and set to zero. The following example shows a marker byte.



**Example of Setting a Marker Byte**

Binary 0000 0101  
Hex 05

Sets markers 1 and 3 on for a waveform point

The following example shows a marker binary file (all values in hex) for a waveform with 200 points. Notice the first marker point, 0f, shows all four markers on for only the first waveform point.

|                  |   |                         |
|------------------|---|-------------------------|
| <b>00000000:</b> | 0f 01 01 01 01 01 01 01 01 01 01 01 01 01 01 01 | 0f = All markers on     |
| <b>00000010:</b> | 01 01 01 01 01 01 01 01 01 01 01 01 01 01 01 01 | 01 = Marker 1 on        |
| <b>00000020:</b> | 01 01 01 01 01 01 01 01 01 01 01 01 01 01 01 01 | 05 = Markers 1 and 3 on |
| <b>00000030:</b> | 01 05 05 05 05 05 05 05 05 05 05 05 05 05 05 05 | 04 = Marker 3 on        |
| <b>00000040:</b> | 05 05 05 05 05 05 05 05 05 05 05 05 05 05 05 05 | 00 = No active markers  |
| <b>00000050:</b> | 05 05 05 05 05 05 05 05 05 05 05 05 05 05 05 05 |                         |
| <b>00000060:</b> | 05 05 05 05 04 04 04 04 04 04 04 04 04 04 04 04 |                         |
| <b>00000070:</b> | 04 04 04 04 04 04 04 04 04 04 04 04 04 04 04 04 |                         |
| <b>00000080:</b> | 04 04 04 04 04 04 04 04 04 04 04 04 04 04 04 04 |                         |
| <b>00000090:</b> | 04 04 04 04 04 04 00 00 00 00 00 00 00 00 00 00 |                         |
| <b>000000a0:</b> | 00 00 00 00 00 00 00 00 00 00 00 00 00 00 00 00 |                         |
| <b>000000b0:</b> | 00 00 00 00 00 00 00 00 00 00 00 00 00 00 00 00 |                         |
| <b>000000c0:</b> | 00 00 00 00 00 00 00 00 00 00 00 00 00 00 00 00 |                         |

If you create your own marker file, its name must be the same as the waveform file. If you download I/Q data without a marker file, the signal generator automatically creates a marker file with all points set to zero. For more information on markers, see the *User's Guide*.

---

**NOTE** Downloading marker data using a file name that currently resides on the signal generator overwrites the existing marker file without affecting the I/Q (waveform) file. However, downloading just the I/Q data with the same file name as an existing I/Q file also overwrites the existing marker file setting all bits to zero.

---



## I/Q File

The I/Q file contains the interleaved I and Q data points (signed 16-bit integers for each I and Q data point). Each I/Q point equals one waveform point. The signal generator stores the I/Q data in the waveform directory.

---

**NOTE** If you download I/Q data using a file name that currently resides on the signal generator, it also overwrites the existing marker file setting all bits to zero and the file header setting all parameters to unspecified.

---

## Waveform

A waveform consists of samples. When you select a waveform for playback, the signal generator loads settings from the file header. When the ARB is on, it creates the waveform samples from the data in the marker and I/Q (waveform) files. The file header, while required, does not affect the number of bytes that compose a waveform sample. One sample contains five bytes:

|                 |           |          |                                |          |                          |
|-----------------|-----------|----------|--------------------------------|----------|--------------------------|
| <b>I/Q Data</b> |           | <b>+</b> | <b>Marker Data</b>             | <b>=</b> | <b>1 Waveform Sample</b> |
| 2 bytes I       | 2 bytes Q |          | 1 byte (8 bits)                |          | 5 bytes                  |
| (16 bits)       | (16 bits) |          | Bits 4–7 reserved—Bits 0–3 set |          |                          |

To create a waveform, the signal generator requires a minimum of 60 samples. To help minimize signal imperfections, use an even number of samples (for information on waveform continuity, see [“Waveform Phase Continuity” on page 14](#)). When you store waveforms, the signal generator saves changes to the waveform file, marker file, and file header.

## Waveform Phase Continuity


### Phase Discontinuity, Distortion, and Spectral Regrowth

The most common arbitrary waveform generation use case is to play back a waveform that is finite in length and repeat it continuously. Although often overlooked, a phase discontinuity between the end of a waveform and the beginning of the next repetition can lead to periodic spectral regrowth and distortion.

For example, the sampled sinewave segment in the following figure may have been simulated in software or captured off the air and sampled. It is an accurate sinewave for the time period it occupies, however the waveform does not occupy an entire period of the sinewave or some multiple thereof. Therefore, when repeatedly playing back the waveform by an arbitrary waveform generator, a phase discontinuity is introduced at the transition point between the beginning and the end of the waveform.

Repetitions with abrupt phase changes result in high frequency spectral regrowth. In the case of playing back the sinewave samples, the phase discontinuity produces a noticeable increase in distortion components in addition to the line spectra normally representative of a single sinewave.

**Sampled Sinewave with Phase Discontinuity**



### Avoiding Phase Discontinuities

You can easily avoid phase discontinuities for periodic waveforms by simulating an integer number of cycles when you create your waveform segment.

---


**NOTE** If there are  $N$  samples in a complete cycle, only the first  $N-1$  samples are stored in the waveform segment. Therefore, when continuously playing back the segment, the first and  $N$ th waveform samples are always the same, preserving the periodicity of the waveform.

---

By adding off time at the beginning of the waveform and subtracting an equivalent amount of off time from the end of the waveform, you can address phase discontinuity for TDMA or pulsed periodic waveforms. Consequently, when the waveform repeats, the lack of signal present avoids the issue of phase discontinuity.

However, if the period of the waveform exceeds the waveform playback memory available in the arbitrary waveform generator, a periodic phase discontinuity could be unavoidable. N5110B Baseband Studio for Waveform Capture and Playback alleviates this concern because it does not rely on the signal generator waveform memory. It streams data either from the PC hard drive or the installed PCI card for N5110B enabling very large data streams. This eliminates any restrictions associated with waveform memory to correct for repetitive phase discontinuities. Only the memory capacity of the hard drive or the PCI card limits the waveform size.


### Sampled Sinewave with No Discontinuity



The following figures illustrate the influence a single sample can have. The generated 3-tone test signal requires 100 samples in the waveform to maintain periodicity for all three tones. The measurement on the left shows the effect of using the first 99 samples rather than all 100 samples. Notice all the distortion products (at levels up to  $-35$  dBc) introduced in addition to the wanted 3-tone signal. The measurement on the right shows the same waveform using all 100 samples to


maintain periodicity and avoid a phase discontinuity. Maintaining periodicity removes the distortion products.

### Phase Discontinuity



3-tone - 20 MHz Bandwidth  
Measured distortion = 35 dBc

### Phase Continuity



3-tone - 20 MHz Bandwidth  
Measured distortion = 86 dBc

## Waveform Memory

The signal generator provides two types of memory, volatile and non-volatile. You can download files to either memory type.

---

**NOTE** On the Agilent MXG the non-volatile memory is referred to as internal media and external media.

---

**Volatile** Random access memory that does not survive cycling of the signal generator power. This memory is commonly referred to as waveform memory (WFM1) or waveform playback memory. To play back waveforms, they must reside in volatile memory. The following file types share this memory:

**Table 0** Signal Generators and Volatile Memory Types

| Volatile Memory Type | Model of Signal Generator           |                                       |                          |                  |
|----------------------|-------------------------------------|---------------------------------------|--------------------------|------------------|
|                      | N5182A with Option 651, 652, or 654 | E4438C with Option 001/601 or 002/602 | E8267D Option 601 or 602 | All Other models |
| I/Q                  | x                                   | x                                     | x                        | x                |
| Marker               | x                                   | x                                     | x                        | x                |
| File header          | x                                   | x                                     | x                        | x                |
| User PRAM            | –                                   | x                                     | x                        | –                |

**Non-volatile** Storage memory where files survive cycling the signal generator power. Files remain until overwritten or deleted. To play back waveforms after cycling the signal generator power, you must load waveforms from non-volatile waveform memory (NVWFM) to volatile waveform memory (WFM1). The following file types share this memory:

**Table 1** Signal Generators and Non-Volatile Memory Types

| Non-Volatile Memory Type | Model of Signal Generator           |                                       |                          |                  |
|--------------------------|-------------------------------------|---------------------------------------|--------------------------|------------------|
|                          | N5182A with Option 651, 652, or 654 | E4438C with Option 001/601 or 002/602 | E8267D Option 601 or 602 | All Other models |
| I/Q                      | x                                   | x                                     | x                        | x                |
| Marker                   | x                                   | x                                     | x                        | x                |
| File header              | x                                   | x                                     | x                        | x                |
| Sweep List               | x                                   | x                                     | x                        | x                |


Table 1 Signal Generators and Non-Volatile Memory Types

| Non-Volatile Memory Type                                   | Model of Signal Generator |   |   |   |
|--|---------------------------|---|---|---|
| User Data  | x                         | x | x | x |
| User PRAM  | -                         | x | x | - |
| Instrument State   | x                         | x | x | x |
| Waveform Sequences<br>(multiple I/Q files played together) | x                         | x | x | - |

The following figure shows the locations within the signal generator for volatile and non-volatile waveform data.

**NOTE** The volatile memory of the signal generator can also be referred to as “WFM1” and “BBG1” memory.

In the Agilent MXG the non-volatile memory can be referred to as the internal media or external media. For more information, refer to the *User’s Guide*.



<sup>1</sup>The ARBI, ARBQ, NVARBI, NVARQ, and SECUREWAVE directories are “virtual” directories and can be used for “viewing” files only (i.e. they have no storage values on their own). For exceptions, refer to [“Non-Volatile Memory \(Agilent MXG\)” on page 20](#).

<sup>2</sup>The Agilent MXG uses an optional “External Media” to store non-volatile waveform data using a similar directory structure (i.e. HEADER, MARKERS, WAVEFORM, and SECUREWAVE).

<sup>3</sup>The Agilent MXG internal non-volatile memory is referred to as “Internal Media”.

## Memory Allocation

### Volatile Memory

The signal generator allocates volatile memory in blocks of 1024 bytes. For example, a waveform file with 60 samples (the minimum number of samples) has 300 bytes (5 bytes per sample × 60 samples), but the signal generator allocates 1024 bytes of memory. If a waveform is too large to fit into 1024 bytes, the signal generator allocates additional memory in multiples of 1024 bytes. For example, the signal generator allocates 3072 bytes of memory for a waveform with 500 samples (2500 bytes).

$$3 \times 1024 \text{ bytes} = 3072 \text{ bytes of memory}$$

As shown in the examples, waveforms can cause the signal generator to allocate more memory than what is actually used, which decreases the amount of available memory.

---

**NOTE** In the first block of data of volatile memory that is allocated for each waveform file, the file header requires 512 bytes (N5182A) or 256 bytes (E4438C/E8267D).

---

### Non-Volatile Memory (Agilent MXG)

---

**NOTE** If the Agilent MXG's external USB flash memory port is used, the USB flash memory can provide actual physical storage of non-volatile data in the SECUREWAVE directory versus the "virtual" only data.

ARB waveform encryption of proprietary information is supported on the external non-volatile USB flash memory.

---

On the N5182A, non-volatile files are stored on the non-volatile internal signal generator memory (internal media) or to an USB external media, if available.

The Agilent MXG non-volatile internal memory is allocated according to a Microsoft compatible file allocation table (FAT) file system. The Agilent MXG signal generator allocates non-volatile memory in clusters according to the drive size (see [Table 2 on page 21](#)). For example, referring to [Table 2 on page 21](#), if the drive size is 15 MB and if the file is less than or equal to 4K bytes, the file uses only one 4 KB cluster of memory. For files larger than 4 KB, and with a drive size of 15 MB, the signal generator allocates additional memory in multiples of 4KB clusters. For example, a file that has 21,538 bytes consumes 6 memory clusters (24,000 bytes).

For more information on default cluster sizes for FAT file structures, refer to [Table 2 on page 21](#) and to <http://support.microsoft.com/>.

---

Microsoft is a registered trademark of Microsoft Corporation.



**Table 2 Drive Size (logical volume)**

| Drive Size (logical volume) | Cluster Size (Bytes)<br>(Minimum Allocation Size) |
|-----------------------------|---|
| 0 MB - 15 MB                | 4K  |
| 16 MB - 127 MB              | 2K  |
| 128 MB - 255 MB             | 4K  |
| 256 MB - 511 MB             | 8K  |
| 512 MB - 1023 MB            | 16K   |
| 1024 MB - 2048 MB           | 32K   |
| 2048 MB - 4096 MB           | 64K   |
| 4096 MB - 8192 MB           | 128K  |
| 8192 MB - 16384 MB          | 256K  |

### Non-Volatile Memory (ESG/PSG)

The ESG/PSG signal generators allocate non-volatile memory in blocks of 512 bytes. For files less than or equal to 512 bytes, the file uses only one block of memory. For files larger than 512 bytes, the signal generator allocates additional memory in multiples of 512 byte blocks. For example, a file that has 21,538 bytes consumes 43 memory blocks (22,016 bytes).

## Memory Size

---

**NOTE** The Agilent MXG's baseband generator (BBG) can be used to play waveforms, but not to create them. The ESG and PSG's baseband generator (BBG) can be used to create and play waveforms.

---

The amount of available memory, volatile and non-volatile, varies by option and the size of the other files that share the memory. When we refer to waveform files, we state the memory size in samples (one sample equals five bytes). The ESG and PSG baseband generator (BBG) options (001/601 and 002/602) and the Agilent MXG baseband generator (BBG) Option (651, 652, and 654) contain the waveform playback memory. Refer to [Tables 3 on page 22](#) through [Table 5 on page 23](#) for the maximum available memory.

### Volatile and Non-Volatile Memory (N5182A)

**Table 3** N5182A Volatile (WFM1) and Non-Volatile (NVWFM) Memory

| Volatile (WFM1) Memory    |                 | Non-Volatile (NVWFM) Memory |                        |
|---------------------------|-----------------|-----------------------------|------------------------|
| Option                    | Size            | Option                      | Size                   |
| <b>N5182A<sup>1</sup></b> |                 |                             |                        |
| <b>651/652/654 (BBG)</b>  | 8 MSa (40 MB)   | <b>Standard (N5182A)</b>    | 100 MSa (512 MB)       |
| <b>019</b>                | 64 MSa (320 MB) | <b>USB memory stick</b>     | <i>user determined</i> |

1. On the N5182A, 512 bytes is reserved for each waveform's header file (i.e. The largest waveform that could be played with a N5182A with Option 019 (320 MB) is: 320 MB – 512 = 319,999,488 MB.)

## Volatile Memory and Non-Volatile Memory (E4438C and E8267D Only)

**NOTE** When considering volatile memory, it is not necessary to keep track of marker data, as this memory is consumed automatically and proportionally to the I/Q data created (i.e. 1 marker byte for every 4 bytes of I/Q data).

On the E4438C and E8267D, the fixed file system overhead on the signal generator is used to store directory information. When calculating the available volatile memory for waveform files it is important to consider the fixed file system overhead for the volatile memory of your signal generator.

**Table 4 Fixed File System Overhead**

| Volatile (WFM1) Memory and Fixed File Overhead |                 |   |   |                                       |
|--|-----------------|---|---|---------------------------------------|
| Option   | Size            | Maximum Number of Files<br><i>(MaxNumFiles)</i> | Memory (Bytes) Used for Fixed File System Overhead <sup>1</sup><br><i>[16 + (44 x MaxNumFiles)]</i> | Memory Available for Waveform Samples |
| <b>E4438C and E8267D</b>                       |                 |   |   |                                       |
| <b>001/601 (BBG)</b>                           | 8 MSa (40 MB)   | 1024  | 46,080  | <i>8,377,088 Samples</i>              |
| <b>002 (BBG)</b>                               | 32 MSa (160 MB) | 4096  | 181,248   | <i>33,509,120 Samples</i>             |
| <b>602 (BBG)</b>                               | 64 MSa (320 MB) | 8192  | 361,472   | <i>67,018,496 Samples</i>             |

1. The expression  $[16 + [44 \times \text{MaxNumFiles}]]$  has been rounded up to nearest memory block (1024 bytes). (To find the I/Q waveform sample size, this resulting value needs to be divided by 4.)

**Table 5 E4438C and E8267D Non-Volatile (NVWFM) Memory**

| Non-Volatile (NVWFM) Memory |                |
|-----------------------------|----------------|
| Option                      | Size           |
| <b>E4438C and E8267D</b>    |                |
| <b>Standard</b>             | 3 MSa (15 MB)  |
| <b>005 (Hard disk)</b>      | 1.2 GSa (6 GB) |

## Commands for Downloading and Extracting Waveform Data

You can download I/Q data, the associated file header, and marker file information (collectively called waveform data) into volatile or non-volatile memory. For information on waveform structure, see [“Waveform Structure” on page 11](#).

---

**CAUTION** To turn off the ARB remotely, send: `:SOURce:RADio:ARB:STATe OFF`.

---

The signal generator provides the option of downloading waveform data either for extraction or not for extraction. When you extract waveform data, the signal generator may require it to be read out in encrypted form. The SCPI download commands determine whether the waveform data is extractable.

If you use SCPI commands to download waveform data to be extracted later, you must use the `MEM:DATA:UNPRotected` command. If you use FTP commands, no special command syntax is necessary.

---

**NOTE** On the N5182A the `:MEM:DATA:UNPRotected` command is *not* required to be able to extract files (i.e. use `:MEM:DATA`). For more information, refer to the *SCPI Command Reference*.

---

You can download or extract waveform data created in any of the following ways:

- with signal simulation software, such as MATLAB or Agilent Advanced Design System (ADS)
- with advanced programming languages, such as C++, VB or VEE
- with Agilent Signal Studio software
- with the signal generator

### Waveform Data Encryption

You can download encrypted waveform data extracted from one signal generator into another signal generator with the same option or software license for the modulation format. You can also extract encrypted waveform data created with software such as MATLAB or ADS, providing the data was downloaded to the signal generator using the proper command.

When you generate a waveform from the signal generator’s internal ARB modulation format (ESG/PSG only), the resulting waveform data is automatically stored in volatile memory and is available for extraction as an encrypted file.

When you download an exported waveform using a Agilent Signal Studio software product, you can use the FTP process and the `securewave` directory or SCPI commands, to extract the encrypted file to the non-volatile memory on the signal generator. Refer to [“File Transfer Methods” on page 26](#).

### Encrypted I/Q Files and the Securewave Directory

The signal generator uses the `securewave` directory to perform file encryption (extraction) and decryption (downloads). The `securewave` directory is not an actual storage directory, but rather a portal for the encryption and decryption process. While the `securewave` directory contains file names, these are actually pointers to the true files located in signal generator memory (volatile or non-volatile). When you download an encrypted file, the `securewave` directory decrypts the file and

unpackages the contents into its file header, I/Q data, and marker data. When you extract a file, the `securewave` directory packages the file header, I/Q data, and marker data and encrypts the waveform data file. When you extract the waveform file (I/Q data file), it includes the other two files, so there is no need to extract each one individually.

The signal generator uses the following `securewave` directory paths for file extractions and encrypted file downloads:

Volatile                    `/user/bbg1/securewave/file_name` or `swfm:file_name`

Non-volatile                `/user/securewave` or `snvwfm1:file_name`

---

**NOTE** To extract files (other than user-created I/Q files) and to download encrypted files, you *must* use the `securewave` directory. If you attempt to extract previously downloaded encrypted files (including Signal Studio downloaded files or internally created signal generator files (ESG/PSG only)) *without* using the `securewave` directory, the signal generator generates an error and displays:

ERROR: 221, Access Denied.

---

### Encrypted I/Q Files and the Securewave Directory (Agilent MXG Only)

---

**CAUTION** Attributes of files stored on the Agilent MXG's USB external storage media cannot be changed (e.g. data that has been stored as read-only cannot be changed to a writeable format).

---

**NOTE** Agilent MXG non-volatile memory stores encrypted files in the encrypted format.

---

If the user wants to be able to have greater flexibility with the stored waveform formats, it is recommended that the files are stored internally in the signal generator. So, if the waveform data is being stored to the external flash memory, it is important to consider the type of data extraction format that best fits the application:

- `:MEMory:DATA` (waveform data cannot be read as encrypted data)
- 

**NOTE** On the N5182A the `:MEM:DATA:UNPRotected` command is *not* required to be able to extract files (i.e. use `:MEM:DATA`). For more information, refer to the *SCPI Command Reference*.

---

- `:MEMory:DATA:UNPRotected` or FTP commands (waveform data can be read as encrypted or unencrypted)
  - User un-encrypted waveform data (can only be read as unencrypted)
-

## File Transfer Methods

- SCPI using VXI-11 (VMEbus Extensions for Instrumentation as defined in VXI-11)
- SCPI over the GPIB or RS 232
- SCPI with sockets LAN (using port 5025)
- File Transfer Protocol (FTP)

## SCPI Command Line Structure

The signal generator expects to see waveform data as block data (binary files). The IEEE standard 488.2-1992 section 7.7.6 defines block data. The following example shows how to structure a SCPI command for downloading waveform data (#ABC represents the block data):

```
:MMEM:DATA "<file_name>",#ABC
```

"<file\_name>" the I/Q file name and file path within the signal generator

# indicates the start of the data block

A the number of decimal digits present in B

B a decimal number specifying the number of data bytes to follow in C

C the actual binary waveform data

The following example demonstrates this structure:

```
MMEM:DATA "WFM1:my_file",#3|240|12%S!4&07#8g*Y9@7...|
```

|  |           |   |   |   |
|--|-----------|---|---|---|
|  |           |   |   |   |
|  | file_name | A | B | C |

WFM1: the file path

my\_file the I/Q file name as it will appear in the signal generator's memory catalog

# indicates the start of the data block

3 B has three decimal digits

240 240 bytes of data to follow in C

12%S!4&07#8g\*Y9@7... the ASCII representation of some of the binary data downloaded to the signal generator, however not all ASCII values are printable

## Commands and File Paths for Downloading and Extracting Waveform Data

**NOTE** The “@” command syntax for downloading and extracting encrypted or unencrypted files, is demonstrated in the following tables (Table 7, “Downloading Encrypted Files for No Extraction (Extraction allowed on the Agilent MXG Only),” on page 28 through Table 11, “Extracting Encrypted Waveform Data,” on page 29). But, the “@” method is typically *not* the recommended or preferred command syntax and is shown for reference purposes only. Example: The command syntax: MMEM:DATA "SNVWFM:<file\_name>",<blockdata>, is recommended, rather than this version: MMEM:DATA "file\_name@SNVWFM",<blockdata>.

You can download or extract waveform data using the commands and file paths in the following tables:

- Table 6, “Downloading Unencrypted Files for No Extraction (Extraction allowed on the Agilent MXG Only),” on page 27
- Table 7, “Downloading Encrypted Files for No Extraction (Extraction allowed on the Agilent MXG Only),” on page 28
- Table 8, “Downloading Unencrypted Files for Extraction,” on page 28
- Table 10, “Downloading Encrypted Files for Extraction,” on page 29
- Table 11, “Extracting Encrypted Waveform Data,” on page 29

**Table 6 Downloading Unencrypted Files for No Extraction (Extraction allowed on the Agilent MXG<sup>1</sup> Only)**

| Download Method/<br>Memory Type                   | Command Syntax Options  |
|---|---|
| SCPI/volatile memory                              | MMEM:DATA "WF1:<file_name>",<blockdata><br>MMEM:DATA "MKR1:<file_name>",<blockdata><br>MMEM:DATA "HDR1:<file_name>",<blockdata>   |
| SCPI/volatile memory with full directory path     | MMEM:DATA "user/bbgl/waveform/<file_name>",<blockdata><br>MMEM:DATA "user/bbgl/markers/<file_name>",<blockdata><br>MMEM:DATA "user/bbgl/header/<file_name>",<blockdata> |
| SCPI/non-volatile memory                          | MMEM:DATA "NVWFM:<file_name>",<blockdata><br>MMEM:DATA "NVMKR:<file_name>",<blockdata><br>MMEM:DATA "NVHDR:<file_name>",<blockdata>                                     |
| SCPI/non-volatile memory with full directory path | MMEM:DATA /user/waveform/<file_name>",<blockdata><br>MMEM:DATA /user/markers/<file_name>",<blockdata><br>MMEM:DATA /user/header/<file_name>",<blockdata>                |

1. Refer to note on page 24.

**Table 7 Downloading Encrypted Files for No Extraction (Extraction allowed on the Agilent MXG<sup>1</sup> Only)**

| Download Method /Memory Type | Command Syntax Options   |
|------------------------------|--|
| SCPI/volatile memory         | MMEM:DATA "user/bbgl/securewave/<file_name>",<blockdata><br>MMEM:DATA "SWF1:<file_name>",<blockdata><br>MMEM:DATA "file_name@SWF1",<blockdata> |
| SCPI/non-volatile memory     | MMEM:DATA "user/securewave/<file_name>",<blockdata><br>MMEM:DATA "SNVWF1:<file_name>",<blockdata><br>MMEM:DATA "file_name@SNVWF1",<blockdata>  |

1. Refer to note on [page 24](#).

**Table 8 Downloading Unencrypted Files for Extraction**

| Download Method/ Memory Type          | Command Syntax Options  |
|---------------------------------------|---|
| SCPI/volatile memory <sup>1</sup>     | MEM:DATA:UNProtected "/user/bbgl/waveform/file_name",<blockdata><br>MEM:DATA:UNProtected "/user/bbgl/markers/file_name",<blockdata><br>MEM:DATA:UNProtected "/user/bbgl/header/file_name",<blockdata><br>MEM:DATA:UNProtected "WF1:file_name",<blockdata><br>MEM:DATA:UNProtected "MKR1:file_name",<blockdata><br>MEM:DATA:UNProtected "HDR1:file_name",<blockdata><br>MEM:DATA:UNProtected "file_name@WF1",<blockdata><br>MEM:DATA:UNProtected "file_name@MKR1",<blockdata><br>MEM:DATA:UNProtected "file_name@HDR1",<blockdata> |
| SCPI/non-volatile memory <sup>1</sup> | MEM:DATA:UNProtected "/user/waveform/file_name",<blockdata><br>MEM:DATA:UNProtected "/user/markers/file_name",<blockdata><br>MEM:DATA:UNProtected "/user/header/file_name",<blockdata><br>MEM:DATA:UNProtected "NVWF1:file_name",<blockdata><br>MEM:DATA:UNProtected "NVMKR:file_name",<blockdata><br>MEM:DATA:UNProtected "NVHDR:file_name",<blockdata><br>MEM:DATA:UNProtected "file_name@NVWF1",<blockdata><br>MEM:DATA:UNProtected "file_name@NVMKR",<blockdata><br>MEM:DATA:UNProtected "file_name@NVHDR",<blockdata>        |
| FTP/volatile memory <sup>2</sup>      | put <file_name> /user/bbgl/waveform/<file_name><br>put <file_name> /user/bbgl/markers/<file_name><br>put <file_name> /user/bbgl/header/<file_name>  |
| FTP/non-volatile memory <sup>2</sup>  | put <file_name> /user/waveform/<file_name><br>put <file_name> /user/markers/<file_name><br>put <file_name> /user/header/<file_name>   |

1. On the N5182A the :MEM:DATA:UNProtected command is *not* required to be able to extract files (i.e. use :MEM:DATA). For more information, refer to the *SCPI Command Reference*.

2. See "FTP Procedures" on [page 31](#).



**Table 9** Extracting Unencrypted I/Q Data

| Download Method/Memory Type          | Command Syntax Options   |
|--------------------------------------|--|
| SCPI/volatile memory                 | MMEM:DATA? "/user/bbgl/waveform/<file_name>"<br>MMEM:DATA? "WF1:<file_name>"<br>MMEM:DATA? "<file_name>@WF1"   |
| SCPI/non-volatile memory             | MMEM:DATA? "/user/waveform/<file_name>"<br>MMEM:DATA? "NVWF1:<file_name>"<br>MMEM:DATA? "<file_name>@NVWF1"    |
| FTP/volatile memory <sup>1</sup>     | get /user/bbgl/waveform/<file_name><br>get /user/bbgl/markers/<file_name><br>get /user/bbgl/header/<file_name> |
| FTP/non-volatile memory <sup>1</sup> | get /user/waveform/<file_name><br>get /user/markers/<file_name><br>get /user/header/<file_name>                |

1. See "FTP Procedures" on page 31.

**Table 10** Downloading Encrypted Files for Extraction

| Download Method/Memory Type           | Command Syntax Options   |
|---------------------------------------|--|
| SCPI/volatile <sup>1</sup> memory     | MEM:DATA:UNProtected "/user/bbgl/securewave/file_name",<blockdata><br>MEM:DATA:UNProtected "SWF1:file_name",<blockdata><br>MEM:DATA:UNProtected "file_name@SWF1",<blockdata> |
| SCPI/non-volatile memory <sup>1</sup> | MEM:DATA:UNProtected "/user/securewave/file_name",<blockdata><br>MEM:DATA:UNProtected "SNVWF1:file_name",<blockdata><br>MEM:DATA:UNProtected "file_name@SNVWF1",<blockdata>  |
| FTP/volatile memory <sup>2</sup>      | put <file_name> /user/bbgl/securewave/<file_name>  |
| FTP/non-volatile memory <sup>2</sup>  | put <file_name> /user/securewave/<file_name>   |

1. On the N5182A the :MEM:DATA:UNProtected command is *not* required to be able to extract files (i.e. use :MEM:DATA). For more information, refer to the *SCPI Command Reference*.

2. See "FTP Procedures" on page 31.

**Table 11** Extracting Encrypted Waveform Data

| Download Method/Memory Type | Command Syntax Options   |
|-----------------------------|--|
| SCPI/volatile memory        | MMEM:DATA? "/user/bbgl/securewave/file_name"<br>MMEM:DATA? "SWF1:file_name"<br>MMEM:DATA? "file_name@SWF1" |

Table 11 Extracting Encrypted Waveform Data

| <b>Download Method/Memory Type</b>   | <b>Command Syntax Options</b>   |
|--------------------------------------|---|
| SCPI/non-volatile memory             | MMEM:DATA? "/user/securewave/file_name"<br>MMEM:DATA? "SNVWFM:file_name"<br>MMEM:DATA? "file_name@SNVWFM" |
| FTP/volatile memory <sup>1</sup>     | get /user/bbg1/securewave/<file_name>   |
| FTP/non-volatile memory <sup>1</sup> | get /user/securewave/<file_name>  |

1. See "FTP Procedures" on page 31.

## FTP Procedures

There are three ways to FTP files:

- use Microsoft's® Internet Explorer FTP feature
- use the PC's or UNIX command window
- use the signal generator's internal web server following the firmware requirements in the table below

---

**NOTE** Older versions of signal generator firmware did not have web server capabilities.

---

| Signal Generator | Firmware Version |
|------------------|------------------|
| N518xA           | ≥ A.01.00        |
| E44x8C           | ≥ C.03.10        |
| E82x7D           | All              |

### Using Microsoft's Internet Explorer

1. Enter the signal generator's hostname or IP address as part of the FTP URL.  
*ftp://<host name> or <IP address>*
2. Press **Enter** on the keyboard or **Go** from the Internet Explorer window.  
The signal generator files appear in the Internet Explorer window.
3. Drag and drop files between the PC and the Internet Explorer window

### Using the Command Window (PC or UNIX)

This procedure downloads to non-volatile memory. To download to volatile memory, change the file path.

1. From the PC command prompt or UNIX command line, change to the destination directory for the file you intend to download.
2. From the PC command prompt or UNIX command line, type `ftp <instrument name>`. Where `instrument name` is the signal generator's hostname or IP address.
3. At the `User:` prompt in the ftp window, press **Enter** (no entry is required).
4. At the `Password:` prompt in the ftp window, press **Enter** (no entry is required).
5. At the ftp prompt, type:  
`put <file_name> /user/waveform/<file_name1>`

where `<file_name>` is the name of the file to download and `<file_name1>` is the name designator for the signal generator's `/user/waveform/` directory.

- If a marker file is associated with the data file, use the following command to download it to the signal generator:

```
put <marker file_name> /user/markers/<file_name1>
```

where <marker file\_name> is the name of the file to download and <file\_name1> is the name designator for the file in the signal generator's /user/markers/ directory. Marker files and the associated I/Q waveform data have the same name.

6. At the ftp prompt, type: bye
7. At the command prompt, type: exit

### Using the Signal Generator's Internal Web Server

1. Enter the signal generator's hostname or IP address in the URL.  
*http://<host name> or <IP address>*
2. Click the **Signal Generator FTP Access** button located on the left side of the window.  
The signal generator files appear in the web browser's window.
3. Drag and drop files between the PC and the browser's window

For more information on the web server feature, see the *Programming Guide* for the signal generator.

## Creating Waveform Data

This section examines the C++ code algorithm for creating I/Q waveform data by breaking the programming example into functional parts and explaining the code in generic terms. This is done to help you understand the code algorithm in creating the I and Q data, so you can leverage the concept into your programming environment. The *SCPI Command Reference*, contains information on how to use SCPI commands to define the markers (polarity, routing, and other marker settings). If you do not need this level of detail, you can find the complete programming examples in “[Programming Examples](#)” on page 53.

You can use various programming environments to create ARB waveform data. Generally there are two types:

- **Simulation software**— this includes MATLAB, Agilent Technologies EESof Advanced Design System (ADS), Signal Processing WorkSystem (SPW), and so forth.
- **Advanced programming languages**—this includes, C++, VB, VEE, MS Visual Studio.Net, Labview, and so forth.

No matter which programming environment you use to create the waveform data, make sure that the data conforms to the data requirements shown on [page 3](#). To learn about I/Q data for the signal generator, see “[Understanding Waveform Data](#)” on [page 4](#).

## Code Algorithm

This section uses code from the C++ programming example “[Importing, Byte Swapping, Interleaving, and Downloading I and Q Data—Big and Little Endian Order](#)” on [page 71](#) to demonstrate how to create and scale waveform data.

There are three steps in the process of creating an I/Q waveform:

1. Create the I and Q data.
2. Save the I and Q data to a text file for review.
3. Interleave the I and Q data to make an I/Q file, and swap the byte order for little-endian platforms.

For information on downloading I/Q waveform data to a signal generator, refer to “[Commands and File Paths for Downloading and Extracting Waveform Data](#)” on [page 27](#) and “[Downloading Waveform Data](#)” on [page 40](#).

### 1. Create I and Q data.

The following lines of code create scaled I and Q data for a sine wave. The I data consists of one period of a sine wave and the Q data consists of one period of a cosine wave.

**Line      Code—Create I and Q data**

```

1   const int NUMSAMPLES=500;
2   main(int argc, char* argv[]);
3   {
4       short idata[NUMSAMPLES];
5       short qdata[NUMSAMPLES];
6       int numsamples = NUMSAMPLES;
7       for(int index=0; index<numsamples; index++){
8           {
9               idata[index]=23000 * sin((2*3.14*index)/numsamples);
10              qdata[index]=23000 * cos((2*3.14*index)/numsamples);
11          }
12      }

```

| Line | Code Description—Create I and Q data  |
|------|---|
| 1    | Define the number of waveform points. Note that the maximum number of waveform points that you can set is based on the amount of available memory in the signal generator. For more information on signal generator memory, refer to <a href="#">“Waveform Memory” on page 17</a> . |
| 2    | Define the main function in C++.  |
| 4    | Create an array to hold the generated I values. The array length equals the number of the waveform points. Note that we define the array as type <i>short</i> , which represents a 16-bit signed integer in most C++ compilers.   |
| 5    | Create an array to hold the generated Q values (signed 16-bit integers).  |
| 6    | Define and set a temporary variable, which is used to calculate the I and Q values.   |

| Line | Code Description—Create I and Q data  |
|------|---|
| 7-11 | <p>Create a loop to do the following:</p> <ul style="list-style-type: none"> <li>• Generate and scale the I data (DAC values). This example uses a simple sine equation, where <math>2\pi \cdot 3.14</math> equals one waveform cycle. Change the equation to fit your application.           <ul style="list-style-type: none"> <li>— The array pointer, <i>index</i>, increments from 0-499, creating 500 I data points over one period of the sine waveform.</li> <li>— Set the scale of the DAC values in the range of -32768 to 32767, where the values -32768 and 32767 equal full scale negative and positive respectively. This example uses 23000 as the multiplier, resulting in approximately 70% scaling. For more information on scaling, see <a href="#">“Scaling DAC Values” on page 8</a>.</li> </ul> </li> </ul> <hr/> <p><b>NOTE</b> The signal generator comes from the factory with I/Q scaling set to 70%. If you reduce the DAC input values, ensure that you set the signal generator scaling (:RADiO:ARB:RSCalInG) to an appropriate setting that accounts for the reduced values.</p> <hr/> <ul style="list-style-type: none"> <li>• Generate and scale the Q data (DAC value). This example uses a simple cosine equation, where <math>2\pi \cdot 3.14</math> equals one waveform cycle. Change the equation to fit your application.           <ul style="list-style-type: none"> <li>— The array pointer, <i>index</i>, increments from 0-499, creating 500 Q data points over one period of the cosine waveform.</li> <li>— Set the scale of the DAC values in the range of -32767 to 32768, where the values -32767 and 32768 equal full scale negative and positive respectively. This example uses 23000 as the multiplier, resulting in approximately 70% scaling. For more information on scaling, see <a href="#">“Scaling DAC Values” on page 8</a>.</li> </ul> </li> </ul> |

**2. Save the I/Q data to a text file to review.**

The following lines of code export the I and Q data to a text file for validation. After exporting the data, open the file using Microsoft Excel or a similar spreadsheet program, and verify that the I and Q data are correct.

**Line Code Description—Saving the I/Q Data to a Text File**

```

12 char *ofile = "c:\\temp\\iq.txt";
13 FILE *outfile = fopen(ofile, "w");
14 if (outfile==NULL) perror ("Error opening file to write");
15 for(index=0; index<numsamples; index++)
16 {
17     fprintf(outfile, "%d, %d\n", idata[index], qdata[index]);
18 }
19 fclose(outfile);
  
```

| Line  | Code Description—Saving the I/Q Data to a Text File  |
|-------|--|
| 12    | Set the absolute path of a text file to a character variable. In this example, <i>iq.txt</i> is the file name and <i>*ofile</i> is the variable name.<br><br>For the file path, some operating systems may not use the drive prefix ('c:' in this example), or may require only a single forward slash (/), or both (" <i>temp/iq.txt</i> ") |
| 13    | Open the text file in <i>write</i> format.   |
| 14    | If the text file does not open, print an error message.  |
| 15–18 | Create a loop that prints the array of generated I and Q data samples to the text file.  |
| 19    | Close the text file.   |



### 3. Interleave the I and Q data, and byte swap if using little endian order.

This step has two sets of code:

- Interleaving and byte swapping I and Q data for little endian order
- Interleaving I and Q data for big endian order

For more information on byte order, see “[Little Endian and Big Endian \(Byte Order\)](#)” on page 5.

#### Line Code—Interleaving and Byte Swapping for Little Endian Order

```

20 char iqbuffer[NUMSAMPLES*4];
21 for(index=0; index<numsamples; index++)
22 {
23     short ivalue = idata[index];
24     short qvalue = qdata[index];
25     iqbuffer[index*4] = (ivalue >> 8) & 0xFF;
26     iqbuffer[index*4+1] = ivalue & 0xFF;
27     iqbuffer[index*4+2] = (qvalue >> 8) & 0xFF;
28     iqbuffer[index*4+3] = qvalue & 0xFF;
29 }
30 return 0;

```

| Line  | Code Description—Interleaving and Byte Swapping for Little Endian Order   |
|-------|---|
| 20    | Define a character array to store the interleaved I and Q data. The character array makes byte swapping easier, since each array location accepts only 8 bits (1 byte). The array size increases by four times to accommodate two bytes of I data and two bytes of Q data.  |
| 21–29 | <p>Create a loop to do the following:</p> <ul style="list-style-type: none"> <li>• Save the current I data array value to a variable.</li> </ul> <hr/> <p><b>NOTE</b> In rare instances, a compiler may define <i>short</i> as larger than 16 bits. If this condition exists, replace <i>short</i> with the appropriate object or label that defines a 16-bit integer.</p> <hr/> <ul style="list-style-type: none"> <li>• Save the current Q data array value to a variable.</li> <li>• Swap the low bytes (bits 0–7) of the data with the high bytes of the data (done for both</li> </ul> |

| Line     | Code Description—Interleaving and Byte Swapping for Little Endian Order  |          |          |          |          |          |          |               |    |    |    |    |    |    |      |              |   |              |   |   |      |   |   |   |   |   |   |   |   |   |   |   |   |   |      |    |    |    |    |    |    |   |   |               |   |   |   |   |   |   |   |   |  |          |          |          |          |          |          |          |          |               |   |   |   |   |   |   |   |   |               |    |    |    |    |    |    |   |   |   |   |   |   |   |   |   |   |              |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |      |         |   |        |   |         |   |        |   |              |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |      |
|----------|--|----------|----------|----------|----------|----------|----------|---------------|----|----|----|----|----|----|------|--------------|---|--------------|---|---|------|---|---|---|---|---|---|---|---|---|---|---|---|---|------|----|----|----|----|----|----|---|---|---------------|---|---|---|---|---|---|---|---|--|----------|----------|----------|----------|----------|----------|----------|----------|---------------|---|---|---|---|---|---|---|---|---------------|----|----|----|----|----|----|---|---|---|---|---|---|---|---|---|---|--------------|---|---|---|---|---|---|---|---|---|---|---|---|---|---|---|------|---------|---|--------|---|---------|---|--------|---|--------------|---|---|---|---|---|---|---|---|---|---|---|---|---|---|---|---|---|---|---|---|---|------|
| 21-29    | <p>the I and Q data), and interleave the I and Q data.</p> <ul style="list-style-type: none"> <li>— shift the data pointer right 8 bits to the beginning of the high byte (<i>value &gt;&gt; 8</i>)</li> </ul> <p style="text-align: center;"><b>Little Endian Order</b></p> <table style="width: 100%; border-collapse: collapse;"> <tr> <td style="text-align: center;">7</td><td style="text-align: center;">6</td><td style="text-align: center;">5</td><td style="text-align: center;">4</td><td style="text-align: center;">3</td><td style="text-align: center;">2</td><td style="text-align: center;">1</td><td style="text-align: center;">0</td><td style="text-align: center;">15</td><td style="text-align: center;">14</td><td style="text-align: center;">13</td><td style="text-align: center;">12</td><td style="text-align: center;">11</td><td style="text-align: center;">10</td><td style="text-align: center;">9</td><td style="text-align: center;">8</td><td style="text-align: right;">Bit Position</td> </tr> <tr> <td style="text-align: center;">1</td><td style="text-align: center;">1</td><td style="text-align: center;">1</td><td style="text-align: center;">0</td><td style="text-align: center;">1</td><td style="text-align: center;">0</td><td style="text-align: center;">0</td><td style="text-align: center;">1</td><td style="text-align: center;">1</td><td style="text-align: center;">0</td><td style="text-align: center;">1</td><td style="text-align: center;">1</td><td style="text-align: center;">0</td><td style="text-align: center;">1</td><td style="text-align: center;">1</td><td style="text-align: center;">1</td><td style="text-align: right;">Data</td> </tr> </table> <p style="text-align: right; margin-right: 20px;">Hex values = E9 B7</p> <ul style="list-style-type: none"> <li>— <i>AND</i> (boolean) the high I byte with 0xFF to make the high I byte the value to store in the IQ array—(<i>value &gt;&gt; 8</i>) &amp; 0xFF</li> </ul> <table style="width: 100%; border-collapse: collapse;"> <tr> <td style="text-align: center;">15</td><td style="text-align: center;">14</td><td style="text-align: center;">13</td><td style="text-align: center;">12</td><td style="text-align: center;">11</td><td style="text-align: center;">10</td><td style="text-align: center;">9</td><td style="text-align: center;">8</td><td style="text-align: right;">Hex value =B7</td> </tr> <tr> <td style="text-align: center;">1</td><td style="text-align: center;">0</td><td style="text-align: center;">1</td><td style="text-align: center;">1</td><td style="text-align: center;">0</td><td style="text-align: center;">1</td><td style="text-align: center;">1</td><td style="text-align: center;">1</td><td></td> </tr> <tr> <td style="text-align: center;"><u>1</u></td><td style="text-align: center;"><u>1</u></td><td style="text-align: center;"><u>1</u></td><td style="text-align: center;"><u>1</u></td><td style="text-align: center;"><u>1</u></td><td style="text-align: center;"><u>1</u></td><td style="text-align: center;"><u>1</u></td><td style="text-align: center;"><u>1</u></td><td style="text-align: right;">Hex value =FF</td> </tr> <tr> <td style="text-align: center;">1</td><td style="text-align: center;">0</td><td style="text-align: center;">1</td><td style="text-align: center;">1</td><td style="text-align: center;">0</td><td style="text-align: center;">1</td><td style="text-align: center;">1</td><td style="text-align: center;">1</td><td style="text-align: right;">Hex value =B7</td> </tr> </table> <ul style="list-style-type: none"> <li>— <i>AND</i> (boolean) the low I byte with 0xFF (<i>value &amp; 0xFF</i>) to make the low I byte the value to store in the I/Q array location just after the high byte [<i>index * 4 + 1</i>]</li> </ul> <p style="text-align: center;"><b>I Data in I/Q Array after Byte Swap (Big Endian Order)</b></p> <table style="width: 100%; border-collapse: collapse;"> <tr> <td style="text-align: center;">15</td><td style="text-align: center;">14</td><td style="text-align: center;">13</td><td style="text-align: center;">12</td><td style="text-align: center;">11</td><td style="text-align: center;">10</td><td style="text-align: center;">9</td><td style="text-align: center;">8</td><td style="text-align: center;">7</td><td style="text-align: center;">6</td><td style="text-align: center;">5</td><td style="text-align: center;">4</td><td style="text-align: center;">3</td><td style="text-align: center;">2</td><td style="text-align: center;">1</td><td style="text-align: center;">0</td><td style="text-align: right;">Bit Position</td> </tr> <tr> <td style="text-align: center;">1</td><td style="text-align: center;">0</td><td style="text-align: center;">1</td><td style="text-align: center;">1</td><td style="text-align: center;">0</td><td style="text-align: center;">1</td><td style="text-align: center;">1</td><td style="text-align: center;">1</td><td style="text-align: center;">1</td><td style="text-align: center;">1</td><td style="text-align: center;">0</td><td style="text-align: center;">1</td><td style="text-align: center;">0</td><td style="text-align: center;">0</td><td style="text-align: center;">1</td><td style="text-align: right;">Data</td> </tr> </table> <p style="text-align: right; margin-right: 20px;">Hex value = B7 E9</p> <ul style="list-style-type: none"> <li>— Swap the Q byte order within the same loop. Notice that the I and Q data interleave with each loop cycle. This is due to the I/Q array shifting by one location for each I and Q operation [<i>index * 4 + n</i>].</li> </ul> <p style="text-align: center;"><b>Interleaved I/Q Array in Big Endian Order</b></p> <table style="width: 100%; border-collapse: collapse;"> <tr> <td style="text-align: center;">15.....</td><td style="text-align: center;">8</td><td style="text-align: center;">7.....</td><td style="text-align: center;">0</td><td style="text-align: center;">15.....</td><td style="text-align: center;">8</td><td style="text-align: center;">7.....</td><td style="text-align: center;">0</td><td style="text-align: right;">Bit Position</td> </tr> <tr> <td style="text-align: center;">1</td><td style="text-align: center;">0</td><td style="text-align: center;">1</td><td style="text-align: center;">1</td><td style="text-align: center;">1</td><td style="text-align: center;">1</td><td style="text-align: center;">1</td><td style="text-align: center;">1</td><td style="text-align: center;">0</td><td style="text-align: center;">1</td><td style="text-align: center;">0</td><td style="text-align: center;">0</td><td style="text-align: center;">1</td><td style="text-align: center;">1</td><td style="text-align: center;">1</td><td style="text-align: center;">1</td><td style="text-align: center;">0</td><td style="text-align: center;">1</td><td style="text-align: center;">0</td><td style="text-align: center;">1</td><td style="text-align: center;">1</td><td style="text-align: right;">Data</td> </tr> </table> <p style="text-align: center;"> <span style="margin-right: 100px;">I Data</span> <span>Q Data</span> </p> | 7        | 6        | 5        | 4        | 3        | 2        | 1             | 0  | 15 | 14 | 13 | 12 | 11 | 10   | 9            | 8 | Bit Position | 1 | 1 | 1    | 0 | 1 | 0 | 0 | 1 | 1 | 0 | 1 | 1 | 0 | 1 | 1 | 1 | Data | 15 | 14 | 13 | 12 | 11 | 10 | 9 | 8 | Hex value =B7 | 1 | 0 | 1 | 1 | 0 | 1 | 1 | 1 |  | <u>1</u> | <u>1</u> | <u>1</u> | <u>1</u> | <u>1</u> | <u>1</u> | <u>1</u> | <u>1</u> | Hex value =FF | 1 | 0 | 1 | 1 | 0 | 1 | 1 | 1 | Hex value =B7 | 15 | 14 | 13 | 12 | 11 | 10 | 9 | 8 | 7 | 6 | 5 | 4 | 3 | 2 | 1 | 0 | Bit Position | 1 | 0 | 1 | 1 | 0 | 1 | 1 | 1 | 1 | 1 | 0 | 1 | 0 | 0 | 1 | Data | 15..... | 8 | 7..... | 0 | 15..... | 8 | 7..... | 0 | Bit Position | 1 | 0 | 1 | 1 | 1 | 1 | 1 | 1 | 0 | 1 | 0 | 0 | 1 | 1 | 1 | 1 | 0 | 1 | 0 | 1 | 1 | Data |
| 7        | 6  | 5        | 4        | 3        | 2        | 1        | 0        | 15            | 14 | 13 | 12 | 11 | 10 | 9  | 8    | Bit Position |   |              |   |   |      |   |   |   |   |   |   |   |   |   |   |   |   |   |      |    |    |    |    |    |    |   |   |               |   |   |   |   |   |   |   |   |  |          |          |          |          |          |          |          |          |               |   |   |   |   |   |   |   |   |               |    |    |    |    |    |    |   |   |   |   |   |   |   |   |   |   |              |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |      |         |   |        |   |         |   |        |   |              |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |      |
| 1        | 1  | 1        | 0        | 1        | 0        | 0        | 1        | 1             | 0  | 1  | 1  | 0  | 1  | 1  | 1    | Data         |   |              |   |   |      |   |   |   |   |   |   |   |   |   |   |   |   |   |      |    |    |    |    |    |    |   |   |               |   |   |   |   |   |   |   |   |  |          |          |          |          |          |          |          |          |               |   |   |   |   |   |   |   |   |               |    |    |    |    |    |    |   |   |   |   |   |   |   |   |   |   |              |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |      |         |   |        |   |         |   |        |   |              |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |      |
| 15       | 14   | 13       | 12       | 11       | 10       | 9        | 8        | Hex value =B7 |    |    |    |    |    |    |      |              |   |              |   |   |      |   |   |   |   |   |   |   |   |   |   |   |   |   |      |    |    |    |    |    |    |   |   |               |   |   |   |   |   |   |   |   |  |          |          |          |          |          |          |          |          |               |   |   |   |   |   |   |   |   |               |    |    |    |    |    |    |   |   |   |   |   |   |   |   |   |   |              |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |      |         |   |        |   |         |   |        |   |              |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |      |
| 1        | 0  | 1        | 1        | 0        | 1        | 1        | 1        |               |    |    |    |    |    |    |      |              |   |              |   |   |      |   |   |   |   |   |   |   |   |   |   |   |   |   |      |    |    |    |    |    |    |   |   |               |   |   |   |   |   |   |   |   |  |          |          |          |          |          |          |          |          |               |   |   |   |   |   |   |   |   |               |    |    |    |    |    |    |   |   |   |   |   |   |   |   |   |   |              |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |      |         |   |        |   |         |   |        |   |              |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |      |
| <u>1</u> | <u>1</u>   | <u>1</u> | <u>1</u> | <u>1</u> | <u>1</u> | <u>1</u> | <u>1</u> | Hex value =FF |    |    |    |    |    |    |      |              |   |              |   |   |      |   |   |   |   |   |   |   |   |   |   |   |   |   |      |    |    |    |    |    |    |   |   |               |   |   |   |   |   |   |   |   |  |          |          |          |          |          |          |          |          |               |   |   |   |   |   |   |   |   |               |    |    |    |    |    |    |   |   |   |   |   |   |   |   |   |   |              |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |      |         |   |        |   |         |   |        |   |              |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |      |
| 1        | 0  | 1        | 1        | 0        | 1        | 1        | 1        | Hex value =B7 |    |    |    |    |    |    |      |              |   |              |   |   |      |   |   |   |   |   |   |   |   |   |   |   |   |   |      |    |    |    |    |    |    |   |   |               |   |   |   |   |   |   |   |   |  |          |          |          |          |          |          |          |          |               |   |   |   |   |   |   |   |   |               |    |    |    |    |    |    |   |   |   |   |   |   |   |   |   |   |              |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |      |         |   |        |   |         |   |        |   |              |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |      |
| 15       | 14   | 13       | 12       | 11       | 10       | 9        | 8        | 7             | 6  | 5  | 4  | 3  | 2  | 1  | 0    | Bit Position |   |              |   |   |      |   |   |   |   |   |   |   |   |   |   |   |   |   |      |    |    |    |    |    |    |   |   |               |   |   |   |   |   |   |   |   |  |          |          |          |          |          |          |          |          |               |   |   |   |   |   |   |   |   |               |    |    |    |    |    |    |   |   |   |   |   |   |   |   |   |   |              |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |      |         |   |        |   |         |   |        |   |              |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |      |
| 1        | 0  | 1        | 1        | 0        | 1        | 1        | 1        | 1             | 1  | 0  | 1  | 0  | 0  | 1  | Data |              |   |              |   |   |      |   |   |   |   |   |   |   |   |   |   |   |   |   |      |    |    |    |    |    |    |   |   |               |   |   |   |   |   |   |   |   |  |          |          |          |          |          |          |          |          |               |   |   |   |   |   |   |   |   |               |    |    |    |    |    |    |   |   |   |   |   |   |   |   |   |   |              |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |      |         |   |        |   |         |   |        |   |              |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |      |
| 15.....  | 8  | 7.....   | 0        | 15.....  | 8        | 7.....   | 0        | Bit Position  |    |    |    |    |    |    |      |              |   |              |   |   |      |   |   |   |   |   |   |   |   |   |   |   |   |   |      |    |    |    |    |    |    |   |   |               |   |   |   |   |   |   |   |   |  |          |          |          |          |          |          |          |          |               |   |   |   |   |   |   |   |   |               |    |    |    |    |    |    |   |   |   |   |   |   |   |   |   |   |              |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |      |         |   |        |   |         |   |        |   |              |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |      |
| 1        | 0  | 1        | 1        | 1        | 1        | 1        | 1        | 0             | 1  | 0  | 0  | 1  | 1  | 1  | 1    | 0            | 1 | 0            | 1 | 1 | Data |   |   |   |   |   |   |   |   |   |   |   |   |   |      |    |    |    |    |    |    |   |   |               |   |   |   |   |   |   |   |   |  |          |          |          |          |          |          |          |          |               |   |   |   |   |   |   |   |   |               |    |    |    |    |    |    |   |   |   |   |   |   |   |   |   |   |              |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |      |         |   |        |   |         |   |        |   |              |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |   |      |

**Line Code—Interleaving I and Q data for Big Endian Order**

```

20 short iqbuffer[NUMSAMPLES*2];
21 for(index=0; index<numsamples; index++)
22 {
23 iqbuffer[index*2] = idata[index];
24 iqbuffer[index*2+1] = qdata[index];
25 }
26 return 0;
  
```

| Line                 | Code Description—Interleaving I and Q data for Big Endian Order   |         |   |                      |   |         |   |              |   |              |   |   |   |   |   |   |   |   |      |   |   |   |   |   |   |   |   |  |                      |  |  |  |                      |  |  |  |  |        |  |  |  |        |  |  |  |  |
|----------------------|---|---------|---|----------------------|---|---------|---|--------------|---|--------------|---|---|---|---|---|---|---|---|------|---|---|---|---|---|---|---|---|--|----------------------|--|--|--|----------------------|--|--|--|--|--------|--|--|--|--------|--|--|--|--|
| 20                   | Define a 16-bit integer (short) array to store the interleaved I and Q data. The array size increases by two times to accommodate two bytes of I data and two bytes of Q data. <hr/> <p><b>NOTE</b> In rare instances, a compiler may define <i>short</i> as larger than 16 bits. If this condition exists, replace <i>short</i> with the appropriate object or label that defines a 16-bit integer.</p> <hr/>  |         |   |                      |   |         |   |              |   |              |   |   |   |   |   |   |   |   |      |   |   |   |   |   |   |   |   |  |                      |  |  |  |                      |  |  |  |  |        |  |  |  |        |  |  |  |  |
| 21–25                | Create a loop to do the following: <ul style="list-style-type: none"> <li>• Store the I data values to the I/Q array location [<i>index</i>*2].</li> <li>• Store the Q data values to the I/Q array location [<i>index</i>*2+1].</li> </ul> <p style="text-align: center;"><b>Interleaved I/Q Array in Big Endian Order</b></p> <table style="margin-left: auto; margin-right: auto; border-collapse: collapse;"> <tr> <td style="text-align: center;">15.....</td> <td style="text-align: center;">8</td> <td style="text-align: center;">7.....</td> <td style="text-align: center;">0</td> <td style="text-align: center;">15.....</td> <td style="text-align: center;">8</td> <td style="text-align: center;">7.....</td> <td style="text-align: center;">0</td> <td style="text-align: right;">Bit Position</td> </tr> <tr> <td style="text-align: center;">1</td> <td style="text-align: center;">0</td> <td style="text-align: center;">1</td> <td style="text-align: center;">1</td> <td style="text-align: center;">1</td> <td style="text-align: center;">1</td> <td style="text-align: center;">1</td> <td style="text-align: center;">0</td> <td style="text-align: right;">Data</td> </tr> <tr> <td style="text-align: center;">1</td> <td style="text-align: center;">0</td> <td style="text-align: center;">1</td> <td style="text-align: center;">1</td> <td style="text-align: center;">1</td> <td style="text-align: center;">1</td> <td style="text-align: center;">0</td> <td style="text-align: center;">1</td> <td></td> </tr> <tr> <td colspan="4" style="text-align: center;">└──────────────────┘</td> <td colspan="4" style="text-align: center;">└──────────────────┘</td> <td></td> </tr> <tr> <td colspan="4" style="text-align: center;">I Data</td> <td colspan="4" style="text-align: center;">Q Data</td> <td></td> </tr> </table> | 15..... | 8 | 7.....               | 0 | 15..... | 8 | 7.....       | 0 | Bit Position | 1 | 0 | 1 | 1 | 1 | 1 | 1 | 0 | Data | 1 | 0 | 1 | 1 | 1 | 1 | 0 | 1 |  | └──────────────────┘ |  |  |  | └──────────────────┘ |  |  |  |  | I Data |  |  |  | Q Data |  |  |  |  |
| 15.....              | 8   | 7.....  | 0 | 15.....              | 8 | 7.....  | 0 | Bit Position |   |              |   |   |   |   |   |   |   |   |      |   |   |   |   |   |   |   |   |  |                      |  |  |  |                      |  |  |  |  |        |  |  |  |        |  |  |  |  |
| 1                    | 0   | 1       | 1 | 1                    | 1 | 1       | 0 | Data         |   |              |   |   |   |   |   |   |   |   |      |   |   |   |   |   |   |   |   |  |                      |  |  |  |                      |  |  |  |  |        |  |  |  |        |  |  |  |  |
| 1                    | 0   | 1       | 1 | 1                    | 1 | 0       | 1 |              |   |              |   |   |   |   |   |   |   |   |      |   |   |   |   |   |   |   |   |  |                      |  |  |  |                      |  |  |  |  |        |  |  |  |        |  |  |  |  |
| └──────────────────┘ |   |         |   | └──────────────────┘ |   |         |   |              |   |              |   |   |   |   |   |   |   |   |      |   |   |   |   |   |   |   |   |  |                      |  |  |  |                      |  |  |  |  |        |  |  |  |        |  |  |  |  |
| I Data               |   |         |   | Q Data               |   |         |   |              |   |              |   |   |   |   |   |   |   |   |      |   |   |   |   |   |   |   |   |  |                      |  |  |  |                      |  |  |  |  |        |  |  |  |        |  |  |  |  |

To download the data created in the above example, see [“Using Advanced Programming Languages” on page 43](#).

## Downloading Waveform Data

This section examines methods of downloading I/Q waveform data created in MATLAB (a simulation software) and C++ (an advanced programming language). For more information on simulation and advanced programming environments, see [“Creating Waveform Data” on page 33](#).

To download data from simulation software environments, it is typically easier to use one of the free download utilities (described on [page 49](#)), because simulation software usually saves the data to a file. In MATLAB however, you can either save data to a .mat file or create a complex array. To facilitate downloading a MATLAB complex data array, Agilent created the Agilent MXG/PSG/ESG Download Assistant (one of the free download utilities), which downloads the complex data array from within the MATLAB environment. This section shows how to use the download assistant.

For advanced programming languages, this section closely examines the code algorithm for downloading I/Q waveform data by breaking the programming examples into functional parts and explaining the code in generic terms. This is done to help you understand the code algorithm in downloading the interleaved I/Q data, so you can leverage the concept into your programming environment. While not discussed in this section, you may also save the data to a binary file and use one of the download utilities to download the waveform data (see [“Using the Download Utilities” on page 49](#)).

If you do not need the level of detail this section provides, you can find complete programming examples in [“Programming Examples” on page 53](#). Prior to downloading the I/Q data, ensure that it conforms to the data requirements shown on [page 3](#). To learn about I/Q data for the signal generator, see [“Understanding Waveform Data” on page 4](#). For creating waveform data, see [“Creating Waveform Data” on page 33](#).

---

**NOTE** To avoid overwriting the current waveform in volatile memory, before downloading files into volatile memory (WFM1), change the file name or turn off the ARB. For more information, on manually turning off the ARB, refer to the *User’s Guide*.

To turn off the ARB remotely, send: `:SOURCE:RADio:ARB:STATE OFF`.

---

## Using Simulation Software

This procedure uses a complex data array created in MATLAB and uses the Agilent MXG/PSG/ESG Download Assistant to download the data. To obtain the Agilent MXG/PSG/ESG Download Assistant, see [“Using the Download Utilities” on page 49](#).

There are two steps in the process of downloading an I/Q waveform:

1. Open a connection session.
2. Download the I/Q data.

**1. Open a connection session with the signal generator.**

The following code establishes a LAN connection with the signal generator, sends the IEEE SCPI command `*idn?`, and if the connection fails, displays an error message.

**Line Code—Open a Connection Session**

```

1  io = agt_newconnection('tcpip','IP address');
   %io = agt_newconnection('gpib',<primary address>,<secondary address>);
2  [status,status_description,query_result] = agt_query(io,'*idn?');
3  if status == -1
4  display 'fail to connect to the signal generator';
5  end;

```

| Line | Code Description—Open a Connection Session with the Signal Generator  |
|------|---|
| 1    | <p>Sets up a structure (indicated above by <i>io</i>) used by subsequent function calls to establish a LAN connection to the signal generator.</p> <ul style="list-style-type: none"> <li><i>agt_newconnection()</i> is the function of Agilent Download Assistant used in MATLAB to build a connection to the signal generator.</li> <li>If you are using GPIB to connect to the signal generator, provide the board, primary address, and secondary address: <i>io = agt_newconnection('gpib',0,19);</i> Change the GPIB address based on your instrument setting.</li> </ul> |
| 2    | <p>Send a query to the signal generator to verify the connection.</p> <ul style="list-style-type: none"> <li><i>agt_query()</i> is an Agilent Download Assistant function that sends a query to the signal generator.</li> <li>If signal generator receives the query <code>*idn?</code>, <i>status</i> returns zero and <i>query_result</i> returns the signal generator's model number, serial number, and firmware version.</li> </ul>   |
| 3-5  | <p>If the query fails, display a message.</p>   |

## 2. Download the I/Q data

The following code downloads the generated waveform data to the signal generator, and if the download fails, displays a message.

### Line Code—Download the I/Q data

```

6 [status, status_description] = agt_waveformload(io, IQwave,
  'waveformfile1', 2000, 'no_play', 'norm_scale');
7 if status == -1
8 display 'fail to download to the signal generator';
9 end;
  
```

| Line | Code Description—Download the I/Q data  |
|------|---|
| 6    | <p>Download the I/Q waveform data to the signal generator by using the function call (<i>agt_waveformload</i>) from the Agilent Download Assistant. Some of the arguments are optional as indicated below, but if one is used, you must use all arguments previous to the one you require.</p> <p>Notice that with this function, you can perform the following actions:</p> <ul style="list-style-type: none"> <li>• download complex I/Q data</li> <li>• name the file (optional argument)</li> <li>• set the sample rate (optional argument)<br/>If you do not set a value, the signal generator uses its preset value of 125 MHz (N5182A) or 100 MHz (E4438C/E8267D), or if a waveform was previously play, the value from that waveform.</li> <li>• start or not start waveform playback after downloading the data (optional argument)<br/>Use either the argument <i>play</i> or the argument <i>no_play</i>.</li> <li>• whether to normalize and scale the I/Q data (optional argument)<br/>If you normalize and scale the data within the body of the code, then use <i>no_normscale</i>, but if you need to normalize and scale the data, use <i>norm_scale</i>. This normalizes the waveform data to the DAC values and then scales the data to 70% of the DAC values.</li> <li>• download marker data (optional argument)<br/>If there is no marker data, the signal generator creates a default marker file, all marker set to zero.</li> </ul> <p>To verify the waveform data download, see <a href="#">“Loading, Playing, and Verifying a Downloaded Waveform” on page 46</a>.</p> |
| 7–9  | If the download fails, display an error message.  |

## Using Advanced Programming Languages

This procedure uses code from the C++ programming example “Importing, Byte Swapping, Interleaving, and Downloading I and Q Data—Big and Little Endian Order” on page 71.

For information on creating I/Q waveform data, refer to “Creating Waveform Data” on page 33.

There are two steps in the process of downloading an I/Q waveform:

1. Open a connection session.
2. Download the I/Q data.

### 1. Open a connection session with the signal generator.

The following code establishes a LAN connection with the signal generator or prints an error message if the session is not opened successfully.

| Line | Code | Description—Open a Connection Session |
|------|------|---------------------------------------|
|------|------|---------------------------------------|

```

1 char* instOpenString = "lan[hostname or IP address]";
  //char* instOpenString = "gpib<primary addr>,<secondary addr>";
2 INST id=iopen(instOpenString);
3 if (!id)
4 {
5     fprintf(stderr, "iopen failed (%s)\n", instOpenString);
6     return -1;
7 }
  
```

| Line | Description—Open a Connection Session  |
|------|--|
| 1    | <p>Assign the signal generator’s LAN hostname, IP address, or GPIB address to a character string.</p> <ul style="list-style-type: none"> <li>• This example uses the Agilent IO library’s <i>iopen()</i> SICL function to establish a LAN connection with the signal generator. The input argument, <i>lan[hostname or IP address]</i> contains the device, interface, or commander address. Change it to your signal generator host name or just set it to the IP address used by your signal generator. For example: “<i>lan[999.137.240.9]</i>”</li> <li>• If you are using GPIB to connect to the signal generator, use the commented line in place of the first line. Insert the GPIB address based on your instrument setting, for example “<i>gpib0,19</i>”.</li> <li>• For the detailed information about the parameters of the SICL function <i>iopen()</i>, refer to the online “<i>Agilent SICL User’s Guide for Windows</i>.”</li> </ul> |
| 2    | <p>Open a connection session with the signal generator to download the generated I/Q data.</p> <p>The SICL function <i>iopen()</i> is from the Agilent IO library and creates a session that returns an identifier to <i>id</i>.</p> <ul style="list-style-type: none"> <li>• If <i>iopen()</i> succeeds in establishing a connection, the function returns a valid session <i>id</i>. The valid session <i>id</i> is not viewable, and can only be used by other SICL functions.</li> <li>• If <i>iopen()</i> generates an error before making the connection, the session identifier is always set to zero. This occurs if the connection fails.</li> <li>• To use this function in C++, you must include the standard header <code>#include &lt;sicl.h&gt;</code> before the <code>main()</code> function.</li> </ul>   |

| Line | Code Description—Open a Connection Session  |
|------|---|
| 3-7  | If <i>id</i> = 0, the program prints out the error message and exits the program. |

## 2. Download the I/Q data.

The following code sends the SCPI command and downloads the generated waveform data to the signal generator.

### Line CodeDescription—Download the I/Q Data

```

8   int bytesToSend;
9   bytesToSend = numsamples*4;
10  char s[20];
11  char cmd[200];
12  sprintf(s, "%d", bytesToSend);
13  sprintf(cmd, ":MEM:DATA \\WF1:FILE1\\", #d%d", strlen(s), bytesToSend);
14  iwrite(id, cmd, strlen(cmd), 0, 0);
15  iwrite(id, iqbuffer, bytesToSend, 0, 0);
16  iwrite(id, "\n", 1, 1, 0);

```

| Line | Code Description—Download the I/Q data  |
|------|---|
| 8    | Define an integer variable ( <i>bytesToSend</i> ) to store the number of bytes to send to the signal generator.   |
| 9    | Calculate the total number of bytes, and store the value in the integer variable defined in line 8.<br><br>In this code, <i>numsamples</i> contains the number of waveform points, not the number of bytes. Because it takes four bytes of data, two I bytes and two Q bytes, to create one waveform point, we have to multiply <i>numsamples</i> by four. This is shown in the following example:<br><br><pre> numsamples = 500 waveform points numsamples × 4 = 2000 (four bytes per point) bytesToSend = 2000 (numsamples × 4) </pre> For information on setting the number of waveform points, see <a href="#">“1. Create I and Q data.” on page 34</a> . |
| 10   | Create a string large enough to hold the <i>bytesToSend</i> value as characters. In this code, string <i>s</i> is set to 20 bytes (20 characters—one character equals one byte)   |
| 11   | Create a string and set its length ( <i>cmd</i> [200]) to hold the SCPI command syntax and parameters. In this code, we define the string length as 200 bytes (200 characters).   |
| 12   | Store the value of <i>bytesToSend</i> in string <i>s</i> . For example, if <i>bytesToSend</i> = 2000; <i>s</i> = "2000"<br><br><i>sprintf()</i> is a standard function in C++, which writes string data to a string variable.   |



| Line | Code Description—Download the I/Q data   |
|------|--|
| 13   | <p>Store the SCPI command syntax and parameters in the string <i>cmd</i>. The SCPI command prepares the signal generator to accept the data.</p> <ul style="list-style-type: none"> <li>• <i>strlen()</i> is a standard function in C++, which returns length of a string.</li> <li>• If <i>bytesToSend</i> = 2000, then <i>s</i> = "2000", <i>strlen(s)</i> = 4, so<br/> <i>cmd</i> = :MEM:DATA "WFM1:FILE1\" #42000.</li> </ul>  |
| 14   | <p>Send the SCPI command stored in the string <i>cmd</i> to the signal generator, which is represented by the session <i>id</i>.</p> <ul style="list-style-type: none"> <li>• <i>iwrite()</i> is a SICL function in Agilent IO library, which writes the data (block data) specified in the string <i>cmd</i> to the signal generator (<i>id</i>).</li> <li>• The third argument of <i>iwrite()</i>, <i>strlen(cmd)</i>, informs the signal generator of the number of bytes in the command string. The signal generator parses the string to determine the number of I/Q data bytes it expects to receive.</li> <li>• The fourth argument of <i>iwrite()</i>, 0, means there is no END of file indicator for the string. This lets the session remain open, so the program can download the I/Q data.</li> </ul>  |
| 15   | <p>Send the generated waveform data stored in the I/Q array (<i>iqbuffer</i>) to the signal generator.</p> <ul style="list-style-type: none"> <li>• <i>iwrite()</i> sends the data specified in <i>iqbuffer</i> to the signal generator (session identifier specified in <i>id</i>).</li> <li>• The third argument of <i>iwrite()</i>, <i>bytesToSend</i>, contains the length of the <i>iqbuffer</i> in bytes. In this example, it is 2000.</li> <li>• The fourth argument of <i>iwrite()</i>, 0, means there is no END of file indicator in the data.</li> </ul> <p>In many programming languages, there are two methods to send SCPI commands and data:</p> <ul style="list-style-type: none"> <li>— Method 1 where the program stops the data download when it encounters the first zero (END indicator) in the data.</li> <li>— Method 2 where the program sends a fixed number of bytes and ignores any zeros in the data. This is the method used in our program.</li> </ul> <p>For your programming language, you must find and use the equivalent of method two. Otherwise you may only achieve a partial download of the I and Q data.</p> |
| 16   | <p>Send the terminating carriage (\n) as the last byte of the waveform data.</p> <ul style="list-style-type: none"> <li>• <i>iwrite()</i> writes the data "\n" to the signal generator (session identifier specified in <i>id</i>).</li> <li>• The third argument of <i>iwrite()</i>, 1, sends one byte to the signal generator.</li> <li>• The fourth argument of <i>iwrite()</i>, 1, is the END of file indicator, which the program uses to terminate the data download.</li> </ul> <p>To verify the waveform data download, see <a href="#">"Loading, Playing, and Verifying a Downloaded Waveform" on page 46</a>.</p>  |

## Loading, Playing, and Verifying a Downloaded Waveform

The following procedures show how to perform the steps using SCPI commands. For front panel key commands, refer to the *User's Guide* or to the Key help in the signal generator.

### Loading a File from Non-Volatile Memory

Select the downloaded I/Q file in non-volatile waveform memory (NVWFM) and load it into volatile waveform memory (WF1). The file comprises three items: I/Q data, marker file, and file header information.

Send one of the following SCPI command to copy the I/Q file, marker file and file header information:

```
:MEMory:COPIY:NAME "<NVWFM:file_name>","<WF1:file_name>"  
:MEMory:COPIY:NAME "<NVMKR:file_name>","<MKR1:file_name>"  
:MEMory:COPIY:NAME "<NVHDR:file_name>","<HDR:file_name>"
```

---

**NOTE** When you copy a waveform file, marker file, or header file information from volatile or non-volatile memory, the waveform and associated marker and header files are all copied. Conversely, when you delete an I/Q file, the associated marker and header files are deleted. It is not necessary to send separate commands to copy or delete the marker and header files.

---

### Playing the Waveform

---

**NOTE** If you would like to build and play a waveform *sequence*, refer to [“Building and Playing Waveform Sequences”](#) on page 48.

---

Play the waveform and use it to modulate the RF carrier.

1. List the waveform files from the volatile memory waveform list:

Send the following SCPI command:

```
:MMEMory:CATalog? "WF1:"
```

2. Select the waveform from the volatile memory waveform list:

Send the following SCPI command:

```
:SOURce:RADio:ARB:WAVeform "WF1:<file_name>"
```

3. Play the waveform:


Send the following SCPI commands:

```
:SOURce:RADio:ARB:STATe ON  
:OUTPut:MODulation:STATe ON  
:OUTPut:STATe ON
```

## Verifying the Waveform

Perform this procedure after completing the steps in the previous procedure, “Playing the Waveform” on page 46.

1. Connect the signal generator to an oscilloscope as shown in the figure.



2. Set an active marker point on the first waveform point for marker one.

---

**NOTE** Select the same waveform selected in “Playing the Waveform” on page 46.

---

Send the following SCPI commands:

```
:SOURCE:RADio:ARB:MARKer:CLEar:ALL "WF1:<file_name>",1  
:SOURCE:RADio:ARB:MARKer:SET "WF1:<file_name>",1,1,1,0.
```

3. Compare the oscilloscope display to the plot of the I and Q data from the text file you created when you generated the data.

If the oscilloscope display, and the I and Q data plots differ, recheck your code. For detailed information on programmatically creating and downloading waveform data, see “Creating Waveform Data” on page 33 and “Downloading Waveform Data” on page 40. For information on the waveform data requirements, see “Waveform Data Requirements” on page 3.

## Building and Playing Waveform Sequences

The signal generator can be used to build waveform sequences. This section assumes you have created the waveform segment file(s) and have the waveform segment file(s) in volatile memory. The following SCPI commands can be used to generate and work with a waveform sequence. For more information refer to the signal generator's *SCPI Command Reference* and *User's Guide*.

---

**NOTE** If you would like to verify the waveform sequence, refer to [“Verifying the Waveform” on page 47](#).

---

1. List the waveform files from the volatile memory waveform list:

Send the following SCPI command:

```
:MMEMemory:CATalog? "WFm1:"
```

2. Select the waveform segment file(s) from the volatile memory waveform list:

Send the following SCPI command:

```
:SOURCE:RADio:ARB:WAVEform "WFm1:<file_name>"
```

3. Save the waveform segment(s) ("`<waveform1>`", "`<waveform2>`", ...), to non-volatile memory as a waveform sequence ("`<file_name>`"), define the number of repetitions (`<reps>`), each waveform segment plays, and enable/disable markers (M1|M2|M3|M4|...), for each waveform segment:

Send the following SCPI command:

```
:SOURCE:RADio:ARB:SEquence  
"<file_name>","<waveform1>",<reps>,M1|M2|M3|M4,{ "<waveform2>",<reps>,ALL}  
  
:SOURCE:RADio:ARB:SEquence? "<file_name>"
```

---

**NOTE** M1|M2|M3|M4 represent the number parameter of the marker selected (i.e. 1|2|3|4). Entering M1|M2|M3|M4 causes the signal generator to display an error. For more information on this SCPI command, refer to the signal generator's *SCPI Command Reference*.

---

4. Play the waveform sequence:

Send the following SCPI commands:

```
:SOURCE:RADio:ARB:STATE ON  
:OUTPut:MODulation:STATE ON  
:OUTPut:STATE ON
```

## Using the Download Utilities

Agilent provides free download utilities to download waveform data into the signal generator. The table in this section describes the capabilities of three such utilities.

For more information and to install the utilities, refer to the following URLs:

- Agilent Signal Studio Toolkit: <http://www.agilent.com/find/signalstudio>

This software provides a graphical interface for downloading files.

- Agilent IntuiLink for Agilent MXG/PSG/ESG/E8663B Signal Generators: <http://www.agilent.com/find/intuilink>

This software places icons in the Microsoft Excel and Word toolbar. Use the icons to connect to the signal generator and open a window for downloading files.

- Agilent MXG/PSG/ESG Download Assistant: <http://www.agilent.com/find/downloadassistant>

This software provides functions for the MATLAB environment to download waveform data.

| Features   | Agilent Signal Studio Toolkit | Agilent IntuiLink | Agilent MXG/PSG/ESG Download Assistant |
|--|-------------------------------|-------------------|--|
| Downloads encrypted waveform files   | X                             |                   |  |
| Downloads Signal Studio waveform files                                     | X <sup>1</sup>                |                   |  |
| Downloads complex MATLAB waveform data                                     |                               |                   | X                                      |
| Downloads MATLAB files (.mat)  | X                             |                   |  |
| Downloads unencrypted interleaved 16-bit I/Q files <sup>2</sup>            | X                             | X                 |  |
| Interleaves and downloads earlier 14-bit E443xB I and Q files <sup>2</sup> | X                             | X                 |  |
| Swaps bytes for little endian order  |                               | X                 |  |
| Downloads user-created marker files  | X                             | X                 | X                                      |
| Performs scaling   | X                             | X                 | X                                      |
| Starts waveform play back  | X                             |                   | X                                      |
| Sends SCPI Commands and Queries  | X                             |                   | X                                      |
| Builds a waveform sequence   | X                             |                   | X                                      |

1. Some Signal Studio products let you create and export waveform files to a PC. Signal Studio Toolkit downloads the exported files.
2. ASCII or binary format.

## Downloading E443xB Signal Generator Files


To download earlier E443xB model I and Q files, use the same SCPI commands as if downloading files to an E443xB signal generator. The signal generator automatically converts the E443xB files to the proper file format as described in [“Waveform Structure” on page 11](#) and stores them in the signal generator’s memory. This conversion process causes the signal generator to take more time to download the earlier file format. To minimize the time to convert earlier E443xB files to the proper file format, store E443xB file downloads to volatile memory, and then transfer them over to non-volatile (NVWFM) memory.

**NOTE** You cannot extract waveform data downloaded as E443xB files.

### E443xB Data Format

The following diagram describes the data format for the E443xB waveform files. This file structure can be compared with the new style file format shown in [“Waveform Structure” on page 11](#). If you create new waveform files for the signal generator, use the format shown in [“Waveform Data Requirements” on page 3](#).

E443xB ARB Data Format



### Storage Locations for E443xB ARB files

Place waveforms in either volatile memory or non-volatile memory. The signal generator supports the E443xB directory structure for waveform file downloads (i.e. “ARBI:”, “ARBQ:”, “NVARBI:”, and “NVARBQ:”, see also [“SCPI Commands” on page 51](#)).

#### Volatile Memory Storage Locations

- /user/arbi/
- /user/arbq/


#### Non-Volatile Memory Storage Locations

- /user/nvarbi/
- /user/nvarbq/


Loading files into the above directories (volatile or non-volatile memory) does not actually store them in those directories. Instead, these directories function as “pipes” to the format translator. The signal generator performs the following functions on the E443xB data:

- Converts the 14-bit I and Q data into 16-bit data (the format required by the signal generator). Subtract 8192, left shifts the data, and appends two bits (zeros) before the least significant bit (i.e. the offset binary values are converted to 2’s complement values by the signal generator).

### E443xB 14-Bit Data




### Subtracts 8192, Left Shifts, and Adds Zeros—Removes Marker and Reserved Bits (16-Bit Data Format)



- Creates a marker file and places the marker information, bits 14 and 15 of the E443xB I data, into the marker file for markers one and two. Markers three and four, within the new marker file, are set to zero (off).

### Places the I Marker Bits into the Signal Generator Marker File



- Interleaves the 16-bit I and Q data creating one I/Q file.
- Creates a file header with all parameters set to unspecified (factory default file header setting).

## SCPI Commands

Use the following commands to download E443xB waveform files into the signal generator.

---

**NOTE** To avoid overwriting the current waveform in volatile memory, before downloading files into volatile memory (WFM1), change the file name or turn off the ARB. For more information, on manually turning off the ARB, refer to the *User's Guide*.

To turn off the ARB remotely, send: :SOURce:RADio:ARB:STATe OFF.

---

| Extraction Method/<br>Memory Type | Command Syntax Options   |
|-----------------------------------|--|
| SCPI/<br>volatile memory          | :MME:DATA "ARBI:<file_name>", <I waveform block data><br>:MME:DATA "ARBQ:<file_name>", <Q waveform data>           |
| SCPI/<br>non-volatile memory      | :MME:DATA "NVARBI:<file_name>", <I waveform block data><br>:MME:DATA "NVARBQ:<file_name>", <Q waveform block data> |

The variables <I waveform block data> and <Q waveform block data> represents data in the E443xB file format. The string variable <file\_name> is the name of the I and Q data file. After downloading the data, the signal generator associates a file header and marker file with the I/Q data file.



## Programming Examples

---

**NOTE** The programming examples contain instrument specific information. However, users can still use these programming examples by substituting in the instrument-specific information for your signal generator. Model specific exceptions for programming use, will be noted at the top of each programming section.

---

The programming examples use GPIB or LAN interfaces and are written in the following languages:

- C++ ([page 53](#))
- MATLAB ([page 78](#))
- Visual Basic ([page 85](#))
- HP Basic ([page 91](#))

See the signal generator's *Programming Guide* for information on interfaces and IO libraries.

The example programs are also available on the signal generator Documentation CD-ROM, which allows you to cut and paste the examples into an editor.

### C++ Programming Examples

This section contains the following programming examples:

- “Creating and Storing Offset I/Q Data—Big and Little Endian Order” on page 54
- “Creating and Storing I/Q Data—Little Endian Order” on page 58
- “Creating and Downloading I/Q Data—Big and Little Endian Order” on page 60
- “Importing and Downloading I/Q Data—Big Endian Order” on page 64
- “Importing and Downloading Using VISA—Big Endian Order” on page 67
- “Importing, Byte Swapping, Interleaving, and Downloading I and Q Data—Big and Little Endian Order” on page 71

## Creating and Storing Offset I/Q Data—Big and Little Endian Order

On the documentation CD, this programming example's name is "*offset\_iq\_c++.txt*."

This C++ programming example (compiled using Microsoft Visual C++ 6.0) follows the same coding algorithm as the MATLAB programming example "[Creating and Storing I/Q Data](#)" on page 78 and performs the following functions:

- error checking
- data creation
- data normalization
- data scaling
- I/Q signal offset from the carrier (single sideband suppressed carrier signal)
- byte swapping and interleaving for little endian order data
- I and Q interleaving for big endian order data
- binary data file storing to a PC or workstation
- reversal of the data formatting process (byte swapping, interleaving, and normalizing the data)

After creating the binary file, you can use FTP, one of the download utilities, or one of the C++ download programming examples to download the file to the signal generator.

```
// This C++ example shows how to
// 1.) Create a simple IQ waveform
// 2.) Save the waveform into the ESG/PSG Internal Arb format
//      This format is for the E4438C, E8267C, E8267D
//      This format will not work with the ESG E443xB or the Agilent MXG N518xA
// 3.) Load the internal Arb format file into an array

#include <stdio.h>
#include <string.h>
#include <math.h>

const int POINTS = 1000; // Size of waveform
const char *computer = "PCWIN";

int main(int argc, char* argv[])
{

// 1.) Create Simple IQ Signal *****
// This signal is a single tone on the upper
// side of the carrier and is usually referred to as
// a Single Side Band Suppressed Carrier (SSBSC) signal.
// It is nothing more than a cosine wavefomm in I
// and a sine waveform in Q.

int points = POINTS; // Number of points in the waveform
int cycles = 101; // Determines the frequency offset from the carrier
```

```

double Iwave[POINTS]; // I waveform
double Qwave[POINTS]; // Q waveform
short int waveform[2*POINTS]; // Holds interleaved I/Q data
double maxAmp = 0; // Used to Normalize waveform data
double minAmp = 0; // Used to Normalize waveform data
double scale = 1;
char buf; // Used for byte swapping
char *pChar; // Used for byte swapping
bool PC = true; // Set flag as appropriate

double phaseInc = 2.0 * 3.141592654 * cycles / points;
double phase = 0;
int i = 0;
for( i=0; i<points; i++ )
{
    phase = i * phaseInc;
    Iwave[i] = cos(phase);
    Qwave[i] = sin(phase);
}

// 2.) Save waveform in internal format *****
// Convert the I and Q data into the internal arb format
// The internal arb format is a single waveform containing interleaved IQ
// data. The I/Q data is signed short integers (16 bits).
// The data has values scaled between +-32767 where
//   DAC Value   Description
//   32767       Maximum positive value of the DAC
//    0          Zero out of the DAC
//  -32767       Maximum negative value of the DAC
// The internal arb expects the data bytes to be in Big Endian format.
// This is opposite of how short integers are saved on a PC (Little Endian).
// For this reason the data bytes are swapped before being saved.

// Find the Maximum amplitude in I and Q to normalize the data between +-1
maxAmp = Iwave[0];
minAmp = Iwave[0];
for( i=0; i<points; i++ )
{
    if( maxAmp < Iwave[i] )
        maxAmp = Iwave[i];
    else if( minAmp > Iwave[i] )
        minAmp = Iwave[i];
}

```

## Creating and Downloading Waveform Files Programming Examples

```
    if( maxAmp < Qwave[i] )
        maxAmp = Qwave[i];
    else if( minAmp > Qwave[i] )
        minAmp = Qwave[i];
}
maxAmp = fabs(maxAmp);
minAmp = fabs(minAmp);
if( minAmp > maxAmp )
    maxAmp = minAmp;

// Convert to short integers and interleave I/Q data
scale = 32767 / maxAmp;    // Watch out for divide by zero.
for( i=0; i<points; i++)
{
    waveform[2*i] = (short)floor(Iwave[i]*scale + 0.5);
    waveform[2*i+1] = (short)floor(Qwave[i]*scale + 0.5);
}
// If on a PC swap the bytes to Big Endian
if( strcmp(computer,"PCWIN") == 0 )
//if( PC )
{
    pChar = (char *)&waveform[0];    // Character pointer to short int data
    for( i=0; i<2*points; i++ )
    {
        buf = *pChar;
        *pChar = *(pChar+1);
        *(pChar+1) = buf;
        pChar+= 2;
    }
}
// Save the data to a file
// Use FTP or one of the download assistants to download the file to the
// signal generator
char *filename = "C:\\Temp\\PSGTestFile";
FILE *stream = NULL;
stream = fopen(filename, "w+b");// Open the file
if (stream==NULL) perror ("Cannot Open File");
int numwritten = fwrite( (void *)waveform, sizeof( short ), points*2, stream );
fclose(stream);// Close the file

// 3.) Load the internal Arb format file *****
// This process is just the reverse of saving the waveform
```

```

// Read in waveform as unsigned short integers.
// Swap the bytes as necessary
// Normalize between +-1
// De-interleave the I/Q Data
// Open the file and load the internal format data
stream = fopen(filename, "r+b");// Open the file
if (stream==NULL) perror ("Cannot Open File");
int numread = fread( (void *)waveform, sizeof( short ), points*2, stream );
fclose(stream);// Close the file
// If on a PC swap the bytes back to Little Endian
if( strcmp(computer,"PCWIN") == 0 )
{
    pChar = (char *)&waveform[0]; // Character pointer to short int data
    for( i=0; i<2*points; i++ )
    {
        buf = *pChar;
        *pChar = *(pChar+1);
        *(pChar+1) = buf;
        pChar+= 2;
    }
}
// Normalize De-Interleave the IQ data
double IwaveIn[POINTS];
double QwaveIn[POINTS];
for( i=0; i<points; i++)
{
    IwaveIn[i] = waveform[2*i] / 32767.0;
    QwaveIn[i] = waveform[2*i+1] / 32767.0;
}
return 0;
}

```

## Creating and Storing I/Q Data—Little Endian Order

On the documentation CD, this programming example's name is "*CreateStore\_Data\_c++.txt*."

This C++ programming example (compiled using Metrowerks CodeWarrior 3.0) performs the following functions:

- error checking
- data creation
- byte swapping and interleaving for little endian order data
- binary data file storing to a PC or workstation

After creating the binary file, you can use FTP, one of the download utilities, or one of the C++ download programming examples to download the file to the signal generator.

```
#include <iostream>
#include <fstream>
#include <math.h>
#include <stdlib.h>

using namespace std;

int main ( void )
{
    ofstream out_stream;          // write the I/Q data to a file
    const unsigned int SAMPLES =200;    // number of sample pairs in the waveform
    const short AMPLITUDE = 32000;     // amplitude between 0 and full scale dac value
    const double two_pi = 6.2831853;

    //allocate buffer for waveform
    short* iqData = new short[2*SAMPLES]; // need two bytes for each integer
    if (!iqData)
    {
        cout << "Could not allocate data buffer." << endl;
        return 1;
    }

    out_stream.open("IQ_data");// create a data file
    if (out_stream.fail())
    {
        cout << "Input file opening failed" << endl;
        exit(1);
    }

    //generate the sample data for I and Q. The I channel will have a sine
    //wave and the Q channel will a cosine wave.
```

```

for (int i=0; i<SAMPLES; ++i)
{
    iqData[2*i] = AMPLITUDE * sin(two_pi*i/(float)SAMPLES);
    iqData[2*i+1] = AMPLITUDE * cos(two_pi*i/(float)SAMPLES);
}
// make sure bytes are in the order MSB(most significant byte) first. (PC only).

char* cptr = (char*)iqData;// cast the integer values to characters

for (int i=0; i<(4*SAMPLES); i+=2)// 4*SAMPLES
{
    char temp = cptr[i];// swap LSB and MSB bytes
    cptr[i]=cptr[i+1];
    cptr[i+1]=temp;
}

// now write the buffer to a file

    out_stream.write((char*)iqData, 4*SAMPLES);
return 0;
}

```

## Creating and Downloading I/Q Data—Big and Little Endian Order

On the documentation CD, this programming example's name is "*CreateDwnLd\_Data\_c++.txt*."

This C++ programming example (compiled using Microsoft Visual C++ 6.0) performs the following functions:

- error checking
- data creation
- data scaling
- text file creation for viewing and debugging data
- byte swapping and interleaving for little endian order data
- interleaving for big endian order data
- data saving to an array (data block)
- data block download to the signal generator

```
// This C++ program is an example of creating and scaling
// I and Q data, and then downloading the data into the
// signal generator as an interleaved I/Q file.
// This example uses a sine and cosine wave as the I/Q
// data.
//
// Include the standard headers for SICL programming
#include <sicl.h>
#include <stdlib.h>
#include <stdio.h>
#include <string.h>
#include <math.h>

// Choose a GPIB, LAN, or RS-232 connection
char* instOpenString = "lan[galqaDhcp1]";
//char* instOpenString = "gpib0,19";

// Pick some maximum number of samples, based on the
// amount of memory in your computer and the signal generator.
const int NUMSAMPLES=500;

int main(int argc, char* argv[])
{
    // Create a text file to view the waveform
    // prior to downloading it to the signal generator.
    // This verifies that the data looks correct.

    char *ofile = "c:\\temp\\iq.txt";
```



```

// Create arrays to hold the I and Q data

int idata[NUMSAMPLES];
int qdata[NUMSAMPLES];

// save the number of samples into numsamples
int numsamples = NUMSAMPLES;

// Fill the I and Q buffers with the sample data
for(int index=0; index<numsamples; index++)
{
    // Create the I and Q data for the number of waveform
    // points and Scale the data (20000 * ...) as a percentage
    // of the DAC full scale (-32768 to 32767). This example
    // scales to approximately 70% of full scale.
    idata[index]=23000 * sin((4*3.14*index)/numsamples);
    qdata[index]=23000 * cos((4*3.14*index)/numsamples);
}

// Print the I and Q values to a text file. View the data
// to see if its correct and if needed, plot the data in a
// spreadsheet to help spot any problems.
FILE *outfile = fopen(ofile, "w");

if (outfile==NULL) perror ("Error opening file to write");
for(index=0; index<numsamples; index++)
{
    fprintf(outfile, "%d, %d\n", idata[index], qdata[index]);
}
fclose(outfile);

// Little endian order data, use the character array and for loop.
// If big endian order, comment out this character array and for loop,
// and use the next loop (Big Endian order data).

// We need a buffer to interleave the I and Q data.
// 4 bytes to account for 2 I bytes and 2 Q bytes.

char iqbuffer[NUMSAMPLES*4];

// Interleave I and Q, and swap bytes from little
// endian order to big endian order.
for(index=0; index<numsamples; index++)
{

```

## Creating and Downloading Waveform Files Programming Examples

```
int ivalue = idata[index];
int qvalue = qdata[index];
iqbuffer[index*4]   = (ivalue >> 8) & 0xFF; // high byte of i
iqbuffer[index*4+1] = ivalue & 0xFF;       // low byte of i
iqbuffer[index*4+2] = (qvalue >> 8) & 0xFF; // high byte of q
iqbuffer[index*4+3] = qvalue & 0xFF;       // low byte of q
}

// Big Endian order data, uncomment the following lines of code.
// Interleave the I and Q data.

// short iqbuffer[NUMSAMPLES*2];           // Big endian order, uncomment this line
// for(index=0; index<numsamples; index++) // Big endian order, uncomment this line
// {                                       // Big endian order, uncomment this line
//     iqbuffer[index*2]   = idata[index]; // Big endian order, uncomment this line
//     iqbuffer[index*2+1] = qdata[index]; // Big endian order, uncomment this line
// }                                       // Big endian order, uncomment this line

// Open a connection to write to the instrument
INST id=iopen(instOpenString);
if (!id)
{
    fprintf(stderr, "iopen failed (%s)\n", instOpenString);
    return -1;
}

// Declare variables to hold portions of the SCPI command
int bytesToSend;
char s[20];
char cmd[200];

bytesToSend = numsamples*4; // calculate the number of bytes
sprintf(s, "%d", bytesToSend); // create a string s with that number of bytes

// The SCPI command has four parts.
// Part 1 = :MEM:DATA "filename",#
// Part 2 = length of Part 3 when written to a string
// Part 3 = length of the data in bytes. This is in s from above.
// Part 4 = the buffer of data

// Build parts 1, 2, and 3 for the I and Q data.
sprintf(cmd, ":MEM:DATA \"WF1:FILE1\", #d%d", strlen(s), bytesToSend);
```

```
// Send parts 1, 2, and 3
iwrite(id, cmd, strlen(cmd), 0, 0);
// Send part 4. Be careful to use the correct command here. In many
// programming languages, there are two methods to send SCPI commands:
// Method 1 = stop at the first '0' in the data
// Method 2 = send a fixed number of bytes, ignoring '0' in the data.
// You must find and use the correct command for Method 2.
iwrite(id, iqbuffer, bytesToSend, 0, 0);
// Send a terminating carriage return
iwrite(id, "\n", 1, 1, 0);

printf("Loaded file using the E4438C, E8267C and E8267D format\n");
return 0;
}
```

## Importing and Downloading I/Q Data—Big Endian Order

On the documentation CD, this programming example's name is "*impDwnLd\_c++.txt*."

This C++ programming example (compiled using Metrowerks CodeWarrior 3.0) assumes that the data is in big endian order and performs the following functions:

- error checking
- binary file importing from the PC or workstation.
- binary file download to the signal generator.

```
// Description: Send a file in blocks of data to a signal generator
//
#include <si1.h>
#include <stdlib.h>
#include <stdio.h>
#include <string.h>

// ATTENTION:
// - Configure these three lines appropriately for your instrument
//   and use before compiling and running
//
char* instOpenString = "gpib7,19"; //for LAN replace with "lan[hostname or IP address]"
const char* localSrcFile = "D:\\home\\TEST_WAVE"; //enter file location on PC/workstation
const char* instDestFile = "/USER/BBG1/WAVEFORM/TEST_WAVE"; //for non-volatile memory
                                                             //remove BBG1 from file path

// Size of the copy buffer
const int BUFFER_SIZE = 100*1024;

int
main()
{
    INST id=iopen(instOpenString);
    if (!id)
    {
        fprintf(stderr, "iopen failed (%s)\n", instOpenString);
        return -1;
    }

    FILE* file = fopen(localSrcFile, "rb");
    if (!file)
    {
        fprintf(stderr, "Could not open file: %s\n", localSrcFile);
        return 0;
    }
}
```

```

if( fseek( file, 0, SEEK_END ) < 0 )
{
    fprintf(stderr,"Cannot seek to the end of file.\n" );
    return 0;
}

long lenToSend = ftell(file);
printf("File size = %d\n", lenToSend);

if (fseek(file, 0, SEEK_SET) < 0)
{
    fprintf(stderr,"Cannot seek to the start of file.\n");
    return 0;
}

char* buf = new char[BUFFER_SIZE];
if (buf && lenToSend)
{
    // Prepare and send the SCPI command header
    char s[20];
    sprintf(s, "%d", lenToSend);
    int lenLen = strlen(s);
    char s2[256];
    sprintf(s2, "mmem:data \"%s\", #d%d", instDestFile, lenLen, lenToSend);
    iwrite(id, s2, strlen(s2), 0, 0);

    // Send file in BUFFER_SIZE chunks
    long numRead;
    do
    {
        numRead = fread(buf, sizeof(char), BUFFER_SIZE, file);
        iwrite(id, buf, numRead, 0, 0);
    } while (numRead == BUFFER_SIZE);

    // Send the terminating newline and EOM
    iwrite(id, "\n", 1, 1, 0);

    delete [] buf;
}
else
{

```

## Creating and Downloading Waveform Files Programming Examples

```
        fprintf(stderr, "Could not allocate memory for copy buffer\n");
    }

    fclose(file);
    iclose(id);
    return 0;
}
```

## Importing and Downloading Using VISA—Big Endian Order

On the documentation CD, this programming example's name is "*DownLoad\_Visa\_c++.txt*."

This C++ programming example (compiled using Microsoft Visual C++ 6.0) assumes that the data is in big endian order and performs the following functions:

- error checking
- binary file importing from the PC or workstation
- binary file download to the signal generator's non-volatile memory

To load the waveform data to volatile (WFM1) memory, change the `instDestfile` declaration to: "USER/BBG1/WAVEFORM/".

```

//*****
// PROGRAM NAME:Download_Visa_c++.cpp
//
// PROGRAM DESCRIPTION:Sample test program to download ARB waveform data. Send a
// file in chunks of ascii data to the signal generator.
//
// NOTE: You must have the Agilent IO Libraries installed to run this program.
//
// This example uses the LAN/TCPIP to download a file to the signal generator's
// non-volatile memory. The program allocates a memory buffer on the PC or
// workstation of 102400 bytes (100*1024 bytes). The actual size of the buffer is
// limited by the memory on your PC or workstation, so the buffer size can be
// increased or decreased to meet your system limitations.
//
// While this program uses the LAN/TCPIP to download a waveform file into
// non-volatile memory, it can be modified to store files in volatile memory
// WFM1 using GPIB by setting the instrOpenString = "TCPIP0::xxx.xxx.xxx.xxx::INSTR"
// declaration with "GPIB::19::INSTR"
//
// The program also includes some error checking to alert you when problems arise
// while trying to download files. This includes checking to see if the file exists.
//*****
// IMPORTANT: Replace the xxx.xxx.xxx.xxx IP address in the instOpenString declaration
// in the code below with the IP address of your signal generator. (or you can use the
// instrument's hostname). Replace the localSrcFile and instDestFile directory paths
// as needed.
//*****

#include <stdlib.h>
#include <stdio.h>
#include <string.h>
#include "visa.h"

```

## Creating and Downloading Waveform Files Programming Examples

```
//  
// IMPORTANT:  
// Configure the following three lines correctly before compiling and running  
  
char* instOpenString = "TCPIP0:xxx.xxx.xxx.xxx::INSTR"; // your instrument's IP address  
  
const char* localSrcFile = "\\Files\\IQ_DataC";  
  
const char* instDestFile = "/USER/WAVEFORM/IQ_DataC";  
  
const int BUFFER_SIZE = 100*1024; // Size of the copy buffer  
  
int main(int argc, char* argv[])  
{  
    ViSession defaultRM, vi;  
    ViStatus status = 0;  
  
    status = viOpenDefaultRM(&defaultRM); // Open the default resource manager  
  
    // TO DO: Error handling here  
  
    status = viOpen(defaultRM, instOpenString, VI_NULL, VI_NULL, &vi);  
  
    if (status) // If any errors then display the error and exit the program  
    {  
        fprintf(stderr, "viOpen failed (%s)\n", instOpenString);  
return -1;  
    }  
  
    FILE* file = fopen(localSrcFile, "rb"); // Open local source file for binary reading  
  
    if (!file) // If any errors display the error and exit the program  
    {  
        fprintf(stderr, "Could not open file: %s\n", localSrcFile);  
return 0;  
    }  
  
    if( fseek( file, 0, SEEK_END ) < 0 )  
    {  
        fprintf(stderr, "Cannot lseek to the end of file.\n" );  
        return 0;  
    }  
}
```



```

long lenToSend = ftell(file); // Number of bytes in the file

printf("File size = %d\n", lenToSend);

if (fseek(file, 0, SEEK_SET) < 0)
{
    fprintf(stderr, "Cannot lseek to the start of file.\n");
    return 0;
}

unsigned char* buf = new unsigned char[BUFFER_SIZE]; // Allocate char buffer memory

if (buf && lenToSend)
{
    // Do not send the EOI (end of instruction) terminator on any write except the
    // last one

    viSetAttribute( vi, VI_ATTR_SEND_END_EN, 0 );

    // Prepare and send the SCPI command header

    char s[20];
    sprintf(s, "%d", lenToSend);

    int lenLen = strlen(s);
    unsigned char s2[256];

    // Write the command mmem:data and the header. The number lenLen represents the
    // number of bytes and the actual number of bytes is the variable lenToSend

    sprintf((char*)s2, "mmem:data \"%s\", #d%d", instDestFile, lenLen, lenToSend);

    // Send the command and header to the signal generator

    viWrite(vi, s2, strlen((char*)s2), 0);

    long numRead;

    // Send file in BUFFER_SIZE chunks to the signal generator

    do

```

## Creating and Downloading Waveform Files Programming Examples

```
{
    numRead = fread(buf, sizeof(char), BUFFER_SIZE, file);

    viWrite(vi, buf, numRead, 0);

} while (numRead == BUFFER_SIZE);

// Send the terminating newline and EOF

viSetAttribute( vi, VI_ATTR_SEND_END_EN, 1 );

char* newLine = "\n";

viWrite(vi, (unsigned char*)newLine, 1, 0);

delete [] buf;
}
else
{
    fprintf(stderr, "Could not allocate memory for copy buffer\n");
}

fclose(file);
viClose(vi);
viClose(defaultRM);

return 0;
}
```

### Importing, Byte Swapping, Interleaving, and Downloading I and Q Data—Big and Little Endian Order

On the documentation CD, this programming example's name is "*impDwnLd2\_c++.txt*."

This C++ programming example (compiled using Microsoft Visual C++ 6.0) performs the following functions:

- error checking
- binary file importing (earlier E443xB or current model signal generators)
- byte swapping and interleaving for little endian order data
- data interleaving for big endian order data
- data scaling
- binary file download for earlier E443xB data or current signal generator formatted data

```
// This C++ program is an example of loading I and Q
// data into an E443xB, E4438C, E8267C, or E8267D signal
// generator.
//
// It reads the I and Q data from a binary data file
// and then writes the data to the instrument.

// Include the standard headers for SICL programming
#include <sicl.h>
#include <stdlib.h>
#include <stdio.h>
#include <string.h>

// Choose a GPIB, LAN, or RS-232 connection
char* instOpenString ="gplib0,19";

// Pick some maximum number of samples, based on the
// amount of memory in your computer and your waveforms.
const int MAXSAMPLES=50000;

int main(int argc, char* argv[])
{
    // These are the I and Q input files.
    // Some compilers will allow '/' in the directory
    // names. Older compilers might need '\\' in the
    // directory names. It depends on your operating system
    // and compiler.
    char *ifile = "c:\\SignalGenerator\\data\\BurstAII.bin";
    char *qfile = "c:\\SignalGenerator\\data\\BurstAIQ.bin";
```

## Creating and Downloading Waveform Files Programming Examples

```
// This is a text file to which we will write the
// I and Q data just for debugging purposes. It is
// a good programming practice to check your data
// in this way before attempting to write it to
// the instrument.
char *ofile = "c:\\SignalGenerator\\data\\iq.txt";

// Create arrays to hold the I and Q data
int idata[MAXSAMPLES];
int qdata[MAXSAMPLES];

// Often we must modify, scale, or offset the data
// before loading it into the instrument. These
// buffers are used for that purpose. Since each
// sample is 16 bits, and a character only holds
// 8 bits, we must make these arrays twice as long
// as the I and Q data arrays.
char ibuffer[MAXSAMPLES*2];
char qbuffer[MAXSAMPLES*2];

// For the E4438C or E8267C/67D, we might also need to interleave
// the I and Q data. This buffer is used for that
// purpose. In this case, this buffer must hold
// both I and Q data so it needs to be four times
// as big as the data arrays.
char iqbuffer[MAXSAMPLES*4];

// Declare variables which will be used later
bool done;
FILE *infile;
int index, numsamples, i1, i2, ivalue;

// In this example, we'll assume the data files have
// the I and Q data in binary form as unsigned 16 bit integers.
// This next block reads those binary files. If your
// data is in some other format, then replace this block
// with appropriate code for reading your format.
// First read I values
done = false;
index = 0;
infile = fopen(infile, "rb");
if (infile==NULL) perror ("Error opening file to read");
```

```

while(!done)
{
    i1 = fgetc(infile); // read the first byte
    if(i1==EOF) break;
    i2 = fgetc(infile); // read the next byte
    if(i2==EOF) break;
    ivalue=i1+i2*256; // put the two bytes together
    // note that the above format is for a little endian
    // processor such as Intel. Reverse the order for
    // a big endian processor such as Motorola, HP, or Sun
    idata[index++]=ivalue;
    if(index==MAXSAMPLES) break;
}
fclose(infile);

// Then read Q values
index = 0;
infile = fopen(qfile, "rb");
if (infile==NULL) perror ("Error opening file to read");
while(!done)
{
    i1 = fgetc(infile); // read the first byte
    if(i1==EOF) break;
    i2 = fgetc(infile); // read the next byte
    if(i2==EOF) break;
    ivalue=i1+i2*256; // put the two bytes together
    // note that the above format is for a little endian
    // processor such as Intel. Reverse the order for
    // a big endian processor such as Motorola, HP, or Sun
    qdata[index++]=ivalue;
    if(index==MAXSAMPLES) break;
}
fclose(infile);

// Remember the number of samples which were read from the file.
numsamples = index;

// Print the I and Q values to a text file. If you are
// having trouble, look in the file and see if your I and
// Q data looks correct. Plot the data from this file if
// that helps you to diagnose the problem.
FILE *outfile = fopen(ofile, "w");

```

## Creating and Downloading Waveform Files Programming Examples

```
if (outfile==NULL) perror ("Error opening file to write");
for(index=0; index<numsamples; index++)
{
    fprintf(outfile, "%d, %d\n", idata[index], qdata[index]);
}
fclose(outfile);

// The E443xB, E4438C, E8267C or E8267D all use big-endian
// processors.  If your software is running on a little-endian
// processor such as Intel, then you will need to swap the
// bytes in the data before sending it to the signal generator.

// The arrays ibuffer and qbuffer are used to hold the data
// after any byte swapping, shifting or scaling.

// In this example, we'll assume that the data is in the format
// of the E443xB without markers.  In other words, the data
// is in the range 0-16383.
// 0 gives negative full-scale output
// 8192 gives 0 V output
// 16383 gives positive full-scale output
// If this is not the scaling of your data, then you will need
// to scale your data appropriately in the next two blocks.

// ibuffer and qbuffer will hold the data in the E443xB format.
// No scaling is needed, however we need to swap the byte order
// on a little endian computer.  Remove the byte swapping
// if you are using a big endian computer.
for(index=0; index<numsamples; index++)
{
    int ivalue = idata[index];
    int qvalue = qdata[index];
    ibuffer[index*2]   = (ivalue >> 8) & 0xFF; // high byte of i
    ibuffer[index*2+1] = ivalue & 0xFF;         // low byte of i
    qbuffer[index*2]   = (qvalue >> 8) & 0xFF; // high byte of q
    qbuffer[index*2+1] = qvalue & 0xFF;         // low byte of q
}

// iqbuffer will hold the data in the E4438C, E8267C, E8267D
// format.  In this format, the I and Q data is interleaved.
// The data is in the range -32768 to 32767.
// -32768 gives negative full-scale output
```

```

//      0 gives 0 V output
//      32767 gives positive full-scale output
// From these ranges, it appears you should offset the
// data by 8192 and scale it by 4. However, due to the
// interpolators in these products, it is better to scale
// the data by a number less than four. Commonly a good
// choice is 70% of 4 which is 2.8.
// By default, the signal generator scales data to 70%
// If you scale the data here, you may want to change the
// signal generator scaling to 100%
// Also we need to swap the byte order on a little endian
// computer. This code also works for big endian order data
// since it swaps bytes based on the order.
for(index=0; index<numsamples; index++)
{
    int iscaled = 2.8*(idata[index]-8192); // shift and scale
    int qscaled = 2.8*(qdata[index]-8192); // shift and scale
    iqbuffer[index*4]   = (iscaled >> 8) & 0xFF; // high byte of i
    iqbuffer[index*4+1] = iscaled & 0xFF;        // low byte of i
    iqbuffer[index*4+2] = (qscaled >> 8) & 0xFF; // high byte of q
    iqbuffer[index*4+3] = qscaled & 0xFF;        // low byte of q
}

// Open a connection to write to the instrument
INST id=iopen(instOpenString);
if (!id)
{
    fprintf(stderr, "iopen failed (%s)\n", instOpenString);
    return -1;
}

// Declare variables which will be used later
int bytesToSend;
char s[20];
char cmd[200];

// The E4438C, E8267C and E8267D accept the E443xB format.
// so we can use this next section on any of these signal generators.
// However the E443xB format only uses 14 bits.

bytesToSend = numsamples*2; // calculate the number of bytes
sprintf(s, "%d", bytesToSend); // create a string s with that number of bytes

```

## Creating and Downloading Waveform Files Programming Examples

```
// The SCPI command has four parts.
// Part 1 = :MEM:DATA "filename",
// Part 2 = length of Part 3 when written to a string
// Part 3 = length of the data in bytes. This is in s from above.
// Part 4 = the buffer of data

// Build parts 1, 2, and 3 for the I data.
sprintf(cmd, ":MEM:DATA \"ARBI:FILE1\", %#d%d", strlen(s), bytesToSend);
// Send parts 1, 2, and 3
iwrite(id, cmd, strlen(cmd), 0, 0);
// Send part 4. Be careful to use the correct command here. In many
// programming languages, there are two methods to send SCPI commands:
// Method 1 = stop at the first '0' in the data
// Method 2 = send a fixed number of bytes, ignoring '0' in the data.
// You must find and use the correct command for Method 2.
iwrite(id, ibuffer, bytesToSend, 0, 0);
// Send a terminating carriage return
iwrite(id, "\n", 1, 1, 0);

// Identical to the section above, except for the Q data.
sprintf(cmd, ":MEM:DATA \"ARBQ:FILE1\", %#d%d", strlen(s), bytesToSend);
iwrite(id, cmd, strlen(cmd), 0, 0);
iwrite(id, qbuffer, bytesToSend, 0, 0);
iwrite(id, "\n", 1, 1, 0);

printf("Loaded FILE1 using the E443xB format\n");

// The E4438C, E8267C and E8267D have a newer faster format which
// allows 16 bits to be used. However this format is not accepted in
// the E443xB. Therefore do not use this next section for the E443xB.

printf("Note: Loading FILE2 on a E443xB will cause \"ERROR: 208, I/O error\"\n");

// Identical to the I and Q sections above except
// a) The I and Q data are interleaved
// b) The buffer of I+Q is twice as long as the I buffer was.
// c) The SCPI command uses WFM1 instead of ARBI and ARBQ.
bytesToSend = numsamples*4;
sprintf(s, "%d", bytesToSend);
sprintf(cmd, ":mem:data \"WFM1:FILE2\", %#d%d", strlen(s), bytesToSend);
iwrite(id, cmd, strlen(cmd), 0, 0);
```



```
iwrite(id, iqbuffer, bytesToSend, 0, 0);  
iwrite(id, "\n", 1, 1, 0);  
printf("Loaded FILE2 using the E4438C, E8267C and E8267D format\n");  
return 0;  
}
```

## MATLAB Programming Examples

This section contains the following programming examples:

- “Creating and Storing I/Q Data” on page 78
- “Creating and Downloading a Pulse” on page 81

### Creating and Storing I/Q Data

On the documentation CD, this programming example’s name is “*offset\_iq\_ml.m.*”

This MATLAB programming example follows the same coding algorithm as the C++ programming example “Creating and Storing Offset I/Q Data—Big and Little Endian Order” on page 54 and performs the following functions:

- error checking
- data creation
- data normalization
- data scaling
- I/Q signal offset from the carrier (single sideband suppressed carrier signal)
- byte swapping and interleaving for little endian order data
- I and Q interleaving for big endian order data
- binary data file storing to a PC or workstation
- reversal of the data formatting process (byte swapping, interleaving, and normalizing the data)

```
function main
% Using MatLab this example shows how to
% 1.) Create a simple IQ waveform
% 2.) Save the waveform into the Agilent MXG/ESG/PSG Internal Arb format
%     This format is for the N5182A, E4438C, E8267C, and E8267D
%     This format will not work with the earlier E443xB ESG
% 3.) Load the internal Arb format file into a MatLab array

% 1.) Create Simple IQ Signal *****
% This signal is a single tone on the upper
% side of the carrier and is usually referred to as
% a Single Side Band Suppressed Carrier (SSBSC) signal.
% It is nothing more than a cosine wavefomm in I
% and a sine waveform in Q.
%
points = 1000;      % Number of points in the waveform
cycles = 101;      % Determines the frequency offset from the carrier

phaseInc = 2*pi*cycles/points;
phase = phaseInc * [0:points-1];

Iwave = cos(phase);
```

```

Qwave = sin(phase);

% 2.) Save waveform in internal format *****
% Convert the I and Q data into the internal arb format
% The internal arb format is a single waveform containing interleaved IQ
% data. The I/Q data is signed short integers (16 bits).
% The data has values scaled between +-32767 where
%   DAC Value   Description
%   32767       Maximum positive value of the DAC
%    0          Zero out of the DAC
%  -32767       Maximum negative value of the DAC
% The internal arb expects the data bytes to be in Big Endian format.
% This is opposite of how short integers are saved on a PC (Little Endian).
% For this reason the data bytes are swapped before being saved.

% Interleave the IQ data
waveform(1:2:2*points) = Iwave;
waveform(2:2:2*points) = Qwave;
%[Iwave;Qwave];
%waveform = waveform(:)';

% Normalize the data between +-1
waveform = waveform / max(abs(waveform));    % Watch out for divide by zero.

% Scale to use full range of the DAC
waveform = round(waveform * 32767);        % Data is now effectively signed short integer values

% waveform = round(waveform * (32767 / max(abs(waveform))));    % More efficient than previous two
% steps!

% PRESERVE THE BIT PATTERN but convert the waveform to
% unsigned short integers so the bytes can be swapped.
% Note: Can't swap the bytes of signed short integers in MatLab.
waveform = uint16(mod(65536 + waveform,65536)); %

% If on a PC swap the bytes to Big Endian
if strcmp( computer, 'PCWIN' )
    waveform = bitor(bitshift(waveform,-8),bitshift(waveform,8));
end

% Save the data to a file
% Note: The waveform is saved as unsigned short integers. However,
%       the actual bit pattern is that of signed short integers and

```

## Creating and Downloading Waveform Files Programming Examples

```
%          that is how the Agilent MXG/ESG/PSG interprets them.
filename = 'C:\Temp\PSGTestFile';
[FID, message] = fopen(filename,'w');% Open a file to write data
if FID == -1 error('Cannot Open File'); end
fwrite(FID,waveform,'unsigned short');% write to the file
fclose(FID);                          % close the file

% 3.) Load the internal Arb format file *****
% This process is just the reverse of saving the waveform
% Read in waveform as unsigned short integers.
% Swap the bytes as necessary
% Convert to signed integers then normalize between +-1
% De-interleave the I/Q Data

% Open the file and load the internal format data
[FID, message] = fopen(filename,'r');% Open file to read data
if FID == -1 error('Cannot Open File'); end
[internalWave,n] = fread(FID, 'uint16');% read the IQ file
fclose(FID);% close the file

internalWave = internalWave'; % Conver from column array to row array

% If on a PC swap the bytes back to Little Endian
if strcmp( computer, 'PCWIN' ) % Put the bytes into the correct order
    internalWave= bitor(bitshift(internalWave,-8),bitshift(bitand(internalWave,255),8));
end

% convert unsigned to signed representation
internalWave = double(internalWave);
tmp = (internalWave > 32767.0) * 65536;
iqWave = (internalWave - tmp) ./ 32767; % and normalize the data

% De-Interleave the IQ data
IwaveIn = iqWave(1:2:n);
QwaveIn = iqWave(2:2:n);
```

## Creating and Downloading a Pulse

---

**NOTE** This section applies only to the Agilent MXG and the PSG.

For the Agilent MXG, the maximum frequency is 6 GHz, and the *pulsepat.m* program's `SOURCE:FREQUENCY 20000000000` value must be changed as required in the following programs. For more frequency information, refer to the signal generator's *Data Sheet*.

---

On the documentation CD, this programming example's name is "*pulsepat.m*."

This MATLAB programming example performs the following functions:

- I and Q data creation for 10 pulses
- marker file creation
- data scaling
- downloading using Agilent MXG/PSG Download Assistant functions (see ["Using the Download Utilities" on page 49](#) for more information)

% Script file: pulsepat.m

%

% Purpose:

%To calculate and download an arbitrary waveform file that simulates a

%simple antenna scan pulse pattern to the Agilent MXG/PSG vector signal generator.

%

% Define Variables:

% n -- counting variable (no units)

% t -- time (seconds)

% rise -- raised cosine pulse rise-time definition (samples)

% on -- pulse on-time definition (samples)

% fall -- raised cosine pulse fall-time definition (samples)

% i -- in-phase modulation signal

% q -- quadrature modulation signal

n=4; % defines the number of points in the rise-time and fall-time

t=-1:2/n:1-2/n; % number of points translated to time

rise=(1+sin(t\*pi/2))/2; % defines the pulse rise-time shape

on=ones(1,120); % defines the pulse on-time characteristics

fall=(1+sin(-t\*pi/2))/2; % defines the pulse fall-time shape

off=zeros(1,896); % defines the pulse off-time characteristics

```
% arrange the i-samples and scale the amplitude to simulate an antenna scan
% pattern comprised of 10 pulses
i = .707*[rise on fall off...
[.9*[rise on fall off]]...
[.8*[rise on fall off]]...
[.7*[rise on fall off]]...
[.6*[rise on fall off]]...
[.5*[rise on fall off]]...
[.4*[rise on fall off]]...
[.3*[rise on fall off]]...
[.2*[rise on fall off]]...
[.1*[rise on fall off]];

% set the q-samples to all zeroes
q = zeros(1,10240);

% define a composite iq matrix for download to the Agilent MXG/PSG using the
% PSG Download Assistant
IQData = [i + (j * q)];

% define a marker matrix and activate a marker to indicate the beginning of the waveform
Markers = zeros(2,length(IQData));    % fill marker array with zero, i.e no markers set
Markers(1,1) = 1;    % set marker to first point of playback

% make a new connection to theAgilent MXG/PSG over the GPIB interface
io = agt_newconnection('gpib',0,19);

% verify that communication with the Agilent MXG/PSG has been established
[status, status_description, query_result] = agt_query(io,'*idn?');
if (status < 0) return; end

% set the carrier frequency and power level on the Agilent MXG/PSG using the Agilent MXG/PSG
% Download Assistant
```

```
[status, status_description] = agt_sendcommand(io, 'SOURCE:FREQUENCY 20000000000');
[status, status_description] = agt_sendcommand(io, 'POWER 0');


% define the ARB sample clock for playback
sampclk = 40000000;

% download the iq waveform to the PSG baseband generator for playback
[status, status_description] = agt_waveformload(io, IQData, 'pulsepat', sampclk, 'play', 'no_normscale',
Markers);

% turn on RF output power
[status, status_description ] = agt_sendcommand( io, 'OUTPUT:STATE ON' )
```

You can test your program by performing a simulated plot of the in-phase modulation signal in Matlab (see [Figure 11 on page 83](#)). To do this, enter `plot (i)` at the Matlab command prompt.

**Figure 11 Simulated Plot of In-Phase Signal**



The following additional Matlab M-file pulse programming examples are also available on the *Documentation CD-ROM* for your Agilent MXG and PSG signal generator:

---

**NOTE** For the Agilent MXG, the `SOURCE:FREQUENCY 20000000000` value must be changed as required in the following programs. For more information, refer to the *Data Sheet*.

---

|              |   |
|--------------|---|
| barker.m     | This programming example calculates and downloads an arbitrary waveform file that simulates a simple 7-bit barker RADAR signal to the PSG vector signal generator.  |
| chirp.m      | This programming example calculates and downloads an arbitrary waveform file that simulates a simple compressed pulse RADAR signal using linear FM chirp to the PSG vector signal generator.  |
| FM.m         | This programming example calculates and downloads an arbitrary waveform file that simulates a single tone FM signal with a rate of 6 KHz, deviation of $\pm 14.3$ KH, Bessel null of $\text{dev}/\text{rate}=2.404$ to the Agilent MXG/PSG vector signal generator. |
| nchirp.m     | This programming example calculates and downloads an arbitrary waveform file that simulates a simple compressed pulse RADAR signal using non-linear FM chirp to the PSG vector signal generator.  |
| pulse.m      | This programming example calculates and downloads an arbitrary waveform file that simulates a simple pulse signal to the PSG vector signal generator.   |
| pulsedroop.m | This programming example calculates and downloads an arbitrary waveform file that simulates a simple pulse signal with pulse droop to the PSG vector signal generator.  |



## Visual Basic Programming Examples

### Creating I/Q Data—Little Endian Order

On the documentation CD, this programming example's name is "*Create\_IQData\_vb.txt*."

This Visual Basic programming example, using Microsoft Visual Basic 6.0, uses little endian order data, and performs the following functions:

- error checking
- I an Q integer array creation
- I an Q data interleaving
- byte swapping to convert to big endian order
- binary data file storing to a PC or workstation

Once the file is created, you can download the file to the signal generator using FTP (see "[FTP Procedures](#)" on page 31).

```

*****
' Program Name: Create_IQData
' Program Description: This program creates a sine and cosine wave using 200 I/Q data
' samples. Each I and Q value is represented by a 2 byte integer. The sample points are
' calculated, scaled using the AMPLITUDE constant of 32767, and then stored in an array
' named iq_data. The AMPLITUDE scaling allows for full range I/Q modulator DAC values.
' Data must be in 2's complement, MSB/LSB big-endian format. If your PC uses LSB/MSB
' format, then the integer bytes must be swapped. This program converts the integer
' array values to hex data types and then swaps the byte positions before saving the
' data to the IQ_DataVB file.
*****

Private Sub Create_IQData()
Dim index As Integer
Dim AMPLITUDE As Integer
Dim pi As Double
Dim loByte As Byte
Dim hiByte As Byte
Dim loHex As String
Dim hiHex As String
Dim strSrc As String
Dim numPoints As Integer
Dim FileHandle As Integer
Dim data As Byte
Dim iq_data() As Byte
Dim strFilename As String

strFilename = "C:\IQ_DataVB"

Const SAMPLES = 200      ' Number of sample PAIRS of I and Q integers for the waveform

```

## Creating and Downloading Waveform Files Programming Examples

```
AMPLITUDE = 32767      ' Scale the amplitude for full range of the signal generators
                        ' I/Q modulator DAC

pi = 3.141592

Dim intIQ_Data(0 To 2 * SAMPLES - 1) 'Array for I and Q integers: 400
ReDim iq_data(0 To (4 * SAMPLES - 1)) 'Need MSB and LSB bytes for each integer value: 800

'Create an integer array of I/Q pairs

For index = 0 To (SAMPLES - 1)
    intIQ_Data(2 * index) = CInt(AMPLITUDE * Sin(2 * pi * index / SAMPLES))
    intIQ_Data(2 * index + 1) = CInt(AMPLITUDE * Cos(2 * pi * index / SAMPLES))
Next index

'Convert each integer value to a hex string and then write into the iq_data byte array
'MSB, LSB ordered
For index = 0 To (2 * SAMPLES - 1)
    strSrc = Hex(intIQ_Data(index)) 'convert the integer to a hex value

    If Len(strSrc) <> 4 Then
        strSrc = String(4 - Len(strSrc), "0") & strSrc 'Convert to hex format i.e "800F"
    End If
        'Pad with 0's if needed to get 4
        'characters i.e '0' to "0000"

    hiHex = Mid$(strSrc, 1, 2) 'Get the first two hex values (MSB)
    loHex = Mid$(strSrc, 3, 2) 'Get the next two hex values (LSB)
    loByte = CByte("&H" & loHex) 'Convert to byte data type LSB
    hiByte = CByte("&H" & hiHex) 'Convert to byte data type MSB

    iq_data(2 * index) = hiByte      'MSB into first byte
    iq_data(2 * index + 1) = loByte  'LSB into second byte

Next index

'Now write the data to the file

FileHandle = FreeFile()      'Get a file number

numPoints = UBound(iq_data) 'Get the number of bytes in the file

Open strFilename For Binary Access Write As #FileHandle Len = numPoints + 1
```

```
On Error GoTo file_error

    For index = 0 To (numPoints)
        data = iq_data(index)
        Put #FileHandle, index + 1, data 'Write the I/Q data to the file
    Next index

Close #FileHandle

Call MsgBox("Data written to file " & strFilename, vbOKOnly, "Download")

Exit Sub

file_error:
    MsgBox Err.Description
    Close #FileHandle

End Sub
```

## Downloading I/Q Data

On the signal generator's documentation CD, this programming example's name is "*Download\_File\_vb.txt*."

This Visual Basic programming example, using Microsoft Visual Basic 6.0, downloads the file created in "[Creating I/Q Data—Little Endian Order](#)" on page 85 into non-volatile memory using a LAN connection. To use GPIB, replace the `instOpenString` object declaration with "GPIB::19::INSTR". To download the data into volatile memory, change the `instDestfile` declaration to "USER/BBG1/WAVEFORM/".

---

**NOTE** The example program listed here uses the VISA COM IO API, which includes the `WriteIEEEBlock` method. This method eliminates the need to format the download command with arbitrary block information such as defining number of bytes and byte numbers. Refer to "[SCPI Command Line Structure](#)" on page 26 for more information.

---

This program also includes some error checking to alert you when problems arise while trying to download files. This includes checking to see if the file exists.

```
*****
' Program Name: Download_File
' Program Description: This program uses Microsoft Visual Basic 6.0 and the Agilent
' VISA COM I/O Library to download a waveform file to the signal generator.
'
' The program downloads a file (the previously created 'IQ_DataVB' file) to the signal
' generator. Refer to the Programming Guide for information on binary
' data requirements for file downloads. The waveform data 'IQ_DataVB' is
' downloaded to the signal generator's non-volatile memory(NVWFM)
' " /USER/WAVEFORM/IQ_DataVB". For volatile memory(WFM1) download to the
' " /USER/BBG1/WAVEFORM/IQ_DataVB" directory.
'
' You must reference the Agilent VISA COM Resource Manager and VISA COM 1.0 Type
' Library in your Visual Basic project in the Project/References menu.
' The VISA COM 1.0 Type Library, corresponds to VISACOM.tlb and the Agilent
' VISA COM Resource Manager, corresponds to AgTRM.DLL.
' The VISA COM 488.2 Formatted I/O 1.0, corresponds to the BasicFormattedIO.dll
' Use a statement such as "Dim Instr As VisaComLib.FormattedIO488" to
' create the formatted I/O reference and use
' "Set Instr = New VisaComLib.FormattedIO488" to create the actual object.
*****
' IMPORTANT: Use the TCP/IP address of your signal generator in the rm.Open
' declaraion. If you are using the GPIB interface in your project use "GPIB::19::INSTR"
' in the rm.Open declaration.
*****
```

```

Private Sub Download_File()
' The following four lines declare IO objects and instantiate them.
Dim rm As VisaComLib.ResourceManager
Set rm = New AgilentRMLib.SRMClS
Dim SigGen As VisaComLib.FormattedIO488
Set SigGen = New VisaComLib.FormattedIO488

' NOTE: Use the IP address of your signal generator in the rm.Open declaration
Set SigGen.IO = rm.Open("TCPIP0::000.000.000.000")

Dim data As Byte
Dim iq_data() As Byte
Dim FileHandle As Integer
Dim numPoints As Integer
Dim index As Integer
Dim Header As String
Dim response As String
Dim hiByte As String
Dim loByte As String
Dim strFilename As String

strFilename = "C:\IQ_DataVB" 'File Name and location on PC
                        'Data will be saved to the signal generator's NVWFM
                        '\USER/WAVEFORM/IQ_DataVB directory.

FileHandle = FreeFile()

On Error GoTo errorhandler

With SigGen
    .IO.Timeout = 5000 'Set up the signal generator to accept a download
                        'Timeout 50 seconds
    .WriteString "*RST" 'Reset the signal generator.
End With

numPoints = (FileLen(strFilename)) 'Get number of bytes in the file: 800 bytes

ReDim iq_data(0 To numPoints - 1) 'Dimension the iq_data array to the
                                'size of the IQ_DataVB file: 800 bytes

Open strFilename For Binary Access Read As #FileHandle 'Open the file for binary read
On Error GoTo file_error

For index = 0 To (numPoints - 1) 'Write the IQ_DataVB data to the iq_data array

```

## Creating and Downloading Waveform Files Programming Examples

```
        Get #FileHandle, index + 1, data      '(index+1) is the record number
        iq_data(index) = data
Next index

        Close #FileHandle                    'Close the file

'Write the command to the Header string. NOTE: syntax
Header = "MEM:DATA ""/USER/WAVEFORM/IQ_Data.vb"", "

'Now write the data to the signal generator's non-volatile memory (NVWFM)

SigGen.WriteIEEEBlock Header, iq_data

SigGen.WriteString "*OPC?"                  'Wait for the operation to complete
response = SigGen.ReadString                'Signal generator response to the OPC? query
Call MsgBox("Data downloaded to the signal generator", vbOKOnly, "Download")
Exit Sub
errorhandler:
    MsgBox Err.Description, vbExclamation, "Error Occurred", Err.HelpFile, Err.HelpContext
Exit Sub
file_error:
    Call MsgBox(Err.Description, vbOKOnly) 'Display any error message
    Close #FileHandle
End Sub
```

## HP Basic Programming Examples

This section contains the following programming examples:

- “Creating and Downloading Waveform Data Using HP BASIC for Windows®” on page 91
- “Creating and Downloading Waveform Data Using HP BASIC for UNIX” on page 94
- “Creating and Downloading E443xB Waveform Data Using HP BASIC for Windows” on page 96
- “Creating and Downloading E443xB Waveform Data Using HP Basic for UNIX” on page 98

### Creating and Downloading Waveform Data Using HP BASIC for Windows®

On the documentation CD, this programming example’s name is “*hpbasicWin.txt*.”

The following program will download a waveform using HP Basic for Windows into volatile ARB memory. The waveform generated by this program is the same as the default SINE\_TEST\_WFM waveform file available in the signal generator’s waveform memory. This code is similar to the code shown for BASIC for UNIX but there is a formatting difference in line 130 and line 140.

To download into non-volatile memory, replace line 190 with:

```
190 OUTPUT @PSG USING "#,K";":MMEM:DATA ""NVWFM:testfile"", #"
```

As discussed at the beginning of this section, I and Q waveform data is interleaved into one file in 2’s compliment form and a marker file is associated with this I/Q waveform file.

In the Output commands, USING “#,K” formats the data. The pound symbol (#) suppresses the automatic EOL (End of Line) output. This allows multiple output commands to be concatenated as if they were a single output. The “K” instructs HP Basic to output the following numbers or strings in the default format.

```
10 ! RE-SAVE "BASIC_Win_file"
20 Num_points=200
30 ALLOCATE INTEGER Int_array(1:Num_points*2)
40 DEG
50 FOR I=1 TO Num_points*2 STEP 2
60     Int_array(I)=INT(32767*(SIN(I*360/Num_points)))
70 NEXT I
80 FOR I=2 TO Num_points*2 STEP 2
90     Int_array(I)=INT(32767*(COS(I*360/Num_points)))
100 NEXT I
110 PRINT "Data Generated"
120 Nbytes=4*Num_points
130 ASSIGN @PSG TO 719
140 ASSIGN @PSGb TO 719:FORMAT MSB FIRST
150 Nbytes$=VAL$(Nbytes)
160 Ndigits=LEN(Nbytes$)
```

Windows and MS Windows are U.S registered trademarks of Microsoft Corporation.

Creating and Downloading Waveform Files  
Programming Examples

```

170  Ndigits$=VAL$(Ndigits)
180  WAIT 1
190  OUTPUT @PSG USING "#,K";":MMEM:DATA " "WFM1:data_file" ",#"
200  OUTPUT @PSG USING "#,K";Ndigits$
210  OUTPUT @PSG USING "#,K";Nbytes$
220  WAIT 1
230  OUTPUT @PSGb;Int_array(*)
240  OUTPUT @PSG;END
250  ASSIGN @PSG TO *
260  ASSIGN @PSGb TO *
270  PRINT
280  PRINT "*END*"
290  END

```

**Program Comments**

|             |   |
|-------------|---|
| 10:         | Program file name   |
| 20:         | Sets the number of points in the waveform.  |
| 30:         | Allocates integer data array for I and Q waveform points.   |
| 40:         | Sets HP BASIC to use degrees for cosine and sine functions.   |
| 50:         | Sets up first loop for I waveform points.   |
| 60:         | Calculate and interleave I waveform points.   |
| 70:         | End of loop   |
| 80:         | Sets up second loop for Q waveform points.  |
| 90:         | Calculate and interleave Q waveform points.   |
| 100:        | End of loop.  |
| 120:        | Calculates number of bytes in I/Q waveform.   |
| 130:        | Opens an IO path to the signal generator using GPIB. 7 is the address of the GPIB card in the computer, and 19 is the address of the signal generator. This IO path is used to send ASCII data to the signal generator. |
| 140:        | Opens an IO path for sending binary data to the signal generator.   |
| 150:        | Creates an ASCII string representation of the number of bytes in the waveform.  |
| 160 to 170: | Finds the number of digits in Nbytes.   |
| 190:        | Sends the first part of the SCPI command, MEM:DATA along with the name of the file, data_file, that will receive the waveform data. The name, data_file, will appear in the signal generator's memory catalog.          |
| 200 to 210: | Sends the rest of the ASCII header.   |



**Program Comments (Continued)**

|             |  |
|-------------|--|
| 230:        | Sends the binary data. Note that PSGb is the binary IO path. |
| 240:        | Sends an End-of-Line to terminate the transmission.          |
| 250 to 260: | Closes the connections to the signal generator.              |
| 290:        | End the program.   |

## Creating and Downloading Waveform Data Using HP BASIC for UNIX

On the documentation CD, this programming example's name is "*hpbasicUx.txt*."

The following program shows you how to download waveforms using HP Basic for UNIX. The code is similar to that shown for HP BASIC for Windows, but there is a formatting difference in line 130 and line 140.

To download into non-volatile memory, replace line 190 with:

```
190 OUTPUT @PSG USING "#,K";":MMEM:DATA ""NVWFM:testfile"", #"
```

As discussed at the beginning of this section, I and Q waveform data is interleaved into one file in 2's compliment form and a marker file is associated with this I/Q waveform file.

In the Output commands, USING "#,K" formats the data. The pound symbol (#) suppresses the automatic EOL (End of Line) output. This allows multiple output commands to be concatenated as if they were a single output. The "K" instructs HP BASIC to output the following numbers or strings in the default format.

```
10 ! RE-SAVE "UNIX_file"
20 Num_points=200
30 ALLOCATE INTEGER Int_array(1:Num_points*2)
40 DEG
50 FOR I=1 TO Num_points*2 STEP 2
60   Int_array(I)=INT(32767*(SIN(I*360/Num_points)))
70 NEXT I
80 FOR I=2 TO Num_points*2 STEP 2
90   Int_array(I)=INT(32767*(COS(I*360/Num_points)))
100 NEXT I
110 PRINT "Data generated "
120 Nbytes=4*Num_points
130 ASSIGN @PSG TO 719;FORMAT ON
140 ASSIGN @PSGb TO 719;FORMAT OFF
150 Nbytes$=VAL$(Nbytes)
160 Ndigits=LEN(Nbytes$)
170 Ndigits$=VAL$(Ndigits)
180 WAIT 1
190 OUTPUT @PSG USING "#,K";":MMEM:DATA ""WF1:data_file"",#"
200 OUTPUT @PSG USING "#,K";Ndigits$
210 OUTPUT @PSG USING "#,K";Nbytes$
220 WAIT 1
230 OUTPUT @PSGb;Int_array(*)
240 WAIT 2
241 OUTPUT @PSG;END
250 ASSIGN @PSG TO *
260 ASSIGN @PSGb TO *
270 PRINT
280 PRINT "**END**"
```

290 END

**Program Comments**

|             |  |
|-------------|--|
| 10:         | Program file name  |
| 20:         | Sets the number of points in the waveform.   |
| 30:         | Allocates integer data array for I and Q waveform points.  |
| 40:         | Sets HP BASIC to use degrees for cosine and sine functions.  |
| 50:         | Sets up first loop for I waveform points.  |
| 60:         | Calculate and interleave I waveform points.  |
| 70:         | End of loop  |
| 80          | Sets up second loop for Q waveform points.   |
| 90:         | Calculate and interleave Q waveform points.  |
| 100:        | End of loop.   |
| 120:        | Calculates number of bytes in I/Q waveform.  |
| 130:        | Opens an IO path to the signal generator using GPIB. 7 is the address of the GPIB card in the computer, and 19 is the address of the signal generator. This IO path is used to send ASCII data to the signal generator.                    |
| 140:        | Opens an IO path for sending binary data to the signal generator.  |
| 150:        | Creates an ASCII string representation of the number of bytes in the waveform.   |
| 160 to 170: | Finds the number of digits in Nbytes.  |
| 190:        | Sends the first part of the SCPI command, MEM:DATA along with the name of the file, <code>data_file</code> , that will receive the waveform data. The name, <code>data_file</code> , will appear in the signal generator's memory catalog. |
| 200 to 210: | Sends the rest of the ASCII header.  |
| 230:        | Sends the binary data. Note that <code>PSGB</code> is the binary IO path.  |
| 240:        | Sends an End-of-Line to terminate the transmission.  |
| 250 to 260: | Closes the connections to the signal generator.  |
| 290:        | End the program.   |

## Creating and Downloading E443xB Waveform Data Using HP BASIC for Windows

On the documentation CD, this programming example's name is "e443xb\_hpbasicWin2.txt."

The following program shows you how to download waveforms using HP Basic for Windows into volatile ARB memory. This program is similar to the following program example as well as the previous examples. The difference between BASIC for UNIX and BASIC for Windows is the way the formatting, for the most significant bit (MSB) on lines 110 and 120, is handled.

To download into non-volatile ARB memory, replace line 160 with:

```
160 OUTPUT @ESG USING "#,K";":MMEM:DATA ""NVARBI:testfile"", #"
```

and replace line 210 with:

```
210 OUTPUT @ESG USING "#,K";":MMEM:DATA ""NVARBQ:testfile"", #"
```

First, the I waveform data is put into an array of integers called Iwfm\_data and the Q waveform data is put into an array of integers called Qwfm\_data. The variable Nbytes is set to equal the number of bytes in the I waveform data. This should be twice the number of integers in Iwfm\_data, since an integer is 2 bytes. Input integers must be between 0 and 16383.

In the Output commands, USING "#,K" formats the data. The pound symbol (#) suppresses the automatic EOL (End of Line) output. This allows multiple output commands to be concatenated as if they were a single output. The "K" instructs HP Basic to output the following numbers or strings in the default format.

```
10 ! RE-SAVE "ARB_IQ_Win_file"
20 Num_points=200
30 ALLOCATE INTEGER Iwfm_data(1:Num_points),Qwfm_data(1:Num_points)
40 DEG
50 FOR I=1 TO Num_points
60 Iwfm_data(I)=INT(8191*(SIN(I*360/Num_points))+8192)
70 Qwfm_data(I)=INT(8191*(COS(I*360/Num_points))+8192)
80 NEXT I
90 PRINT "Data Generated"
100 Nbytes=2*Num_points
110 ASSIGN @Esg TO 719
120 !ASSIGN @Esgb TO 719;FORMAT MSB FIRST
130 Nbytes$=VAL$(Nbytes)
140 Ndigits=LEN(Nbytes$)
150 Ndigits$=VAL$(Ndigits)
160 OUTPUT @Esg USING "#,K";":MMEM:DATA ""ARBI:file_name_1"" ,#"
170 OUTPUT @Esg USING "#,K";Ndigits$
180 OUTPUT @Esg USING "#,K";Nbytes$
190 OUTPUT @Esgb;Iwfm_data(*)
200 OUTPUT @Esg;END
210 OUTPUT @Esg USING "#,K";":MMEM:DATA ""ARBQ:file_name_1"" ,#"
220 OUTPUT @Esg USING "#,K";Ndigits$
230 OUTPUT @Esg USING "#,K";Nbytes$
240 OUTPUT @Esgb;Qwfm_data(*)
```

```

250  OUTPUT @Esg;END
260  ASSIGN @Esg TO *
270  ASSIGN @Esgb TO *
280  PRINT
290  PRINT "**END*"
300  END

```

**Program Comments**

|              |   |
|--------------|---|
| 10:          | Program file name.  |
| 20           | Sets the number of points in the waveform.                                  |
| 30:          | Defines arrays for I and Q waveform points. Sets them to be integer arrays. |
| 40:          | Sets HP BASIC to use degrees for cosine and sine functions.                 |
| 50:          | Sets up loop to calculate waveform points.                                  |
| 60:          | Calculates I waveform points.   |
| 70:          | Calculates Q waveform points.   |
| 80:          | End of loop.  |
| 160 and 210: | The I and Q waveform files have the same name                               |
| 90 to 300:   | See the <a href="#">table on page 92</a> for program comments.              |

## Creating and Downloading E443xB Waveform Data Using HP Basic for UNIX

On the documentation CD, this programming example's name is "*e443xb\_hpbasicUx2.txt*."

The following program shows you how to download waveforms using HP BASIC for UNIX. It is similar to the previous program example. The difference is the way the formatting for the most significant bit (MSB) on lines is handled.

First, the I waveform data is put into an array of integers called *Iwfm\_data* and the Q waveform data is put into an array of integers called *Qwfm\_data*. The variable *Nbytes* is set to equal the number of bytes in the I waveform data. This should be twice the number of integers in *Iwfm\_data*, since an integer is represented 2 bytes. Input integers must be between 0 and 16383.

In the Output commands, USING "#,K" formats the data. The pound symbol (#) suppresses the automatic EOL (End of Line) output. This allows multiple output commands to be concatenated as if they were a single output. The "K" instructs HP BASIC to output the following numbers or strings in the default format.

```
10 ! RE-SAVE "ARB_IQ_file"
20 Num_points=200
30 ALLOCATE INTEGER Iwfm_data(1:Num_points),Qwfm_data(1:Num_points)
40 DEG
50 FOR I=1 TO Num_points
60     Iwfm_data(I)=INT(8191*(SIN(I*360/Num_points))+8192)
70     Qwfm_data(I)=INT(8191*(COS(I*360/Num_points))+8192)
80 NEXT I
90 PRINT "Data Generated"
100 Nbytes=2*Num_points
110 ASSIGN @Esg TO 719;FORMAT ON
120 ASSIGN @Esgb TO 719;FORMAT OFF
130 Nbytes$=VAL$(Nbytes)
140 Ndigits=LEN(Nbytes$)
150 Ndigits$=VAL$(Ndigits)
160 OUTPUT @Esg USING "#,K";":MMEM:DATA " "ARBI:file_name_1"," ,#"
170 OUTPUT @Esg USING "#,K";Ndigits$
180 OUTPUT @Esg USING "#,K";Nbytes$
190 OUTPUT @Esgb;Iwfm_data(*)
200 OUTPUT @Esg;END
210 OUTPUT @Esg USING "#,K";":MMEM:DATA " "ARBQ:file_name_1"," ,#"
220 OUTPUT @Esg USING "#,K";Ndigits$
230 OUTPUT @Esg USING "#,K";Nbytes$
240 OUTPUT @Esgb;Qwfm_data(*)
250 OUTPUT @Esg;END
260 ASSIGN @Esg TO *
270 ASSIGN @Esgb TO *
280 PRINT
290 PRINT "**END**"
```

300 END

**Program Comments**


|              |   |
|--------------|---|
| 10:          | Program file name.  |
| 20           | Sets the number of points in the waveform.                                  |
| 30:          | Defines arrays for I and Q waveform points. Sets them to be integer arrays. |
| 40:          | Sets HP BASIC to use degrees for cosine and sine functions.                 |
| 50:          | Sets up loop to calculate waveform points.                                  |
| 60:          | Calculates I waveform points.   |
| 70:          | Calculates Q waveform points.   |
| 80:          | End of loop.  |
| 160 and 210: | The I and Q waveform files have the same name                               |
| 90 to 300    | See the <a href="#">table on page 95</a> for program comments.              |

## Troubleshooting Waveform Files

| Symptom                        | Possible Cause   |
|--------------------------------|--|
| ERROR 224, Text file busy      | <p>Attempting to download a waveform that has the same name as the waveform currently being played by the signal generator.</p> <p>To solve the problem, either change the name of the waveform being downloaded or turn off the ARB.</p>  |
| ERROR 628, DAC over range      | <p>The amplitude of the signal exceeds the DAC input range. The typical causes are unforeseen overshoot (DAC values within range) or the input values exceed the DAC range.</p> <p>To solve the problem, scale or reduce the DAC input values. For more information, see <a href="#">“DAC Input Values” on page 7</a>.</p>   |
| ERROR 629, File format invalid | <p>The signal generator requires a minimum of 60 samples to build a waveform and the same number of I and Q data points.</p>   |
| ERROR -321, Out of memory      | <p>There is not enough space in the ARB memory for the waveform file being downloaded.</p> <p>To solve the problem, either reduce the file size of the waveform file or delete unnecessary files from ARB memory. Refer to <a href="#">“Waveform Memory” on page 17</a>.</p>   |
| No RF Output                   | <p>The marker RF blanking function may be active. To check for and turn RF blanking off, refer to <a href="#">“Configuring the Pulse/RF Blank (Agilent MXG)” on page 101</a> and <a href="#">“Configuring the Pulse/RF Blank (ESG/PSG)” on page 101</a>. This problem occurs when the file header contains unspecified settings and a previously played waveform used the marker RF blanking function.</p> <p>For more information on the marker functions, see the <i>User's Guide</i>.</p> |
| Undesired output signal        | <p>Check for the following:</p> <ul style="list-style-type: none"> <li>• The data was downloaded in little endian order. See <a href="#">“Little Endian and Big Endian (Byte Order)” on page 5</a> for more information.</li> <li>• The waveform contains an odd number of samples. An odd number of samples can cause waveform discontinuity. See <a href="#">“Waveform Phase Continuity” on page 14</a> for more information.</li> </ul>   |



## Configuring the Pulse/RF Blank (Agilent MXG)




SCPI commands:

```
[ :SOURCE]:RADIO[1]:ARB:MDESTINATION:PULSE NONE|M1|M2|M3|M4
[:SOURCE]:RADIO[1]:ARB:MDESTINATION:PULSE?
```

For details on each key, use the key help. Refer to the signal generator's *Programming Guide* and the *User's Guide*. For additional SCPI command information, refer to the SCPI Command Reference.

## Configuring the Pulse/RF Blank (ESG/PSG)



For details on each key, use the *Key and Data Field Reference*. For additional SCPI command information, refer to the SCPI Command Reference.



## Numerics

2's complement data format, [9](#)

## A

### Agilent

#### e8663b

global settings, configuring, [101](#)  
Pulse/Rf Blank, configuring, [101](#)

#### esg

Download Assistant, [49](#)  
global settings, configuring, [101](#)  
memory allocation, non-volatile memory, [21](#)  
Pulse/Rf Blank, configuring, [101](#)

#### mxg

Download Assistant, [49](#)  
global settings, configuring, [101](#)  
memory allocation, non-volatile memory, [20](#)

#### psg

Download Assistant, [49](#)  
global settings, configuring, [101](#)  
memory allocation, non-volatile memory, [21](#)  
Pulse/Rf Blank, configuring, [101](#)

#### Signal Studio, [49](#)

#### Signal Studio Toolkit, [2](#)

### ARB waveform file downloads

#### data requirements

waveform, [3](#)

download utilities, [2, 49](#)

## B

### Baseband Studio

for Waveform Capture and Playback, [15](#)

### big endian and little endian (byte order)

interleaving and byte swapping, [37](#)

### big-endian

changing byte order, [6](#)  
example, programming, [85](#)

### bits and bytes, [4](#)

### byte order

byte swapping, [6](#)  
changing byte order, [6](#)  
interleaving I/Q data, [37](#)

## C

### C++

programming examples, [53](#)

### creating waveform data

C++, using, [33](#)  
saving to a text file for review, [36](#)

### creating waveform files

overview, [1](#)

## D

DAC input values, [7](#)

### data

encryption, [24, 25](#)  
format, e443xb signal generator, [50](#)  
requirements, waveform, [3](#)

decryption, [24, 25](#)

### download

#### utilities

Agilent Signal Studio, Toolkit, [2](#)  
differences, [49](#)  
Download Assistant, [2](#)  
IntuiLink for signal generators, [2](#)

#### waveform data

advanced programming languages, [43](#)  
commands, [24](#)  
e443xb signal generator files, [7, 50](#)  
encrypted files for extraction, [29](#)  
encrypted files for no extraction, [28](#)  
FTP procedures, [31](#)  
memory locations, [25](#)  
overview, [1, 40](#)  
simulation software, [40](#)  
unencrypted files for extraction, [28](#)  
unencrypted files for no extraction, [27](#)

### downloading

C++, using, [53](#)  
HP Basic, [91](#)  
MATLAB, [81](#)  
Visual Basic, [88](#)

## E

### e443xb

#### files

downloading, [50, 51](#)  
formatting, [7, 50](#)  
programming examples, [71](#)  
storing, [50](#)

programming examples, [91](#)

### encryption

#### downloading

for extraction, [29](#)  
for no extraction, [28](#)  
extracting waveform data, [29](#)

I/Q files, [24](#)

I/Q files, agilent mxg (only), [25](#)

#### securewave directory

agilent mxg (only), [25](#)  
esg, [24](#)  
psg, [24](#)

waveform data, [24](#)

even number of samples, [13](#)

example programs *See* programming examples, [53](#)

---

# Index

## F

### files

- decryption, [24, 25](#)
- download utilities, [49](#)
- encryption, [24](#)
- encryption, agilent mxg (only), [25](#)
- extraction commands and file paths, [27](#)
- header information, [11, 24, 25](#)
- transfer methods, [26](#)
- waveform structure, [11](#)

### FTP

- commands for downloading and extracting files, [28–30](#)
- downloading and extracting files, commands, [28–29](#)
- methods, [26](#)
- procedures for downloading files, [31](#)
- web server procedure, [32](#)

## G

### global settings

- Agilent mxg, [101](#)
- e8663b, [101](#)
- esg, [101](#)
- psg, [101](#)

## H

### hexadecimal data, [85](#)

### HP Basic

- programming examples, [91](#)

## I

### I/Q data

- creating with advanced programming languages, [34](#)
- encryption, [24](#)
- encryption, agilent mxg (only), [25](#)
- interleaving
  - big endian and little endian, [37](#)
  - byte swapping, [37](#)
  - little endian, byte swapping, [37](#)
  - waveform data, creating, [10](#)
- memory locations, [19, 38](#)
- saving to a text file for review, [36](#)
- scaling, [8](#)
- waveform structure, [13](#)
- input values, DAC, [7](#)
- interleaving, *See* I/Q data, [10](#)
- IntuiLink for signal generators, [6, 49](#)

## L

### LAN

- establishing a connection, [41, 43](#)
- loading waveforms, [46](#)
- LSB, [4](#)

LSB/MSB, [85](#)

## M

marker file, [11, 24, 25](#)

### MATLAB

- download utility, [49](#)
- downloading data, [40](#)
- programming examples, [78](#)

### memory

- allocation, [20](#)
- defined, [17](#)
- locations, [17](#)
- non-volatile (NVWFM), [24, 25](#)
- size, [22](#)
- volatile (WFM1), [25](#)

MSB, [4](#)

## N

### n5181a/82a

- Pulse/RF Blank configuring, [101](#)

### non-volatile memory

- memory allocation
  - Agilent mxg, [20](#)
  - esg, [21](#)
  - psg, [21](#)
- securewave directory, [25](#)
- waveform, [17](#)

## P

PC, [85](#)

### phase discontinuity

- avoiding, [14](#)
  - Baseband Studio, for Waveform Capture and Playback, [15](#)
- samples, [15](#)
- waveform, [14](#)

phase distortion, [14](#)

playing waveforms, [46](#)

### programming

- creating waveform data, [33](#)
- downloading waveform data, [40](#)
- little endian order, byte swapping, [37](#)

### programming examples

- C++, [53](#)
- e443xb
  - files, [71](#)
- e443xb files, [91](#)
- HP Basic, [91](#)
- introduction, [53](#)
- MATLAB, [78](#)
- Visual Basic, [85, 88](#)
- Pulse/RF Blank
  - e8663b, setting, [101](#)

esg, setting, [101](#)  
 n5181a/82a, setting, [101](#)  
 psg, setting, [101](#)

## R

requirements, waveform data, [3](#)

## S

samples

even number, [13](#)  
 waveform, [13](#)

scaling I/Q data, [8](#)

SCPI

file transfer methods, [26](#)

SCPI commands

command line structure, [26](#)  
 download e443xb files, [51](#)  
 encrypted files, [28, 29](#)  
 extraction, [24, 27, 28, 29](#)  
 no extraction, [27, 28](#)  
 unencrypted files, [27, 28](#)

securewave directory

decryption, file, [24, 25](#)  
 downloading encrypted files, [29](#)  
 downloads, file, [24, 25](#)  
 encryption, file, [24, 25](#)  
 extracting waveform data, [29](#)  
 extraction, file, [24, 25](#)

sequences

waveforms, building, [48](#)

setting

Pulse/RF Blank  
 e8663b, [101](#)  
 esg, [101](#)  
 n5181a/82a, [101](#)  
 psg, [101](#)

signal generator

Download Assistant, [49](#)

Signal Studio Toolkit, [2, 49](#)

simulation software, [40](#)

## T

Toolkit, Signal Studio, [2, 49](#)

## U

unencrypted files

downloading for extraction, [28](#)  
 downloading for no extraction, [27](#)

## V

verifying waveforms, [46](#)

VISA

library, [85](#)

Visual Basic

programming examples, [85](#)

volatile memory

file, decryption, [24, 25](#)  
 file, encryption, [24, 25](#)  
 memory allocation, [20](#)  
 securewave directory, [24, 25](#)  
 memory, volatile (WFM1), [24](#)  
 waveform, [17](#)

## W

waveform data

2's complement data format, [9](#)

bits and bytes, [4](#)

byte order, [6](#)

byte swapping, [6](#)

commands for downloading and extracting, [24–32](#)  
 creating, [33](#)

DAC input values, [7](#)

data requirements, [3](#)

encryption, [24–29](#)

explained, [4](#)

extracting, [24, 28–29](#)

I and Q interleaving, [10](#)

LSB and MSB, [4](#)

saving to a text file for review, [36](#)

waveform downloads

advanced programming languages, using, [43](#)

download utilities, using, [49](#)

HP BASIC, using, [91–98](#)

memory, [17](#)

allocation, [20](#)

size, [22](#)

volatile and non-volatile, [17](#)

samples, [13](#)

simulation software, using, [40](#)

structure, [13](#)

troubleshooting files, [100](#)

using advanced programming languages, [43](#)

with Visual Basic 6.0, [88](#)

waveform files

creating, [1](#)

downloading, [1](#)

waveform generation

C++, [53](#)

HP Basic, using, [91](#)

MATLAB, using, [78](#)

Visual Basic 6.0, using, [85](#)

waveforms

loading, [46](#)

playing, [46](#)

sequences, building, [48](#)

---

# Index

verifying, [46](#)  
WriteIEEEBlock, [88](#)