# TPRO/TSAT-PCI SYNCHRONIZABLE TIMECODE GENERATOR with UNIVERSAL PCI BUS INTERFACE

Windows Driver Application Programmer's Guide

95 Methodist Hill Drive Rochester, NY 14623

Phone: US +1.585.321.5800 Fax: US +1.585.321.5219



www.spectracomcorp.com
Part Number 1186-5002-0050
Manual Revision C
December 2010

Copyright © 2009 Spectracom Corporation. The contents of this publication may not be reproduced in any form without the written permission of Spectracom Corporation. Printed in USA.
Specifications subject to change or improvement without notice.
Spectracom, NetClock, Ageless, TimeGuard, TimeBurst, TimeTap, LineTap, MultiTap, VersaTap, and Legally Traceable Time are Spectracom registered trademarks. All other products are identified by trademarks of their respective companies or organizations. All rights reserved.

# SPECTRACOM LIMITED WARRANTY

#### LIMITED WARRANTY

Spectracom warrants each new product manufactured and sold by it to be free from defects in software, material, workmanship, and construction, except for batteries, fuses, or other material normally consumed in operation that may be contained therein AND AS NOTED BELOW, for five years after shipment to the original purchaser (which period is referred to as the "warranty period"). This warranty shall not apply if the product is used contrary to the instructions in its manual or is otherwise subjected to misuse, abnormal operations, accident, lightning or transient surge, repairs or modifications not performed by Spectracom.

The GPS receiver is warranted for one year from date of shipment and subject to the exceptions listed above. The power adaptor, if supplied, is warranted for one year from date of shipment and subject to the exceptions listed above.

THE ANALOG CLOCKS ARE WARRANTED FOR ONE YEAR FROM DATE OF SHIPMENT AND SUBJECT TO THE EXCEPTIONS LISTED ABOVE.

THE TIMECODE READER/GENERATORS ARE WARRANTED FOR ONE YEAR FROM DATE OF SHIPMENT AND SUBJECT TO THE EXCEPTIONS LISTED ABOVE.

The Rubidium oscillator, if supplied, is warranted for two years from date of shipment and subject to the exceptions listed above.

All other items and pieces of equipment not specified above, including the antenna unit, antenna surge suppressor and antenna pre-amplifier are warranted for 5 years, subject to the exceptions listed above.

#### WARRANTY CLAIMS

Spectracom's obligation under this warranty is limited to in-factory service and repair, at Spectracom's option, of the product or the component thereof, which is found to be defective. If in Spectracom's judgment the defective condition in a Spectracom product is for a cause listed above for which Spectracom is not responsible, Spectracom will make the repairs or replacement of components and charge its then current price, which buyer agrees to pay.

Spectracom shall not have any warranty obligations if the procedure for warranty claims is not followed. Users must notify Spectracom of the claim with full information as to the claimed defect. Spectracom products shall not be returned unless a return authorization number is issued by Spectracom.

Spectracom products must be returned with the description of the claimed defect and identification of the individual to be contacted if additional information is needed. Spectracom products must be returned properly packed with transportation charges prepaid.

Shipping expense: Expenses incurred for shipping Spectracom products to and from Spectracom (including international customs fees) shall be paid for by the customer, with the following exception. For customers located within the United States, any product repaired by Spectracom under a "warranty repair" will be shipped back to the customer at Spectracom's expense unless special/faster delivery is requested by customer.

Spectracom highly recommends that prior to returning equipment for service work, our technical support department be contacted to provide trouble shooting assistance while the equipment is still installed. If equipment is returned without first contacting the support department and "no problems are found" during the repair work, an evaluation fee may be charged.

EXCEPT FOR THE LIMITED WARRANTY STATED ABOVE, SPECTRACOM DISCLAIMS ALL WARRANTIES OF ANY KIND WITH REGARD TO SPECTRACOM PRODUCTS OR OTHER MATERIALS PROVIDED BY SPECTRACOM, INCLUDING WITHOUT LIMITATION ANY IMPLIED WARRANTY OR MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE.

Spectracom shall have no liability or responsibility to the original customer or any other party with respect to any liability, loss, or damage caused directly or indirectly by any Spectracom product, material, or software sold or provided by Spectracom, replacement parts or units, or services provided, including but not limited to any interruption of service, excess charges resulting from malfunctions of hardware or software, loss of business or anticipatory profits resulting from the use or operation of the Spectracom product or software, whatsoever or howsoever caused. In no event shall Spectracom be liable for any direct, indirect, special or consequential damages whether the claims are grounded in contract, tort (including negligence), or strict liability.

#### EXTENDED WARRANTY COVERAGE

Extended warranties can be purchased for additional periods beyond the standard five-year warranty. Contact Spectracom no later than the last year of the standard five-year warranty for extended coverage.

# Table of Contents

1	OVERVIEW	
2	INSTALLING THE DRIVER	2-1
2.1	Running the TPRO/TSAT Control Utility	
2.2	Clock Daemon Utilities	
2.3	Example Executables and Source Code	2-4
3	INTERFACE TO THE WINDOWS API	3-1
3.1	Header File	3-1
3.2	TPRO API — Routine Descriptions	

# 1 Overview

### 1.1 General

The TPRO/TSAT PCI Windows Driver provides an interface between the PCI board and applications developed for 32-bit or 64-bit Windows™ operating systems. In addition to the interface library, a Control Utility program, Time Daemon Utility and example programs with source code are provided. The TPRO/TSAT PCI Windows Driver has been tested for compatibility with the following versions of Windows:

- Windows 2000
- Windows XP
- Windows Server 2003
- Windows Vista
- Windows Server 2008 & R2
- Windows 7

The 32-bit library file and DLL (tpro.lib & tpro.dll) can be found in the "KSI\Dev" directory under "Program Files". Similarly, the 64-bit versions of the same files are located in the "KSI\Dev64" directory under "Program Files (x86)" on 64-bit operating systems.

#### 1.2 Features

The TPRO/TSAT PCI Windows Driver includes the following:

- Interface API library that accesses all of the PCI board features
- Example programs with source code, utilizing the API library
- A Control Utility that can be used to retrieve data from the card and/or modify card settings
- A Time Daemon tray Utility and Time Daemon service that query the TPRO/TSAT-PCI card and sets the computer's system clock at a user-defined interval

# 2 Installing the Driver

**NOTE:** If your system is equipped with the TPRO-TSAT PCI software driver, it must be uninstalled before installing the new, updated driver. To uninstall the driver:

- 1. Go to "Control Panel", "Add/Remove Programs"
- 2. Remove "TPRO-TSAT PCI"

To install the driver, perform the following steps:

- 1. Install the TPRO/TSAT-PCI card in a vacant slot on the computer to be used.
- 2. Switch on the PC power. Once the PC is running, Windows may prompt you to install the newly found hardware. Disregard and cancel this dialog box.
- 3. Insert the CD with the TPRO/TSAT-PCI driver into the CD-ROM drive and follow the automated installation procedure. If Auto-Run is disabled, manually install the driver by running "setup.exe" from the Windows driver folder located on the CD.
- 4. Once the driver installation has completed, the computer must be rebooted for the changes to take effect.

The following folders are created in the Program Files folder under "KSI" when the driver is installed:

- control contains the Clock Daemon utilities, daemon.ini, and Control utility
- dev contains "tpro.h" and "tpro.dll" files needed for application software development
- documentation contains PCI user manual and application programmer's guide
- drivers contains all Windows driver files
- examples contains example executables and source code for each TPRO API

# 2.1 Running the TPRO/TSAT Control Utility

- 1. From the Windows Start menu, select the "Programs" folder.
- 2. Select the "Spectracom\PCI" folder.
- 3. Select the "TPRO-TSAT Control Utility" program.



### 2.2 Clock Daemon Utilities


Two clock daemon utilities are provided that can be used to set the computer's system clock: "Clock Daemon.exe" and "ClockDaemonService.exe". Both will query the TPRO/TSAT PCI and set the system clock on a periodic basis.

**NOTE:** If the PCI board is not synchronized to an external reference, the system clock will not be set.

#### Clock Daemon.exe:

When the driver is installed, a shortcut to "Clock Daemon.exe" is automatically added to the user's Startup folder and will run automatically from the system tray when the computer boots up.

A small icon — — will show up in the system tray. Double click on that icon to display a window. A shortcut can also be found in the "Start/Spectracom Corp/PCI" Windows Start menu.



Device Name: Will select which board you want to use as a time source.

The default is "tpropci0".

Update Interval: Controls how often the PCI board time will be gueried.

The default is "300" seconds.

To enable the clock daemon on startup, make sure the "Enable On Startup" checkbox has been selected before starting the program.

#### ClockDaemonService.exe:

"Clock DaemonService.exe" will set the computer's system clock as does the "Clock Daemon.exe", but it will run as a Windows service. It will run automatically at boot-up and does not need to be added to the user's Startup folder. The program can be found in the folder C:\Program Files\KSI\control and a shortcut can be found in the "Start/Spectracom Corp/PCI" Windows Start menu.

**NOTE:** Do not attempt to run "Clock DaemonService.exe" and "Clock Daemon.exe" at the same time. When running the Clock Daemon Service, stop "Clock Daemon.exe" and remove it from the Startup folder.

Executing ClockDaemonService.exe from the command prompt stops, removes, installs, and starts the "Clock Daemon" service. The service startup type defaults to automatic. To remove the "Clock Daemon" service, run ClockDaemonService.exe from a command prompt with the -r option (ClockDaemonService.exe -r).

The controls for device name and update interval are setup by the "daemon.ini" located in the folder C:\Program Files\KSI\control.

## 2.3 Example Executables and Source Code

The driver package includes folders with example programs to interface to the board. The source code and make files for the example programs are included. All of the example programs were compiled using **Visual Studio 2005**. All example programs are 32-bit applications.

To see usage help for any example program, execute the program with no parameters:

> HW GetTime.exe

# 3 Interface to the Windows API

#### 3.1 Header File

The following is the "TPRO.H" API Interface Header File.

```
/*********************
* *
** Module:
              tpro.h
             08/08/2007
** Purpose: Contains structures and definions used to interface
               with the TPRO-PCI or TSAT-PCI API. Applications
               that access the API should include this header.
**
** Copyright(C) 2007 Spectracom Corporation. All Rights Reserved
*****************
** Modifications:
* *
               08/08/2007 Multi-user enablement
****************************
#ifndef defined TPRO
#define defined TPRO
#pragma pack(8)
\begin{array}{ll} \texttt{\#ifdef} & \underline{\quad} \texttt{cplusplus} \\ \texttt{extern} & \underline{\quad} \texttt{"C"} \end{array} \\ \\ \end{array}
#endif
#define DLL EXPORT declspec(dllexport)
/*****************************
                     SUPPORT CONSTANTS
    Heartbeat constants
                             // signal type for PCI card
                    (0xE5)
#define SIG_PULSE
#define SIG_SQUARE
                     (0xE7)
                                    // signal type for PCI card
#define SIG NO JAM
                     (0)
                                   // output type for PCI card
#define SIG JAM
                                   // output type for PCI card
                     (1)
#define HEART NORMAL
                                   // signal type for CPCI card
#define HEART INVERT
                     (8)
                                   // signal type for CPCI card
#define HEART DISABLE (0)
                                   // output type for CPCI card
#define HEART ENABLE (4)
                                   // output type for CPCI card
#define CLK_10MHZ
#define CLK_3MHZ
#define CLK_1MHZ
#define CLK_1KHZ
                     (0)
                                   // clock frequency for CPCI board
                                   // clock frequency for CPCI board
                     (1)
                                   // clock frequency for CPCI board
                     (2)
                     (3)
                                   // clock frequency for CPCI board
```

```
** Length of firmware rev string
#define TPRO FIRMWARE LENGTH (4)
** Length of driver version string "XX.YY"
** (not including termination)
*/
#define TPRO_DRV_VERSION_LENGTH ( 5 )
*** Match constants
#define MATCH_TIME_START (0)  // start time
#define MATCH_TIME_STOP (1)  // stop time
** board sync options
*/
#define TPRO_DISABLE_SYNC ( 0x0 ) /* freewheel */
#define TPRO_ENABLE_SYNC ( 0x1 ) /* sync to input */
#define TPRO_SYNC_STAT_FREE ( 0x0 ) /* sync is freewheel */
*** Oscillator frequencies - for Compact PCI Card Only
#define OSC OUT OFF
#define OSC_OUT_1KHZ
                  (1)
#define OSC_OUT_1MHZ
#define OSC_OUT_5MHZ
                  (2)
                  (3)
#define OSC OUT 10MHZ
                  (4)
/******************************
                 OBJECTS
***********************
/*_____
              TPRO BOARD OBJECT
_____*/
typedef struct TPRO BoardObj
{ /*-----
 void *hDevice;
 unsigned short options;
 unsigned char slotPosition;
} /*----
TPRO BoardObj;
/*-----
             TPRO ALTITUDE OBJECT
_____*
typedef struct TPRO AltObj
{ /*----*/
                        /*-- meters -----*/
float meters;
} /*-----*/
TPRO AltObj;
TPRO DATE OBJECT
______/
typedef struct TPRO_DateObj
{ /*----*/
 unsigned short year;
                            /*-- year -----*/
```

```
unsigned char month;
                             /*-- month -----*/
 unsigned char day;
                             /*-- day -----*/
TPRO DateObj;
TPRO LONGITUDE/LATTITUDE OBJECT
typedef struct TPRO LongLat
{    /*-----*/
                      /*-- degrees -----*/
/*-- minutes -----*/
 unsigned short degrees;
unsigned short degrees; /*-- degrees ------*/
float minutes; /*-- minutes ------*/
} /*-------*/
TPRO LongObj, TPRO LatObj;
/*-----
               TPRO MATCH OBJECT
========*/
typedef struct TPRO_MatchObj

      unsigned char unsigned char double
      matchType;
      /*-- start/stop time ----*/

      double
      seconds;
      /*-- seconds ------*/

      unsigned char minutes;
      /*-- minutes ------*/

      unsigned char hours;
      /*-- hours ------*/

      unsigned short days;
      /*-- days -------/

TPRO MatchObj;
        TPRO SATINFO OBJECT
______/
typedef struct TPRO SatObj
{ /*----*/
 unsigned char satsTracked; /*-- num sats tracked ----*/
                             /*-- num sats in view ----*/
 unsigned char satsView;
TPRO SatObj;
/*-----
           TPRO HEARTBEAT OBJECT
typedef struct TPRO HeartObj
TPRO HeartObj;
               TPRO TIME OBJECT
typedef struct TPRO TimeObj
/*-- seconds -----*/
/*-- seconds -----*/
 double secsDouble;
 unsigned char seconds;
                           /*-- minutes ------*/
/*-- hours ------*/
/*-- days -----*/
 unsigned char minutes;
 unsigned char hours;
 unsigned short days;
```

```
unsigned short year;
                                       /*-- year for CPCI board -*/
  unsigned short sync;
                                      /*--sync flags (0x91xx boards -*/
TPRO TimeObj;
/*-----
                      TPRO WAIT OBJECT
_____*/
typedef struct TPRO WaitObj
 {-/*-----*/
                                                 /*-- # ticks to wait ----*/
  unsigned int ticks;
                                                /*-- seconds -----*/
  double
                seconds;
                                                /*-- minutes -----*/
  unsigned char minutes;
  unsigned char hours;
unsigned short days;
                                                 /*-- hours -----*/
                                                 /*-- days -----*/
                                                 /*-- year for cPCI card --*/
  unsigned short year;
  unsigned char month;
unsigned char day;
                                                 /*-- month for cPCI card -*/
                                                 /*-- day for cPCI card ---*/
} /*-----*/
TPRO_WaitObj;
               TPRO MEM OBJECT FOR PEEK/POKE
typedef struct TPRO MemObj
unsigned short offset;
  unsigned long value;
 } /*-----*/
TPRO MemObj;
ERROR CODES
#define TPRO_SUCCESS (0) // success
#define TPRO_HANDLE_ERR (1) // error creating handle to device
#define TPRO_OBJECT_ERR (2) // error creating device object
#define TPRO_CLOSE_HANDLE_ERR (3) // error closing device handle
#define TPRO_DEVICE_NOT_OPEN_ERR (4) // tpro device was not opened
#define TPRO_INVALID_BOARD_TYPE_ERR (5) // function is not available for board type
#define TPRO_FREQ_ERR (6) // invalid frequency
#define TPRO_YEAR_PARM_ERR (7) // invalid year parameter
#define TPRO_DAY_PARM_ERR (8) // invalid day parameter
#define TPRO_HOUR_PARM_ERR (9) // invalid hour parameter
#define TPRO_HOUR_PARM_ERR (10) // invalid minutes parameter
#define TPRO_SEC_PARM_ERR (11) // invalid seconds parameter
#define TPRO_DELAY_PARM_ERR (12) // invalid delay factor
#define TPRO_TIMEOUT_ERR (13) // device timed out
#define TPRO_COMM_ERR (14) // error communicating with driver
#define TPRO_DEV_BUSY (15) // The driver is currently busy executing a request
from a different user
from a different user
/***********************
                     PUBLIC ROUTINE PROTOTYPES
*************************
DLL EXPORT
unsigned char TPRO open
                                      (TPRO BoardObj **hnd, char *deviceName);
DLL EXPORT
unsigned char TPRO close (TPRO BoardObj *hnd);
DLL EXPORT
```

```
unsigned char TPRO flushFIFO
                                 (TPRO BoardObj *hnd);
DLL EXPORT
unsigned char TPRO getAltitude
                                    (TPRO BoardObj *hnd, TPRO AltObj *Altp);
DLL EXPORT
unsigned char TPRO getDate
                                    (TPRO BoardObj *hnd, TPRO DateObj *Datep);
DLL EXPORT
unsigned char TPRO getDriver
                                  (TPRO BoardObj *hnd, char *driver);
DLL EXPORT
                                          (TPRO BoardObj *hnd, char *firmware);
unsigned char TPRO getFirmware
DLL EXPORT
unsigned char TPRO getFPGA
                                  (TPRO BoardObj *hnd, char *fpga);
DLL EXPORT
unsigned char TPRO getLatitude
                                    (TPRO BoardObj *hnd, TPRO LatObj *Latp);
DLL EXPORT
                                    (TPRO BoardObj *hnd, TPRO LongObj *Longp);
unsigned char TPRO getLongitude
DLL EXPORT
unsigned char TPRO getSatInfo
                                   (TPRO BoardObj *hnd, TPRO SatObj *Satp);
DLL EXPORT
unsigned char TPRO getTime
                                  (TPRO BoardObj *hnd, TPRO TimeObj *Timep);
DLL EXPORT
unsigned char TPRO resetFirmware
                                    (TPRO BoardObj *hnd);
DLL EXPORT
unsigned char TPRO setHeartbeat
                                    (TPRO BoardObj *hnd, TPRO HeartObj *Heartp);
DLL EXPORT
                                    (TPRO BoardObj *hnd, TPRO MatchObj *Matchp);
unsigned char TPRO setMatchTime
DLL EXPORT
                                    (TPRO BoardObj *hnd, unsigned char *freq);
unsigned char TPRO_setOscillator
unsigned char TPRO setPropDelayCorr (TPRO BoardObj *hnd, int *us);
DLL EXPORT
                                    (TPRO BoardObj *hnd, TPRO TimeObj *Timep);
unsigned char TPRO_setTime
DLL EXPORT
                                   (TPRO BoardObj *hnd, unsigned short *yr);
unsigned char TPRO setYear
DLL EXPORT
unsigned char TPRO simEvent
                                 (TPRO BoardObj *hnd);
DLL EXPORT
unsigned char TPRO synchControl
                                    (TPRO BoardObj *hnd, unsigned char *enbp);
DLL EXPORT
unsigned char TPRO_synchStatus
                                    (TPRO BoardObj *hnd, unsigned char *status);
DLL EXPORT
unsigned char TPRO waitEvent
                                    (TPRO BoardObj *hnd, TPRO WaitObj *waitp);
DLL EXPORT
                                    (TPRO BoardObj *hnd, unsigned int *ticks);
unsigned char TPRO waitHeartbeat
DLL EXPORT
unsigned char TPRO waitMatch
                                    (TPRO BoardObj *hnd, unsigned int *ticks);
DLL EXPORT
                                          (TPRO_BoardObj *hnd, TPRO MemObj *Mem);
unsigned char TPRO peek
```

## 3.2 TPRO API — Routine Descriptions

The TPRO-PCI driver permits overlapping use of the TPRO-waitXXX routines and other device access routines.

**NOTE:** Simultaneous access to the device requires multiple open device handles. (If an application requires access to the device driver from two different threads, each thread must have its own device handle.)

#### 3.2.1.1.1 TPRO open

```
unsigned char TPRO open (TPRO BoardObj **hnd, char *deviceName);
```

This routine allocates a TPRO\_BoardObj obect, sets a handle to the TPRO/TSAT, and sets the driver firmware, fpga revision (if applicable), and the driver revision strings.

#### 3.2.1.1.2 TPRO close

```
unsigned char TPRO close (TPRO BoardObj *hnd);
```

This routine frees the allocated board object and closes the handle to the TPRO/TSAT device.

```
Arguments: Pointer to TPRO_BoardObj

Returns: TPRO_CLOSE_HANDLE_ERR - error closing handle to device TPRO_DEVICE_NOT_OPEN - device is not open TPRO_SUCCESS - success
```

# 3.2.1.1.3 TPRO getAltitude

```
unsigned char TPRO_getAltitude (TPRO_BoardObj *hnd, TPRO_AltObj *Altp);
```

This routine retrieves the altitude information from the TSAT board. Altitude distance is in meters.

```
Arguments: Pointer to TPRO_BoardObj
Pointer to TPRO_AltObj

Returns: TPRO_INVALID_BOARD_TYPE_ERR - invalid board type for function
TPRO_COMM_ERR - error communicating with driver
TPRO_SUCCESS - success
```

#### 3.2.1.1.4 TPRO getDate

```
unsigned char TPRO getDate (TPRO BoardObj *hnd, TPRO DateObj *Datep);
```

This routine retrieves the current date from the TPRO/TSAT board. The date is in Gregorian Format.

Arguments: Pointer to TPRO\_BoardObj

Pointer to TPRO DateObj

Returns: TPRO\_INVALID\_BOARD\_TYPE\_ERR - invalid board type for function

TPRO\_COMM\_ERR - error communicating with driver

TPRO SUCCESS - success

#### 3.2.1.1.5 TPRO\_getLatitude

```
unsigned char TPRO_getLattitude(TPRO_BoardObj *hnd, TPRO_LatObj *Latp);
```

This routine retrieves the latitude information from the TSAT device.

Arguments: Pointer to TPRO BoardObj

Pointer to TPRO LatObj

Returns: TPRO INVALID BOARD TYPE ERR - invalid board type for function

TPRO\_COMM\_ERR - error communicating with driver

TPRO SUCCESS - success

## 3.2.1.1.6 TPRO getLongitude

unsigned char TPRO getLongitude(TPRO BoardObj \*hnd, TPRO LongObj \*Longp);

This routine retrieves the longitude information from the TSAT device.

Arguments: Pointer to the TPRO\_BoardObj

Pointer to the TPRO LongObj

Returns: TPRO INVALID BOARD TYPE ERR - invalid board type for function

TPRO\_COMM\_ERR - error communicating with driver

TPRO SUCCESS - success

#### 3.2.1.1.7 TPRO getSatInfo

```
unsigned char TPRO getSatInfo(TPRO BoardObj *hnd, TPRO SatObj *Satp);
```

This routine retrieves the number of satellites tracked from the TSAT device.

```
Arguments: Pointer to the TPRO BoardObj
           Pointer to the TPRO SatObj
```

Returns: TPRO\_INVALID\_BOARD\_TYPE\_ERR - invalid board type for function

TPRO\_COMM\_ERR - error communicating with driver

TPRO SUCCESS - success

#### 3.2.1.1.8 TPRO getTime

```
unsigned char TPRO getTime(TPRO BoardObj *hnd, TPRO TimeObj *Timep);
```

This routine retrieves the current time from the TPRO/TSAT device. The seconds value is received as type double.

```
Arguments: Pointer to the TPRO BoardObj
```

Pointer to the TPRO TimeObj

TPRO\_COMM\_ERR - error communicating with driver TPRO\_SUCCESS - success Returns:

#### 3.2.1.1.9

### 3.2.1.1.10 TPRO resetFirmware

```
unsigned char TPRO resetFirmware(TPRO BoardObj *hnd);
```

This routine resets the firmware programmed on the TPRO/TSAT device. This function is for troubleshooting purposes only and should not be used in the main application.

```
Arguments: Pointer to the TPRO BoardObj
```

Returns: - error communicating with driver TPRO\_COMM\_ERR

TPRO SUCCESS - success

#### 3.2.1.1.11 TPRO setHeartbeat

```
unsigned char TPRO_setHeartbeat(TPRO_BoardObj *hnd, TPRO_HeartObj *Heartp);
```

This routine controls the hearbeat output. The heartbeat output may be a square wave or pulse at various frequencies.

```
Arguments: Pointer to the TPRO_BoardObj
Pointer to the TPRO_HeartObj

Returns: TPRO_FREQ_ERR - invalid frequency value
TPRO_COMM_ERR - error communicating with driver
TPRO_SUCCESS - success
```

#### 3.2.1.1.12 TPRO setMatchTime

```
unsigned char TPRO setMatchTime(TPRO BoardObj *hnd, TPRO MatchObj *Matchp);
```

This routine drives the match output line high (start time) or low (stop time) when the desired time is met.

```
Arguments: Pointer to the TPRO_BoardObj
Pointer to the TPRO_MatchObj

Returns: TPRO_DAY_PARM_ERR - invalid days parameter (must be 0-366)
TPRO_HOUR_PARM_ERR - invalid hours parameter (must be 0 - 23)
TPRO_MIN_PARM_ERR - invalid minutes parameter (must be 0 - 59)
TPRO_SEC_PARM_ERR - invalid seconds parameter (must be 0 - 69)
TPRO_COMM_ERR - error communicating with driver
TPRO_SUCCESS - success
```

### 3.2.1.1.13 TPRO setPropDelayCorr

```
unsigned char TPRO setPropDelayCorr (TPRO BoardObj *hnd, int *us);
```

This routine sets the propagation delay correction factor.

```
Arguments: Pointer to the TPRO_BoardObj
Pointer to correction factor in microseconds

Returns: TPRO_DELAY_PARM_ERR - invalid propagation delay factor
TPRO_COMM_ERR - error communicating with driver
TPRO_SUCCESS - success
```

#### 3.2.1.1.14 TPRO setTime

```
unsigned char TPRO_setTime(TPRO_BoardObj *hnd, TPRO_TimeObj *Timep);
```

This routine sets the time on the on-board clock of the TPRO/TSAT device. If the board is synchronized to a GPS antenna this value will not be accepted.

#### 3.2.1.1.15 *TPRO\_setYear*

```
unsigned char TPRO_setYear(TPRO_BoardObj *hnd, unsigned short *yr);
```

This routine programs the TPRO/TSAT device with the desired year. If the board is synchronized to a GPS antenna this value will not be accepted.

```
Arguments: Pointer to the TPRO_BoardObj
Pointer to the desired year

Returns: TPRO_INVALID_BOARD_TYPE_ERR - invalid board type for function
TPRO_COMM_ERR - error communicating with driver
TPRO_SUCCESS - success
```

#### 3.2.1.1.16 *TPRO\_simEvent*

```
unsigned char TPRO simEvent(TPRO BoardObj *hnd);
```

This routine simulates an external time tag event.

```
Arguments: Pointer to the TPRO_BoardObj

Returns: TPRO_COMM_ERR - error communicating with driver TPRO_SUCCESS - success
```

#### 3.2.1.1.17 TPRO synchControl

```
unsigned char TPRO synchControl(TPRO BoardObj *hnd, unsigned char *enbp);
```

This routine commands the TPRO/TSAT device to synchronize to input or freewheel. This distinction is made using the enable argument. If the enable argument is (0) the clock will freewheel, otherwise it will synchronize to input. When disabling synchronization (freewheeling), the device will continue to synchronize until the time is set.

```
Arguments: Pointer to the TPRO_BoardObj
Pointer to the synch enable

Returns: TPRO_COMM_ERR - error communicating with driver
TPRO_SUCCESS - success
```

#### 3.2.1.1.18 TPRO\_synchStatus

```
unsigned char TPRO synchStatus(TPRO BoardObj *hnd, unsigned char *status);
```

This routine reports the synchronization status of the TPRO/TSAT device. When status is equal to zero, the device is freewheeling. Otherwise the device is synchronized to its input.

```
Arguments: Pointer to the TPRO_BoardObj
Pointer to the synch status variable

Returns: TPRO_COMM_ERR - error communicating with driver
TPRO_SUCCESS - success
```

### 3.2.1.1.19 TPRO\_waitEvent

```
unsigned char TPRO waitEvent(TPRO BoardObj *hnd, TPRO WaitObj*waitp);
```

This routine will report the time an external event was detected on the Time Tag Input pin. The routine will block for a given number of ticks (in milliseconds) until an event occurs or the timeout period has been reached.

```
Arguments: Pointer to the TPRO_BoardObj
Pointer to wait time

Returns: TPRO_TIMEOUT_ERR - routine has timed-out
TPRO_COMM_ERR - error communicating with driver
TPRO_SUCCESS - success
```

#### 3.2.1.1.20 TPRO waitHeartbeat

unsigned char TPRO\_waitHeartbeat(TPRO\_BoardObj \*hnd, unsigned int \*ticks);

This routine will reports the condition of the heartbeat output. The routine will block for a given number of ticks (in milliseconds) until a heartbeat occurs or the timeout period has been reached.

Arguments: Pointer to the TPRO\_BoardObj

Pointer to timeout variable in milliseconds

Returns: TPRO TIMEOUT ERR - routine has timed-out

TPRO COMM ERR - error communicating with driver

TPRO SUCCESS - success

#### 3.2.1.1.21 TPRO waitMatch

unsigned char TPRO waitMatch(TPRO BoardObj \*hnd, unsigned int \*ticks);

This routine will reports the condition of the match start time. The routine will block for a given number of ticks (in milliseconds) until a match start time occurs or the timeout period has been reached.

Arguments: Pointer to the TPRO BoardObj

Pointer to wait time

Returns: TPRO TIMEOUT ERR - routine has timed-out

TPRO COMM ERR - error communicating with driver

TPRO\_SUCCESS - success

Document Revision History				
Rev	ECN	Description	Date	
Α	2325	First draft of Spectracom documentation for this product.		
В	2332	Minor corrections.		
С	2552	Added 32/64-bit Lib/DLL comments. Added Windows 7 support comment. Other minor corrections.	December 2010	

Spectracom Corporation 95 Methodist Hill Drive Rochester, NY 14623 www.spectracomcorp.com Phone: US +1.585.321.5800

Fax: US +1.585.321.5219