

Wireless Testbench™

Reference



MATLAB®

R2023a



How to Contact MathWorks



Latest news: www.mathworks.com
Sales and services: www.mathworks.com/sales_and_services
User community: www.mathworks.com/matlabcentral
Technical support: www.mathworks.com/support/contact_us



Phone: 508-647-7000



The MathWorks, Inc.
1 Apple Hill Drive
Natick, MA 01760-2098

Wireless Testbench™ Reference

© COPYRIGHT 2022–2023 by The MathWorks, Inc.

The software described in this document is furnished under a license agreement. The software may be used or copied only under the terms of the license agreement. No part of this manual may be photocopied or reproduced in any form without prior written consent from The MathWorks, Inc.

FEDERAL ACQUISITION: This provision applies to all acquisitions of the Program and Documentation by, for, or through the federal government of the United States. By accepting delivery of the Program or Documentation, the government hereby agrees that this software or documentation qualifies as commercial computer software or commercial computer software documentation as such terms are used or defined in FAR 12.212, DFARS Part 227.72, and DFARS 252.227-7014. Accordingly, the terms and conditions of this Agreement and only those rights specified in this Agreement, shall pertain to and govern the use, modification, reproduction, release, performance, display, and disclosure of the Program and Documentation by the federal government (or other entity acquiring for or through the federal government) and shall supersede any conflicting contractual terms or conditions. If this License fails to meet the government's needs or is inconsistent in any respect with federal procurement law, the government agrees to return the Program and Documentation, unused, to The MathWorks, Inc.

Trademarks

MATLAB and Simulink are registered trademarks of The MathWorks, Inc. See www.mathworks.com/trademarks for a list of additional trademarks. Other product or brand names may be trademarks or registered trademarks of their respective holders.

Patents

MathWorks products are protected by one or more U.S. patents. Please see www.mathworks.com/patents for more information.

Revision History

March 2022	Online only	New for Version 1.0 (Release 2022a)
September 2022	Online only	Revised for Version 1.1 (Release 2022b)
March 2023	Online only	Revised for Version 1.2 (Release 2023a)

1 | Objects

2 | Functions

Objects


basebandReceiver

Configure SDR as baseband receiver

Description

Use the `basebandReceiver` object to configure the specified software-defined radio (SDR) as a baseband receiver to capture raw IQ data from the air.

This diagram shows a conceptual overview of capturing radio signals in Wireless Testbench™ using a radio that you configure with this object. The onboard data buffering ensures contiguous data capture.



Creation

Syntax

```
bbrx = basebandReceiver(radio)
bbrx = basebandReceiver(radio,Name=Value)
```

Description

`bbrx = basebandReceiver(radio)` creates a baseband receiver configuration object for the specified radio `radio`.

Note The object requires exclusive access to radio hardware resources. Before creating this object, clear any existing Wireless Testbench object associated with the specified radio from the workspace.

`bbrx = basebandReceiver(radio,Name=Value)` sets properties on page 1-3 using one or more name-value arguments. For example, `CaptureDataType="double"` sets the data type of the returned captured data to `double`.

Input Arguments

radio — Radio setup configuration

string scalar

Radio setup configuration, specified as a string scalar. To create a radio setup configuration, set up your radio and save your radio setup configuration using the Radio Setup wizard. Call the `radioConfigurations` function to list all saved radio setup configurations. For more information, see “Connect and Set Up NI USRP Radios”.

Example: "MyRadio" indicates that you saved a radio setup configuration under the name MyRadio in the Radio Setup wizard.

Properties

CenterFrequency — Radio center frequency in Hz

2.4e9 (default) | positive numeric scalar | numeric array

Radio center frequency in Hz, specified as one of these options.

- Positive numeric scalar — The object applies this value by scalar expansion to each antenna in the `Antennas` property.
- Numeric array — The object applies the *i*th array element value to the *i*th antenna in the `Antennas` property.

The valid center frequency range depends on the radio device.

Radio Device	Center Frequency
USRP™ N310	1 MHz to 6 GHz
USRP N320	1 MHz to 6 GHz
USRP N321	1 MHz to 6 GHz
USRP X310	10 MHz to 6 GHz
USRP X410	1 MHz to 8 GHz

Note When setting this property for multiple antennas on the USRP N310 radio, consider these hardware characteristics.

- The antenna ports on the RF0 and RF1 radio channels use the same center frequency. Therefore, set identical center frequency values for the antennas specified as "RF0:RX2" and "RF1:RX2".
- The antenna ports on the RF2 and RF3 radio channels use the same center frequency. Therefore, set identical center frequency values for the antennas specified as "RF2:RX2" and "RF3:RX2".

Data Types: double

Antennas — Capture radio antennas

string scalar | string array

Capture radio antennas, specified as one of these options.

- String scalar — Specify use of single antenna.
- String array — Specify use of multiple antennas.

Use this table to identify a supported radio antenna port on the radio device and the corresponding string constant that you can specify for this property. The default value depends on the radio.

Radio Device	Supported Antenna Port	Valid String Scalar
USRP N310	RF0 channel: RX2 port	"RF0:RX2" (default)
	RF1 channel: RX2 port	"RF1:RX2"
	RF2 channel: RX2 port	"RF2:RX2"
	RF3 channel: RX2 port	"RF3:RX2"
USRP N320	RF0 channel: RX2 port	"RF0:RX2" (default)
	RF1 channel: RX2 port	"RF1:RX2"
USRP N321	RF0 channel: RX2 port	"RF0:RX2" (default)
	RF1 channel: RX2 port	"RF1:RX2"
USRP X310	RFA channel: RX2 port	"RFA:RX2" (default)
	RFB channel: RX2 port	"RFB:RX2"
USRP X410	DB0 RF0 channel: RX 1 port	"DB0:RF0:RX1" (default)
	DB0 RF1 channel: RX 1 port	"DB0:RF1:RX1"
	DB1 RF0 channel: RX 1 port	"DB1:RF0:RX1"
	DB1 RF1 channel: RX 1 port	"DB1:RF1:RX1"

Note When you update this property, the execution time of the next object function call increases by a few seconds.

Example: `Antennas=["RF0:RX2", "RF1:RX2"]` specifies two capture antennas.

Data Types: `string`

RadioGain — Capture radio gain in dB

10 (default) | positive numeric scalar | numeric array

Capture radio gain in dB, specified as one of these options.

- Positive numeric scalar — The object applies this value by scalar expansion to each antenna that you specify in the `Antennas` property.
- Numeric array — The object applies the *i*th array element value to the *i*th antenna in the `Antennas` property.

The valid gain range depends on the radio device.

Radio Device	Capture Radio Gain
USRP N310	0 dB to 75 dB
USRP N320	0 dB to 60 dB

Radio Device	Capture Radio Gain
USRP N321	0 dB to 60 dB
USRP X310	0 dB to 31.5 dB
USRP X410	0 dB to 60 dB

Data Types: double

SampleRate — Baseband sample rate in Hz

highest device sample rate (default) | positive numeric scalar

Baseband sample rate in Hz, specified as a positive numeric scalar. For more information on how the radio achieves the specified sample rate, see “Baseband Sample Rate in NI USRP Radios”.

The valid sample rate depends on the radio device.

Radio Device	Sample Rate
USRP N310	<ul style="list-style-type: none"> • 120,945 Hz to 76.8 MHz • 122.88 MHz • 125.00 MHz • 153.60 MHz (default)
USRP N320	<ul style="list-style-type: none"> • 196,851 Hz to 125 MHz • 200.00 MHz • 245.76 MHz • 250.00 MHz (default)
USRP N321	<ul style="list-style-type: none"> • 196,851 Hz to 125 MHz • 200.00 MHz • 245.76 MHz • 250.00 MHz (default)
USRP X310	<ul style="list-style-type: none"> • 181,418 Hz to 100 MHz • 184.32 MHz • 200.00 MHz (default)
USRP X410	<ul style="list-style-type: none"> • 241,890 Hz to 125 MHz • 245.76 MHz • 250.00 MHz (default)

Note When you update this property, the execution time of the next object function call increases by a few seconds.

Data Types: double

CaptureDataType — Data type of captured data

"int16" (default) | "double" | "single"

Data type of the captured data, specified as "int16", "double", or "single". Use this property to set the data type of the captured data that the capture object function returns.

Note When you update this property, the execution time of the next object function call increases by a few seconds.

Data Types: string

DroppedSamplesAction — Behavior upon dropped samples

"error" (default) | "warning" | "none"

Behavior of the capture object function upon dropped samples, specified as one of these values.

- "error" — The object function stops with an error message.
- "warning" — The object function displays a warning message.
- "none" — The object function ignores dropped samples.

Data Types: string

Object Functions

capture Capture IQ data using baseband receiver or transceiver

Examples

Configure Baseband Receiver and Capture Data

Create a baseband receiver object, specifying a radio setup configuration previously saved in the Radio Setup wizard.

```
bbrx = basebandReceiver("MyRadio")  
  
bbrx =  
    basebandReceiver with properties:  
  
        RadioGain: 10  
        CenterFrequency: 2.4000e+09  
        SampleRate: 250000000  
        Antennas: "RF0:RX2"  
        DroppedSamplesAction: "error"  
        CaptureDataType: "int16"
```

Set the baseband sample rate and center frequency.

```
bbrx.SampleRate = 122.88e6;  
bbrx.CenterFrequency = 2.2e9;
```

Capture 3 ms of IQ data with the radio associated with the baseband receiver object using the default antenna.

```
[data,~] = capture(bbrx,milliseconds(3));
```

Version History

Introduced in R2022a

See Also

Functions

radioConfigurations

Objects

basebandTransceiver | basebandTransmitter

Topics

“Supported Radio Devices”


basebandTransmitter

Configure SDR as baseband transmitter

Description

Use the `basebandTransmitter` object to configure the specified software-defined radio (SDR) as a baseband transmitter to transmit IQ waveforms to the air.

This diagram shows the conceptual overview of transmitting radio signals in Wireless Testbench using a radio that you configure with this object. The onboard data buffering ensures contiguous data transmit. The transmission controller enables you to specify continuous or single-shot transmissions.



Creation

Syntax

```
bbtx = basebandTransmitter(radio)
bbtx = basebandTransmitter(radio,Name=Value)
```

Description

`bbtx = basebandTransmitter(radio)` creates a baseband transmitter object for the specified radio `radio`.

Note The object requires exclusive access to radio hardware resources. Before creating this object, clear any existing Wireless Testbench object associated with the specified radio from the workspace.

`bbtx = basebandTransmitter(radio,Name=Value)` sets properties on page 1-9 using one or more name-value arguments. For example, `CenterFrequency=2.2e9` sets the center frequency to 2.2 GHz.

Input Arguments

radio — Radio setup configuration

string scalar

Radio setup configuration, specified as a string scalar. To create a radio setup configuration, set up your radio and save your radio setup configuration using the Radio Setup wizard. Call the `radioConfigurations` function to list all saved radio setup configurations. For more information, see “Connect and Set Up NI USRP Radios”.

Example: "MyRadio" indicates that you saved a radio setup configuration under the name MyRadio in the Radio Setup wizard.

Properties

CenterFrequency — Radio center frequency in Hz

2.4e9 (default) | positive numeric scalar | numeric array

Radio center frequency in Hz, specified as one of these options.

- Positive numeric scalar — The object applies this value by scalar expansion to each antenna in the `Antennas` property.
- Numeric array — The object applies the *i*th array element value to the *i*th antenna in the `Antennas` property.

The valid center frequency range depends on the radio device.

Radio Device	Center Frequency
USRP N310	1 MHz to 6 GHz
USRP N320	1 MHz to 6 GHz
USRP N321	1 MHz to 6 GHz
USRP X310	10 MHz to 6 GHz
USRP X410	1 MHz to 8 GHz

Note When setting this property for multiple antennas on the USRP N310 radio, consider these hardware characteristics.

- The antenna ports on the RF0 and RF1 radio channels use the same center frequency. Therefore, set identical center frequency values for the antennas specified as "RF0:TX/RX" and "RF1:TX/RX".
- The antenna ports on the RF2 and RF3 radio channels use the same center frequency. Therefore, set identical center frequency values for the antennas specified as "RF2:TX/RX" and "RF3:TX/RX".

Data Types: double

Antennas — Transmit radio antennas

string scalar | string array

Transmit radio antennas, specified as one of these options.

- String scalar — Specify use of single antenna.
- String array — Specify use of multiple antennas.

Use this table to identify a supported radio antenna port on the radio device and the corresponding string constant that you can specify for this property. The default value depends on the radio.

Radio Device	Supported Antenna Port	Valid String Scalar
USRP N310	RF0 channel: TX/RX port	"RF0:TX/RX" (default)
	RF1 channel: TX/RX port	"RF1:TX/RX"
	RF2 channel: TX/RX port	"RF2:TX/RX"
	RF3 channel: TX/RX port	"RF3:TX/RX"
USRP N320	RF0 channel: TX/RX port	"RF0:TX/RX" (default)
	RF1 channel: TX/RX port	"RF1:TX/RX"
USRP N321	RF0 channel: TX/RX port	"RF0:TX/RX" (default)
	RF1 channel: TX/RX port	"RF1:TX/RX"
USRP X310	RFA channel: TX/RX port	"RFA:TX/RX" (default)
	RFB channel: TX/RX port	"RFB:TX/RX"
USRP X410	DB0 RF0 channel: TX/RX 0 port	"DB0:RF0:TX/RX0" (default)
	DB0 RF1 channel: TX/RX 0 port	"DB0:RF1:TX/RX0"
	DB1 RF0 channel: TX/RX 0 port	"DB1:RF0:TX/RX0"
	DB1 RF1 channel: TX/RX 0 port	"DB1:RF1:TX/RX0"

Note When you update this property, the execution time of the next object function call increases by a few seconds.

Data Types: `string`

RadioGain — Transmit radio gain in dB

10 (default) | positive numeric scalar | numeric array

Transmit radio gain in dB, specified as one of these options.

- Positive numeric scalar — The object applies this value by scalar expansion to each antenna that you specify in the `Antennas` property.
- Numeric array — The object applies the *i*th array element value to the *i*th antenna in the `Antennas` property.

The valid gain range depends on the radio device.

Radio Device	Transmit Radio Gain
USRP N310	0 dB to 65 dB
USRP N320	0 dB to 60 dB

Radio Device	Transmit Radio Gain
USRP N321	0 dB to 60 dB
USRP X310	0 dB to 31.5 dB
USRP X410	0 dB to 60 dB

Data Types: double

SampleRate — Baseband sample rate in Hz

highest device sample rate (default) | positive numeric scalar

Baseband sample rate in Hz, specified as a positive numeric scalar. For more information on how the radio achieves the specified sample rate, see “Baseband Sample Rate in NI USRP Radios”.

The valid sample rate depends on the radio device.

Radio Device	Sample Rate
USRP N310	<ul style="list-style-type: none"> • 120,945 Hz to 76.8 MHz • 122.88 MHz • 125.00 MHz • 153.60 MHz (default)
USRP N320	<ul style="list-style-type: none"> • 196,851 Hz to 125 MHz • 200.00 MHz • 245.76 MHz • 250.00 MHz (default)
USRP N321	<ul style="list-style-type: none"> • 196,851 Hz to 125 MHz • 200.00 MHz • 245.76 MHz • 250.00 MHz (default)
USRP X310	<ul style="list-style-type: none"> • 181,418 Hz to 100 MHz • 184.32 MHz • 200.00 MHz (default)
USRP X410	<ul style="list-style-type: none"> • 241,890 Hz to 125 MHz • 245.76 MHz • 250.00 MHz (default)

Note To update this property, you must stop any ongoing transmission by calling the `stopTransmission` function on the object. When you update this property, the execution time of the next object function call increases by a few seconds.

Data Types: double

Object Functions

`transmit` Transmit waveform using baseband transmitter or transceiver
`stopTransmission` Stop transmission from baseband transmitter or transceiver

Examples

Configure Baseband Transmitter and Transmit Waveform

Create a baseband transmitter object, specifying a radio setup configuration previously saved in the Radio Setup wizard.

```
bbtx = basebandTransmitter("MyRadio")  
  
bbtx =  
    basebandTransmitter with properties:  
  
        RadioGain: 10  
        CenterFrequency: 2.4000e+09  
        SampleRate: 250000000  
        Antennas: "RF0:TX/RX"
```

Set the baseband sample rate and center frequency.

```
bbtx.SampleRate = 122.88e6;  
bbtx.CenterFrequency = 2.2e9;
```

Generate random transmit waveform.

```
txWaveform = complex(randn(1000,1),randn(1000,1));
```

Transmit the generated waveform continuously with the radio associated with the baseband transmitter object using the default antenna.

```
transmit(bbtx,txWaveform,"continuous");
```

Stop the continuous transmission after 5 seconds.

```
pause(5);  
stopTransmission(bbtx);
```

Version History

Introduced in R2022a

See Also

Functions

`radioConfigurations`

Objects

`basebandTransceiver` | `basebandReceiver`


basebandTransceiver

Configure SDR as baseband transceiver

Description

Use the `basebandTransceiver` object to configure the specified software-defined radio (SDR) as a baseband transceiver to simultaneously transmit and capture IQ waveforms over the air.

This diagram shows a conceptual overview of capturing and transmitting radio signals in Wireless Testbench using a radio that you configure with this object. The onboard data buffering ensures contiguous data capture and transmit. The transmission controller enables you to specify continuous or single-shot transmissions.



Creation

Syntax

```
bbtrx = basebandTransceiver(radio)
bbtrx = basebandTransceiver(radio,Name=Value)
```

Description

`bbtrx = basebandTransceiver(radio)` creates a baseband transceiver object for the specified radio `radio`.

Note The object requires exclusive access to radio hardware resources. Before creating this object, clear any existing Wireless Testbench object associated with the specified radio from the workspace.

`bbtrx = basebandTransceiver(radio,Name=Value)` sets properties on page 1-14 using one or more name-value arguments. For example, `CaptureDataType="double"` sets the data type of the returned captured data to double.

Input Arguments

radio — Radio setup configuration

string scalar

Radio setup configuration, specified as a string scalar. To create a radio setup configuration, set up your radio and save your radio setup configuration using the Radio Setup wizard. Call the `radioConfigurations` function to list all saved radio setup configurations. For more information, see “Connect and Set Up NI USRP Radios”.

Example: "MyRadio" indicates that you saved a radio setup configuration under the name MyRadio in the Radio Setup wizard.

Properties

TransmitCenterFrequency — Transmit center frequency in Hz

2.4e9 (default) | positive numeric scalar

Transmit center frequency in Hz, specified as a positive numeric scalar. The valid center frequency range depends on the radio device.

Radio Device	Center Frequency
USRP N310	1 MHz to 6 GHz
USRP N320	1 MHz to 6 GHz
USRP N321	1 MHz to 6 GHz
USRP X310	10 MHz to 6 GHz
USRP X410	1 MHz to 8 GHz

TransmitAntennas — Transmit radio antenna

string scalar

Transmit radio antenna, specified as a string scalar. Use this table to identify a supported radio antenna port on the radio device and the corresponding string constant that you can specify for this property. The default value depends on the radio.

Radio Device	Supported Antenna Port	Valid String Scalar
USRP N310	RF0 channel: TX/RX port	"RF0:TX/RX" (default)
	RF1 channel: TX/RX port	"RF1:TX/RX"
	RF2 channel: TX/RX port	"RF2:TX/RX"
	RF3 channel: TX/RX port	"RF3:TX/RX"
USRP N320	RF0 channel: TX/RX port	"RF0:TX/RX" (default)
	RF1 channel: TX/RX port	"RF1:TX/RX"
USRP N321	RF0 channel: TX/RX port	"RF0:TX/RX" (default)
	RF1 channel: TX/RX port	"RF1:TX/RX"

Radio Device	Supported Antenna Port	Valid String Scalar
USRP X310	RFA channel: TX/RX port	"RFA:TX/RX" (default)
	RFB channel: TX/RX port	"RFB:TX/RX"
USRP X410	DB0 RF0 channel: TX/RX 0 port	"DB0:RF0:TX/RX0" (default)
	DB0 RF1 channel: TX/RX 0 port	"DB0:RF1:TX/RX0"
	DB1 RF0 channel: TX/RX 0 port	"DB1:RF0:TX/RX0"
	DB1 RF1 channel: TX/RX 0 port	"DB1:RF1:TX/RX0"

Note When you update this property, the execution time of the next object function call increases by a few seconds.

Data Types: string

TransmitRadioGain — Transmit radio gain in dB

10 (default) | positive numeric scalar

Transmit radio gain in dB, specified as a positive numeric scalar. The valid gain range depends on the radio device.

Radio Device	Transmit Radio Gain
USRP N310	0 dB to 65 dB
USRP N320	0 dB to 60 dB
USRP N321	0 dB to 60 dB
USRP X310	0 dB to 31.5 dB
USRP X410	0 dB to 60 dB

Data Types: double

CaptureCenterFrequency — Capture center frequency in Hz

2.4e9 (default) | positive numeric scalar

Capture center frequency in Hz, specified as a positive numeric scalar. The valid center frequency range depends on the radio device.

Radio Device	Center Frequency
USRP N310	1 MHz to 6 GHz
USRP N320	1 MHz to 6 GHz
USRP N321	1 MHz to 6 GHz
USRP X310	10 MHz to 6 GHz
USRP X410	1 MHz to 8 GHz

Data Types: double

CaptureAntennas — Capture radio antenna

string scalar

Capture radio antenna, specified as a string scalar. Use this table to identify a supported radio antenna port on the radio device and the corresponding string constant that you can specify for this property. The default value depends on the radio.

Radio Device	Supported Antenna Port	Valid String Scalar
USRP N310	RF0 channel: RX2 port	"RF0:RX2" (default)
	RF1 channel: RX2 port	"RF1:RX2"
	RF2 channel: RX2 port	"RF2:RX2"
	RF3 channel: RX2 port	"RF3:RX2"
USRP N320	RF0 channel: RX2 port	"RF0:RX2" (default)
	RF1 channel: RX2 port	"RF1:RX2"
USRP N321	RF0 channel: RX2 port	"RF0:RX2" (default)
	RF1 channel: RX2 port	"RF1:RX2"
USRP X310	RFA channel: RX2 port	"RFA:RX2" (default)
	RFB channel: RX2 port	"RFB:RX2"
USRP X410	DB0 RF0 channel: RX 1 port	"DB0:RF0:RX1" (default)
	DB0 RF1 channel: RX 1 port	"DB0:RF1:RX1"
	DB1 RF0 channel: RX 1 port	"DB1:RF0:RX1"
	DB1 RF1 channel: RX 1 port	"DB1:RF1:RX1"

Note When you update this property, the execution time of the next object function call increases by a few seconds.

Data Types: `string`

CaptureRadioGain — Capture radio gain in dB

10 (default) | positive numeric scalar

Capture radio gain in dB, specified as a positive numeric scalar. The valid gain range depends on the radio device.

Radio Device	Capture Radio Gain
USRP N310	0 dB to 75 dB
USRP N320	0 dB to 60 dB
USRP N321	0 dB to 60 dB
USRP X310	0 dB to 31.5 dB
USRP X410	0 dB to 60 dB

Data Types: `double`

CaptureDataType — Data type of captured data

"int16" (default) | "double" | "single"

Data type of the captured data, specified as "int16", "double", or "single". Use this property to set the data type of the captured data that the capture object function returns.

Note When you update this property, the execution time of the next object function call increases by a few seconds.

Data Types: `string`

SampleRate — Baseband sample rate in Hz

highest device sample rate (default) | positive numeric scalar

Baseband sample rate in Hz, specified as a positive numeric scalar. For more information on how the radio achieves the specified sample rate, see “Baseband Sample Rate in NI USRP Radios”.

The valid sample rate depends on the radio device.

Radio Device	Sample Rate
USRP N310	<ul style="list-style-type: none"> • 120,945 Hz to 76.8 MHz • 122.88 MHz • 125.00 MHz • 153.60 MHz (default)
USRP N320	<ul style="list-style-type: none"> • 196,851 Hz to 125 MHz • 200.00 MHz • 245.76 MHz • 250.00 MHz (default)
USRP N321	<ul style="list-style-type: none"> • 196,851 Hz to 125 MHz • 200.00 MHz • 245.76 MHz • 250.00 MHz (default)
USRP X310	<ul style="list-style-type: none"> • 181,418 Hz to 100 MHz • 184.32 MHz • 200.00 MHz (default)
USRP X410	<ul style="list-style-type: none"> • 241,890 Hz to 125 MHz • 245.76 MHz • 250.00 MHz (default)

Note To update this property, you must stop any ongoing transmission by calling the `stopTransmission` function on the object. When you update this property, the execution time of the next object function call increases by a few seconds.

Data Types: `double`

DroppedSamplesAction — Behavior upon dropped samples

"error" (default) | "warning" | "none"

Behavior of the capture object function upon dropped samples, specified as one of these values.

- "error" — The object function stops with an error message.
- "warning" — The object function displays a warning message.
- "none" — The object function ignores dropped samples.

Data Types: string

Object Functions

capture	Capture IQ data using baseband receiver or transceiver
transmit	Transmit waveform using baseband transmitter or transceiver
stopTransmission	Stop transmission from baseband transmitter or transceiver

Examples

Configure Baseband Transceiver to Transmit and Capture Data

Create a baseband transceiver object, specifying a radio setup configuration previously saved in the Radio Setup wizard.

```
bbtrx = basebandTransceiver("MyRadio")
```

```
bbtrx =  
    basebandTransceiver with properties:  
  
        TransmitRadioGain: 10  
    TransmitCenterFrequency: 2.4000e+09  
        TransmitAntennas: "RF0:TX/RX"  
        CaptureRadioGain: 10  
    CaptureCenterFrequency: 2.4000e+09  
        CaptureAntennas: "RF0:RX2"  
        CaptureDataType: "int16"  
    DroppedSamplesAction: "error"  
        SampleRate: 250000000
```

Set the baseband sample rate.

```
bbtrx.SampleRate = 122.88e6;
```

Set the transmit and capture center frequencies.

```
bbtrx.TransmitCenterFrequency = 2.2e9;  
bbtrx.CaptureCenterFrequency = 2.2e9;
```

Generate random transmit waveform.

```
txWaveform = complex(randn(1000,1),randn(1000,1));
```

Transmit the generated waveform continuously with the radio associated with the baseband transceiver object using the default transmit antenna.

```
transmit(bbtrx,txWaveform,"continuous");
```

Capture IQ data with the radio associated with the baseband transceiver object using the default capture antenna.

```
[data,~] = capture(bbtrx,milliseconds(3));
```

Stop the continuous transmission after data capture is complete.

```
stopTransmission(bbtrx);
```

Version History

Introduced in R2022a

See Also

Functions

radioConfigurations

Objects

basebandTransmitter | basebandReceiver


preambleDetector

Configure SDR as preamble detector

Description

Use the `preambleDetector` object to configure the specified software-defined radio (SDR) as a preamble detector, which you can use to detect and capture a signal of interest from the air using a correlation with a known preamble sequence. The object specifies the preamble sequence and the thresholding and triggering parameters. For more details on the internal architecture of the preamble detector, see “Algorithms” on page 1-26.

This diagram shows a conceptual overview of detecting and capturing radio signals in Wireless Testbench using a radio that you configure with this object. The object also enables you to send a test waveform for detection and capture. The onboard data buffering ensures contiguous data capture and transmit.



Creation

Syntax

```
pd = preambleDetector(radio)
pd = preambleDetector(radio, Name=Value)
```

Description

`pd = preambleDetector(radio)` creates a preamble detector configuration object for the specified radio `radio`.

Note The object requires exclusive access to radio hardware resources. Before creating this object, clear any existing Wireless Testbench object associated with the specified radio from the workspace.

`pd = preambleDetector(radio,Name=Value)` sets properties on page 1-21 using one or more name-value arguments. For example, `CaptureDataType="double"` sets the data type of the returned captured signal to double.

Input Arguments

radio — Radio setup configuration

string scalar

Radio setup configuration, specified as a string scalar. To create a radio setup configuration, set up your radio and save your radio setup configuration using the Radio Setup wizard. Call the `radioConfigurations` function to list all saved radio setup configurations. For more information, see “Connect and Set Up NI USRP Radios”.

Example: "MyRadio" indicates that you saved a radio setup configuration under the name MyRadio in the Radio Setup wizard.

Properties

CenterFrequency — Capture center frequency in Hz

2.4e9 (default) | positive numeric scalar

Capture center frequency in Hz, specified as a positive numeric scalar. The valid center frequency range depends on the radio device.

Radio Device	Center Frequency
USRP N310	1 MHz to 6 GHz
USRP N320	1 MHz to 6 GHz
USRP N321	1 MHz to 6 GHz
USRP X310	10 MHz to 6 GHz
USRP X410	1 MHz to 8 GHz

Data Types: double

RadioGain — Capture radio gain in dB

10 (default) | positive numeric scalar

Capture radio gain in dB, specified as a positive numeric scalar. The valid gain range depends on the radio device.

Radio Device	Capture Radio Gain
USRP N310	0 dB to 75 dB
USRP N320	0 dB to 60 dB
USRP N321	0 dB to 60 dB
USRP X310	0 dB to 31.5 dB
USRP X410	0 dB to 60 dB

Data Types: double

Antennas — Capture radio antenna

string scalar

Capture radio antenna, specified as a string scalar. Use this table to identify a supported radio antenna port on the radio device and the corresponding string constant that you can specify for this property. The default value depends on the radio.

Radio Device	Supported Antenna Port	Valid String Scalar
USRP N310	RF0 channel: RX2 port	"RF0:RX2" (default)
	RF1 channel: RX2 port	"RF1:RX2"
	RF2 channel: RX2 port	"RF2:RX2"
	RF3 channel: RX2 port	"RF3:RX2"
USRP N320	RF0 channel: RX2 port	"RF0:RX2" (default)
	RF1 channel: RX2 port	"RF1:RX2"
USRP N321	RF0 channel: RX2 port	"RF0:RX2" (default)
	RF1 channel: RX2 port	"RF1:RX2"
USRP X310	RFA channel: RX2 port	"RFA:RX2" (default)
	RFB channel: RX2 port	"RFB:RX2"
USRP X410	DB0 RF0 channel: RX 1 port	"DB0:RF0:RX1" (default)
	DB0 RF1 channel: RX 1 port	"DB0:RF1:RX1"
	DB1 RF0 channel: RX 1 port	"DB1:RF0:RX1"
	DB1 RF1 channel: RX 1 port	"DB1:RF1:RX1"

Note When you update this property, the execution time of the next object function call increases by a few seconds.

Data Types: string

SampleRate — Baseband sample rate in Hz

highest device sample rate (default) | positive numeric scalar

Baseband sample rate in Hz, specified as a positive numeric scalar. For more information on how the radio achieves the specified sample rate, see "Baseband Sample Rate in NI USRP Radios".

The valid sample rate depends on the radio device.

Radio Device	Sample Rate
USRP N310	<ul style="list-style-type: none"> • 120,945 Hz to 76.8 MHz • 122.88 MHz • 125.00 MHz • 153.60 MHz (default)

Radio Device	Sample Rate
USRP N320	<ul style="list-style-type: none"> • 196,851 Hz to 125 MHz • 200.00 MHz • 245.76 MHz • 250.00 MHz (default)
USRP N321	<ul style="list-style-type: none"> • 196,851 Hz to 125 MHz • 200.00 MHz • 245.76 MHz • 250.00 MHz (default)
USRP X310	<ul style="list-style-type: none"> • 181,418 Hz to 100 MHz • 184.32 MHz • 200.00 MHz (default)
USRP X410	<ul style="list-style-type: none"> • 241,890 Hz to 125 MHz • 245.76 MHz • 250.00 MHz (default)

Note To update this property, you must stop any ongoing transmission by calling the `stopTransmission` function on the object. When you update this property, the execution time of the next object function call increases by a few seconds.

Data Types: `double`

CaptureDataType — Data type of captured data

`"int16"` (default) | `"double"` | `"single"`

Data type of the captured data, specified as `"int16"`, `"double"`, or `"single"`. Use this property to set the data type of the captured data that the capture object function returns.

Note When you update this property, the execution time of the next object function call increases by a few seconds.

Data Types: `string`

DroppedSamplesAction — Behavior upon dropped samples

`"error"` (default) | `"warning"` | `"none"`

Behavior of the capture and `plotThreshold` object functions upon dropped samples, specified as one of these values.

- `"error"` — The object function stops with an error message.
- `"warning"` — The object function displays a warning message.
- `"none"` — The object function ignores dropped samples.

Data Types: `string`

Preamble — Preamble sequence

16-by-1 vector of all zeros (default) | numeric column vector

Preamble sequence, specified as a numeric column vector of length between 4 and 1024 and vector elements in the range [-1, 1]. The first object function call validates the preamble length against the maximum preamble length.

You can assign a `double`, `single`, or `fi` (requires Fixed-Point Designer™) data type to this property. To assign a fixed-point data type, use the `fi` object. The fixed-point data type must be signed with the `WordLength` property set to 16 and `FractionLength` property set to 15.

Note To update this property, you must stop any ongoing transmission by calling the `stopTransmission` function on the object. When you update this property, the execution time of the next object function call increases by a few seconds.

Data Types: `double` | `single` | `fi`

ThresholdMethod — Threshold calculation method

"adaptive" (default) | "fixed"

Threshold calculation method to trigger data capture, specified as one of these values.

- "adaptive" — The threshold is the scaled signal power. To configure the scaled signal power, set the `AdaptiveThresholdGain` and `AdaptiveThresholdOffset` properties.
- "fixed" — The threshold is a constant, specified by the `FixedThreshold` property.

For more details, see "Internal Architecture of Preamble Detection" on page 1-26.

Note To update this property, you must stop any ongoing transmission by calling the `stopTransmission` function on the object. When you update this property, the execution time of the next object function call increases by a few seconds.

Data Types: `string`

FixedThreshold — Fixed threshold value

0 (default) | numeric scalar in the range [0, 4095]

Fixed threshold value, specified as a numeric scalar in the range [0, 4095]. For more details, see "Internal Architecture of Preamble Detection" on page 1-26.

Dependencies

This property is applicable only when `ThresholdMethod` is set to "fixed".

Data Types: `double`

AdaptiveThresholdOffset — Adaptive threshold offset

0 (default) | numeric scalar in the range [0, 2]

Adaptive threshold offset to avoid false trigger points, specified as a numeric scalar in the range [0, 2]. For more details, see "Internal Architecture of Preamble Detection" on page 1-26.

Dependencies

This property is applicable only when `ThresholdMethod` is set to "adaptive".

Data Types: double

AdaptiveThresholdGain — Adaptive threshold gain

0 (default) | numeric scalar in the range [0, 64]

Adaptive threshold gain value applied to the average input signal power before adaptive threshold calculation, specified as a numeric scalar in the range [0, 64]. For more details, see "Internal Architecture of Preamble Detection" on page 1-26.

Dependencies

This property is applicable only when `ThresholdMethod` is set to "adaptive".

Data Types: double

TriggerOffset — Trigger point offset

0 (default) | integer in the range [-3096, 4096]

Trigger point offset, specified as an integer in the range [-3096, 4096]. This value specifies the start of data capture relative to the trigger point. For more details, see "Thresholding and Triggering" on page 1-27.

Note To update this property, you must stop any ongoing transmission by calling the `stopTransmission` function on the object. When you update this property, the execution time of the next object function call increases by a few seconds.

Data Types: double

Object Functions

<code>capture</code>	Capture signal of interest from the air upon detection
<code>plotThreshold</code>	Plot preamble detection signals for triggering
<code>transmit</code>	Transmit waveform using preamble detector
<code>stopTransmission</code>	Stop transmission from preamble detector

Examples**Configure Preamble Detector and Capture Data**

Define a preamble sequence with good correlation properties. For example, generate and normalize a Zadoff-Chu sequence of length 137.

```
seq = zadoffChuSeq(38,137);
preamble = seq/norm(seq,2);
```

Create and configure a preamble detector object, specifying a radio setup configuration previously saved in the Radio Setup wizard.

```
pd = preambleDetector("MyRadio")
```

```
pd =  
  preambleDetector with properties:  
      CenterFrequency: 2.4000e+09  
      RadioGain: 10  
      Antennas: "RF0:RX2"  
      SampleRate: 250000000  
      CaptureDataType: "int16"  
      DroppedSamplesAction: "error"  
      Preamble: 0  
      ThresholdMethod: "adaptive"  
      FixedThreshold: 0  
      AdaptiveThresholdOffset: 0  
      AdaptiveThresholdGain: 0  
      TriggerOffset: 0
```

```
pd.SampleRate = 10.24e6;  
pd.CenterFrequency = 2.2e9;  
pd.CaptureDataType = "double";
```

Specify the preamble.

```
pd.Preamble = preamble;
```

Set the trigger offset to a negative value to capture 500 samples before the trigger point.

```
pd.TriggerOffset = -500;
```


Capture 10 ms of data with a timeout of 1 second.

```
[data,timestamp,droppedSamples,status] = capture(pd,milliseconds(10),seconds(1));
```

Algorithms

Internal Architecture of Preamble Detection

This diagram shows a conceptual overview of triggered capture based on preamble detection. The input is an RF signal received from the RF board of the radio.



- The **Programmable FIR filter** correlates the input signal with a known preamble sequence. To specify the preamble sequence, use the `Preamble` property.
- The **Threshold calculation** component provides the threshold for the trigger point generation. For more information on how to adjust the threshold, see “Thresholding and Triggering” on page 1-27.
- The **Capture controller** component controls the triggered capture.
 - The **Comparator** component generates the trigger point, which is the first data sample for which the correlator output power is greater than the threshold.
 - The **Data packaging** component starts the data capture at the trigger point. To adjust the start of the data capture relative to the trigger point, use the `TriggerOffset` property.


Thresholding and Triggering

The trigger point is the first data sample for which the correlator output power is greater than the threshold. To calibrate the thresholding and triggering operation:


- 1 Adjust the gain on the RF signal by using the `RadioGain` property.
- 2 Adjust the threshold. You can specify an adaptive threshold or a fixed threshold.
 - For adaptive threshold, set the `ThresholdMethod` property to "adaptive", then use the `AdaptiveThresholdGain` property to set the adaptive threshold gain value. To avoid false triggers, adjust the `AdaptiveThresholdOffset` property.
 - For fixed threshold, set the `ThresholdMethod` property to "fixed", then use the `FixedThreshold` property to set the fixed threshold value.
- 3 Call the `plotThreshold` object function to display and analyze the correlator output power, threshold, and corresponding trigger points.

By default, data capture starts at the trigger point. To adjust the start of the data capture relative to the trigger point, use the TriggerOffset property.

For example, this figure shows a scenario in which the trigger offset is 0. Hence, data capture starts at the trigger point.



In this second scenario, the trigger point is the same, but the trigger offset is -9. Hence, data capture starts at the specified trigger offset.



For an example of how to calibrate the thresholding and triggering operation, see “Triggered Capture Using Preamble Detection”.

Version History

Introduced in R2022a

R2023a: Updates to Preamble property

- The valid length of the preamble sequence specified by the `Preamble` property has changed. The preamble sequence now must be a vector of length between 4 and 1024. In previous releases, the maximum sequence length depends on the master clock rate that the object automatically selects for the radio based on the sample rate.
- The vector elements of the preamble sequence are now in the range $[-1, 1]$. In previous releases, you cannot set the vector elements of the preamble sequence to 1.

See Also

Functions

`radioConfigurations`

Topics

“Triggered Capture Using Preamble Detection”

“Supported Radio Devices”

“Connect and Set Up NI USRP Radios”

Functions

capture

Capture signal of interest from the air upon detection

Syntax

```
[data,timestamp,droppedSamples,status] = capture(pd,length,timeout)
```

Description

`[data,timestamp,droppedSamples,status] = capture(pd,length,timeout)` captures a signal of interest of length `length` from the air using the preamble detector `pd` with the detection timeout `timeout`. The function returns captured signal `data`, capture request timestamp `timestamp`, dropped samples status `droppedSamples`, and capture outcome status `status`.

Examples

Configure Preamble Detector and Capture Data

Define a preamble sequence with good correlation properties. For example, generate and normalize a Zadoff-Chu sequence of length 137.

```
seq = zadoffChuSeq(38,137);
preamble = seq/norm(seq,2);
```

Create and configure a preamble detector object, specifying a radio setup configuration previously saved in the Radio Setup wizard.

```
pd = preambleDetector("MyRadio")
pd =
  preambleDetector with properties:
      CenterFrequency: 2.4000e+09
      RadioGain: 10
      Antennas: "RF0:RX2"
      SampleRate: 250000000
      CaptureDataType: "int16"
      DroppedSamplesAction: "error"
      Preamble: 0
      ThresholdMethod: "adaptive"
      FixedThreshold: 0
      AdaptiveThresholdOffset: 0
      AdaptiveThresholdGain: 0
      TriggerOffset: 0
```

```
pd.SampleRate = 10.24e6;
pd.CenterFrequency = 2.2e9;
pd.CaptureDataType = "double";
```

Specify the preamble.

```
pd.Preamble = preamble;
```

Set the trigger offset to a negative value to capture 500 samples before the trigger point.

```
pd.TriggerOffset = -500;
```

Capture 10 ms of data with a timeout of 1 second.

```
[data,timestamp,droppedSamples,status] = capture(pd,milliseconds(10),seconds(1));
```

Input Arguments

pd – Preamble detector

preambleDetector object

Preamble detector, specified as a preambleDetector object.

Note The first object function call in which you specify this object as an input requires a few extra seconds to load the application onto the hardware.

Length – Capture length

integer number of samples | duration

Capture length, specified as an integer number of samples or a duration value in time units. The function converts length into N samples based on the SampleRate property of the pd input and captures $\text{ceil}(N)$ number of data samples.

Specify the capture length relative to the onboard radio memory buffer size.

Radio Device	Memory Buffer Size	Maximum Data Samples
USRP N310	2 GB	2^{29}
USRP N320	2 GB	2^{29}
USRP N321	2 GB	2^{29}
USRP X310	1 GB	2^{28}
USRP X410	4 GB	2^{30}

Note

- Capture and transmit data samples are buffered in the onboard radio memory. Therefore, when specifying the capture length, you must also take into account the length of the transmit waveform of any continuous transmission that you specify when calling the transmit object function with the pd input.
 - If your host computer does not have enough free memory to receive the captured data from the radio buffer, the function call can hang or error out. To free up memory space on your host computer, try closing other software or reduce the capture length.
-

Example: seconds(5)

Data Types: `double` | `duration`

timeout — Preamble signal detection timeout

`duration`

Preamble signal detection timeout on the radio, specified as a `duration` value in time units. If the `pd.Preamble` property specifies a periodic signal, set the detection timeout to a value that is equal to or greater than the preamble signal period. Setting the detection timeout to a value less than the preamble signal period can end the detection operation prematurely.

Example: `milliseconds(100)`

Data Types: `duration`

Output Arguments**data — Captured signal**

column vector of complex values

Captured signal, returned as a column vector of complex values. Use the `CaptureDataType` property of the `pd` input to specify the output data type of the captured data. If you specify the return data type as `single` or `double`, the function scales the captured data sample values to the range `[-1, 1]`.

Data Types: `int16` | `single` | `double`

Complex Number Support: Yes

timestamp — Capture request timestamp

`datetime` value

Capture request timestamp, returned as a `datetime` value. The function creates this timestamp just before requesting data capture from the hardware.

Data Types: `datetime`

droppedSamples — Status of dropped samples

`1` | `0`

Status of dropped samples, returned as one of these logical values.

- `1` — Samples are dropped during capture.
- `0` — Samples are not dropped during capture.

Use the `DroppedSamplesAction` property of the `pd` input to specify the behavior of the capture function upon dropped samples.

Data Types: `logical`

status — Capture outcome status

`1` | `0`

Capture outcome status, returned as one of these logical values.

- `1` — Capture operation was successful and the captured signal of interest is returned in `data`.
- `0` — Detect and capture operation timed out.

Data Types: logical

Version History

Introduced in R2022a

See Also

Functions

duration | plotThreshold

capture

Capture IQ data using baseband receiver or transceiver

Syntax

```
[data,timestamp,droppedSamples] = capture(bba,length)
```

Description

`[data,timestamp,droppedSamples] = capture(bba,length)` captures IQ data of length `length` from the air using the specified baseband receiver or baseband transceiver `bba`. The function returns the captured signal data, capture request timestamp `timestamp`, and dropped samples status `droppedSamples`.

Examples

Configure Baseband Receiver and Capture Data

Create a baseband receiver object, specifying a radio setup configuration previously saved in the Radio Setup wizard.

```
bbrx = basebandReceiver("MyRadio")  
  
bbrx =  
    basebandReceiver with properties:  
  
        RadioGain: 10  
        CenterFrequency: 2.4000e+09  
        SampleRate: 250000000  
        Antennas: "RF0:RX2"  
        DroppedSamplesAction: "error"  
        CaptureDataType: "int16"
```

Set the baseband sample rate and center frequency.

```
bbrx.SampleRate = 122.88e6;  
bbrx.CenterFrequency = 2.2e9;
```

Capture 3 ms of IQ data with the radio associated with the baseband receiver object using the default antenna.

```
[data,~] = capture(bbrx,milliseconds(3));
```

Configure Baseband Transceiver to Transmit and Capture Data

Create a baseband transceiver object, specifying a radio setup configuration previously saved in the Radio Setup wizard.


```

bbtrx = basebandTransceiver("MyRadio")
bbtrx =
  basebandTransceiver with properties:

    TransmitRadioGain: 10
    TransmitCenterFrequency: 2.4000e+09
    TransmitAntennas: "RF0:TX/RX"
    CaptureRadioGain: 10
    CaptureCenterFrequency: 2.4000e+09
    CaptureAntennas: "RF0:RX2"
    CaptureDataType: "int16"
    DroppedSamplesAction: "error"
    SampleRate: 250000000

```

Set the baseband sample rate.

```
bbtrx.SampleRate = 122.88e6;
```

Set the transmit and capture center frequencies.

```
bbtrx.TransmitCenterFrequency = 2.2e9;
bbtrx.CaptureCenterFrequency = 2.2e9;
```

Generate random transmit waveform.

```
txWaveform = complex(randn(1000,1),randn(1000,1));
```

Transmit the generated waveform continuously with the radio associated with the baseband transceiver object using the default transmit antenna.

```
transmit(bbtrx,txWaveform,"continuous");
```

Capture IQ data with the radio associated with the baseband transceiver object using the default capture antenna.

```
[data,~] = capture(bbtrx,milliseconds(3));
```

Stop the continuous transmission after data capture is complete.

```
stopTransmission(bbtrx);
```

Input Arguments

bba — Baseband application

basebandReceiver object | basebandTransceiver object

Baseband application, specified as a basebandReceiver object or basebandTransceiver object.

Note The first object function call in which you specify this object as an input requires a few extra seconds to load the application onto the hardware.

length — Capture length

integer number of samples | duration

Capture length, specified as an integer number of samples or a `duration` value in time units. The function converts `length` into N samples based on the `SampleRate` property of the `bba` input and captures `ceil(N)` number of data samples.

Specify the capture length relative to the onboard radio memory buffer size.

Radio Device	Memory Buffer Size	Maximum Data Samples
USRP N310	2 GB	2^{29}
USRP N320	2 GB	2^{29}
USRP N321	2 GB	2^{29}
USRP X310	1 GB	2^{28}
USRP X410	4 GB	2^{30}

Note

- Transmit and capture data samples on the baseband transceiver are buffered in the onboard radio memory. Therefore, if the `bba` input is a baseband transceiver, you must also take into account the length of the transmit waveform of any continuous transmission that you specify when calling the `transmit` object function with the `bba` input.
 - If your host computer does not have enough free memory to receive the captured data from the radio buffer, the function call can hang or error out. To free up memory space on your host computer, try closing other software or reduce the capture length.
-

Example: `seconds(5)`

Data Types: `double` | `duration`

Output Arguments

data — Captured signal

complex-valued column vector | complex-valued matrix

Captured signal, returned as one of these options.

- Complex-valued column vector — The vector contains data that is captured on a single capture antenna.
- Complex-valued matrix — The matrix contains data that is captured on multiple capture antennas. This option applies only when `bba` is a baseband receiver. The number of antennas specified by the `Antennas` property of the `bba` input determines the number of matrix columns.

Use the `bba.CaptureDataType` property to specify the data type of the returned data. If you specify the return data type as `single` or `double`, the function scales the captured data sample values to the range `[-1, 1]`.

Note The first data samples of the captured signal can contain transient values from the radio data path.

Data Types: `int16` | `single` | `double`
Complex Number Support: Yes

timestamp — Capture request timestamp

`datetime` value

Capture request timestamp, returned as a `datetime` value. The function creates this timestamp just before requesting data capture from the hardware.

Data Types: `datetime`

droppedSamples — Status of dropped samples

`1` | `0`

Status of dropped samples, returned as one of these logical values.

- `1` — Samples are dropped during capture.
- `0` — Samples are not dropped during capture.

Use the `DroppedSamplesAction` property of the `bba` input to specify the behavior of the function upon dropped samples.

Data Types: `logical`

Version History

Introduced in R2022a

See Also

Functions

`transmit`

Objects

`basebandReceiver` | `basebandTransceiver`

plotThreshold

Plot preamble detection signals for triggering

Syntax

```
plotThreshold(pd, length)
droppedSamples = plotThreshold(pd, length)
```

Description

`plotThreshold(pd, length)` plots preamble detection signals while detecting a preamble in live data of length `length` from the air using the preamble detector `pd`. The plot shows the correlator output power, threshold, and trigger points of the detection. Use the displayed information to calibrate the threshold in the preamble detector for triggering.

`droppedSamples = plotThreshold(pd, length)` returns the status information of dropped samples, in addition to plotting preamble detection signals.

Examples

Configure Preamble Detector and Plot Detection Threshold

Define a preamble sequence with good correlation properties. For example, generate and normalize a Zadoff-Chu sequence of length 137.

```
zcseq = zadoffChuSeq(38, 137);
preamble = zcseq/norm(zcseq, 2);
```

Create and configure a preamble detector object, specifying a radio setup configuration previously saved in the Radio Setup wizard.

```
pd = preambleDetector("MyRadio")
```

```
pd =
  preambleDetector with properties:
    CenterFrequency: 2.4000e+09
    RadioGain: 10
    Antennas: "RF0:RX2"
    SampleRate: 250000000
    CaptureDataType: "int16"
    DroppedSamplesAction: "error"
    Preamble: [16×1 double]
    ThresholdMethod: "adaptive"
    FixedThreshold: 0
    AdaptiveThresholdOffset: 0
    AdaptiveThresholdGain: 0
    TriggerOffset: 0
```

```
pd.SampleRate = 30.72e6;  
pd.RadioGain = 30;
```

Specify the preamble.

```
pd.Preamble = preamble;
```

Specify a fixed threshold.

```
pd.ThresholdMethod = "Fixed";  
pd.FixedThreshold = 0.1;
```

Generate test waveform for detection.


```
prePadLen = 2501;  
postPadLen = 2500;  
headSignal = complex(zeros(prePadLen,1),zeros(prePadLen,1));  
rearSignal = complex(zeros(postPadLen,1),zeros(postPadLen,1));  
testWaveform = [headSignal; zcseq*0.75; rearSignal];
```

Send the test waveform continuously.

```
transmit(pd,testWaveform,"continuous", ...  
    TransmitGain=30);
```

Plot the specified number of samples of the correlator output power. Use the displayed information to calibrate thresholding parameters.

```
plotThreshold(pd,10000);
```



Stop test waveform transmission.

```
stopTransmission(pd);
```

Input Arguments

pd — Preamble detector
preambleDetector object

Preamble detector, specified as a preambleDetector object.

Note The first object function call in which you specify this object as an input requires a few extra seconds to load the application onto the hardware.

length — Plotted data length
integer number of samples | duration

Plotted data length, specified as an integer number of samples or a duration value in time units. The function converts `length` into N samples based on the `pd.SampleRate` property and plots `ceil(N)` number of data samples.

Specify the plotted data length relative to the onboard radio memory buffer size.

Radio Device	Memory Buffer Size	Maximum Data Samples
USRP N310	2 GB	2^{29}
USRP N320	2 GB	2^{29}
USRP N321	2 GB	2^{29}
USRP X310	1 GB	2^{28}
USRP X410	4 GB	2^{30}

Note Plotted and transmit data samples are buffered in the onboard radio memory. Therefore, when specifying the plotted data length, you must also take into account the length of the transmit waveform of any continuous transmission that you specify when calling the `transmit` object function with the `pd` input.

Example: `seconds(5)`

Data Types: `double` | `duration`

Output Arguments

droppedSamples — Status of dropped samples

1 | 0

Status of dropped samples, returned as one of these logical values.

- 1 — Samples are dropped while plotting the signals.
- 0 — Samples are not dropped while plotting the signals.

Use the `DroppedSamplesAction` property of the `pd` input to specify the behavior of the `plotThreshold` function upon dropped samples.

Data Types: `logical`

Version History

Introduced in R2022a

See Also

Functions

`capture`

radioConfigurations

List saved radio setup configurations

Syntax

```
radios = radioConfigurations
```

Description

`radios = radioConfigurations` lists all radio setup configurations that you saved using the Radio Setup wizard. Use this function to identify your radio when you create the `preambleDetector`, `basebandReceiver`, `basebandTransceiver`, or `basebandTransmitter` objects.

Examples

List Radio Setup Configurations

```
radios = radioConfigurations;
```

Specify the name of a saved radio setup configuration when creating an application object, for example, a preamble detector object.

```
radioName = radios(1).Name;  
pd = preambleDetector(radioName);
```

Output Arguments

radios — Radio setup configurations

structure array

Radio setup configurations, returned as a structure array. Each structure contains the name of a radio setup configuration and the associated radio device and IP address information.

Data Types: `struct`

Version History

Introduced in R2022a

See Also

Objects

`preambleDetector` | `basebandReceiver` | `basebandTransceiver` | `basebandTransmitter`

Topics

“Supported Radio Devices”

“Connect and Set Up NI USRP Radios”

stopTransmission

Stop transmission from preamble detector

Syntax

```
stopTransmission(pd)
```

Description

`stopTransmission(pd)` stops continuous IQ waveform transmission to the air from the preamble detector `pd`.

Examples

Configure Preamble Detector and Capture Test Waveform

Configure a preamble detector to continuously send a test waveform with a known preamble sequence and capture data samples of the transmitted waveform.

Define a preamble sequence with good correlation properties. For example, generate and normalize a Zadoff-Chu sequence of length 137.

```
zcseq = zadoffChuSeq(38,137);
preamble = zcseq/norm(zcseq,2);
```

Generate a test waveform.

```
prePadding = complex(zeros(999,1),zeros(999,1));
postPadding = complex(zeros(1000,1),zeros(1000,1));
testWaveform = [prePadding;zcseq*0.75;postPadding];
```

Create and configure a preamble detector object, specifying a radio setup configuration previously saved in the Radio Setup wizard.

```
pd = preambleDetector("MyRadio")
```

```
pd =
  preambleDetector with properties:
    CenterFrequency: 2.4000e+09
    RadioGain: 10
    Antennas: "RF0:RX2"
    SampleRate: 153600000
    CaptureDataType: "int16"
    DroppedSamplesAction: "error"
    Preamble: [16x1 double]
    ThresholdMethod: "adaptive"
    FixedThreshold: 0
    AdaptiveThresholdOffset: 0
    AdaptiveThresholdGain: 0
    TriggerOffset: 0
```

```
pd.SampleRate = 10.24e6;
```

Specify the preamble.

```
pd.Preamble = preamble;
```

Send the test waveform continuously.

```
transmit(pd, testWaveform, "continuous", ...  
        TransmitGain=30);
```

Capture 10 ms of data of the transmitted waveform.

```
[data, timestamp, droppedSamples, status] = capture(pd, milliseconds(10), milliseconds(50));
```

Stop test waveform transmission.

```
stopTransmission(pd);
```

Input Arguments

pd – Preamble detector

preambleDetector object

Preamble detector, specified as a preambleDetector object.

Note The first object function call in which you specify this object as an input requires a few extra seconds to load the application onto the hardware.

Version History

Introduced in R2022a

See Also

Functions

transmit

stopTransmission

Stop transmission from baseband transmitter or transceiver

Syntax

```
stopTransmission(bba)
```

Description

`stopTransmission(bba)` stops continuous IQ waveform transmission from the specified baseband transmitter or baseband transceiver `bba`.

Examples

Configure Baseband Transmitter and Transmit Waveform

Create a baseband transmitter object, specifying a radio setup configuration previously saved in the Radio Setup wizard.

```
bmtx = basebandTransmitter("MyRadio")  
bmtx =  
    basebandTransmitter with properties:  
        RadioGain: 10  
        CenterFrequency: 2.4000e+09  
        SampleRate: 250000000  
        Antennas: "RF0:TX/RX"
```

Set the baseband sample rate and center frequency.

```
bmtx.SampleRate = 122.88e6;  
bmtx.CenterFrequency = 2.2e9;
```

Generate random transmit waveform.

```
txWaveform = complex(randn(1000,1),randn(1000,1));
```

Transmit the generated waveform continuously with the radio associated with the baseband transmitter object using the default antenna.

```
transmit(bmtx,txWaveform,"continuous");
```

Stop the continuous transmission after 5 seconds.

```
pause(5);  
stopTransmission(bmtx);
```

Configure Baseband Transceiver to Transmit and Capture Data

Create a baseband transceiver object, specifying a radio setup configuration previously saved in the Radio Setup wizard.

```
bbtrx = basebandTransceiver("MyRadio")
bbtrx =
  basebandTransceiver with properties:
    TransmitRadioGain: 10
    TransmitCenterFrequency: 2.4000e+09
    TransmitAntennas: "RF0:TX/RX"
    CaptureRadioGain: 10
    CaptureCenterFrequency: 2.4000e+09
    CaptureAntennas: "RF0:RX2"
    CaptureDataType: "int16"
    DroppedSamplesAction: "error"
    SampleRate: 250000000
```

Set the baseband sample rate.

```
bbtrx.SampleRate = 122.88e6;
```

Set the transmit and capture center frequencies.

```
bbtrx.TransmitCenterFrequency = 2.2e9;
bbtrx.CaptureCenterFrequency = 2.2e9;
```

Generate random transmit waveform.

```
txWaveform = complex(randn(1000,1),randn(1000,1));
```

Transmit the generated waveform continuously with the radio associated with the baseband transceiver object using the default transmit antenna.

```
transmit(bbtrx,txWaveform,"continuous");
```

Capture IQ data with the radio associated with the baseband transceiver object using the default capture antenna.

```
[data,~] = capture(bbtrx,milliseconds(3));
```

Stop the continuous transmission after data capture is complete.

```
stopTransmission(bbtrx);
```

Input Arguments

bbba — Baseband application

basebandTransmitter object | basebandTransceiver object

Baseband application, specified as a basebandTransmitter object or basebandTransceiver object.

Note The first object function call in which you specify this object as an input requires a few extra seconds to load the application onto the hardware.

Version History

Introduced in R2022a

See Also

Functions

transmit

transmit

Transmit waveform using preamble detector

Syntax

```
transmit(pd,waveform,"continuous")
transmit( ____,Name=Value)
```

Description

`transmit(pd,waveform,"continuous")` continuously transmits the IQ waveform `waveform` to the air using the preamble detector `pd`. Use this function to send a test waveform to the air while trying to detect and capture a signal of interest using the same preamble detector. To stop the transmission, call `stopTransmission(pd)`.

`transmit(____,Name=Value)` specifies optional name-value arguments for the transmission, in addition to the input arguments from the previous syntax.

Examples

Configure Preamble Detector and Capture Test Waveform

Configure a preamble detector to continuously send a test waveform with a known preamble sequence and capture data samples of the transmitted waveform.

Define a preamble sequence with good correlation properties. For example, generate and normalize a Zadoff-Chu sequence of length 137.

```
zcseq = zadoffChuSeq(38,137);
preamble = zcseq/norm(zcseq,2);
```

Generate a test waveform.

```
prePadding = complex(zeros(999,1),zeros(999,1));
postPadding = complex(zeros(1000,1),zeros(1000,1));
testWaveform = [prePadding;zcseq*0.75;postPadding];
```

Create and configure a preamble detector object, specifying a radio setup configuration previously saved in the Radio Setup wizard.

```
pd = preambleDetector("MyRadio")
```

```
pd =
  preambleDetector with properties:
    CenterFrequency: 2.4000e+09
    RadioGain: 10
    Antennas: "RF0:RX2"
    SampleRate: 153600000
    CaptureDataType: "int16"
    DroppedSamplesAction: "error"
```

```

        Preamble: [16x1 double]
        ThresholdMethod: "adaptive"
        FixedThreshold: 0
    AdaptiveThresholdOffset: 0
        AdaptiveThresholdGain: 0
        TriggerOffset: 0
    
```

```
pd.SampleRate = 10.24e6;
```

Specify the preamble.

```
pd.Preamble = preamble;
```

Send the test waveform continuously.

```
transmit(pd, testWaveform, "continuous", ...
    TransmitGain=30);
```

Capture 10 ms of data of the transmitted waveform.

```
[data, timestamp, droppedSamples, status] = capture(pd, milliseconds(10), milliseconds(50));
```

Stop test waveform transmission.

```
stopTransmission(pd);
```

Input Arguments

pd — Preamble detector

preambleDetector object

Preamble detector, specified as a preambleDetector object.

Note The first object function call in which you specify this object as an input requires a few extra seconds to load the application onto the hardware.

waveform — IQ waveform to transmit

column vector of complex values

IQ waveform to transmit, specified as a column vector of complex values.

If you specify a waveform with a single or double data type, you must scale the transmit data sample values to the range [-1, 1).

The waveform length must be relative to the onboard radio memory buffer size.

Radio Device	Memory Buffer Size	Maximum Data Samples
USRP N310	2 GB	2 ²⁹
USRP N320	2 GB	2 ²⁹
USRP N321	2 GB	2 ²⁹

Radio Device	Memory Buffer Size	Maximum Data Samples
USRP X310	1 GB	2^{28}
USRP X410	4 GB	2^{30}

Note

- Transmit data samples and capture or plotted data samples are buffered in the onboard radio memory. Therefore, when specifying the transmit waveform, take also into account the data capture length or plotted data length that you specify when calling the `capture` or `plotThreshold` object functions, respectively, with the `pd` input.
- To avoid underflow during the transmission of a waveform of length less than 513 samples, the function reserves up to 1024 samples on the onboard radio memory.
- If the `pd` object uses a Farrow rate converter to achieve the sample rate that you specify by the `pd.SampleRate` property, the object resamples the transmit waveform. The resulting waveform has an increased number of data samples. For more information, see “Baseband Sample Rate in NI USRP Radios”.

Data Types: `int16` | `single` | `double`

Complex Number Support: Yes

Name-Value Pair Arguments

Specify optional pairs of arguments as `Name1=Value1, . . . , NameN=ValueN`, where `Name` is the argument name and `Value` is the corresponding value. Name-value arguments must appear after other arguments, but the order of the pairs does not matter.

Example: `TransmitGain=50` applies a gain of 50 dB to the transmit waveform.

TransmitGain — Transmit gain in dB

10 (default) | positive numeric scalar

Transmit gain in dB, specified as a positive numeric scalar. The valid gain range depends on the radio device.

Radio Device	Transmit Radio Gain
USRP N310	0 dB to 65 dB
USRP N320	0 dB to 60 dB
USRP N321	0 dB to 60 dB
USRP X310	0 dB to 31.5 dB
USRP X410	0 dB to 60 dB

Data Types: `double`

TransmitCenterFrequency — Transmit center frequency in Hz

`pd.CenterFrequency` (default) | positive numeric scalar

Transmit center frequency in Hz, specified as a positive numeric scalar. The valid center frequency range depends on the radio device.

Radio Device	Center Frequency
USRP N310	1 MHz to 6 GHz
USRP N320	1 MHz to 6 GHz
USRP N321	1 MHz to 6 GHz
USRP X310	10 MHz to 6 GHz
USRP X410	1 MHz to 8 GHz

Data Types: double

TransmitAntennas — Transmit radio antenna

"RF0:TX/RX" or "RFA:TX/RX" (default) | string constant

Transmit radio antenna, specified as a string constant. Use this table to identify a supported radio antenna port on the radio device and the corresponding string constant that you can specify for this input.

Radio Device	Supported Antenna Port	Valid String Scalar
USRP N310	RF0 channel: TX/RX port	"RF0:TX/RX" (default)
	RF1 channel: TX/RX port	"RF1:TX/RX"
	RF2 channel: TX/RX port	"RF2:TX/RX"
	RF3 channel: TX/RX port	"RF3:TX/RX"
USRP N320	RF0 channel: TX/RX port	"RF0:TX/RX" (default)
	RF1 channel: TX/RX port	"RF1:TX/RX"
USRP N321	RF0 channel: TX/RX port	"RF0:TX/RX" (default)
	RF1 channel: TX/RX port	"RF1:TX/RX"
USRP X310	RFA channel: TX/RX port	"RFA:TX/RX" (default)
	RFB channel: TX/RX port	"RFB:TX/RX"
USRP X410	DB0 RF0 channel: TX/RX 0 port	"DB0:RF0:TX/RX0" (default)
	DB0 RF1 channel: TX/RX 0 port	"DB0:RF1:TX/RX0"
	DB1 RF0 channel: TX/RX 0 port	"DB1:RF0:TX/RX0"
	DB1 RF1 channel: TX/RX 0 port	"DB1:RF1:TX/RX0"

Data Types: string

Version History

Introduced in R2022a

See Also

Functions

stopTransmission

transmit

Transmit waveform using baseband transmitter or transceiver

Syntax

```
transmit(bba, waveform, mode)
```

Description

`transmit(bba, waveform, mode)` transmits the IQ waveform `waveform` to the air using the specified baseband transmitter or baseband transceiver `bba`. The input `mode` specifies continuous or single-shot transmission. To stop a continuous transmission, call `stopTransmission(bba)`.

Examples

Configure Baseband Transmitter and Transmit Waveform

Create a baseband transmitter object, specifying a radio setup configuration previously saved in the Radio Setup wizard.

```
bmtx = basebandTransmitter("MyRadio")
bmtx =
  basebandTransmitter with properties:
    RadioGain: 10
    CenterFrequency: 2.4000e+09
    SampleRate: 250000000
    Antennas: "RF0:TX/RX"
```

Set the baseband sample rate and center frequency.

```
bmtx.SampleRate = 122.88e6;
bmtx.CenterFrequency = 2.2e9;
```

Generate random transmit waveform.

```
txWaveform = complex(randn(1000,1), randn(1000,1));
```

Transmit the generated waveform continuously with the radio associated with the baseband transmitter object using the default antenna.

```
transmit(bmtx, txWaveform, "continuous");
```

Stop the continuous transmission after 5 seconds.

```
pause(5);
stopTransmission(bmtx);
```

Configure Baseband Transceiver to Transmit and Capture Data

Create a baseband transceiver object, specifying a radio setup configuration previously saved in the Radio Setup wizard.

```
bbtrx = basebandTransceiver("MyRadio")  
  
bbtrx =  
    basebandTransceiver with properties:  
  
        TransmitRadioGain: 10  
    TransmitCenterFrequency: 2.4000e+09  
        TransmitAntennas: "RF0:TX/RX"  
        CaptureRadioGain: 10  
    CaptureCenterFrequency: 2.4000e+09  
        CaptureAntennas: "RF0:RX2"  
        CaptureDataType: "int16"  
    DroppedSamplesAction: "error"  
        SampleRate: 250000000
```

Set the baseband sample rate.

```
bbtrx.SampleRate = 122.88e6;
```

Set the transmit and capture center frequencies.

```
bbtrx.TransmitCenterFrequency = 2.2e9;  
bbtrx.CaptureCenterFrequency = 2.2e9;
```

Generate random transmit waveform.

```
txWaveform = complex(randn(1000,1),randn(1000,1));
```

Transmit the generated waveform continuously with the radio associated with the baseband transceiver object using the default transmit antenna.

```
transmit(bbtrx,txWaveform,"continuous");
```

Capture IQ data with the radio associated with the baseband transceiver object using the default capture antenna.

```
[data,~] = capture(bbtrx,milliseconds(3));
```

Stop the continuous transmission after data capture is complete.

```
stopTransmission(bbtrx);
```

Input Arguments

bba — Baseband application

basebandTransmitter object | basebandTransceiver object

Baseband application, specified as a basebandTransmitter object or basebandTransceiver object.

Note The first object function call in which you specify this object as an input requires a few extra seconds to load the application onto the hardware.

waveform — IQ waveform to transmit

complex-valued column vector | complex-valued matrix

IQ waveform to transmit, specified as one of these options.

- Complex-valued column vector with even number of rows — Use this option to send an IQ waveform on a single transmit antenna.
- Complex-valued matrix with even number of rows — Use this option to send IQ waveforms on multiple transmit antennas. This option applies only when `bba` is a baseband transmitter. The number of antennas specified by the `Antennas` property of the `bba` input must match the number of matrix columns.

If you specify a waveform with a `single` or `double` data type, you must scale the transmit data sample values to the range `[-1, 1]`.

The waveform length across all applicable antennas must be relative to the onboard radio memory buffer size.

Radio Device	Memory Buffer Size	Maximum Data Samples
USRP N310	2 GB	2^{29}
USRP N320	2 GB	2^{29}
USRP N321	2 GB	2^{29}
USRP X310	1 GB	2^{28}
USRP X410	4 GB	2^{30}

Note

- Transmit and capture data samples on the baseband transceiver are buffered in the onboard radio memory. Therefore, if the `bba` input is a baseband transceiver, you must also take into account the data capture length that you specify when calling the `capture` object function with the `bba` input.
 - To avoid underflow during the transmission of a waveform of length less than 513 samples, the function reserves up to 1024 samples on the onboard radio memory.
 - If the `bba` object uses a Farrow rate converter to achieve the sample rate that you specify by the `bba.SampleRate` property, the object resamples the transmit waveform. The resulting waveform has an increased number of data samples. For more information, see “Baseband Sample Rate in NI USRP Radios”.
-

Data Types: `int16` | `single` | `double`
 Complex Number Support: Yes

mode — Transmission mode

`"continuous"` | `"once"`

Transmission mode, specified as one of these options.

- "continuous" — The function transmits the waveform waveform continuously to the air by repeating the data samples until you call `stopTransmission(bba)`.
- "once" — The function transmits the waveform waveform once in a single-shot transmission.

Data Types: `string`

Version History

Introduced in R2022a

See Also

Functions

`stopTransmission`