

**Using Your NI-488[®] and NI-488.2[™]
Subroutines for Visual Basic
for Windows**

February 1994 Edition

Part Number 320418-01

**© Copyright 1991, 1994 National Instruments Corporation.
All Rights Reserved.**

National Instruments Corporate Headquarters

6504 Bridge Point Parkway

Austin, TX 78730-5039

(512) 794-0100

Technical support fax: (800) 328-2203

(512) 794-5678

Branch Offices:

Australia (03) 879 9422, Austria (0662) 435986, Belgium 02/757.00.20,
Canada (Ontario) (519) 622-9310, Canada (Québec) (514) 694-8521,
Denmark 45 76 26 00, Finland (90) 527 2321, France (1) 48 14 24 24,
Germany 089/741 31 30, Italy 02/48301892, Japan (03) 3788-1921,
Netherlands 03480-33466, Norway 32-848400, Spain (91) 640 0085,
Sweden 08-730 49 70, Switzerland 056/27 00 20, U.K. 0635 523545

Limited Warranty

The media on which you receive National Instruments software are warranted not to fail to execute programming instructions, due to defects in materials and workmanship, for a period of 90 days from date of shipment, as evidenced by receipts or other documentation. National Instruments will, at its option, repair or replace software media that do not execute programming instructions if National Instruments receives notice of such defects during the warranty period. National Instruments does not warrant that the operation of the software shall be uninterrupted or error free.

A Return Material Authorization (RMA) number must be obtained from the factory and clearly marked on the outside of the package before any equipment will be accepted for warranty work. National Instruments will pay the shipping costs of returning to the owner parts which are covered by warranty.

National Instruments believes that the information in this manual is accurate. The document has been carefully reviewed for technical accuracy. In the event that technical or typographical errors exist, National Instruments reserves the right to make changes to subsequent editions of this document without prior notice to holders of this edition. The reader should consult National Instruments if errors are suspected. In no event shall National Instruments be liable for any damages arising out of or related to this document or the information contained in it.

EXCEPT AS SPECIFIED HEREIN, NATIONAL INSTRUMENTS MAKES NO WARRANTIES, EXPRESS OR IMPLIED, AND SPECIFICALLY DISCLAIMS ANY WARRANTY OF MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. CUSTOMER'S RIGHT TO RECOVER DAMAGES CAUSED BY FAULT OR NEGLIGENCE ON THE PART OF NATIONAL INSTRUMENTS SHALL BE LIMITED TO THE AMOUNT THEREFORE PAID BY THE CUSTOMER. NATIONAL INSTRUMENTS WILL NOT BE LIABLE FOR DAMAGES RESULTING FROM LOSS OF DATA, PROFITS, USE OF PRODUCTS, OR INCIDENTAL OR CONSEQUENTIAL DAMAGES, EVEN IF ADVISED OF THE POSSIBILITY THEREOF. This limitation of the liability of National Instruments will apply regardless of the form of action, whether in contract or tort, including negligence. Any action against National Instruments must be brought within one year after the cause of action accrues. National Instruments shall not be liable for any delay in performance due to causes beyond its reasonable control. The warranty provided herein does not cover damages, defects, malfunctions, or service failures caused by owner's failure to follow the National Instruments installation, operation, or maintenance instructions; owner's modification of

the product; owner's abuse, misuse, or negligent acts; and power failure or surges, fire, flood, accident, actions of third parties, or other events outside reasonable control.

Copyright

Under the copyright laws, this publication may not be reproduced or transmitted in any form, electronic or mechanical, including photocopying, recording, storing in an information retrieval system, or translating, in whole or in part, without the prior written consent of National Instruments Corporation.

Trademarks

NI-488[®] and NI-488.2[™] are trademarks of National Instruments Corporation.

Product and company names listed are trademarks or trade names of their respective companies.

Warning Regarding Medical and Clinical Use of National Instruments Products

National Instruments products are not designed with components and testing intended to ensure a level of reliability suitable for use in treatment and diagnosis of humans. Applications of National Instruments products involving medical or clinical treatment can create a potential for accidental injury caused by product failure, or by errors on the part of the user or application designer. Any use or application of National Instruments products for or involving medical or clinical treatment must be performed by properly trained and qualified medical personnel, and all traditional medical safeguards, equipment, and procedures that are appropriate in the particular situation to prevent serious injury or death should always continue to be used when National Instruments products are being used. National Instruments products are NOT intended to be a substitute for any form of established process, procedure, or equipment used to monitor or safeguard human health and safety in medical or clinical treatment.

Contents

About This Manual vii
 Organization of This Manual vii
 Conventions Used in This Manual viii
 Related Documentation ix
 Customer Communication ix

Chapter 1

General Information 1-1
 Visual Basic Files 1-1
 Programming Preparations 1-2
 Visual Basic NI-488 I/O Calls and Functions 1-3
 NI-488 IL Functions 1-6
 Dynamic Reconfiguration of Board and
 Device Characteristics 1-8
 Using the NI-488.2 Routine Examples 1-9

Chapter 2

Programming Examples 2-1
 Visual Basic NI-488.2 Programming Example 2-1
 Visual Basic Example Program–NI-488.2
 Routines 2-4
 GPIB Programming Examples 2-12
 Visual Basic Example Program–Device Functions 2-14
 Visual Basic Example Program–Board Functions 2-18

Appendix A

Multiline Interface Messages A-1

Appendix B

Customer Communication B-1

Glossary G-1

Figures

Figure 1-1. GPIBPROJ.MAK 1-3
Figure 2-1. VB488_2.MAK 2-3
Figure 2-2. VBDEVICE.MAK 2-13

Tables

Table 1-1. Visual Basic NI-488 Calls 1-4
Table 1-2. Functions That Alter Default Characteristics 1-8
Table 1-3. Visual Basic NI-488.2 Routines 1-9

About This Manual

This manual contains information for programming the NI-488.2 routines and the NI-488 functions in Visual Basic. The term *Visual Basic* as used in this manual refers to Microsoft Visual Basic for Windows.

This manual assumes that the driver is installed and that you are familiar with the driver operation and programming in Visual Basic.

Organization of This Manual

This manual is organized as follows.

- Chapter 1, *General Information*, contains information you need to prepare for programming the NI-488.2 driver in Visual Basic.
- Chapter 2, *Programming Examples*, contains programming examples for the NI-488.2 routines and NI-488 functions.
- Appendix A, *Multiline Interface Messages*, contains an interface message reference list, which describes the mnemonics and messages that correspond to the interface functions.
- Appendix B, *Customer Communication*, contains forms you can use to request help from National Instruments or to comment on our products and manuals.
- The *Glossary* contains an alphabetical list and description of terms used in this manual, including abbreviations, acronyms, metric prefixes, mnemonics, and symbols.

Conventions Used in This Manual

The following conventions are used in this manual:

<i>italic</i>	Italic text denotes emphasis, a cross reference, or an introduction to a key concept.
<i>bold italic</i>	Bold italic text denotes a note, caution, or warning.
monospace	Lowercase text in this font denotes text or characters that are to be literally input from the keyboard, sections of code, programming examples, and syntax examples. This font is also used for the proper names of disk drives, paths, directories, programs, subprograms, subroutines, device names, functions, variables, filenames, and extensions, and for statements and comments taken from program code.
bold monospace	Lowercase text in this font is used to highlight the location and usage of NI-488.2 routines and NI-488 functions on sample programs
◇	Angle brackets enclose the name of a key on the keyboard—for example, <PageDown>.
<Control>	Key names are capitalized.
IEEE 488 IEEE 488.2	IEEE 488 and IEEE 488.2 are used throughout this manual to refer to the ANSI/IEEE Standard 488.1-1987 and the ANSI/IEEE Standard 488.2-1987, respectively, which define the GPIB.
NI-488.2	NI-488.2 is used throughout this manual to refer to the NI-488.2 software unless otherwise noted.

Visual Basic Visual Basic is used throughout this manual to refer to Visual Basic for Windows unless otherwise noted.

Abbreviations, acronyms, metric prefixes, mnemonics, symbols, and terms are listed in the *Glossary*.

Related Documentation

The following documents contain information that you may find helpful as you read this manual:

- *NI-488.2 Software Reference Manual for MS-DOS, (part number 320282-01)*
- *ANSI/IEEE Standard 488.1-1987, IEEE Standard Digital Interface for Programmable Instrumentation*
- *ANSI/IEEE Standard 488.2-1987, IEEE Standard Codes, Formats, Protocols, and Common Commands*
- *Microsoft Visual Basic Programmer's Guide*

Customer Communication

National Instruments wants to receive your comments on our products and manuals. We are interested in the applications you develop with our products, and we want to help if you have problems with them. To make it easy for you to contact us, this manual contains comment and configuration forms for you to complete. These forms are in Appendix B, *Customer Communication*, at the end of this manual.

Chapter 1

General Information

This chapter contains information you need to prepare for programming the NI-488.2 driver in Visual Basic.

Visual Basic Files

The *NI-488.2 for Windows Language Interface for Microsoft Visual Basic* diskette contains the following files which are relevant to programming in Visual Basic.

The following are Microsoft Visual Basic language interface files.

VBIB . BAS	Visual Basic source file with NI-488 functions and NI-488.2 routines that call the GPIB . DLL.
NIGLOBAL . BAS	Visual Basic global module, includes certain predefined constant declarations.

The following is a skeleton for creating a new Visual Basic application project.

GPIBPROJ . MAK	skeleton's project file
GPIBPROJ . FRM	skeleton's form file

The following is a sample project that uses NI-488 board-level functions.

VBBOARD . MAK	sample's project file
VBBOARD . FRM	sample's form file
VBBOARD . EXE	sample made into an executable file

The following is a sample project that uses NI-488 device-level functions.

VBDEVICE . MAK	sample's project file
VBDEVICE . FRM	sample's form file
VBDEVICE . EXE	sample made into an executable file

The following is a sample project that uses NI-488.2 routines.

VB488_2.MAK	sample's project file
VB488_2.FRM	sample's form file
VB488_2.EXE	sample made into an executable file

Copy the Visual Basic distribution files to your work area and store the original diskettes in a safe place.

Programming Preparations

Both the NIGLOBAL.BAS and VBIB.BAS files must be included as part of your application project. The NIGLOBAL.BAS file contains all the GPIB-related variable declarations and constant definitions. Any global constants or type declarations that are part of your application should be included in this file. The VBIB.BAS file provides the interface to the NI-488 and NI-488.2 function calls in the GPIB.DLL.

An application project template, GPIBPROJ.MAK, is provided to make it easy to create a new Visual Basic GPIB application project. Open the project GPIBPROJ.MAK, add the code and forms necessary for your GPIB application, and save it as YOURPROJ.MAK. The GPIBPROJ.MAK file already includes NIGLOBAL.BAS and VBIB.BAS.

If you are using Microsoft Visual Basic 1.0, you must edit NIGLOBAL.BAS to define the constants TRUE and FALSE as follows:

```
Global Const True = -1
Global Const False = 0
```

In Microsoft Visual Basic 2.0 and higher, TRUE and FALSE are reserved words, therefore these constants are no longer defined in NIGLOBAL.BAS.




Figure 1-1. GPIBPROJ.MAK

For more details on creating new Visual Basic projects, forms, and controls, see the *Microsoft Visual Basic Programmer's Guide*.

Visual Basic NI-488 I/O Calls and Functions

The most commonly used I/O calls are `ibrd` and `ibwrt`. In Visual Basic, these functions read and write from a character string that can be approximately 65,535 bytes in length.

In addition, integer I/O calls (`ibrdi` and `ibwrti`) are provided for users who need to perform arithmetic operations on the data and want to avoid the overhead of converting to the character strings required by `ibrd` and `ibwrt` and back into the integer format for the arithmetic operations.

`ibrdi` and `ibwrti` are passed data in the form of an integer array, instead of a character string. Using these functions, you can access the data directly as integers instead of defining them as characters and then converting each pair of characters to an integer. Internally, the `ibwrti` function sends each integer to the GPIB in low-byte, high-byte order. The

`ibrdi` function reads a series of data bytes from the GPIB and stores them into the integer array in low-byte, high-byte order.

In addition to `ibrdi` and `ibwrti`, the asynchronous functions `ibrdia` and `ibwrtia` are provided to perform asynchronous integer reads and writes.

Table 1-1 contains a summary of the Visual Basic NI-488 calls. These calls have the same syntax as the QuickBASIC/BASIC NI-488 functions. For a more detailed description, see the *NI-488.2 Software Reference Manual for MS-DOS*.

The first argument of all function calls except `ibfind` and `ibdev` is the integer variable `ud`, which serves as a unit descriptor. Refer to the *IBFIND* and *IBDEV* function descriptions in Chapter 5, *NI-488 Software Characteristics and Functions*, of the *NI-488.2 Software Reference Manual for MS-DOS*, to determine the type of unit descriptor to use.

Table 1-1. Visual Basic NI-488 Calls

Call Syntax	Description
<code>ibask (ud%,option%,value%)</code>	Return information about software configuration parameters
<code>ibbna (ud%,bname\$)</code>	Change board of device
<code>ibcac (ud%,v%)</code>	Become Active Controller
<code>ibclr (ud%)</code>	Clear specified device
<code>ibcmd (ud%,cmd\$)</code>	Send commands from string
<code>ibcmda (ud%,cmd\$)</code>	Send commands asynchronously from string
<code>ibconfig (ud%,option%,value%)</code>	Configure the driver
<code>ibdev (board.index%,pad%,sad%,tmo%,eot%,eos%,ud%)</code>	Open and initialize an unused device when the device name is unknown

(continues)

Table 1-1. Visual Basic NI-488 Calls (continued)

Call Syntax	Description
ibdma (ud%,v%)	Enable/disable DMA
ibeos (ud%,v%)	Change/disable EOS mode
ibeot (ud%,v%)	Enable/disable END message
ibevent (ud%,event%)	Return the next event
ibfind (brdname\$,ud%)	Open device and return unit descriptor
ibgts (ud%,v%)	Go from Active Controller to standby
ibist (ud%,v%)	Set/clear ist
iblines (board.index%,lines%)	Get status of GPIB lines
ibln (ud%,pad%,sad%,listen%)	Check for presence of device on bus.
ibloc (ud%)	Go to local
ibonl (ud%,v%)	Place device online/offline
ibpad (ud%,v%)	Change primary address
ibpct (ud%)	Pass control
ibppc (ud%,v%)	Parallel poll configure
ibrd (ud%,rd\$)	Read data to string
ibrda (ud%,rd\$)	Read data asynchronously to string
ibrdf (ud%,filename\$)	Read data to file
ibrdkey [†] (ud%,rd\$)	Read data from a hardware key
ibrpp (ud%,ppr%)	Conduct a parallel poll
ibrsc (ud%,v%)	Request/release system control
ibrsp (ud%,spr%)	Return serial poll byte
ibrsv (ud%,v%)	Request service

(continues)

Table 1-1. Visual Basic NI-488 Calls (continued)

Call Syntax	Description
<code>ibsad (ud%,v%)</code>	Change secondary address
<code>ibsic (ud%)</code>	Send interface clear
<code>ibsre (ud%,v%)</code>	Set/clear remote enable line
<code>ibstop (ud%)</code>	Abort asynchronous operation
<code>ibtmo (ud%,v%)</code>	Change/disable time limit
<code>ibtrg (ud%)</code>	Trigger selected device
<code>ibwait (ud%,mask%)</code>	Wait for selected event
<code>ibwrt (ud%,wrt\$)</code>	Write data from string
<code>ibwrta (ud%,wrt\$)</code>	Write data asynchronously from string
<code>ibwrtf (ud%,filename\$)</code>	Write data from file
<code>ibwrtkey[†] (ud%,wrt\$)</code>	Write data to a hardware key
[†] <code>ibrdkey</code> and <code>ibwrtkey</code> are OEM functions. Refer to <i>NI-488 Hardware Key Functions Reference Guide</i> , for a detailed description of these functions.	

NI-488 IL Functions

Visual Basic, like QuickBASIC (versions 4.0 and later) and BASIC (version 7.0), supports both function and subroutine calls. The NI-488 routines are all Visual Basic subroutines. This interface has been expanded so that the NI-488 routines can be accessed as Visual Basic functions. Refer to *NI-488 IL Functions* in Chapter 5, *NI-488 Software Characteristics and Functions*, of the *NI-488.2 Software Reference Manual for MS-DOS*.

- All NI-488 subroutines (`ibrd`, `ibwrt`, ...) are available via the `Call` statement.
- The names of the new functions are identical to the existing subroutine names, except that the second letter of each name has been changed from `b` to `l`. For example, the subroutine `ibsic` is also available as the function `ilsic`.

- GPIB subroutine and function calls may be freely mixed throughout a Visual Basic project.
- The GPIB Visual Basic language interface file, `VBIB.BAS`, contains a complete list of all the subroutine and function declarations. The `NIGLOBAL.BAS` file contains the declaration of the global variables `ibsta`, `iberr`, `ibcnt`, and `ibcntl`. These two files must both be part of any GPIB Visual Basic application project.
- In general, the functions behave identically to the subroutines with the few exceptions noted in the following paragraph. The description of each subroutine found in this manual can be applied to the functions, except for the syntax-specific information.

Here are the differences between the existing subroutines and the `il-` functions.

- `ilfind` returns a descriptor associated with the specified board or device. Use this value in all subsequent functions that access that device. Normal usage would resemble the following.

```
ud% = ilfind ("GPIB0 ")
```

- `ildev` opens and initializes an unused device when the device name is unknown. Normal usage would resemble the following.

```
ud% = ildev (0, 6, &H67, 13, 7, 0)
```

- `ilcmd`, `ilcmda`, `ilrd`, `ilrda`, `ilwrt`, and `ilwrta` require a third parameter which specifies the number of bytes to transfer. The function syntax is as follows.

```
sta% = ilcmd (ud%, cmd$, cnt%)
sta% = ilcmda (ud%, cmd$, cnt%)
sta% = ilrd (ud%, rd$, cnt%)
sta% = ilrda (ud%, rd$, cnt%)
sta% = ilwrt (ud%, wrt$, cnt%)
sta% = ilwrta (ud%, wrt$, cnt%)
```

- All functions, except `ilfind` and `ildev`, return the value of `ibsta`, permitting the following construct.

```
If (ilrd (ud%, rd%, cnt%) < 0) Then call GPIBERROR
```


Dynamic Reconfiguration of Board and Device Characteristics

Some functions can be called during the execution of an application program to dynamically change some of the configured values. These functions are shown in Table 1-2.

Table 1-2. Functions That Alter Default Characteristics

Characteristic	Dynamically Changed by
Primary GPIB address	ibpad
Secondary GPIB address	ibsad
End-of-string (EOS) byte	ibeos
7- or 8-bit compare on EOS	ibeos
Set EOI with EOS on Write	ibeos
Terminate a Read on EOS	ibeos
Set EOI w/last byte of Write	ibeot
Change board assignment	ibbna
Enable or disable DMA	ibdma
Change or disable time limit	ibtmo
Request/release system control	ibrsc
Set/clear individual status bit	ibist
Set/change serial poll status byte	ibrsv
Set/clear Remote Enable line	ibsre
Most of the above and more	ibconfig

Using the NI-488.2 Routine Examples

Table 1-3 lists the call syntax for each NI-488.2 routine and a brief description of what each does in your Visual Basic application project. These calls have the same syntax as the QuickBASIC/BASIC NI-488 functions. For a more detailed description, see Chapter 4, *NI-488.2 Software Characteristics and Routines*, in the *NI-488.2 Software Reference Manual for MS-DOS*.

Table 1-3. Visual Basic NI-488.2 Routines

Call Syntax	Description
AllSpoll (board%,addresslist%(), resultlist%())	Serial poll all devices
DevClear (board%,address%)	Clear a single device
DevClearList (board%, addresslist%())	Clear multiple devices
EnableLocal (board%,addresslist%())	Enable operations from the front of a device
EnableRemote (board%, addresslist%())	Enable remote GPIB programming of devices
FindLstn (board%,addresslist%(), resultlist%(),limit%)	Find all Listeners
FindRQS (board%,addresslist%(), result%)	Determine which device is requesting service
PassControl (board%,address%)	Pass control to another device with Controller capability
PPoll (board%,result%)	Perform a parallel poll
PPollConfig (board%,address%, dataline%,sense%)	Configure a device for parallel polls
PPollUnconfig (board%, addresslist%())	Unconfigure devices for parallel polls
RcvRespMsg (board%,data\$, termination%)	Read data bytes from already addressed device
ReadStatusByte (board%,address%, result%)	Serial poll a single device to get its status byte

(continues)

Table 1-3. Visual Basic NI-488.2 Routines (continued)

Call Syntax	Description
Receive (board%,address%,data\$, termination%)	Read data bytes from a GPIB device
ReceiveSetup (board%,address%)	Prepare a particular device to send data bytes and prepare the board to read them
ResetSys (board%,addresslist%())	Initialize a GPIB system on three levels
Send (board%,address%,data\$, eotmode%)	Send data bytes to a single GPIB device
SendCmds (board%,commands\$)	Send GPIB command bytes
SendDataBytes (board%,data\$, eotmode%)	Send data bytes to already addressed devices
SendIFC (board%)	Clear the GPIB interface functions with IFC
SendList (board%,addresslist%(), data\$,eotmode%)	Send data bytes to multiple GPIB devices
SendLLO (board%)	Send the local lockout message to all devices
SendSetUp (board%,addresslist%())	Prepare particular devices to receive data bytes
SetRWLS (board%,addresslist%)	Place particular devices in the Remote with Lockout state
TestSRQ (board%,result%)	Determine the current state of the SRQ line
TestSys (board%,addresslist%, resultlist%())	Cause devices to conduct self-tests
Trigger (board%,address%)	Trigger a single device
TriggerList (board%,addresslist%())	Trigger multiple devices
WaitSRQ (board%,result%)	Wait until a device asserts Service Request

Chapter 2

Programming Examples

This chapter contains programming examples for the NI-488.2 routines and NI-488 functions. A detailed description of both the routines and functions can be found in the *NI-488.2 Software Reference Manual for MS-DOS*.

Visual Basic NI-488.2 Programming Example

You can take full advantage of the IEEE 488.2-1987 standard by using the NI-488.2 routines. These routines are completely compatible with the controller commands and protocols defined in IEEE 488.2.

The NI-488.2 routines are easy to learn and use. Only a few routines are needed for most application programs.

This example illustrates the programming steps that you can use to program a representative IEEE 488.2 instrument from your personal computer using the NI-488.2 routines. The NI-488.2 routines and subroutines are in bold text to highlight their location and usage within the program. The applications are written in Visual Basic. The target instrument is a Fluke 45. The purpose here is to explain how to use the driver to execute NI-488.2 programming and control sequences and not how to determine those sequences.

Note: *For a more detailed description of each step, refer to Chapter 3, Writing an Advanced Program Using NI-488.2 Routines, in the getting started manual that you received with your interface board.*

1. Load in the definitions of the NI-488.2 routines from a file that is on your distribution diskette.
2. Initialize the IEEE 488 bus and the interface board Controller circuitry so that the IEEE 488 interface for each device is quiescent, and so that the interface board is Controller-In-Charge and is in the Active Controller State (CACS).

3. Find all of the following Listeners.
 - a. Find all of the instruments attached to the IEEE 488 bus.
 - b. Create an array that contains all of the IEEE 488 primary addresses that could possibly be connected to the IEEE 488 bus.
 - c. Find out which, if any, device or devices are connected.
4. Send an identification query to each device for identification.
5. Initialize the instrument as follows.
 - a. Clear the multimeter.
 - b. Send the IEEE 488.2 Reset command to the meter.
6. Instruct the meter to measure volts alternating current (VAC) using auto-ranging (AUTO), to wait for a trigger from the Controller before starting a measurement (TRIGGER 2), and to assert the IEEE 488 Service Request signal line, SRQ, when the measurement has been completed and the meter is ready to send the result (*SRE 16).
7. Perform the following steps for each measurement.
 - a. Send the TRIGGER command to the multimeter. The command "VAL1?" instructs the meter to send the next triggered reading to its IEEE 488.2 output buffer.
 - b. Wait until the Fluke 45 asserts Service Request (SRQ) to indicate that the measurement is ready to be read.
 - c. Read the status byte to determine if the measured data is valid or if a fault condition exists. You can find out by checking the message available (MAV) bit, bit 4 in the status byte.
 - d. If the data is valid, read 10 bytes from the Fluke 45.
8. End the session.

Figure 2-1 shows the Visual Basic environment with VB488_2.MAK loaded. You can enter the **Number of Readings** used by your Fluke 45. Clicking on **Run Test** runs the test program and clicking on **Quit** exits the test program.




Figure 2-1. VB488_2.MAK

Visual Basic Example Program—NI-488.2 Routines

```

'
' This function is the test program.
'
Sub RunTest ()

    Static ReadingsArray#(100)

' Clear status and calculated data displays.

    CurrentSample.Text = ""
    CurrentReading.Text = ""
    AvgVal.Text = ""
    StdDevVal.Text = ""

    Call ClearReadingsList

' Disable user inputs during test.

    QuitButton.Enabled = 0

' The number of readings must be less than 101.

    NumberOfReadings% = Val(NumReadings.Text)
    If NumberOfReadings% > 100 Then
        NumberOfReadings% = 50
    End If
    NumReadings.Text = Format$(NumberOfReadings%, "#")

    Status.Caption = " FINDING "
    Status.Refresh

    Do
        tmp% = Meter_Init()
    Loop Until tmp% = 1

    AvgValue# = 0#
    Status.Caption = " RUNNING "
    Status.Refresh

' Collect the readings.

    For i% = 1 To NumberOfReadings%
        Do
            tmp% = Meter_Get_Reading(ReadingsArray#(i%))
            Loop Until tmp% = 1
            CurrentSample.Text = Str$(i%)

```

```

    CurrentReading.Text = FormatReading$(
        (ReadingsArray#(i%))
    AvgValue# = AvgValue# + ReadingsArray#(i%)
Next i%

' Display the list of readings.

For i% = 1 To NumberOfReadings%
    If i% < 10 Then
        DispStr$ = Format$(i%, "  #") + Space$(16) +
            FormatReading$(ReadingsArray#(i%))
    Else
        DispStr$ = Format$(i%, " #") + Space$(16) +
            FormatReading$(ReadingsArray#(i%))
    End If
    ReadingsList.AddItem DispStr$
Next i%

' Put the board off-line

If (ilowl(0, 0) < 0) Then
    Call ErrMsg("Error putting board off-line. ")
End If

' Calculate the average and standard deviation values.

AvgValue# = AvgValue# / NumberOfReadings%
AvgVal.Text = Format$(AvgValue#, "0.00000")
StdDev# = 0#
For i% = 1 To NumberOfReadings%
    StdDev# = StdDev# +
        (ReadingsArray#(i%) - AvgValue#) ^ 2
Next i%
StdDev# = Sqr(StdDev# / NumberOfReadings%)
StdDevVal.Text = Format$(StdDev#, "0.00000")

' Enable user inputs.

QuitButton.Enabled = 1
CurrentSample.Text = ""
CurrentReading.Text = ""
Status.Caption = " STOPPED "
End Sub

' This function initialized the meter by calling ibfind
' to open the DLL, ibpad to set the correct address of

```



```

' the meter, and ibclr to clear the instrument to a
' known default state.

Function Meter_Init () As Integer
  ReDim result%(30)
  ReDim instruments%(31)      ' array of primary addresses

  Fluke% = -1

  ' Our board needs to be the Controller-In-Charge in
  ' order to find all listeners on the GPIB.
  ' To accomplish this, the subroutine SendIFC is
  ' called.  If the error bit EERR is set in IBSTA%,
  ' call GPIBERR with an error message.

  Call SendIFC(0)
  If ibsta% And EERR Then
    Call ErrMsg("Error sending IFC.")
    Meter_Init = 0
    Exit Function
  End If

  ' Create an array containing all valid GPIB primary
  ' addresses.  This array (INSTRUMENTS%) will be given
  ' to the subroutine FindLstn to find all listeners.
  ' The constant NOADDR, defined in NIGLOBAL.BAS,
  ' signifies the end of the array.

  For k% = 0 To 30
    instruments%(k%) = k%
  Next k%
  instruments%(31) = NOADDR

  ' Print "Finding all listeners on the bus..."

  Call FindLstn(0, instruments%(), result%(), 31)
  If ibsta% And EERR Then
    Call ErrMsg("Error finding all listeners.")
    Meter_Init = 0
    Exit Function
  End If

  ' Assign the value of IBCNT% to the variable
  ' NUM_LISTENERS%.  The GPIB board is detected
  ' as a listener on the bus; however, it is
  ' not included in the final count of the
  ' number of listeners.  Print the number of
  ' listeners found.

```

```

num_listeners% = ibcnt% - 1

' Send the *IDN? command to each device that was
' found. Your GPIB board is at address 0 by
' default. The board does not respond to *IDN?,
' so skip it.

' Establish a For loop to determine if the Fluke
' 45 is a listener on the GPIB. The variable k%
' will serve as a counter for the For loop and as
' the index to the array RESULT%.

For k% = 1 To num_listeners%

' Send the identification query to each listen
' address in the array RESULT%. The constant
' NLEnd, defined in NIGLOBAL.BAS, instructs the
' subroutine Send to append a linefeed character
' with EOI asserted to the end of the message.
' If the error bit EERR is set in IBSTA%,
' call GPIBERR with an error message.

    Call Send(0, result%(k%), "*IDN?", NLEnd)
    If ibsta% And EERR Then
        Call ErrMsg("Error sending '*IDN?'. ")
        Meter_Init = 0
        Exit Function
    End If

' Read the name identification response
' returned from each device. Store the response
' in string READING$. The constant STOPend,
' defined in NIGLOBAL.BAS, instructs the
' subroutine Receive to terminate the read when
' END is detected. If the error bit EERR is
' set in IBSTA%, call GPIBERR with an error message.

    Reading$ = Space$(&H32)
    Call Receive(0, result%(k%), Reading$, STOPend)
    If ibsta% And EERR Then
        Call ErrMsg("Error in receiving response
            to '*IDN?'. ")
        Meter_Init = 0
        Exit Function
    End If

```

```
' The low byte of the listen address is the primary
' address. Assign the variable PAD% the primary
' address of the device.
```

```
    pad% = result%(k%) And &HFF
```

```
' Determine if the name identification is the
' Fluke 45. If it is the Fluke 45, assign PAD%
' to FLUKE%, print message that the Fluke 45 has
' been found, call the subroutine FOUND, branch
' to the label PROGEND.
```

```
    If Left$(Reading$, 9) = "Fluke, 45" Then
        Fluke% = pad%
        Exit For
    End If
```

```
Next k%                ' End of For loop
```

```
If (Fluke% <> -1) Then
    tmp$ = "Found the Fluke 45 at primary address " +
        Str$(Fluke%)
    MsgBox tmp$, 0
Else
    Call ErrMsg("Did not find Fluke 45. Check your
        GPIB cables and try again.")
    Meter_Init = 0
    Exit Function
End If
```

```
' DevClear will send the GPIB Selected Device Clear
' (SDC) command message to the Fluke 45. If the
' error bit EERR is set in IBSTA%, call GPIBERR
' with an error message.
```

```
Call DevClear(0, Fluke%)
If ibsta% And EERR Then
    Call ErrMsg("Error in clearing the Fluke 45. ")
    Meter_Init = 0
    Exit Function
End If
```

```
' Reset the Fluke 45 (*RST). Program the Fluke 45 to
' measure using volts alternating current (VAC) using
' autoranging (AUTO), to wait for a trigger from the
' board (TRIGGER 2), and then assert the IEEE 488
' Service Request, SRQ. When the measurement
' has been completed and the Fluke 45 is ready to send
' the result (*SRE 16).
```

```
Call Send(0, Fluke%, "*RST; VAC; AUTO; TRIGGER 2;
           *SRE 16", NLen)
```

```
If ibsta% And EERR Then
    Call ErrMsg("Error in writing commands to
               Fluke 45. ")
    Meter_Init = 0
    Exit Function
End If
```

```
Meter_Init = 1
```

End Function

Function Meter_Get_Reading (reading_val#) As Integer

```
' Trigger the Fluke 45 by sending the trigger
' command (*TRG) and request a measurement by
' sending the command "VAL1?". If the error bit
' EERR is set in IBSTA%, call GPIBERR with an
' error message.
```

```
Static Status As Integer
```

```
Call Send(0, Fluke%, "*TRG; VAL1?", NLen)
```

```
If ibsta% And EERR Then
    Call ErrMsg("Error sending trigger. ")
    Meter_Get_Reading = 0
    Exit Function
End If
```

```
' Wait for the Fluke 45 to assert SRQ. This means it is
' ready to send a measurement. If SRQ is not
' asserted within the timeout period, call GPIBERR
' with an error message. The timeout period by
' default is 10 seconds.
```

```
Call WaitSRQ(0, SRQasserted%)
```

```
If SRQasserted% = 0 Then
    Call ErrMsg("Error: Fluke 45 did not assert SRQ. ")
```

```

    Meter_Get_Reading = 0
    Exit Function
End If

' Read the serial poll status byte of the Fluke 45.
' If the error bit EERR is set in IBSTA%, call
' GPIBERR with an error message.

Call ReadStatusByte(0, Fluke%, Status%)
If ibsta% And EERR Then
    Call ErrMsg("Error: could not read status byte from
                Fluke 45. ")
    Meter_Get_Reading = 0
    Exit Function
End If

' Check to see if the Message Available Bit (bit 4)
' of the return status byte is set. If this bit is
' not set, print the status byte and call GPIBERR
' with an error message.

If (Status% And &H10) <> &H10 Then
    Call ErrMsg("Error: status byte does not have
                MAV bit (&H10) set. ")
    Meter_Get_Reading = 0
    Exit Function
End If

' Read the Fluke 45 measurement. Store the
' measurement in string READING$. The constant
' STOPend, defined in NIGLOBAL.BAS, instructs the
' subroutine Receive to terminate the read when
' END is detected. If the error bit EERR is set
' in IBSTA%, call GPIBERR with an error
' message.

Reading$ = Space$(20)
Call Receive(0, Fluke%, Reading$, STOPend)
If ibsta% And EERR Then
    Call ErrMsg("Error getting reading from Fluke 45. ")
    Meter_Get_Reading = 0
    Exit Function
End If

```

```
' The intent of this next line is to tack a ';' onto  
' the end of the Reading$. This is so the subsequent  
' call to Val works properly.
```

```
Reading$ = Mid$(Reading$, 1, ibcnt%) + ";"  
reading_val# = Val(Reading$)
```

```
Meter_Get_Reading = 1
```

End Function

GPIB Programming Examples

The sample project that follows illustrates the programming steps that you can use to program a representative IEEE 488 instrument from your personal computer using the NI-488 functions. The NI-488 functions and subroutines are in bold text to highlight their location and usage within the program. The target instrument is a Fluke 45 dual display multimeter. The purpose of this example is to illustrate both how you can use the NI-488 functions to program an IEEE 488 instrument and how you can use Visual Basic to create a user-friendly graphical environment in which to run your application.

The following sequence of actions is necessary to program the Fluke 45 to make and return measurements of a high frequency AC voltage signal in the autoranging mode.

1. Initialize the GPIB interface and Fluke 45.
2. Instruct the Fluke 45 to measure volts alternating current (VAC) using autoranging (AUTO), to wait for a trigger from the Controller before starting a measurement (TRIGGER 2), and to assert the IEEE 488 Service Request signal line, SRQ, when the measurement has been completed and the meter is ready to send the result (*SRE 16).
3. Complete the following steps for each measurement.
 - a. Trigger the Fluke 45 and then write "VAL1?" to the Fluke 45 to tell it to send the next reading to its IEEE 488 output buffer.
 - b. Wait for the Fluke 45 to assert SRQ to indicate that the next measurement is ready.
 - c. Serial poll the Fluke 45 to determine whether the measured data is valid or if a fault condition exists. The measured data is valid if the MAV (message available) bit (bit 4) is set in the status byte returned from the serial poll.
 - d. If the data is valid, then read 10 bytes from the Fluke 45.

Figure 2-2 shows the graphical user interface window which is opened when you run one of the GPIB sample projects. You can enter the **Number of Readings** and the **Primary Address** used by your Fluke 45. Clicking on **Run Test** runs the test program and clicking on **Quit** exits the test program.




Figure 2-2. VBDEVICE.MAK

Visual Basic Example Program—Device Functions

```

Sub RunTest ( )

    Static ReadingsArray#(100)

' Clear status and calculated data displays.

    CurrentSample.Text = ""
    CurrentReading.Text = ""
    AvgVal.Text = ""
    StdDevVal.Text = ""

    Call ClearReadingsList

' Disable the user inputs during test.

    QuitButton.Enabled = 0

' The number of readings must be less than 101.

    NumberOfReadings% = Val(NumReadings.Text)
    If NumberOfReadings% > 100 Then
        NumberOfReadings% = 50
    End If
    NumReadings.Text = Format$(NumberOfReadings%, "#")

    Do
        tmp% = Meter_Init(Val(addr.Text))
    Loop Until tmp% = 1

    AvgValue# = 0#
    status.Caption = " RUNNING "
    status.Refresh

' Collect the readings.

    For i% = 1 To NumberOfReadings%
        Do
            tmp% = Meter_Get_Reading(ReadingsArray#(i%))
        Loop Until tmp% = 1
        CurrentSample.Text = Str$(i%)
        CurrentReading.Text = FormatReading$(
            ReadingsArray#(i%))
        AvgValue# = AvgValue# + ReadingsArray#(i%)
    Next i%

```

```

' Display the list of readings.

For i% = 1 To NumberOfReadings%
  If i% < 10 Then
    DispStr$ = Format$(i%, " #") + Space$(16) +
              FormatReading$(ReadingsArray#(i%))
  Else
    DispStr$ = Format$(i%, " #") + Space$(16) +
              FormatReading$(ReadingsArray#(i%))
  End If
  ReadingsList.AddItem DispStr$
Next i%

' Put the device off-line.

If (ilowl(Dev%, 0) < 0) Then
  Call ErrMsg("Error putting device off-line.")
End If

' Calculate the average and standard deviation values.

AvgValue# = AvgValue# / NumberOfReadings%
AvgVal.Text = Format$(AvgValue#, "0.00000")
StdDev# = 0#
For i% = 1 To NumberOfReadings%
  StdDev# = StdDev# +
            (ReadingsArray#(i%) - AvgValue#) ^ 2
Next i%
StdDev# = Sqr(StdDev# / NumberOfReadings%)
StdDevVal.Text = Format$(StdDev#, "0.00000")

' Enable the user inputs.

QuitButton.Enabled = 1
CurrentSample.Text = ""
CurrentReading.Text = ""
status.Caption = " STOPPED "
End Sub

Function Meter_Get_Reading (reading_val#) As Integer

  ' Trigger the Fluke 45.

```

```
If (iltrg(Dev%) < 0) Then
    Call ErrMsg("Error triggering device.")
    Meter_Get_Reading = 0
    Exit Function
End If

' Request the triggered measurement by sending
' VAL1?

wrtbuf$ = "VAL1?"
If (ilwrt(Dev%, wrtbuf$, Len(wrtbuf$)) < 0) Then
    Call ErrMsg("Error writing to device.")
    Meter_Get_Reading = 0
    Exit Function
End If

' Wait for the Fluke 45 to request service (RQS)
' or timeout.

If (ilwait(Dev%, &H4800) < 0) Then
    Call ErrMsg("Error waiting for RQS or TIMO.")
    Meter_Get_Reading = 0
    Exit Function
End If
If (ibsta And &H4000) Then
    Call ErrMsg("Wait for RQS timed out.")
    Meter_Get_Reading = 0
    Exit Function
End If

' If the returned status byte is &H50, then the
' Fluke 45 has valid data to send.

If (ilrsp(Dev%, SPollByte%) < 0) Then
    Call ErrMsg("Error serial polling the device.")
    Meter_Get_Reading = 0
    Exit Function
End If
If (SPollByte% <> &H50) Then
    Call ErrMsg("Serial poll byte is NOT &H50.")
    Meter_Get_Reading = 0
    Exit Function
End If

' Read the Fluke 45 measurement.
```

```

rdbuf$ = Space$(10)
If (ilrd(Dev%, rdbuf$, Len(rdbuf$)) < 0) Then
    Call ErrMsg("Error reading from device.")
    Meter_Get_Reading = 0
    Exit Function
End If
reading_val# = Val(rdbuf$)

Meter_Get_Reading = 1
End Function

Function Meter_Init (addr%) As Integer
Dev% = ilfind("DEV1")
If Dev% < 0 Then
    MsgBox "Error opening device. I'm quitting!", 16
    End
End If
If (ilpad(Dev%, addr%) < 0) Then
    Call ErrMsg("Error device's address.")
    Meter_Init = 0
    Exit Function
End If
If (ilclr(Dev%) < 0) Then
    Call ErrMsg("Error clearing device.")
    Meter_Init = 0
    Exit Function
End If

' Reset the Fluke 45 (*RST), program the Fluke 45
' to measure using volts alternating current (VAC)
' using autoranging (AUTO), to wait for a trigger
' from the board (TRIGGER 2), and
' then assert the IEEE 488 Service Request, SRQ,
' when the measurement has been completed and the
' Fluke 45 is ready to send the result (*SRE 16).

wrtbuf$ = "*RST; VAC; AUTO; TRIGGER 2; *SRE 16"
If (ilwrt(Dev%, wrtbuf$, Len(wrtbuf$)) < 0) Then
    Call ErrMsg("Error initializing device.")
    Meter_Init = 0
    Exit Function
End If

Meter_Init = 1

End Function

```

Visual Basic Example Program—Board Functions

```

' This function is the test program.

Sub RunTest ()

    Static ReadingsArray#(100)

' Clear status and calculated data displays.

    CurrentSample.Text = ""
    CurrentReading.Text = ""
    AvgVal.Text = ""
    StdDevVal.Text = ""

    Call ClearReadingsList

' Disable the user inputs during test.

    QuitButton.Enabled = 0

' The number of readings must be less than 101.

    NumberOfReadings% = Val(NumReadings.Text)
    If NumberOfReadings% > 100 Then
        NumberOfReadings% = 50
    End If
    NumReadings.Text = Format$(NumberOfReadings%, "#")

    Do
        tmp% = Meter_Init(Val(addr.Text))
    Loop Until tmp% = 1

    AvgValue# = 0#
    status.Caption = "RUNNING "
    status.Refresh

' Collect the readings.

    For i% = 1 To NumberOfReadings%
        Do
            tmp% = Meter_Get_Reading(ReadingsArray#(i%))
        Loop Until tmp% = 1
        CurrentSample.Text = Str$(i%)
        CurrentReading.Text = FormatReading$(
            ReadingsArray#(i%))
        AvgValue# = AvgValue# + ReadingsArray#(i%)
    Next i%

```

```

' Display the list of readings.

For i% = 1 To NumberOfReadings%
  If i% < 10 Then
    DispStr$ = Format$(i%, "  #") + Space$(16) +
              FormatReading$(ReadingsArray#(i%))
  Else
    DispStr$ = Format$(i%, " #") + Space$(16) +
              FormatReading$(ReadingsArray#(i%))
  End If
  ReadingsList.AddItem DispStr$
Next i%

' Put the board off-line.

If (ilOnl(Bd%, 0) < 0) Then
  Call ErrMsg("Error putting board off-line. Press
              OK to ignore or Cancel to quit.")
End If

' Calculate the average and standard deviation values.

AvgValue# = AvgValue# / NumberOfReadings%
AvgVal.Text = Format$(AvgValue#, "0.00000")
StdDev# = 0#
For i% = 1 To NumberOfReadings%
  StdDev# = StdDev# +
            (ReadingsArray#(i%) - AvgValue#) ^ 2
Next i%
StdDev# = Sqr(StdDev# / NumberOfReadings%)
StdDevVal.Text = Format$(StdDev#, "0.00000")

' Enable user inputs.

QuitButton.Enabled = 1
CurrentSample.Text = ""
CurrentReading.Text = ""
status.Caption = " STOPPED "
End Sub

' This function reads from the instrument a string
' containing a reading in ASCII format. The value
' in the string is converted and returned to you
' as a real number so you can use the value for
' other calculations and decision making.

```

Function Meter_Get_Reading (reading_val#) As Integer

```

' Trigger the Fluke 45.

  trg$ = "?_" + Chr$(&H20 + (Val(addr.Text))) +
        "@" + Chr$(&H8)
  If (ilcmd(Bd%, trg$, 5) < 0) Then
    Call ErrMsg("Error triggering device.")
    Meter_Get_Reading = 0
    Exit Function
  End If

' Request the triggered measurement by sending VAL1?

  wrtbuf$ = "VAL1?"
  If (ilwrt(Bd%, "VAL1?", 5) < 0) Then
    Call ErrMsg("Error writing to device.")
    Meter_Get_Reading = 0
    Exit Function
  End If

' Wait for the Fluke 45 to request service (SRQI) or
' timeout (TIMO).

  If (ilwait(Bd%, &H5000) < 0) Then
    Call ErrMsg("Error waiting for SRQI or TIMO.")
    Meter_Get_Reading = 0
    Exit Function
  End If
  If (ibsta And &H4000) Then
    Call ErrMsg("Wait for SRQI timed out.")
    Meter_Get_Reading = 0
    Exit Function
  End If

' Conduct a serial poll by doing the following:
' 1. send UNT UNL SPE fluke-talk-address board-
'    listen-address
' 2. read the 1 byte serial poll response
' 3. send SPD

' UNT is untalk (&H5F = '_'), UNL is unlisten
' (&H3F = '?'), SPE is serial poll enable (&H18),
' fluke-talk-address is (pad + &H40), board-listen-
' address is (0 + &H20 = ' '), and SPD is serial
' poll disable (&H19). See Appendix A of the
' Software Reference Manual for a complete
' description of the GPIB command bytes.

```

```

cmd$ = "_" + Chr$(&H18) + Chr$(&H40 +
    (Val(addr.Text))) + " "
If (ilcmd(Bd%, cmd$, Len(cmd$)) < 0) Then
    Call ErrMsg("Error sending UNT UNL SPE MTA MLA
        to device.")
End If
rdbuf$ = Space$(1)
If (ilrd(Bd%, rdbuf$, 1) < 0) Then
    Call ErrMsg("Error reading response from device.")
    Meter_Get_Reading = 0
    Exit Function
End If
If (Asc(rdbuf$) <> &H50) Then
    Call ErrMsg("Serial poll byte is NOT &H50.")
    Meter_Get_Reading = 0
    Exit Function
End If
cmd$ = Chr$(&H19)
If (ilcmd(Bd%, cmd$, 1) < 0) Then
    Call ErrMsg("Error sending SPD to device.")
    Meter_Get_Reading = 0
    Exit Function
End If

' Read the Fluke 45 measurement.

rdbuf$ = Space$(10)
If (ilrd(Bd%, rdbuf$, Len(rdbuf$)) < 0) Then
    Call ErrMsg("Error reading from device.")
    Meter_Get_Reading = 0
    Exit Function
End If
reading_val# = Val(rdbuf$)

Meter_Get_Reading = 1
End Function

' This function initializes the meter by calling ibfind
' to open the DLL, ibpad to set the correct address of
' the meter, and ibclr to clear the instrument to a
' known default state.

```


Function Meter_Init (addr%) As Integer

```

    Bd% = ilfind("GPIB0")
    If Bd% < 0 Then
        MsgBox "Error finding board. I'm quitting!", 16
        End
    End If

' Send interface clear (IFC) to all devices.

    If (ilsic(Bd%) < 0) Then
        Call ErrMsg("Error with send IFC.")
        Meter_Init = 0
        Exit Function
    End If

' Turn on the Remote Enable (REN) signal.

    If (ilsre(Bd%, 1) < 0) Then
        Call ErrMsg("Error with send IFC.")
        Meter_Init = 0
        Exit Function
    End If

' Inhibit front panel control with the Local Lockout
' (LLO) command (&H11). Place the Fluke 45 in remote
' mode by addressing it to listen. The listen address
' is the primary address plus &H20. Send the Device
' Clear (DCL) message (&H14) to clear internal device
' functions. Finally, address the GPIB interface
' board to talk by sending its talk address (0 + &H40).

    cmd$ = Chr$(&H11) + Chr$(&H20 + addr%) +
        Chr$(&H14) + Chr$(&H40)
    If (ilcmd(Bd%, cmd$, 4) < 0) Then
        Call ErrMsg("Error with sending command bytes.")
        Meter_Init = 0
        Exit Function
    End If

' Reset the Fluke 45 (*RST), program the Fluke 45 to
' measure using volts alternating current (VAC) using
' autoranging (AUTO), to wait for a trigger from the
' board (TRIGGER 2), and then assert the
' IEEE 488 Service Request, SRQ, when the measurement
' has been completed and the Fluke 45 is ready to send
' the result (*SRE 16).

```

```
wrtbuf$ = "*RST; VAC; AUTO; TRIGGER 2; *SRE 16"  
If (ilwrt(Bd%, wrtbuf$, Len(wrtbuf$)) < 0) Then  
    Call ErrMsg("Error writing commands to Fluke 45.")  
    Meter_Init = 0  
    Exit Function  
End If  
  
Meter_Init = 1  
End Function
```

Appendix A

Multiline Interface Messages

This appendix contains an interface message reference list, which describes the mnemonics and messages that correspond to the interface functions. These multiline interface messages are sent and received with ATN TRUE.

For more information on these messages, refer to the ANSI/IEEE Standard 488.1-1987, *IEEE Standard Digital Interface for Programmable Instrumentation*.

Multiline Interface Messages

<u>Hex</u>	<u>Oct</u>	<u>Dec</u>	<u>ASCII</u>	<u>Msg</u>	<u>Hex</u>	<u>Oct</u>	<u>Dec</u>	<u>ASCII</u>	<u>Msg</u>
00	000	0	NUL		20	040	32	SP	MLA0
01	001	1	SOH	GTL	21	041	33	!	MLA1
02	002	2	STX		22	042	34	"	MLA2
03	003	3	ETX		23	043	35	#	MLA3
04	004	4	EOT	SDC	24	044	36	\$	MLA4
05	005	5	ENQ	PPC	25	045	37	%	MLA5
06	006	6	ACK		26	046	38	&	MLA6
07	007	7	BEL		27	047	39	'	MLA7
08	010	8	BS	GET	28	050	40	(MLA8
09	011	9	HT	TCT	29	051	41)	MLA9
0A	012	10	LF		2A	052	42	*	MLA10
0B	013	11	VT		2B	053	43	+	MLA11
0C	014	12	FF		2C	054	44	,	MLA12
0D	015	13	CR		2D	055	45	-	MLA13
0E	016	14	SO		2E	056	46	.	MLA14
0F	017	15	SI		2F	057	47	/	MLA15
10	020	16	DLE		30	060	48	0	MLA16
11	021	17	DC1	LLO	31	061	49	1	MLA17
12	022	18	DC2		32	062	50	2	MLA18
13	023	19	DC3		33	063	51	3	MLA19
14	024	20	DC4	DCL	34	064	52	4	MLA20
15	025	21	NAK	PPU	35	065	53	5	MLA21
16	026	22	SYN		36	066	54	6	MLA22
17	027	23	ETB		37	067	55	7	MLA23
18	030	24	CAN	SPE	38	070	56	8	MLA24
19	031	25	EM	SPD	39	071	57	9	MLA25
1A	032	26	SUB		3A	072	58	:	MLA26
1B	033	27	ESC		3B	073	59	;	MLA27
1C	034	28	FS		3C	074	60	<	MLA28
1D	035	29	GS		3D	075	61	=	MLA29
1E	036	30	RS		3E	076	62	>	MLA30
1F	037	31	US		3F	077	63	?	UNL

Message Definitions

DCL	Device Clear	MSA	My Secondary Address
GET	Group Execute Trigger	MTA	My Talk Address
GTL	Go To Local	PPC	Parallel Poll Configure
LLO	Local Lockout	PPD	Parallel Poll Disable
MLA	My Listen Address		

Multiline Interface Messages

<u>Hex</u>	<u>Oct</u>	<u>Dec</u>	<u>ASCII</u>	<u>Msg</u>	<u>Hex</u>	<u>Oct</u>	<u>Dec</u>	<u>ASCII</u>	<u>Msg</u>
40	100	64	@	MTA0	60	140	96	`	MSA0,PPE
41	101	65	A	MTA1	61	141	97	a	MSA1,PPE
42	102	66	B	MTA2	62	142	98	b	MSA2,PPE
43	103	67	C	MTA3	63	143	99	c	MSA3,PPE
44	104	68	D	MTA4	64	144	100	d	MSA4,PPE
45	105	69	E	MTA5	65	145	101	e	MSA5,PPE
46	106	70	F	MTA6	66	146	102	f	MSA6,PPE
47	107	71	G	MTA7	67	147	103	g	MSA7,PPE
48	110	72	H	MTA8	68	150	104	h	MSA8,PPE
49	111	73	I	MTA9	69	151	105	i	MSA9,PPE
4A	112	74	J	MTA10	6A	152	106	j	MSA10,PPE
4B	113	75	K	MTA11	6B	153	107	k	MSA11,PPE
4C	114	76	L	MTA12	6C	154	108	l	MSA12,PPE
4D	115	77	M	MTA13	6D	155	109	m	MSA13,PPE
4E	116	78	N	MTA14	6E	156	110	n	MSA14,PPE
4F	117	79	O	MTA15	6F	157	111	o	MSA15,PPE
50	120	80	P	MTA16	70	160	112	p	MSA16,PPD
51	121	81	Q	MTA17	71	161	113	q	MSA17,PPD
52	122	82	R	MTA18	72	162	114	r	MSA18,PPD
53	123	83	S	MTA19	73	163	115	s	MSA19,PPD
54	124	84	T	MTA20	74	164	116	t	MSA20,PPD
55	125	85	U	MTA21	75	165	117	u	MSA21,PPD
56	126	86	V	MTA22	76	166	118	v	MSA22,PPD
57	127	87	W	MTA23	77	167	119	w	MSA23,PPD
58	130	88	X	MTA24	78	170	120	x	MSA24,PPD
59	131	89	Y	MTA25	79	171	121	y	MSA25,PPD
5A	132	90	Z	MTA26	7A	172	122	z	MSA26,PPD
5B	133	91	[MTA27	7B	173	123	{	MSA27,PPD
5C	134	92	\	MTA28	7C	174	124		MSA28,PPD
5D	135	93]	MTA29	7D	175	125	}	MSA29,PPD
5E	136	94	^	MTA30	7E	176	126	~	MSA30,PPD
5F	137	95	_	UNT	7F	177	127	DEL	

PPE Parallel Poll Enable
 PPU Parallel Poll Unconfigure
 SDC Selected Device Clear
 SPD Serial Poll Disable

SPE Serial Poll Enable
 TCT Take Control
 UNL Unlisten
 UNT Untalk

Appendix B

Customer Communication

For your convenience, this appendix contains forms to help you gather the information necessary to help us solve technical problems you might have as well as a form you can use to comment on the product documentation. Filling out a copy of the *Technical Support Form* before contacting National Instruments helps us help you better and faster.

National Instruments provides comprehensive technical assistance around the world. In the U.S. and Canada, applications engineers are available Monday through Friday from 8:00 a.m. to 6:00 p.m. (central time). In other countries, contact the nearest branch office. You may fax questions to us at any time.

Corporate Headquarters

(512) 795-8248

Technical support fax: (800) 328-2203
(512) 794-5678

Branch Offices	Phone Number	Fax Number
Australia	03 879 9422	03 879 9179
Austria	0662 435986	0662 437010 19
Belgium	02 757 00 20	02 757 03 11
Denmark	45 76 26 00	45 76 71 11
Finland	90 527 2321	90 502 2930
France	1 48 65 33 00	1 48 65 19 07
Germany	089 7 14 50 93	089 7 14 60 35
Italy	02 48301892	02 48301915
Japan	03 3788 1921	03 3788 1923
Netherlands	01720 45761	01720 42140
Norway	03 846866	03 846860
Spain	91 640 0085	91 640 0533
Sweden	08 730 49 70	08 730 43 70
Switzerland	056 27 00 20	056 27 00 25
U.K.	0635 523545	0635 523154

or 0800 289877 (in U.K. only)

Technical Support Form

Photocopy this form and update it each time you make changes to your software or hardware, and use the completed copy of this form as a reference for your current configuration. Completing this form accurately before contacting National Instruments for technical support helps our applications engineers answer your questions more efficiently.

If you are using any National Instruments hardware or software products related to this problem, include the configuration forms from their user manuals. Include additional pages if necessary.

Name _____

Company _____

Address _____

Fax (____) _____ Phone (____) _____

Computer brand _____

Model _____ Processor _____

Operating system _____

Speed _____MHz RAM _____MB

Display adapter _____

Mouse _____yes _____no

Other adapters installed _____

Hard disk capacity _____MB Brand _____

Instruments used _____

National Instruments hardware product model _____

Revision _____

Configuration _____

(continues)

Version _____

Configuration _____

The problem is _____

List any error messages _____

The following steps will reproduce the problem _____

Visual Basic Hardware and Software Configuration Form

Record the settings and revisions of your hardware and software on the line to the right of each item. Update this form each time you revise your software or hardware configuration, and use this form as a reference for your current configuration.

National Instruments Products

- NI-488.2 Software Revision Number on Disk _____
- Programming Language Interface Revision _____
- Type of National Instruments GPIB boards installed and their respective hardware settings

Board Type	Base I/O Address	Interrupt Level	DMA Channel
_____	_____	_____	_____
_____	_____	_____	_____
_____	_____	_____	_____

Other Products

- Computer Make and Model _____
- Microprocessor _____
- Clock Frequency _____
- Type of Monitor Card Installed _____
- DOS Version _____
- Windows Version _____
- Programming Language Version _____
- Type of other boards installed and their respective hardware settings

Board Type	Base I/O Address	Interrupt Level	DMA Channel
_____	_____	_____	_____
_____	_____	_____	_____
_____	_____	_____	_____

If you find errors in the manual, please record the page numbers and describe the errors.

Thank you for your help.

Name _____

Title _____

Company _____

Address _____

Phone (_____) _____

Mail to: **Technical Publications
National Instruments Corporation
6504 Bridge Point Parkway, MS 53-02
Austin, TX 78730-5039**

Fax to: **Technical Publications
National Instruments Corporation
MS 53-02
(512) 794-5678**

Glossary

Prefix	Meaning	Value
m	milli	10^{-3}
μ	micro	10^{-6}
n	nano	10^{-9}
M	mega	10^6

AC	alternating current
ANSI	American National Standards Institute
ASCII	American Standard Code for Information Interchange
ATN	Attention
AUTO	autoranging
DCL	Device Clear
DLL	dynamic link library
DMA	direct memory access
DVM	digital voltmeter
EOI	end or identify
EOS	end of string
GPIB	General Purpose Interface bus
hex	hexadecimal
Hz	hertz
IEEE	Institute of Electrical and Electronic Engineers
IFC	Interface Clear
I/O	input/output
IFC	Interface Clear
LLO	Local Lockout
MB	megabytes of memory
MAV	message available bit
MLA	My Listen Address
MTA	My Talk Address
OEM	original equipment manufacturer
PPC	Parallel Poll Configure
PPD	Parallel Poll Disable
PPE	Parallel Poll Enable
RAM	random-access memory

Glossary

REN	Remote Enable
SDC	Select Device Clear
SPD	Serial Poll Disable
SPE	Serial Poll Enable
SRQ	Service Request
SRQI	Request Service
TIMO	Timeout Command
UNL	Unlisten Command
UNT	Untalk Command
VAC	volts alternating current
Val	value