nag mv ordinal multidimscale (g03fcc)

1. Purpose

nag mv ordinal multidimscale (g03fcc) performs non-metric (ordinal) multidimensional scaling.

2. Specification

```
#include <nag.h>
#include <nagg03.h>
```

```
void nag_mv_ordinal_multidimscale(Nag_ScaleCriterion type, Integer n,
         Integer ndim, double d[], double x[], Integer tdx,
         double *stress, double dfit[], Nag_E04_Opt *options,
         NagError *fail)
```
3. Description

For a set of n objects, a distance or dissimilarity matrix D can be calculated such that d_{ii} is a measure of how 'far apart' objects i and j are. If p variables x_k have been recorded for each observation this measure may be based on Euclidean distance, $d_{ij} = \sum_{k=1}^{p} (x_{ki} - x_{kj})^2$, or some other calculation such as the number of variables for which $x_{kj} \neq x_{ki}$. Alternatively, the distances may be the result of a subjective assessment. For a given distance matrix, multidimensional scaling produces a configuration of n points in a chosen number of dimensions, m , such that the distance between the points in some way best matches the distance matrix. For some distance measures, such as Euclidean distance, the size of distance is meaningful, for other measures of distance all that can be said is that one distance is greater or smaller than another. For the former, metric scaling can be used, see nag mv-prin coord analysis (g03fac), for the latter, a non-metric scaling is more appropriate.

For non-metric multidimensional scaling, the criterion used to measure the closeness of the fitted distance matrix to the observed distance matrix is known as *STRESS*. *STRESS* is given by,

$$
\sqrt{\frac{\sum_{i=1}^{n} \sum_{j=1}^{i-1} (\hat{d}_{ij} - \tilde{d}_{ij})^2}{\sum_{i=1}^{n} \sum_{j=1}^{i-1} \hat{d}_{ij}^2}}
$$

where \hat{d}_{ij}^2 is the Euclidean squared distance between points i and j and \tilde{d}_{ij} is the fitted distance obtained when \hat{d}_{ij} is monotonically regressed on d_{ij} , that is, \tilde{d}_{ij} is monotonic relative to d_{ij} and is obtained from \hat{d}_{ij} with the smallest number of changes. So $STRESS$ is a measure of by how much the set of points preserve the order of the distances in the original distance matrix. Non-metric multidimensional scaling seeks to find the set of points that minimize the STRESS.

An alternate measure is squared STRESS, SSTRESS,

$$
\sqrt{\frac{\sum_{i=1}^{n} \sum_{j=1}^{i-1} (\hat{d}_{ij}^2 - \tilde{d}_{ij}^2)^2}{\sum_{i=1}^{n} \sum_{j=1}^{i-1} \hat{d}_{ij}^4}}
$$

in which the distances in ST RESS are replaced by squared distances.

In order to perform a non-metric scaling, an initial configuration of points is required. This can be obtained from principal co-ordinate analysis, see nag mv prin coord analysis (g03fac). Given an initial configuration, nag mv ordinal multidimscale uses the optimization routine nag opt conj grad (e04dgc) to find the configuration of points that minimizes ST RESS or SST RESS. The routine nag opt conj grad (e04dgc) uses a conjugate gradient algorithm. nag mv ordinal multidimscale will find an optimum that may only be a local optimum, to be more sure of finding a global optimum several different initial configurations should be used; these can be obtained by randomly perturbing the original initial configuration using routines from Chapter g05.

4. Parameters

type

Input: indicates whether ST RESS or SST RESS is to be used as the criterion.

If **type** = **Nag Stress**, ST RESS is used. If **type** = **Nag SStress**, SST RESS is used.

Constraint: **type** = **Nag Stress** or **Nag SStress**.

n

Input: the number of objects in the distance matrix, n .

Constraint: $\mathbf{n} > \mathbf{ndim}$.

ndim

Input: the number of dimensions used to represent the data, m.

Constraint: **ndim** ≥ 1 .

d[n∗**(n**−**1)/2]**

Input: the lower triangle of the distance matrix D stored packed by rows. That is **d**[$(i-1) * (i-2)/2 + j - 1$] must contain d_{ij} for $i = 2, 3, ..., n; j = 1, 2, ..., i - 1$. If d_{ij} is missing then set $d_{ij} < 0$; For further comments on missing values see Section 6.

x[n][tdx]

Input: the ith row must contain an initial estimate of the co-ordinates for the ith point, $i = 1, 2, \ldots, n$. One method of computing these is to use nag_mv_prin_coord_analysis (g03fac). Output: the *i*th row contains m co-ordinates for the *i*th point, $i = 1, 2, \ldots, n$.

tdx

Input: the last dimension of the array **x** as declared in the calling program. Constraint: $\mathbf{tdx} \geq \mathbf{ndim}$.

stress

Output: the value of *STRESS* or *SSTRESS* at the final iteration.

dfit[2∗**n**∗**(n**−**1)]**

Output: auxiliary outputs. If **type** = **Nag_Stress**, the first $n(n-1)/2$ elements contain the distances, \hat{d}_{ij} , for the points returned in **x**, the second set of $n(n-1)/2$ contains the distances \hat{d}_{ij} ordered by the input distances, d_{ij} , the third set of $n(n-1)/2$ elements contains the monotonic distances, \tilde{d}_{ij} , ordered by the input distances, d_{ij} and the final set of $n(n-1)/2$ elements contains fitted monotonic distances, \tilde{d}_{ij} , for the points in **x**. The \tilde{d}_{ij} corresponding to distances which are input as missing are set to zero. If **type** = **Nag SStress**, the results are as above except that the squared distances are returned.

Each distance matrix is stored in lower triangular packed form in the same way as the input matrix D.

options

Input/Output: a pointer to a structure of type Nag E04 Opt whose members are optional parameters for nag opt conj grad (e04dgc). These structure members offer the means of adjusting some of the parameter values of the algorithm and on output will supply further details of the results. You are referred to the nag-opt-conj-grad (e04dgc) document for further details.

The default values used by nag mv ordinal multidimscale when the options parameter is set to the NAG defined null pointer, E04 DEFAULT, are as follows:

```
options.optim_tol = 0.00001;
options.print level = Nag NoPrint;
options.list = FALSE;
options.verify grad = FALSE;
options.max_iter = MAX(50, n*ndim).
```
If a different value is required for any of these four structure members or if other options available in nag opt conj grad (e04dgc) are to be used, then the structure **options** should be declared and initialised by a call to nag opt init (e04xxc) and supplied as an argument to nag mv ordinal multidimscale. In this case, the structure members listed above except for **list** will have the default values as specified above; **options.list** = **TRUE** in this case.

fail

The NAG error parameter, see the Essential Introduction to the NAG C Library.

5. Error Indications and Warnings

NE BAD PARAM

On entry, parameter **type** had an illegal value.

NE INT ARG LT

On entry, **ndim** must not be less than 1: $\textbf{ndim} = \langle \text{value} \rangle$.

NE 2 INT ARG LE

On entry, $\mathbf{n} = \langle value \rangle$ while $\mathbf{ndim} = \langle value \rangle$. These parameters must satisfy $n >$ **ndim**.

NE 2 INT ARG LT

On entry, $\mathbf{tdx} = \langle value \rangle$ while $\mathbf{ndim} = \langle value \rangle$. These parameters must satisfy $\mathbf{tdx} \geq \mathbf{ndim}$.

NE NEG OR ZERO ARRAY

All elements of array $d \leq 0.0$. Constraint: At least one element of **d** must be positive.

NE ALLOC FAIL

Memory allocation failed.

NE INTERNAL ERROR

An internal error has occurred in this function.

Check the function call and any array sizes. If the call is correct then please consult NAG for assistance.

Additional error messages are output if the optimization fails to converge or if the options are set incorrectly, Details of these can be found in the nag opt conj grad (e04dgc) document.

6. Further Comments

Missing values in the input distance matrix can be specified by a negative value and providing there are not more than about two thirds of the values missing, the algorithm may still work. However, the routine nag mv prin coord analysis (g03fac) does not allow for missing values so an alternative method of obtaining an initial set of co-ordinates is required. It may be possible to estimate the missing values with some form of average and then use nag mv prin coord analysis (g03fac) to give an initial set of co-ordinates.

6.1. Accuracy

After a successful optimization, the relative accuracy of $STRESS$ should be approximately ϵ , as specified by **options.optim tol**.

6.2. References

Chatfield C and Collins A J (1980) *Introduction to Multivariate Analysis* Chapman and Hall. Krzanowski W J (1990) *Principles of Multivariate Analysis* Oxford University Press.

7. See Also

nag mv prin coord analysis (g03fac) nag opt conj grad (e04dgc)

8. Example

The data, given by Krzanowski (1990), are dissimilarities between water vole populations in Europe. Initial estimates are provided by the first two principal co-ordinates computed by nag mv prin coord analysis (g03fac). The two dimension solution is computed using nag mv ordinal multidimscale.

8.1. Program Text

```
/* nag_mv_ordinal_multidimscale (g03fcc) Example Program.
 *
 * Copyright 1998 Numerical Algorithms Group.
 *
 * Mark 5, 1998.
 *
 */
#include <nag.h>
#include <stdio.h>
#include <nag_stdlib.h>
#include <nagg01.h>
#include <nagg03.h>
#define NMAX 14
#define MMAX 2
#define NNMAX NMAX*(NMAX-1)/2
#define X(I,J) = X(I-1)*NMAX + (J-1)#define XTMP(I) xtmp[(I)-1]
#define YTMP(I) ytmp[(I)-1]
main()
{
  double d[NNMAX], dfit[4*NNMAX], wk[NNMAX+15*NMAX*MMAX],
  x[NMAX*NMAX];
  double stress;
  Integer ndim;
  Integer i, j, n;
  Integer nn;
  Integer \text{tdx} = \text{NMAX};
  char char_type[2];
  Nag_ScaleCriterion type;
  Vprintf("g03fcc Example Program Results\n\n");
  /* Skip heading in data file */
  Vscanf("%*[^\n]");
  Vscanf("%ld",&n);
  Vscanf("%ld",&ndim);
  Vscanf("%s",char_type);
  if (n \leq NMAX){
      nn = n * (n - 1) / 2;for (i = 1; i <= nn; ++i)
        Vscanf("%lf",&d[i-1]);
      g03fac(Nag_LargeEigVals, n, d, ndim, x, tdx, wk, NAGERR_DEFAULT);
      if (*char_type == 'T')type = Nag_Stress;
      else
        type = Nag_SStress;
      g03fcc(type, n, ndim, d, x, tdx, &stress, dfit,
             E04_DEFAULT, NAGERR_DEFAULT);
      Vprint(f' \n) STRESS = \frac{1}{3}.4e \n}n'', stress);
      Vprintf("Co-ordinates\n\n");
      for (i = 1; i \le n; ++i)\overline{f}for (j = 1; j <= ndim; ++j)
             Vprintf("%10.4f",X(i,j));
```

```
Vprintf("\n");
      }
    exit(EXIT_SUCCESS);
  }
else
  {
    Vprintf("Incorrect input value of n.\n");
    exit(EXIT_FAILURE);
  }
```
8.2. Program Data

}

g03fcc Example Program Data

14 2 T

0.099 0.033 0.022 0.183 0.114 0.042 0.148 0.224 0.059 0.068 0.198 0.039 0.053 0.085 0.051 0.462 0.266 0.322 0.435 0.268 0.025 0.628 0.442 0.444 0.406 0.240 0.129 0.014 0.113 0.070 0.046 0.047 0.034 0.002 0.106 0.129 0.173 0.119 0.162 0.331 0.177 0.039 0.089 0.237 0.071 0.434 0.419 0.339 0.505 0.469 0.390 0.315 0.349 0.151 0.430 0.762 0.633 0.781 0.700 0.758 0.625 0.469 0.618 0.440 0.538 0.607 0.530 0.389 0.482 0.579 0.597 0.498 0.374 0.562 0.247 0.383 0.387 0.084 0.586 0.435 0.550 0.530 0.552 0.509 0.369 0.471 0.234 0.346 0.456 0.090 0.038

8.3. Program Results

g03fcc Example Program Results

STRESS = 1.2557e-01

Co-ordinates

