

D01PAF – NAG Fortran Library Routine Document

Note. Before using this routine, please read the Users' Note for your implementation to check the interpretation of bold italicised terms and other implementation-dependent details.

1 Purpose

D01PAF returns a sequence of approximations to the integral of a function over a multi-dimensional simplex, together with an error estimate for the last approximation.

2 Specification

```

SUBROUTINE D01PAF(NDIM, VERTEX, IV1, IV2, FUNCTN, MINORD, MAXORD,
1              FINVLS, ESTERR, IFAIL)
  INTEGER      NDIM, IV1, IV2, MINORD, MAXORD, IFAIL
  real        VERTEX(IV1,IV2), FUNCTN, FINVLS(MAXORD), ESTERR
  EXTERNAL    FUNCTN

```

3 Description

The subroutine
 computes a sequence of approximations $\text{FINVLS}(j)$, for $j = \text{MINORD}+1, \text{MINORD}+2, \dots, \text{MAXORD}$,
 to an integral

$$\int_S f(x_1, x_2, \dots, x_n) dx_1 dx_2 \dots dx_n$$

where S is an n -dimensional simplex defined in terms of its $n+1$ vertices. $\text{FINVLS}(j)$ is an approximation which will be exact (except for rounding errors) whenever the integrand is a polynomial of total degree $2j-1$ or less.

The type of method used has been described by Grundmann and Moller [1], and is implemented in an extrapolated form using the theory from de Doncker [2].

4 References

- [1] Grundmann A and Moller H M (1978) Invariant integration formulas for the n -simplex by combinatorial methods *SIAM J. Numer. Anal.* **15** 282–290
- [2] de Doncker E (1979) New Euler–Maclaurin Expansions and their application to quadrature over the s -dimensional simplex *Math. Comput.* **33** 1003–1018

5 Parameters

- 1: NDIM — INTEGER *Input*
On entry: the number of dimensions of the integral, n .
Constraint: $\text{NDIM} \geq 2$.
- 2: VERTEX(IV1,IV2) — *real* array *Input/Output*
On entry: VERTEX(i, j) must be set to the j th component of the i th vertex for the simplex integration region, for $i = 1, 2, \dots, n+1$; $j = 1, 2, \dots, n$. If $\text{MINORD} > 0$, VERTEX must be unchanged since the previous call of D01PAF.
On exit: these values are unchanged. The rest of the array VERTEX is used for workspace and contains information to be used if another call of D01PAF is made with $\text{MINORD} > 0$. In particular VERTEX($n+1, 2n+2$) contains the volume of the simplex.

- 3:** IV1 — INTEGER *Input*
On entry: the first dimension of the array VERTEX as declared in the (sub)program from which D01PAF is called.
Constraint: $IV1 \geq NDIM + 1$.
- 4:** IV2 — INTEGER *Input*
On entry: the second dimension of the array VERTEX as declared in the (sub)program from which D01PAF is called.
Constraint: $IV2 \geq 2 \times (NDIM + 1)$.
- 5:** FUNCTN — *real* FUNCTION, supplied by the user. *External Procedure*
 FUNCTN must return the value of the integrand f at a given point.
 Its specification is:

<pre> real FUNCTION FUNCTN(NDIM, X) INTEGER NDIM real X(NDIM) </pre>

- | |
|--|
| <p>1: NDIM — INTEGER <i>Input</i>
 <i>On entry:</i> the number of dimensions of the integral, n.</p> <p>2: X(NDIM) — <i>real</i> array <i>Input</i>
 <i>On entry:</i> the co-ordinates of the point at which the integrand must be evaluated.</p> |
|--|

FUNCTN must be declared as EXTERNAL in the (sub)program from which D01PAF is called. Parameters denoted as *Input* must **not** be changed by this procedure.

- 6:** MINORD — INTEGER *Input/Output*
On entry: MINORD must specify the highest order of the approximations currently available in the array FINVLS. MINORD = 0 indicates an initial call; MINORD > 0 indicates that FINVLS(1),FINVLS(2),...,FINVLS(MINORD) have already been computed in a previous call of D01PAF.
Constraint: MINORD \geq 0.
On exit: MINORD = MAXORD.
- 7:** MAXORD — INTEGER *Input*
On entry: the highest order of approximation to the integral to be computed.
Constraint: MAXORD > MINORD.
- 8:** FINVLS(MAXORD) — *real* array *Input/Output*
On entry: FINVLS(1),FINVLS(2),...,FINVLS(MINORD) must contain approximations to the integral previously computed by D01PAF.
On exit: FINVLS contains these values unchanged, and the newly computed values FINVLS(MINORD+1),FINVLS(MINORD+2),...,FINVLS(MAXORD). FINVLS(j) is an approximation to the integral of polynomial degree $2j - 1$.
- 9:** ESTERR — *real* *Output*
On exit: an absolute error estimate for FINVLS(MAXORD).

10: IFAIL — INTEGER*Input/Output*

On entry: IFAIL must be set to 0, -1 or 1. For users not familiar with this parameter (described in Chapter P01) the recommended value is 0.

On exit: IFAIL = 0 unless the routine detects an error (see Section 6).

6 Error Indicators and Warnings

Errors detected by the routine:

IFAIL = 1

On entry, NDIM < 2,
 or IV1 < NDIM + 1,
 or IV2 < 2 × (NDIM + 1),
 or MINORD < 0,
 or MAXORD ≤ MINORD.

IFAIL = 2

The volume of the simplex integration region (computed as a determinant by F03AAF) is too large or too small to be representable in the machine.

7 Accuracy

An absolute error estimate is output through the parameter ESTERR.

8 Further Comments

The running time for D01PAF will usually be dominated by the time used to evaluate the integrand FUNCTN. The maximum time that could be used by D01PAF will be approximately given by

$$T \times \frac{(\text{MAXORD} + \text{NDIM})!}{(\text{MAXORD} - 1)! (\text{NDIM} + 1)!}$$

where T is the time needed for one call of FUNCTN.

9 Example

A program demonstrating the use of the subroutine with the integral

$$\int_0^1 \int_0^{1-x} \int_0^{1-x-y} \exp(x+y+z) \cos(x+y+z) dz dy dx = \frac{1}{4}$$

is given below.

9.1 Program Text

Note. The listing of the example program presented below uses bold italicised terms to denote precision-dependent details. Please read the Users' Note for your implementation to check the interpretation of these terms. As explained in the Essential Introduction to this manual, the results produced may not be identical for all implementations.

```
*      D01PAF Example Program Text
*      Mark 14 Revised.  NAG Copyright 1989.
*      .. Parameters ..
      INTEGER          NDIM, IV1, IV2, MXORD
      PARAMETER        (NDIM=3, IV1=NDIM+1, IV2=2*(NDIM+1), MXORD=5)
      INTEGER          NOUT
      PARAMETER        (NOUT=6)
```

```

* .. Local Scalars ..
  real ESTERR
  INTEGER IFAIL, J, K, MAXORD, MINORD, NEVALS
* .. Local Arrays ..
  real FINVLS(MXORD), VERTEX(IV1,IV2)
* .. External Functions ..
  real FUNCTN
  EXTERNAL FUNCTN
* .. External Subroutines ..
  EXTERNAL D01PAF
* .. Executable Statements ..
  WRITE (NOUT,*) 'D01PAF Example Program Results'
  DO 40 J = 1, IV1
    DO 20 K = 1, NDIM
      VERTEX(J,K) = 0.0e0
20    CONTINUE
      IF (J.GT.1) VERTEX(J,J-1) = 1.0e0
40  CONTINUE
    MINORD = 0
    NEVALS = 1
    WRITE (NOUT,*)
    WRITE (NOUT,*)
+   'MAXORD Estimated Estimated Integrand'
    WRITE (NOUT,*)
+   ' value accuracy evaluations'
    DO 60 MAXORD = 1, MXORD
      IFAIL = 0
*
      CALL D01PAF(NDIM,VERTEX,IV1,IV2,FUNCTN,MINORD,MAXORD,FINVLS,
+              ESTERR,IFAIL)
*
      WRITE (NOUT,99999) MAXORD, FINVLS(MAXORD), ESTERR, NEVALS
      NEVALS = (NEVALS*(MAXORD+NDIM+1))/MAXORD
60  CONTINUE
    STOP
*
99999 FORMAT (1X,I4,F13.5,e16.3,I15)
    END
*
  real FUNCTION FUNCTN(NDIM,X)
* .. Scalar Arguments ..
  INTEGER NDIM
* .. Array Arguments ..
  real X(NDIM)
* .. Intrinsic Functions ..
  INTRINSIC COS, EXP
* .. Executable Statements ..
  FUNCTN = EXP(X(1)+X(2)+X(3))*COS(X(1)+X(2)+X(3))
  RETURN
  END

```

9.2 Program Data

None.

9.3 Program Results

D01PAF Example Program Results

MAXORD	Estimated value	Estimated accuracy	Integrand evaluations
1	0.25816	0.258E+00	1
2	0.25011	0.806E-02	5
3	0.25000	0.107E-03	15
4	0.25000	0.410E-06	35
5	0.25000	0.173E-08	70
