

G01AAF – NAG Fortran Library Routine Document

Note. Before using this routine, please read the Users' Note for your implementation to check the interpretation of bold italicised terms and other implementation-dependent details.

1 Purpose

G01AAF calculates the mean, standard deviation, coefficients of skewness and kurtosis, and the maximum and minimum values for a set of ungrouped data. Weighting may be used.

2 Specification

```

SUBROUTINE G01AAF(N, X, IWT, WT, XMEAN, S2, S3, S4, XMIN, XMAX,
1           WTSUM, IFAIL)
  INTEGER   N, IWT, IFAIL
  real      X(N), WT(N), XMEAN, S2, S3, S4, XMIN, XMAX, WTSUM

```

3 Description

The data consist of a single sample of n observations, denoted by x_i , with corresponding weights, w_i , for $i = 1, 2, \dots, n$.

If no specific weighting is required, then each w_i is set to 1.

The quantities computed are:

- (a) The sum of the weights

$$W = \sum_{i=1}^n w_i.$$

- (b) Mean

$$\bar{x} = \frac{\sum_{i=1}^n w_i x_i}{W}.$$

- (c) Standard deviation

$$s_2 = \sqrt{\frac{\sum_{i=1}^n w_i (x_i - \bar{x})^2}{d}}, \text{ where } d = W - \frac{\sum_{i=1}^n w_i^2}{W}.$$

- (d) Coefficient of skewness

$$s_3 = \frac{\sum_{i=1}^n w_i (x_i - \bar{x})^3}{d \times s_2^3}.$$

- (e) Coefficient of kurtosis

$$s_4 = \frac{\sum_{i=1}^n w_i (x_i - \bar{x})^4}{d \times s_2^4} - 3.$$

- (f) Maximum and minimum elements of the sample.

- (g) The number of observations for which $w_i > 0$, i.e., the number of **valid** observations. Suppose m observations are valid, then the quantities in (c), (d) and (e) will be computed if $m \geq 2$, and will be based on $m - 1$ degrees of freedom. The other quantities are evaluated provided $m \geq 1$.

4 References

None.

5 Parameters

- 1:** N — INTEGER *Input*
On entry: the number of observations, n .
Constraint: $N \geq 1$.
- 2:** X(N) — *real* array *Input*
On entry: the sample observations, x_i , for $i = 1, 2, \dots, n$.
- 3:** IWT — INTEGER *Input/Output*
On entry: indicates whether weights are to be supplied by the user or not. In the latter case, the weights will be assumed equal and assigned the value 1.0 in the routine.
 IWT = 0
 indicates no user-supplied weights.
 IWT = 1
 indicates user-supplied weights are required, and they will be supplied in the array WT.
On exit: IWT is used to indicate the number of valid observations, m – see 3(g) above.
- 4:** WT(N) — *real* array *Input/Output*
On entry: if IWT = 1, then the elements of WT must contain the weights associated with the observations, w_i , for $i = 1, 2, \dots, n$.
 If IWT = 0, then the elements of WT need not be set.
On exit: if IWT = 1 the elements of WT are unchanged.
 If IWT = 0 each element of WT will be assigned the value 1.0.
- 5:** XMEAN — *real* *Output*
On exit: the mean, \bar{x} .
- 6:** S2 — *real* *Output*
On exit: the standard deviation, s_2 .
- 7:** S3 — *real* *Output*
On exit: the coefficient of skewness, s_3 .
- 8:** S4 — *real* *Output*
On exit: the coefficient of kurtosis, s_4 .
- 9:** XMIN — *real* *Output*
On exit: the smallest value in the sample.
- 10:** XMAX — *real* *Output*
On exit: the largest value in the sample.
- 11:** WTSUM — *real* *Output*
On exit: the sum of the weights in the array WT, that is $\sum_{i=1}^n w_i$. This will be N if IWT was 0 on entry.

12: IFAIL — INTEGER*Input/Output*

On entry: IFAIL must be set to 0, -1 or 1. For users not familiar with this parameter (described in Chapter P01) the recommended value is 0.

On exit: IFAIL = 0 unless the routine detects an error (see Section 6).

6 Error Indicators and Warnings

Errors detected by the routine:

IFAIL = 1

On entry, $N < 1$.

IFAIL = 2

The number of valid cases, m , is 1. In this case, standard deviation and coefficients of skewness and of kurtosis cannot be calculated.

IFAIL = 3

Either the number of valid cases is 0, or at least one weight is negative.

7 Accuracy

The method used is believed to be stable.

8 Further Comments

The time taken by the routine is approximately proportional to n .

9 Example

In the example program, NPROB determines the number of data sets to be analysed. For each analysis, a set of observations and, optionally, weights is read and printed. After calling the routine, the calculated quantities are printed. In the example, there is one set of data with 24 unweighted data values.

9.1 Program Text

Note. The listing of the example program presented below uses bold italicised terms to denote precision-dependent details. Please read the Users' Note for your implementation to check the interpretation of these terms. As explained in the Essential Introduction to this manual, the results produced may not be identical for all implementations.

```

*      G01AAF Example Program Text
*      Mark 14 Revised.  NAG Copyright 1989.
*      .. Parameters ..
      INTEGER          NMAX
      PARAMETER       (NMAX=30)
      INTEGER          NIN, NOUT
      PARAMETER       (NIN=5,NOUT=6)
*      .. Local Scalars ..
      real            S2, S3, S4, WTSUM, XBAR, XMAX, XMIN
      INTEGER          I, IFAIL, IWT, J, N, NPROB
*      .. Local Arrays ..
      real            WT(NMAX), X(NMAX)
*      .. External Subroutines ..
      EXTERNAL        G01AAF
*      .. Executable Statements ..
      WRITE (NOUT,*) 'G01AAF Example Program Results'

```

```

*      Skip heading in data file
      READ (NIN,*)
      READ (NIN,*) NPROB
      DO 20 J = 1, NPROB
        READ (NIN,*) N, IWT
        WRITE (NOUT,*)
        WRITE (NOUT,99999) 'Problem ', J
        WRITE (NOUT,99999) 'Number of cases ', N
        IF (N.GE.1 .AND. N.LE.NMAX) THEN
          READ (NIN,*) (X(I),I=1,N)
          WRITE (NOUT,*) 'Data as input -'
          WRITE (NOUT,99998) (X(I),I=1,N)
          IF (IWT.EQ.1) THEN
            WRITE (NOUT,*) 'Weights as input -'
            READ (NIN,*) (WT(I),I=1,N)
            WRITE (NOUT,99998) (WT(I),I=1,N)
          END IF
          IFAIL = 1
*
*      CALL G01AAF(N,X,IWT,WT,XBAR,S2,S3,S4,XMIN,XMAX,WTSUM,IFAIL)
*
      WRITE (NOUT,*)
      IF (IFAIL.EQ.0) THEN
        WRITE (NOUT,*) 'Successful call of G01AAF'
        WRITE (NOUT,99999) 'No. of valid cases ', IWT
        WRITE (NOUT,99997) 'Mean ', XBAR
        WRITE (NOUT,99997) 'Std devn ', S2
        WRITE (NOUT,99997) 'Skewness ', S3
        WRITE (NOUT,99997) 'Kurtosis ', S4
        WRITE (NOUT,99997) 'Minimum ', XMIN
        WRITE (NOUT,99997) 'Maximum ', XMAX
        WRITE (NOUT,99997) 'Sum of weights', WTSUM
      ELSE
        WRITE (NOUT,*) 'Unsuccessful call of G01AAF'
        WRITE (NOUT,99999) 'IFAIL =', IFAIL
        IF (IFAIL.EQ.2) THEN
          WRITE (NOUT,99999) 'No. of valid cases', IWT
          WRITE (NOUT,99997) 'Mean ', XBAR
          WRITE (NOUT,99997) 'Minimum ', XMIN
          WRITE (NOUT,99997) 'Maximum ', XMAX
          WRITE (NOUT,99997) 'Sum of weights', WTSUM
          WRITE (NOUT,*) 'Std devn and coeffts of skewness'
          WRITE (NOUT,*) 'and kurtosis not defined'
        END IF
      END IF
      ELSE
        STOP
      END IF
    20 CONTINUE
      STOP
*
99999 FORMAT (1X,A,I5)
99998 FORMAT (1X,5F12.1)
99997 FORMAT (1X,A,F13.1)
      END

```

9.2 Program Data

G01AAF Example Program Data

```

1
24 0
193.0 215.0 112.0 161.0 92.0 140.0 38.0 33.0 279.0 249.0
473.0 339.0 60.0 130.0 20.0 50.0 257.0 284.0 447.0 52.0
67.0 61.0 150.0 2200.0

```

9.3 Program Results

G01AAF Example Program Results

```

Problem      1
Number of cases      24
Data as input -
      193.0      215.0      112.0      161.0      92.0
      140.0      38.0      33.0      279.0      249.0
      473.0      339.0      60.0      130.0      20.0
      50.0      257.0      284.0      447.0      52.0
      67.0      61.0      150.0      2200.0

```

```

Successful call of G01AAF
No. of valid cases      24
Mean                    254.3
Std devn                433.5
Skewness                 3.9
Kurtosis                14.7
Minimum                 20.0
Maximum                 2200.0
Sum of weights          24.0

```
