

## G01HAF – NAG Fortran Library Routine Document

**Note.** Before using this routine, please read the Users' Note for your implementation to check the interpretation of bold italicised terms and other implementation-dependent details.

### 1 Purpose

G01HAF returns the lower tail probability for the bivariate Normal distribution, via the routine name.

### 2 Specification

```

real FUNCTION G01HAF(X, Y, RHO, IFAIL)
  INTEGER          IFAIL
  real           X, Y, RHO

```

### 3 Description

For the two random variables  $(X, Y)$  following a bivariate Normal distribution with:

$$E[X] = 0, E[Y] = 0, E[X^2] = 1, E[Y^2] = 1 \text{ and } E[XY] = \rho,$$

the lower tail probability is defined by:

$$P(X \leq x, Y \leq y : \rho) = \frac{1}{2\pi\sqrt{1-\rho^2}} \int_{-\infty}^y \int_{-\infty}^x \exp\left[-\frac{(X^2 - 2\rho XY + Y^2)}{2(1-\rho^2)}\right] dXdY.$$

For a more detailed description of the bivariate Normal distribution and its properties see Abramowitz and Stegun [1] and Kendall and Stuart [3] The method used is described by Divgi [2].

### 4 References

- [1] Abramowitz M and Stegun I A (1972) *Handbook of Mathematical Functions* Dover Publications (3rd Edition)
- [2] Divgi D R (1979) Calculation of univariate and bivariate normal probability functions *Ann. Statist.* **7** 903–910
- [3] Kendall M G and Stuart A (1969) *The Advanced Theory of Statistics (Volume 1)* Griffin (3rd Edition)

### 5 Parameters

- 1: X — **real** *Input*  
*On entry:* the first argument for which the bivariate Normal distribution function is to be evaluated,  $x$ .
- 2: Y — **real** *Input*  
*On entry:* the second argument for which the bivariate Normal distribution function is to be evaluated,  $y$ .
- 3: RHO — **real** *Input*  
*On entry:* the correlation coefficient,  $\rho$ .  
*Constraint:*  $-1.0 \leq \text{RHO} \leq 1.0$

**4: IFAIL — INTEGER***Input/Output*

*On entry:* IFAIL must be set to 0, -1 or 1. For users not familiar with this parameter (described in Chapter P01) the recommended value is 0.

*On exit:* IFAIL = 0 unless the routine detects an error (see Section 6).

**6 Error Indicators and Warnings**

If on entry IFAIL = 0 or -1, explanatory error messages are output on the current error message unit (as defined by X04AAF).

Errors detected by the routine:

IFAIL = 1

On entry, RHO < -1.0,  
or RHO > 1.0.

If on exit IFAIL = 1 then G01HAF returns zero.

**7 Accuracy**

Accuracy is discussed in Divgi [2]. A higher order polynomial approximation to Mills ratio is used in G01HAF, (15 terms) than is given in [2]. This will give higher absolute accuracy of about 10 digits on machines of sufficiently high precision.

**8 Further Comments**

The probabilities for the univariate normal distribution can be computed using S15ABF and S15ABF.

**9 Example**

Values of  $x$  and  $y$  for a bivariate Normal distribution are read along with the value of  $\rho$ . The lower tail probabilities are computed.

**9.1 Program Text**

**Note.** The listing of the example program presented below uses bold italicised terms to denote precision-dependent details. Please read the Users' Note for your implementation to check the interpretation of these terms. As explained in the Essential Introduction to this manual, the results produced may not be identical for all implementations.

```
*      G01HAF Example Program Text
*      Mark 14 Release.  NAG Copyright 1989.
*      .. Parameters ..
      INTEGER          NIN, NOUT
      PARAMETER       (NIN=5,NOUT=6)
*      .. Local Scalars ..
      real            PROB, RHO, X, Y
      INTEGER          IFAIL
*      .. External Functions ..
      real            G01HAF
      EXTERNAL         G01HAF
*      .. Executable Statements ..
      WRITE (NOUT,*) 'G01HAF Example Program Results'
*      Skip heading in data file
      READ (NIN,*)
      WRITE (NOUT,*)
```

```

        WRITE (NOUT,*) '      X      Y      RHO      PROB'
        WRITE (NOUT,*)
20      READ (NIN,*,END=40) X, Y, RHO
        IFAIL = 0
*
        PROB = G01HAF(X,Y,RHO,IFAIL)
*
        WRITE (NOUT,99999) X, Y, RHO, PROB
        GO TO 20
40      STOP
*
99999  FORMAT (1X,3F8.3,F8.4)
        END

```

## 9.2 Program Data

G01HAF Example Program Data

1.7	23.1	0.0	:X Y RHO
0.0	0.0	0.1	:X Y RHO
3.3	11.1	0.54	:X Y RHO
9.1	9.1	0.17	:X Y RHO

## 9.3 Program Results

G01HAF Example Program Results

X	Y	RHO	PROB
1.700	23.100	0.000	0.9554
0.000	0.000	0.100	0.2659
3.300	11.100	0.540	0.9995
9.100	9.100	0.170	1.0000

---