

G05CFF – NAG Fortran Library Routine Document

Note. Before using this routine, please read the Users' Note for your implementation to check the interpretation of bold italicised terms and other implementation-dependent details.

1 Purpose

G05CFF saves the values of the seeds used by the generator mechanism.

2 Specification

```
SUBROUTINE G05CFF(IA, NI, XA, NX, IFAIL)
  INTEGER          IA(NI), NI, NX, IFAIL
  real           XA(NX)
```

3 Description

This routine saves information about the generator to enable G05CGF subsequently to restore the generator to its current state. The values of NI, NX, IA and XA must not be altered between a call of G05CFF and a call of G05CGF.

4 References

None.

5 Parameters

- | | | |
|----|-----------------------------------------------------------------------------------------------------------------------------------------------------|---------------------|
| 1: | IA(NI) — INTEGER array | <i>Output</i> |
| | <i>On exit:</i> information about the generator. | |
| 2: | NI — INTEGER | <i>Input</i> |
| | <i>On entry:</i> the dimension of the array IA as declared in the (sub)program from which G05CFF is called. | |
| | <i>Constraint:</i> NI ≥ 9. | |
| 3: | XA(NX) — <i>real</i> array | <i>Output</i> |
| | <i>On exit:</i> information about the generator. | |
| 4: | NX — INTEGER | <i>Input</i> |
| | <i>On entry:</i> the dimension of the array XA as declared in the (sub)program from which G05CFF is called. | |
| | <i>Constraint:</i> NX ≥ 4. | |
| 5: | IFAIL — INTEGER | <i>Input/Output</i> |
| | <i>On entry:</i> IFAIL must be set to 0, -1 or 1. For users not familiar with this parameter (described in Chapter P01) the recommended value is 0. | |
| | <i>On exit:</i> IFAIL = 0 unless the routine detects an error (see Section 6). | |

6 Error Indicators and Warnings

Errors detected by the routine:

IFAIL = 1

On entry, NI < 9.

IFAIL = 2

On entry, NX < 4.

7 Accuracy

Not applicable.

8 Further Comments

None.

9 Example

The example program prints 10 pseudo-random numbers generated by G05CFF; it saves the generator state after the 2nd, and restores it after the 7th so that the 8th, 9th and 10th numbers are the same as the 3rd, 4th and 5th.

The generator mechanism used is selected by an initial call to G05ZAF.

9.1 Program Text

Note. The listing of the example program presented below uses bold italicised terms to denote precision-dependent details. Please read the Users' Note for your implementation to check the interpretation of these terms. As explained in the Essential Introduction to this manual, the results produced may not be identical for all implementations.

```

*      G05CFF Example Program Text
*      NAG Fortran SMP Library, Release 2.  NAG Copyright 2000.
*      .. Parameters ..
      INTEGER          NOUT
      PARAMETER       (NOUT=6)
*      .. Local Scalars ..
      DOUBLE PRECISION R
      INTEGER          I, IFAIL
*      .. Local Arrays ..
      DOUBLE PRECISION X(5), XA(4)
      INTEGER          IA(9)
*      .. External Functions ..
      DOUBLE PRECISION G05CAF
      EXTERNAL        G05CAF
*      .. External Subroutines ..
      EXTERNAL        G05CBF, G05CFF, G05CGF, G05ZAF
*      .. Executable Statements ..
      CALL G05ZAF('0')
      WRITE (NOUT,*) 'G05CFF Example Program Results'
      WRITE (NOUT,*)
      CALL G05CBF(0)
      IFAIL = 0
      DO 20 I = 1, 5
         X(I) = G05CAF(R)
*

```

```
        IF (I.EQ.2) CALL G05CFF(IA,9,XA,4,IFAIL)
*
20 CONTINUE
  WRITE (NOUT,99999) (X(I),I=1,5)
  DO 40 I = 1, 5
    X(I) = G05CAF(R)
*
        IF (I.EQ.2) CALL G05CGF(IA,9,XA,4,IFAIL)
*
40 CONTINUE
  WRITE (NOUT,99999) (X(I),I=1,5)
  STOP
*
99999 FORMAT (1X,5F10.4)
      END
```

9.2 Program Data

None.

9.3 Program Results

G05CFF Example Program Results

0.7951	0.2257	0.3713	0.2250	0.8787
0.0475	0.1806	0.3713	0.2250	0.8787
