Input

# NAG Fortran Library Routine Document

### F11JPF

Note: before using this routine, please read the Users' Note for your implementation to check the interpretation of **bold italicised** terms and other implementation-dependent details.

# 1 Purpose

F11JPF solves a system of complex linear equations involving the incomplete Cholesky preconditioning matrix generated by F11JNF.

# 2 Specification

SUBROUTINE F11JPF(N, A, LA, IROW, ICOL, IPIV, ISTR, CHECK, Y, X, IFAIL)
INTEGER

N, LA, IROW(LA), ICOL(LA), IPIV(N), ISTR(N+1), IFAIL

complex

A(LA), Y(N), X(N)

CHARACTER\*1

CHECK

# 3 Description

This routine solves a system of linear equations

$$Mx = y$$

involving the preconditioning matrix  $M = PLDL^HP^T$ , corresponding to an incomplete Cholesky decomposition of a complex sparse Hermitian matrix stored in symmetric coordinate storage (SCS) format (see Section 2.1.2 of the F11 Chapter Introduction), as generated by F11JNF.

In the above decomposition L is a complex lower triangular sparse matrix with unit diagonal, D is a real diagonal matrix and P is a permutation matrix. L and D are supplied to F11JPF through the matrix

$$C = L + D^{-1} - I$$

which is a lower triangular n by n complex sparse matrix, stored in SCS format, as returned by F11JNF. The permutation matrix P is returned from F11JNF via the array IPIV.

F11JPF may also be used in combination with F11JNF to solve a sparse complex Hermitian positive-definite system of linear equations directly (see F11JNF). This is illustrated in Section 9.

### 4 References

None.

### 5 Parameters

1: N – INTEGER Input

On entry: n, the order of the matrix M. This **must** be the same value as was supplied in the preceding call to F11JNF.

Constraint: N > 1.

2: A(LA) - complex array

On entry: the values returned in array A by a previous call to F11JNF.

[NP3546/20A] F11JPF.1

3: LA – INTEGER Input

On entry: the dimension of the arrays A, IROW and ICOL as declared in the (sub)program from which F11JPF is called. This **must** be the same value as was supplied in the preceding call to F11JNF.

4: IROW(LA) – INTEGER array

Input

5: ICOL(LA) – INTEGER array

Input

6: IPIV(N) – INTEGER array

Input/Output

7: ISTR(N+1) - INTEGER array

Input

On entry: the values returned in arrays IROW, ICOL, IPIV and ISTR by a previous call to F11JNF. On exit: IPIV is used as internal workspace prior to being restored and hence is unchanged.

#### 8: CHECK – CHARACTER\*1

Input

On entry: specifies whether or not the input data should be checked:

if CHECK = 'C', checks are carried out on the values of N, IROW, ICOL, IPIV and ISTR;

if CHECK = 'N', none of these checks are carried out.

Constraint: CHECK = 'C' or 'N'.

# 9: Y(N) - complex array

Input

On entry: the right-hand side vector y.

10: X(N) - complex array

Output

On exit: the solution vector x.

#### 11: IFAIL – INTEGER

Input/Output

On entry: IFAIL must be set to 0, -1 or 1. Users who are unfamiliar with this parameter should refer to Chapter P01 for details.

On exit: IFAIL = 0 unless the routine detects an error (see Section 6).

For environments where it might be inappropriate to halt program execution when an error is detected, the value -1 or 1 is recommended. If the output of error messages is undesirable, then the value 1 is recommended. Otherwise, for users not familiar with this parameter the recommended value is 0. When the value -1 or 1 is used it is essential to test the value of IFAIL on exit.

# 6 Error Indicators and Warnings

If on entry IFAIL = 0 or -1, explanatory error messages are output on the current error message unit (as defined by X04AAF).

Errors or warnings detected by the routine:

IFAIL = 1

On entry, CHECK  $\neq$  'C' or 'N'.

IFAIL = 2

On entry, N < 1.

IFAIL = 3

On entry, the SCS representation of the preconditioning matrix M is invalid. Further details are given in the error message. Check that the call to F11JPF has been preceded by a valid call to F11JNF and that the arrays A, IROW, ICOL, IPIV and ISTR have not been corrupted between the two calls.

F11JPF.2 [NP3546/20A]

# 7 Accuracy

The computed solution x is the exact solution of a perturbed system of equations  $(M + \delta M)x = y$ , where

$$|\delta M| \le c(n)\epsilon P|L||D||L^H|P^T$$
,

c(n) is a modest linear function of n, and  $\epsilon$  is the machine precision.

#### 8 Further Comments

# 8.1 Timing

The time taken for a call to F11JPF is proportional to the value of NNZC returned from F11JNF.

# 9 Example

This example program reads in a complex sparse Hermitian positive-definite matrix A and a vector y. It then calls F11JNF, with LFILL = -1 and DTOL = 0.0, to compute the **complete** Cholesky decomposition of A:

$$A = PLDL^H P^T$$
.

Finally it calls F11JPF to solve the system

$$PLDL^{H}P^{T}x = y.$$

# 9.1 Program Text

**Note:** the listing of the example program presented below uses **bold italicised** terms to denote precision-dependent details. Please read the Users' Note for your implementation to check the interpretation of these terms. As explained in the Essential Introduction to this manual, the results produced may not be identical for all implementations.

```
F11JPF Example Program Text.
  Mark 19 Release. NAG Copyright 1999.
   .. Parameters ..
   INTEGER
                    NIN, NOUT
   PARAMETER
                    (NIN=5, NOUT=6)
   INTEGER
                    NMAX, LA, LIWORK
                    (NMAX=1000,LA=10000,LIWORK=2*LA+7*NMAX+1)
   .. Local Scalars ..
   real
                    DSCALE, DTOL
                    I, IFAIL, LFILL, N, NNZ, NNZC, NPIVM
   INTEGER
                    CHECK, MIC, PSTRAT
   CHARACTER
   .. Local Arrays ..
   complex
                    A(LA), X(NMAX), Y(NMAX)
                    ICOL(LA), IPIV(NMAX), IROW(LA), ISTR(NMAX+1),
  INTEGER
                    IWORK(LIWORK)
   .. External Subroutines ..
  EXTERNAL
                    F11JNF, F11JPF
   .. Executable Statements ..
   WRITE (NOUT,*) 'F11JPF Example Program Results'
   Skip heading in data file
  READ (NIN,*)
   Read order of matrix and number of non-zero entries
  READ (NIN,*) N
   IF (N.LE.NMAX) THEN
      READ (NIN,*) NNZ
      Read the matrix A
      DO 20 I = 1, NNZ
         READ (NIN,*) A(I), IROW(I), ICOL(I)
20
      CONTINUE
      Read the vector y
```

[NP3546/20A] F11JPF.3

```
READ (NIN, \star) (Y(I), I=1, N)
         Calculate Cholesky factorization
         LFILL = -1
         DTOL = 0.0e0
         MIC = 'N'
         DSCALE = 0.0e0
         PSTRAT = 'M'
         IFAIL = 0
         CALL F11JNF(N,NNZ,A,LA,IROW,ICOL,LFILL,DTOL,MIC,DSCALE,PSTRAT,
                      IPIV, ISTR, NNZC, NPIVM, IWORK, LIWORK, IFAIL)
         Check the output value of NPIVM
         IF (NPIVM.NE.O) THEN
            WRITE (NOUT,*) 'Factorization is not complete'
         ELSE
                         н т
            Solve P L D L P x = y
            CHECK = 'C'
            CALL F11JPF(N,A,LA,IROW,ICOL,IPIV,ISTR,CHECK,Y,X,IFAIL)
            Output results
            WRITE (NOUT,*) 'Solution of linear system'
            DO 40 I = 1, N
               WRITE (NOUT, 99999) X(I)
   40
            CONTINUE
         END IF
      END IF
      STOP
99999 FORMAT (1x,'(',e16.4,',',e16.4,')')
      END
```

#### 9.2 Program Data

```
F11JPF Example Program Data
  9
 23
                           NNZ
 (6.,0.)
                1
                      1
 (-1., 1.)
                2
                      1
 ( 6., 0.)
( 0., 1.)
( 5., 0.)
                2
                      2
                3
                      2
                3
                      3
 (5.,0.)
                4
                      4
 (2.,-2.)
                5
                      1
 ( 4., 0.)
                5
                      5
 ( 1., 1.)
( 2., 0.)
                6
                      3
                6
                      4
 (6.,0.)
                      6
                6
 (-4., 3.)
(0., 1.)
(-1., 0.)
                7
                      2
                7
                      5
                7
                      6
 (6.,0.)
                7
                      7
 (-1.,-1.)
                8
                      4
 ( 0.,-1.)
( 9., 0.)
( 1., 3.)
                      6
                8
                8
                      8
                9
                      1
 (1., 2.)
                9
                      5
                9
 (-1., 0.)
                      6
 (1., 4.)
                9
                      8
                            A(I), IROW(I), ICOL(I), I=1,...,NNZ
                9
                      9
```

F11JPF.4 [NP3546/20A]

```
(8.,54.) (-10.,-92.)
(25.,27.) (26., -28.)
(54.,12.) (26.,-22.)
(47.,65.) (71.,-57.)
(60.,70.) Y(I), I=1,...,N
```

### 9.3 Program Results

```
F11JPF Example Program Results
Solution of linear system
       0.1000E+01,
                       0.9000E+01)
      0.2000E+01,
                       -0.8000E+01)
      0.3000E+01,
                      0.7000E+01)
      0.4000E+01,
                      -0.6000E+01)
      0.5000E+01,
                       0.5000E+01)
      0.6000E+01,
                       -0.4000E+01)
      0.7000E+01,
                       0.3000E+01)
      0.8000E+01,
                       -0.2000E+01)
      0.9000E+01,
                       0.1000E+01)
```

[NP3546/20A] F11JPF.5 (last)