NAG Fortran Library Routine Document

M01DAF

Note: before using this routine, please read the Users' Note for your implementation to check the interpretation of *bold italicised* terms and other implementation-dependent details.

1 Purpose

M01DAF ranks a vector of *real* numbers in ascending or descending order.

2 Specification

SUBROUTINE MO1DAF(RV, M1, M2, ORDER, IRANK, IFAIL)INTEGERM1, M2, IRANK(M2), IFAILrealRV(M2)CHARACTER*1ORDER

3 Description

M01DAF uses a variant of list-merging, as described by Knuth (1973) pp 165-166. The routine takes advantage of natural ordering in the data, and uses a simple list insertion in a preparatory pass to generate ordered lists of length at least 10. The ranking is stable: equal elements preserve their ordering in the input data.

4 References

Knuth D E (1973) The Art of Computer Programming (Volume 3) (2nd Edition) Addison-Wesley

5 Parameters

1:	RV(M2) – <i>real</i> array	Input
	On entry: elements M1 to M2 of RV must contain real values to be ranked.	
2:	M1 – INTEGER	Input
	On entry: the index of the first element of RV to be ranked.	
	Constraint: $M1 > 0$.	
3:	M2 – INTEGER	Input
	On entry: the index of the last element of RV to be ranked.	
	<i>Constraint</i> : $M2 \ge M1$.	
4:	ORDER – CHARACTER*1	Input
	<i>On entry</i> : if ORDER is 'A', the values will be ranked in ascending (i.e., non-decreasing) of ORDER is 'D', into descending order.	der; if
	Constraint: $ORDER = 'A'$ or 'D'.	
5:	IRANK(M2) – INTEGER array	Output
	On avit elements M1 to M2 of IPANK contain the ranks of the corresponding elements	of $\mathbf{D}\mathbf{V}$

On exit: elements M1 to M2 of IRANK contain the ranks of the corresponding elements of RV. Note that the ranks are in the range M1 to M2: thus, if RV(i) is the first element in the rank order, IRANK(i) is set to M1.

6: IFAIL – INTEGER

Input/Output

On entry: IFAIL must be set to 0, -1 or 1. Users who are unfamiliar with this parameter should refer to Chapter P01 for details.

On exit: IFAIL = 0 unless the routine detects an error (see Section 6).

For environments where it might be inappropriate to halt program execution when an error is detected, the value -1 or 1 is recommended. If the output of error messages is undesirable, then the value 1 is recommended. Otherwise, for users not familiar with this parameter the recommended value is 0. When the value -1 or 1 is used it is essential to test the value of IFAIL on exit.

6 Error Indicators and Warnings

If on entry IFAIL = 0 or -1, explanatory error messages are output on the current error message unit (as defined by X04AAF).

Errors or warnings detected by the routine:

IFAIL = 1

IFAIL = 2

On entry, ORDER is not 'A' or 'D'.

7 Accuracy

Not applicable.

8 Further Comments

The average time taken by the routine is approximately proportional to $n \times \log n$, where n = M2 - M1 + 1.

9 Example

The example program reads a list of *real* numbers and ranks them in ascending order.

9.1 Program Text

Note: the listing of the example program presented below uses *bold italicised* terms to denote precision-dependent details. Please read the Users' Note for your implementation to check the interpretation of these terms. As explained in the Essential Introduction to this manual, the results produced may not be identical for all implementations.

```
MO1DAF Example Program Text
*
      Mark 14 Revised. NAG Copyright 1989.
*
      .. Parameters ..
*
      INTEGER
                       NMAX
      PARAMETER
                       (NMAX=100)
      INTEGER
                       NIN, NOUT
                       (NIN=5,NOUT=6)
     PARAMETER
      .. Local Scalars ..
*
      INTEGER
                       I, IFAIL, N
      .. Local Arrays ..
     real
                       RV(NMAX)
      INTEGER
                       IRANK(NMAX)
      .. External Subroutines ..
*
      EXTERNAL
                       M01DAF
      .. Executable Statements ..
      WRITE (NOUT, *) 'MO1DAF Example Program Results'
      Skip heading in data file
```

```
READ (NIN,*)
     READ (NIN,*) N
     IF (N.GE.1 .AND. N.LE.NMAX) THEN
        READ (NIN,*) (RV(I),I=1,N)
        IFAIL = 0
*
        CALL MO1DAF(RV,1,N,'Ascending',IRANK,IFAIL)
*
        WRITE (NOUT, *)
        WRITE (NOUT, *) '
                          Data Ranks'
        WRITE (NOUT, *)
        DO 20 I = 1, N
           WRITE (NOUT,99999) RV(I), IRANK(I)
  20
        CONTINUE
     END IF
     STOP
99999 FORMAT (1X,F7.1,I7)
     END
```

9.2 Program Data

MO1DAF Example Program Data 12 5.3 4.6 7.8 1.7 5.3 9.9 3.2 4.3 7.8 4.5 1.2 7.6

9.3 Program Results

MO1DAF Example Program Results

Data Ranks 5.3 7 4.6 6 7.8 10 2 1.7 5.3 8 9.9 12 3 4 3.2 4.3 7.8 11 4.5 5 1.2 1 7.6 9