

# NAG Fortran Library Routine Document

## S18AEF

**Note:** before using this routine, please read the Users' Note for your implementation to check the interpretation of ***bold italicised*** terms and other implementation-dependent details.

### 1 Purpose

S18AEF returns the value of the modified Bessel Function  $I_0(x)$ , via the routine name.

### 2 Specification

```

real FUNCTION S18AEF(X, IFAIL)
  INTEGER          IFAIL
  real            X

```

### 3 Description

This routine evaluates an approximation to the modified Bessel Function of the first kind  $I_0(x)$ .

**Note:**  $I_0(-x) = I_0(x)$ , so the approximation need only consider  $x \geq 0$ .

The routine is based on three Chebyshev expansions:

For  $0 < x \leq 4$ ,

$$I_0(x) = e^x \sum_{r=0}' a_r T_r(t), \quad \text{where } t = 2\left(\frac{x}{4}\right) - 1.$$

For  $4 < x \leq 12$ ,

$$I_0(x) = e^x \sum_{r=0}' b_r T_r(t), \quad \text{where } t = \frac{x-8}{4}.$$

For  $x > 12$ ,

$$I_0(x) = \frac{e^x}{\sqrt{x}} \sum_{r=0}' c_r T_r(t), \quad \text{where } t = 2\left(\frac{12}{x}\right) - 1.$$

For small  $x$ ,  $I_0(x) \simeq 1$ . This approximation is used when  $x$  is sufficiently small for the result to be correct to ***machine precision***.

For large  $x$ , the routine must fail because of the danger of overflow in calculating  $e^x$ .

### 4 References

Abramowitz M and Stegun I A (1972) *Handbook of Mathematical Functions* (3rd Edition) Dover Publications

### 5 Parameters

1: X – ***real*** *Input*

*On entry:* the argument  $x$  of the function.

2: IFAIL – INTEGER *Input/Output*

*On entry:* IFAIL must be set to 0, -1 or 1. Users who are unfamiliar with this parameter should refer to Chapter P01 for details.

*On exit:* IFAIL = 0 unless the routine detects an error (see Section 6).

For environments where it might be inappropriate to halt program execution when an error is detected, the value  $-1$  or  $1$  is recommended. If the output of error messages is undesirable, then the value  $1$  is recommended. Otherwise, for users not familiar with this parameter the recommended value is  $0$ . **When the value  $-1$  or  $1$  is used it is essential to test the value of IFAIL on exit.**

## 6 Error Indicators and Warnings

If on entry  $IFAIL = 0$  or  $-1$ , explanatory error messages are output on the current error message unit (as defined by X04AAF).

Errors or warnings detected by the routine:

$IFAIL = 1$

X is too large. On soft failure the routine returns the approximate value of  $I_0(x)$  at the nearest valid argument.

## 7 Accuracy

Let  $\delta$  and  $\epsilon$  be the relative errors in the argument and result respectively.

If  $\delta$  is somewhat larger than the *machine precision* (i.e., if  $\delta$  is due to data errors etc.), then  $\epsilon$  and  $\delta$  are approximately related by:

$$\epsilon \simeq \left| \frac{xI_1(x)}{I_0(x)} \right| \delta.$$

Figure 1 shows the behaviour of the error amplification factor

$$\left| \frac{xI_1(x)}{I_0(x)} \right|.$$




Figure 1

However if  $\delta$  is of the same order as *machine precision*, then rounding errors could make  $\epsilon$  slightly larger than the above relation predicts.

For small  $x$  the amplification factor is approximately  $\frac{x^2}{2}$ , which implies strong attenuation of the error, but in general  $\epsilon$  can never be less than the *machine precision*.

For large  $x$ ,  $\epsilon \simeq x\delta$  and we have strong amplification of errors. However the routine must fail for quite moderate values of  $x$ , because  $I_0(x)$  would overflow; hence in practice the loss of accuracy for large  $x$  is not excessive. Note that for large  $x$  the errors will be dominated by those of the Fortran intrinsic function EXP.

## 8 Further Comments

None.

## 9 Example

The example program reads values of the argument  $x$  from a file, evaluates the function at each value of  $x$  and prints the results.

### 9.1 Program Text

**Note:** the listing of the example program presented below uses *bold italicised* terms to denote precision-dependent details. Please read the Users' Note for your implementation to check the interpretation of these terms. As explained in the Essential Introduction to this manual, the results produced may not be identical for all implementations.

```
*      S18AEF Example Program Text
*      Mark 14 Revised.  NAG Copyright 1989.
*      .. Parameters ..
      INTEGER          NIN, NOUT
      PARAMETER       (NIN=5,NOUT=6)
*      .. Local Scalars ..
      real            X, Y
      INTEGER          IFAIL
*      .. External Functions ..
      real            S18AEF
      EXTERNAL        S18AEF
*      .. Executable Statements ..
      WRITE (NOUT,*) 'S18AEF Example Program Results'
*      Skip heading in data file
      READ (NIN,*)
      WRITE (NOUT,*)
      WRITE (NOUT,*) '      X              Y              IFAIL'
      WRITE (NOUT,*)
20     READ (NIN,*,END=40) X
      IFAIL = 1
*
      Y = S18AEF(X,IFAIL)
*
      WRITE (NOUT,99999) X, Y, IFAIL
      GO TO 20
40     STOP
*
99999  FORMAT (1X,1P,2E12.3,I7)
      END
```

## 9.2 Program Data

S18AEF Example Program Data

```
0.0
0.5
1.0
3.0
6.0
8.0
10.0
15.0
20.0
-1.0
```

## 9.3 Program Results

S18AEF Example Program Results

X	Y	IFAIL
0.000E+00	1.000E+00	0
5.000E-01	1.063E+00	0
1.000E+00	1.266E+00	0
3.000E+00	4.881E+00	0
6.000E+00	6.723E+01	0
8.000E+00	4.276E+02	0
1.000E+01	2.816E+03	0
1.500E+01	3.396E+05	0
2.000E+01	4.356E+07	0
-1.000E+00	1.266E+00	0

---