# NAG Fortran Library Routine Document

## F01RJF

Note: before using this routine, please read the Users' Note for your implementation to check the interpretation of *bold italicised* terms and other implementation-dependent details.

## 1 Purpose

F01RJF finds the RQ factorization of the complex m by  $n \ (m \le n)$ , matrix A, so that A is reduced to upper triangular form by means of unitary transformations from the right.

## 2 Specification

SUBROUTINE FO1RJF(M, N, A, LDA, THETA, IFAIL)INTEGERM, N, LDA, IFAILcomplexA(LDA,\*), THETA(\*)

## **3** Description

The m by n matrix A is factorized as

$$\label{eq:alpha} \begin{split} A &= ( \begin{array}{cc} R & 0 \end{array} ) P^H & \text{when } m < n, \\ \\ A &= R P^H & \text{when } m = n, \end{split}$$

where P is an n by n unitary matrix and R is an m by m upper triangular matrix.

P is given as a sequence of Householder transformation matrices

$$P = P_m \cdots P_2 P_1,$$

the (m - k + 1)th transformation matrix,  $P_k$ , being used to introduce zeros into the kth row of A.  $P_k$  has the form

$$P_k = I - \gamma_k u_k u_k^H,$$

where

$$u_k = \begin{pmatrix} w_k \\ \zeta_k \\ 0 \\ z_k \end{pmatrix}.$$

 $\gamma_k$  is a scalar for which  $\operatorname{Re} \gamma_k = 1.0$ ,  $\zeta_k$  is a real scalar,  $w_k$  is a (k-1) element vector and  $z_k$  is an (n-m) element vector.  $\gamma_k$  and  $u_k$  are chosen to annihilate the elements in the kth row of A.

The scalar  $\gamma_k$  and the vector  $u_k$  are returned in the kth element of THETA and in the kth row of A, such that  $\theta_k$ , given by

$$\theta_k = (\zeta_k, \operatorname{Im} \gamma_k).$$

is in THETA(k), the elements of  $w_k$  are in A(k, 1), ..., A(k, k - 1) and the elements of  $z_k$  are in A(k, m + 1), ..., A(k, n). The elements of R are returned in the upper triangular part of A.

#### **4** References

Golub G H and van Loan C F (1996) *Matrix Computations* (3rd Edition) Johns Hopkins University Press, Baltimore

Wilkinson J H (1965) The Algebraic Eigenvalue Problem Oxford University Press, Oxford

## **5** Parameters

## 1: M – INTEGER

On entry: m, the number of rows of A. When M=0 an immediate return is effected. Constraint:  $M \ge 0$ .

#### 2: N – INTEGER

On entry: n, the number of columns of A. Constraint:  $N \ge M$ .

#### 3: A(LDA,\*) – *complex* array

Note: the second dimension of the array A must be at least max(1, N).

On entry: the leading m by n part of the array A must contain the matrix to be factorized.

On exit: the m by m upper triangular part of A will contain the upper triangular matrix R, and the m by m strictly lower triangular part of A and the m by (n - m) rectangular part of A to the right of the upper triangular part will contain details of the factorization as described in Section 3.

4: LDA – INTEGER

On entry: the first dimension of the array A as declared in the (sub)program from which F01RJF is called.

*Constraint*: LDA  $\geq \max(1, M)$ .

#### 5: THETA(\*) – *complex* array

Note: the dimension of the array THETA must be at least max(1, M).

On exit: THETA(k) contains the scalar  $\theta_k$  for the (m - k + 1)th transformation. If  $P_k = I$  then THETA(k) = 0.0; if

$$T_k = \begin{pmatrix} I & 0 & 0 \\ 0 & \alpha & 0 \\ 0 & 0 & I \end{pmatrix}, \quad \operatorname{Re} \alpha < 0.0$$

then THETA(k) =  $\alpha$ , otherwise THETA(k) contains  $\theta_k$  as described in Section 3 and  $\theta_k$  is always in the range  $(1.0, \sqrt{2.0})$ .

#### 6: IFAIL – INTEGER

On entry: IFAIL must be set to 0, -1 or 1. Users who are unfamiliar with this parameter should refer to Chapter P01 for details.

On exit: IFAIL = 0 unless the routine detects an error (see Section 6).

For environments where it might be inappropriate to halt program execution when an error is detected, the value -1 or 1 is recommended. If the output of error messages is undesirable, then the value 1 is recommended. Otherwise, for users not familiar with this parameter the recommended value is 0. When the value -1 or 1 is used it is essential to test the value of IFAIL on exit.

## 6 Error Indicators and Warnings

If on entry IFAIL = 0 or -1, explanatory error messages are output on the current error message unit (as defined by X04AAF).

Errors or warnings detected by the routine:

Output

Input/Output

Input

Input

Input/Output

Input

IFAIL = -1

 $\begin{array}{lll} & \text{On entry,} & M < 0, \\ & \text{or} & N < M, \\ & \text{or} & LDA < M. \end{array}$ 

## 7 Accuracy

The computed factors R and P satisfy the relation

$$(R\ 0)P^H = A + E,$$

where

$$||E|| \le c\epsilon ||A||,$$

 $\epsilon$  is the *machine precision* (see X02AJF), c is a modest function of m and n, and  $\|.\|$  denotes the spectral (two) norm.

## 8 Further Comments

The approximate number of floating-point operations is given by  $8m^2(3n-m)/3$ .

The first k rows of the unitary matrix  $P^H$  can be obtained by calling F01RKF, which overwrites the k rows of  $P^H$  on the first k rows of the array A.  $P^H$  is obtained by the call:

```
IFAIL = 0
CALL F01RKF('Separate',M,N,K,A,LDA,THETA,WORK,IFAIL)
```

WORK must be a  $\max(m-1, k-m, 1)$  element array. If K is larger than M, then A must have been declared to have at least K rows.

Operations involving the matrix R can readily be performed by the Level 2 BLAS routines F06SJF (CTRSV/ZTRSV) and F06SFF (CTRMV/ZTRMV), (see Chapter F06), but note that no test for near singularity of R is incorporated into F06SFF (CTRMV/ZTRMV). If R is singular, or nearly singular then F02XUF can be used to determine the singular value decomposition of R.

## 9 Example

To obtain the RQ factorization of the 3 by 5 matrix

$$A = \begin{pmatrix} -0.5i & 0.4 - 0.3i & 0.4 & 0.3 & 0.4i & 0.3i \\ -0.5 - 1.5i & 0.9 - 1.3i & -0.4 - 0.4i & 0.1 - 0.7i & 0.3 - 0.3i \\ -1.0 - 1.0i & 0.2 - 1.4i & 1.8 & 0.0 & -2.4i \end{pmatrix}.$$

#### 9.1 Program Text

**Note:** the listing of the example program presented below uses *bold italicised* terms to denote precision-dependent details. Please read the Users' Note for your implementation to check the interpretation of these terms. As explained in the Essential Introduction to this manual, the results produced may not be identical for all implementations.

```
FO1RJF Example Program Text
*
     Mark 14 Release. NAG Copyright 1989.
*
      .. Parameters ..
                       NIN, NOUT
     INTEGER
     PARAMETER
                       (NIN=5,NOUT=6)
     INTEGER
                       MMAX, NMAX, LDA
     PARAMETER
                       (MMAX=10,NMAX=20,LDA=MMAX)
*
      .. Local Scalars ..
                       I, IFAIL, J, M, N
      INTEGER
      .. Local Arrays ..
     complex
                       A(LDA,NMAX), THETA(MMAX)
      .. External Subroutines ..
+
     EXTERNAL
                      FO1RJF
      .. Executable Statements ..
     WRITE (NOUT,*) 'F01RJF Example Program Results'
```

#### F01RJF

```
Skip heading in data file
*
      READ (NIN, *)
      READ (NIN,*) M, N
      WRITE (NOUT, *)
      IF ((M.GT.MMAX) .OR. (N.GT.NMAX)) THEN
         WRITE (NOUT, *) 'M or N is out of range.'
         WRITE (NOUT, 99999) 'M = ', M, '
                                           N = ', N
      ELSE
         READ (NIN,*) ((A(I,J),J=1,N),I=1,M)
         IFAIL = 0
*
         Find the RQ factorization of A
         CALL FO1RJF(M,N,A,LDA,THETA,IFAIL)
*
         WRITE (NOUT, *) 'RQ factorization of A'
         WRITE (NOUT, *)
         WRITE (NOUT, *) 'Vector THETA'
         WRITE (NOUT, 99998) (THETA(I), I=1, M)
         WRITE (NOUT, *)
        WRITE (NOUT, *)
     + 'Matrix A after factorization (R is in left-hand upper triangle)'
         DO 20 I = 1, M
            WRITE (NOUT, 99998) (A(I,J), J=1,N)
        CONTINUE
   20
      END IF
      STOP
99999 FORMAT (1X,A,I5,A,I5)
99998 FORMAT (5(' (',F6.3,',',F6.3,')',:))
      END
```

## 9.2 Program Data

```
FO1RJF Example Program Data35:Values of M and N(0.00,-0.50)(0.40,-0.30)(0.40, 0.00)(0.30, 0.40)(0.00, 0.30)(-0.50,-1.50)(0.90,-1.30)(-0.40,-0.40)(0.10,-0.70)(0.30,-0.30)(-1.00,-1.00)(0.20,-1.40)(1.80, 0.00)(0.00, 0.00)(0.00,-2.40):End of matrix A
```

## 9.3 Program Results

FO1RJF Example Program Results

RQ factorization of A

Vector THETA ( 1.039,-0.101) ( 1.181, 0.381) ( 1.224,-0.000)

Matrix A after factorization (R is in left-hand upper triangle)
( 0.788, 0.000) (-0.255,-0.401) (-0.277,-0.277) (-0.285, 0.559) ( 0.115, 0.703)
( 0.040, 0.522) (-2.112, 0.000) (-1.109,-0.555) ( 0.128, 0.232) ( 0.079,-0.036)
(-0.227, 0.227) ( 0.045, 0.317) (-3.606, 0.000) ( 0.000,-0.000) ( 0.000, 0.544)