

# NAG Fortran Library Routine Document

## F04ACF

**Note:** before using this routine, please read the Users' Note for your implementation to check the interpretation of *bold italicised* terms and other implementation-dependent details.

### 1 Purpose

F04ACF calculates the approximate solution of a set of real symmetric positive-definite band equations with multiple right-hand sides, using a Cholesky factorization.

### 2 Specification

```
SUBROUTINE F04ACF(A, IA, B, IB, N, M, IR, C, IC, RL, IRL, M1, IFAIL)
INTEGER          IA, IB, N, M, IR, IC, IRL, M1, IFAIL
real           A(IA,M1), B(IB,IR), C(IC,IR), RL(IRL,M1)
```

### 3 Description

Given a set of real linear equations  $AX = B$ , where  $A$  is a symmetric positive-definite band matrix, the routine computes a Cholesky factorization of  $A$  as  $A = LL^T$ , where  $L$  is a lower triangular band matrix. The columns  $x$  of the solution  $X$  are found by forward and backward substitution in  $Ly = b$  and  $L^T x = y$ , where  $b$  is a column of the right-hand side matrix  $B$ .

### 4 References

Wilkinson J H and Reinsch C (1971) *Handbook for Automatic Computation II, Linear Algebra* Springer-Verlag

### 5 Parameters

1:  $A(IA,M1)$  – **real** array *Input*

*On entry:* the lower triangle of the  $n$  by  $n$  positive-definite symmetric band matrix  $A$ , with the diagonal of the matrix stored in the  $(m + 1)$ th column of the array, and the  $m$  sub-diagonals within the band stored in the first  $m$  columns of the array. Each row of the matrix is stored in the corresponding row of the array. For example, if  $n = 5$  and  $m = 2$ , the storage scheme is:

$$\begin{pmatrix} * & * & a_{11} \\ * & a_{21} & a_{22} \\ a_{31} & a_{32} & a_{33} \\ a_{42} & a_{43} & a_{44} \\ a_{53} & a_{54} & a_{55} \end{pmatrix}.$$

The elements in the top left corner of the array are not used. The following code may be used to assign elements within the band of the lower triangle of the matrix to the correct elements of the array:

```
DO 20 I = 1, N
  DO 10 J = MAX(1,I-M), I
    A(I,J-I+M+1) = matrix(I,J)
  10 CONTINUE
  20 CONTINUE
```

2:  $IA$  – INTEGER *Input*

*On entry:* the first dimension of the array  $A$  as declared in the (sub)program from which F04ACF is called.

- Constraint:*  $IA \geq N$ .
- 3: B(IB,IR) – *real* array *Input*  
*On entry:* the  $n$  by  $r$  right-hand side matrix  $B$ . See also Section 8.
- 4: IB – INTEGER *Input*  
*On entry:* the first dimension of the array B as declared in the (sub)program from which F04ACF is called.  
*Constraint:*  $IB \geq N$ .
- 5: N – INTEGER *Input*  
*On entry:*  $n$ , the order of the matrix  $A$ .
- 6: M – INTEGER *Input*  
*On entry:*  $m$ , the number of sub-diagonals within the band of  $A$ .
- 7: IR – INTEGER *Input*  
*On entry:*  $r$ , the number of right-hand sides.
- 8: C(IC,IR) – *real* array *Output*  
*On exit:* the  $n$  by  $r$  solution matrix  $X$ . See also Section 8.
- 9: IC – INTEGER *Input*  
*On entry:* the first dimension of the array C as declared in the (sub)program from which F04ACF is called.  
*Constraint:*  $IC \geq N$ .
- 10: RL(IRL,M1) – *real* array *Output*  
*On exit:* the lower triangular band matrix  $L$  stored in the same form as  $A$ , except that the reciprocals of the diagonal elements are stored instead of the elements themselves.
- 11: IRL – INTEGER *Input*  
*On entry:* the first dimension of the array RL as declared in the (sub)program from which F04ACF is called.  
*Constraint:*  $IRL \geq N$ .
- 12: M1 – INTEGER *Input*  
*On entry:* the value  $m + 1$ .
- 13: IFAIL – INTEGER *Input/Output*  
*On entry:* IFAIL must be set to 0, -1 or 1. Users who are unfamiliar with this parameter should refer to Chapter P01 for details.  
*On exit:* IFAIL = 0 unless the routine detects an error (see Section 6).
- For environments where it might be inappropriate to halt program execution when an error is detected, the value -1 or 1 is recommended. If the output of error messages is undesirable, then the value 1 is recommended. Otherwise, for users not familiar with this parameter the recommended value is 0. **When the value -1 or 1 is used it is essential to test the value of IFAIL on exit.**



```

IR = 1
IF (N.GT.0 .AND. N.LE.NMAX .AND. M1.GT.0 .AND. M1.LE.M1MAX) THEN
  READ (NIN,*) ((A(I,J),J=1,M1),B(I,1),I=1,N)
  M = M1 - 1
  IFAIL = 1
*
  CALL F04ACF(A,IA,B,IB,N,M,IR,C,IC,RL,IRL,M1,IFAIL)
*
  IF (IFAIL.NE.0) THEN
    WRITE (NOUT,99999) 'Error in F04ACF. IFAIL =', IFAIL
  ELSE
    WRITE (NOUT,*) ' Solution'
    WRITE (NOUT,99998) (C(I,1),I=1,N)
  END IF
ELSE
  WRITE (NOUT,99999) 'N or M1 is out of range: N = ', N,
+ ' M1 = ', M1
END IF
STOP
*
99999 FORMAT (1X,A,I5,A,I5)
99998 FORMAT (1X,F9.4)
END

```

## 9.2 Program Data

F04ACF Example Program Data

```

7 3
0 0 5 0
0 -4 6 0
1 -4 6 0
1 -4 6 1
1 -4 6 0
1 -4 6 0
1 -4 5 0

```

## 9.3 Program Results

F04ACF Example Program Results

```

Solution
4.0000
7.5000
10.0000
11.0000
10.0000
7.5000
4.0000

```