

NAG Fortran Library Routine Document

F07BFF (DGBEQU)

Note: before using this routine, please read the Users' Note for your implementation to check the interpretation of *bold italicised* terms and other implementation-dependent details.

1 Purpose

F07BFF (DGBEQU) computes diagonal scaling matrices D_R and D_C intended to equilibrate a real m by n band matrix A of band width $(k_l + k_u + 1)$, and reduce its condition number.

2 Specification

```

SUBROUTINE F07BFF (M, N, KL, KU, AB, LDAB, R, C, ROWCND, COLCND, AMAX,
1              INFO)
    INTEGER          M, N, KL, KU, LDAB, INFO
    double precision AB(LDAB,*), R(*), C(*), ROWCND, COLCND, AMAX

```

The routine may be called by its LAPACK name *dgbequ*.

3 Description

F07BFF (DGBEQU) computes the diagonal scaling matrices. The diagonal scaling matrices are chosen to try to make the elements of largest absolute value in each row and column of the matrix B given by

$$B = D_R A D_C$$

have absolute value 1. The diagonal elements of D_R and D_C are restricted to lie in the safe range $(\delta, 1/\delta)$, where δ is the value returned by routine X02AMF. Use of these scaling factors is not guaranteed to reduce the condition number of A but works well in practice.

4 References

None.

5 Parameters

- | | | |
|----|---|--------------|
| 1: | M – INTEGER | <i>Input</i> |
| | <i>On entry:</i> m , the number of rows of the matrix A . | |
| | <i>Constraint:</i> $M \geq 0$. | |
| 2: | N – INTEGER | <i>Input</i> |
| | <i>On entry:</i> n , the number of columns of the matrix A . | |
| | <i>Constraint:</i> $N \geq 0$. | |
| 3: | KL – INTEGER | <i>Input</i> |
| | <i>On entry:</i> k_l , the number of subdiagonals of the matrix A . | |
| | <i>Constraint:</i> $KL \geq 0$. | |
| 4: | KU – INTEGER | <i>Input</i> |
| | <i>On entry:</i> k_u , the number of superdiagonals of the matrix A . | |
| | <i>Constraint:</i> $KU \geq 0$. | |

- 5: AB(LDAB,*) – *double precision* array *Input*
Note: the second dimension of the array AB must be at least $\max(1, N)$.
On entry: the band matrix A whose scaling factors are to be computed, stored in rows 1 to $k_l + k_u + 1$ of AB. The j th column of the matrix A is stored in the j th column of the array AB as follows:

$$AB(k_u + 1 + i - j, j) = a_{ij}, \quad \text{for } \max(1, j - k_u) \leq i \leq \min(m, j + k_l).$$
- 6: LDAB – INTEGER *Input*
On entry: the first dimension of the array AB as declared in the (sub)program from which F07BFF (DGBEQU) is called.
Constraint: $LDAB \geq KL + KU + 1$.
- 7: R(*) – *double precision* array *Output*
Note: the dimension of the array R must be at least $\max(1, M)$.
On exit: if $INFO = 0$ or $INFO > M$, R contains the row scale factors, the diagonal elements of D_R . The elements of R will be positive.
- 8: C(*) – *double precision* array *Output*
Note: the dimension of the array C must be at least $\max(1, N)$.
On exit: if $INFO = 0$, C contains the column scale factors, the diagonal elements of D_C . The elements of C will be positive.
- 9: ROWCND – *double precision* *Output*
On exit: if $INFO = 0$ or $INFO > M$, ROWCND contains the ratio of the smallest value of $R(i)$ to the largest value of $R(i)$. If $ROWCND \geq 0.1$ and AMAX is neither too large nor too small, it is not worth scaling by D_R .
- 10: COLCND – *double precision* *Output*
On exit: if $INFO = 0$, COLCND contains the ratio of the smallest value of $C(i)$ to the largest value of $C(i)$.
If $COLCND \geq 0.1$, it is not worth scaling by D_C .
- 11: AMAX – *double precision* *Output*
On exit: $\max |a_{ij}|$. If AMAX is very close to overflow or underflow, the matrix A should be scaled.
- 12: INFO – INTEGER *Output*
On exit: $INFO = 0$ unless the routine detects an error (see Section 6).

6 Error Indicators and Warnings

Errors or warnings detected by the routine:

$INFO < 0$

If $INFO = -i$, the i th argument had an illegal value. An explanatory message is output, and execution of the program is terminated.

$INFO > 0$ and $INFO \leq M$

If $INFO = i$, the i th row of A is exactly zero.

INFO > M

If INFO = i , the $(i - M)$ th column of A is exactly zero

7 Accuracy

The computed scale factors will be close to the exact scale factors.

8 Further Comments

The complex analogue of this routine is F07BTF (ZGBEQU).

9 Example

To equilibrate the band matrix A given by

$$A = \begin{pmatrix} -0.23 & 2.54 & -3.66 \times 10^{-10} & 0 \\ -6.98 \times 10^{10} & 2.46 \times 10^{10} & -2.73 & -2.13 \times 10^{10} \\ 0 & 2.56 & 2.46 \times 10^{-10} & 4.07 \\ 0 & 0 & -4.78 \times 10^{-10} & -3.82 \end{pmatrix}.$$

Details of the scaling factors, and the scaled matrix are output.

9.1 Program Text

```
*      F07BFF Example Program Text
*      Mark 21 Release. NAG Copyright 2004.
*      .. Parameters ..
INTEGER      NIN, NOUT
PARAMETER    (NIN=5,NOUT=6)
INTEGER      NMAX, KLMAX, KUMAX
PARAMETER    (NMAX=8, KLMAX=4, KUMAX=4)
INTEGER      LDAB
PARAMETER    (LDAB=KLMAX+KUMAX+1)
*      .. Local Scalars ..
DOUBLE PRECISION AMAX, BIG, CJ, COLCND, ROWCND, SMALL
INTEGER      I, IFAIL, INFO, J, K, KL, KU, N
*      .. Local Arrays ..
DOUBLE PRECISION AB(LDAB,NMAX), C(NMAX), R(NMAX)
*      .. External Functions ..
DOUBLE PRECISION X02AJF, X02AMF
INTEGER      X02BHF
EXTERNAL     X02AJF, X02AMF, X02BHF
*      .. External Subroutines ..
EXTERNAL     DGBEQU, X04CEF
*      .. Intrinsic Functions ..
INTRINSIC    MAX, MIN
*      .. Executable Statements ..
WRITE (NOUT,*) 'F07BFF Example Program Results'
WRITE (NOUT,*)
*      Skip heading in data file
READ (NIN,*)
READ (NIN,*) N, KL, KU
IF (N.LE.NMAX .AND. KL.LE.KLMAX .AND. KU.LE.KUMAX) THEN
*
*      Read the band matrix A from data file
*
      K = KU + 1
      READ (NIN,*) ((AB(K+I-J,J),J=MAX(I-KL,1),MIN(I+KU,N)),I=1,N)
*
*      Print the matrix A
*
      IFAIL = 0
      CALL X04CEF(N,N,KL,KU,AB,LDAB,'Matrix A',IFAIL)
      WRITE (NOUT,*)
*

```

```

*      Compute row and column scaling factors
*
      CALL DGBEQU(N,N,KL,KU,AB,LDAB,R,C,ROWCND,COLCND,AMAX,INFO)
*
      IF (INFO.GT.0) THEN
        IF (INFO.LE.N) THEN
          WRITE (NOUT,99999) 'Row ', INFO, ' of A is exactly zero'
        ELSE
          WRITE (NOUT,99999) 'Column ', INFO - N,
+           ' of A is exactly zero'
        END IF
      ELSE
*
*      Print ROWCND, COLCND, AMAX and the scale factors
*
      WRITE (NOUT,99998) 'ROWCND = ', ROWCND, ', COLCND = ',
+       COLCND, ', AMAX = ', AMAX
      WRITE (NOUT,*)
      WRITE (NOUT,*) 'Row scale factors'
      WRITE (NOUT,99997) (R(I),I=1,N)
      WRITE (NOUT,*)
      WRITE (NOUT,*) 'Column scale factors'
      WRITE (NOUT,99997) (C(I),I=1,N)
      WRITE (NOUT,*)
*
*      Compute values close to underflow and overflow
*
      SMALL = X02AMF()/(X02AJF()*X02BHF())
      BIG = 1.0D0/SMALL
      IF ((ROWCND.GE.0.1D0) .AND. (AMAX.GE.SMALL)
+       .AND. (AMAX.LE.BIG)) THEN
        IF (COLCND.LT.0.1D0) THEN
*
*      Just column scale A
*
          DO 40 J = 1, N
            CJ = C(J)
            K = KU + 1 - J
            DO 20 I = MAX(1,J-KU), MIN(N,J+KL)
              AB(K+I,J) = AB(K+I,J)*CJ
            CONTINUE
          CONTINUE
20      CONTINUE
40
*
*      Print the column scaled matrix
*
          IFAIL = 0
          CALL X04CEF(N,N,KL,KU,AB,LDAB,'Scaled matrix',IFAIL)
*
          END IF
        ELSE IF (COLCND.GE.0.1D0) THEN
*
*      Just row scale A
*
          DO 80 J = 1, N
            K = KU + 1 - J
            DO 60 I = MAX(1,J-KU), MIN(N,J+KL)
              AB(K+I,J) = R(I)*AB(K+I,J)
            CONTINUE
          CONTINUE
60      CONTINUE
80
*
*      Print the row scaled matrix
*
          IFAIL = 0
          CALL X04CEF(N,N,KL,KU,AB,LDAB,'Scaled matrix',IFAIL)
*
          ELSE
*
*      Row and column scale A
*
          DO 120 J = 1, N
            CJ = C(J)

```

```

          K = KU + 1 - J
          DO 100 I = MAX(1,J-KU), MIN(N,J+KL)
            AB(K+I,J) = R(I)*AB(K+I,J)*CJ
100       CONTINUE
120       CONTINUE
*
*           Print the row and column scaled matrix
*
          IFAIL = 0
          CALL XO4CEF(N,N,KL,KU,AB,LDAB,'Scaled matrix',IFAIL)
*
          END IF
        END IF
      ELSE
        WRITE (NOUT,*)
+       'One or more of NMAX, KLMAX or KUMAX is too small'
      END IF
      STOP
*
99999 FORMAT (1X,A,I4,A)
99998 FORMAT (1X,3(A,1P,E7.1))
99997 FORMAT ((1X,1P,7E11.1))
      END

```

9.2 Program Data

F07BFF Example Program Data

```

  4  1  2                               :Values of N, KL and KU
-2.30D-01  2.54D+00 -3.66D-10
-6.98D+10  2.46D+10 -2.73D+00 -2.13D+10
          2.56D+00  2.46D-10  4.07D+00
          -4.78D-10 -3.82D+00       :End of matrix A

```

9.3 Program Results

F07BFF Example Program Results

Matrix A

	1	2	3	4
1	-2.3000E-01	2.5400E+00	-3.6600E-10	
2	-6.9800E+10	2.4600E+10	-2.7300E+00	-2.1300E+10
3		2.5600E+00	2.4600E-10	4.0700E+00
4			-4.7800E-10	-3.8200E+00

ROWCND = 3.6E-11, COLCND = 1.4E-10, AMAX = 7.0E+10

Row scale factors

3.9E-01	1.4E-11	2.5E-01	2.6E-01
---------	---------	---------	---------

Column scale factors

1.0E+00	1.0E+00	6.9E+09	1.0E+00
---------	---------	---------	---------

Scaled matrix

	1	2	3	4
1	-0.0906	1.0000	-1.0000	
2	-1.0000	0.3524	-0.2714	-0.3052
3		0.6290	0.4195	1.0000
4			-0.8684	-1.0000