

# NAG Fortran Library Routine Document

## F08NVF (ZGEBAL)

**Note:** before using this routine, please read the Users' Note for your implementation to check the interpretation of *bold italicised* terms and other implementation-dependent details.

### 1 Purpose

F08NVF (ZGEBAL) balances a complex general matrix in order to improve the accuracy of computed eigenvalues and/or eigenvectors.

### 2 Specification

```
SUBROUTINE F08NVF (JOB, N, A, LDA, ILO, IHI, SCALE, INFO)
INTEGER          N, LDA, ILO, IHI, INFO
double precision SCALE(*)
complex*16     A(LDA,*)
CHARACTER*1     JOB
```

The routine may be called by its LAPACK name *zgebal*.

### 3 Description

F08NVF (ZGEBAL) balances a complex general matrix  $A$ . The term 'balancing' covers two steps, each of which involves a similarity transformation of  $A$ . The routine can perform either or both of these steps.

1. The routine first attempts to permute  $A$  to block upper triangular form by a similarity transformation:

$$PAP^T = A' = \begin{pmatrix} A'_{11} & A'_{12} & A'_{13} \\ 0 & A'_{22} & A'_{23} \\ 0 & 0 & A'_{33} \end{pmatrix}$$

where  $P$  is a permutation matrix, and  $A'_{11}$  and  $A'_{33}$  are upper triangular. Then the diagonal elements of  $A'_{11}$  and  $A'_{33}$  are eigenvalues of  $A$ . The rest of the eigenvalues of  $A$  are the eigenvalues of the central diagonal block  $A'_{22}$ , in rows and columns  $i_{lo}$  to  $i_{hi}$ . Subsequent operations to compute the eigenvalues of  $A$  (or its Schur factorization) need only be applied to these rows and columns; this can save a significant amount of work if  $i_{lo} > 1$  and  $i_{hi} < n$ . If no suitable permutation exists (as is often the case), the routine sets  $i_{lo} = 1$  and  $i_{hi} = n$ , and  $A'_{22}$  is the whole of  $A$ .

2. The routine applies a diagonal similarity transformation to  $A'$ , to make the rows and columns of  $A'_{22}$  as close in norm as possible:

$$A'' = DA'D^{-1} = \begin{pmatrix} I & 0 & 0 \\ 0 & D_{22} & 0 \\ 0 & 0 & I \end{pmatrix} \begin{pmatrix} A'_{11} & A'_{12} & A'_{13} \\ 0 & A'_{22} & A'_{23} \\ 0 & 0 & A'_{33} \end{pmatrix} \begin{pmatrix} I & 0 & 0 \\ 0 & D_{22}^{-1} & 0 \\ 0 & 0 & I \end{pmatrix}.$$

This scaling can reduce the norm of the matrix (that is,  $\|A''\| < \|A'_{22}\|$ ) and hence reduce the effect of rounding errors on the accuracy of computed eigenvalues and eigenvectors.

### 4 References

Golub G H and Van Loan C F (1996) *Matrix Computations* (3rd Edition) Johns Hopkins University Press, Baltimore

## 5 Parameters

- 1: JOB – CHARACTER\*1 *Input*  
*On entry:* indicates whether  $A$  is to be permuted and/or scaled (or neither).  
 JOB = 'N'  
 $A$  is neither permuted nor scaled (but values are assigned to ILO, IHI and SCALE).  
 JOB = 'P'  
 $A$  is permuted but not scaled.  
 JOB = 'S'  
 $A$  is scaled but not permuted.  
 JOB = 'B'  
 $A$  is both permuted and scaled.  
*Constraint:* JOB = 'N', 'P', 'S' or 'B'.
- 2: N – INTEGER *Input*  
*On entry:*  $n$ , the order of the matrix  $A$ .  
*Constraint:*  $N \geq 0$ .
- 3: A(LDA,\*) – **complex\*16** array *Input/Output*  
**Note:** the second dimension of the array  $A$  must be at least  $\max(1, N)$ .  
*On entry:* the  $n$  by  $n$  matrix  $A$ .  
*On exit:* is overwritten by the balanced matrix. If JOB = 'N',  $A$  is not referenced.
- 4: LDA – INTEGER *Input*  
*On entry:* the first dimension of the array  $A$  as declared in the (sub)program from which F08NVF (ZGEBAL) is called.  
*Constraint:*  $LDA \geq \max(1, N)$ .
- 5: ILO – INTEGER *Output*  
 6: IHI – INTEGER *Output*  
*On exit:* the values  $i_{lo}$  and  $i_{hi}$  such that on exit  $A(i, j)$  is zero if  $i > j$  and  $1 \leq j < i_{lo}$  or  $i_{hi} < i \leq n$ .  
 If JOB = 'N' or 'S',  $i_{lo} = 1$  and  $i_{hi} = n$ .
- 7: SCALE(\*) – **double precision** array *Output*  
**Note:** the dimension of the array SCALE must be at least  $\max(1, N)$ .  
*On exit:* details of the permutations and scaling factors applied to  $A$ . More precisely, if  $p_j$  is the index of the row and column interchanged with row and column  $j$  and  $d_j$  is the scaling factor used to balance row and column  $j$  then
 
$$\text{SCALE}(j) = \begin{cases} p_j, & j = 1, 2, \dots, i_{lo} - 1 \\ d_j, & j = i_{lo}, i_{lo} + 1, \dots, i_{hi} \quad \text{and} \\ p_j, & j = i_{hi} + 1, i_{hi} + 2, \dots, n. \end{cases}$$
 The order in which the interchanges are made is  $n$  to  $i_{hi} + 1$  then 1 to  $i_{lo} - 1$ .
- 8: INFO – INTEGER *Output*  
*On exit:* INFO = 0 unless the routine detects an error (see Section 6).

## 6 Error Indicators and Warnings

Errors or warnings detected by the routine:

INFO < 0

If INFO =  $-i$ , the  $i$ th parameter had an illegal value. An explanatory message is output, and execution of the program is terminated.

## 7 Accuracy

The errors are negligible, compared with those in subsequent computations.

## 8 Further Comments

If the matrix  $A$  is balanced by F08NVF (ZGEBAL), then any eigenvectors computed subsequently are eigenvectors of the matrix  $A''$  (see Section 3) and hence F08NWF (ZGEBAK) **must** then be called to transform them back to eigenvectors of  $A$ .

If the Schur vectors of  $A$  are required, then this routine must **not** be called with JOB = 'S' or 'B', because then the balancing transformation is not unitary. If this routine is called with JOB = 'P', then any Schur vectors computed subsequently are Schur vectors of the matrix  $A''$ , and F08NWF (ZGEBAK) **must** be called (with SIDE = 'R') to transform them back to Schur vectors of  $A$ .

The total number of real floating-point operations is approximately proportional to  $n^2$ .

The real analogue of this routine is F08NHF (DGEBAL).

## 9 Example

This example computes all the eigenvalues and right eigenvectors of the matrix  $A$ , where

$$A = \begin{pmatrix} 1.50 - 2.75i & 0.00 + 0.00i & 0.00 + 0.00i & 0.00 + 0.00i \\ -8.06 - 1.24i & -2.50 - 0.50i & 0.00 + 0.00i & -0.75 + 0.50i \\ -2.09 + 7.56i & 1.39 + 3.97i & -1.25 + 0.75i & -4.82 - 5.67i \\ 6.18 + 9.79i & -0.92 - 0.62i & 0.00 + 0.00i & -2.50 - 0.50i \end{pmatrix}.$$

The program first calls F08NVF (ZGEBAL) to balance the matrix; it then computes the Schur factorization of the balanced matrix, by reduction to Hessenberg form and the  $QR$  algorithm. Then it calls F08QXF (ZTREVC) to compute the right eigenvectors of the balanced matrix, and finally calls F08NWF (ZGEBAK) to transform the eigenvectors back to eigenvectors of the original matrix  $A$ .

### 9.1 Program Text

```
*      F08NVF Example Program Text
*      Mark 20 Revised. NAG Copyright 2001.
*      .. Parameters ..
      INTEGER          NIN, NOUT
      PARAMETER       (NIN=5,NOUT=6)
      INTEGER          NMAX, LDA, LDH, LWORK, LDVL, LDVR
      PARAMETER       (NMAX=8,LDA=NMAX,LDH=NMAX,LWORK=64*NMAX,LDVL=1,
+                    LDVR=NMAX)
*      .. Local Scalars ..
      INTEGER          I, IFAIL, IHI, ILO, INFO, J, M, N
*      .. Local Arrays ..
      COMPLEX *16     A(LDA,NMAX), H(LDH,NMAX), TAU(NMAX), VL(LDVL,1),
+                    VR(LDVR,NMAX), W(NMAX), WORK(LWORK)
      DOUBLE PRECISION RWORK(NMAX), SCALE(NMAX)
      LOGICAL         SELECT(1)
      CHARACTER       CLABS(1), RLABS(1)
*      .. External Subroutines ..
      EXTERNAL        F06TFF, X04DBF, ZGEBAK, ZGEBAL, ZGEHRD, ZHSEQR,
+                    ZTREVC, ZUNGHR
*      .. Intrinsic Functions ..
```

```

      INTRINSIC          DBLE, AIMAG
*      .. Executable Statements ..
      WRITE (NOUT,*) 'F08NVF Example Program Results'
*      Skip heading in data file
      READ (NIN,*)
      READ (NIN,*) N
      IF (N.LE.NMAX) THEN
*
*         Read A from data file
*
*         READ (NIN,*) ((A(I,J),J=1,N),I=1,N)
*
*         Balance A
*
*         CALL ZGEBAL('Both',N,A,LDA,ILO,IHI,SCALE,INFO)
*
*         Reduce A to upper Hessenberg form H = (Q**H)*A*Q
*
*         CALL ZGHRD(N,ILO,IHI,A,LDA,TAU,WORK,LWORK,INFO)
*
*         Copy A to H
*
*         CALL F06TFF('General',N,N,A,LDA,H,LDH)
*
*         Copy A into VR
*
*         CALL F06TFF('General',N,N,A,LDA,VR,LDVR)
*
*         Form Q explicitly, storing the result in VR
*
*         CALL ZUNGHR(N,1,N,VR,LDVR,TAU,WORK,LWORK,INFO)
*
*         Calculate the eigenvalues and Schur factorization of A
*
*         CALL ZHSEQR('Schur form','Vectors',N,ILO,IHI,H,LDH,W,VR,LDVR,
+             WORK,LWORK,INFO)
*
*         WRITE (NOUT,*)
*         IF (INFO.GT.0) THEN
*           WRITE (NOUT,*) 'Failure to converge.'
*         ELSE
*           WRITE (NOUT,*) 'Eigenvalues'
*           WRITE (NOUT,99999) (' (',DBLE(W(I))',',',AIMAG(W(I))',')',I=1,
+             N)
*
*         Calculate the eigenvectors of A, storing the result in VR
*
*         CALL ZTREVC('Right','Backtransform',SELECT,N,H,LDH,VL,LDVL,
+             VR,LDVR,N,M,WORK,RWORK,INFO)
*
*         CALL ZGEBAK('Both','Right',N,ILO,IHI,SCALE,M,VR,LDVR,INFO)
*
*         Print eigenvectors
*
*         WRITE (NOUT,*)
*         IFAIL = 0
*
*         CALL X04DBF('General',' ',N,M,VR,LDVR,'Bracketed','F7.4',
+             'Contents of array VR','Integer',RLABS,
+             'Integer',CLABS,80,0,IFAIL)
*
*         END IF
*         END IF
*         STOP
*
* 99999 FORMAT ((3X,4(A,F7.4,A,F7.4,A,:))
*             END

```

## 9.2 Program Data

F08NVF Example Program Data

```

4
( 1.50,-2.75) ( 0.00, 0.00) ( 0.00, 0.00) ( 0.00, 0.00)
(-8.06,-1.24) (-2.50,-0.50) ( 0.00, 0.00) (-0.75, 0.50)
(-2.09, 7.56) ( 1.39, 3.97) (-1.25, 0.75) (-4.82,-5.67)
( 6.18, 9.79) (-0.92,-0.62) ( 0.00, 0.00) (-2.50,-0.50)
:Value of N
:End of matrix A

```

## 9.3 Program Results

F08NVF Example Program Results

Eigenvalues

```
(-1.2500, 0.7500) (-1.5000,-0.4975) (-3.5000,-0.5025) ( 1.5000,-2.7500)
```

Contents of array VR

```

1 2 3 4
1 ( 0.0000, 0.0000) ( 0.0000, 0.0000) ( 0.0000, 0.0000) ( 0.1452, 0.0000)
2 ( 0.0000, 0.0000) (-0.0616, 0.0413) ( 0.4613,-0.0000) (-0.2072,-0.2450)
3 ( 1.0000, 0.0000) ( 0.6032,-0.3968) ( 0.2983, 0.7017) ( 0.7768, 0.2232)
4 ( 0.0000, 0.0000) ( 0.0822, 0.0000) ( 0.4251, 0.2850) (-0.0119, 0.4372)

```

---