

NAG Fortran Library Routine Document

H02CCF

Note: before using this routine, please read the Users' Note for your implementation to check the interpretation of *bold italicised* terms and other implementation-dependent details.

1 Purpose

To supply optional parameters to H02CBF from an external file.

2 Specification

```
SUBROUTINE H02CCF (IOPTNS, INFORM)
INTEGER          IOPTNS, INFORM
```

3 Description

H02CCF may be used to supply values for optional parameters to H02CBF. H02CCF reads an external file and each line of the file defines a single optional parameter. It is only necessary to supply values for those parameters whose values are to be different from their default values.

Each optional parameter is defined by a single character string of up to 72 characters, consisting of one or more items. The items associated with a given option must be separated by spaces, or equal signs [=]. Alphabetic characters may be upper or lower case. The string

```
Print level = 1
```

is an example of a string used to set an optional parameter. For each option the string contains one or more of the following items:

- (a) a mandatory keyword;
- (b) a phrase that qualifies the keyword;
- (c) a number that specifies an INTEGER or *real* value. Such numbers may be up to 16 contiguous characters in Fortran 77's I, F, E or D formats, terminated by a space if this is not the last item on the line.

Blank strings and comments are ignored. A comment begins with an asterisk (*) and all subsequent characters in the string are regarded as part of the comment.

The file containing the options must start with **begin** and must finish with **end**. An example of a valid options file is:

```
Begin * Example options file
Print level = 10
End
```

Normally each line of the file is printed as it is read, on the current advisory message unit (see X04ABF), but printing may be suppressed using the keyword **nolist**. To suppress printing of **begin**, **nolist** must be the first option supplied as in the file:

```
Begin
Nolist
Print level = 10
End
```

Printing will automatically be turned on again after a call to H02CBF and may be turned on again at any time by the user by using the keyword **list**.

Optional parameter settings are preserved following a call to H02CBF, and so the keyword **defaults** is provided to allow the user to reset all the optional parameters to their default values prior to a subsequent call to H02CBF.

A complete list of optional parameters, their abbreviations, synonyms and default values is given in Section 11 of the document for H02CBF.

4 References

None.

5 Parameters

- 1: IOPTNS – INTEGER *Input*
On entry: the unit number of the options file to be read.
Constraint: $0 \leq \text{IOPTNS} \leq 99$.
- 2: INFORM – INTEGER *Output*
On exit: contains zero if the options file has been successfully read and a value > 0 otherwise, as indicated below.
 INFORM = 1
 IOPTNS is not in the range $[0, 99]$.
 INFORM = 2
 begin was found, but end-of-file was found before **end** was found.
 INFORM = 3
 end-of-file was found before **begin** was found.

6 Error Indicators and Warnings

If a line is not recognized as a valid option, then a warning message is output on the current advisory message unit (see X04ABF).

7 Accuracy

Not applicable.

8 Further Comments

H02CDF may also be used to supply optional parameters to H02CBF. Note that if E04NFF/E04NFA is used in the same program as H02CBF, then in general H02CCF will also affect the options used by E04NFF/E04NFA.

9 Example

This example solves the same problem as the example for H02CBF, but in addition illustrates the use of H02CCF and H02CDF to set optional parameters for H02CBF.

In this example the options file read by H02CCF is appended to the data file for the program (see H02CCF). It would usually be more convenient in practice to keep the data file and the options file separate.

9.1 Program Text

Note: the listing of the example program presented below uses *bold italicised* terms to denote precision-dependent details. Please read the Users' Note for your implementation to check the interpretation of these terms. As explained in the Essential Introduction to this manual, the results produced may not be identical for all implementations.

```

*      H02CCF Example Program Text.
*      Mark 20 Revised. NAG Copyright 2001.
*      .. Parameters ..
INTEGER      NIN, NOUT, LINTVR
PARAMETER    (NIN=5,NOUT=6,LINTVR=1)
INTEGER      NMAX, NCMAX
PARAMETER    (NMAX=10,NCMAX=10)
INTEGER      LDA, LDH
PARAMETER    (LDA=NCMAX,LDH=NMAX)
INTEGER      LIWORK, LWORK, MDEPTH
PARAMETER    (LIWORK=1000,LWORK=10000,MDEPTH=30)
*      .. Local Scalars ..
real      OBJ
INTEGER      I, IFAIL, INFORM, J, N, NCLIN, STRTGY
*      .. Local Arrays ..
real      A(LDA,NMAX), AX(NCMAX), BL(NMAX+NCMAX),
+          BU(NMAX+NCMAX), CLAMDA(NMAX+NCMAX), CVEC(NMAX),
+          H(LDH,NMAX), WORK(LWORK), X(NMAX+NCMAX)
INTEGER      INTVAR(LINTVR), ISTATE(NMAX+NCMAX), IWORK(LIWORK)
*      .. External Subroutines ..
EXTERNAL     EO4NFU, H02CBF, H02CBU, H02CCF, H02CDF, X04ABF
*      .. Executable Statements ..
WRITE (NOUT,*) 'H02CCF Example Program Results'
*      Skip heading in data file
READ (NIN,*)
READ (NIN,*) N, NCLIN
IF (N.LE.NMAX .AND. NCLIN.LE.NCMAX) THEN
*
*      Read CVEC, A, BL, BU, X and H from data file
*
      READ (NIN,*) (CVEC(I),I=1,N)
      READ (NIN,*) ((A(I,J),J=1,N),I=1,NCLIN)
      READ (NIN,*) (BL(I),I=1,N+NCLIN)
      READ (NIN,*) (BU(I),I=1,N+NCLIN)
      READ (NIN,*) (X(I),I=1,N)
      READ (NIN,*) ((H(I,J),J=1,N),I=1,N)
*
*      Set four options using H02CDF
*
      CALL H02CDF(' Print Level = 1 ')
*
      CALL H02CDF(' Check Frequency = 10 ')
*
      CALL H02CDF(' Crash Tolerance = 0.05 ')
*
      CALL H02CDF(' Infinite Bound Size = 1.0D+25 ')
*
*      Set the unit number for advisory messages to NOUT
*
      CALL X04ABF(1,NOUT)
*
*      Read the options file for the remaining options
*
      CALL H02CCF(NIN,INFORM)
*
      IF (INFORM.NE.0) THEN
+          WRITE (NOUT,99998) 'H02CCF terminated with INFORM = ',
+          INFORM
          STOP
      END IF
*
      STRTGY = 2
      INTVAR(1) = 4
*
      CALL H02CDF('Nolist')

```

```

      CALL H02CDF('Print Level = 0')
*
*   Solve the problem
*
      IFAIL = 1
*
      CALL H02CBF(N,NCLIN,A,LDA,BL,BU,CVEC,H,LDH,E04NFU,INTVAR,
+             LINTVR,MDEPTH,ISTATE,X,OBJ,AX,CLAMDA,STRTRY,IWORK,
+             LIWORK,WORK,LWORK,H02CBU,IFAIL)
*
*   Print out the best integer solution found
*
      WRITE (NOUT,99999) OBJ, (I,X(I),I=1,N)
*
      END IF
*
      STOP
*
99999 FORMAT (//' Optimal Integer Value is = ',e20.8,/' Components ar',
+           'e ',/' x(',I3,') = ',F15.8)
99998 FORMAT (A,I3)
      END

```

9.2 Program Data

H02CCF Example Program Data

```

  7 7                                     :Values of N and NCLIN
-0.02 -0.20 -0.20 -0.20 -0.20  0.04  0.04 :End of CVEC
  1.00  1.00  1.00  1.00  1.00  1.00  1.00
  0.15  0.04  0.02  0.04  0.02  0.01  0.03
  0.03  0.05  0.08  0.02  0.06  0.01  0.00
  0.02  0.04  0.01  0.02  0.02  0.00  0.00
  0.02  0.03  0.00  0.00  0.01  0.00  0.00
  0.70  0.75  0.80  0.75  0.80  0.97  0.00
  0.02  0.06  0.08  0.12  0.02  0.01  0.97 :End of matrix A
-0.01 -0.10 -0.01 -0.04 -0.10 -0.01 -0.01
-0.13 -1.0e+25 -1.0e+25 -1.0e+25 -1.0e+25 -9.92e-02 -3.0e-03 :End of BL
  0.01  0.15  0.03  0.02  0.05  1.0e+25  1.0e+25
-0.13 -4.9e-03 -6.4e-03 -3.7e-03 -1.2e-03  1.0e+25  2.0e-03 :End of BU
-0.01 -0.03  0.00 -0.01 -0.10  0.02  0.01 :End of X
  2.00  0.00  0.00  0.00  0.00  0.00  0.00
  0.00  2.00  0.00  0.00  0.00  0.00  0.00
  0.00  0.00  2.00  2.00  0.00  0.00  0.00
  0.00  0.00  2.00  2.00  0.00  0.00  0.00
  0.00  0.00  0.00  0.00  2.00  0.00  0.00
  0.00  0.00  0.00  0.00  0.00 -2.00 -2.00
  0.00  0.00  0.00  0.00  0.00 -2.00 -2.00 :End of matrix H
Begin Example options file for H02CCF
  Feasibility Phase Iteration Limit = 5 * (Default = 70)
  Optimality Phase Iteration Limit = 10 * (Default = 70)
End

```

9.3 Program Results

H02CCF Example Program Results

Calls to H02CDF

Print Level = 1
Check Frequency = 10
Crash Tolerance = 0.05
Infinite Bound Size = 1.0E+25

OPTIONS file

Begin Example options file for H02CCF
Feasibility Phase Iteration Limit = 5 * (Default = 70)
Optimality Phase Iteration Limit = 10 * (Default = 70)
End

Optimal Integer Value is = 0.37469662E-01

Components are

x(1) = -0.01000000
x(2) = -0.07332830
x(3) = -0.00025809
x(4) = 0.00000000
x(5) = -0.06335433
x(6) = 0.01410944
x(7) = 0.00283128
