

NAG Toolbox for MATLAB

f07be

1 Purpose

f07be solves a real band system of linear equations with multiple right-hand sides,

$$AX = B \quad \text{or} \quad A^T X = B,$$

where A has been factorized by f07bd.

2 Syntax

```
[b, info] = f07be(trans, kl, ku, ab, ipiv, b, 'n', n, 'nrhs_p', nrhs_p)
```

3 Description

f07be is used to solve a real band system of linear equations $AX = B$ or $A^T X = B$, the function must be preceded by a call to f07bd which computes the LU factorization of A as $A = PLU$. The solution is computed by forward and backward substitution.

If **trans** = 'N', the solution is computed by solving $PLY = B$ and then $UX = Y$.

If **trans** = 'T' or 'C', the solution is computed by solving $U^T Y = B$ and then $L^T P^T X = Y$.

4 References

Golub G H and Van Loan C F 1996 *Matrix Computations* (3rd Edition) Johns Hopkins University Press, Baltimore

5 Parameters

5.1 Compulsory Input Parameters

1: **trans** – string

Indicates the form of the equations.

trans = 'N'

$AX = B$ is solved for X .

trans = 'T' or 'C'

$A^T X = B$ is solved for X .

Constraint: **trans** = 'N', 'T' or 'C'.

2: **kl** – int32 scalar

k_l , the number of subdiagonals within the band of the matrix A .

Constraint: **kl** ≥ 0 .

3: **ku** – int32 scalar

k_u , the number of superdiagonals within the band of the matrix A .

Constraint: **ku** ≥ 0 .

4: **ab(ldab,*) – double array**

The first dimension of the array **ab** must be at least $2 \times \mathbf{kl} + \mathbf{ku} + 1$

The second dimension of the array must be at least $\max(1, \mathbf{n})$

The *LU* factorization of *A*, as returned by f07bd.

5: **ipiv(*) – int32 array**

Note: the dimension of the array **ipiv** must be at least $\max(1, \mathbf{n})$.

The pivot indices, as returned by f07bd.

6: **b(ldb,*) – double array**

The first dimension of the array **b** must be at least $\max(1, \mathbf{n})$

The second dimension of the array must be at least $\max(1, \mathbf{nrhs_p})$

The *n* by *r* right-hand side matrix *B*.

5.2 Optional Input Parameters1: **n – int32 scalar**

Default: The second dimension of the array **ab**.

n, the order of the matrix *A*.

Constraint: $\mathbf{n} \geq 0$.

2: **nrhs_p – int32 scalar**

Default: The second dimension of the array **b**.

r, the number of right-hand sides.

Constraint: $\mathbf{nrhs_p} \geq 0$.

5.3 Input Parameters Omitted from the MATLAB Interface

ldab, ldb

5.4 Output Parameters1: **b(ldb,*) – double array**

The first dimension of the array **b** must be at least $\max(1, \mathbf{n})$

The second dimension of the array must be at least $\max(1, \mathbf{nrhs_p})$

The *n* by *r* solution matrix *X*.

2: **info – int32 scalar**

info = 0 unless the function detects an error (see Section 6).

6 Error Indicators and Warnings

Errors or warnings detected by the function:

info = $-i$

If **info** = $-i$, parameter *i* had an illegal value on entry. The parameters are numbered as follows:

1: **trans**, 2: **n**, 3: **kl**, 4: **ku**, 5: **nrhs_p**, 6: **ab**, 7: **ldab**, 8: **ipiv**, 9: **b**, 10: **ldb**, 11: **info**.

It is possible that **info** refers to a parameter that is omitted from the MATLAB interface. This usually indicates that an error in one of the other input parameters has caused an incorrect value to be inferred.

7 Accuracy

For each right-hand side vector b , the computed solution x is the exact solution of a perturbed system of equations $(A + E)x = b$, where

$$|E| \leq c(k)\epsilon P|L||U|,$$

$c(k)$ is a modest linear function of $k = k_l + k_u + 1$, and ϵ is the *machine precision*. This assumes $k \ll n$.

If \hat{x} is the true solution, then the computed solution x satisfies a forward error bound of the form

$$\frac{\|x - \hat{x}\|_\infty}{\|x\|_\infty} \leq c(k) \text{cond}(A, x)\epsilon$$

where $\text{cond}(A, x) = \| |A^{-1}| |A| |x| \|_\infty / \|x\|_\infty \leq \text{cond}(A) = \| |A^{-1}| |A| \|_\infty \leq \kappa_\infty(A)$.

Note that $\text{cond}(A, x)$ can be much smaller than $\text{cond}(A)$, and $\text{cond}(A^T)$ can be much larger (or smaller) than $\text{cond}(A)$.

Forward and backward error bounds can be computed by calling f07bh, and an estimate for $\kappa_\infty(A)$ can be obtained by calling f07bg with **norm_p** = 'I'.

8 Further Comments

The total number of floating-point operations is approximately $2n(2k_l + k_u)r$, assuming $n \gg k_l$ and $n \gg k_u$.

This function may be followed by a call to f07bh to refine the solution and return an error estimate.

The complex analogue of this function is f07bs.

9 Example

```
trans = 'N';
m = int32(4);
kl = int32(1);
ku = int32(2);
ab = [0, 0, 0, 0;
      0, 0, -3.66, -2.13;
      0, 2.54, -2.73, 4.07;
      -0.23, 2.46, 2.46, -3.82;
      -6.98, 2.56, -4.78, 0];
b = [4.42, -36.01;
     27.13, -31.67;
     -6.14, -1.16;
     10.5, -25.82];
[ab, ipiv, info] = f07bd(m, kl, ku, ab);
[bOut, info] = f07be(trans, kl, ku, ab, ipiv, b)

bOut =
    -2.0000    1.0000
     3.0000   -4.0000
     1.0000    7.0000
    -4.0000   -2.0000
info =
      0
```