

NAG Toolbox for MATLAB

f08pb

1 Purpose

f08pb computes the eigenvalues, the real Schur form T , and, optionally, the matrix of Schur vectors Z for an n by n real nonsymmetric matrix A .

2 Syntax

```
[a, sdim, wr, wi, vs, rconde, rcondv, info] = f08pb(jobvs, sort, select, sense, a, 'n', n)
```

3 Description

The real Schur factorization of A is given by

$$A = ZTZ^T,$$

where Z is orthogonal, the matrix of Schur vectors, and T is upper quasi-triangular with 1 by 1 and 2 by 2 diagonal blocks.

A matrix is in real Schur form if it is upper quasi-triangular with 1 by 1 and 2 by 2 blocks. 2 by 2 blocks will be standardized in the form

$$\begin{bmatrix} a & b \\ c & a \end{bmatrix}$$

where $bc < 0$. The eigenvalues of such a block are $a \pm \sqrt{bc}$.

Optionally, f08pb also orders the eigenvalues on the diagonal of the real Schur form so that selected eigenvalues are at the top left; computes a reciprocal condition number for the average of the selected eigenvalues (**rconde**); and computes a reciprocal condition number for the right invariant subspace corresponding to the selected eigenvalues (**rcondv**). The leading columns of Z form an orthonormal basis for this invariant subspace.

For further explanation of the reciprocal condition numbers **rconde** and **rcondv**, see Section 4.8 of Anderson *et al.* 1999 (where these quantities are called s and sep respectively).

4 References

Anderson E, Bai Z, Bischof C, Blackford S, Demmel J, Dongarra J J, Du Croz J J, Greenbaum A, Hammarling S, McKenney A and Sorensen D 1999 *LAPACK Users' Guide* (3rd Edition) SIAM, Philadelphia URL: <http://www.netlib.org/lapack/lug>

Golub G H and Van Loan C F 1996 *Matrix Computations* (3rd Edition) Johns Hopkins University Press, Baltimore

5 Parameters

5.1 Compulsory Input Parameters

1: **jobvs** – string

If **jobvs** = 'N', Schur vectors are not computed.

If **jobvs** = 'V', Schur vectors are computed.

Constraint: **jobvs** = 'N' or 'V'.

2: **sort – string**

Specifies whether or not to order the eigenvalues on the diagonal of the Schur form.

sort = 'N'

Eigenvalues are not ordered.

sort = 'S'

Eigenvalues are ordered (see user-supplied logical function **select**).

Constraint: **sort** = 'N' or 'S'.

3: **select – string containing name of m-file**

If **sort** = 'S', **select** is used to select eigenvalues to sort to the top left of the Schur form.

If **sort** = 'N', **select** is not referenced and f08pb may be called with the string 'f08paz'.

Its specification is:

```
[result] = select(wr, wi)
```

Input Parameters

1: **wr – double scalar**

2: **wi – double scalar**

An eigenvalue $\mathbf{wr}(j) + \sqrt{-1} \times \mathbf{wi}(j)$ is selected if **select**(**wr**(*j*), **wi**(*j*)) is **true**. If either one of a complex conjugate pair of eigenvalues is selected, then both are. Note that a selected complex eigenvalue may no longer satisfy **select**(**wr**(*j*), **wi**(*j*)) = **true** after ordering, since ordering may change the value of complex eigenvalues (especially if the eigenvalue is ill-conditioned); in this case **info** is set to **n** + 2 (see **info** below).

Output Parameters

1: **result – logical scalar**

The result of the function.

4: **sense – string**

Determines which reciprocal condition numbers are computed.

sense = 'N'

None are computed.

sense = 'E'

Computed for average of selected eigenvalues only.

sense = 'V'

Computed for selected right invariant subspace only.

sense = 'B'

Computed for both.

If **sense** = 'E', 'V' or 'B', **sort** must equal 'S'.

Constraint: **sense** = 'N', 'E', 'V' or 'B'.

5: **a(lda,*) – double array**

The first dimension of the array **a** must be at least $\max(1, \mathbf{n})$

The second dimension of the array must be at least $\max(1, \mathbf{n})$

The n by n matrix A .

5.2 Optional Input Parameters

1: **n** – int32 scalar

Default: The first dimension of the array **a** and the second dimension of the array **a**. (An error is raised if these dimensions are not equal.)

n , the order of the matrix A .

Constraint: $\mathbf{n} \geq 0$.

5.3 Input Parameters Omitted from the MATLAB Interface

lda, ldvs, work, lwork, iwork, liwork, bwork

5.4 Output Parameters

1: **a(lda,*)** – double array

The first dimension of the array **a** must be at least $\max(1, \mathbf{n})$

The second dimension of the array must be at least $\max(1, \mathbf{n})$

a contains its real Schur form T .

2: **sdim** – int32 scalar

If **sort** = 'N', **sdim** = 0.

If **sort** = 'S', **sdim** = number of eigenvalues (after sorting) for which user-supplied logical function **select** is **true**. (Complex conjugate pairs for which **select** is **true** for either eigenvalue count as 2.)

3: **wr(*)** – double array

Note: the dimension of the array **wr** must be at least $\max(1, \mathbf{n})$.

See the description of **wi**.

4: **wi(*)** – double array

Note: the dimension of the array **wi** must be at least $\max(1, \mathbf{n})$.

wr and **wi** contain the real and imaginary parts, respectively, of the computed eigenvalues in the same order that they appear on the diagonal of the output Schur form T . Complex conjugate pairs of eigenvalues will appear consecutively with the eigenvalue having the positive imaginary part first.

5: **vs(ldvs,*)** – double array

The first dimension, **ldvs**, of the array **vs** must satisfy

if **jobvs** = 'V', **ldvs** $\geq \max(1, \mathbf{n})$;
ldvs ≥ 1 otherwise.

The second dimension of the array must be at least $\max(1, \mathbf{n})$ if **jobvs** = 'V', and at least 1 otherwise

If **jobvs** = 'V', **vs** contains the orthogonal matrix Z of Schur vectors.

If **jobvs** = 'N', **vs** is not referenced.

6: **rconde** – double scalar

If **sense** = 'E' or 'B', contains the reciprocal condition number for the average of the selected eigenvalues.

If **sense** = 'N' or 'V', **rconde** is not referenced.

7: **rcondv** – double scalar

If **sense** = 'V' or 'B', **rcondv** contains the reciprocal condition number for the selected right invariant subspace.

If **sense** = 'N' or 'E', **rcondv** is not referenced.

8: **info** – int32 scalar

info = 0 unless the function detects an error (see Section 6).

6 Error Indicators and Warnings

Errors or warnings detected by the function:

info = $-i$

If **info** = $-i$, parameter i had an illegal value on entry. The parameters are numbered as follows:

1: **jobvs**, 2: **sort**, 3: **select**, 4: **sense**, 5: **n**, 6: **a**, 7: **lda**, 8: **sdim**, 9: **wr**, 10: **wi**, 11: **vs**, 12: **ldvs**, 13: **rconde**, 14: **rcondv**, 15: **work**, 16: **lwork**, 17: **iwork**, 18: **liwork**, 19: **bwork**, 20: **info**.

It is possible that **info** refers to a parameter that is omitted from the MATLAB interface. This usually indicates that an error in one of the other input parameters has caused an incorrect value to be inferred.

info = 1 to N

If **info** = i and $i \leq n$, the *QR* algorithm failed to compute all the eigenvalues

info = $N + 1$

The eigenvalues could not be reordered because some eigenvalues were too close to separate (the problem is very ill-conditioned).

info = $N + 2$

After reordering, roundoff changed values of some complex eigenvalues so that leading eigenvalues in the Schur form no longer satisfy **select** = **true**. This could also be caused by underflow due to scaling.

7 Accuracy

The computed Schur factorization satisfies

$$A + E = ZTZ^T,$$

where

$$\|E\|_2 = O(\epsilon)\|A\|_2,$$

and ϵ is the *machine precision*. See Section 4.8 of Anderson *et al.* 1999 for further details.

8 Further Comments

The total number of floating-point operations is proportional to n^3 .

The complex analogue of this function is f08pp.

9 Example

```
f08pb_select.m
```

```
function [result] = select(wr, wi)
    if (wi == 0)
        result = true;
    else
        result = false;
    end
```

```
jobvs = 'Vectors (Schur)';
sort = 'Sort';
sense = 'Both reciprocal condition numbers';
a = [0.35, 0.45, -0.14, -0.17;
     0.09, 0.070000000000000001, -0.54, 0.35;
     -0.44, -0.33, -0.03, 0.17;
     0.25, -0.32, -0.13, 0.11];
[aOut, sdim, wr, wi, vs, rconde, rcondv, info] = ...
    f08pb(jobvs, sort, 'f08pb_select', sense, a)
```

```
aOut =
    0.7995    -0.0059    -0.0751    -0.0927
         0    -0.1007     0.3937     0.3569
         0         0    -0.0994    -0.5128
         0         0     0.3132    -0.0994
```

```
sdim =
         2
```

```
wr =
    0.7995
   -0.1007
   -0.0994
   -0.0994
```

```
wi =
         0
         0
    0.4008
   -0.4008
```

```
vs =
   -0.6551   -0.1210   -0.5032    0.5504
   -0.5236   -0.3286    0.7857    0.0229
    0.5362   -0.5974    0.0904    0.5894
   -0.0956   -0.7215   -0.3482   -0.5908
```

```
rconde =
    0.5699
```

```
rcondv =
    0.3102
```

```
info =
         0
```